

Object Storage Migration Service

API Reference

Issue 01

Date 2024-12-27



HUAWEI TECHNOLOGIES CO., LTD.



Copyright © Huawei Technologies Co., Ltd. 2024. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Huawei Technologies Co., Ltd.

Address: Huawei Industrial Base
 Bantian, Longgang
 Shenzhen 518129
 People's Republic of China

Website: <https://www.huawei.com>

Email: support@huawei.com

Security Declaration

Vulnerability

Huawei's regulations on product vulnerability management are subject to the *Vul. Response Process*. For details about this process, visit the following web page:

<https://www.huawei.com/en/psirt/vul-response-process>

For vulnerability information, enterprise customers can visit the following web page:

<https://securitybulletin.huawei.com/enterprise/en/security-advisory>

Contents

1 Before You Start.....	1
2 API Overview.....	3
3 Calling APIs.....	4
3.1 Making an API Request.....	4
3.2 Authentication.....	7
3.3 Response.....	8
4 Getting Started.....	10
5 Application Examples.....	14
5.1 Creating a Migration Task.....	14
5.2 Starting a Migration Task.....	17
5.3 Example 3: Pausing and Deleting a Migration Task.....	19
6 APIs V2 (Recommended).....	23
6.1 API Version Query.....	23
6.1.1 Listing API Versions.....	23
6.1.2 Querying an API Version.....	26
6.2 Migration Task Management.....	28
6.2.1 Listing Migration Tasks.....	28
6.2.2 Querying a Migration Task.....	44
6.2.3 Creating a Migration Task.....	59
6.2.4 Pausing a Migration Task.....	76
6.2.5 Starting a Migration Task.....	78
6.2.6 Deleting a Migration Task.....	81
6.2.7 Updating the Traffic Limiting Rules of a Migration Task.....	83
6.2.8 Updating Tasks in Batches.....	86
6.3 Migration Task Group Management.....	89
6.3.1 Listing Migration Task Groups.....	89
6.3.2 Creating a Migration Task Group.....	112
6.3.3 Querying a Migration Task Group.....	128
6.3.4 Deleting a Migration Task Group.....	141
6.3.5 Pausing a Migration Task Group.....	143
6.3.6 Resuming a Migration Task Group.....	145

6.3.7 Restarting a Migration Task Group.....	148
6.3.8 Modifying the Traffic Limiting Rules of a Migration Task Group.....	152
6.4 Operations on Buckets.....	154
6.4.1 Listing Objects in a Bucket.....	154
6.4.2 Querying the CDN Information of a Bucket.....	159
6.4.3 Listing Buckets.....	164
6.4.4 Querying the Region of a Bucket.....	167
6.4.5 Checking Whether a Source Bucket Has Objects with a Specified Prefix.....	170
6.5 Querying Supported Source Clouds.....	174
6.5.1 Querying All Supported Cloud Vendors.....	174
6.6 Querying Supported Regions.....	176
6.6.1 Querying Regions Supported for a Cloud Vendor.....	176
7 Appendix.....	180
7.1 Status Codes.....	180
7.2 Error Codes.....	182
7.3 Migration Failure Causes.....	212
7.4 Obtaining a Project ID.....	216

1

Before You Start

Welcome to *Object Storage Migration Service API Reference*. Object Storage Migration Service (OMS) is an online data migration service that helps you easily and smoothly migrate object storage data from the other public clouds to Huawei Cloud.

This document describes how to use application programming interfaces (APIs) to perform operations on OMS, such as creating, deleting, or querying migration tasks. For details about all supported operations, see [API Overview](#).

If you plan to access OMS through an API, ensure that you are familiar with OMS concepts. For details, see [What Is OMS?](#)

Endpoints

An endpoint is the **request address** for calling an API. Endpoints vary depending on services and regions. For the OMS endpoints, see [Regions and Endpoints](#).

Concepts


- Account
 - An account is created upon successful registration. The account has full access permissions for all of its cloud services and resources. It can be used to reset user passwords and grant user permissions. The account is a payment entity, which should not be used directly to perform routine management. To ensure account security, create Identity and Access Management (IAM) users and grant them permissions for routine management.
- User
 - An IAM user is created by an account in IAM to use cloud services. Each IAM user has its own identity credentials (password and access keys).
API authentication requires information such as the account name, username, and password.
- Region
 - Regions are divided based on geographical location and network latency. Public services, such as Elastic Cloud Server (ECS), Elastic Volume Service (EVS), Object Storage Service (OBS), Virtual Private Cloud (VPC), Elastic IP (EIP), and Image Management Service (IMS), are shared within the same region. Regions are classified into universal regions and dedicated regions. A

universal region provides universal cloud services for common tenants. A dedicated region provides specific services for specific tenants.

For details, see [Region and AZ](#).

- AZ
An AZ comprises of one or more physical data centers equipped with independent ventilation, fire, water, and electricity facilities. Compute, network, storage, and other resources in an AZ are logically divided into multiple clusters. AZs within a region are interconnected using high-speed optical fibers to allow you to build cross-AZ high-availability systems.
- Project
A project corresponds to a region. Default projects are defined to a group and have physically isolated resources (including computing, storage, and network resources) across regions. Users can be granted permissions in a default project to access all resources in the region under their accounts. If you need more refined access control, create subprojects under a default project and create resources in subprojects. Then you can assign users the permissions required to access only the resources in the specific subprojects.

Figure 1-1 Project isolation model



- Enterprise project
Enterprise projects group and manage resources across regions. Resources in different enterprise projects are logically isolated. An enterprise project can contain resources of multiple regions, and resources can be added to or removed from enterprise projects.
For details about enterprise projects and about how to obtain enterprise project IDs, see [Enterprise Management User Guide](#).

2 API Overview

OMS provides version query APIs and task management APIs.

Table 2-1 OMS APIs

Location	Description
Listing API Versions	Query all API versions of OMS.
Querying an API Version	Query a specified API version of OMS.
Listing Migration Tasks	Query information about all tasks under a user account.
Querying a Migration Task	Query details about a migration task based on its ID.
Creating a Migration Task	Create a migration task.
Starting a Migration Task	Start a migration task after the migration task has been paused or failed.
Pausing a Migration Task	Stop a migration task that is in the Migrating state.
Deleting a Migration Task	Delete a migration task based on its ID.
Updating the Traffic Limiting Rules of a Migration Task	Update the traffic limiting rules of a migration task before the task is complete.

3 Calling APIs

3.1 Making an API Request

This section describes the structure of a RESTful API request, and uses the IAM API for [creating an IAM user](#) as an example to demonstrate how to call an API.

Request URI

A request URI is in the following format:

{URI-scheme}://{Endpoint}/{resource-path}?{query-string}

Although a request URI is included in the request header, most programming languages or frameworks require the request URI to be transmitted separately.

Table 3-1 URI parameter description

Parameter	Description
URI-scheme	Protocol used to transmit requests. All APIs use HTTPS.
Endpoint	Domain name or IP address of the server bearing the REST service. The endpoint varies between services in different regions. It can be obtained from Regions and Endpoints. For example, the endpoint of IAM in region CN-Hong Kong is iam.ap-southeast-1.myhuaweicloud.com .
resource-path	Access path of an API for performing a specified operation. Obtain the path from the URI of an API. For example, the resource-path of the API used by the administrator to create an IAM user is /v3.0/OS-USER/u .
query-string	Query parameter, which is optional. Ensure that a question mark (?) is included before each query parameter that is in the format of " <i>Parameter name=Parameter value</i> ". For example, ?limit=10 indicates that a maximum of 10 data records will be displayed.

IAM is a global service. You can create an IAM user using the endpoint of IAM in any region. For example, to create an IAM user in the Europe-Dublin region, obtain the endpoint of IAM (`iam.ap-southeast-1.myhuaweicloud.com`) for this region and the **resource-path** (`/v3.0/OS-USER/users`) in the URI of the API used to [create an IAM User as the administrator](#). Then, construct the URL as follows:

`https://iam.myhuaweicloud.eu/v3.0/OS-USER/users`

Figure 3-1 Example URI



NOTE

To simplify the URI display in this document, each API is provided only with a **resource-path** and a request method. The **URI-scheme** of all APIs is **HTTPS**, and the endpoints of all APIs in the same region are identical.

Request Methods

The HTTP protocol defines the following request methods that can be used to send a request to the server.

Table 3-2 HTTP methods

Method	Description
GET	Requests the server to return specified resources.
PUT	Requests the server to update specified resources.
POST	Requests the server to add resources or perform special operations.
DELETE	Requests the server to delete specified resources, for example, an object.
HEAD	Same as GET except that the server must return only the response header.
PATCH	Requests the server to update partial content of a specified resource. If the resource does not exist, a new resource will be created.

For example, in the case of the API used to [create an IAM user](#), the request method is **POST**. The request is as follows:

`POST https://iam.ap-southeast-1.myhuaweicloud.com/v3.0/OS-USER/users`

Request Header

You can also add additional header fields to a request, such as the fields required by a specified URI or HTTP method. For example, to request for the authentication information, add **Content-Type**, which specifies the request body type.

Common request header fields are as follows.

Table 3-3 Common request header fields

Parameter	Description
Content-Type	Type or format of the request body. This field is mandatory and its default value is application/json . Other values of this field will be provided for specific APIs if any.
Authorization	Signature authentication information. This field is optional. During AK/SK-based authentication, this field is automatically specified when SDKs are used to sign the request. For more information, see AK/SK-based Authentication .
X-Sdk-Date	Time when a request is sent. This field is optional. When AK/SK authentication is used, this field is automatically specified when SDKs are used to sign the request. For more information, see AK/SK-based Authentication .
X-Auth-Token	User token. This field is mandatory only for token-based authentication. The user token is a response to the API used to obtain a user token . This API is the only one that does not require authentication.
X-Project-ID	Subproject ID. This parameter is mandatory only in multi-project scenarios. The X-Project-ID field is mandatory in the request header for accessing resources in a sub-project through AK/SK-based authentication.
X-Domain-ID	Account ID. The X-Domain-ID field is mandatory for calling APIs of global services through AK/SK-based authentication.

The API used to [create an IAM user](#) does not require authentication. Therefore, only the **Content-Type** field needs to be added to requests for calling the API. An example of such requests is as follows:

```
POST https://iam.ap-southeast-1.myhuaweicloud.com/v3.0/OS-USER/users
Content-Type: application/json
X-Sdk-Date: 20240416T095341Z
Authorization: SDK-HMAC-SHA256 Access=*****,
SignedHeaders=content-type;host;x-sdk-date,
Signature=*****
```

(Optional) Request Body

This part is optional. The body of a request is often sent in a structured format as specified in the **Content-Type** header field. The request body transfers content except the request header.

The request body varies between APIs. Some APIs do not require the request body, such as the APIs requested using the GET and DELETE methods.

In the case of the API used to [create an IAM user](#), the request parameters and parameter description can be obtained from the API request. The following provides an example request with a body included. Replace the italic fields in bold with the actual values.

- **accountid**: account ID of an IAM user
- **username**: name of an IAM user
- **email**: email of an IAM user
- *********: login password of an IAM user

```
POST https://iam.myhuaweicloud.eu/v3.0/OS-USER/users
Content-Type: application/json
X-Sdk-Date: 20240416T095341Z
Authorization: SDK-HMAC-SHA256 Access=*****,
SignedHeaders=content-type;host;x-sdk-date,
Signature=*****"

{
    "user": {
        "domain_id": "accountid",
        "name": "username",
        "password": "*****",
        "email": "email",
        "description": "IAM User Description"
    }
}
```

If all data required for the API request is available, you can send the request to call the API through [curl](#), [Postman](#), or coding. In the response to the API used to obtain a user token, **x-subject-token** is the desired user token. This token can then be used to authenticate the calling of other APIs.

3.2 Authentication

Requests for calling an API can be authenticated using either of the following methods:

- AK/SK authentication: Requests are encrypted using AK/SK pairs. AK/SK authentication is recommended because it is more secure than token authentication.
- Token authentication: Requests are authenticated using Tokens.

AK/SK Authentication



NOTE

- AK/SK authentication supports API requests with a body not larger than 12 MB. For API requests with a larger body, token authentication is recommended.
- The AK/SK can be either a permanent access key or a temporary access key. If it is a temporary access key, the **X-Security-Token** field must be added to the request. The value is the **security_token** of the temporary access key.

In AK/SK-based authentication, AK/SK is used to sign requests and the signature is then added to the requests for authentication.

- AK: access key ID, which is a unique identifier used in conjunction with a secret access key to sign requests cryptographically.
- SK: secret access key, which is used in conjunction with an AK to sign requests cryptographically. It identifies a request sender and prevents the request from being modified.

In AK/SK authentication, you can use an AK/SK pair to sign requests based on the signature algorithm or using the signing SDK. For details about how to sign requests and use the signing SDK, see [API Request Signing Guide](#).

 NOTE

The signing SDK is only used for signing requests and is different from the SDKs provided by services.

3.3 Response

Status Code

After sending a request, you will receive a response, including a status code, response header, and response body.

A status code is a group of digits, ranging from 1xx to 5xx. It indicates the status of a request. For more information, see [Status Codes](#).

For example, if status code **201** is returned for calling the API used to [create an IAM user](#), the request is successful.

Response Header

Similar to a request, a response also has a header, for example, **Content-Type**.

The following shows part of the response body for the API to [create an IAM user](#).

Figure 3-2 Header fields of the response to the request for creating an IAM user

```
"X-Frame-Options": "SAMEORIGIN",
"X-IAM-ETag-id": "2562365939-d8f6f12921974cb097338ac11fceac8a",
"Transfer-Encoding": "chunked",
"Strict-Transport-Security": "max-age=31536000; includeSubdomains;",
"Server": "api-gateway",
"X-Request-Id": "af2953f2bcc67a42325a69a19e6c32a2",
"X-Content-Type-Options": "nosniff",
"Connection": "keep-alive",
"X-Download-Options": "noopen",
"X-XSS-Protection": "1; mode=block;",
"X-IAM-Trace-Id": "token_____null_af2953f2bcc67a42325a69a19e6c32a2",
"Date": "Tue, 21 May 2024 09:03:40 GMT",
"Content-Type": "application/json; charset=utf8"
```

(Optional) Response Body

The body of a response is often returned in structured format as specified in the **Content-Type** header field. The response body transfers content except the response header.

The following shows part of the response body for the API to [create an IAM user](#).

```
{  
    "user": {  
        "id": "c131886aec...",  
        "name": "IAMUser",  
        "description": "IAM User Description",  
        "areacode": "",  
        "phone": "",  
        "email": "***@***.com",  
        "status": null,  
        "enabled": true,  
        "pwd_status": false,  
        "access_mode": "default",  
        "is_domain_owner": false,  
        "xuser_id": "",  
        "xuser_type": "",  
        "password_expires_at": null,  
        "create_time": "2024-05-21T09:03:41.000000",  
        "domain_id": "d78cbac1.....",  
        "xdomain_id": "30086000.....",  
        "xdomain_type": "",  
        "default_project_id": null  
    }  
}
```

If an error occurs during API calling, an error code and a message will be displayed. The following shows an error response body.

```
{  
    "error_msg": "The format of message is error",  
    "error_code": "AS.0001"  
}
```

In the response body, **error_code** is an error code, and **error_msg** provides information about the error.

4 Getting Started

Scenarios

This section describes the basic procedure of calling OMS APIs by creating an object data migration task.

For details, see [Calling APIs](#).

Involved APIs

- [Obtaining a User Token Through Password Authentication](#): This API is used to obtain the user token for authentication.
- [Creating a Migration Task](#): used to create a migration task using the source and destination AK/SK pairs
- [Querying a Migration Task](#): used to query the task details based on the migration task ID to check whether the migration task has been created successfully

Prerequisites

- You have obtained the AK/SK pair of the source platform account.
- You have obtained AK/SK of the destination platform account. For details about how to obtain AKs and SKs, see [Creating Access Keys \(AK and SK\)](#).
- You have obtained the endpoints of IAM and OMS. For details, see Regions and Endpoints.
- You have obtained the region where the source bucket locates.
- The destination bucket has been created. For details, see [Creating a Bucket](#).
- You have obtained the region where the destination bucket locates. For details, see [Viewing Bucket Information](#).
- You have obtained the project ID. For details, see [Obtaining a Project ID](#).

Creating an Application

Assume that you have obtained the required information shown as follows, which are examples. You need to replace them based on the actual situation.

- IAM endpoint: **iam_endpoint**

- OMS endpoint: **oms.cn-north-1.myhuaweicloud.com**
- Project ID: **0215ef11e49d4743be23dd97a156xxxx**
- Region where the source bucket locates: **cn-beijing**
- Region where the destination bucket locates: **cn-north-1**
- Source AK: **source_ak**
- Source SK: **source_sk**
- Destination AK: **destination_ak**
- Destination SK: **destination_sk**
- Source bucket name: **source_bucket**
- Destination bucket name: **destination_bucket**
- Source type: **cloud_type**

Procedure

Step 1 Obtain the token of the IAM user.

- API

URI format: POST /v3/auth/tokens

For details, see [Obtaining a User Token Through Password Authentication](#).

- Example request

POST: [https://\[iam_endpoint\]/v3/auth/tokens](https://[iam_endpoint]/v3/auth/tokens)

Obtain *{endpoint}* from Regions and Endpoints.

Body:

```
{
    "auth": {
        "identity": {
            "methods": [
                "password"
            ],
            "password": {
                "user": {
                    "name": "testname",
                    "domain": {
                        "name": "testname"
                    },
                    "password": "Password"
                }
            }
        },
        "scope": {
            "project": {
                "id": "0215ef11e49d4743be23dd97a156xxxx"
            }
        }
    }
}
```

In the response header, the value of **X-Subject-Token** is the token.

X-Subject-Token:MIIDkgYJKoZIhvcNAQcCollDgzCCA38CAQExDTALBglghkgBZQMEAqEwgXXXXX...

Step 2 Make a call to the API for creating a migration task to create a migration task.

- API

URI format: POST /v1/{project_id}/objectstorage/task

For details, see [Creating a Migration Task](#).

- Example request

POST: <https://oms.cn-north-1.myhuaweicloud.com/v1/0215ef11e49d4743be23dd97a1561e91/objectstorage/task>

Obtain *{endpoint}* from Regions and Endpoints.

Header:

Content-Type: application/json
X-Auth-Token: "Token"

Body:

```
{  
    "src_node": {  
        "region": "cn-beijing",  
        "ak": "source_ak",  
        "sk": "source_sk",  
        "object_key": {  
            "path": "",  
            "keys": []  
        },  
        "bucket": "source_bucket",  
        "cloud_type": "{cloud_type}"  
    },  
    "thread_num": 50,  
    "enableKMS": false,  
    "description": "A migration task.",  
    "dst_node": {  
        "region": "cn-north-1",  
        "ak": "destination_ak",  
        "sk": "destination_sk",  
        "object_key": "/",  
        "bucket": "destination_bucket",  
        "cloud_type": "OBS"  
    },  
    "task_type": "object",  
    "enable_failed_object_recording": false  
}
```

- Example response

```
{  
    "id": 180890111968184,  
    "task_name": "task_name"  
}
```

Step 3 Make a call to the task viewing API to view the task status.

- API

URI format:

GET /v1/{project_id}/objectstorage/task/{task_id}

For details, see [Querying a Migration Task](#).

- Example request

GET: https://oms.cn-north-1.myhuaweicloud.com/v1/0215ef11e49d4743be23dd97a1561e91/objectstorage/task/{task_id}

Obtain *{endpoint}* from Regions and Endpoints.

Header:

Content-Type: application/json
X-Auth-Token: "Token"

- Example response

```
{  
    "id": 180894011968184,  
    "name": "task_name",  
    "src_node": {  
        "region": "cn-beijing",  
        "bucket": "source_bucket",  
        "object_key": ["/"],  
        "path": ""  
    },  
    "dst_node": {  
        "region": "cn-north-1",  
        "bucket": "destination_bucket",  
        "object_key": "",  
        "path": ""  
    },  
    "status": "running",  
    "progress": 100,  
    "start_time": "2024-12-27T10:00:00Z",  
    "end_time": "2024-12-27T10:10:00Z",  
    "duration": "10m",  
    "log_url": "https://oms.cn-north-1.myhuaweicloud.com/v1/0215ef11e49d4743be23dd97a1561e91/objectstorage/task/180894011968184/log",  
    "error": null  
}
```

```
"list_file": "",  
  "cloud_type": "{cloud_type}"  
},  
"dst_node": {  
  "region": "cn-north-1",  
  "bucket": "destination_bucket",  
  "object_key": "/",  
  "cloud_type": "OBS"  
},  
"thread_num": 50,  
"is_query_over": true,  
"status": 5,  
"progress": 1,  
"total_num": 1001,  
"success_num": 1001,  
"fail_num": 0,  
"skip_num": 0,  
"description": "A migration task.",  
"enableKMS": false,  
"error_reason": "",  
"total_size": 10240000,  
"real_size": 10240000,  
"complete_size": 10240000,  
"migrate_speed": 577552,  
"start_time": 1534762935868,  
"left_time": 0,  
"total_time": 17730,  
"migrate_since": 0,  
"task_type": "object",  
"failed_object_record": {  
  "result": false,  
  "list_file_key": "",  
  "reson": "S3M.0301"  
}  
}
```

status indicates the task execution status. The value **5** indicates that the task is successfully executed.

----End

5 Application Examples

5.1 Creating a Migration Task

Scenarios

This section describes how to create a migration task by calling APIs. For details, see [Calling APIs](#).

Supported migration task types include URL list migration, object name prefix migration, object list migration, and file/folder migration. This section describes how to create a file/folder migration task.

Involved APIs

- [Obtaining a User Token Through Password Authentication](#): This API is used to obtain the user token for authentication.
- [Creating a Migration Task](#): used to create a migration task using the source and destination AK/SK pairs
- [Querying a Migration Task](#): used to query the task details based on the migration task ID to check whether the migration task has been created successfully

Prerequisites

- You have obtained the AK/SK pair of the source platform account.
- You have obtained AK/SK of the destination platform account. For details about how to obtain AKs and SKs, see [Creating Access Keys \(AK and SK\)](#).
- You have obtained the endpoints of IAM and OMS. For details, see Regions and Endpoints.
- You have obtained the region where the source bucket locates.
- The destination bucket has been created. For details, see [Creating a Bucket](#).
- You have obtained the region where the destination bucket locates. For details, see [Viewing Bucket Information](#).
- You have obtained the project ID. For details, see [Obtaining a Project ID](#).

Procedure

Step 1 Obtain the token of the IAM user.

- API

URI format: POST /v3/auth/tokens

For details, see [Obtaining a User Token Through Password Authentication](#).

- Example request

POST: https://{iam_endpoint}/v3/auth/tokens

Obtain *{endpoint}* from Regions and Endpoints.

Body:

```
{
  "auth": {
    "identity": {
      "methods": [
        "password"
      ],
      "password": {
        "user": {
          "name": "username",
          "domain": {
            "name": "domainname"
          },
          "password": "*****"
        }
      }
    },
    "scope": {
      "project": {
        "id": "0215ef11e49d4743be23dd97a1561e91"
      }
    }
  }
}
```

In the response header, the value of **X-Subject-Token** is the token.

X-Subject-Token:MIIDkgYJKoZIhvcNAQcCoIJDgzCCA38CAQExDTALBglhgkBZQMEAegEwgXXXXX...

Step 2 Make a call to the API for creating a migration task to create a migration task.

- API

URI format: POST /v2/{project_id}/tasks

For details, see [Creating a Migration Task](#).

- Example request

POST: https://{oms_endpoint}/v2/{project_id}/tasks

Obtain *{endpoint}* from Regions and Endpoints.

Header:

Content-Type: application/json
X-Auth-Token: "Token"

Body:

```
{
  "src_node": {
    "region": "source_bucket_region",
    "ak": "source_ak",
    "sk": "source_sk",
    "bucket": "source_bucket",
    "cloud_type": "cloud_type",
    "object_key": ["01.png", "list.txt"]
  },
  "enable_kms": false,
```

```
"description" : "",  
"dst_node" : {  
    "region" : "destination_bucket_region",  
    "ak" : "destination_ak",  
    "sk" : "destination_sk",  
    "bucket" : "destination_bucket"  
},  
"enable_failed_object_recording" : true,  
"enable_restore" : false,  
"task_type" : "object"  
}
```

- Example response

```
{  
    "id" : 200477729979132,  
    "task_name" : "task_name"  
}
```

Step 3 Make a call to the task viewing API to view the task status.

- API

URI format:

```
GET /v2/{project_id}/tasks/{task_id}
```

For details, see [Querying a Migration Task](#).

- Example request

```
GET: https://{oms_endpoint}/v2/{project_id}/tasks/{task_id}
```

Obtain *{endpoint}* from Regions and Endpoints.

Header:

```
Content-Type: application/json  
X-Auth-Token: "Token"
```

- Example response

```
{  
    "bandwidth_policy" : [],  
    "complete_size" : 2223728,  
    "description" : "",  
    "dst_node" : {  
        "bucket" : "api-test-outline",  
        "region" : "cn-north-7"  
    },  
    "enable_failed_object_recording" : true,  
    "enable_kms" : false,  
    "enable_restore" : false,  
    "error_reason" : null,  
    "failed_num" : 0,  
    "failed_object_record" : {  
        "result" : null,  
        "list_file_key" : null,  
        "error_code" : null  
    },  
    "group_id" : "",  
    "id" : 200477729979132,  
    "is_query_over" : true,  
    "left_time" : 0,  
    "migrate_since" : 0,  
    "migrate_speed" : 71477,  
    "name" : "task_name",  
    "progress" : 1.0,  
    "real_size" : 2223728,  
    "skipped_num" : 0,  
    "src_node" : {  
        "bucket" : "a-test-1",  
        "cloud_type" : "HuaweiCloud",  
        "region" : "cn-north-7",  
        "app_id" : "",  
        "object_key" : ["01.png", "list.txt"],  
    }  
}
```

```
        "list_file" : null
    },
    "start_time" : 1589267678170,
    "status" : 5,
    "successful_num" : 2,
    "task_type" : "object",
    "total_num" : 2,
    "total_size" : 2223728,
    "total_time" : 31111,
    "smn_info" : null,
    "source_cdn" : null
}
```

status indicates the task execution status. The value **5** indicates that the task is successfully executed.

----End

5.2 Starting a Migration Task

Scenarios

This section describes how to start a migration task by calling APIs. For details, see [Calling APIs](#).

Before starting a migration task, you need to obtain a token. After starting a migration task, you need to query the task status. You can only start failed or paused tasks.

Involved APIs

- [Obtaining a User Token Through Password Authentication](#): This API is used to obtain the user token for authentication.
- [Starting a Migration Task](#): used to start a failed or paused migration task using the source and destination AK/SK pairs
- [Querying a Migration Task](#): used to query the task details based on the migration task ID to check whether the migration task has been started successfully

Procedure

Step 1 Obtain the token of the IAM user.

- API
URI format: POST /v3/auth/tokens
For details, see [Obtaining a User Token Through Password Authentication](#).
- Example request
POST: https://[iam_endpoint]/v3/auth/tokens
Obtain *{endpoint}* from Regions and Endpoints.

Body:

```
{
    "auth": {
        "identity": {
            "methods": [
                "password"
            ],
            "password": {

```

```
        "user": {
            "name": "testname",
            "domain": {
                "name": "testname"
            },
            "password": "Password"
        }
    },
    "scope": {
        "project": {
            "id": "0215ef11e49d4743be23dd97a1561e91"
        }
    }
}
```

In the response header, the value of **X-Subject-Token** is the token.

X-Subject-Token:MIIDkgYJKoZIhvNAQcColIDgzCCA38CAQExDTALBglghkgBZQMEAegEwgXXXX...

Step 2 Make a call to the API for starting a migration task to start a migration task.

- API

URI format: POST /v2/{project_id}/tasks/{task_id}/start

For details, see [Starting a Migration Task](#).

- Example request

POST: https://{oms_endpoint}/v2/{project_id}/tasks/{task_id}/start

Obtain {endpoint} from Regions and Endpoints.

Header:

Content-Type: application/json
X-Auth-Token: "Token"

Body:

```
{
    "dst_ak" : "destination_ak",
    "dst_sk" : "destination_sk",
    "src_ak" : "source_ak",
    "src_sk" : "source_sk",
    "migrate_failed_object" : false
}
```

If the response code is 200, the API is successfully called.

Step 3 Make a call to the task viewing API to view the task status.

- API

URI format:

GET /v2/{project_id}/tasks/{task_id}

For details, see [Querying a Migration Task](#).

- Example request

GET: https://{oms_endpoint}/v2/{project_id}/tasks/{task_id}

Obtain {endpoint} from Regions and Endpoints.

Header:

Content-Type: application/json
X-Auth-Token: "Token"

- Example response

```
{
    "bandwidth_policy" : [],
    "complete_size" : 2223728,
    "description" : ""
```

```
"dst_node": {  
    "bucket": "api-test-outline",  
    "region": "cn-north-7"  
},  
"enable_failed_object_recording": true,  
"enable_kms": false,  
"enable_restore": false,  
"error_reason": null,  
"failed_num": 0,  
"failed_object_record": {  
    "result": null,  
    "list_file_key": null,  
    "error_code": null  
},  
"group_id": "",  
"id": 20047729979132,  
"is_query_over": true,  
"left_time": 0,  
"migrate_since": 0,  
"migrate_speed": 71477,  
"name": "task_name",  
"progress": 1.0,  
"real_size": 2223728,  
"skipped_num": 0,  
"src_node": {  
    "bucket": "a-test-1",  
    "cloud_type": "HuaweiCloud",  
    "region": "cn-north-7",  
    "app_id": "",  
    "object_key": ["01.png", "list.txt"],  
    "list_file": null  
},  
"start_time": 1589267678170,  
"status": 5,  
"successful_num": 2,  
"task_type": "object",  
"total_num": 2,  
"total_size": 2223728,  
"total_time": 31111,  
"smn_info": null,  
"source_cdn": null  
}
```

status indicates the task execution status. The value **2** indicates that the task is being executed, and the value **5** indicates that the task is successfully executed.

----End

5.3 Example 3: Pausing and Deleting a Migration Task

Scenarios

This section describes how to pause and delete a migration task using an API. For details, see [Calling APIs](#).

Before deleting a migration task, you need to obtain the token. After pausing the migration task, you need to query the task status. The migration task can be deleted only after it is paused.

Involved APIs

- [Obtaining a User Token Through Password Authentication](#): This API is used to obtain the user token for authentication.

- **Pausing a Migration Task:** used to pause a migration task based on the migration task ID
- **Querying a Migration Task:** used to query the task details based on the migration task ID to check whether the migration task is successfully paused
- **Deleting a Migration Task:** used to delete a migration task based on the migration task ID

Procedure

Step 1 Obtain the token of the IAM user.

- API
URI format: POST /v3/auth/tokens
For details, see [Obtaining a User Token Through Password Authentication](#).
- Example request
POST: https://{iam_endpoint}/v3/auth/tokens
Obtain *{endpoint}* from Regions and Endpoints.

Body:

```
{
  "auth": {
    "identity": {
      "methods": [
        "password"
      ],
      "password": {
        "user": {
          "name": "testname",
          "domain": {
            "name": "testname"
          },
          "password": "Password"
        }
      }
    },
    "scope": {
      "project": {
        "id": "0215ef11e49d4743be23dd97a1561e91"
      }
    }
  }
}
```

In the response header, the value of **X-Subject-Token** is the token.

X-Subject-Token:MIIDkgYJKoZIhvcNAQcCoIJDgzCCA38CAQExDTALBglghkgBZQMEA...
...

Step 2 Make a call to the API for pausing a migration task to pause a migration task.

- API
URI format: POST /v2/{project_id}/tasks/{task_id}/stop
For details, see [Pausing a Migration Task](#).
- Example request
POST: https://{oms_endpoint}/v2/{project_id}/tasks/{task_id}/stop
Obtain *{endpoint}* from Regions and Endpoints.
Header:
Content-Type: application/json
X-Auth-Token: "Token"

If the response code is 200, the API is successfully called.

Step 3 Make a call to the task viewing API to view the task status.

- API

URI format:

```
GET /v2/{project_id}/tasks/{task_id}
```

For details, see [Querying a Migration Task](#).

- Example request

```
GET: https://{oms_endpoint}/v2/{project_id}/tasks/{task_id}
```

Obtain *{endpoint}* from Regions and Endpoints.

Header:

```
Content-Type: application/json  
X-Auth-Token: "Token"
```

- Example response

```
{
    "bandwidth_policy" : [],
    "complete_size" : 2223728,
    "description" : "",
    "dst_node" : {
        "bucket" : "api-test-outline",
        "region" : "cn-north-7"
    },
    "enable_failed_object_recording" : true,
    "enable_kms" : false,
    "enable_restore" : false,
    "error_reason" : null,
    "failed_num" : 0,
    "failed_object_record" : {
        "result" : null,
        "list_file_key" : null,
        "error_code" : null
    },
    "group_id" : "",
    "id" : 200477729979132,
    "is_query_over" : true,
    "left_time" : 0,
    "migrate_since" : 0,
    "migrate_speed" : 71477,
    "name" : "task_name",
    "progress" : 1.0,
    "real_size" : 2223728,
    "skipped_num" : 0,
    "src_node" : {
        "bucket" : "a-test-1",
        "cloud_type" : "HuaweiCloud",
        "region" : "cn-north-7",
        "app_id" : "",
        "object_key" : ["01.png", "list.txt"],
        "list_file" : null
    },
    "start_time" : 1589267678170,
    "status" : 3,
    "successful_num" : 2,
    "task_type" : "object",
    "total_num" : 2,
    "total_size" : 2223728,
    "total_time" : 31111,
    "smn_info" : null,
    "source_cdn" : null
}
```

status indicates the task execution status. The value **3** indicates that the task is paused.

Step 4 Make a call to the API for deleting a migration task to delete a migration task.

- API
URI format: DELETE /v2/{project_id}/tasks/{task_id}

For details, see [Deleting a Migration Task](#).

- Example request
DELETE: `https://{oms_endpoint}/v2/{project_id}/tasks/{task_id}`

Obtain `{endpoint}` from Regions and Endpoints.

Header:

`Content-Type: application/json`
`X-Auth-Token: "Token"`

If the response code is 200, the migration task is deleted successfully.

----End

6 APIs V2 (Recommended)

6.1 API Version Query

6.1.1 Listing API Versions

Function

This API is used to list all OMS API versions.

Calling Method

For details, see [Calling APIs](#).

URI

GET /

Request

Table 6-1 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 200

Table 6-2 Response body parameter

Parameter	Type	Description
versions	Array of Version objects	The version list. Array length: 0 to 1,024

Table 6-3 Version

Parameter	Type	Description
id	String	The API version, for example, v1 .
links	Array of Link objects	The link address. Array length: 0 to 100
status	String	The version status. CURRENT : indicates a widely used version. SUPPORTED : indicates an earlier version which is still supported. DEPRECATED : indicates a deprecated version which may be deleted later. The value can be: <ul style="list-style-type: none">• CURRENT• DEPRECATED• SUPPORTED
updated	String	The time when the version is updated. The format is yyyy-mm-ddThh:mm:ssZ. T is the separator between the calendar and the hourly notation of time. Z indicates Coordinated Universal Time (UTC). Minimum length: 0 characters Maximum length: 32 characters

Table 6-4 Link field description

Parameter	Type	Description
href	String	The link address.
rel	String	Its value is self , indicating that href is a local link.

Status code: 403

Table 6-5 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries the list of supported API versions.

```
GET https://[endpoint]/
```

Example Response

Status code: 200

OK

```
{
  "versions" : [ {
    "links" : [ {
      "rel" : "self",
      "href" : "https://oms.cn-north-1.myhuaweicloud.com/v1/"
    }],
    "id" : "v1",
    "updated" : "2020-01-01T12:00:00Z",
    "status" : "SUPPORTED"
  }, {
    "links" : [ {
      "rel" : "self",
      "href" : "https://oms.cn-north-1.myhuaweicloud.com/v2/"
    }],
    "id" : "v1",
    "updated" : "2020-01-01T12:00:00Z",
    "status" : "SUPPORTED"
  ]
}
```

Status Codes

Status Code	Description
200	OK
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.1.2 Querying an API Version

Function

This API is used to query a specified API version of OMS.

Calling Method

For details, see [Calling APIs](#).

URI

GET /{version}

Table 6-6 Path parameters

Parameter	Mandatory	Type	Description
version	Yes	String	The version. Minimum length: 1 character Maximum length: 10 characters

Request

Table 6-7 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 200

Table 6-8 Response body parameters

Parameter	Type	Description
id	String	The API version, for example, v1.
links	Array of Link objects	The link address. Array length: 0 to 100

Parameter	Type	Description
status	String	<p>The version status.</p> <p>CURRENT: indicates a widely used version.</p> <p>SUPPORTED: indicates an earlier version which is still supported.</p> <p>DEPRECATED: indicates a deprecated version which may be deleted later.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • CURRENT • DEPRECATED • SUPPORTED
updated	String	<p>The time when the version is updated.</p> <p>The format is yyyy-mm-ddT hh:mm:ssZ.</p> <p>T is the separator between the calendar and the hourly notation of time. Z indicates the UTC.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 32 characters</p>

Table 6-9 Link field description

Parameter	Type	Description
href	String	The link address.
rel	String	Its value is self , indicating that href is a local link.

Status code: 403

Table 6-10 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries a specified OMS API version.

```
GET https://[endpoint]/v2
```

Example Response

Status code: 200

The version information is obtained.

```
{  
  "links" : [ {  
    "rel" : "self",  
    "href" : "https://oms.cn-north-1.myhuaweicloud.com/v1/"  
  },  
  "id" : "v2",  
  "updated" : "2020-04-01T12:00:00Z",  
  "status" : "SUPPORTED"  
}
```

Status Codes

Status Code	Description
200	The version information is obtained.
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.2 Migration Task Management

6.2.1 Listing Migration Tasks

Function

This API is used to list all migration tasks in a user account.

Calling Method

For details, see [Calling APIs](#).

URI

GET /v2/{project_id}/tasks

Table 6-11 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Table 6-12 Query parameters

Parameter	Mandatory	Type	Description
group_id	No	String	The migration task group ID. Minimum length: 1 character Maximum length: 100 characters
limit	No	Integer	The maximum number of migration tasks displayed on one page. By default, 10 migration tasks are displayed on one page. A maximum of 100 migration tasks can be displayed. Minimum value: 1 Maximum value: 100 Default value: 10
offset	No	Integer	The start serial number of migration tasks. The value must be greater than or equal to 0. If offset is set to 0, the query starts from the first record. Minimum value: 0 Maximum value: 2147483647 Default value: 0
status	No	Integer	The migration task status. If this parameter is not specified, migration tasks in all statuses will be queried. The value can be 1 (Waiting), 2 (Migrating), 3 (Paused), 4 (Failed), 5 (Succeeded), or 7 (Paused). Minimum value: 1 Maximum value: 7

Request

Table 6-13 Request header parameter

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 200

Table 6-14 Response body parameters

Parameter	Type	Description
tasks	Array of TaskResp objects	The details of queried migration tasks. Array length: 0 to 100
count	Long	The total number of the migration tasks that meet the search criteria. Minimum value: 0 Maximum value: 9223372036854775807

Table 6-15 TaskResp field description

Parameter	Type	Description
bandwidth_policy	Array of BandwidthPolicyDto objects	The traffic limiting rules. A maximum of five traffic limiting rules can be set for a single task. Array length: 0 to 5
complete_size	Long	The size (in bytes) of the objects that have been migrated in the task. Minimum value: 0 Maximum value: 9223372036854775807
description	String	The task description. If this parameter is not set, the value is an empty string. Minimum length: 0 characters Maximum length: 255 characters

Parameter	Type	Description
dst_node	DstNodeResp object	The destination node information.
enable_failed_object_recording	Boolean	Indicates whether to record the objects that failed to be migrated. If this function is enabled, information about objects that fail to be migrated will be stored in the destination bucket.
enable_kms	Boolean	Indicates whether to use KMS to encrypt the data to be stored in the destination OBS bucket.
enable_metadata_migration	Boolean	Indicates whether metadata migration is enabled. The default value is false . Even if this function is disabled, the ContentType metadata will still be migrated to ensure a successful migration.
enable_restore	Boolean	Indicates whether to restore archive data in the source bucket. It takes a long time to restore archive data in the source bucket, which will greatly slow down the migration speed. You are advised to restore the archive objects before the migration. After this function is enabled, archive objects will be automatically restored and then migrated. By default, this function is disabled, archive objects will be ignored during the migration, and the information about these objects will be recorded in the list of failed objects.
error_reason	ErrorReasonResponse object	The task failure cause. The value is an empty string if the task is not in the Migration failed state.
failed_num	Long	<p>The number of objects that failed to be migrated.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
failed_object_record	FailedObjectRecordDto object	The records of the objects that failed to be migrated. If the record is successful, the path for storing the list of failed objects is displayed. If the record fails, the failure cause is displayed.
group_id	String	<p>The ID of migration task group to which the task belongs. If a task is created by a migration task group, the ID of the migration task group is included.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 36 characters</p>

Parameter	Type	Description
id	Long	The task ID. Minimum value: 0 Maximum value: 9999999999999999
is_query_over	Boolean	Indicates whether the source object statistics are scanned for the migration task.
left_time	Long	The remaining time (in milliseconds) of the task. Minimum value: 0 Maximum value: 9223372036854775807
migrate_since	Long	The specified migration time (timestamp, in milliseconds). Only source objects that are modified after the specified time will be migrated. Default value 0 indicates that no time is specified. Minimum value: 0 Maximum value: 9223372036854775807
migrate_speed	Long	The migration speed (byte/s). Minimum value: 0 Maximum value: 9223372036854775807
name	String	The task name. Minimum length: 0 characters Maximum length: 10,240 characters
progress	Double	The task progress. For example, 0.522 represents the progress is 52.2%, and 1 represents the progress is 100%. Minimum value: 0 Maximum value: 1
real_size	Long	The total size (in bytes) of the migrated objects. The size of ignored objects is not counted. Minimum value: 0 Maximum value: 9223372036854775807
skipped_num	Long	The number of objects that are skipped during the migration. The following objects will be skipped: objects whose last modification time is earlier than the specified migration time, and objects that exist in the destination bucket. Minimum value: 0 Maximum value: 9223372036854775807

Parameter	Type	Description
src_node	SrcNodeResp object	The source node information.
start_time	Long	The start time (UNIX timestamp, in milliseconds) of the migration task. Minimum value: 0 Maximum value: 9223372036854775807
status	Integer	The task status. 1 : Waiting, 2 : Migrating, 3 : Paused, 4 : Failed, 5 : Succeeded, 7 : Pausing Minimum value: 1 Maximum value: 7
successful_num	Long	The number of successfully migrated objects. Minimum value: 0 Maximum value: 9223372036854775807
task_type	String	The task type. list indicates migrating objects using an object list. object indicates migrating selected files or folders. prefix indicates migrating objects with specified prefixes. url_list indicates migrating objects using a URL object list. Default value: object The value can be: <ul style="list-style-type: none">• list• object• prefix• url_list
group_type	String	The task group type. NORMAL_TASK indicates a general migration task. SYNC_TASK indicates a migration task to which a synchronization task belongs. GROUP_TASK indicates a subtask in a migration task group. Default value: NORMAL_TASK The value can be: <ul style="list-style-type: none">• NORMAL_TASK• SYNC_TASK• GROUP_TASK
total_num	Long	The total number of the objects that have been migrated in the task. Minimum value: 0 Maximum value: 9223372036854775807

Parameter	Type	Description
total_size	Long	The size (in bytes) of the objects that have been migrated in the task. Minimum value: 0 Maximum value: 9223372036854775807
total_time	Long	The total time used (in milliseconds). Minimum value: 0 Maximum value: 9223372036854775807
smn_info	SmnInfo object	The SMN notification results.
source_cdn	SourceCdnResponse object	Indicates whether migration from CDN is enabled. If it is enabled, the source objects to be migrated are obtained from the specified CDN domain name during migration. If this field is included, migration from CDN is supported. Otherwise, it is not supported.
success_record_error_reason	String	The error code returned for the failure in recording the list of objects that are successfully migrated. If the list is recorded successfully, this parameter is left blank. Minimum length: 0 characters Maximum length: 255 characters
skip_record_error_reason	String	The error code returned for the failure in recording the list of objects that are ignored. If the list is recorded successfully, this parameter is left blank. Minimum length: 0 characters Maximum length: 255 characters

Parameter	Type	Description
object_overwrite_mode	String	<p>Indicates whether to skip a source object or allow the source object to overwrite its paired destination object. The default value is SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE. NO_OVERWRITE indicates the system never allows overwrite. The system always skips source objects and keeps their paired destination objects.</p> <p>SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE indicates the system allows overwrite based on the results of size or modification time checks. It is the default setting. If a source object is not as large as or was last modified more recently than its paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped.</p> <p>CRC64_COMPARISON_OVERWRITE indicates the system allows overwrite if the source and destination objects have different CRC64 checksums. This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object has a CRC64 checksum different from the paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped. If one of them does not have a CRC64 checksum, their sizes and last modification times are checked.</p> <p>FULL_OVERWRITE indicates the system always allows overwrite. The system always allows source objects to overwrite their paired destination objects.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • NO_OVERWRITE • SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE • CRC64_COMPARISON_OVERWRITE • FULL_OVERWRITE

Parameter	Type	Description
dst_storage_policy	String	<p>The destination storage class. STANDARD indicates the Huawei Cloud OBS Standard. IA indicates the Huawei Cloud OBS Infrequent Access. ARCHIVE indicates the Huawei Cloud OBS Archive. DEEP_ARCHIVE indicates the Huawei Cloud OBS Deep Archive.</p> <p>SRC_STORAGE_MAPPING converts the source storage class into an OBS storage class based on the predefined rules.</p> <p>Default value: STANDARD</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 128 characters</p> <p>The value can be:</p> <ul style="list-style-type: none">• STANDARD• IA• ARCHIVE• DEEP_ARCHIVE• SRC_STORAGE_MAPPING

Parameter	Type	Description
consistency_check	String	<p>The consistency check method, which is used to check whether objects are consistent before and after migration. The selected check method and results will be recorded in the object list. The default value is size_last_modified.</p> <p>size_last_modified: It is the default setting. The system checks object consistency with object size and last modification time. If a source object is as large as but was last modified earlier than its paired destination object, the system considers the source object does not need to be migrated or has been already migrated successfully.</p> <p>crc64: This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object and its paired destination object have CRC64 checksums, the checksums are checked. Otherwise, their sizes and last modification times are checked.</p> <p>no_check: This option is only available for migration of HTTP/HTTPS data. This option takes effect for source objects whose sizes cannot be obtained using the content-length field in the standard HTTP protocol. These source objects will overwrite their paired destination objects directly. If the size of a source object can be obtained from the Content-Length field in the standard HTTP protocol, its size and last modification time will be checked.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • size_last_modified • crc64 • no_check
enable_requester_pays	Boolean	Indicates whether to let the requester make payment. After this function is enabled, the requester pays for the request and data transmission.
task_priority	String	<p>The task priority.</p> <p>Default value: MEDIUM</p> <p>The value can be:</p> <ul style="list-style-type: none"> • HIGH • MEDIUM • LOW

Table 6-16 BandwidthPolicyDto field description

Parameter	Type	Description
end	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.
max_bandwidth	Long	The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s). Minimum value: 1048576 Maximum value: 209715200
start	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Table 6-17 DstNodeResp field description

Parameter	Type	Description
bucket	String	The name of the destination bucket. Maximum length: 1,024 characters
region	String	The region where the destination bucket is located. The value must be the same as that of the service endpoint. Minimum length: 0 characters Maximum length: 100 characters
save_prefix	String	The path prefix in the destination bucket. The prefix is added before an object key to form a new key. The length of the new key cannot exceed 1,024 characters. Minimum length: 0 characters Maximum length: 1,024 characters

Table 6-18 ErrorReasonResp field description

Parameter	Type	Description
error_code	String	The error code returned for a migration failure. Minimum length: 0 characters Maximum length: 10 characters

Parameter	Type	Description
error_msg	String	The migration failure cause. Minimum length: 0 characters Maximum length: 1,024 characters

Table 6-19 FailedObjectRecordDto field description

Parameter	Type	Description
result	Boolean	Indicates whether to retransmit failed objects.
list_file_key	String	The path for storing the list of failed objects. Minimum length: 0 characters Maximum length: 1,024 characters
error_code	String	The error code returned when the list of failed objects fails to be uploaded. Minimum length: 0 characters Maximum length: 10 characters

Table 6-20 SrcNodeResp field description

Parameter	Type	Description
bucket	String	The name of the source bucket. Minimum length: 0 characters Maximum length: 1,024 characters

Parameter	Type	Description
cloud_type	String	<p>The source cloud service provider. The value can be AWS, Azure, Aliyun, Tencent, HuaweiCloud, QingCloud, KingsoftCloud, Baidu, Google, Qiniu, URLSource, or UCloud. The default value is Aliyun.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • AWS • Azure • Aliyun • Tencent • HuaweiCloud • QingCloud • KingsoftCloud • Baidu • Qiniu • URLSource • UCloud • Google
region	String	<p>The region where the source bucket is located.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 100 characters</p>
app_id	String	<p>This parameter is returned when cloud_type is Tencent.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 255 characters</p>
object_key	Array of strings	<p>If the task_type is object, this parameter indicates the names of the objects to be migrated. If the task_type is prefix, this parameter indicates the name prefixes of the objects to be migrated.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 1,024 characters</p> <p>Array length: 0 to 500</p>
list_file	ListFile object	<p>The list file configuration. list_file is mandatory when task_type is set to list or url_list.</p>

Table 6-21 ListFile field description

Parameter	Type	Description
list_file_key	String	The object names in the object list file or URL list file. Minimum length: 1 character Maximum length: 1,024 characters
obs_bucket	String	The name of the OBS bucket for storing the object list files. Ensure that the OBS bucket is in the same region as the destination bucket, or the task will fail to be created. Minimum length: 0 characters Maximum length: 1,024 characters
list_file_num	String	The number of stored object list files. Minimum length: 0 characters Maximum length: 65,535 characters

Table 6-22 SmnInfo field description

Parameter	Type	Description
notify_result	Boolean	Indicates whether the SMN messages are sent successfully after migration tasks are complete.
notify_error_message	String	The error codes that record why the SMN messages failed to be sent. The value is empty if migration tasks are successful. Minimum length: 0 characters Maximum length: 1,024 characters
topic_name	String	The SMN topic name. The value is empty if SMN messages are sent successfully. Minimum length: 0 characters Maximum length: 5,120 characters

Table 6-23 SourceCdnResp field description

Parameter	Type	Description
domain	String	The domain name from which to obtain objects to be migrated. Minimum length: 0 characters Maximum length: 1,024 characters

Parameter	Type	Description
protocol	String	The protocol type. The value can be: <ul style="list-style-type: none">• HTTP• HTTPS
authentication_type	String	The authentication type. The value can be: <ul style="list-style-type: none">• NONE• QINIU_PRIVATE_AUTHENTICATION• ALIYUN_OSS_A• ALIYUN_OSS_B• ALIYUN_OSS_C• KSYUN_PRIVATE_AUTHENTICATION• AZURE_SAS_TOKEN• TENCENT_COS_A• TENCENT_COS_B• TENCENT_COS_C• TENCENT_COS_D

Status code: 400

Table 6-24 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries 10 failed tasks under the project whose ID is **2c0689c860ad4728a497c91ec0844383**.

```
GET https://{endpoint}/v2/2c0689c860ad4728a497c91ec0844383/tasks?offset=0&limit=10&status=4
```

Example Response

Status code: 200

OK

```
{  
  "tasks" : [ {  
    "bandwidth_policy" : [ {
```

```
"end" : "23:59",
"max_bandwidth" : 0,
"start" : "00:00"
} ],
"complete_size" : 0,
"description" : "test log",
"dst_node" : {
"bucket" : "dst_bucket",
"region" : "cn-north-1"
},
"enable_failed_object_recording" : true,
"enable_kms" : true,
"enable_restore" : false,
"error_reason" : {
"error_code" : "string",
"error_msg" : "string"
},
"failed_num" : 0,
"failed_object_record" : {
"result" : true,
"list_file_key" : "string",
"error_code" : "string"
},
"group_id" : "string",
"id" : 0,
"is_query_over" : true,
"left_time" : 0,
"migrate_since" : 0,
"migrate_speed" : 0,
"name" : "string",
"progress" : 0,
"real_size" : 0,
"skipped_num" : 0,
"src_node" : {
"bucket" : "src_bucket",
"cloud_type" : "AWS",
"region" : "cn-north-1",
"app_id" : "string",
"object_key" : [ "string", "string" ],
"list_file" : {
"list_file_key" : "object_list_file.txt",
"obs_bucket" : "obs_bucket"
}
},
"start_time" : 0,
"status" : 0,
"successful_num" : 0,
"task_type" : "list",
"total_num" : 0,
"total_size" : 0,
"total_time" : 0,
"smn_info" : {
"notify_result" : true,
"notify_error_message" : "string",
"topic_name" : "string"
},
"source_cdn" : {
"domain" : "xxx.xxx.xxx",
"protocol" : "http",
"authentication_type" : "string"
}
},
"count" : 1
}
```

Status Codes

Status Code	Description
200	OK
400	Bad Request

Error Codes

For details, see [Error Codes](#).

6.2.2 Querying a Migration Task

Function

This API is used to query details about a task with a specified ID.

Calling Method

For details, see [Calling APIs](#).

URI

GET /v2/{project_id}/tasks/{task_id}

Table 6-25 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
task_id	Yes	String	The task ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-26 Request header parameter

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 200

Table 6-27 Response body parameters

Parameter	Type	Description
bandwidth_policy	Array of BandwidthPolicyDto objects	The traffic limiting rules. A maximum of five traffic limiting rules can be set for a single task. Array length: 0 to 5
complete_size	Long	The size (in bytes) of the objects that have been migrated in the task. Minimum value: 0 Maximum value: 9223372036854775807
description	String	The task description. If this parameter is not set, the value is an empty string. Minimum length: 0 characters Maximum length: 255 characters
dst_node	DstNodeResp object	The destination node information.
enable_failed_object_recording	Boolean	Indicates whether to record the objects that failed to be migrated. If this function is enabled, information about objects that fail to be migrated will be stored in the destination bucket.
enable_kms	Boolean	Indicates whether to use KMS to encrypt the data to be stored in the destination OBS bucket.

Parameter	Type	Description
enable_metadata_migration	Boolean	Indicates whether metadata migration is enabled. The default value is false . Even if this function is disabled, the ContentType metadata will still be migrated to ensure a successful migration.
enable_restore	Boolean	Indicates whether to restore archive data in the source bucket. It takes a long time to restore archive data in the source bucket, which will greatly slow down the migration speed. You are advised to restore the archive objects before the migration. After this function is enabled, archive objects will be automatically restored and then migrated. By default, this function is disabled, archive objects will be ignored during the migration, and the information about these objects will be recorded in the list of failed objects.
error_reason	ErrorReasonResponse object	The task failure cause. The value is an empty string if the task is not in the Migration failed state.
failed_num	Long	The number of objects that failed to be migrated. Minimum value: 0 Maximum value: 9223372036854775807
failed_object_record	FailedObjectRecordDto object	The records of the objects that failed to be migrated. If the record is successful, the path for storing the list of failed objects is displayed. If the record fails, the failure cause is displayed.
group_id	String	The ID of migration task group to which the task belongs. If a task is created by a migration task group, the ID of the migration task group is included. Minimum length: 0 characters Maximum length: 36 characters
id	Long	The task ID. Minimum value: 0 Maximum value: 9999999999999999
is_query_over	Boolean	Indicates whether the source object statistics are scanned for the migration task.

Parameter	Type	Description
left_time	Long	The remaining time (in milliseconds) of the task. Minimum value: 0 Maximum value: 9223372036854775807
migrate_since	Long	The specified migration time (timestamp, in milliseconds). Only source objects that are modified after the specified time will be migrated. Default value 0 indicates that no time is specified. Minimum value: 0 Maximum value: 9223372036854775807
migrate_speed	Long	The migration speed (byte/s). Minimum value: 0 Maximum value: 9223372036854775807
name	String	The task name. Minimum length: 0 characters Maximum length: 10,240 characters
progress	Double	The task progress. For example, 0.522 represents the progress is 52.2%, and 1 represents the progress is 100%. Minimum value: 0 Maximum value: 1
real_size	Long	The total size (in bytes) of the migrated objects. The size of ignored objects is not counted. Minimum value: 0 Maximum value: 9223372036854775807
skipped_num	Long	The number of objects that are skipped during the migration. The following objects will be skipped: objects whose last modification time is earlier than the specified migration time, and objects that exist in the destination bucket. Minimum value: 0 Maximum value: 9223372036854775807
src_node	SrcNodeResp object	The source node information.
start_time	Long	The start time (UNIX timestamp, in milliseconds) of the migration task. Minimum value: 0 Maximum value: 9223372036854775807

Parameter	Type	Description
status	Integer	The task status. 1 : Waiting, 2 : Migrating, 3 : Paused, 4 : Failed, 5 : Succeeded, 7 : Pausing Minimum value: 1 Maximum value: 7
successful_num	Long	The number of successfully migrated objects. Minimum value: 0 Maximum value: 9223372036854775807
task_type	String	The task type. list indicates migrating objects using an object list. object indicates migrating selected files or folders. prefix indicates migrating objects with specified prefixes. url_list indicates migrating objects using a URL object list. Default value: object The value can be: <ul style="list-style-type: none">• list• object• prefix• url_list
group_type	String	The task group type. NORMAL_TASK indicates a general migration task. SYNC_TASK indicates a migration task to which a synchronization task belongs. GROUP_TASK indicates a subtask in a migration task group. Default value: NORMAL_TASK The value can be: <ul style="list-style-type: none">• NORMAL_TASK• SYNC_TASK• GROUP_TASK
total_num	Long	The total number of the objects that have been migrated in the task. Minimum value: 0 Maximum value: 9223372036854775807
total_size	Long	The size (in bytes) of the objects that have been migrated in the task. Minimum value: 0 Maximum value: 9223372036854775807
total_time	Long	The total time used (in milliseconds). Minimum value: 0 Maximum value: 9223372036854775807

Parameter	Type	Description
smn_info	SmnInfo object	The SMN notification results.
source_cdn	SourceCdnResponse object	Indicates whether migration from CDN is enabled. If it is enabled, the source objects to be migrated are obtained from the specified CDN domain name during migration. If this field is included, migration from CDN is supported. Otherwise, it is not supported.
success_record_error_reason	String	<p>The error code returned for the failure in recording the list of objects that are successfully migrated. If the list is recorded successfully, this parameter is left blank.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 255 characters</p>
skip_record_error_reason	String	<p>The error code returned for the failure in recording the list of objects that are ignored. If the list is recorded successfully, this parameter is left blank.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 255 characters</p>

Parameter	Type	Description
object_overwrite_mode	String	<p>Indicates whether to skip a source object or allow the source object to overwrite its paired destination object. The default value is SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE. NO_OVERWRITE indicates the system never allows overwrite. The system always skips source objects and keeps their paired destination objects.</p> <p>SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE indicates the system allows overwrite based on the results of size or modification time checks. It is the default setting. If a source object is not as large as or was last modified more recently than its paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped.</p> <p>CRC64_COMPARISON_OVERWRITE indicates the system allows overwrite if the source and destination objects have different CRC64 checksums. This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object has a CRC64 checksum different from the paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped. If one of them does not have a CRC64 checksum, their sizes and last modification times are checked.</p> <p>FULL_OVERWRITE indicates the system always allows overwrite. The system always allows source objects to overwrite their paired destination objects.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • NO_OVERWRITE • SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE • CRC64_COMPARISON_OVERWRITE • FULL_OVERWRITE

Parameter	Type	Description
dst_storage_policy	String	<p>The destination storage class. STANDARD indicates the Huawei Cloud OBS Standard. IA indicates the Huawei Cloud OBS Infrequent Access. ARCHIVE indicates the Huawei Cloud OBS Archive. DEEP_ARCHIVE indicates the Huawei Cloud OBS Deep Archive.</p> <p>SRC_STORAGE_MAPPING converts the source storage class into an OBS storage class based on the predefined rules.</p> <p>Default value: STANDARD</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 128 characters</p> <p>The value can be:</p> <ul style="list-style-type: none">• STANDARD• IA• ARCHIVE• DEEP_ARCHIVE• SRC_STORAGE_MAPPING

Parameter	Type	Description
consistency_check	String	<p>The consistency check method, which is used to check whether objects are consistent before and after migration. The selected check method and results will be recorded in the object list. The default value is size_last_modified.</p> <p>size_last_modified: It is the default setting. The system checks object consistency with object size and last modification time. If a source object is as large as but was last modified earlier than its paired destination object, the system considers the source object does not need to be migrated or has been already migrated successfully.</p> <p>crc64: This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object and its paired destination object have CRC64 checksums, the checksums are checked. Otherwise, their sizes and last modification times are checked.</p> <p>no_check: This option is only available for migration of HTTP/HTTPS data. This option takes effect for source objects whose sizes cannot be obtained using the content-length field in the standard HTTP protocol. These source objects will overwrite their paired destination objects directly. If the size of a source object can be obtained from the Content-Length field in the standard HTTP protocol, its size and last modification time will be checked.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • size_last_modified • crc64 • no_check
enable_requester_pays	Boolean	Indicates whether to let the requester make payment. After this function is enabled, the requester pays for the request and data transmission.
task_priority	String	<p>The task priority.</p> <p>Default value: MEDIUM</p> <p>The value can be:</p> <ul style="list-style-type: none"> • HIGH • MEDIUM • LOW

Table 6-28 BandwidthPolicyDto field description

Parameter	Type	Description
end	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.
max_bandwidth	Long	The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s). Minimum value: 1048576 Maximum value: 209715200
start	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Table 6-29 DstNodeResp field description

Parameter	Type	Description
bucket	String	The name of the destination bucket. Maximum length: 1,024 characters
region	String	The region where the destination bucket is located. The value must be the same as that of the service endpoint. Minimum length: 0 characters Maximum length: 100 characters
save_prefix	String	The path prefix in the destination bucket. The prefix is added before an object key to form a new key. The length of the new key cannot exceed 1,024 characters. Minimum length: 0 characters Maximum length: 1,024 characters

Table 6-30 ErrorReasonResp field description

Parameter	Type	Description
error_code	String	The error code returned for a migration failure. Minimum length: 0 characters Maximum length: 10 characters

Parameter	Type	Description
error_msg	String	The migration failure cause. Minimum length: 0 characters Maximum length: 1,024 characters

Table 6-31 FailedObjectRecordDto field description

Parameter	Type	Description
result	Boolean	Indicates whether to retransmit failed objects.
list_file_key	String	The path for storing the list of failed objects. Minimum length: 0 characters Maximum length: 1,024 characters
error_code	String	The error code returned when the list of failed objects fails to be uploaded. Minimum length: 0 characters Maximum length: 10 characters

Table 6-32 SrcNodeResp field description

Parameter	Type	Description
bucket	String	The name of the source bucket. Minimum length: 0 characters Maximum length: 1,024 characters

Parameter	Type	Description
cloud_type	String	<p>The source cloud service provider. The value can be AWS, Azure, Aliyun, Tencent, HuaweiCloud, QingCloud, KingsoftCloud, Baidu, Google, Qiniu, URLSource, or UCloud. The default value is Aliyun.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • AWS • Azure • Aliyun • Tencent • HuaweiCloud • QingCloud • KingsoftCloud • Baidu • Qiniu • URLSource • UCloud • Google
region	String	<p>The region where the source bucket is located.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 100 characters</p>
app_id	String	<p>This parameter is returned when cloud_type is Tencent.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 255 characters</p>
object_key	Array of strings	<p>If the task_type is object, this parameter indicates the names of the objects to be migrated. If the task_type is prefix, this parameter indicates the name prefixes of the objects to be migrated.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 1,024 characters</p> <p>Array length: 0 to 500</p>
list_file	ListFile object	<p>The list file configuration. list_file is mandatory when task_type is set to list or url_list.</p>

Table 6-33 ListFile field description

Parameter	Type	Description
list_file_key	String	The object names in the object list file or URL list file. Minimum length: 1 character Maximum length: 1,024 characters
obs_bucket	String	The name of the OBS bucket for storing the object list files. Ensure that the OBS bucket is in the same region as the destination bucket, or the task will fail to be created. Minimum length: 0 characters Maximum length: 1,024 characters
list_file_num	String	The number of stored object list files. Minimum length: 0 characters Maximum length: 65,535 characters

Table 6-34 SmnInfo field description

Parameter	Type	Description
notify_result	Boolean	Indicates whether the SMN messages are sent successfully after migration tasks are complete.
notify_error_message	String	The error codes that record why the SMN messages failed to be sent. The value is empty if migration tasks are successful. Minimum length: 0 characters Maximum length: 1,024 characters
topic_name	String	The SMN topic name. The value is empty if SMN messages are sent successfully. Minimum length: 0 characters Maximum length: 5,120 characters

Table 6-35 SourceCdnResp field description

Parameter	Type	Description
domain	String	The domain name from which to obtain objects to be migrated. Minimum length: 0 characters Maximum length: 1,024 characters

Parameter	Type	Description
protocol	String	The protocol type. The value can be: <ul style="list-style-type: none">• HTTP• HTTPS
authentication_type	String	The authentication type. The value can be: <ul style="list-style-type: none">• NONE• QINIU_PRIVATE_AUTHENTICATION• ALIYUN_OSS_A• ALIYUN_OSS_B• ALIYUN_OSS_C• KSYUN_PRIVATE_AUTHENTICATION• AZURE_SAS_TOKEN• TENCENT_COS_A• TENCENT_COS_B• TENCENT_COS_C• TENCENT_COS_D

Status code: 404

Table 6-36 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries the details of task **191297407830872** in project **2c0689c860ad4728a497c91ec0844383**.

```
GET https://{endpoint}/v2/2c0689c860ad4728a497c91ec0844383/tasks/191297407830872
```

Example Response

Status code: 200

OK

```
{  
  "bandwidth_policy" : [ {  
    "end" : "23:59",  
    "start" : "00:00"  
  } ]  
}
```

```
"max_bandwidth" : 0,
"start" : "00:00"
},
"complete_size" : 0,
"description" : "test log",
"dst_node" : {
  "bucket" : "dst_bucket",
  "region" : "cn-north-1"
},
"enable_failed_object_recording" : true,
"enable_kms" : true,
"enable_restore" : false,
"error_reason" : {
  "error_code" : "string",
  "error_msg" : "string"
},
"failed_num" : 0,
"failed_object_record" : {
  "result" : true,
  "list_file_key" : "string",
  "error_code" : "string"
},
"group_id" : "string",
"id" : 0,
"is_query_over" : true,
"left_time" : 0,
"migrate_since" : 0,
"migrate_speed" : 0,
"name" : "string",
"progress" : 0,
"real_size" : 0,
"skipped_num" : 0,
"src_node" : {
  "bucket" : "src_bucket",
  "cloud_type" : "AWS",
  "region" : "cn-north-1",
  "app_id" : "string",
  "object_key" : [ "string", "string" ],
  "list_file" : {
    "list_file_key" : "object_list_file.txt",
    "obs_bucket" : "obs_bucket"
  }
},
"start_time" : 0,
"status" : 0,
"successful_num" : 0,
"task_type" : "list",
"total_num" : 0,
"total_size" : 0,
"total_time" : 0,
"smn_info" : {
  "notify_result" : true,
  "notify_error_message" : "string",
  "topic_name" : "string"
},
"source_cdn" : {
  "domain" : "xxx.xxx.xxx",
  "protocol" : "http",
  "authentication_type" : "string"
}
}
```

Status Codes

Status Code	Description
200	OK
404	Not Found

Error Codes

For details, see [Error Codes](#).

6.2.3 Creating a Migration Task

Function

This API is used to create a migration task. After the migration task is created, it will be automatically started.

Constraints

- A tenant can create a maximum of 1,500 migration tasks within 24 hours.
- A tenant cannot create more migration tasks if the tenant already has 1,500 migration tasks in the **Waiting to migrate** state.

Calling Method

For details, see [Calling APIs](#).

URI

POST /v2/{project_id}/tasks

Table 6-37 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-38 Request header parameter

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-39 Request body parameters

Parameter	Mandatory	Type	Description
task_type	No	String	The task type. list indicates migrating objects using an object list. url_list indicates migrating objects using a URL object list. object indicates migrating selected files or folders. prefix indicates migrating objects with specified prefixes. Default value: object The value can be: <ul style="list-style-type: none">• list• url_list• object• prefix
src_node	Yes	SrcNodeReq object	The source information.
dst_node	Yes	DstNodeReq object	The destination information.
enable_kms	No	Boolean	Indicates whether KMS encryption is enabled. This function is disabled by default. Default value: false

Parameter	Mandatory	Type	Description
description	No	String	<p>The task group description, which cannot exceed 255 characters. The following special characters are not allowed: ^<>& ""</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 255 characters</p>
migrate_since	No	Long	<p>A timestamp in second. The system migrates only the objects that are modified after the specified time. No time is specified by default.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p> <p>Default value: 0</p>
bandwidth_policy	No	Array of BandwidthPolicyDto objects	<p>The traffic limiting rules. Each element in the array corresponds to the maximum bandwidth in a time period. A maximum of five periods are allowed, and the periods cannot overlap.</p> <p>Array length: 0 to 5</p>
source_cdn	No	SourceCdnReq object	<p>Indicates whether migration from CDN is enabled. If this field is contained, migration from CDN is supported. Otherwise, it is not supported. If migration from CDN is enabled, the source objects to be migrated are obtained from the specified CDN domain name during migration.</p>
smn_config	No	SmnConfig object	The SMN message sending configuration.
enable_metadata_migration	No	Boolean	<p>Indicates whether metadata migration is enabled. The default value is false. Even if this function is disabled, the ContentType metadata will still be migrated to ensure a successful migration.</p> <p>Default value: false</p>

Parameter	Mandatory	Type	Description
enable_restore	No	Boolean	<p>Indicates whether archive data restoration is enabled.</p> <p>If this function is enabled, archive data is automatically restored and migrated.</p> <p>Default value: false</p>
enable_failed_object_recording	No	Boolean	<p>Indicates whether to record failed objects. This function is enabled by default.</p> <p>If this function is enabled, information about objects that fail to be migrated will be stored in the destination bucket.</p> <p>Default value: true</p>

Parameter	Mandatory	Type	Description
object_overwrite_mode	No	String	<p>Indicates whether to skip a source object or allow the source object to overwrite its paired destination object. The default value is SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE. NO_OVERWRITE indicates the system never allows overwrite. The system always skips source objects and keeps their paired destination objects. SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE indicates the system allows overwrite based on the results of size or modification time checks. It is the default setting. If a source object is not as large as or was last modified more recently than its paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped. CRC64_COMPARISON_OVERWRITE indicates the system allows overwrite if the source and destination objects have different CRC64 checksums. This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object has a CRC64 checksum different from the paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped. If one of them does not have a CRC64 checksum, their sizes and last modification times are checked. FULL_OVERWRITE indicates the system always allows overwrite. The system always allows source objects</p>

Parameter	Mandatory	Type	Description
			<p>to overwrite their paired destination objects.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • NO_OVERWRITE • SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE • CRC64_COMPARISON_OVERWRITE • FULL_OVERWRITE
dst_storage_policy	No	String	<p>The destination storage class. STANDARD indicates the Huawei Cloud OBS Standard. IA indicates the Huawei Cloud OBS Infrequent Access. ARCHIVE indicates the Huawei Cloud OBS Archive. DEEP_ARCHIVE indicates the Huawei Cloud OBS Deep Archive. SRC_STORAGE_MAPPING converts the source storage class into an OBS storage class based on the predefined rules. Default value: STANDARD. Minimum length: 0 characters. Maximum length: 128 characters.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • STANDARD • IA • ARCHIVE • DEEP_ARCHIVE • SRC_STORAGE_MAPPING

Parameter	Mandatory	Type	Description
consistency_check	No	String	<p>The consistency check method, which is used to check whether objects are consistent before and after migration. The selected check method and results will be recorded in the object list. The default value is size_last_modified.</p> <p>size_last_modified: It is the default setting. The system checks object consistency with object size and last modification time. If a source object is as large as but was last modified earlier than its paired destination object, the system considers the source object does not need to be migrated or has been already migrated successfully.</p> <p>crc64: This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object and its paired destination object have CRC64 checksums, the checksums are checked. Otherwise, their sizes and last modification times are checked.</p> <p>no_check: This option is only available for migration of HTTP/HTTPS data. This option takes effect for source objects whose sizes cannot be obtained using the content-length field in the standard HTTP protocol. These source objects will overwrite their paired destination objects directly. If the size of a source object can be obtained from the Content-Length field in the standard HTTP protocol, its size and last modification time will be checked.</p> <p>Default value: size_last_modified</p> <p>The value can be:</p> <ul style="list-style-type: none"> • size_last_modified

Parameter	Mandatory	Type	Description
			<ul style="list-style-type: none"> • crc64 • no_check
enable_requester_pays	No	Boolean	Indicates whether to let the requester make payment. After this function is enabled, the requester pays for the request and data transmission. Default value: false
task_priority	No	String	The task priority. Default value: MEDIUM The value can be: <ul style="list-style-type: none"> • HIGH • MEDIUM • LOW

Table 6-40 SrcNodeReq

Parameter	Mandatory	Type	Description
cloud_type	No	String	The source cloud service provider. If task_type is not url_list , this parameter is mandatory and must be URLSource . The value can be AWS , Azure , Aliyun , Tencent , HuaweiCloud , QingCloud , KingsoftCloud , Baidu , Qiniu , Google , URLSource , or UCloud . The default value is Aliyun . Default value: Aliyun
region	No	String	The region where the source bucket is located. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters

Parameter	Mandatory	Type	Description
ak	No	String	The AK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters
sk	No	String	The SK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters
json_auth_file	No	String	The file used for Google Cloud Storage authentication. Minimum length: 0 characters Maximum length: 65,535 characters
security_token	No	String	The temporary token for accessing the source bucket. Minimum length: 0 characters Maximum length: 16,384 characters
app_id	No	String	This parameter is mandatory when cloud_type is Tencent . Minimum length: 0 characters Maximum length: 255 characters
bucket	No	String	The name of the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 1,024 characters

Parameter	Mandatory	Type	Description
object_key	No	Array of strings	If task-type is set to object , this parameter specifies the names of the objects to be migrated. The character strings ending with a slash (/) indicate the folders to be migrated, and the character strings not ending with a slash (/) indicate the files to be migrated. The name prefixes of objects to be migrated if task_type is set to prefix . If you want to migrate the entire bucket, set this parameter to [""]. Minimum length: 0 characters Maximum length: 1,024 characters Array length: 0 to 500
list_file	No	ListFile object	The list file configuration. list_file is mandatory when task_type is set to list or url_list .

Table 6-41 ListFile field description

Parameter	Mandatory	Type	Description
list_file_key	Yes	String	The object names in the object list file or URL list file. Minimum length: 1 character Maximum length: 1,024 characters
obs_bucket	Yes	String	The name of the OBS bucket for storing the object list files. Ensure that the OBS bucket is in the same region as the destination bucket, or the task will fail to be created. Minimum length: 0 characters Maximum length: 1,024 characters

Parameter	Mandatory	Type	Description
list_file_num	No	String	The number of stored object list files. Minimum length: 0 characters Maximum length: 65,535 characters

Table 6-42 DstNodeReq field description

Parameter	Mandatory	Type	Description
ak	Yes	String	The AK for accessing the destination bucket. Minimum length: 0 characters Maximum length: 100 characters
sk	Yes	String	The SK for accessing the destination bucket. Minimum length: 0 characters Maximum length: 100 characters
security_token	No	String	The temporary token for accessing the destination bucket. Minimum length: 0 characters Maximum length: 16,384 characters
bucket	Yes	String	The name of the destination bucket. Minimum length: 0 characters Maximum length: 1,024 characters
save_prefix	No	String	The path prefix in the destination bucket. The prefix is added before an object key to form a new key. The length of the new key cannot exceed 1,024 characters. Minimum length: 0 characters Maximum length: 1,024 characters

Parameter	Mandatory	Type	Description
region	Yes	String	The region where the destination bucket is located. The value must be the same as that of the service endpoint. Minimum length: 0 characters Maximum length: 100 characters

Table 6-43 BandwidthPolicyDto field description

Parameter	Mandatory	Type	Description
end	Yes	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.
max_bandwidth	Yes	Long	The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s). Minimum value: 1048576 Maximum value: 209715200
start	Yes	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Table 6-44 SourceCdnReq field description

Parameter	Mandatory	Type	Description
authentication_key	No	String	<p>The CDN authentication key. If the CDN authentication is required, this parameter is mandatory.</p> <p>If no authorization is required, do not set this parameter.</p> <p>Qiniu: You do not need to set this parameter. Aliyun: Set this parameter based on the value of authentication_type.</p> <p>KingsCloud: You do not need to set this parameter.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 255 characters</p>
authentication_type	Yes	String	<p>The authentication type.</p> <p>Default value: NONE</p> <p>The value can be:</p> <ul style="list-style-type: none"> • NONE • QINIU_PRIVATE_AUTHENTICATION • ALIYUN_OSS_A • ALIYUN_OSS_B • ALIYUN_OSS_C • KSYUN_PRIVATE_AUTHENTICATION • AZURE_SAS_TOKEN • TENCENT_COS_A • TENCENT_COS_B • TENCENT_COS_C • TENCENT_COS_D
domain	Yes	String	<p>The domain name from which to obtain objects to be migrated.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 1,024 characters</p>

Parameter	Mandatory	Type	Description
protocol	Yes	String	<p>The protocol type. The value can be:</p> <ul style="list-style-type: none"> • HTTP • HTTPS

Table 6-45 SmnConfig field description

Parameter	Mandatory	Type	Description
language	No	String	<p>The management console language chosen by you. The value can be zh-cn or en-us. Default value: en-us The value can be:</p> <ul style="list-style-type: none"> • zh-cn • en-us
topic_urn	Yes	String	<p>The SMN message topic URN bound to a migration task. Minimum length: 0 characters Maximum length: 1,024 characters</p>
trigger_conditions	Yes	Array of strings	<p>The trigger conditions of sending messages using SMN. The message varies depending on the status of the migration task. The migration task state can be SUCCESS or FAILURE.</p> <ul style="list-style-type: none"> • FAILURE: indicates that an SMN message will be sent after the migration task fails. • SUCCESS: indicates that an SMN message will be sent after the migration task succeeds. <p>Array length: 1 to 2</p>

Parameter	Mandatory	Type	Description
message_template_name	No	String	If this parameter is specified, SMN messages are sent using the specified template. Template example: <pre>{"Task_Status": "", "Task_Name": "", "Start_Time": "", "Total_Time_Used": "", "Transferred_Data": "", "Average_Speed": "", "Source_Bucket": "", "Destination_Bucket": "", "List_File_Bucket": "", "List_File_Key": "", "Success_object_list_path": "", "Skip_object_list_path": "", "Failed_object_list_path": "" }</pre>

Response

Status code: 200

Table 6-46 Response body parameters

Parameter	Type	Description
id	Long	The task ID. Minimum value: 0 Maximum value: 9999999999999999
task_name	String	The task name. Minimum length: 0 characters Maximum length: 2,048 characters

Status code: 400

Table 6-47 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

- This example migrates HTTPS data from Alibaba Cloud CDN, uses the type A authentication mode, enables time period-based rate limiting, sets the rate limit to 50 MB/s, migrates objects in **object_list_file.txt**, and enables migration result notification.

```
POST https://{endpoint}/v2/{project_id}/tasks
```

```
{  
    "task_type" : "list",  
    "src_node" : {  
        "cloud_type" : "HuaweiCloud",  
        "region" : "cn-north-1",  
        "bucket" : "src_bucket",  
        "ak" : "src_ak",  
        "sk" : "src_sk",  
        "list_file" : {  
            "obs_bucket" : "list_file_bucket",  
            "list_file_key" : "object_list_file.txt"  
        }  
    },  
    "dst_node" : {  
        "region" : "cn-north-1",  
        "ak" : "dst_ak",  
        "sk" : "dst_sk",  
        "bucket" : "dst_bucket"  
    },  
    "enable_kms" : false,  
    "enable_failed_object_recording" : true,  
    "description" : "xxx",  
    "migrate_since" : 123456789,  
    "bandwidth_policy" : [ {  
        "start" : "00:00",  
        "end" : "23:59",  
        "max_bandwidth" : 50000000  
    } ],  
    "source_cdn" : {  
        "protocol" : "https",  
        "domain" : "xxx.xxx.xxx",  
        "authentication_type" : "ALIYUN_OSS_A",  
        "authentication_key" : "xxx"  
    },  
    "smn_config" : {  
        "topic_urn" : "urn:smn:region:4cf2090802d94440b4cdd72ef26857b2:OMS",  
        "trigger_conditions" : [ "SUCCESS", "FAILURE" ],  
        "language" : "en-us"  
    }  
}
```

- This example migrates HTTPS data from Alibaba Cloud CDN, uses the type A authentication mode, enables time period-based rate limiting, sets the rate limit to 50 MB/s, migrates object **file1.xxx** and **file2.xxx** and objects prefixed with **path1/**, and enables migration result notification.

```
POST https://{endpoint}/v2/{project_id}/tasks
```

```
{  
    "task_type" : "object",  
    "src_node" : {  
        "cloud_type" : "HuaweiCloud",  
        "region" : "cn-north-1",  
        "bucket" : "src_bucket",  
        "ak" : "src_ak",  
        "sk" : "src_sk",  
        "object_key" : [ "file1.xxx", "file2.xxx", "path1/" ]  
    },  
    "dst_node" : {  
        "region" : "cn-north-1",  
    }
```

```
        "ak" : "dst_ak",
        "sk" : "dst_sk",
        "bucket" : "dst_bucket"
    },
    "enable_kms" : false,
    "enable_failed_object_recording" : true,
    "description" : "xxx",
    "migrate_since" : 123456789,
    "bandwidth_policy" : [ {
        "start" : "00:00",
        "end" : "23:59",
        "max_bandwidth" : 50000000
    } ],
    "source_cdn" : {
        "protocol" : "https",
        "domain" : "xxx.xxx.xxx",
        "authentication_type" : "ALIYUN_OSS_A",
        "authentication_key" : "xxx"
    },
    "smn_config" : {
        "topic_urn" : "urn:smn:region:4cf2090802d94440b4cdd72ef26857b2:OMS",
        "trigger_conditions" : [ "SUCCESS", "FAILURE" ],
        "language" : "en-us"
    }
}
```

- This example creates a URL list migration task to migrate objects listed in the **object_list_file.txt** file.

POST https://{{endpoint}}/v2/{{project_id}}/tasks

```
{
    "task_type" : "url_list",
    "src_node" : {
        "cloud_type" : "URLSource",
        "list_file" : {
            "obs_bucket" : "list_file_bucket",
            "list_file_key" : "object_list_file.txt"
        }
    },
    "dst_node" : {
        "region" : "cn-north-1",
        "ak" : "dst_ak",
        "sk" : "dst_sk",
        "bucket" : "dst_bucket"
    },
    "enable_kms" : false,
    "enable_failed_object_recording" : true,
    "description" : "xxx"
}
```

- This example creates a prefix-based migration task to migrate objects prefixed with "abc", "123", "prefix3", or "path/prefix4".

POST https://{{endpoint}}/v2/{{project_id}}/tasks

```
{
    "task_type" : "prefix",
    "src_node" : {
        "cloud_type" : "HuaweiCloud",
        "region" : "cn-north-1",
        "bucket" : "src_bucket",
        "ak" : "src_ak",
        "sk" : "src_sk",
        "object_key" : [ "abc", "123", "prefix3", "path/prefix4" ]
    },
    "dst_node" : {
        "region" : "cn-north-1",
        "ak" : "dst_ak",
        "sk" : "dst_sk",
        "bucket" : "dst_bucket"
    }
}
```

```
        },
        "enable_kms" : false,
        "enable_failed_object_recording" : true,
        "description" : "xxx"
    }
```

Example Response

Status code: 200

Created

```
{
    "id" : 200429548242937,
    "task_name" : "task_name"
}
```

Status Codes

Status Code	Description
200	Created
400	Bad Request

Error Codes

For details, see [Error Codes](#).

6.2.4 Pausing a Migration Task

Function

This API is used to stop a migration task that is in the **Migrating** state.

Calling Method

For details, see [Calling APIs](#).

URI

POST /v2/{project_id}/tasks/{task_id}/stop

Table 6-48 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Parameter	Mandatory	Type	Description
task_id	Yes	String	The migration task ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-49 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 400

Table 6-50 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 403

Table 6-51 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example pauses the task **191297407830872** in the project **2c0689c860ad4728a497c91ec0844383**.

POST https://[endpoint]/v2/2c0689c860ad4728a497c91ec0844383/tasks/191297407830872

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.2.5 Starting a Migration Task

Function

This API is used to start a migration task when the migration task is paused or failed.

Calling Method

For details, see [Calling APIs](#).

URI

POST /v2/{project_id}/tasks/{task_id}/start

Table 6-52 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
task_id	Yes	String	The migration task ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-53 Request header parameter

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-54 Request body parameters

Parameter	Mandatory	Type	Description
src_ak	No	String	The AK for accessing the source node. Enter a maximum of 100 characters. This parameter is not required for URL list-based migration tasks. Minimum length: 1 character Maximum length: 100 characters
src_sk	No	String	The SK for accessing the source node. Enter a maximum of 100 characters. This parameter is not required for URL list-based migration tasks. Minimum length: 1 character Maximum length: 100 characters
json_auth_file	No	String	The file used for Google Cloud Storage authentication. Minimum length: 0 characters Maximum length: 65,535 characters
src_security_token	No	String	The temporary token for accessing the source node. Minimum length: 0 characters Maximum length: 16,384 characters

Parameter	Mandatory	Type	Description
dst_ak	Yes	String	The AK for accessing the destination node. Minimum length: 1 character Maximum length: 100 characters
dst_sk	Yes	String	The SK for accessing the destination node. Minimum length: 1 character Maximum length: 100 characters
dst_security_token	No	String	The temporary token for accessing the destination node. Minimum length: 0 characters Maximum length: 16,384 characters
source_cdn_authentication_key	No	String	The CDN authentication key. Minimum length: 0 characters Maximum length: 255 characters
migrate_failed_object	No	Boolean	Indicates whether to migrate all objects in the migration task. The default value is false (full migration). If the value is true , only failed objects will be migrated again. If the value is blank or false , all objects in the migration task will be migrated again. Default value: false

Response

Status code: 400

Table 6-55 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

- This example starts a suspended non-URL list migration task using the AK/SK pairs of the source and destination accounts.

```
POST https://[endpoint]/v2/{project_id}/tasks/{task_id}/start
```

```
{  
    "src_ak": "src_ak",  
    "src_sk": "src_sk",  
    "dst_ak": "dst_ak",  
    "dst_sk": "dst_sk",  
    "migrate_failed_object": false  
}
```

- This example starts a suspended URL list migration task using the AK/SK pair of the destination account.

```
POST https://[endpoint]/v2/{project_id}/tasks/{task_id}/start
```

```
{  
    "dst_ak": "dst_ak",  
    "dst_sk": "dst_sk",  
    "migrate_failed_object": false  
}
```

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request

Error Codes

For details, see [Error Codes](#).

6.2.6 Deleting a Migration Task

Function

This API is used to delete a migration task. In-progress tasks cannot be deleted. If you try to delete an in-progress task, the system will return a message indicating the deletion fails. To delete such a task, pause the task first.

Calling Method

For details, see [Calling APIs](#).

URI

```
DELETE /v2/{project_id}/tasks/{task_id}
```

Table 6-56 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
task_id	Yes	String	The migration task ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-57 Request header parameter

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 400

Table 6-58 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 403

Table 6-59 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.

Parameter	Type	Description
error_code	String	The error code.

Example Request

This example deletes the task **191297407830872** in the project **2c0689c860ad4728a497c91ec0844383**.

```
DELETE https://{endpoint}/v2/2c0689c860ad4728a497c91ec0844383/tasks/191297407830872
```

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.2.7 Updating the Traffic Limiting Rules of a Migration Task

Function

This API is used to update the traffic limiting rules for a migration task before it is completed.

Calling Method

For details, see [Calling APIs](#).

URI

```
PUT /v2/{project_id}/tasks/{task_id}/bandwidth-policy
```

Table 6-60 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
task_id	Yes	String	The task ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-61 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-62 Request body parameters

Parameter	Mandatory	Type	Description
bandwidth_policy	Yes	Array of BandwidthPolicyDto objects	The traffic limiting rules. Each element in the array corresponds to the maximum bandwidth in a time period. A maximum of five periods are allowed, and the periods cannot overlap. Array length: 0 to 5

Table 6-63 [BandwidthPolicyDto](#) field description

Parameter	Mandatory	Type	Description
end	Yes	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Parameter	Mandatory	Type	Description
max_bandwidth	Yes	Long	The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s). Minimum value: 1048576 Maximum value: 209715200
start	Yes	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Response

Status code: 400

Table 6-64 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example sets the migration rate limit for the task whose ID is xxxxxxxx during the time period from 00:01 to 23:59 to 50 MB/s.

```
/v2/{project_id}/tasks/xxxxxxxx/bandwidth-policy
{
  "bandwidth_policy" : [ {
    "start" : "00:01",
    "end" : "23:59",
    "max_bandwidth" : 50000000
  } ]
}
```

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request

Error Codes

For details, see [Error Codes](#).

6.2.8 Updating Tasks in Batches

Function

This API is used to update migration tasks in batches. You can update all migration tasks in a migration task group or update migration tasks with specified IDs.

Calling Method

For details, see [Calling APIs](#).

URI

POST /v2/{project_id}/tasks/batch-update

Table 6-65 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-66 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The IAM token authentication. Ensure that the project ID contained in the token matches the project ID in the request URI. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-67 Request body parameters

Parameter	Mandatory	Type	Description
group_id	No	String	The ID of the migration task group. All tasks in the task group will be updated. Either group_id or ids must be specified. Minimum length: 1 character Maximum length: 36 characters
ids	No	Array of longs	The migration task ID array, including IDs of all tasks to be updated in batches. Either group_id or ids must be specified. Minimum value: 0 Maximum value: 9223372036854775807 Array length: 0 to 20
bandwidth_policy	Yes	Array of BandwidthPolicyDto objects	The traffic limiting rules. Each element in the array corresponds to the maximum bandwidth in a time period. A maximum of five periods are allowed, and the periods cannot overlap. Array length: 0 to 5

Parameter	Mandatory	Type	Description
task_priority	No	String	<p>The task priority. There are three priority levels: high, medium, and low. This parameter takes effects only for tasks in waiting, paused, and failed statuses.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • HIGH • MEDIUM • LOW

Table 6-68 BandwidthPolicyDto field description

Parameter	Mandatory	Type	Description
end	Yes	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.
max_bandwidth	Yes	Long	<p>The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s).</p> <p>Minimum value: 1048576</p> <p>Maximum value: 209715200</p>
start	Yes	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Response

Status code: 400

Table 6-69 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

- This example updates the traffic limiting rules for tasks in the task group with ID **xxxxxxxx** by setting **start** to **00:01**, **end** to **23:59**, and **max_bandwidth** to **50000000**.

```
/v2/{project_id}/tasks/batch-update
{
  "group_id": "xxxxxxxx",
  "bandwidth_policy": [ {
    "start": "00:01",
    "end": "23:59",
    "max_bandwidth": 50000000
  } ]
}
```

- This example updates the traffic limiting rules for tasks with IDs **111** and **222** by setting **start** to **00:01**, **end** to **23:59**, and **max_bandwidth** to **50000000**.

```
/v2/{project_id}/tasks/batch-update
{
  "ids": [ 111, 222 ],
  "bandwidth_policy": [ {
    "start": "00:01",
    "end": "23:59",
    "max_bandwidth": 50000000
  } ]
}
```

Example Response

None

Status Codes

Status Code	Description
200	OK. Batch update succeeded.
400	Bad request. Invalid parameters.

Error Codes

For details, see [Error Codes](#).

6.3 Migration Task Group Management

6.3.1 Listing Migration Task Groups

Function

This API is used to list all migration task groups in an account.

Calling Method

For details, see [Calling APIs](#).

URI

GET /v2/{project_id}/taskgroups

Table 6-70 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Table 6-71 Query parameters

Parameter	Mandatory	Type	Description
limit	No	Integer	The maximum number of migration task groups displayed on one page. A maximum of 100 migration task groups can be displayed. Minimum value: 1 Maximum value: 100 Default value: 10
offset	No	Integer	The start serial number of migration task groups. The value must be greater than or equal to 0. If offset is set to 0, the query starts from the first record. Minimum value: 0 Maximum value: 2147483647 Default value: 0

Parameter	Mandatory	Type	Description
status	No	Integer	<p>The status of the migration task group. If this parameter is not specified, task groups in all states are queried. 0: Waiting, 1: Executing/Creating, 2: Monitoring, 3: Paused, 4: Creation failed, 5: Migration failed, 6: Migration completed, 7: Pausing, 8: Waiting for deletion, 9: Deleted</p> <p>Minimum value: 0</p> <p>Maximum value: 9</p>

Request

Table 6-72 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	<p>The token used for IAM authentication.</p> <p>Minimum length: 1 character</p> <p>Maximum length: 16,384 characters</p>

Response

Status code: 200

Table 6-73 Response body parameters

Parameter	Type	Description
count	Long	<p>The total number of the migration task groups that meet the search criteria.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
taskgroups	Array of TaskGroupRe sp objects	The details of queried migration task groups. Array length: 0 to 100

Table 6-74 TaskGroupResp field description

Parameter	Type	Description
group_id	String	The task group ID. Minimum length: 1 character Maximum length: 100 characters
status	Integer	The migration task group status. 0 : Waiting, 1 : Executing/Creating, 2 : Monitoring, 3 : Paused, 4 : Creation failed, 5 : Migration failed, 6 : Migration completed, 7 : Pausing, 8 : Waiting for deletion, 9 : Deleted Minimum value: 0 Maximum value: 9
error_reason	ErrorReasonResp object	The task group failure cause. The value is an empty string if the task is not in the Migration failed state.
src_node	TaskGroupSrcNodeResp object	The source information.
description	String	The task group description, which cannot exceed 255 characters. The following special characters are not allowed: ^<>&"" Minimum length: 0 characters Maximum length: 255 characters
dst_node	TaskGroupDstNodeResp object	The destination information.
enable_metadata_migration	Boolean	Indicates whether metadata migration is enabled. The default value is false . Even if this function is disabled, the ContentType metadata will still be migrated to ensure a successful migration. Default value: false
enable_failed_object_recording	Boolean	Indicates whether to record the objects that failed to be migrated.

Parameter	Type	Description
enable_restore	Boolean	Indicates whether to restore archive data in the source bucket. It takes a long time to restore archive data in the source bucket, which will greatly slow down the migration speed. You are advised to restore the archive objects before the migration. After this function is enabled, archive objects will be automatically restored and then migrated. By default, this function is disabled, archive objects will be ignored during the migration, and the information about these objects will be recorded in the list of failed objects.
enable_kms	Boolean	Indicates whether to use KMS to encrypt the data to be stored in the destination OBS bucket.
task_type	String	<p>The task type. The default value is PREFIX. LIST indicates that the system will migrate the objects specified in the object list. URL_LIST indicates that the system will migrate the objects specified in the URL list. PREFIX indicates that the system will migrate the objects with a specific prefix.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • LIST • URL_LIST • PREFIX
bandwidth_policy	Array of BandwidthPolicyDto objects	The traffic limiting rules. Each element in the array corresponds to the maximum bandwidth in a time period. A maximum of five periods are allowed, and the periods cannot overlap. Array length: 0 to 5
smn_config	SmnInfo object	The SMN message sending configuration.
source_cdn	SourceCdnResponse object	Indicates whether migration from CDN is enabled. If this field is contained, migration from CDN is supported. Otherwise, it is not supported. If migration from CDN is enabled, the source objects to be migrated are obtained from the specified CDN domain name during migration.

Parameter	Type	Description
migrate_since	Long	<p>The specified migration time (timestamp, in milliseconds). Only source objects that are modified after the specified time will be migrated. Default value 0 indicates that no time is specified.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p> <p>Default value: 0</p>
migrate_speed	Long	<p>The migration speed (byte/s).</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
total_time	Long	<p>The total amount of time used by the migration task group, in ms.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
start_time	Long	<p>The start time (Unix timestamp, in millisecond) of the migration task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
total_task_num	Long	<p>The total number of migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
create_task_num	Long	<p>The number of created migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
failed_task_num	Long	<p>The number of failed migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
complete_task_num	Long	<p>The number of completed migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
paused_task_num	Long	<p>The number of paused migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>

Parameter	Type	Description
executing_task_num	Long	The number of executing migration tasks in the task group. Minimum value: 0 Maximum value: 9223372036854775807
waiting_task_num	Long	The number of waiting migration tasks in the task group. Minimum value: 0 Maximum value: 9223372036854775807
total_num	Long	The total number of objects to be migrated in the migration task group. Minimum value: 0 Maximum value: 9223372036854775807
create_complete_num	Long	The total number of objects contained in created migration tasks. Minimum value: 0 Maximum value: 9223372036854775807
success_num	Long	The number of migrated objects. Minimum value: 0 Maximum value: 9223372036854775807
fail_num	Long	The number of failed objects. Minimum value: 0 Maximum value: 9223372036854775807
skip_num	Long	The number of skipped objects. Minimum value: 0 Maximum value: 9223372036854775807
total_size	Long	The size (in bytes) of the objects that have been migrated. Minimum value: 0 Maximum value: 9223372036854775807
create_complete_size	Long	The total size (in bytes) of objects migrated in created migration tasks. Minimum value: 0 Maximum value: 9223372036854775807
complete_size	Long	The total size of migrated objects, in bytes. Minimum value: 0 Maximum value: 9223372036854775807

Parameter	Type	Description
failed_object_record	FailedObjectRecordDto object	The record of failed objects.
object_overwrite_mode	String	<p>Indicates whether to skip a source object or allow the source object to overwrite its paired destination object. The default value is SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE. NO_OVERWRITE indicates the system never allows overwrite. The system always skips source objects and keeps their paired destination objects.</p> <p>SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE indicates the system allows overwrite based on the results of size or modification time checks. It is the default setting. If a source object is not as large as or was last modified more recently than its paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped.</p> <p>CRC64_COMPARISON_OVERWRITE indicates the system allows overwrite if the source and destination objects have different CRC64 checksums. This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object has a CRC64 checksum different from the paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped. If one of them does not have a CRC64 checksum, their sizes and last modification times are checked.</p> <p>FULL_OVERWRITE indicates the system always allows overwrite. The system always allows source objects to overwrite their paired destination objects.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • NO_OVERWRITE • SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE • CRC64_COMPARISON_OVERWRITE • FULL_OVERWRITE

Parameter	Type	Description
dst_storage_policy	String	<p>The destination storage class. STANDARD indicates the Huawei Cloud OBS Standard. IA indicates the Huawei Cloud OBS Infrequent Access. ARCHIVE indicates the Huawei Cloud OBS Archive. DEEP_ARCHIVE indicates the Huawei Cloud OBS Deep Archive.</p> <p>SRC_STORAGE_MAPPING converts the source storage class into an OBS storage class based on the predefined rules.</p> <p>Default value: STANDARD</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 128 characters</p> <p>The value can be:</p> <ul style="list-style-type: none">• STANDARD• IA• ARCHIVE• DEEP_ARCHIVE• SRC_STORAGE_MAPPING

Parameter	Type	Description
consistency_check	String	<p>The consistency check method, which is used to check whether objects are consistent before and after migration. The selected check method and results will be recorded in the object list. The default value is size_last_modified. size_last_modified is the default setting. The system checks object consistency with object size and last modification time. If a source object is as large as but was last modified earlier than its paired destination object, the system considers the source object does not need to be migrated or has been already migrated successfully. crc64 is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object and its paired destination object have CRC64 checksums, the checksums are checked. Otherwise, their sizes and last modification times are checked. no_check is only available for migration of HTTP/HTTPS data. This option takes effect for source objects whose sizes cannot be obtained using the content-length field in the standard HTTP protocol. These source objects will overwrite their paired destination objects directly. If the size of a source object can be obtained from the Content-Length field in the standard HTTP protocol, its size and last modification time will be checked.</p> <p>The value can be:</p> <ul style="list-style-type: none">• size_last_modified• crc64• no_check
enable_requester_pays	Boolean	Indicates whether to let the requester make payment. After this function is enabled, the requester pays for the request and data transmission.

Table 6-75 ErrorReasonResp field description

Parameter	Type	Description
error_code	String	The error code returned for a migration failure. Minimum length: 0 characters Maximum length: 10 characters

Parameter	Type	Description
error_msg	String	The migration failure cause. Minimum length: 0 characters Maximum length: 1,024 characters

Table 6-76 TaskGroupSrcNodeResp field description

Parameter	Type	Description
bucket	String	The name of the source bucket. Minimum length: 0 characters Maximum length: 1,024 characters
cloud_type	String	<p>The source cloud service provider. The value can be AWS, AZURE, ALIYUN, TENCENT, HUAWEICLOUD, QINGCLOUD, KINGSOFTCLOUD, BAIDU, QINIU, GOOGLE, URLSOURCE, or UCLOUD. The default value is ALIYUN.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • AWS • AZURE • ALIYUN • TENCENT • HUAWEICLOUD • QINGCLOUD • KINGSOFTCLOUD • BAIDU • QINIU • URLSOURCE • UCLOUD • GOOGLE
region	String	The region where the source bucket is located. Minimum length: 0 characters Maximum length: 100 characters
app_id	String	This parameter is returned when cloud_type is Tencent . Minimum length: 0 characters Maximum length: 255 characters

Parameter	Type	Description
object_key	Array of strings	The name prefixes of objects to be migrated if task_type is set to prefix . Minimum length: 0 characters Maximum length: 1,024 characters Array length: 0 to 500
list_file	ListFile object	The list file configuration. list_file is mandatory when task_type is set to list or url_list .

Table 6-77 ListFile field description

Parameter	Type	Description
list_file_key	String	The object names in the object list file or URL list file. Minimum length: 1 character Maximum length: 1,024 characters
obs_bucket	String	The name of the OBS bucket for storing the object list files. Ensure that the OBS bucket is in the same region as the destination bucket, or the task will fail to be created. Minimum length: 0 characters Maximum length: 1,024 characters
list_file_num	String	The number of stored object list files. Minimum length: 0 characters Maximum length: 65,535 characters

Table 6-78 TaskGroupDstNodeResp field description

Parameter	Type	Description
bucket	String	The name of the destination bucket. Minimum length: 0 characters Maximum length: 1,024 characters
region	String	The region where the destination bucket is located. Minimum length: 0 characters Maximum length: 100 characters

Parameter	Type	Description
save_prefix	String	<p>The path prefix in the destination bucket. The prefix is added before an object key to form a new key. The length of the new key cannot exceed 1,024 characters.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 1,024 characters</p>

Table 6-79 BandwidthPolicyDto field description

Parameter	Type	Description
end	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.
max_bandwidth	Long	<p>The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s).</p> <p>Minimum value: 1048576</p> <p>Maximum value: 209715200</p>
start	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Table 6-80 SmnInfo field description

Parameter	Type	Description
notify_result	Boolean	Indicates whether the SMN messages are sent successfully after migration tasks are complete.
notify_error_message	String	<p>The error codes that record why the SMN messages failed to be sent. The value is empty if migration tasks are successful.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 1,024 characters</p>
topic_name	String	<p>The SMN topic name. The value is empty if SMN messages are sent successfully.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 5,120 characters</p>

Table 6-81 SourceCdnResp field description

Parameter	Type	Description
domain	String	The domain name from which to obtain objects to be migrated. Minimum length: 0 characters Maximum length: 1,024 characters
protocol	String	The protocol type. The value can be: <ul style="list-style-type: none">• HTTP• HTTPS
authentication_type	String	The authentication type. The value can be: <ul style="list-style-type: none">• NONE• QINIU_PRIVATE_AUTHENTICATION• ALIYUN_OSS_A• ALIYUN_OSS_B• ALIYUN_OSS_C• KSYUN_PRIVATE_AUTHENTICATION• AZURE_SAS_TOKEN• TENCENT_COS_A• TENCENT_COS_B• TENCENT_COS_C• TENCENT_COS_D

Table 6-82 FailedObjectRecordDto field description

Parameter	Type	Description
result	Boolean	Indicates whether to retransmit failed objects.
list_file_key	String	The path for storing the list of failed objects. Minimum length: 0 characters Maximum length: 1,024 characters
error_code	String	The error code returned when the list of failed objects fails to be uploaded. Minimum length: 0 characters Maximum length: 10 characters

Status code: 400

Table 6-83 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 403

Table 6-84 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 500

Table 6-85 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries 10 migration task groups in project f4e146cac1de45669c3fed73dc3b9c6f.

Get <https://{{endpoint}}/v2/f4e146cac1de45669c3fed73dc3b9c6f/taskgroups?offset=0&limit=10>

Example Response

Status code: 200

OK

```
{  
    "count": 353,  
    "taskgroups": [ {  
        "group_id": "9dd98a5e-7ea3-4d80-abff-4c23914313e4",  
        "status": 6,  
        "error_reason": null,  
        "src_node": {  
            "bucket": "api-auto-test",  
            "cloud_type": "TENCENT",  
            "region": "ap-beijing",  
            "app_id": "1254563210",  
            "object_key": [ "test" ]  
        }  
    } ]  
}
```

```
        "list_file" : null
    },
    "description" : "",
    "dst_node" : {
        "bucket" : "test-l30022277",
        "region" : "cn-north-7",
        "save_prefix" : ""
    },
    "enable_metadata_migration" : false,
    "enable_failed_object_recording" : true,
    "enable_restore" : false,
    "enable_kms" : false,
    "task_type" : "PREFIX",
    "bandwidth_policy" : [ ],
    "smn_config" : null,
    "source_cdn" : null,
    "migrate_since" : 0,
    "migrate_speed" : 0,
    "total_time" : 973657,
    "start_time" : 1663654062461,
    "total_task_num" : null,
    "create_task_num" : null,
    "failed_task_num" : null,
    "complete_task_num" : null,
    "paused_task_num" : null,
    "executing_task_num" : null,
    "waiting_task_num" : null,
    "total_num" : 6,
    "create_complete_num" : null,
    "success_num" : 6,
    "fail_num" : 0,
    "skip_num" : 0,
    "total_size" : 2469022100,
    "create_complete_size" : null,
    "complete_size" : 2469022100,
    "failed_object_record" : {
        "result" : null,
        "list_file_key" : null,
        "error_code" : null
    },
    "object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
    "consistency_check" : "size_last_modified",
    "enable_requester_pays" : false
}, {
    "group_id" : "2597fc69-af30-4411-b59d-b37857b69792",
    "status" : 6,
    "error_reason" : null,
    "src_node" : {
        "bucket" : "test-retry",
        "cloud_type" : "HUAWEICLOUD",
        "region" : "cn-north-7",
        "app_id" : "",
        "object_key" : [ "%21" ],
        "list_file" : null
    },
    "description" : "",
    "dst_node" : {
        "bucket" : "assess-bucket-1",
        "region" : "cn-north-7",
        "save_prefix" : ""
    },
    "enable_metadata_migration" : false,
    "enable_failed_object_recording" : true,
    "enable_restore" : false,
    "enable_kms" : false,
    "task_type" : "PREFIX",
    "bandwidth_policy" : [ ],
    "smn_config" : null,
    "source_cdn" : null,
```

```
"migrate_since" : 0,
"migrate_speed" : 0,
"total_time" : 43440,
"start_time" : 1663340552910,
"total_task_num" : null,
"create_task_num" : null,
"failed_task_num" : null,
"complete_task_num" : null,
"paused_task_num" : null,
"executing_task_num" : null,
"waiting_task_num" : null,
"total_num" : 1,
"create_complete_num" : null,
"success_num" : 0,
"fail_num" : 0,
"skip_num" : 1,
"total_size" : 1205,
"create_complete_size" : null,
"complete_size" : 1205,
"failed_object_record" : {
    "result" : null,
    "list_file_key" : null,
    "error_code" : null
},
"object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
"consistency_check" : "size_last_modified",
"enable_requester_pays" : false
}, {
"group_id" : "d85ed5a8-61a1-492f-a146-2fd092dc37cf",
"status" : 5,
"error_reason" : null,
"src_node" : {
    "bucket" : "assess-bucket-1",
    "cloud_type" : "HUAWEICLOUD",
    "region" : "cn-north-7",
    "app_id" : "",
    "object_key" : [ "" ],
    "list_file" : null
},
"description" : "",
"dst_node" : {
    "bucket" : "assess-bucket-1",
    "region" : "cn-north-7",
    "save_prefix" : ""
},
"enable_metadata_migration" : false,
"enable_failed_object_recording" : true,
"enable_restore" : false,
"enable_kms" : false,
"task_type" : "PREFIX",
"bandwidth_policy" : [ ],
"smn_config" : null,
"source_cdn" : null,
"migrate_since" : 0,
"migrate_speed" : 0,
"total_time" : 4047612,
"start_time" : 1663070894867,
"total_task_num" : null,
"create_task_num" : null,
"failed_task_num" : null,
"complete_task_num" : null,
"paused_task_num" : null,
"executing_task_num" : null,
"waiting_task_num" : null,
"total_num" : 99020,
"create_complete_num" : null,
"success_num" : 0,
"fail_num" : 99020,
"skip_num" : 0,
```

```
"total_size" : 954329692,
"create_complete_size" : null,
"complete_size" : 954329692,
"failed_object_record" : {
    "result" : true,
    "list_file_key" : "oms/task_group/d85ed5a8-61a1-492f-a146-2fd092dc37cf/failed_object_lists/",
    "error_code" : null
},
"object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
"consistency_check" : "size_last_modified",
"enable_requester_pays" : false
}, {
"group_id" : "2a84320a-eddb-4413-9b12-a0251aae0f3e",
"status" : 6,
"error_reason" : null,
"src_node" : {
    "bucket" : "api-test",
    "cloud_type" : "UCLOUD",
    "region" : "cn-bj",
    "app_id" : "",
    "object_key" : [ "test" ],
    "list_file" : null
},
"description" : "",
"dst_node" : {
    "bucket" : "test-l30022277",
    "region" : "cn-north-7",
    "save_prefix" : ""
},
"enable_metadata_migration" : false,
"enable_failed_object_recording" : true,
"enable_restore" : false,
"enable_kms" : false,
"task_type" : "PREFIX",
"bandwidth_policy" : [ ],
"smn_config" : null,
"source_cdn" : null,
"migrate_since" : 0,
"migrate_speed" : 0,
"total_time" : 63228,
"start_time" : 1662725286648,
"total_task_num" : null,
"create_task_num" : null,
"failed_task_num" : null,
"complete_task_num" : null,
"paused_task_num" : null,
"executing_task_num" : null,
"waiting_task_num" : null,
"total_num" : 6,
"create_complete_num" : null,
"success_num" : 5,
"fail_num" : 0,
"skip_num" : 1,
"total_size" : 0,
"create_complete_size" : null,
"complete_size" : 0,
"failed_object_record" : {
    "result" : null,
    "list_file_key" : null,
    "error_code" : null
},
"object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
"consistency_check" : "size_last_modified",
"enable_requester_pays" : false
}, {
"group_id" : "64bca3b2-6ccc-4ca4-8394-17d3c7bdf871",
"status" : 6,
"error_reason" : null,
"src_node" : {
```

```
"bucket" : "api-auto-test",
"cloud_type" : "TENCENT",
"region" : "ap-beijing",
"app_id" : "1254563210",
"object_key" : [ "test" ],
"list_file" : null
},
"description" : "",
"dst_node" : {
"bucket" : "test-l30022277",
"region" : "cn-north-7",
"save_prefix" : ""
},
"enable_metadata_migration" : false,
"enable_failed_object_recording" : true,
"enable_restore" : false,
"enable_kms" : false,
"task_type" : "PREFIX",
"bandwidth_policy" : [ ],
"smn_config" : null,
"source_cdn" : null,
"migrate_since" : 0,
"migrate_speed" : 0,
"total_time" : 553999,
"start_time" : 1662725057215,
"total_task_num" : null,
"create_task_num" : null,
"failed_task_num" : null,
"complete_task_num" : null,
"paused_task_num" : null,
"executing_task_num" : null,
"waiting_task_num" : null,
"total_num" : 6,
"create_complete_num" : null,
"success_num" : 6,
"fail_num" : 0,
"skip_num" : 0,
"total_size" : 2469022100,
"create_complete_size" : null,
"complete_size" : 2469022100,
"failed_object_record" : {
"result" : null,
"list_file_key" : null,
"error_code" : null
},
"object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
"consistency_check" : "size_last_modified",
"enable_requester_pays" : false
}, {
"group_id" : "4c019e94-9ac1-4cd6-b404-982816b20c2f",
"status" : 6,
"error_reason" : null,
"src_node" : {
"bucket" : "api-auto-hangzhou",
"cloud_type" : "ALIYUN",
"region" : "cn-hangzhou",
"app_id" : "",
"object_key" : [ "test" ],
"list_file" : null
},
"description" : "",
"dst_node" : {
"bucket" : "test-l30022277",
"region" : "cn-north-7",
"save_prefix" : ""
},
"enable_metadata_migration" : false,
"enable_failed_object_recording" : true,
"enable_restore" : false,
```

```
"enable_kms" : false,
"task_type" : "PREFIX",
"bandwidth_policy" : [ ],
"smn_config" : null,
"source_cdn" : null,
"migrate_since" : 0,
"migrate_speed" : 0,
"total_time" : 33279,
"start_time" : 1662723650469,
"total_task_num" : null,
"create_task_num" : null,
"failed_task_num" : null,
"complete_task_num" : null,
"paused_task_num" : null,
"executing_task_num" : null,
"waiting_task_num" : null,
"total_num" : 3,
"create_complete_num" : null,
"success_num" : 3,
"fail_num" : 0,
"skip_num" : 0,
"total_size" : 31840,
"create_complete_size" : null,
"complete_size" : 31840,
"failed_object_record" : {
    "result" : null,
    "list_file_key" : null,
    "error_code" : null
},
"object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
"consistency_check" : "size_last_modified",
"enable_requester_pays" : false
}, {
    "group_id" : "5f5dd578-a3a6-4324-ad64-647a38ffb395",
    "status" : 6,
    "error_reason" : null,
    "src_node" : {
        "bucket" : "api-auto-test",
        "cloud_type" : "BAIDU",
        "region" : "bj",
        "app_id" : "",
        "object_key" : [ "test" ],
        "list_file" : null
    },
    "description" : "",
    "dst_node" : {
        "bucket" : "assess-bucket-1",
        "region" : "cn-north-7",
        "save_prefix" : ""
    },
    "enable_metadata_migration" : false,
    "enable_failed_object_recording" : true,
    "enable_restore" : false,
    "enable_kms" : false,
    "task_type" : "PREFIX",
    "bandwidth_policy" : [ ],
    "smn_config" : null,
    "source_cdn" : null,
    "migrate_since" : 0,
    "migrate_speed" : 0,
    "total_time" : 53427,
    "start_time" : 1662722500472,
    "total_task_num" : null,
    "create_task_num" : null,
    "failed_task_num" : null,
    "complete_task_num" : null,
    "paused_task_num" : null,
    "executing_task_num" : null,
    "waiting_task_num" : null,
```

```
"total_num" : 15,
"create_complete_num" : null,
"success_num" : 15,
"fail_num" : 0,
"skip_num" : 0,
"total_size" : 94864941,
"create_complete_size" : null,
"complete_size" : 94864941,
"failed_object_record" : {
    "result" : null,
    "list_file_key" : null,
    "error_code" : null
},
"object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
"consistency_check" : "size_last_modified",
"enable_requester_pays" : false
}, {
"group_id" : "912e951b-ae19-4f65-bb94-c889601d8a43",
"status" : 6,
"error_reason" : null,
"src_node" : {
    "bucket" : "assess-bucket-1",
    "cloud_type" : "HUAWEICLOUD",
    "region" : "cn-north-7",
    "app_id" : "",
    "object_key" : [ "" ],
    "list_file" : null
},
"description" : "",
"dst_node" : {
    "bucket" : "oms-onebox-lqm",
    "region" : "cn-north-7",
    "save_prefix" : ""
},
"enable_metadata_migration" : false,
"enable_failed_object_recording" : true,
"enable_restore" : false,
"enable_kms" : false,
"task_type" : "PREFIX",
"bandwidth_policy" : [ ],
"smn_config" : null,
"source_cdn" : null,
"migrate_since" : 0,
"migrate_speed" : 0,
"total_time" : 590588,
"start_time" : 1662640213374,
"total_task_num" : null,
"create_task_num" : null,
"failed_task_num" : null,
"complete_task_num" : null,
"paused_task_num" : null,
"executing_task_num" : null,
"waiting_task_num" : null,
"total_num" : 99052,
"create_complete_num" : null,
"success_num" : 99052,
"fail_num" : 0,
"skip_num" : 0,
"total_size" : 1847919442,
"create_complete_size" : null,
"complete_size" : 1847919442,
"failed_object_record" : {
    "result" : null,
    "list_file_key" : null,
    "error_code" : null
},
"object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
"consistency_check" : "size_last_modified",
"enable_requester_pays" : false
```

```
}, {
    "group_id" : "398b5845-b180-47a1-a7c9-56f051ed3f34",
    "status" : 5,
    "error_reason" : null,
    "src_node" : {
        "bucket" : "hw-src",
        "cloud_type" : "HUAWEICLOUD",
        "region" : "cn-north-7",
        "app_id" : "",
        "object_key" : [ "gd.jpg" ],
        "list_file" : null
    },
    "description" : "",
    "dst_node" : {
        "bucket" : "zzww",
        "region" : "cn-north-7",
        "save_prefix" : ""
    },
    "enable_metadata_migration" : false,
    "enable_failed_object_recording" : true,
    "enable_restore" : false,
    "enable_kms" : false,
    "task_type" : "PREFIX",
    "bandwidth_policy" : [ ],
    "smn_config" : null,
    "source_cdn" : null,
    "migrate_since" : 0,
    "migrate_speed" : 0,
    "total_time" : 709891300,
    "start_time" : 1662369530210,
    "total_task_num" : null,
    "create_task_num" : null,
    "failed_task_num" : null,
    "complete_task_num" : null,
    "paused_task_num" : null,
    "executing_task_num" : null,
    "waiting_task_num" : null,
    "total_num" : 1,
    "create_complete_num" : null,
    "success_num" : 0,
    "fail_num" : 1,
    "skip_num" : 0,
    "total_size" : 3528,
    "create_complete_size" : null,
    "complete_size" : 0,
    "failed_object_record" : {
        "result" : true,
        "list_file_key" : "oms/task_group/398b5845-b180-47a1-a7c9-56f051ed3f34/failed_object_lists/",
        "error_code" : null
    },
    "object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
    "consistency_check" : "size_last_modified",
    "enable_requester_pays" : false
}, {
    "group_id" : "494cad85-cbe5-4d62-8e70-e4f0e847e39c",
    "status" : 6,
    "error_reason" : null,
    "src_node" : {
        "bucket" : "test-l30022277-src",
        "cloud_type" : "HUAWEICLOUD",
        "region" : "cn-north-7",
        "app_id" : "",
        "object_key" : [ "test" ],
        "list_file" : null
    },
    "description" : "",
    "dst_node" : {
        "bucket" : "test-l30022277",
        "region" : "cn-north-7",
    }
}
```

```
        "save_prefix" : "",
    },
    "enable_metadata_migration" : false,
    "enable_failed_object_recording" : true,
    "enable_restore" : false,
    "enable_kms" : false,
    "task_type" : "PREFIX",
    "bandwidth_policy" : [ ],
    "smn_config" : null,
    "source_cdn" : null,
    "migrate_since" : 0,
    "migrate_speed" : 0,
    "total_time" : 33513,
    "start_time" : 1661928705453,
    "total_task_num" : null,
    "create_task_num" : null,
    "failed_task_num" : null,
    "complete_task_num" : null,
    "paused_task_num" : null,
    "executing_task_num" : null,
    "waiting_task_num" : null,
    "total_num" : 2,
    "create_complete_num" : null,
    "success_num" : 0,
    "fail_num" : 0,
    "skip_num" : 2,
    "total_size" : 155,
    "create_complete_size" : null,
    "complete_size" : 155,
    "failed_object_record" : {
        "result" : null,
        "list_file_key" : null,
        "error_code" : null
    },
    "object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",
    "consistency_check" : "size_last_modified",
    "enable_requester_pays" : false
} ]
}
```

Status Codes

Status Code	Description
200	OK
400	Bad Request
403	Forbidden
500	Server Error

Error Codes

For details, see [Error Codes](#).

6.3.2 Creating a Migration Task Group

Function

This API is used to create a migration task group. After a migration task group is created, migration tasks are automatically created in the task group. You do not need to manually call APIs to create migration tasks.

Calling Method

For details, see [Calling APIs](#).

URI

POST /v2/{project_id}/taskgroups

Table 6-86 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-87 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-88 Request body parameters

Parameter	Mandatory	Type	Description
src_node	Yes	TaskGroupSrcNode object	The source information.

Parameter	Mandatory	Type	Description
description	No	String	The task group description, which cannot exceed 255 characters. The following special characters are not allowed: ^<>&'" Minimum length: 0 characters Maximum length: 255 characters
dst_node	Yes	TaskGroupDstNode object	The destination information.
enable_metadata_migration	No	Boolean	Indicates whether metadata migration is enabled. The default value is false . Even if this function is disabled, the ContentType metadata will still be migrated to ensure a successful migration. Default value: false
enable_failed_object_recording	No	Boolean	Indicates whether to record the objects that failed to be migrated. Default value: true
enable_restore	No	Boolean	Indicates whether archive data restoration is enabled. If this function is enabled, archive data is automatically restored and migrated.
enable_kms	Yes	Boolean	Indicates whether KMS encryption is enabled. This function is disabled by default. Default value: false

Parameter	Mandatory	Type	Description
task_type	No	String	<p>The task type. The default value is PREFIX. LIST indicates that the system will migrate the objects specified in the object list. URL_LIST indicates that the system will migrate the objects specified in the URL list. PREFIX indicates that the system will migrate the objects with a specific prefix.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • LIST • URL_LIST • PREFIX
bandwidth_policy	No	Array of BandwidthPolicyDto objects	<p>The traffic limiting rules. Each element in the array corresponds to the maximum bandwidth in a time period. A maximum of five periods are allowed, and the periods cannot overlap.</p> <p>Array length: 0 to 5</p>
smn_config	No	SmnConfig object	The SMN message sending configuration.
source_cdn	No	SourceCdnReq object	<p>Indicates whether migration from CDN is enabled. If this field is contained, migration from CDN is supported. Otherwise, it is not supported. If migration from CDN is enabled, the source objects to be migrated are obtained from the specified CDN domain name during migration.</p>
migrate_since	No	Long	<p>A timestamp in second. The system migrates only the objects that are modified after the specified time. No time is specified by default.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p> <p>Default value: 0</p>

Parameter	Mandatory	Type	Description
object_overwrite_mode	No	String	<p>Indicates whether to skip a source object or allow the source object to overwrite its paired destination object. The default value is SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE. NO_OVERWRITE indicates the system never allows overwrite. The system always skips source objects and keeps their paired destination objects.</p> <p>SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE indicates the system allows overwrite based on the results of size or modification time checks. It is the default setting. If a source object is not as large as or was last modified more recently than its paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped.</p> <p>CRC64_COMPARISON_OVERWRITE indicates the system allows overwrite if the source and destination objects have different CRC64 checksums. This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object has a CRC64 checksum different from the paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped. If one of them does not have a CRC64 checksum, their sizes and last modification times are checked.</p> <p>FULL_OVERWRITE indicates the system always allows overwrite. The system always allows source objects</p>

Parameter	Mandatory	Type	Description
			<p>to overwrite their paired destination objects.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • NO_OVERWRITE • SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE • CRC64_COMPARISON_OVERWRITE • FULL_OVERWRITE
dst_storage_policy	No	String	<p>The destination storage class. STANDARD indicates the Huawei Cloud OBS Standard. IA indicates the Huawei Cloud OBS Infrequent Access. ARCHIVE indicates the Huawei Cloud OBS Archive. DEEP_ARCHIVE indicates the Huawei Cloud OBS Deep Archive. SRC_STORAGE_MAPPING converts the source storage class into an OBS storage class based on the predefined rules.</p> <p>Default value: STANDARD</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 128 characters</p> <p>The value can be:</p> <ul style="list-style-type: none"> • STANDARD • IA • ARCHIVE • DEEP_ARCHIVE • SRC_STORAGE_MAPPING

Parameter	Mandatory	Type	Description
consistency_check	No	String	<p>The consistency check method, which is used to check whether objects are consistent before and after migration. The selected check method and results will be recorded in the object list. The default value is size_last_modified. size_last_modified is the default setting. The system checks object consistency with object size and last modification time. If a source object is as large as but was last modified earlier than its paired destination object, the system considers the source object does not need to be migrated or has been already migrated successfully. crc64 is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object and its paired destination object have CRC64 checksums, the checksums are checked. Otherwise, their sizes and last modification times are checked. no_check is only available for migration of HTTP/HTTPS data. This option takes effect for source objects whose sizes cannot be obtained using the content-length field in the standard HTTP protocol. These source objects will overwrite their paired destination objects directly. If the size of a source object can be obtained from the Content-Length field in the standard HTTP protocol, its size and last modification time will be checked.</p> <p>Default value: size_last_modified</p> <p>The value can be:</p> <ul style="list-style-type: none"> • size_last_modified • crc64

Parameter	Mandatory	Type	Description
			<ul style="list-style-type: none"> • no_check
enable_requester_pays	No	Boolean	<p>Indicates whether to let the requester make payment. After this function is enabled, the requester pays for the request and data transmission.</p> <p>Default value: false</p>

Table 6-89 TaskGroupSrcNode field description

Parameter	Mandatory	Type	Description
ak	No	String	<p>The AK for accessing the source bucket. This parameter is mandatory when task_type is not url_list.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 100 characters</p>
sk	No	String	<p>The SK for accessing the destination bucket. This parameter is mandatory when task_type is not url_list.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 100 characters</p>
json_auth_file	No	String	<p>The file used for Google Cloud Storage authentication.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 65,535 characters</p>
app_id	No	String	<p>This parameter is mandatory when cloud_type is Tencent.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 255 characters</p>

Parameter	Mandatory	Type	Description
region	No	String	The region where the source bucket is located. region is mandatory when task_type is not URL_LIST . Minimum length: 0 characters Maximum length: 100 characters
object_key	No	Array of strings	The name prefixes of objects to be migrated if task_type is set to prefix . If you want to migrate the entire bucket, set this parameter to [""]. Minimum length: 0 characters Maximum length: 1,024 characters Array length: 0 to 500
bucket	No	String	The source bucket. Minimum length: 0 characters Maximum length: 1,024 characters
cloud_type	No	String	The source cloud service provider. If task_type is URL_LIST , this parameter is mandatory and must be URLSource . The value can be AWS , Azure , Aliyun , Tencent , HuaweiCloud , QingCloud , KingsoftCloud , Baidu , Qiniu , URLSource , Google , or UCloud . The default value is Aliyun . Default value: Aliyun Minimum length: 0 characters Maximum length: 100 characters
list_file	No	ListFile object	The list file configuration. list_file is mandatory when task_type is set to LIST or URL_LIST .

Table 6-90 ListFile field description

Parameter	Mandatory	Type	Description
list_file_key	Yes	String	The object names in the object list file or URL list file. Minimum length: 1 character Maximum length: 1,024 characters
obs_bucket	Yes	String	The name of the OBS bucket for storing the object list files. Ensure that the OBS bucket is in the same region as the destination bucket, or the task will fail to be created. Minimum length: 0 characters Maximum length: 1,024 characters
list_file_num	No	String	The number of stored object list files. Minimum length: 0 characters Maximum length: 65,535 characters

Table 6-91 TaskGroupDstNode field description

Parameter	Mandatory	Type	Description
ak	Yes	String	The AK for accessing the destination bucket. Minimum length: 0 characters Maximum length: 100 characters
sk	Yes	String	The SK for accessing the destination bucket. Minimum length: 0 characters Maximum length: 100 characters

Parameter	Mandatory	Type	Description
region	Yes	String	The region where the destination bucket is located. The value must be the same as that of the service endpoint. Minimum length: 0 characters Maximum length: 100 characters
bucket	Yes	String	The destination bucket. Minimum length: 0 characters Maximum length: 1,024 characters
cloud_type	No	String	The destination cloud. Huawei Cloud is the destination by default. The default value is HEC . Default value: HEC Minimum length: 0 characters Maximum length: 100 characters
save_prefix	No	String	The path prefix in the destination bucket. The prefix is added before an object key to form a new key. The length of the new key cannot exceed 1,024 characters. Minimum length: 0 characters Maximum length: 1,024 characters

Table 6-92 BandwidthPolicyDto field description

Parameter	Mandatory	Type	Description
end	Yes	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Parameter	Mandatory	Type	Description
max_bandwidth	Yes	Long	The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s). Minimum value: 1048576 Maximum value: 209715200
start	Yes	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Table 6-93 SmnConfig field description

Parameter	Mandatory	Type	Description
language	No	String	The management console language chosen by you. The value can be zh-cn or en-us . Default value: en-us The value can be: <ul style="list-style-type: none">• zh-cn• en-us
topic_urn	Yes	String	The SMN message topic URN bound to a migration task. Minimum length: 0 characters Maximum length: 1,024 characters

Parameter	Mandatory	Type	Description
trigger_conditions	Yes	Array of strings	<p>The trigger conditions of sending messages using SMN. The message varies depending on the status of the migration task.</p> <p>The migration task state can be SUCCESS or FAILURE.</p> <ul style="list-style-type: none"> • FAILURE: indicates that an SMN message will be sent after the migration task fails. • SUCCESS: indicates that an SMN message will be sent after the migration task succeeds. <p>Array length: 1 to 2</p>
message_template_name	No	String	<p>If this parameter is specified, SMN messages are sent using the specified template.</p> <p>Template example:</p> <pre>{"Task_Status": "", "Task_Name": "", "Start_Time": "", "Total_Time_Used": "", "Transferred_Data": "", "Average_Speed": "", "Source_Bucket": "", "Destination_Bucket": "", "List_File_Bucket": "", "List_File_Key": "", "Success_object_list_path": "", "Skip_object_list_path": "", "Failed_object_list_path": "" }</pre>

Table 6-94 SourceCdnReq field description

Parameter	Mandatory	Type	Description
authentication_key	No	String	<p>The CDN authentication key. If the CDN authentication is required, this parameter is mandatory.</p> <p>If no authorization is required, do not set this parameter.</p> <p>Qiniu: You do not need to set this parameter. Aliyun: Set this parameter based on the value of authentication_type.</p> <p>KingsCloud: You do not need to set this parameter.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 255 characters</p>
authentication_type	Yes	String	<p>The authentication type.</p> <p>Default value: NONE</p> <p>The value can be:</p> <ul style="list-style-type: none"> • NONE • QINIU_PRIVATE_AUTHENTICATION • ALIYUN_OSS_A • ALIYUN_OSS_B • ALIYUN_OSS_C • KSYUN_PRIVATE_AUTHENTICATION • AZURE_SAS_TOKEN • TENCENT_COS_A • TENCENT_COS_B • TENCENT_COS_C • TENCENT_COS_D
domain	Yes	String	<p>The domain name from which to obtain objects to be migrated.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 1,024 characters</p>

Parameter	Mandatory	Type	Description
protocol	Yes	String	The protocol type. The value can be: <ul style="list-style-type: none">• HTTP• HTTPS

Response

Status code: 200

Table 6-95 Response body parameters

Parameter	Type	Description
group_id	String	The ID of the created migration task group. Minimum length: 1 character Maximum length: 100 characters

Status code: 400

Table 6-96 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 403

Table 6-97 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 500

Table 6-98 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

- This example creates a migration task group to migrate objects listed in TXT object list files stored in the **hw/** directory to the destination bucket **zzww**.

```
POST https://[endpoint]/v2/{project_id}/taskgroups
```

```
{
  "enable_failed_object_recording" : true,
  "src_node" : {
    "bucket" : "hw-src",
    "cloud_type" : "HuaweiCloud",
    "ak" : "*****",
    "sk" : "*****",
    "region" : "cn-north-7",
    "list_file" : {
      "obs_bucket" : "list-file-bucket",
      "list_file_key" : "hw/"
    }
  },
  "enable_kms" : false,
  "task_type" : "LIST",
  "enable_restore" : false,
  "dst_node" : {
    "bucket" : "zzww",
    "cloud_type" : "HEC",
    "ak" : "*****",
    "sk" : "*****",
    "region" : "cn-north-7"
  },
  "enable_metadata_migration" : true
}
```

- This example creates a migration task group to migrate objects prefixed with Objectlist from the source bucket **src-bucket** to the destination bucket **dst-bucket**.

```
POST https://[endpoint]/v2/{project_id}/taskgroups
```

```
{
  "src_node" : {
    "region" : "cn-north-4",
    "ak" : "*****",
    "sk" : "*****",
    "bucket" : "src-bucket",
    "cloud_type" : "HuaweiCloud",
    "object_key" : [ "Objectlist" ]
  },
  "dst_node" : {
    "region" : "cn-north-4",
    "ak" : "*****",
    "sk" : "*****",
    "bucket" : "dst-bucket"
  },
  "task_type" : "PREFIX",
  "enable_failed_object_recording" : true,
  "enable_kms" : false,
  "bandwidth_policy" : [ {
```

- ```
 "max_bandwidth" : 1048576,
 "start" : "00:01",
 "end" : "23:59"
 }
}

● This example creates a migration task group to migrate objects listed in the TXT URL list files stored in the test01/ directory to the destination bucket jjyy.
```
- POST [https://{{endpoint}}/v2/{{project\\_id}}/taskgroups](https://{{endpoint}}/v2/{{project_id}}/taskgroups)
- ```
{
  "src_node": {
    "cloud_type": "URLSource",
    "list_file": {
      "obs_bucket": "url-file-bucket",
      "list_file_key": "test01/"
    }
  },
  "description": "",
  "dst_node": {
    "region": "cn-north-4",
    "ak": "*****",
    "sk": "*****",
    "bucket": "jjyy",
    "cloud_type": "HEC"
  },
  "enable_failed_object_recording": true,
  "enable_restore": false,
  "enable_metadata_migration": false,
  "enable_kms": false,
  "task_type": "URL_LIST"
}
```

Example Response

Status code: 200

Created

```
{
  "group_id": "9ad15f51-778f-4684-b47b-4c5109c0e105"
}
```

Status Codes

Status Code	Description
200	Created
400	Bad Request
403	Forbidden
500	Server Error

Error Codes

For details, see [Error Codes](#).

6.3.3 Querying a Migration Task Group

Function

This API is used to query the information about a migration task group with a specified ID.

Calling Method

For details, see [Calling APIs](#).

URI

GET /v2/{project_id}/taskgroups/{group_id}

Table 6-99 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
group_id	Yes	String	The task group ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-100 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 200

Table 6-101 Response body parameters

Parameter	Type	Description
group_id	String	The task group ID. Minimum length: 1 character Maximum length: 100 characters
status	Integer	The migration task group status. 0 : Waiting, 1 : Executing/Creating, 2 : Monitoring, 3 : Paused, 4 : Creation failed, 5 : Migration failed, 6 : Migration completed, 7 : Pausing, 8 : Waiting for deletion, 9 : Deleted Minimum value: 0 Maximum value: 9
error_reason	ErrorReasonResp object	The task group failure cause. The value is an empty string if the task is not in the Migration failed state.
src_node	TaskGroupSrcNodeResp object	The source information.
description	String	The task group description, which cannot exceed 255 characters. The following special characters are not allowed: ^<>&"" Minimum length: 0 characters Maximum length: 255 characters
dst_node	TaskGroupDstNodeResp object	The destination information.
enable_metadata_migration	Boolean	Indicates whether metadata migration is enabled. The default value is false . Even if this function is disabled, the ContentType metadata will still be migrated to ensure a successful migration. Default value: false
enable_failed_object_recording	Boolean	Indicates whether to record the objects that failed to be migrated.

Parameter	Type	Description
enable_restore	Boolean	Indicates whether to restore archive data in the source bucket. It takes a long time to restore archive data in the source bucket, which will greatly slow down the migration speed. You are advised to restore the archive objects before the migration. After this function is enabled, archive objects will be automatically restored and then migrated. By default, this function is disabled, archive objects will be ignored during the migration, and the information about these objects will be recorded in the list of failed objects.
enable_kms	Boolean	Indicates whether to use KMS to encrypt the data to be stored in the destination OBS bucket.
task_type	String	<p>The task type. The default value is PREFIX. LIST indicates that the system will migrate the objects specified in the object list. URL_LIST indicates that the system will migrate the objects specified in the URL list. PREFIX indicates that the system will migrate the objects with a specific prefix.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • LIST • URL_LIST • PREFIX
bandwidth_policy	Array of BandwidthPolicyDto objects	<p>The traffic limiting rules. Each element in the array corresponds to the maximum bandwidth in a time period. A maximum of five periods are allowed, and the periods cannot overlap.</p> <p>Array length: 0 to 5</p>
smn_config	SmnInfo object	The SMN message sending configuration.
source_cdn	SourceCdnResponse object	Indicates whether migration from CDN is enabled. If this field is contained, migration from CDN is supported. Otherwise, it is not supported. If migration from CDN is enabled, the source objects to be migrated are obtained from the specified CDN domain name during migration.

Parameter	Type	Description
migrate_since	Long	<p>The specified migration time (timestamp, in milliseconds). Only source objects that are modified after the specified time will be migrated. Default value 0 indicates that no time is specified.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p> <p>Default value: 0</p>
migrate_speed	Long	<p>The migration speed (byte/s).</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
total_time	Long	<p>The total amount of time used by the migration task group, in ms.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
start_time	Long	<p>The start time (Unix timestamp, in millisecond) of the migration task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
total_task_num	Long	<p>The total number of migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
create_task_num	Long	<p>The number of created migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
failed_task_num	Long	<p>The number of failed migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
complete_task_num	Long	<p>The number of completed migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>
paused_task_num	Long	<p>The number of paused migration tasks in the task group.</p> <p>Minimum value: 0</p> <p>Maximum value: 9223372036854775807</p>

Parameter	Type	Description
executing_task_num	Long	The number of executing migration tasks in the task group. Minimum value: 0 Maximum value: 9223372036854775807
waiting_task_num	Long	The number of waiting migration tasks in the task group. Minimum value: 0 Maximum value: 9223372036854775807
total_num	Long	The total number of objects to be migrated in the migration task group. Minimum value: 0 Maximum value: 9223372036854775807
create_complete_num	Long	The total number of objects contained in created migration tasks. Minimum value: 0 Maximum value: 9223372036854775807
success_num	Long	The number of migrated objects. Minimum value: 0 Maximum value: 9223372036854775807
fail_num	Long	The number of failed objects. Minimum value: 0 Maximum value: 9223372036854775807
skip_num	Long	The number of skipped objects. Minimum value: 0 Maximum value: 9223372036854775807
total_size	Long	The size (in bytes) of the objects that have been migrated. Minimum value: 0 Maximum value: 9223372036854775807
create_complete_size	Long	The total size (in bytes) of objects migrated in created migration tasks. Minimum value: 0 Maximum value: 9223372036854775807
complete_size	Long	The total size of migrated objects, in bytes. Minimum value: 0 Maximum value: 9223372036854775807

Parameter	Type	Description
failed_object_record	FailedObjectRecordDto object	The record of failed objects.
object_overwrite_mode	String	<p>Indicates whether to skip a source object or allow the source object to overwrite its paired destination object. The default value is SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE. NO_OVERWRITE indicates the system never allows overwrite. The system always skips source objects and keeps their paired destination objects.</p> <p>SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE indicates the system allows overwrite based on the results of size or modification time checks. It is the default setting. If a source object is not as large as or was last modified more recently than its paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped.</p> <p>CRC64_COMPARISON_OVERWRITE indicates the system allows overwrite if the source and destination objects have different CRC64 checksums. This option is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object has a CRC64 checksum different from the paired destination object, the source object will overwrite the destination object. Otherwise, the source object will be skipped. If one of them does not have a CRC64 checksum, their sizes and last modification times are checked.</p> <p>FULL_OVERWRITE indicates the system always allows overwrite. The system always allows source objects to overwrite their paired destination objects.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • NO_OVERWRITE • SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE • CRC64_COMPARISON_OVERWRITE • FULL_OVERWRITE

Parameter	Type	Description
dst_storage_policy	String	<p>The destination storage class. STANDARD indicates the Huawei Cloud OBS Standard. IA indicates the Huawei Cloud OBS Infrequent Access. ARCHIVE indicates the Huawei Cloud OBS Archive. DEEP_ARCHIVE indicates the Huawei Cloud OBS Deep Archive.</p> <p>SRC_STORAGE_MAPPING converts the source storage class into an OBS storage class based on the predefined rules.</p> <p>Default value: STANDARD</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 128 characters</p> <p>The value can be:</p> <ul style="list-style-type: none">• STANDARD• IA• ARCHIVE• DEEP_ARCHIVE• SRC_STORAGE_MAPPING

Parameter	Type	Description
consistency_check	String	<p>The consistency check method, which is used to check whether objects are consistent before and after migration. The selected check method and results will be recorded in the object list. The default value is size_last_modified. size_last_modified is the default setting. The system checks object consistency with object size and last modification time. If a source object is as large as but was last modified earlier than its paired destination object, the system considers the source object does not need to be migrated or has been already migrated successfully. crc64 is only available for migration on Huawei Cloud or from Alibaba Cloud or Tencent Cloud. If a source object and its paired destination object have CRC64 checksums, the checksums are checked. Otherwise, their sizes and last modification times are checked. no_check is only available for migration of HTTP/HTTPS data. This option takes effect for source objects whose sizes cannot be obtained using the content-length field in the standard HTTP protocol. These source objects will overwrite their paired destination objects directly. If the size of a source object can be obtained from the Content-Length field in the standard HTTP protocol, its size and last modification time will be checked.</p> <p>The value can be:</p> <ul style="list-style-type: none">• size_last_modified• crc64• no_check
enable_requester_pays	Boolean	Indicates whether to let the requester make payment. After this function is enabled, the requester pays for the request and data transmission.

Table 6-102 ErrorReasonResp field description

Parameter	Type	Description
error_code	String	The error code returned for a migration failure. Minimum length: 0 characters Maximum length: 10 characters

Parameter	Type	Description
error_msg	String	The migration failure cause. Minimum length: 0 characters Maximum length: 1,024 characters

Table 6-103 TaskGroupSrcNodeResp field description

Parameter	Type	Description
bucket	String	The name of the source bucket. Minimum length: 0 characters Maximum length: 1,024 characters
cloud_type	String	<p>The source cloud service provider. The value can be AWS, AZURE, ALIYUN, TENCENT, HUAWEICLOUD, QINGCLOUD, KINGSOFTCLOUD, BAIDU, QINIU, GOOGLE, URLSOURCE, or UCLOUD. The default value is ALIYUN.</p> <p>The value can be:</p> <ul style="list-style-type: none"> • AWS • AZURE • ALIYUN • TENCENT • HUAWEICLOUD • QINGCLOUD • KINGSOFTCLOUD • BAIDU • QINIU • URLSOURCE • UCLOUD • GOOGLE
region	String	The region where the source bucket is located. Minimum length: 0 characters Maximum length: 100 characters
app_id	String	This parameter is returned when cloud_type is Tencent . Minimum length: 0 characters Maximum length: 255 characters

Parameter	Type	Description
object_key	Array of strings	The name prefixes of objects to be migrated if task_type is set to prefix . Minimum length: 0 characters Maximum length: 1,024 characters Array length: 0 to 500
list_file	ListFile object	The list file configuration. list_file is mandatory when task_type is set to list or url_list .

Table 6-104 ListFile field description

Parameter	Type	Description
list_file_key	String	The object names in the object list file or URL list file. Minimum length: 1 character Maximum length: 1,024 characters
obs_bucket	String	The name of the OBS bucket for storing the object list files. Ensure that the OBS bucket is in the same region as the destination bucket, or the task will fail to be created. Minimum length: 0 characters Maximum length: 1,024 characters
list_file_num	String	The number of stored object list files. Minimum length: 0 characters Maximum length: 65,535 characters

Table 6-105 TaskGroupDstNodeResp field description

Parameter	Type	Description
bucket	String	The name of the destination bucket. Minimum length: 0 characters Maximum length: 1,024 characters
region	String	The region where the destination bucket is located. Minimum length: 0 characters Maximum length: 100 characters

Parameter	Type	Description
save_prefix	String	<p>The path prefix in the destination bucket. The prefix is added before an object key to form a new key. The length of the new key cannot exceed 1,024 characters.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 1,024 characters</p>

Table 6-106 BandwidthPolicyDto field description

Parameter	Type	Description
end	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.
max_bandwidth	Long	<p>The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s).</p> <p>Minimum value: 1048576</p> <p>Maximum value: 209715200</p>
start	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Table 6-107 SmnInfo field description

Parameter	Type	Description
notify_result	Boolean	Indicates whether the SMN messages are sent successfully after migration tasks are complete.
notify_error_message	String	<p>The error codes that record why the SMN messages failed to be sent. The value is empty if migration tasks are successful.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 1,024 characters</p>
topic_name	String	<p>The SMN topic name. The value is empty if SMN messages are sent successfully.</p> <p>Minimum length: 0 characters</p> <p>Maximum length: 5,120 characters</p>

Table 6-108 SourceCdnResp field description

Parameter	Type	Description
domain	String	The domain name from which to obtain objects to be migrated. Minimum length: 0 characters Maximum length: 1,024 characters
protocol	String	The protocol type. The value can be: <ul style="list-style-type: none">• HTTP• HTTPS
authentication_type	String	The authentication type. The value can be: <ul style="list-style-type: none">• NONE• QINIU_PRIVATE_AUTHENTICATION• ALIYUN_OSS_A• ALIYUN_OSS_B• ALIYUN_OSS_C• KSYUN_PRIVATE_AUTHENTICATION• AZURE_SAS_TOKEN• TENCENT_COS_A• TENCENT_COS_B• TENCENT_COS_C• TENCENT_COS_D

Table 6-109 FailedObjectRecordDto field description

Parameter	Type	Description
result	Boolean	Indicates whether to retransmit failed objects.
list_file_key	String	The path for storing the list of failed objects. Minimum length: 0 characters Maximum length: 1,024 characters
error_code	String	The error code returned when the list of failed objects fails to be uploaded. Minimum length: 0 characters Maximum length: 10 characters

Status code: 404

Table 6-110 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries the information about migration task group **157ece42-3270-4824-a3d2-f0187a03ca01** in project **f4e146cac1de45669c3fed73dc3b9c6f**.

```
Get https://{endpoint}/v2/f4e146cac1de45669c3fed73dc3b9c6f/taskgroups/157ece42-3270-4824-a3d2-f0187a03ca01
```

Example Response

Status code: 200

OK

```
{  
    "group_id": "9522a7e5-b4fc-44b9-93e1-4dbadbd86e67",  
    "status": 3,  
    "error_reason": null,  
    "src_node": {  
        "bucket": "dst-test-001",  
        "cloud_type": "HUAWEICLOUD",  
        "region": "cn-north-7",  
        "app_id": "",  
        "object_key": [ "" ],  
        "list_file": null  
    },  
    "description": "",  
    "dst_node": {  
        "bucket": "assess-bucket-1",  
        "region": "cn-north-7",  
        "save_prefix": ""  
    },  
    "enable_metadata_migration": false,  
    "enable_failed_object_recording": true,  
    "enable_restore": false,  
    "enable_kms": false,  
    "task_type": "PREFIX",  
    "bandwidth_policy": [ ],  
    "smn_config": null,  
    "source_cdn": null,  
    "migrate_since": 0,  
    "migrate_speed": 0,  
    "total_time": 7907369,  
    "start_time": 1659937788779,  
    "total_task_num": null,  
    "create_task_num": null,  
    "failed_task_num": null,  
    "complete_task_num": null,  
    "paused_task_num": null,  
    "executing_task_num": null,  
    "waiting_task_num": null,  
    "total_num": 4128588,  
    "create_complete_num": null,  
    "success_num": 0,  
}
```

```
"fail_num" : 0,  
"skip_num" : 0,  
"total_size" : 27814708666,  
"create_complete_size" : null,  
"complete_size" : 0,  
"failed_object_record" : {  
    "result" : null,  
    "list_file_key" : null,  
    "error_code" : null  
},  
"object_overwrite_mode" : "SIZE_LAST_MODIFIED_COMPARISON_OVERWRITE",  
"consistency_check" : "size_last_modified",  
"enable_requester_pays" : false  
}
```

Status Codes

Status Code	Description
200	OK
404	Not Found

Error Codes

For details, see [Error Codes](#).

6.3.4 Deleting a Migration Task Group

Function

This API is used to delete a migration task group. Task groups in **Creating**, **Monitoring**, or **Paused** status cannot be deleted. If you try to delete such a task group, the system will return a message indicating the deletion fails. To delete the task group, pause it first.

Calling Method

For details, see [Calling APIs](#).

URI

DELETE /v2/{project_id}/taskgroups/{group_id}

Table 6-111 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Parameter	Mandatory	Type	Description
group_id	Yes	String	The task group ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-112 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 400

Table 6-113 Response body parameters

Parameter	Type	Description
error_code	String	The error code returned for a migration failure. Minimum length: 0 characters Maximum length: 10 characters
error_msg	String	The migration failure cause. Minimum length: 0 characters Maximum length: 1,024 characters

Status code: 403

Table 6-114 Response body parameters

Parameter	Type	Description
error_code	String	The error code returned for a migration failure. Minimum length: 0 characters Maximum length: 10 characters

Parameter	Type	Description
error_msg	String	The migration failure cause. Minimum length: 0 characters Maximum length: 1,024 characters

Example Request

This example deletes the migration task group **157ece42-3270-4824-a3d2-f0187a03ca01** in the project **f4e146cac1de45669c3fed73dc3b9c6f**.

```
DELETE https://{endpoint}/v2/f4e146cac1de45669c3fed73dc3b9c6f/taskgroups/157ece42-3270-4824-a3d2-f0187a03ca01
```

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.3.5 Pausing a Migration Task Group

Function

This API is used to pause a migration task group when the migration task group is in **Creating** or **Monitoring** status.

Calling Method

For details, see [Calling APIs](#).

URI

```
PUT /v2/{project_id}/taskgroups/{group_id}/stop
```

Table 6-115 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
group_id	Yes	String	The task group ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-116 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 400

Table 6-117 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 403

Table 6-118 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.

Parameter	Type	Description
error_code	String	The error code.

Example Request

This example pauses the migration task group **157ece42-3270-4824-a3d2-f0187a03ca01** in the project **f4e146cac1de45669c3fed73dc3b9c6f**.

```
PUT https://[endpoint]/v2/f4e146cac1de45669c3fed73dc3b9c6f/taskgroups/157ece42-3270-4824-a3d2-f0187a03ca01
```

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.3.6 Resuming a Migration Task Group

Function

This API is used to resume a paused migration task group with the specified ID.

Calling Method

For details, see [Calling APIs](#).

URI

```
PUT /v2/{project_id}/taskgroups/{group_id}/start
```

Table 6-119 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
group_id	Yes	String	The task group ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-120 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-121 Request body parameters

Parameter	Mandatory	Type	Description
src_ak	No	String	The AK for accessing the source node. Enter a maximum of 100 characters. This parameter is not required for URL list-based migration task groups. Minimum length: 1 character Maximum length: 100 characters

Parameter	Mandatory	Type	Description
src_sk	No	String	The SK for accessing the source node. Enter a maximum of 100 characters. This parameter is not required for URL list-based migration task groups. Minimum length: 1 character Maximum length: 100 characters
json_auth_file	No	String	The file used for Google Cloud Storage authentication. Minimum length: 0 characters Maximum length: 65,535 characters
dst_ak	Yes	String	The AK for accessing the destination node. Enter a maximum of 100 characters. Minimum length: 1 character Maximum length: 100 characters
dst_sk	Yes	String	The SK for accessing the destination node. Enter a maximum of 100 characters. Minimum length: 1 character Maximum length: 100 characters
source_cdn_authentication_key	No	String	The CDN authentication key. Minimum length: 0 characters Maximum length: 255 characters

Response

Status code: 400

Table 6-122 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 403

Table 6-123 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example resumes the migration task group whose ID is **2c11d99a-9596-4bc6-a6ad-2336455b149c** using the AK/SK pairs of the source and destination accounts.

```
PUT https://{endpoint}/v2/{project_id}/taskgroups/00878453-3402-4a86-9e2a-5d5217cd35b2/start
{
    "src_ak" : "src_AK",
    "src_sk" : "src_SK",
    "dst_ak" : "dst_AK",
    "dst_sk" : "dst_SK"
}
```

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.3.7 Restarting a Migration Task Group

Function

This API is used to restart a failed migration task group.

Calling Method

For details, see [Calling APIs](#).

URI

PUT /v2/{project_id}/taskgroups/{group_id}/retry

Table 6-124 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
group_id	Yes	String	The task group ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-125 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-126 Request body parameters

Parameter	Mandatory	Type	Description
src_ak	No	String	The AK for accessing the source. Enter a maximum of 100 characters. Minimum length: 0 characters Maximum length: 100 characters
src_sk	No	String	The SK for accessing the source. Enter a maximum of 100 characters. Minimum length: 0 characters Maximum length: 100 characters

Parameter	Mandatory	Type	Description
json_auth_file	No	String	The file used for Google Cloud Storage authentication. Minimum length: 0 characters Maximum length: 65,535 characters
dst_ak	No	String	The AK for accessing the destination. Enter a maximum of 100 characters. Minimum length: 0 characters Maximum length: 100 characters
dst_sk	No	String	The SK for accessing the destination. Enter a maximum of 100 characters. Minimum length: 0 characters Maximum length: 100 characters
source_cdn_authentication_key	No	String	The CDN authentication key. Minimum length: 0 characters Maximum length: 255 characters
migrate_failed_object	No	Boolean	The retry mode of failed tasks. It specifies whether to migrate all objects in the failed tasks again. If the value is true , only failed objects will be migrated again. If the value is false or not specified, all objects will be migrated again. By default, the objects that have been migrated to the destination are skipped. Default value: false

Response

Status code: 400

Table 6-127 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.

Parameter	Type	Description
error_code	String	The error code.

Status code: 403

Table 6-128 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example retries the migration task group whose ID is **2c11d99a-9596-4bc6-a6ad-2336455b149c** using the AK/SK pairs of the source and destination accounts.

```
PUT https://[endpoint]/v2/[project_id]/taskgroups/2c11d99a-9596-4bc6-a6ad-2336455b149c/retry
{
    "src_ak": "src_AK",
    "src_sk": "src_SK",
    "dst_ak": "dst_AK",
    "dst_sk": "dst_SK",
    "migrate_failed_object": false
}
```

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.3.8 Modifying the Traffic Limiting Rules of a Migration Task Group

Function

This API is used to update the traffic limiting rules for a migration task group before it is completed.

Calling Method

For details, see [Calling APIs](#).

URI

PUT /v2/{project_id}/taskgroups/{group_id}/update

Table 6-129 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters
group_id	Yes	String	The task group ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-130 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The token used for IAM authentication. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-131 Request body parameters

Parameter	Mandatory	Type	Description
bandwidth_policy	Yes	Array of BandwidthPolicyDto objects	The traffic limiting rules. Each element in the array corresponds to the maximum bandwidth in a time period. A maximum of five periods are allowed, and the periods cannot overlap. Array length: 0 to 5

Table 6-132 BandwidthPolicyDto field description

Parameter	Mandatory	Type	Description
end	Yes	String	The end time of the traffic limiting rule. The format is hh:mm, for example, 12:03.
max_bandwidth	Yes	Long	The maximum traffic bandwidth allowed in the specified time period. The unit is byte/s. The value ranges from 1,048,576 bytes/s (equivalent to 1 MB/s) to 209,715,200 bytes/s (equivalent to 200 MB/s). Minimum value: 1048576 Maximum value: 209715200
start	Yes	String	The start time of the traffic limiting rule. The format is hh:mm, for example, 12:03.

Response

Status code: 400

Table 6-133 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Status code: 403

Table 6-134 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example updates the migration rate limit for the task whose ID is **xxxxxxxx** from 00:01 to 23:59 to 50 MB/s.

```
PUT /v2/{project_id}/taskgroup/xxxxxxxx/update
{
  "bandwidth_policy" : [ {
    "start" : "00:01",
    "end" : "23:59",
    "max_bandwidth" : 50000000
  } ]
}
```

Example Response

None

Status Codes

Status Code	Description
200	OK
400	Bad Request
403	Forbidden

Error Codes

For details, see [Error Codes](#).

6.4 Operations on Buckets

6.4.1 Listing Objects in a Bucket

Function

This API is used to list objects in a bucket.

Calling Method

For details, see [Calling APIs](#).

URI

POST /v2/{project_id}/objectstorage/buckets/objects

Table 6-135 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-136 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The IAM token authentication. Ensure that the project ID contained in the token matches the project ID in the request URI. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-137 Request body parameters

Parameter	Mandatory	Type	Description
cloud_type	Yes	String	The cloud service provider. The value can be AWS , Aliyun , Qiniu , QingCloud , Tencent , Baidu , KingsoftCloud , Azure , UCloud , HuaweiCloud , Google , URLSource , or HEC . Minimum length: 0 characters Maximum length: 100 characters

Parameter	Mandatory	Type	Description
file_path	Yes	String	The path to be queried in the bucket, which must end with a slash (/). Minimum length: 0 characters Maximum length: 1,023 characters
ak	No	String	The AK for accessing the source bucket. Minimum length: 0 characters Maximum length: 100 characters
sk	No	String	The SK for accessing the source bucket. Minimum length: 0 characters Maximum length: 100 characters
json_auth_file	No	String	The file used for Google Cloud Storage authentication. Minimum length: 0 characters Maximum length: 65,535 characters
data_center	Yes	String	The region. Minimum length: 0 characters Maximum length: 100 characters
page_size	Yes	Integer	The page size. Minimum value: 0 Maximum value: 100
behind_filename	Yes	String	The name of the last object on the current page (offset). Minimum length: 0 characters Maximum length: 1,024 characters
app_id	No	String	This parameter is mandatory when cloud_type is Tencent . Minimum length: 0 characters Maximum length: 255 characters

Parameter	Mandatory	Type	Description
bucket_name	Yes	String	The bucket name. Minimum length: 0 characters Maximum length: 100 characters

Response

Status code: 200

Table 6-138 Response body parameters

Parameter	Type	Description
next_page	Boolean	Whether there is a next page.
next_marker	String	Marker required for querying the next page (object name at the end of the current page, offset) Minimum length: 0 characters Maximum length: 1,024 characters
records	Array of ShowBucketRecord objects	The queried object information. Array length: 0 to 100

Table 6-139 ShowBucketRecord field description

Parameter	Type	Description
name	String	The object name. Minimum length: 0 characters Maximum length: 1,024 characters
size	String	The object size. If the object does not have the size attribute, "--" is returned. Minimum length: 0 characters Maximum length: 100 characters

Status code: 400

Table 6-140 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example lists objects in a specified bucket and returns the object information on multiple pages.

```
POST https://{endpoint}/v2/{project_id}/objectstorage/buckets/objects
{
    "page_size": 100,
    "behind_filename": "",
    "file_path": "A/",
    "cloud_type": "HuaweiCloud",
    "bucket_name": "xxx",
    "ak": "xxxxxak",
    "sk": "xxxxxsk",
    "data_center": "cn-north-x"
}
```

Example Response

Status code: 200

The object information is obtained.

```
{
    "next_page": false,
    "next_marker": null,
    "records": [
        {
            "name": "xxxx",
            "size": "--"
        },
        {
            "name": "xxxx",
            "size": "73.59 MB"
        }
    ]
}
```

Status Codes

Status Code	Description
200	The object information is obtained.
400	Standard error response.

Error Codes

For details, see [Error Codes](#).

6.4.2 Querying the CDN Information of a Bucket

Function

This API is used to query the CDN information of a bucket.

Calling Method

For details, see [Calling APIs](#).

URI

POST /v2/{project_id}/objectstorage/buckets/cdn-info

Table 6-141 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-142 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The IAM token authentication. Ensure that the project ID contained in the token matches the project ID in the request URI. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-143 Request body parameters

Parameter	Mandatory	Type	Description
ak	Yes	String	The AK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters
sk	Yes	String	The SK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters
cloud_type	Yes	String	The cloud service provider. The value can be AWS , Aliyun , Qiniu , QingCloud , Tencent , Baidu , KingsoftCloud , Azure , UCloud , HuaweiCloud , URLSource , or HEC . Minimum length: 0 characters Maximum length: 100 characters
region	Yes	String	The region. Minimum length: 0 characters Maximum length: 100 characters
app_id	No	String	This parameter is mandatory when cloud_type is Tencent . Minimum length: 0 characters Maximum length: 255 characters
bucket	Yes	String	The bucket name. Minimum length: 0 characters Maximum length: 100 characters
prefix	No	PrefixKeyInfo object	The prefix.

Parameter	Mandatory	Type	Description
source_cdn	Yes	SourceCdnReq object	Indicates whether migration from CDN is enabled. If this field is contained, migration from CDN is supported. Otherwise, it is not supported. If migration from CDN is enabled, the source objects to be migrated are obtained from the specified CDN domain name during migration.

Table 6-144 PrefixKeyInfo field description

Parameter	Mandatory	Type	Description
keys	Yes	Array of strings	The object names. Minimum length: 0 characters Maximum length: 2,048 characters Array length: 0 to 100

Table 6-145 SourceCdnReq field description

Parameter	Mandatory	Type	Description
authentication_key	No	String	The CDN authentication key. If the CDN authentication is required, this parameter is mandatory. If no authorization is required, do not set this parameter. Qiniu: You do not need to set this parameter. Aliyun: Set this parameter based on the value of authentication_type . KingsoftCloud: You do not need to set this parameter. Minimum length: 0 characters Maximum length: 255 characters

Parameter	Mandatory	Type	Description
authentication_type	Yes	String	<p>The authentication type. Default value: NONE The value can be:</p> <ul style="list-style-type: none"> • NONE • QINIU_PRIVATE_AUTHENTICATION • ALIYUN_OSS_A • ALIYUN_OSS_B • ALIYUN_OSS_C • KSYUN_PRIVATE_AUTHENTICATION • AZURE_SAS_TOKEN • TENCENT_COS_A • TENCENT_COS_B • TENCENT_COS_C • TENCENT_COS_D
domain	Yes	String	<p>The domain name from which to obtain objects to be migrated. Minimum length: 0 characters Maximum length: 1,024 characters</p>
protocol	Yes	String	<p>The protocol type. The value can be:</p> <ul style="list-style-type: none"> • http • https

Response

Status code: 200

Table 6-146 Response body parameters

Parameter	Type	Description
is_same_cloud_type	Boolean	Whether the CDN is provided by the source cloud vendor.
is_download_available	Boolean	Whether source data can be downloaded from the CDN.

Parameter	Type	Description
checked_keys	Array of CheckedKey objects	Returned array of checked objects Array length: 0 to 1,000

Table 6-147 CheckedKey

Parameter	Type	Description
key	String	The object name. Minimum length: 0 characters Maximum length: 2,048 characters
is_etag_matching	Boolean	Whether the etag is matched.
is_object_existing	Boolean	Whether the object is found.

Status code: 400

Table 6-148 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries the CDN information of the **xxx** bucket using the **xcsad** key in ALIYUN_OSS_B authentication type.

```
POST https://[endpoint]/v2/{project_id}/objectstorage/buckets/cdn-info
{
    "ak" : "xxx",
    "sk" : "xxx",
    "cloud_type" : "Aliyun",
    "region" : "cn-hangzhou",
    "bucket" : "xxx",
    "source_cdn" : {
        "protocol" : "https",
        "domain" : "xxx",
        "authentication_type" : "ALIYUN_OSS_B",
        "authentication_key" : "xcsad"
    }
}
```

Example Response

Status code: 200

The CDN information was returned.

```
{  
    "is_same_cloud_type" : false,  
    "is_download_available" : false,  
    "checked_keys" : [ {  
        "key" : "xxx",  
        "is_etag_matching" : false,  
        "is_object_existing" : false  
    }, {  
        "key" : "yyy",  
        "is_etag_matching" : false,  
        "is_object_existing" : false  
    }, {  
        "key" : "ccc",  
        "is_etag_matching" : false,  
        "is_object_existing" : false  
    }, {  
        "key" : "bbb",  
        "is_etag_matching" : false,  
        "is_object_existing" : false  
    }, {  
        "key" : "nnnn",  
        "is_etag_matching" : false,  
        "is_object_existing" : false  
    } ]  
}
```

Status Codes

Status Code	Description
200	The CDN information was returned.
400	Standard error response.

Error Codes

For details, see [Error Codes](#).

6.4.3 Listing Buckets

Function

This API is used to list buckets.

Calling Method

For details, see [Calling APIs](#).

URI

POST /v2/{project_id}/objectstorage/buckets

Table 6-149 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-150 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The IAM token authentication. Ensure that the project ID contained in the token matches the project ID in the request URI. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-151 Request body parameters

Parameter	Mandatory	Type	Description
cloud_type	Yes	String	The cloud service provider. The value can be AWS , Aliyun , Qiniu , QingCloud , Tencent , Baidu , KingsoftCloud , Azure , UCloud , HuaweiCloud , Google , URLSource , or HEC . Default value: Aliyun Minimum length: 0 characters Maximum length: 100 characters
ak	No	String	The AK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters

Parameter	Mandatory	Type	Description
sk	No	String	The SK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters
json_auth_file	No	String	The file used for Google Cloud Storage authentication. Minimum length: 0 characters Maximum length: 65,535 characters
app_id	No	String	This parameter is mandatory when cloud_type is Tencent . Minimum length: 0 characters Maximum length: 255 characters

Response

Status code: 200

Table 6-152 Response body parameters

Parameter	Type	Description
[Array element]	Array of strings	The bucket list.

Status code: 400

Table 6-153 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries the list of all buckets in an account using an AK/SK pair.

```
POST https://[endpoint]/v2/{project_id}/objectstorage/buckets
{
    "cloud_type" : "HuaweiCloud",
    "ak" : "xxxxak",
    "sk" : "xxxxsk",
    "app_id" : "apptest123"
}
```

Example Response

Status code: 200

The bucket list was returned.

```
[ "xxxx" ]
```

Status Codes

Status Code	Description
200	The bucket list was returned.
400	Standard error response.

Error Codes

For details, see [Error Codes](#).

6.4.4 Querying the Region of a Bucket

Function

This API is used to query the region of a bucket.

Calling Method

For details, see [Calling APIs](#).

URI

```
POST /v2/{project_id}/objectstorage/buckets/regions
```

Table 6-154 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-155 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The IAM token authentication. Ensure that the project ID contained in the token matches the project ID in the request URI. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-156 Request body parameters

Parameter	Mandatory	Type	Description
cloud_type	Yes	String	The cloud service provider. The value can be AWS , Aliyun , Qiniu , QingCloud , Tencent , Baidu , KingsoftCloud , Azure , UCloud , HuaweiCloud , Google , URLSource , or HEC . Default value: Aliyun Minimum length: 0 characters Maximum length: 100 characters
ak	No	String	The AK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters
sk	No	String	The SK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters

Parameter	Mandatory	Type	Description
json_auth_file	No	String	The file used for Google Cloud Storage authentication. Minimum length: 0 characters Maximum length: 65,535 characters
app_id	No	String	This parameter is mandatory when cloud_type is Tencent . Minimum length: 0 characters Maximum length: 255 characters
bucket_name	Yes	String	The bucket name. Minimum length: 0 characters Maximum length: 100 characters

Response

Status code: 200

Table 6-157 Response body parameters

Parameter	Type	Description
id	String	The region ID. Minimum length: 0 characters Maximum length: 1,024 characters
name	String	The region name. Minimum length: 0 characters Maximum length: 1,024 characters
support	Boolean	Specifies whether the region is supported for migration.

Status code: 400

Table 6-158 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example queries the region of a bucket.

```
POST https://{endpoint}/v2/{project_id}/objectstorage/buckets/regions
{
  "cloud_type" : "HuaweiCloud",
  "ak" : "xxxxak",
  "sk" : "xxxxsk",
  "app_id" : "apptest123",
  "bucket_name" : "xxx"
}
```

Example Response

Status code: 200

Response to the query of a bucket's region.

```
{
  "id" : "string",
  "name" : "string"
}
```

Status Codes

Status Code	Description
200	Response to the query of a bucket's region.
400	Standard error response.

Error Codes

For details, see [Error Codes](#).

6.4.5 Checking Whether a Source Bucket Has Objects with a Specified Prefix

Function

This API is used to check whether there are objects with a specified prefix in a source bucket.

Calling Method

For details, see [Calling APIs](#).

URI

```
POST /v2/{project_id}/objectstorage/buckets/prefix
```

Table 6-159 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-160 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The IAM token authentication. Ensure that the project ID contained in the token matches the project ID in the request URI. Minimum length: 1 character Maximum length: 16,384 characters

Table 6-161 Request body parameters

Parameter	Mandatory	Type	Description
cloud_type	Yes	String	The cloud service provider. The value can be AWS , Aliyun , Qiniu , QingCloud , Tencent , Baidu , KingsoftCloud , Azure , UCloud , HuaweiCloud , Google , URLSource , or HEC . Default value: Aliyun Minimum length: 0 characters Maximum length: 100 characters
ak	No	String	The AK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters

Parameter	Mandatory	Type	Description
sk	No	String	The SK for accessing the source bucket. This parameter is mandatory when task_type is not url_list . Minimum length: 0 characters Maximum length: 100 characters
json_auth_file	No	String	The file used for Google Cloud Storage authentication. Minimum length: 0 characters Maximum length: 65,535 characters
app_id	No	String	This parameter is mandatory when cloud_type is Tencent . Minimum length: 0 characters Maximum length: 255 characters
bucket_name	Yes	String	The bucket name. Minimum length: 0 characters Maximum length: 100 characters
file_name	Yes	String	The prefix. Minimum length: 0 characters Maximum length: 1,024 characters
data_center	Yes	String	The region. Minimum length: 0 characters Maximum length: 100 characters
security_token	No	String	The security token. Minimum length: 0 characters Maximum length: 16,384 characters

Response

Status code: 200

Table 6-162 Response body parameters

Parameter	Type	Description
exist	Boolean	Whether the prefix is found. Default value: false

Status code: 400

Table 6-163 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

This example checks whether bucket **xxx** has objects with prefix **xxxx**.

```
POST https://{endpoint}/v2/{project_id}/objectstorage/buckets/prefix
{
    "cloud_type" : "HuaweiCloud",
    "ak" : "xxxxak",
    "sk" : "xxxxsk",
    "app_id" : "apptest123",
    "bucket_name" : "xxx",
    "file_name" : "xxxx",
    "data_center" : "cn-north-x",
    "security_token" : "string"
}
```

Example Response

Status code: 200

The prefix was found.

```
{
    "exist" : true
}
```

Status Codes

Status Code	Description
200	The prefix was found.
400	Standard error response.

Error Codes

For details, see [Error Codes](#).

6.5 Querying Supported Source Clouds

6.5.1 Querying All Supported Cloud Vendors

Function

This API is used to query supported cloud vendors.

Calling Method

For details, see [Calling APIs](#).

URI

GET /v2/{project_id}/objectstorage/cloud-type

Table 6-164 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Table 6-165 Query parameters

Parameter	Mandatory	Type	Description
type	Yes	String	The connection end type. The value can be src (source) or dst (destination). Minimum length: 1 character Maximum length: 25 characters

Request

Table 6-166 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The IAM token authentication. Ensure that the project ID contained in the token matches the project ID in the request URI. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 200

Table 6-167 Response body parameters

Parameter	Type	Description
[Array element]	Array of strings	Supported cloud vendors.

Status code: 400

Table 6-168 Response body parameters

Parameter	Type	Description
error_msg	String	The error message.
error_code	String	The error code.

Example Request

None

Example Response

Status code: 200

Supported cloud vendors were returned.

```
[ "AWS", "Aliyun", "Qiniu", "QingCloud", "Tencent", "Baidu", "KingsoftCloud", "Azure", "UCloud",  
"HuaweiCloud", "URLSource" ]
```

Status Codes

Status Code	Description
200	Supported cloud vendors were returned.
400	Standard error response.

Error Codes

For details, see [Error Codes](#).

6.6 Querying Supported Regions

6.6.1 Querying Regions Supported for a Cloud Vendor

Function

This API is used to query regions supported for a cloud vendor.

Calling Method

For details, see [Calling APIs](#).

URI

GET /v2/{project_id}/objectstorage/data-center

Table 6-169 Path parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	The project ID. Minimum length: 1 character Maximum length: 1,024 characters

Request

Table 6-170 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	The IAM token authentication. Ensure that the project ID contained in the token matches the project ID in the request URI. Minimum length: 1 character Maximum length: 16,384 characters

Response

Status code: 200

Table 6-171 Response body parameters

Parameter	Type	Description
[Array element]	Array of ShowRegionInfoResp objects	The queried region information.

Table 6-172 [ShowRegionInfoResp](#) field description

Parameter	Type	Description
service_name	String	The cloud vendor name. Minimum length: 0 characters Maximum length: 255 characters
region_list	Array of RegionInfo objects	The region list. Array length: 0 to 1,024

Table 6-173 RegionInfo field description

Parameter	Type	Description
cloud_type	String	The cloud service name. Minimum length: 1 character Maximum length: 255 characters
value	String	The region name. Minimum length: 1 character Maximum length: 255 characters
description	String	The region description. Minimum length: 0 characters Maximum length: 1,024 characters

Example Request

None

Example Response

Status code: 200

The region list was returned.

```
[ {  
    "service_name" : "AWS",  
    "region_list" : [ {  
        "cloud_type" : "AWS",  
        "value" : "us-east-1",  
        "description" : "US Standard (N. Virginia)"  
    }, {  
        "cloud_type" : "AWS",  
        "value" : "us-west-1",  
        "description" : "US West (N. California)"  
    }, {  
        "cloud_type" : "AWS",  
        "value" : "us-west-2",  
        "description" : "US West (Oregon)"  
    }, {  
        "cloud_type" : "AWS",  
        "value" : "eu-west-1",  
        "description" : "EU (Ireland)"  
    }, {  
        "cloud_type" : "AWS",  
        "value" : "eu-central-1",  
        "description" : "EU (Frankfurt)"  
    }, {  
        "cloud_type" : "AWS",  
        "value" : "ap-northeast-1",  
        "description" : "Asia Pacific (Tokyo)"  
    }, {  
        "cloud_type" : "AWS",  
        "value" : "ap-northeast-2",  
        "description" : "Asia Pacific (Seoul)"  
    }, {  
        "cloud_type" : "AWS",  
        "value" : "ap-southeast-1",  
        "description" : "Asia Pacific (Singapore)"  
    } ]
```

```
        "description" : "Asia Pacific (Singapore)"  
}, {  

```

Status Codes

Status Code	Description
200	The region list was returned.

Error Codes

For details, see [Error Codes](#).

7 Appendix

7.1 Status Codes

Table 7-1 describes the status codes.

Table 7-1 Status codes

Status Code	Description	Description
200	OK	The request is successfully processed.
201	Created	The request for creating a resource or task has been fulfilled.
202	Accepted	The request has been accepted, but the processing has not been completed.
204	No Content	The server has successfully processed the request, but has not returned any content. The status code is returned in response to an HTTP OPTIONS request.
400	Bad Request	Invalid request. The client should not repeat the request without modifications.
401	Unauthorized	The status code is returned after the client provides the authentication information, indicating that the authentication information is incorrect or invalid.

Status Code	Description	Description
403	Forbidden	The server understood the request, but is refusing to fulfill it. The client should not repeat the request without modifications.
404	Not Found	The requested resource cannot be found. The client should not repeat the request without modifications.
405	Method Not Allowed	The method specified in the request is not supported for the requested resource. The client should not repeat the request without modifications.
406	Not Acceptable	The server cannot fulfill the request according to the content characteristics of the request.
409	Conflict	The request could not be processed due to a conflict. This status code indicates that the resource that the client attempts to create already exists, or the request fails to be processed because of the update of the conflict request.
413	Request Entity Too Large	The request is larger than that a server is able to process. The server may close the connection to prevent the client from continuing the request. If the server cannot process the request temporarily, the response will contain a Retry-After header field.
415	Unsupported Media Type	The server is unable to process the media format in the request.
500	Internal Server Error	The server is able to receive the request but it could not understand the request.
501	Not Implemented	The server does not support the requested function.
503	Service Unavailable	The requested service is invalid. The client should not repeat the request without modifications.

7.2 Error Codes

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0001	System error. Click Restart to restart the migration task.	System error.	Click Restart to restart the migration task.
200	TRF.0003	Waiting for task execution timed out. Click Restart to restart the migration task.	Waiting for task execution timed out.	Click Restart to restart the migration task.
200	TRF.0012	Failed to verify the task parameters. Ensure that there are objects for the selected migration method.	Failed to verify the task parameters.	Ensure that there are objects for the selected migration method.
200	TRF.0013	The object list file does not exist or cannot be obtained. Ensure that the object list file exists, and the current AK and SK have read and write permissions for the file.	The object list file does not exist or cannot be obtained.	Ensure that the object list file exists, and the current AK and SK have read and write permissions for the file.
200	TRF.0014	Invalid object list file. Ensure the object list file is a .txt file, and is no larger than 100 MB.	Invalid object list file.	Ensure the object list file is a .txt file, and is no larger than 100 MB.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0015	The source AK and SK are invalid because the Azure storage account does not use Blob storage. Enter a valid AK and SK.	The source AK and SK are invalid because the Azure storage account does not use Blob storage.	Enter a valid AK and SK.
200	TRF.0016	The format of the URL list file is incorrect. Check the format of the URL list file by referring to OMS User Guide or contact technical support.	The format of the URL list file is incorrect.	Check the format of the URL list file by referring to <i>OMS User Guide</i> or contact technical support.
200	TRF.0017	No URL found in the specified list file. Check the list file.	No URL found in the specified list file.	Check the list file.
200	TRF.0051	The account corresponding to the entered AK/SK does not have the permissions to access the destination bucket or objects. Ensure that the account has the required permissions and try again.	The account corresponding to the entered AK/SK does not have the permissions to access the destination bucket or objects.	Ensure that the account has the required permissions and try again.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0052	The account corresponding to the entered AK/SK does not have the permissions to access the destination bucket or objects. Ensure that the account has the required permissions and try again.	The account corresponding to the entered AK/SK does not have the permissions to access the destination bucket or objects.	Ensure that the account has the required permissions and try again.
200	TRF.0053	The migration cannot be completed because your HUAWEI CLOUD account is expired or frozen. Contact customer service.	The migration cannot be completed because your HUAWEI CLOUD account is expired or frozen.	Contact customer service.
200	TRF.0054	The account corresponding to the entered AK/SK does not have the permissions to access the destination bucket or objects. Ensure that the account has the required permissions and try again.	The account corresponding to the entered AK/SK does not have the permissions to access the destination bucket or objects.	Ensure that the account has the required permissions and try again.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0055	The destination OBS bucket does not have enough space. Ensure that the destination bucket has enough space and try again.	The destination OBS bucket does not have enough space.	Ensure that the destination bucket has enough space and try again.
200	TRF.0056	Your HUAWEI CLOUD account is frozen. Try again after your account is unfrozen.	Your HUAWEI CLOUD account is frozen.	Try again after your account is unfrozen.
200	TRF.0057	Invalid AK or SK. Enter the correct AK and SK and try again.	Invalid AK or SK.	Enter the correct AK and SK and try again.
200	TRF.0058	The destination OBS bucket does not exist (do not modify permissions to access the destination bucket or objects during the migration). Ensure that the destination bucket name is correct and try again.	The destination OBS bucket does not exist (do not modify permissions to access the destination bucket or objects during the migration).	Ensure that the destination bucket name is correct and try again.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0059	The destination objects do not exist (do not modify permissions to access the destination bucket or objects during the migration). Ensure that the names of the destination bucket and objects are correct and try again.	The destination objects do not exist (do not modify permissions to access the destination bucket or objects during the migration).	Ensure that the names of the destination bucket and objects are correct and try again.
200	TRF.0060	The path for storing the migrated objects is too long. Change the object names or the path for storing them.	The path for storing the migrated objects is too long.	Change the object names or the path for storing them.
200	TRF.0061	There is a problem with the destination object storage service. Try again later or contact technical support.	There is a problem with the destination object storage service.	Try again later or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0062	Some objects cannot be migrated. Ensure that there are no tasks to migrate those objects and try again later.	Some objects cannot be migrated.	Ensure that there are no tasks to migrate those objects and try again later.
200	TRF.0063	The migration task failed. Data cannot be migrated to the destination OBS bucket because your account balance is insufficient. Top up your account or contact customer service.	The migration task failed. Data cannot be migrated to the destination OBS bucket because your account balance is insufficient.	Top up your account or contact customer service.
200	TRF.0151	The source AK/SK is invalid. Enter the correct AK and SK and try again.	The source AK or SK is invalid.	Enter the correct AK and SK and try again.
200	TRF.0152	The account corresponding to the entered AK/SK does not have the permissions to access the source bucket or objects. Ensure that the account has the required permissions and try again.	The account corresponding to the entered AK/SK does not have the permissions to access the source bucket or objects.	Ensure that the account has the required permissions and try again.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0153	The account corresponding to the entered AK/SK does not have the permissions to access the source bucket or objects. Ensure that the account has the required permissions and try again.	The account corresponding to the entered AK/SK does not have the permissions to access the source bucket or objects.	Ensure that the account has the required permissions and try again.
200	TRF.0154	The account corresponding to the entered AK/SK does not have the permissions to access the source bucket or objects. Ensure that the account has the required permissions and try again.	The account corresponding to the entered AK/SK does not have the permissions to access the source bucket or objects.	Ensure that the account has the required permissions and try again.
200	TRF.0155	The source bucket does not exist (do not modify permissions to access the source bucket or objects during the migration). Ensure that the source bucket name is correct and try again.	The source bucket does not exist (do not modify permissions to access the source bucket or object during the migration).	Ensure that the source bucket name is correct and try again.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0156	The source objects do not exist (do not modify permissions to access the source bucket or objects during the migration). Ensure that the names of the source bucket and objects are correct and try again.	The source objects do not exist (do not modify permissions to access the source bucket or objects during the migration).	Ensure that the names of the destination bucket and objects are correct and try again.
200	TRF.0157	There is a problem with the source object storage service. Try again later or contact technical support.	There is a problem with the source object storage service.	Try again later or contact technical support.
200	TRF.0158	The migration task is completed, but the object data in the destination bucket is unencrypted. Check whether the region where the destination bucket is located supports KMS encryption.	The migration task is completed, but the object data in the destination bucket is unencrypted.	Check whether the region where the destination bucket is located supports KMS encryption.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0159	The task failed because the frequency of access to the source object storage exceeded the allowed limit. For details, see the returned error message or contact technical support.	The task failed because the frequency of access to the source object storage exceeded the allowed limit.	For details, see the returned error message or contact technical support.
200	TRF.0160	Failed to read archived data. Restore archived data and restart the task.	Failed to read archived data.	Restore archived data and restart the task.
200	TRF.0201	Failed to restore archived data. Restore archived data on the source server and restart the task.	Failed to restore archived data.	Restore archived data on the source server and restart the task.
200	TRF.0202	Failed to migrate the data because there is archived data that has not been restored. Restore archived data and restart the task.	Failed to migrate the data because there is archived data that has not been restored.	Restore archived data and restart the task.

Status Code	Error Code	Error Message	Description	Handling Measure
200	TRF.0301	The object list file cannot be read. Restore the object list file and restart the task.	The object list file cannot be read.	Restore the object list file and restart the task.
400	OMS.0001	Invalid parameter settings. Modify the request parameters.	Invalid parameter settings.	Modify the request parameters.
400	OMS.0002	Invalid parameter format. Modify the parameter format.	Invalid parameter format.	Modify the parameter format.
400	OMS.0004	Invalid HTTP request. Modify the parameter format.	Invalid HTTP request.	Modify the parameter format.
400	OMS.0005	The HTTP request method does not exist. Ensure that the request method is correct.	The HTTP request method does not exist.	Ensure that the request method is correct.
400	OMS.0051	Invalid value for parameter range. Enter a valid value for range.	Invalid value for parameter range.	Enter a valid value for range.
400	OMS.0052	Invalid value for parameter state. Enter a value from 0 to 5 (whole numbers only).	Invalid value for parameter state.	Enter a value from 0 to 5 (whole numbers only).

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0053	Task query failed due to invalid parameters or insufficient permissions. Check whether the parameters are correct and whether you have the required permissions.	Task query failed due to invalid parameters or insufficient permissions.	Check whether the parameters are correct and whether you have the required permissions.
400	OMS.0054	Invalid task ID. Enter a valid task ID.	Invalid task ID.	Enter a valid task ID.
400	OMS.0057	Invalid values for source parameters. Modify the source parameters.	Invalid values for source parameters.	Modify the source parameters.
400	OMS.0058	Invalid values for destination parameters. Modify the destination parameters.	Invalid values for destination parameters.	Modify the destination parameters.
400	OMS.0059	Invalid value for the number of threads specified for migration. Enter a value from 0 to 50 (whole numbers only).	Invalid value for the number of threads specified for migration.	Enter a value from 0 to 50 (whole numbers only).

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0060	Migration to the current region is not supported. For details, see the returned error message or contact technical support.	Migration to the current region is not supported.	For details, see the returned error message or contact technical support.
400	OMS.0061	Invalid format for task parameters. Modify the parameter format.	Invalid format for task parameters.	Modify the parameter format.
400	OMS.0062	Failed to save the task. For details, see the returned error message or contact technical support.	Failed to save the task.	For details, see the returned error message or contact technical support.
400	OMS.0063	The task is in progress. Pause the task and then delete it.	The task is in progress.	Pause the task and then delete it.
400	OMS.0064	Invalid request parameters. Enter valid parameter values.	Invalid request parameters.	Enter valid parameter values.
400	OMS.0065	The task has already started.	The task has already started.	None

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0066	Failed to pause the task. The task is not in progress. Check the task status.	Failed to pause the task. The task is not in progress.	Check the task status.
400	OMS.0067	The parameters are not in JSON format. Modify the parameter format.	The parameter is not in JSON format.	Modify the parameter format.
400	OMS.0068	Token authentication failed. For details, see the returned error message or contact technical support.	Authentication failed.	For details, see the returned error message or contact technical support.
400	OMS.0070	The task is complete. You cannot start or stop it.	The task is complete. You cannot start or stop it.	None
400	OMS.0072	You do not have the required permissions. For details, see the returned error message or contact technical support.	You do not have the required permissions.	For details, see the returned error message or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0073	Failed to delete the task. For details, see the returned error message or contact technical support.	Failed to delete the task.	For details, see the returned error message or contact technical support.
400	OMS.0074	The parameters must be the same as those in the OMS API Reference. Modify the parameter format by referring to OMS API Reference.	The parameters must be the same as those in the <i>OMS API Reference</i> .	Modify the parameter format by referring to <i>OMS API Reference</i> .
400	OMS.0077	The number of created migration tasks has exceeded the limit. Try again later or contact customer service.	The number of created migration tasks has exceeded the limit.	Try again later or contact technical support.
400	OMS.0078	The description cannot contain the following special characters: <>()"& Delete the special characters that are not allowed.	The description cannot contain the following special characters: <>()"&	Delete the special characters that are not allowed.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0079	Migration from the region where the source bucket is located is not supported. Modify the source bucket parameter.	Migration from the region where the source bucket is located is not supported.	Modify the source bucket parameter.
400	OMS.0080	Migration to the region where the selected destination bucket is located is not supported. Modify the destination bucket parameter.	Migration to the region where the selected destination bucket is located is not supported.	Modify the destination bucket parameter.
400	OMS.0081	Failed to pass the custom domain name check. Enter a valid custom domain name.	Failed to pass the custom domain name check.	Enter a valid custom domain name.
400	OMS.0083	The number of traffic limit rules exceeds the maximum. Change the number of traffic limit rules. Refer to OMS API Reference for details.	The number of traffic limit rules exceeds the maximum.	Change the number of traffic limit rules. Refer to OMS API Reference for details.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0084	The maximum traffic value is out of the range. Change the maximum traffic value. Refer to OMS API Reference for details.	The maximum traffic value is out of the range.	Change the maximum traffic value. Refer to OMS API Reference for details.
400	OMS.0085	The time segments are overlapped. Ensure that time segments do not overlap.	The time segments are overlapped.	Ensure that time segments do not overlap.
400	OMS.0086	Failed to update the bandwidth policy. Try again later or contact technical support.	Failed to update the bandwidth policy.	Try again later or contact technical support.
400	OMS.0087	Invalid values for time segments. Modify the time segments.	Invalid values for time segments.	Modify the time segments.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0089	The source objects do not exist (do not modify permissions to access the source bucket or objects during the migration). Ensure that the names of the source bucket and objects are correct and try again.	The source objects do not exist (do not modify permissions to access the source bucket or objects during the migration).	Ensure that the names of the destination bucket and objects are correct and try again.
400	OMS.0151	Invalid parameters. For details, see the returned error message or contact technical support.	Invalid parameters.	For details, see the returned error message or contact technical support.
400	OMS.0152	Failed to query regions. For details, see the returned error message or contact technical support.	Failed to query regions.	For details, see the returned error message or contact technical support.
400	OMS.0153	Failed to query the bucket information. For details, see the returned error message or contact technical support.	Failed to query the bucket information.	For details, see the returned error message or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0155	Failed to get the bucket region. For details, see the returned error message or contact technical support.	Failed to get bucket region.	For details, see the returned error message or contact technical support.
400	OMS.0156	Failed to send the notification using SMN. Internal SMN service errors. Try again later or contact customer service.	Failed to send the notification using SMN. Internal SMN service errors.	Try again later or contact technical support.
400	OMS.0157	Failed to send the notification using SMN. The SMN topic does not exist. For details, see the returned error message or contact technical support.	Failed to send the notification using SMN. The SMN topic does not exist.	For details, see the returned error message or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0158	Failed to send the notification using SMN. OMS has not been authorized to access the SMN topic. For details, see the returned error message or contact technical support.	Failed to send the notification using SMN. OMS has not been authorized to access the SMN topic.	For details, see the returned error message or contact technical support.
400	OMS.0159	System error. Failed to send the SMN notification. Try again later or contact customer service.	System busy. Failed to send the SMN notification.	Try again later or contact technical support.
400	OMS.0160	System busy. Failed to send the SMN notification. Try again later or contact customer service.	System busy. Failed to send the SMN notification.	Try again later or contact technical support.
400	OMS.0161	Network error. Failed to send the SMN notification. Try again later or contact customer service.	Network error. Failed to send the SMN notification.	Try again later or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0167	Failed to find the list of failed objects. For details, see the returned error message or contact technical support.	Failed to find the list of failed objects.	For details, see the returned error message or contact technical support.
400	OMS.0168	Failed to send the SMN notification. The selected topic is not in the same region as the current service. For details, see the returned error message or contact technical support.	Failed to send the SMN notification. The selected topic is not in the same region as the current service.	For details, see the returned error message or contact technical support.
400	OMS.0169	The SMN topic does not exist or you do not have the permissions needed to use the current topic. Select another topic or obtain the required permissions.	The SMN topic does not exist or you do not have the permissions needed to use the current topic.	Select another topic or obtain the required permissions.
400	OMS.0201	Your account has been restricted. Check your account balance or contact customer service.	Your account has been restricted.	Top up your account or contact customer service.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0202	Sorry, your account has been frozen. Contact customer service.	Sorry, your account has been frozen.	Contact customer service.
400	OMS.0203	Validate your personal information before continuing using OMS. For details, see the returned error message or contact technical support.	Validate your personal information before continuing using OMS.	For details, see the returned error message or contact technical support.
400	OMS.0204	Real-name authentication is required for this operation. Complete real-name authentication.	Real-name authentication is required for this operation.	Complete real-name authentication.
400	OMS.0302	Failed to list source objects. For details, see the returned error message or contact technical support.	Failed to list source objects.	For details, see the returned error message or contact technical support.
400	OMS.0303	Failed to record objects failed to be migrated. For details, see the returned error message or contact technical support.	Failed to record objects failed to be migrated.	For details, see the returned error message or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.0304	Failed to store the list of objects failed to be migrated. For details, see the returned error message or contact technical support.	Failed to store the list of objects failed to be migrated.	For details, see the returned error message or contact technical support.
400	OMS.0305	Object list file has reached the maximum allowed size. Check the size of the object list. Refer to OMS API Reference for details.	Object list file has reached the maximum allowed size.	Check the size of the object list. Refer to OMS API Reference for details.
400	OMS.0306	No source objects found. Ensure that there are objects in the source bucket.	No source objects found.	Ensure that there are objects in the source bucket.
400	OMS.0307	Failed to add the information about failed objects to the OBS bucket. For details, see the returned error message or contact technical support.	Failed to add the information about failed objects to the OBS bucket.	For details, see the returned error message or contact technical support.
400	OMS.0308	Incomplete list of failed objects. Contact technical support.	Incomplete list of failed objects.	Contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.1001	Internal service error. For details, see the returned error message or contact technical support.	Internal service error.	For details, see the returned error message or contact technical support.
400	OMS.1002	Invalid parameter type. Use a valid parameter type as described in OMS API Reference.	Invalid parameter type.	Use a valid parameter type as described in OMS API Reference.
400	OMS.1003	Incorrect parameter constraints. Modify the parameter constraints. Refer to OMS API Reference for details.	Incorrect parameter constraints.	Modify the parameter constraints. Refer to OMS API Reference for details.
400	OMS.1004	Some required parameters are missing. Ensure that all required parameters are included.	Some required parameters are missing.	Ensure that all required parameters are included.
400	OMS.1005	Authentication failed. For details, see the returned error message or contact technical support.	Authentication failed.	For details, see the returned error message or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.1006	The parameter is not in JSON format. Ensure that the parameter format is in JSON format.	The parameter is not in JSON format.	Ensure that the parameter format is in JSON format.
400	OMS.1007	Some required parameters are missing. Ensure that all required parameters are included.	Some required parameters are missing.	Ensure that all required parameters are included.
400	OMS.1008	Invalid request method. Use the request method described in OMS API Reference.	Invalid request method.	Use the request method described in OMS API Reference.
400	OMS.1009	No resources found. Ensure that the resources exist and resource parameters are correct.	No resources found.	Ensure that the resources exist and resource parameters are correct.
400	OMS.1010	Incorrect parameter type. Use the correct parameter type.	Incorrect parameter type.	Use the correct parameter type.
400	OMS.1011	No bucket ID found in the list. Ensure that bucket list contains bucket IDs.	No bucket ID found in the list.	Ensure that bucket list contains bucket IDs.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.1012	You can create a maximum of 50 evaluation tasks at a time. Try again later or contact technical support.	You can create a maximum of 50 evaluation tasks at a time.	Try again later or contact technical support.
400	OMS.1013	Invalid bucket ID. Enter a valid bucket ID.	Invalid bucket ID.	Enter a valid bucket ID.
400	OMS.1014	Failed to obtain source bucket details. Ensure that the AK and SK are correct and you have the permissions to access the bucket.	Failed to obtain source bucket details.	Ensure that the AK and SK are correct and you have the permissions to access the bucket.
400	OMS.1015	A maximum of 500 buckets can be evaluated per day. Try again later or contact technical support.	A maximum of 500 buckets can be evaluated per day.	Try again later or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.1016	Failed to obtain the source bucket details because the authentication failed or no bucket ID was found in the list. Ensure that the AK and SK are correct and you have the permissions to access the bucket.	Failed to obtain the source bucket details because the authentication failed or no bucket ID was found in the list.	Ensure that the AK and SK are correct and you have the permissions to access the bucket.
400	OMS.1017	A maximum of 50 buckets can be selected at a time. Try again later or contact technical support.	A maximum of 50 buckets can be selected at a time.	Try again later or contact technical support.
400	OMS.1018	Invalid source bucket. Check the source bucket parameter.	Invalid source bucket.	Check the source bucket parameter.
400	OMS.1019	You can create a migration task only after the source bucket evaluation succeeds. Try again later.	You can create a migration task only after the source bucket evaluation succeeds.	Try again later.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.1020	Failed to access the destination bucket. Ensure that the AK and SK are correct and you have the permissions to access the bucket.	Failed to access the destination bucket.	Ensure that the AK and SK are correct and you have the permissions to access the bucket.
400	OMS.1021	The number of created migration tasks exceeded the quota. Please try again in 24 hours.	The number of created migration tasks exceeded the quota.	Please try again in 24 hours.
400	OMS.1022	A migration task is being created for the source bucket. Select another bucket. If the error persists, contact technical support.	A migration task is being created for the source bucket. Select another bucket.	If the error persists, contact technical support.
400	OMS.1023	No bucket selected.	No bucket selected.	None
400	OMS.1026	Failed to create the migration task due a service error. For details, see the returned error message or contact technical support.	Failed to create the migration task due a service error.	For details, see the returned error message or contact technical support.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.1027	The failed objects record is empty. Select another one.	The failed objects record is empty. Select another one.	None
400	OMS.1028	A maximum of 50 tasks can be retried at a time.	A maximum of 50 tasks can be retried at a time.	None
400	OMS.1030	Invalid record status. For details, see the returned error message or contact technical support.	Invalid record status.	For details, see the returned error message or contact technical support.
400	OMS.1031	Failed to recreate the migration task because only the tasks under the same cloud service provider can be recreated. Select one cloud service provider during retry.	Failed to recreate the migration task because only the tasks under the same cloud service provider can be recreated.	Select one cloud service provider during retry.
400	OMS.1032	CDN authentication key required. Enter the correct CDN authentication key.	CDN authentication key required.	Enter the correct CDN authentication key.
400	OMS.1033	Only tasks in Evaluating state can be stopped. Check the task status.	Only tasks in Evaluating state can be stopped.	Check the task status.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.1035	Failed to upload the object list file. For details, see the returned error message or contact technical support.	Failed to upload the object list file.	For details, see the returned error message or contact technical support.
400	OMS.1036	Operations cannot be performed on task groups in current state. Check the task group status.	Operations cannot be performed on task groups in current state.	Check the task group status.
400	OMS.1037	The number of task group that can be create each day cannot exceed 100. Try again later or contact customer service.	A maximum of 100 task groups can be created per day.	Try again later or contact technical support.
400	OMS.1038	Only tasks in Executing state can be paused. Check the task status.	Only tasks in Executing state can be paused.	Check the task status.
400	OMS.1039	Only tasks in Paused state can be resumed. Check the task status.	Only tasks in Paused state can be resumed.	Check the task status.

Status Code	Error Code	Error Message	Description	Handling Measure
400	OMS.1040	Only tasks in Creation failed or Failed state can be restarted. Check the task status.	Only tasks in Creation failed or Failed state can be restarted.	Check the task status.
400	OMS.1041	Authentication failed because the migration task contains buckets that do not belong to the logged-in user account. Ensure that all selected buckets belong to the logged-in user.	Authentication failed because the migration task contains buckets that do not belong to the logged-in user account.	Ensure that all selected buckets belong to the logged-in user.
400	OMS.2002	The synchronization task is not found or not started.	The synchronization task is not found or not started.	None
400	TRF.0018	Failed to verify the task parameters. Ensure that the length of each line in the object list file does not exceed 65,535 characters.	Failed to verify the task parameters.	Ensure that the length of each line in the object list file does not exceed 65,535 characters.

Status Code	Error Code	Error Message	Description	Handling Measure
400	TRF.0019	Failed to verify the task parameters. Ensure that contentType in the metadata of the object list file is set to text/plain and contentEncoding is not set.	Failed to verify the task parameters.	Ensure that contentType in the metadata of the object list file is set to text/plain and contentEncoding is not set.
403	OMS.0205	Insufficient permission. Read-only users do not have the permissions to create, modify, or delete resources.	Read-only users do not have the permissions to create, modify, or delete resources.	Check the permission configuration.
403	OMS.0206	Insufficient permissions. You do not have the OMS operation permissions.	You do not have the OMS operation permissions.	Check the permission configuration.
503	OMS.2004	Service busy. Try again later.	Service busy.	Try again later.

7.3 Migration Failure Causes

Failure Cause Code	Failure Cause	Solution
TRF.0001	System error.	Click Restart to restart the migration task.
TRF.0003	Waiting for task execution timed out.	Click Restart to restart the migration task.
TRF.0012	Failed to verify the task parameters.	Ensure that there are objects for the selected migration method.

Failure Cause Code	Failure Cause	Solution
TRF.0013	Failed to verify the task parameters.	Ensure that the object list file exists, and the current AK and SK have read and write permissions for the file.
TRF.0014	Failed to verify the task parameters.	Ensure the object list file is a .txt file, and is no larger than 100 MB.
TRF.0015	The source AK and SK are invalid because the Azure storage account does not use Blob storage.	Enter a valid AK and SK.
TRF.0016	The format of the URL list file is incorrect.	Check the format of the URL list file by referring to SMS User Guide or contact technical support.
TRF.0017	No URL found in the specified list file.	Check the list file.
TRF.0018	Failed to verify the task parameters.	Ensure that the length of each line in the object list file does not exceed 65,535 characters.
TRF.0019	Failed to verify the task parameters.	Ensure that contentType in metaData of the object list file is set to text/plain and contentEncoding is not set.
TRF.0051	The entered AK or SK does not have the permissions required to access the destination bucket or objects.	Ensure that the AK and SK have the required permissions and try again.
TRF.0052	The entered AK or SK does not have the permissions required to access the destination bucket or objects.	Ensure that the AK and SK have the required permissions and try again.
TRF.0053	The migration operation cannot be completed because your OBS account is expired or frozen.	Contact customer service.

Failure Cause Code	Failure Cause	Solution
TRF.0054	The entered AK or SK does not have the permissions required to access the destination bucket or objects.	Ensure that the AK and SK have the required permissions and try again.
TRF.0055	The target OBS bucket does not have enough space.	Ensure that the target bucket has enough space and try again.
TRF.0056	Your OBS account is frozen.	Try again after your account is unfrozen.
TRF.0057	Invalid AK or SK.	Enter the correct AK and SK and try again.
TRF.0058	The destination OBS bucket does not exist (do not modify permissions to access the destination bucket or object during the migration).	Ensure that the source bucket name is correct and try again.
TRF.0059	The destination objects do not exist (do not modify permissions to access the destination bucket or object during the migration).	Ensure that names of the destination bucket and objects are correct and try again.
TRF.0060	The path for storing the migrated objects is too long.	Change the object names or the path for storing them.
TRF.0061	There is a problem with the destination object storage service.	Try again later or contact technical support.
TRF.0062	Some objects fail to be migrated.	Ensure that there are no tasks to migrate those objects and try again later.
TRF.0063	The migration task failed. Data cannot be migrated to the destination OBS bucket because your account balance is insufficient.	Top up your account or contact customer service.
TRF.0151	The source AK or SK is invalid.	Enter the correct AK and SK and try again.
TRF.0152	The entered AK/SK does not have the permissions required to access the source bucket or object.	Ensure that the AK and SK have the required permissions and try again.

Failure Cause Code	Failure Cause	Solution
TRF.0153	The entered AK/SK does not have the permissions required to access the source bucket or object.	Ensure that the AK and SK have the required permissions and try again.
TRF.0154	The entered AK/SK does not have the permissions required to access the source bucket or object.	Ensure that the AK and SK have the required permissions and try again.
TRF.0155	The source bucket does not exist (do not modify permissions to access the source bucket or the source objects during the migration).	Ensure that the source bucket name is correct and try again.
TRF.0156	The source objects do not exist (do not modify permissions to access the source bucket or the source objects during the migration).	Ensure that names of the destination bucket and objects are correct and try again.
TRF.0157	There is a problem with the source object storage service.	Try again later or contact technical support.
TRF.0158	The migration task is completed, but the object data in the destination bucket is unencrypted.	Check whether the region where the destination bucket is located supports KMS encryption.
TRF.0159	The task failed because the frequency of access to the source object storage exceeded the allowed limit.	For details, see the returned error message or contact technical support.
TRF.0160	Failed to read archived data.	Restore archived data and restart the task.
TRF.0201	Failed to restore archived data.	Restore archived data on the source server and restart the task.
TRF.0202	Failed to migrate the data because there is archived data that has not been restored.	Restore archived data and restart the task.
TRF.0301	The object list file cannot be obtained.	Restore the object list file and restart the task.

7.4 Obtaining a Project ID

Scenarios

A project ID is required for some URLs when an API is called. Therefore, you need to obtain a project ID in advance. Two methods are available:

- [Obtain the Project ID by Calling an API](#)
- [Obtain the Project ID from the Console](#)

Obtain the Project ID by Calling an API

You can obtain the project ID by calling the API used to [query projects based on specified criteria](#).

The API used to obtain a project ID is GET <https://{{Endpoint}}/v3/projects>. {{Endpoint}} is the IAM endpoint and can be obtained from Regions and Endpoints. For details about API authentication, see [Authentication](#).

The following is an example response. The value of **id** is the project ID.

```
{  
    "projects": [  
        {  
            "domain_id": "65382450e8f64ac0870cd180d14e684b",  
            "is_domain": false,  
            "parent_id": "65382450e8f64ac0870cd180d14e684b",  
            "name": "project_name",  
            "description": "",  
            "links": {  
                "next": null,  
                "previous": null,  
                "self": "https://www.example.com/v3/projects/a4a5d4098fb4474fa22cd05f897d6b99"  
            },  
            "id": "a4a5d4098fb4474fa22cd05f897d6b99",  
            "enabled": true  
        }  
    ],  
    "links": {  
        "next": null,  
        "previous": null,  
        "self": "https://www.example.com/v3/projects"  
    }  
}
```

Obtain a Project ID from the Console

To obtain a project ID from the console, perform the following operations:

1. Log in to the management console.
2. Click the username and select **My Credentials** from the drop-down list.
On the **API Credentials** page, view the project ID in the project list.

Figure 7-1 Viewing the project ID

The screenshot shows the 'API Credentials' page in a web interface. On the left, there's a sidebar with 'My Credentials' (selected), 'API Credentials' (selected), and 'Access Keys'. The main area is titled 'API Credentials' with a help icon. It includes sections for 'Learn more about HUAWEI CLOUD accounts, IAM users, and projects.', 'IAM User Name' (redacted), 'Account Name' (redacted), 'IAM User ID' (redacted), and 'Account ID' (redacted). Below this is a 'Projects' section with a search bar 'Enter a project name.' and a magnifying glass icon. A table lists projects with columns: 'Project ID' (highlighted with a red border), 'Project Name', and 'Region'. There are two rows of data, each with a '+' button to the left.

Project ID	Project Name	Region
[Redacted]	[Redacted]	[Redacted]
[Redacted]	[Redacted]	[Redacted]