MapReduce Service

FAQs

Issue 01

Date 2023-10-19





Copyright © Huawei Cloud Computing Technologies Co., Ltd. 2023. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Cloud Computing Technologies Co., Ltd.

Trademarks and Permissions

HUAWEI and other Huawei trademarks are the property of Huawei Technologies Co., Ltd. All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei Cloud and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, quarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Contents

1 MRS Overview	1
1.1 What Is MRS Used For?	1
1.2 What Types of Distributed Storage Does MRS Support?	1
1.3 What Are Regions and AZs?	2
1.4 Can I Change the Network Segment of Nodes in an MRS Cluster?	3
1.5 Can I Downgrade the Specifications of an MRS Cluster Node?	4
1.6 Does an MRS Cluster Support Hive on Spark?	4
1.7 Are Hive Components of Different Versions Compatible with Each Other?	4
1.8 What Are the Differences Between OBS and HDFS in Data Storage?	4
1.9 How Do I Obtain the Hadoop Pressure Test Tool?	5
1.10 Statement About the Public IP Addresses in the Open-Source Third-Party SDK Integrated by MRS.	5
1.11 Does MRS Support Running Hive on Kudu?	5
1.12 What Are the Solutions for Processing 1 Billion Data Records?	
1.13 Can I Change the IP address of DBService?	6
1.14 Can Sudo Logs of Nodes in an MRS Cluster Be Cleared?	6
1.15 What Are the Restrictions on the Storm Log Size in an MRS 2.1.0 Cluster?	7
1.16 What Access Protocols Does Kafka Support?	7
1.17 What Should I Do If Error 408 Is Reported When an MRS Node Accesses OBS?	7
1.18 What are the advantages of the compression ratio of zstd?	8
1.19 Which Python Versions Are Supported by Spark Tasks in MRS 3.1.0 Clusters?	
1.20 How Do I Enable Different Service Programs to Use Different Yarn Queues?	8
1.21 What Are the Differences and Relationships Between the MRS Management Console and MRS	
Manager?	
1.22 How Do I Unbind an EIP from FusionInsight Manager of an MRS Cluster?	
1.23 What are the Operating Systems of Hosts in MRS Clusters of Different Versions?	14
2 Billing	16
2.1 Why Is the Price Not Displayed During MRS Cluster Creation?	16
2.2 How Is Auto Scaling Billed for an MRS Cluster?	
2.3 How Are Task Nodes in an MRS Cluster Billed?	
2.4 Why Does My Unsubscription from ECS Fail After I Unsubscribe from MRS?	. 17
3 Cluster Creation	.18
3.1 How Do I Create an MRS Cluster Using a Custom Security Group?	18

3.2 What Should I Do If HDFS, Yarn, and MapReduce Components Are Unavailable When I Buy an MF Cluster?	≀S 18
3.3 What Should I Do If the ZooKeeper Component Is Unavailable When I Buy an MRS Cluster?	
3.4 What Should I Do If Invalid Authentication Is Reported When I Submit an Order for Purchasing an MRS Cluster?	1
4 Account and Password	. 20
4.1 What Is the User for Logging in to FusionInsight Manager?	
4.2 How Do I Query and Change the Password Validity Period of a User In a Cluster?	
5 Account and Permission	22
5.1 Does an MRS Cluster Support Access Permission Control If Kerberos Authentication Is not Enabled	l?
5.2 How Do I Add Tenant Management Permission to Users in a Cluster?	22
5.3 Why Cannot I Find the User Management Page on MRS Manager?	23
5.4 Does Hue Provide the Function of Configuring Account Permissions?	23
5.5 Why Can't I Submit Jobs on the Console After My IAM Account Is Assigned with MRS Permissions?	
6 Client Usage	25
6.1 How Do I Disable SASL Authentication for ZooKeeper?	
6.2 What Can I Do If the Error Message "Permission denied" Is Displayed When kinit Is Executed on a Client Outside the MRS Cluster?	
7 Web Page Access	. 27
7.1 How Do I Change the Session Timeout Duration for an Open Source Component Web UI?	
7.2 What Can I Do If the Dynamic Resource Plan Page in MRS Tenant Management Cannot Be Refreshed?	30
7.3 What Do I Do If the Kafka Topic Monitoring Tab Is Not Displayed on Manager?	30
7.4 What CAN I DO IF an Error Is Reported or Some Functions Are Unavailable When I Access the We UIs of Components such as HDFS, Hue, Yarn, Flink, and HetuEngine?	
7.5 How Do I Switch the Methods to Access MRS Manager?	32
8 Alarm Monitoring	33
8.1 In an MRS Streaming Cluster, Can the Kafka Topic Monitoring Function Send Alarm Notifications?	
8.2 Where can I view the running resource queues when ALM-18022 Insufficient Yarn Queue Resource	es is
8.3 How Do I Understand the Multi-Level Chart Statistics in the HBase Operation Requests Metric?	34
9 Performance Tuning	. 36
9.1 Does an MRS Cluster Support System Reinstallation?	
9.2 Can I Change the OS of an MRS Cluster?	
9.3 How Do I Improve the Resource Utilization of Core Nodes in a Cluster?	36
9.4 How Do I Stop the Firewall Service?	37
10 Job Development	38
10.1 How Do l Get My Data into OBS or HDFS?	
10.2 What Types of Spark Jobs Can Be Submitted in a Cluster?	39

10.3 Can I Run Multiple Spark Tasks at the Same Time After the Minimum Tenant Resources of an MR Cluster Is Changed to 0?	
10.4 What Should I Do If Job Parameters Separated By Spaces Cannot Be Identified?	
10.5 What Are the Differences Between the Client Mode and Cluster Mode of Spark Jobs?	
10.6 How Do I View MRS Job Logs?	
10.7 What Can I Do If the System Displays a Message Indicating that the Current User Does Not Exist Manager When I Submit a Job?	on
10.8 What Can I Do If LauncherJob Fails to Be Executed and the Error Message "jobPropertiesMap is n s Displayed?	ull"
10.9 What Should I Do If the Flink Job Status on the MRS Console Is Inconsistent with That on Yarn?	
10.10 What Can I Do If a SparkStreaming Job Fails After Running for Dozens of Hours and Error 403 Is Reported for OBS Access?	
10.11 What Should I Do If an Alarm Is Reported Indicating that the Memory Is Insufficient When I Execute a SQL Statement on the ClickHouse Client?	43
10.12 What Should I Do If Error Message "java.io.IOException: Connection reset by peer" Is Displayed During the Execution of a Spark Job?	43
10.13 What Should I Do If the Error Message "requestId=XXX" Is Displayed When a Spark Job Accesses	
10.14 What Should I Do If the Error Message "UnknownScannerExeception" Is Displayed for Spark Job	
10.15 What Can I Do If DataArts Studio Occasionally Fails to Schedule Spark Jobs?	
10.16 What Should I Do If a Flink Job Fails to Execute and the Error Message "java.lang.NoSuchFieldEr SECURITY_SSL_ENCRYPT_ENABLED" Is Displayed?	ror
10.17 What Should I Do If Submitted Yarn Jobs Cannot Be Viewed on the Web UI?	45
10.18 How Do I Modify the HDFS fs.defaultFS of an Existing Cluster?	
10.19 What Can I Do If launcher-job Is Terminated by Yarn When a Flink Task Is Submitted?	
10.20 What Should I Do If the Error Message "slot request timeout" Is Displayed When I Submit a Flin	
10.21 FAQs About Importing and Exporting Data Using DistCP Jobs	47
10.22 How Do I View SQL Statements of Hive Jobs on the Yarn Web UI?	
10.23 How Do I View Logs of a Specified Yarn Task?	48
11 Cluster Upgrade/Patching	40
11.1 How Do I Upgrade an MRS Cluster?	
11.2 Does MRS Support Kernel Version Upgrade of Components in a Cluster?	
12 Peripheral Ecosystem Interconnection	
12.1 Does MRS Support Read and Write Operations on DLI Service Tables?	
12.2 Does OBS Support the ListObjectsV2 Protocol?	
12.3 Can a Crawler Service Be Deployed on Nodes in an MRS Cluster?	
12.4 Does MRS Support Secure Deletion?	
12.5 How Do I Use PySpark to Connect MRS Spark?	
12.6 Why Mapped Fields Do not Exist in the Database After HBase Synchronizes Data to CSS?	
12.7 Can MRS Connect to an External KDC?	51
12.8 What Can I Do If Jetty Is Incompatible with MRS when Open-Source Kylin 3.x Is Interconnected w	
MRS 1.9.3?	51

12.9 What Should I Do If Data Failed to Be Exported from MRS to an OBS Encrypted Bucket?	52
12.10 How Do I Interconnect MRS with LTS?	52
12.11 How Do I Install HSS on MRS Cluster Nodes?	54
13 Cluster Access	.56
13.1 How Do I Switch the Login Mode of a Node in an MRS Cluster?	56
13.2 How Can I Obtain the IP Address and Port Number of a ZooKeeper Instance?	
13.3 How Do I Access an MRS Cluster from a Node Outside the Cluster?	
14 Big Data Service Development	. 60
14.1 Can MRS Run Multiple Flume Tasks at a Time?	
14.2 How Do I Change FlumeClient Logs to Standard Logs?	
14.3 Where Are the JAR Files and Environment Variables of Hadoop Stored?	
14.4 What Compression Algorithms Does HBase Support?	
14.5 Can MRS Write Data to HBase Through an HBase External Table of Hive?	
14.6 How Do I View HBase Logs?	
14.7 How Do I Set the TTL for an HBase Table?	61
14.8 How Do I Connect to HBase of MRS Through HappyBase?	
14.9 How Do I Change the Number of HDFS Replicas?	
14.10 How Do I Modify the HDFS Active/Standby Switchover Class?	
14.11 What Data Type in Hive Tables Is Recommended for the Number Type of DynamoDB?	
14.12 Can the Hive Driver Be Interconnected with DBCP2?	
14.13 How Do I View the Hive Table Created by Another User?	
14.14 Where Can I Download the Dependency Package (com.huawei.gaussc10) in the Hive Sample Project?	65
14.15 Can I Export the Query Result of Hive Data?	65
14.16 What Should I Do If an Error Occurs When Hive Runs the beeline -e Command to Execute Mult Statements?	iple
14.17 What Should I Do If a HiveSQL/HiveScript Job Fails to be Submitted After Hive Is Added?	66
14.18 What Can I Do If the Excel File Downloaded by Hue Cannot Be Opened?	66
14.19 How Do I Do If Sessions Are Not Released After Hue Connects to HiveServer and the Error Mess "over max user connections" Is Displayed?	
14.20 How Do I Reset Kafka Data?	
14.21 What Access Protocols Are Supported by Kafka?	
14.22 What Should I Do If the Error Message "Not Authorized to access group XXX" Is Displayed Whei	n
14.23 What Compression Algorithms Does Kudu Support?	69
14.24 How Do I View Kudu Logs?	
14.25 How Do I Handle the Kudu Service Exceptions Generated During Cluster Creation?	
14.26 Does MRS Support Python Code?	
14.27 Does OpenTSDB Support Python APIs?	
14.28 How Do I Configure Other Data Sources on Presto?	
14.29 How Do I Update the Ranger Certificate in MRS 1.9.3?	
14.30 How Do I Connect to Spark Shell from MRS?	
14.31 How Do I Connect to Spark Beeline from MRS?	75

14.32 Where Are the Execution Logs of Spark Jobs Stored?	76
14.33 How Do I Specify a Log Path When Submitting a Task in an MRS Storm Cluster?	76
14.34 How Do I Check the ResourceManager Configuration of Yarn?	
14.35 How Do I Modify the allow_drop_detached Parameter of ClickHouse?	79
14.36 What Should I Do If an Alarm Indicating Insufficient Memory Is Reported During Spark Task Execution?	80
14.37 How Do I Add a Periodic Deletion Policy to Prevent Large ClickHouse System Table Logs?	80
14.38 How Do I Obtain a Spark JAR File?	81
14.39 What Can I Do If an Alarm is Generated Because the NameNode Is not Restarted on Time Afte hdfs-site.xml File Is Modified?	
14.40 What Should I Do If It Takes a Long Time for Spark SQL to Access Hive Partitioned Tables Befor	
14.41 What Should I Do If the spark.yarn.executor.memoryOverhead Setting Does Not Take Effect?	82
14.42 How Do I Change the Time Zone of the ClickHouse Service?	83
14.43 What Should I Do If the Connection to the ClickHouse Server Fails and Error Code 516 Is Repor	
15 API	85
15.1 How Do I Configure the node_id Parameter When Calling the API for Adjusting Cluster Nodes?	85
16 Cluster Management	86
16.1 How Do I View All Clusters?	86
16.2 How Do I View MRS Operation Logs?	86
16.3 How Do I View MRS Cluster Configuration Information?	87
16.4 How Do I Add Components to an MRS Cluster?	87
16.5 Do I Need to Shut Down a Master Node Before Upgrading It?	87
16.6 Can I Delete Components Installed in an MRS Cluster?	88
16.7 Can I Change MRS Cluster Nodes on the MRS Console?	88
16.8 How Do I Cancel Message Notification for Cluster Alarms?	88
16.9 Why Is the Resource Pool Memory Displayed in the MRS Cluster Smaller Than the Actual Cluster Memory?	
16.10 How Do I Configure the knox Memory?	
16.11 What Is the Python Version Installed for an MRS Cluster?	
16.12 How Do I View the Configuration File Directory of Each Component?	
16.13 How Do I Upload a Local File to a Node Inside a Cluster?	
16.14 What Can I Do If the Time Information of an MRS Cluster Node Is Incorrect?	
16.15 How Do I Query the Startup Time of an MRS Node?	
16.16 How Do I Do If Trust Relationships Between Nodes Are Abnormal?	
16.17 How Do I Adjust the Memory Size of the manager-executor Process?	
16.18 Can Master Node Specifications Be Adjusted in an MRS Cluster?	
17 Kerberos Usage	95
17.1 How Do I Enable or Disable Kerberos Authentication for an Existing MRS Cluster?	
17.2 What Are the Ports of the Kerberos Authentication Service?	
17.3 How Do I Prevent Kerberos Authentication Expiration?	

18 Metadata Management	97
18.1 How Do I View MRS Hive Metadata?	97

MRS Overview

1.1 What Is MRS Used For?

Question:

What Can MapReduce Service (MRS) Do?

Answer:

MapReduce Service (MRS) is an enterprise-grade big data platform that allows you to quickly build and operate economical, secure, full-stack, cloud-native big data environments on the cloud. It provides engines such as ClickHouse, Spark, Flink, Kafka, and HBase, and supports convergence of data lake, data warehouse, business intelligence (BI), and artificial intelligence (AI). Fully compatible with open-source components, MRS helps you rapidly innovate and expand service growth.

1.2 What Types of Distributed Storage Does MRS Support?

Question:

What Types of Distributed Storage Do MRS Clusters Support? What Versions Are Available?

Answer:

The MRS clusters use the mainstream big data component Hadoop. Currently, Hadoop 3.x is supported and will be updated as the cluster evolves.

MRS allows you to store data in OBS and use an MRS cluster for data computing only. In this way, storage and compute are decoupled.

For details about the components supported by each MRS version, see **List of MRS Component Versions**.

1.3 What Are Regions and AZs?

A region and an availability zone (AZ) identify the location of a data center. You can create resources in a specific AZ of a region.

- Regions are defined in terms of geographical locations and network latencies. Public services such as Elastic Cloud Server (ECS), Elastic Volume Service (EVS), Object Storage Service (OBS), Virtual Private Cloud (VPC), Elastic IP (EIP), and Image Management Service (IMS) are shared within the same region. Regions are classified into common regions and dedicated regions. A common region provides common cloud services available to all tenants. A dedicated region provides services of a specific type or only for specific tenants.
- An AZ contains one or more physical data centers. Each AZ has independent cooling, fire extinguishing, moisture-proof, and electricity facilities. The computing, network, storage, and other resources in an AZ are logically divided into multiple clusters. AZs within a region are interconnected using high-speed optical fibers to allow you to build cross-AZ high-availability systems.

Figure 1-1 shows the relationship between regions and AZs.




Figure 1-1 Regions and AZs

HUAWEI CLOUD provides services worldwide. You can select a region and AZ as required. For more information, see **HUAWEI CLOUD Global Regions**.

What Are the Considerations for Selecting a Region?

When selecting a region, consider the following factors:

Location

You are advised to select a region closest to your target users. This reduces network latency and improves access rate. However, there is no distinct difference between the infrastructure, BGP network quality, and resource operations and configurations in the same region/country. Therefore, you do not need to consider the network latency when selecting a region in a country.

- If you or your target users are in the Asia Pacific area excluding the Chinese mainland, select the CN-Hong Kong, AP-Bangkok, or AP-Singapore region.
- If you or your target users are in Africa, select the AF-Johannesburg region.
- If you or your target users are in Europe, select the **EU-Paris** region.
- Resource price

Resource prices may vary in different regions. For details, see **Product Pricing Details**.

What Are the Considerations for Selecting an AZ?

Consider the requirements for disaster recovery (DR) and network latency when selecting an AZ:

- Deploy resources in different AZs in the same region for DR purposes.
- Deploy resources in the same AZ for minimum latency.

How Do I Obtain an Endpoint?

When you use resources by using an API, you must specify its regional endpoint. For details about Huawei Cloud regions and endpoints, see **Regions and Endpoints**.

1.4 Can I Change the Network Segment of Nodes in an MRS Cluster?

Question:

Can I Change the Network Segment of Nodes in an MRS Cluster?

Answer:

Yes, you can. Perform the following steps to change the network segment of nodes in a cluster:

- 1. On the **Dashboard** page of the cluster, locate the **Network Information** pane, and click **Change Subnet** on the right of subnet name.
- 2. Select another subnet in the VPC to which the current cluster belongs to expand the available subnet IP addresses.
 - Selecting a new subnet will not change the IP addresses and subnets of existing nodes.

1.5 Can I Downgrade the Specifications of an MRS Cluster Node?

Question:

Can I Downgrade the Specifications of an MRS Cluster Node?

Answer:

Currently, the configuration specifications of nodes in an MRS cluster cannot be downgraded.

1.6 Does an MRS Cluster Support Hive on Spark?

Question:

Does an MRS Cluster Support Hive on Spark?

Answer:

- Clusters of MRS 1.9.*x* support Hive on Spark.
- Clusters of MRS 3.x or later support Hive on Spark.
- You can use Hive on Tez for the clusters of other versions.

1.7 Are Hive Components of Different Versions Compatible with Each Other?

Hive 3.1 is incompatible with Hive 1.2 in the following items:

- Strings cannot be converted to int.
- The user-defined functions (UDFs) of the **Date** type are changed to Hive built-in UDFs.
- Hive 3.1 does not provide the index function anymore.
- Hive 3.1 uses the UTC time in time functions, while Hive 1.2 uses the local time zone.
- The JDBC drivers in Hive 3.1 and Hive 1.2 are incompatible.
- In Hive 3.1, column names in ORC files are case-sensitive and underscoressensitive.
- Hive 3.1 does not allow columns named time.

1.8 What Are the Differences Between OBS and HDFS in Data Storage?

The data processed by MRS is from OBS or HDFS. OBS is an object-based storage service that provides secure, reliable, and cost-effective storage of huge amounts

of data. MRS can directly process data in OBS. You can view, manage, and use data by using the OBS console or OBS client. In addition, you can use REST APIs independently or integrate APIs to service applications to manage and access data.

- Data stored in OBS: Data storage is decoupled from compute. The cluster storage cost is low, and storage capacity is not limited. Clusters can be deleted at any time. However, the computing performance depends on the OBS access performance and is lower than that of HDFS. OBS is recommended for applications that do not demand a lot of computation.
- Data stored in HDFS: Data storage is not decoupled from compute. The cluster storage cost is high, and storage capacity is limited. The computing performance is high. You must export data before you delete clusters. HDFS is recommended for computing-intensive scenarios.

1.9 How Do I Obtain the Hadoop Pressure Test Tool?

Question:

How Do I Obtain the Hadoop Pressure Test Tool?

Answer:

Obtain the Hadoop pressure test tool from the community at https://github.com/ Intel-bigdata/HiBench.

1.10 Statement About the Public IP Addresses in the Open-Source Third-Party SDK Integrated by MRS

Question:

What Is the Public IP Address Statement Contained in the Open-Source Third-Party SDK Integrated with MRS?

Answer:

The open-source third-party packages on which the open-source components integrated by MRS depend contain SDK usage examples. Public IP addresses such as 12.1.2.3, 54.123.4.56, 203.0.113.0, and 203.0.113.12 are example IP addresses. MRS will not initiate a connection to the public IP address or exchange data with the public IP address.

1.11 Does MRS Support Running Hive on Kudu?

Question:

Does MRS Support Running Hive on Kudu?

Answer:

MRS does not support Hive on Kudu.

Currently, MRS supports only the following two methods to access Kudu:

- Access Kudu through Impala tables.
- Access and operate Kudu tables using the client application.

1.12 What Are the Solutions for Processing 1 Billion Data Records?

Question:

What Are the Solutions for processing 1 Billion Data Records?

Answer:

- GaussDB (for MySQL) is recommended for scenarios, such as data updates, online transaction processing (OLTP), and complex analysis of 1 billion data records.
- Impala and Kudu in MRS also meet this requirement. Impala and Kudu can load all join tables to the memory in the join operation.

1.13 Can I Change the IP address of DBService?

Question:

Can I Change the IP address of DBService?

Answer:

The IP address of DBService cannot be changed in the MRS cluster.

1.14 Can Sudo Logs of Nodes in an MRS Cluster Be Cleared?

Question:

Can Sudo Logs of Nodes in an MRS Cluster Be Cleared?

Answer:

The sudo log file on the nodes in the MRS cluster records the operations performed by user **omm** to facilitate fault locating. You can clear the file as you need.

You can delete the logs in earlier days to release storage space.

- 1. If the log file is large, add the log file directory to /etc/logrotate.d/syslog to enable periodical deletion.
 - Run sed -i '3 a/var/log/sudo/sudo.log' /etc/logrotate.d/syslog.
- 2. Set the maximum number and size of logs in /etc/logrotate.d/syslog. If the threshold is exceeded, the logs will be automatically deleted. By default, logs are aged based on the size and number of archived logs. You can use size and rotate to limit the size and number of archived logs, respectively. If required, you can also add daily/weekly/monthly to specify how often the logs are cleared.

1.15 What Are the Restrictions on the Storm Log Size in an MRS 2.1.0 Cluster?

Question:

What Are the Restrictions on the Storm Log Size in an MRS 2.1.0 Cluster?

Answer:

In MRS 2.1.0, the size of Storm logs cannot exceed 20 GB. If the size of Storm logs exceeds 20 GB, the logs will be deleted cyclically.

Logs are stored on the system disk, and the space is limited. If logs need to be stored for a long time, mount the logs.

1.16 What Access Protocols Does Kafka Support?

Question:

What Access Protocols Does Kafka Support?

Answer:

Kafka supports the following access protocols: PLAINTEXT, SSL, SASL_PLAINTEXT, and SASL_SSL.

1.17 What Should I Do If Error 408 Is Reported When an MRS Node Accesses OBS?

Question:

What Should I Do If Error 408 Is Reported When an MRS Node Accesses OBS?

Answer:

If error 408 is reported when an MRS node accesses OBS, you need to change the OBS domain name.

Change the OBS domain name to the domain name suffixed with myhuaweicloud.com.

1.18 What are the advantages of the compression ratio of zstd?

Question:

What are the advantages of the compression ratio of zstd?

Answer:

The compression ratio of zstd is twice that of orc. zstd is open-source.

For details, see https://github.com/L-Angel/compress-demo.

CarbonData does not support lzo. MRS integrates zstd.

1.19 Which Python Versions Are Supported by Spark Tasks in MRS 3.1.0 Clusters?

Question:

Which Python Versions Are Supported by Spark Tasks in MRS 3.1.0 Clusters?

Answer:

For MRS 3.1.0 clusters, Python 2.7 or 3.x is recommended for Spark tasks.

1.20 How Do I Enable Different Service Programs to Use Different Yarn Queues?

Question:

How Do I Enable Different Service Programs to Use Different Yarn Queues?

Answer:

Create a tenant on FusionInsight Manager and bind different cluster service users to different tenants.

For details, see Adding a Sub-Tenant.

Procedure

- **Step 1** Log in to FusionInsight Manager and choose **Tenant Resources**.
- **Step 2** In the tenant list on the left, select a parent tenant and click **①**. On the page for adding a sub-tenant, set attributes for the sub-tenant according to **Table 1-1**.

Table 1-1 Sub-tenant parameters

Parameter	Description	
Cluster	Indicates the cluster to which the parent tenant belongs.	
Parent Tenant Resource	Indicates the name of the parent tenant.	
Name	 Indicates the name of the current tenant. The value consists of 3 to 50 characters, including digits, letters, and underscores (_). Plan a sub-tenant name based on service requirements. The name cannot be the same as that of a role, HDFS directory, or Yarn queue that 	
	exists in the current cluster.	
Tenant Type	Specifies whether the tenant is a leaf tenant.	
	When Leaf Tenant is selected, the current tenant is a leaf tenant and no sub-tenant can be added.	
	When Non-leaf Tenant is selected, the current tenant is not a leaf tenant and sub-tenants can be added to the current tenant. However, the tenant depth cannot exceed 5 levels.	
Computing Resource	Specifies the dynamic computing resources for the current tenant.	
	When Yarn is selected, the system automatically creates a queue in Yarn and the queue is named the same as the sub-tenant name.	
	 A leaf tenant can directly submit jobs to the queue. 	
	 A non-leaf tenant cannot directly submit jobs to the queue. However, Yarn adds an extra queue (hidden) named default for the non-leaf tenant to record the remaining resource capacity of the tenant. Actual jobs do not run in this queue. 	
	If Yarn is not selected, the system does not automatically create a queue.	
Default Resource Pool Capacity (%)	Indicates the percentage of computing resources used by the current tenant. The base value is the total resources of the parent tenant.	
Default Resource Pool Max Capacity (%)	Indicates the maximum percentage of computing resources used by the current tenant. The base value is the total resources of the parent tenant.	

Parameter	Description		
Storage Resource	 Specifies storage resources for the current tenant. When HDFS is selected, the system automatically creates a folder named after the sub-tenant in the HDFS parent tenant directory. When HDFS is not selected, the system does not automatically allocate storage resources. 		
Quota	Indicates the quota for files and directories.		
Space Quota	 Indicates the quota for the HDFS storage space used by the current tenant. If the unit is set to MB, the value ranges from 1 to 8796093022208. If the unit is set to GB, the value ranges from 1 to 8589934592. This parameter indicates the maximum HDFS storage space that can be used by the tenant, but not the actual space used. If its value is greater than the size of the HDFS physical disk, the maximum space available is the full space of the HDFS physical disk. If this quota is greater than the quota of the parent tenant, the actual storage space does not exceed the quota of the parent tenant. 		
Storage Path	 Indicates the HDFS storage directory for the tenant. The system automatically creates a folder named after the sub-tenant name in the directory of the parent tenant by default. For example, if the sub-tenant is ta1s and the parent directory is /tenant/ta1, the storage path for the sub-tenant is then /tenant/ta1/ta1s. The storage path is customizable in the parent directory. 		
Description	Indicates the description of the current tenant.		

Roles, computing resources, and storage resources are automatically created when tenants are created.

- The new role has permissions on the computing and storage resources. This role and its
 permissions are automatically controlled by the system and cannot be manually managed by
 choosing System > Permission > Role. The role name is in the format of Tenant
 name_Cluster ID. The ID of the first cluster is not displayed by default.
- When using this tenant, create a system user and bind the user to the role of the tenant. For details, see Adding a User and Binding the User to a Tenant Role.
- The sub-tenant can further allocate the resources of its parent tenant. The sum of the resource percentages of direct sub-tenants under a parent tenant at each level cannot exceed 100%. The sum of the computing resource percentages of all level-1 tenants cannot exceed 100%.
- **Step 3** Check whether the current tenant needs to be associated with resources of other services.
 - If yes, go to Step 4.
 - If no, go to Step 5.
- **Step 4** Click **Associate Service** to configure other service resources used by the current tenant.
 - 1. Set **Services** to **HBase**.
 - 2. Set **Association Type** as follows:
 - Exclusive indicates that the service resources are used by the tenant exclusively and cannot be associated with other tenants.
 - Shared indicates that the service resources can be shared with other tenants.

■ NOTE

- Only HBase can be associated with a new tenant. However, HDFS, HBase, and Yarn can be associated with existing tenants.
- To associate an existing tenant with service resources, click the target tenant in the tenant list, switch to the **Service Associations** page, and click **Associate Service** to configure resources to be associated with the tenant.
- To disassociate an existing tenant from service resources, click the target tenant in the tenant list, switch to the Service Associations page, and click Delete in the Operation column. In the displayed dialog box, select I have read the information and understand the impact and click OK.
- 3. Click OK.
- **Step 5** Click **OK**. Wait until the system displays a message indicating that the tenant is successfully created.

----End

1.21 What Are the Differences and Relationships Between the MRS Management Console and MRS Manager?

Question:

What Are the Differences and Relationships Between the MRS Management Console and MRS Manager?

Answer:

You can access Manager from the MRS management console.

Manager is classified as MRS Manager and FusionInsight Manager.

- MRS Manager is the manager page of MRS 2.x or earlier clusters.
- FusionInsight Manager is the manager page of MRS 3.x or later clusters. The following table lists the differences and relationships between the management console and FusionInsight Manager.

Common Operation	MRS Console	FusionInsight Manager
Changing subnets, adding security group rules, controlling OBS permissions, managing agencies, and synchronizing IAM users	Supported	Not supported
Adding node groups, scaling out, scaling in, and upgrading specifications	Supported	Not supported
Isolating hosts, starting all roles, and stopping all roles	Supported	Supported
Downloading the client, starting services, stopping services, and perform rolling restart of services	Supported	Supported
Viewing the instance status of services, configuring parameters, and synchronizing configurations	Supported	Supported

Common Operation	MRS Console	FusionInsight Manager
Viewing cleared alarms and events	Supported	Supported
Viewing the alarm help	Supported	Supported
Setting thresholds for threshold alarms	Not supported	Supported
Adding message subscription specifications	Supported	Not supported
Managing files	Supported	Not supported
Managing jobs	Supported	Not supported
Managing tenants	Supported	Supported
Managing tags	Supported	Not supported
Setting permissions (adding and deleting users, user groups, and roles)	Not supported	Supported
Backing up component data and restoring data	Not supported	Supported
Logging metadata operation audit	Not supported	Supported
Monitoring resources	Supported	Supported

1.22 How Do I Unbind an EIP from FusionInsight Manager of an MRS Cluster?

Question:

How Do I Unbind an EIP from FusionInsight Manager of an MRS Cluster?

Answer:

After an EIP is bound to FusionInsight Manager, do not unbind the EIP. Otherwise, other users may fail to access FusionInsight Manager.

■ NOTE

After an EIP is bound to FusionInsight Manager on the MRS console, the EIP cannot be unbound from FusionInsight Manager on the **EIPs** page.



A message is displayed, indicating that this operation cannot be performed because the EIP is being used by MapReduce Service.

To unbind an EIP, call the related API of the EIP service.

Step 1 Log in to the EIP management console. In the EIP list, view and record the ID of the desired EIP.

EIP	Monitoring
2acf3837-7347-48cc-8d79-d7429c848d19	極

Step 2 Unbind the EIP from API Explorer by referring to **Updating an EIP**.

For example, log in to API Explorer as the current user, select a region based on site requirements, and set **project_id** to the project ID of the current region and **publicip_id** to the ID of the EIP to be unbound queried in **Step 1**.

- **Step 3** After the API is successfully called, log in to the EIP management console. In the EIP list, you can see that the EIP is in the **Unbound** state.
- **Step 4** Log in to the MRS management console, go to the **Dashboard** tab page of the cluster, and bind another EIP to the cluster.

----End

1.23 What are the Operating Systems of Hosts in MRS Clusters of Different Versions?

Question:

What are the Operating Systems of Hosts in MRS Clusters of Different Versions?

Answer:

The host operating system varies depending on the cluster version. **Table 1** shows you the mapping relationship.

Table 1-2 Mappings between cluster versions and host OSs

Cluster Version	x86	Kunpeng (Arm)
MRS 3.2.0-LTS.1	EulerOS 2.10	EulerOS 2.10
MRS 3.1.5	EulerOS 2.9	EulerOS 2.9
MRS 3.1.2-LTS.3	EulerOS 2.9	EulerOS 2.9
MRS 3.1.0	EulerOS 2.5	EulerOS 2.8
MRS 1.9.2	EulerOS 2.2	EulerOS 2.8

 $\mathbf{2}_{\scriptscriptstyle{\mathsf{Billing}}}$

2.1 Why Is the Price Not Displayed During MRS Cluster Creation?

Question:

Why Is the Price Not Displayed During MRS Cluster Creation?

Answer:

If you select only the number of disks but not the number of cluster VM instances, the product quotation will not be charged.

The product quotation is displayed in the lower part of the browser only after the customer selects the number of instances.

2.2 How Is Auto Scaling Billed for an MRS Cluster?

Question:

How Is Auto Scaling Billed for an MRS Cluster?

Answer:

The price displayed at the bottom when you purchase an MRS cluster will not include the auto scaling fee if you specify only the auto scaling range for the Task nodes without configuring the instance count. If the number of instances is configured, the product quotation is displayed in the lower part of the browser.

If you add nodes through the auto scaling function, the added nodes will be billed by the actual usage duration per hour regardless of whether the cluster's billing mode is yearly/monthly or pay-per-use mode.

2.3 How Are Task Nodes in an MRS Cluster Billed?

Question:

How Are Task Nodes in an MRS Cluster Billed?

Answer:

Task nodes in a cluster are billed in pay-per-use mode, regardless of the cluster billing mode. That is, they are billed per hour based on the actual usage duration.

2.4 Why Does My Unsubscription from ECS Fail After I Unsubscribe from MRS?

Question:

Why Does My Unsubscription from ECS Fail After I Unsubscribe from MRS?

Answer:

- 1. Check that the ECS ID is not used by an MRS cluster in use.
- On the ECS console, find the ECS to be unsubscribed from and click Locked by MRS to unlock it.
- 3. Click **Unsubscribe** again.
- 4. If the unsubscription still fails, collect the ECS ID and contact Huawei Cloud technical support.

3 Cluster Creation

3.1 How Do I Create an MRS Cluster Using a Custom Security Group?

Question:

How Do I Create an MRS Cluster Using a Custom Security Group?

Answer:

You can create an MRS cluster using a user-defined security group in either of the following ways:

- When purchasing a cluster and using a security group created by yourself, you need to enable port 9022.
- When purchasing a cluster, set **Security Group** to **Auto create**.

3.2 What Should I Do If HDFS, Yarn, and MapReduce Components Are Unavailable When I Buy an MRS Cluster?

Question:

What Should I Do If HDFS, Yarn, and MapReduce Components Are Unavailable When I Buy an MRS Cluster?

Answer:

The HDFS, YARN, and MapReduce components are integrated in Hadoop. If the three components are unavailable when are MRS cluster is bought, select Hadoop instead. After an MRS cluster is created, HDFS, YARN, and MapReduce are available in the **Components** page.

3.3 What Should I Do If the ZooKeeper Component Is Unavailable When I Buy an MRS Cluster?

Question:

Why Cannot I Find the ZooKeeper Component When I Buy an MRS Cluster?

Answer:

- If you create a cluster of a version earlier than MRS 3.x, ZooKeeper is installed by default and is not displayed on the GUI.
 - After the cluster is created, the ZooKeeper component is available on the **Components** page.
- If you create a cluster of MRS 3.x or later, ZooKeeper is available on the GUI and is selected by default.

3.4 What Should I Do If Invalid Authentication Is Reported When I Submit an Order for Purchasing an MRS Cluster?

Question:

What Should I Do If Invalid Authentication Is Reported When I Submit an Order for Purchasing an MRS Cluster?

Answer:

- 1. Contact the administrator to check API request logs. The alarm information is as follows: IAM users have not been assigned the **mrs:cluster:create** permission in the fine-grained policy.
- 2. The IAM user belongs to multiple user groups, and different default MRS policies are assigned to these user groups. Low-permission policies are preferentially matched. This policy does not contain the **mrs:cluster:create** permission. As a result, the cluster creation operation cannot be submitted, and error 401 is reported.
- 3. After the user is removed from the user group corresponding to the low-permission policy, the cluster purchase order can be submitted.

Account and Password

4.1 What Is the User for Logging in to FusionInsight Manager?

Question:

What Is the User for Logging in to FusionInsight Manager?

Answer:

The default account for logging in to Manager is **admin**, and the password is the one you set when you created the cluster.

4.2 How Do I Query and Change the Password Validity Period of a User In a Cluster?

Querying the Password Validity Period

Querying the password validity period of a component running user (human-machine user or machine-machine user):

- **Step 1** Log in to the node where the client is installed as the client installation user.
- **Step 2** Run the following command to switch to the client directory, for example, /opt/Bigdata/client:
 - cd /opt/Bigdata/client
- **Step 3** Run the following command to configure environment variables:
 - source bigdata env
- **Step 4** Run the following command and enter the password of user **kadmin/admin** to log in to the kadmin console:
 - kadmin -p kadmin/admin

The default password of user **kadmin/admin** is **Admin@123**. Change the password upon your first login or as prompted and keep the new password secure.

Step 5 Run the following command to view the user information:

getprinc Internal system username

Example: getprinc user1

```
kadmin: getprinc user1
.....
Expiration date: [never]
Last password change: Sun Oct 09 15:29:54 CST 2022
Password expiration date: [never]
.....
```

----End

Querying the password validity period of an OS user:

- **Step 1** Log in to any master node in the cluster as user **root**.
- **Step 2** Run the following command to view the password validity period (value of **Password expires**):

chage -l Username

For example, to view the password validity period of user **root**, run the **chage -l root** command. The command output is as follows:

```
[root@xxx ~]#chage -l root
Last password change : Sep 12, 2021

Password expires : never

Password inactive : never
Account expires : never
Minimum number of days between password change : 0

Maximum number of days between password change : 99999

Number of days of warning before password expires : 7
```

----End

Changing the Password Validity Period

- The password of a machine-machine user is randomly generated and never expires by default.
- The password validity period of a human-machine user can be changed by modifying the password policy on Manager.

The operations are as follows:

Versions earlier than MRS 3.*x*. Change the password validity period of a human-machine user by referring to **Modifying a Password Policy**.

MRS 3.*x* **or later**: Change the password validity period of a human-machine user by referring to**Configuring Password Policies**.

5 Account and Permission

5.1 Does an MRS Cluster Support Access Permission Control If Kerberos Authentication Is not Enabled?

MRS clusters with versions earlier than 1.8.0 do not support access permission control if Kerberos authentication is not enabled. MRS clusters with Kerberos authentication enabled support role based permission control. For MRS 1.8.0 or later, all clusters support role based permission control.

For MRS cluster 2.1.0 or earlier, choose **System > Configuration > Permission** on MRS Manager.

For MRS cluster 3.x or later, choose **System** > **Permission** on FusionInsight Manager.

For details about how to configure permissions, see **Permission Management**.

For details about how to use clusters with Kerberos authentication enabled, see Clusters with Kerberos Authentication Enabled.

5.2 How Do I Add Tenant Management Permission to Users in a Cluster?

You can assign tenant management permission only in analysis or hybrid clusters, but not in streaming clusters.

The operations vary depending on the MRS cluster version:

Procedure for versions earlier than MRS cluster 3.x:

- **Step 1** Log in to MRS Manager.
- **Step 2** Choose **System > Manage User**. Select the new user, and click **Modify** in the **Operation** column.
- Step 3 In Assign Rights by Role, click Select and Add Role.
 - If you bind the **Manager_tenant** role to the account, the account will have permission to view tenant management information.

 If you bind the Manager_administrator role to the account, the account will have permission to perform tenant management and view related information.

Step 4 Click OK.

----End

Procedure for MRS cluster 3.x and later versions:

- **Step 1** Log in to FusionInsight Manager and choose **System > Permission > User**.
- Step 2 Locate the user and click Modify.

Modify the parameters based on service requirements.

If you bind the **Manager_tenant** role to the account, the account will have permission to view tenant management information. If you bind the **Manager_administrator** role to the account, the account will have permission to perform tenant management and view related information.

It takes about three minutes for the settings to take effect after user group or role permission are modified.

Step 3 Click OK.

----End

5.3 Why Cannot I Find the User Management Page on MRS Manager?

Question:

Why Cannot I Find the User Management Page on MRS Manager?

Answer:

The current login user does not have the **Manager_administrator** role permission. Log in to MRS Manager again as user **admin** or other users who have the Manager management permission.

5.4 Does Hue Provide the Function of Configuring Account Permissions?

Question:

Does Hue Provide the Function of Configuring Account Permissions?

Answer:

The Hue service does not provide the function of configuring account permissions.

You can configure account permissions by configuring user roles and user groups in System Settings on FusionInsight Manager. In this way, Hue permissions can be configured.

5.5 Why Can't I Submit Jobs on the Console After My IAM Account Is Assigned with MRS Permissions?

Question:

Why can't I submit jobs on the MRS console after my IAM account is assigned with the MRS ReadOnlyAccess and MRS FullAccess permissions?

Answer:

The account has the MRS ReadOnlyAccess and MRS FullAccess permissions. Due to the permission priority, the account cannot add jobs on the MRS console.

The group to which the IAM account belongs has the MRS FullAccess, MRS ReadOnlyAccess, and MRS Administrator permissions. MRS FullAccess and MRS ReadOnlyAccess are fine-grained permissions, and MRS Administrator is a role-based access control (RBAC) policy. Fine-grained permissions have higher priorities over RBAC policies. If fine-grained permissions and RBAC policies are configured, fine-grained permissions take effect first. Fine-grained permissions follow the deny priority principle. Therefore, the MRS ReadOnlyAccess permission takes effect finally. So, a message is displayed, indicating that the account does not have the permission.

Delete the MRS ReadOnlyAccess permission, log out of the console, and log in to the console again.

6 Client Usage

6.1 How Do I Disable SASL Authentication for ZooKeeper?

Question:

How Do I Disable ZooKeeper SASL Authentication?

Answer:

- 1. Log in to FusionInsight Manager.
- 2. Choose Cluster > Service > ZooKeeper > Configuration > All Configurations.
- 3. In the navigation tree on the left, choose quorumpeer > Customization and add zookeeper.sasl.disable = false.

Save the configuration and restart the ZooKeeper service.

6.2 What Can I Do If the Error Message "Permission denied" Is Displayed When kinit Is Executed on a Client Outside the MRS Cluster?

Symptom

After the client is installed on a node outside an MRS cluster and the **kinit** command is executed, the following error information is displayed:

-bash kinit Permission denied

The following error information is displayed when the java command is executed:

-bash: /xxx/java: Permission denied

After running the **ll** /Java installation path/JDK/jdk/bin/java command, it is found that the file execution permission is correct.

Fault Locating

Run the **mount | column -t** command to check the status of the mounted partition. It is found that the partition status of the mount point where the Java execution file is located is **noexec**. In the current environment, the data disk where the MRS client is installed is set to **noexec**, that is, binary file execution is prohibited. As a result, Java commands cannot be executed.

Solution

- 1. Log in to the node where the MRS client is located as user **root**.
- 2. Remove the configuration item **noexec** of the data disk where the MRS client is located from the **/etc/fstab** file.
- 3. Run the **umount** command to detach the data disk, and then run the **mount** -a command to remount the data disk.

Web Page Access

7.1 How Do I Change the Session Timeout Duration for an Open Source Component Web UI?

Question:

How Do I Change the Session Timeout Interval on the Web Page of an Open-Source Component?

Answer:

A proper web page timeout interval prevents information leakage caused by longtime web page exposure.

- 1. Checking Whether the Cluster Supports Session Timeout Duration Adjustment
 - For MRS cluster versions earlier than 3.x:
 - i. On the cluster details page, choose **Components** > **meta** > **Service Configuration**.
 - ii. Switch **Basic** to **All**, and search for the **http.server.session.timeout.secs**.
 - If http.server.session.timeout.secs does not exist, the cluster does not support change of the session timeout duration. If the parameter exists, perform the following steps to modify it.
 - MRS 3.x and later: Log in to FusionInsight Manager and choose Cluster > Services > meta. On the displayed page, click Configurations and select All Configurations. Search for the http.server.session.timeout.secs configuration item. If this configuration item exists, perform the following steps to modify it. If the configuration item does not exist, the version does not support dynamic adjustment of the session duration.



You are advised to set all session timeout durations to the same value. Otherwise, the settings of some parameters may not take effect due to value conflict.

- Modifying the Timeout Duration on Manager and the Authentication Center Page
 - For clusters of versions earlier than MRS 3.x.
 - i. Log in to each master node in the cluster and perform 2.ii to 2.iv.
 - ii. Change the value of <session-timeout>20</session-timeout> in the /opt/Bigdata/apache-tomcat-7.0.78/webapps/cas/WEB-INF/ web.xml file. <session-timeout>20</session-timeout> indicates the session timeout duration, in minutes. Change it based on service requirements. The maximum value is 480 minutes.
 - iii. Change the value of <session-timeout>20</session-timeout> in the /opt/Bigdata/apache-tomcat-7.0.78/webapps/web/WEB-INF/ web.xml file. <session-timeout>20</session-timeout> indicates the session timeout duration, in minutes. Change it based on service requirements. The maximum value is 480 minutes.
 - iv. Change the values of p:maxTimeToLiveInSeconds="\$ {tgt.maxTimeToLiveInSeconds:1200}" and p:timeToKillInSeconds="\${tgt.timeToKillInSeconds:1200}" in the /opt/Bigdata/apache-tomcat-7.0.78/webapps/cas/WEB-INF/spring-configuration/ticketExpirationPolicies.xml file. The maximum value is 28,800 seconds.
 - v. Restart the Tomcat node on the active master node.
 - 1) On the active master node, run the **netstat -anp |grep 28443 | grep LISTEN | awk '{print \$7}'** command as user **omm** to query the Tomcat process ID.
 - 2) Run the **kill -9** *{pid}* command, in which *{pid}* indicates the Tomcat process ID obtained in **2.v.1**).
 - 3) Wait until the process automatically restarts. You can run the **netstat -anp |grep 28443 |grep LISTEN** command to check whether the process is successfully restarted. If the process can be queried, the process is successfully restarted. If the process cannot be queried, query the process again later.
 - For clusters of MRS 3.x or later
 - i. Log in to each master node in the cluster and perform **2.ii** to **2.iii** on each master node.
 - ii. Change the value of <session-timeout>20</session-timeout> in the /opt/Bigdata/om-server_xxx/apache-tomcat-xxx/ webapps/web/WEB-INF/web.xml file. <session-timeout>20</ session-timeout> indicates the session timeout duration, in minutes.

- Change it based on service requirements. The maximum value is 480 minutes.
- iii. Add ticket.tgt.timeToKillInSeconds=28800 to the /opt/ Bigdata/om-server_xxx/apache-tomcat-8.5.63/webapps/cas/WEB-INF/classes/config/application.properties file. ticket.tgt.timeToKillInSeconds indicates the validity period of the authentication center, in seconds. Change it based on service requirements. The maximum value is 28,800 seconds.
- iv. Restart the Tomcat node on the active master node.
 - 1) On the active master node, run the **netstat -anp |grep 28443 | grep LISTEN | awk '{print \$7}'** command as user **omm** to query the Tomcat process ID.
 - 2) Run the **kill -9** *{pid}* command, in which *{pid}* indicates the Tomcat process ID obtained in **2.iv.1**).
 - 3) Wait until the process automatically restarts.

 You can run the **netstat -anp |grep 28443 |grep LISTEN**command to check whether the process is successfully restarted.

 If the process is displayed, the process is successfully restarted. If the process is not displayed, query the process again later.
- 3. Modifying the Timeout Duration for an Open-Source Component Web UI
 - a. Access the **All Configurations** page.
 - For MRS cluster versions earlier than MRS 3.x:
 On the cluster details page, choose Components > Meta > Service Configuration.
 - For MRS cluster version 3.x or later:
 Log in to FusionInsight Manager and choose Cluster > Services > meta. On the displayed page, click Configurations and select All Configurations.
 - b. Change the value of **http.server.session.timeout.secs** under **meta** as required. The unit is second.
 - c. Save the settings, deselect **Restart the affected services or instances**, and click **OK**.
 - You are advised to perform the restart during off-peak hours.
 - d. (Optional) If you need to use the Spark web UI, search for **spark.session.maxAge** on the **All Configurations** page of Spark and change the value (in seconds).
 - Save the settings, deselect **Restart the affected services or instances**, and click **OK**.
 - e. Restart the meta service and components on web UI, or restart the cluster during off-peak hours.
 - To prevent service interruption, restart the service during off-peak hours or perform a rolling restart. For details, see **Performing Rolling Restart**.

□ NOTE

The timeout duration of the Flink component web UI cannot be changed.

7.2 What Can I Do If the Dynamic Resource Plan Page in MRS Tenant Management Cannot Be Refreshed?

Question:

What Can I Do If the Dynamic Resource Plan Page in MRS Tenant Management Cannot Be Refreshed?

Answer:

- **Step 1** Log in to the Master1 and Master2 nodes as user **root**.
- **Step 2** Run the **ps -ef |grep aos** command to check the AOS process ID.
- **Step 3** Run the kill -9 AOS process ID command to end the AOS process.
- **Step 4** Wait until the AOS process is automatically restarted. You can run the **ps -ef |grep aos** command to check whether the AOS process exists. If the process exists, the restart is successful. If the process does not exist, retry later.

----End

7.3 What Do I Do If the Kafka Topic Monitoring Tab Is Not Displayed on Manager?

Question:

What Do I Do If the Kafka Topic Monitoring Tab Is Not Displayed on Manager?

Answer:

- **Step 1** Log in to the Master nodes of the cluster and switch to user **omm**.
- Step 2 Go to the /opt/Bigdata/apache-tomcat-7.0.78/webapps/web/WEB-INF/lib/components/Kafka/ directory.
- Step 3 Copy the ZooKeeper package to the cp /opt/share/zookeeper-3.5.1-mrs-2.0/zookeeper-3.5.1-mrs-2.0.jar ./ directory.
- **Step 4** Restart the Tomcat process.
 - sh /opt/Bigdata/apache-tomcat-7.0.78/bin/shutdown.sh
 - sh /opt/Bigdata/apache-tomcat-7.0.78/bin/startup.sh

----End

7.4 What CAN I DO IF an Error Is Reported or Some Functions Are Unavailable When I Access the Web UIs of Components such as HDFS, Hue, Yarn, Flink, and HetuEngine?

Question:


What CAN I DO IF an Error Is Reported or Some Functions Are Unavailable When I Access the Web UIs of Components such as HDFS, Hue, Yarn, Flink, and HetuEngine?

Answer:

Users who access the WebUI of components such as HDFS, Hue, Yarn, Flink, and HetuEngine do not have the management permission of the corresponding components. As a result, an error is reported or some functions are unavailable.


Examples:

 After you log in to the web UI of Flink as the current user, some content cannot be displayed, and you do not have the permission to create applications, cluster connections, or data connections.




No data available


 After you log in to the web UI of HDFS as the current user, error message "Failed to retrieve data from /jmx?qry=java.lang:type=Memory, cause: Forbidden" is displayed.



• After you log in to the web UI of YARN as the current user, you cannot view job information.



• After you log in to the web UI of Hue as the current user, click in the navigation pane on the left, and select **Workflow**, an error message is displayed.



You are advised to log in to the web UIs of the components as a user with corresponding management permissions. For example, you can create a service user who has the management permissions on HDFS and you can log in to the web UI of HDFS as the created user. For details, see **Creating a User**.

7.5 How Do I Switch the Methods to Access MRS Manager?

Question:

How Do I Access MRS Manager Through an EIP After Accessing It Through a Direct Connection in an MRS 3.x Cluster?

Answer:

On the **Dashboard** tab page of the cluster, click = next to **Access Manager** to switch the access mode.

8 Alarm Monitoring

8.1 In an MRS Streaming Cluster, Can the Kafka Topic Monitoring Function Send Alarm Notifications?

Question:

In an MRS Streaming Cluster, Can the Kafka Topic Monitoring Function Send Alarm Notifications?

Answer:

The Kafka topic monitoring cannot send notifications by email or SMS message. Currently, you can view alarm information on Manager.

8.2 Where can I view the running resource queues when ALM-18022 Insufficient Yarn Queue Resources is generated?

Question:

Where can I view the running resource queues when ALM-18022 Insufficient Yarn Queue Resources is generated?

Answer:

Log in to FusionInsight Manager and choose **Cluster** > **Services** > **Yarn**. In the navigation pane on the left, choose **ResourceManager(Active)** and log in to the native Yarn page.

For details, see the online help.

8.3 How Do I Understand the Multi-Level Chart Statistics in the HBase Operation Requests Metric?


Question:

How Do I Understand the Multi-Level Chart Statistics in the HBase Operation Requests Metric?

Answer:


The following uses the **Operation Requests on RegionServers** monitoring item as an example:

Log in to FusionInsight Manager and choose Cluster > Services > HBase >
Resource. On the displayed page, you can view the Operation Requests on
RegionServers chart. If you click all, the top 10 RegionServers ranked by the
total number of operation requests in the current cluster are displayed, the
statistics interval is 5 minutes.



2. Click a point in the chart. A level-2 chart is displayed, showing the number of operation requests of all RegionServers in the past 5 minutes.

Operation Requests on RegionServers



3. Click an operation statistics bar chart. A level-3 chart is displayed, showing the distribution of operations in each region within the period.



4. Click a region name. The distribution chart of operations performed every 5 minutes in the last 12 hours is displayed. You can view the number of operations performed in the period.



9 Performance Tuning

9.1 Does an MRS Cluster Support System Reinstallation?

Question:

Does an MRS Cluster Support System Reinstallation?

Answer:

An MRS cluster does not support system reinstallation.

9.2 Can I Change the OS of an MRS Cluster?

Question:

Can I Change the OS of an MRS Cluster?

Answer:

The OS of an MRS cluster cannot be changed.

9.3 How Do I Improve the Resource Utilization of Core Nodes in a Cluster?

- 1. Go to the Yarn service configuration page.
 - For versions earlier than MRS 1.8.10, log in to MRS Manager, choose
 Services > Yarn > Service Configuration, and select All from the Basic drop-down list.
 - For MRS 1.8.10 or later and MRS 2.x, click the cluster name. On the cluster details page that is displayed, click the **Components** tab and

choose **Yarn**. Click the **Service Configuration** and select **All** from the **Basic** drop-down list.

If the **Components** tab is unavailable, complete IAM user synchronization first. (On the **Dashboard** page, click **Synchronize** on the right side of **IAM User Sync** to synchronize IAM users.)

- For MRS cluster version 3.*x* or later:
 - Log in to FusionInsight Manager. Choose Cluster > Name of the desired cluster > Services > Yarn > Configurations > All Configurations.
- 2. Search for **yarn.nodemanager.resource.memory-mb**, and increase the value based on the actual memory of the cluster nodes.
- 3. Save the change and restart the affected services or instances.

9.4 How Do I Stop the Firewall Service?

Question:

How Do I Stop the Firewall Service?

Answer:

- **Step 1** Log in to each node of a cluster as user **root**.
- **Step 2** Check whether the firewall service is started.

For example, to check the firewall status on EulerOS, run the **systemctl status firewalld.service** command.

Step 3 Stop the firewall service.

For example, to stop the firewall service on EulerOS, run the **systemctl stop firewalld.service** command.

----End

10 Job Development


10.1 How Do I Get My Data into OBS or HDFS?

MRS can process data in OBS and HDFS. You can get your data into OBS or HDFS as follows:

- 1. Upload local data to OBS.
 - a. Log in to the OBS console.
 - b. Create a parallel file system named **userdata** on OBS and create the **program**, **input**, **output**, and **log** folders in the file system.
 - Choose Parallel File System > Create Parallel File System, and create a file system named userdata.
 - ii. In the OBS file system list, click the file system name userdata, choose Files > Create Folder, and create the program, input, output, and log folders.
 - c. Upload data to the **userdata** file system.
 - i. Go to the **program** folder and click **Upload File**.
 - ii. Click add file and select a user program.
 - iii. Click Upload.
 - iv. Upload the user data file to the **input** directory using the same method.
- 2. Import OBS data to HDFS.

You can import OBS data to HDFS only when **Kerberos Authentication** is disabled and the cluster is running.

- a. Log in to the MRS console.
- b. Click the name of the cluster.
- c. On the page displayed, select the **Files** tab page and click **HDFS File List**.
- d. Select a data directory, for example, **bd_app1**.
 - The **bd_app1** directory is only an example. You can use any directory on the page or create a new one.
- e. Click **Import Data** and click **Browse** to select an OBS path and an HDFS path. See **Figure 10-1**.





f. Click **OK**.

You can view the file upload progress on the **File Operation Records** tab page.

10.2 What Types of Spark Jobs Can Be Submitted in a Cluster?

Question:

What Types of Spark Jobs Can Be Submitted in a Cluster?

Answer:

MRS clusters support Spark jobs submitted in Spark, Spark Script, or Spark SQL mode.

10.3 Can I Run Multiple Spark Tasks at the Same Time After the Minimum Tenant Resources of an MRS Cluster Is Changed to 0?

Question:

Can I Run Multiple Spark Tasks at the Same Time After the Minimum Tenant Resources of an MRS Cluster Is Changed to 0?

Answer:

You can run only one Spark task at a time after the minimum tenant resources of an MRS cluster is changed to 0.

10.4 What Should I Do If Job Parameters Separated By Spaces Cannot Be Identified?

Question:

Will Parameters Be Identified If Job Submission Parameters Are Separated by Spaces?

Answer:

Use spaces to separate parameters. To prevent parameters from being saved as plaintext, add an at sign (@) before parameters, for example, **@password=**XXXXXXX.

10.5 What Are the Differences Between the Client Mode and Cluster Mode of Spark Jobs?

You need to understand the concept ApplicationMaster before understanding the essential differences between Yarn-client and Yarn-cluster.

In Yarn, each application instance has an ApplicationMaster process, which is the first container started by the application. It interacts with ResourceManager and requests resources. After obtaining resources, it instructs NodeManager to start containers. The essential difference between the Yarn-cluster and Yarn-client modes lies in the ApplicationMaster process.

In Yarn-cluster mode, Driver runs in ApplicationMaster, which requests resources from Yarn and monitors the running status of a job. After a user submits a job, the client can be stopped and the job continues running on Yarn. Therefore, the Yarn-cluster mode is not suitable for running interactive jobs.

In Yarn-client mode, ApplicationMaster requests only Executor from Yarn. The client communicates with the requested containers to schedule tasks. Therefore, the client cannot be stopped.

10.6 How Do I View MRS Job Logs?

- **Step 1** On the **Jobs** page of the MRS console, you can view logs of each job, including launcherJob and realJob logs.
 - Generally, error logs are printed in **stderr** and **stdout** for launcherJob jobs, as shown in the following figure:

```
org spache hadoop mapred FileAlreadyExistException: Output directory hdfs://hacluster/user/m-0610-100 already exists

at org spache hadoop mapreduce. lib. output FileOutputFormat. checkOutputSpecs(FileOutputFormat. java:164)

at org spache hadoop mapreduce. JobSubmitter. checkSpecs(JobSubmitter java:288)

at org spache hadoop mapreduce. JobSubmitter. submitJobInternal (JobSubmitter java:148)

at org spache hadoop mapreduce. JobSubmitter. submitJobInternal (JobSubmitter java:148)

at org spache hadoop mapreduce. JobSubmitter. submitJobInternal (JobSubmitter java:148)

at org spache hadoop mapreduce. JobSil: num(Job java:1570)

at java: security. AccessController. doFrivileged(Native Method)

at java: security. whit. Subject. doks(Subject. java:422)

at org spache hadoop. mapreduce. Job. submit(Job. java:1567)

at org spache hadoop. mapreduce. Job. submit(Job. java:1567)

at org spache hadoop. mapreduce. Job. submit(Job. java:1568)

at org spache hadoop. mapreduce. Job. waitForCompletion(Job. java:1568)

at org spache hadoop. mapreduce. Job. waitForCompletion(Job. java:157)

at org spache hadoop. mapreduce. Job. waitForCompletion(Job. java:157)


at org spache hadoop. mapreduce. Job. waitForCompletion(Job. java:1581)

at sun reflect. NativeMethodAccessorImpl. invoke (Native Method)

at sun reflect. NativeMethodAccessorImpl. invoke (Native MethodAccessorImpl. java:43)

at sun reflect. NativeMethodAccessorImpl. invoke (Native MethodAccessorImpl. java:43)
```

 You can view reallob logs on the ResourceManager web UI provided by the Yarn service on MRS Manager.



- **Step 2** Log in to the Master node of the cluster to obtain the job log files in **Step 1**. The HDFS path is /tmp/logs/{submit_user}/logs/{application_id}.
- **Step 3** After the job is submitted, if the job application ID cannot be found on the Yarn web UI, the job fails to be submitted. You can log in to the active Master node of the cluster and view the job submission process log /var/log/executor/logs/exe.log.

----End

10.7 What Can I Do If the System Displays a Message Indicating that the Current User Does Not Exist on Manager When I Submit a Job?

Analysis: If IAM synchronization is not performed when a job is submitted to a cluster in security mode, the error message "The current user does not exist on MRS Manager. Grant the user sufficient permissions on IAM and then perform IAM user synchronization on the Dashboard tab page." is displayed.

Solution: Before you submit the job, go to the **Dashboard** page, and click **Synchronize** on the right side of **IAM User Sync**.

10.8 What Can I Do If LauncherJob Fails to Be Executed and the Error Message "jobPropertiesMap is null" Is Displayed?

Question: What should I do if the Launcher job fails because the user who submits the job does not have the write permission on the **hdfs /mrs/job-properties** directory?

Answer: This problem has been fixed in the 2.1.0.6 patch. Additionally, you can also grant the write permission on the **/mrs/job-properties** directory to the synchronized user who submits the job on MRS Manager.

10.9 What Should I Do If the Flink Job Status on the MRS Console Is Inconsistent with That on Yarn?

Question: What should i do if the Flink job status on the MRS console is inconsistent with that on Yarn?

Answer: To save storage space, the Yarn configuration item **yarn.resourcemanager.max-completed-applications** is modified to reduce the number of historical job records stored on Yarn. Flink jobs are long-term jobs. The realJob is still running on Yarn, but the launcherJob has been deleted. As a result, the launcherJob cannot be found on Yarn, and the job status fails to be updated. This problem is fixed in the 2.1.0.6 patch.

Workaround: Stop the jobs where launcherJob cannot be found. The statuses of jobs submitted later will be updated.

10.10 What Can I Do If a SparkStreaming Job Fails After Running for Dozens of Hours and Error 403 Is Reported for OBS Access?

Question: What can I do if a SparkStreaming job fails after running for dozens of hours and error 403 is reported for OBS access?

Answer: When a user submits a job that needs to read and write OBS, the job submission program adds the temporary access key (AK) and secret key (SK) for accessing OBS by default. The temporary AK and SK have expiration time.

If you want to run long-term jobs such as Flink and SparkStreaming jobs, you can enter the AK and SK in **Service Parameter** to prevent jobs execution failure due to key expiration.

10.11 What Should I Do If an Alarm Is Reported Indicating that the Memory Is Insufficient When I Execute a SQL Statement on the ClickHouse Client?

Symptom

The ClickHouse client restricts the memory used by GROUP BY statements. When a SQL statement is executed on the ClickHouse client, the following error information is displayed:

Progress: 1.83 billion rows, 85.31 GB (68.80 million rows/s., 3.21 GB/s.) 6%Received exception from server:
Code: 241. DB::Exception: Received from localhost:9000, 127.0.0.1.

DB::Exception: Memory limit (for query) exceeded: would use 9.31 GiB (attempt to allocate chunk of 1048576 bytes), maximum: 9.31 GiB: (while reading column hits):

Solution

- Run the following command before executing an SQL statement on condition that the cluster has sufficient memory:
 SET max_memory_usage = 128000000000; #128G
- If no sufficient memory is available, ClickHouse enables you to overflow data to disk to free up the memory: You are advised to set the value of max_memory_usage to twice the size of max_bytes_before_external_group_by.
 set max_bytes_before_external_group_by=200000000000; #20G
- If the customer has a large amount of data and the entire table is queried, you are advised to query the data by partition or upgrade the specifications of the core node in the cluster.

10.12 What Should I Do If Error Message "java.io.IOException: Connection reset by peer" Is Displayed During the Execution of a Spark Job?

set max_memory_usage=40000000000; #40G

Symptom

The execution of a Spark job cannot finish and error message "java.io.IOException: Connection reset by peer" is displayed.

Solution

Add the **executor.memory Overhead** parameter to the parameters for submitting a job.

10.13 What Should I Do If the Error Message "requestId=XXX" Is Displayed When a Spark Job Accesses OBS?

Symptom

Error message "requestId=4971883851071737250" is displayed when a Spark job accesses OBS.

Solution

Log in to the node where the Spark client is located, go to the **conf** directory, and change the value of the **fs.obs.metrics.switch** parameter in the **core-site.xml** configuration file to **false**.

10.14 What Should I Do If the Error Message "UnknownScannerExeception" Is Displayed for Spark Jobs?

Symptom

Spark jobs run slowly. Warning information is printed in run logs, and the error cause is **UnknownScannerExeception**.

Solution

Before running a Spark job, adjust the value of **hbase.client.scanner.timeout.period** (for example, from 60 seconds to 120 seconds).

Log in to FusionInsight Manager and choose **Cluster > Services > HBase**. Click **Configurations** then **All Configurations**, search for **hbase.client.scanner.timeout.period**, and change its value to **120000** (unit: ms).

10.15 What Can I Do If DataArts Studio Occasionally Fails to Schedule Spark Jobs?

Symptom

DataArtsStudio occasionally fails to schedule Spark jobs and the rescheduling also fails. The following error information is displayed:

Caused by: org.apache.spark.SparkException: Application application_1619511926396_2586346 finished with failed status

Solution

Log in to the node where the Spark client is located as user **root** and increase the value of the **spark.driver.memory** parameter in the **spark-defaults.conf** file.

10.16 What Should I Do If a Flink Job Fails to Execute and the Error Message "java.lang.NoSuchFieldError: SECURITY_SSL_ENCRYPT_ENABLED" Is Displayed?

Symptom

A Flink job fails to be executed and the following error message is displayed:

Caused by: java.lang.NoSuchFieldError: SECURITY_SSL_ENCRYPT_ENABLED

Solution

The third-party dependency package in the customer code conflicts with the cluster package. As a result, the job fails to be submitted to the MRS cluster. You need to modify the dependency package, set the scope of the open source Hadoop package and Flink package in the POM file to **provide**, and pack and execute the job again.

10.17 What Should I Do If Submitted Yarn Jobs Cannot Be Viewed on the Web UI?

Question: Why a created Yarn job cannot be viewed when I log in to Manager as the **admin** user?

Answer:

- The **admin** user is a user on the cluster management page. Check whether the user has the **supergroup** permission. Generally, only the user with the **supergroup** permission can view jobs.
- Log in to Yarn as the user who submits the job. Do not use the **admin** user to view the job.

10.18 How Do I Modify the HDFS fs.defaultFS of an Existing Cluster?

Question: How do I modify the HDFS NameSpace (fs.defaultFS) of an existing cluster?

Answer: You can modify or add the HDFS NameSpace (fs.defaultFS) of the cluster by modifying the parameters of the **core-site.xml** and **hdfs-site.xml** files on the client. However, you are not advised to perform this operation on the server.

10.19 What Can I Do If launcher-job Is Terminated by Yarn When a Flink Task Is Submitted?

Symptom

Launcher-job is terminated by Yarn due to insufficient heap size when a Flink task is submitted on the management plane.

Solution

Increase the heap size of the launcher-job queue.

- 1. Log in to the active OMS node as user **omm**.
- Change the value of job.launcher.resource.memory.mb in /opt/executor/ webapps/executor/WEB-INF/classes/servicebroker.xml to 2048.
- 3. Run the **sh /opt/executor/bin/restart-executor.sh** command to restart the executor process.

10.20 What Should I Do If the Error Message "slot request timeout" Is Displayed When I Submit a Flink Job?

Symptom

When a Flink job is submitted, JobManager is started successfully. However, TaskManager remains in the starting state until timeout. The following error information is displayed:

org.apache.flink.runtime.jobmanager.scheduler.NoResourceAvailableException: Could not allocate the required slot within slot request timeout. Please make sure that the cluster has enough resources

Possible Causes

- 1. The resources in the YARN queue are insufficient. As a result, TaskManager fails to start.
- 2. Your JAR files conflict with those in the environment. You can execute the WordCount program to determine whether the issue occurs.
- 3. If the cluster is in security mode, the SSL certificate of Flink may be incorrectly configured or has expired.

Solution

- 1. Add resources to the YARN queue.
- 2. Exclude the Flink and Hadoop dependencies in your JAR files so that Flink and Hadoop can depend only on the JAR files in the environment.
- 3. Reconfigure the SSL certificate of Flink. For details, see **Using Flink from Scratch**.

10.21 FAQs About Importing and Exporting Data Using DistCP Jobs

• **Question**: Does a DistCP job check data consistency during data import and export?


Answer: No. DistCP jobs only copy data but do not modify it.

• **Question**: When data is exported from a DistCP job, if some files already exist in OBS, how will the job process the files?


Answer: DistCP jobs will overwrite the files in OBS.

10.22 How Do I View SQL Statements of Hive Jobs on the Yarn Web UI?

- **Step 1** Log in to FusionInsight Manager as a service user.
- Step 2 Choose Cluster > Services > Yarn. Click ResourceManager(xxx,Active) next to ResourceManager WebUI.
- **Step 3** On the YARN web UI, click the ID of the job to be viewed.



Step 4 Click ApplicationMaster or History next to Tracking URL.



Step 5 Choose **Configuration** in the left navigation pane and search for the **hive.query.string** parameter in the upper right corner to query the corresponding HiveSQL.



----End

10.23 How Do I View Logs of a Specified Yarn Task?

- **Step 1** Log in to the active Master node as user **root**.
- **Step 2** Run the following command to initialize environment variables: source Client installation directory/bigdata_env
- Step 3 If Kerberos authentication is enabled for the cluster, run the following command to authenticate the user. If Kerberos authentication is disabled, skip this step.kinit MRS cluster user
- Step 4 Run the following command to obtain the logs of a specified task:

 yarn logs -applicationId application_ID of the job you want to view

 ----End

1 1 Cluster Upgrade/Patching

11.1 How Do I Upgrade an MRS Cluster?

- Non-LTS clusters
 - An existing non-LTS cluster cannot be upgraded to a later version. You can create a cluster of the new version and migrate data from the old cluster to the new cluster.
- MRS LTS clusters
 - MRS LTS clusters can be upgraded to a target LTS version. Contact our O&M engineers to confirm the upgrade path and buy professional services for cluster upgrade.

11.2 Does MRS Support Kernel Version Upgrade of Components in a Cluster?

Question: Does MRS support kernel version upgrade of components in a cluster?

Answer: MRS does not support independent upgrade of kernel versions of components in a cluster. To use components of new versions, delete the current cluster and create a cluster again. For details about the components supported by MRS, see **List of MRS Component Versions**.

12 Peripheral Ecosystem Interconnection

12.1 Does MRS Support Read and Write Operations on DLI Service Tables?

Question: Does MRS support read and write operations on DLI service tables?

Answer: If you have stored data on OBS, you can use Spark in MRS to read Data Lake Insight (DLI) tables, flexibly process table data, and save the result to another DLI table. If you have not stored data on OBS, you cannot use MRS to read or write DLI tables.

12.2 Does OBS Support the ListObjectsV2 Protocol?

Question: Does OBS support the ListObjectsV2 protocol?

Answer: No it doesn't.

12.3 Can a Crawler Service Be Deployed on Nodes in an MRS Cluster?

Question: Can a crawler service be deployed on nodes in an MRS cluster?

Answer: To ensure stable running, the crawler service or other third-party services cannot be deployed on nodes in the MRS cluster.

12.4 Does MRS Support Secure Deletion?

Question: Does MRS support secure deletion (preventing invalid restoration after deletion)?

Answer: Currently, MRS clusters can only restore data backed up by users. That is, MRS supports only secure deletion.

12.5 How Do I Use PySpark to Connect MRS Spark?

Question: How do I use pyspark on an ECS to connect an MRS Spark cluster with Kerberos authentication enabled on the Intranet?

Answer: Change the value of spark.yarn.security.credentials.hbase.enabled in the spark-defaults.conf file of Spark to true and use spark-submit --master yarn --keytab keytabfile --principal principal command to specify the Kerberos authentication file.

12.6 Why Mapped Fields Do not Exist in the Database After HBase Synchronizes Data to CSS?

Question: Why mapped fields do not exist in the database after HBase synchronizes data to CSS?

Answer: After data is synchronized from HBase of MRS to CSS, the database will not have mapped fields. Only a single table has mapped fields.

12.7 Can MRS Connect to an External KDC?

Question: Can MRS Connect to an External Key Distribution Center (KDC)?

Answer: MRS supports only the built-in KDC.

12.8 What Can I Do If Jetty Is Incompatible with MRS when Open-Source Kylin 3.x Is Interconnected with MRS 1.9.3?

For security purposes, MRS has upgraded some open-source third-party components that have serious security vulnerabilities. The upgrade causes the Jetty version compatibility issue when the open-source Kylin interconnects with MRS 1.9.3.

Perform the following operations to solve the issue:

- Install the MRS client on an ECS node. For details, see Using an MRS Client on Nodes Outside a Cluster. This operation uses the MRS client installation path /srv/client/ as an example.
- After the installation is complete, run the following commands to import the MRS client environment variable **bigdata_env** and the environment variables HIVE_CONF and HCAT_HOME required by Kylin.

source /srv/client/bigdata_env export HIVE_CONF=/srv/client/Hive/config/ export HCAT_HOME=/srv/client/Hive/HCatalog 3. Install Kylin on the node where the MRS client is installed and specify **KYLIN_HOME**. For details, see the **Kylin official website**. For MRS 1.9.3, select Kylin for HBase 1.*x* for interconnection.

export KYLIN_HOME=/srv/client/apache-kylin-3.0.2-bin-hbase1x

4. Remove Jetty .jar packages from the /srv/client/Hive/Beeline/lib/ directory in the Hive client directory to prevent version conflicts.

Jetty .jar packages:

javax-websocket-server-impl-9.4.26.v20200117.jar websocket-server-9.4.26.v20200117.jar jetty-all-9.4.26.v20200117-uber.jar jetty-runner-9.4.26.v20200117.jar apache-jsp-9.4.26.v20200117.jar

5. Start the Kylin service and check Kylin logs. In normal cases, the logs do not contain compatibility errors, such as **java.lang.NoSuchMethodException** and **java.lang.ClassNotFoundException**.

\$KYLIN_HOME/bin/kylin.sh start

 Access the native Kylin page at http://<hostname>:7070/kylin and run the sample Cube script \${KYLIN_HOME}/bin/sample.sh to check whether Kylin is running properly.

12.9 What Should I Do If Data Failed to Be Exported from MRS to an OBS Encrypted Bucket?

Question: What should i do if data failed to be exported from MRS to an obs encrypted bucket?

Answer: Only MRS 1.9.x and later versions support OBS bucket encryption. If you want to use encrypted OBS buckets, use MRS cluster version 1.9.x or later.

12.10 How Do I Interconnect MRS with LTS?

Prerequisites

You have obtained an AK/SK pair by referring to **How Do I Obtain an AK/SK Pair?**

Procedure

1. Install ICAgent on the MRS node. For details, see **Installing ICAgent** (HUAWEI CLOUD Hosts).

M NOTE

For the first installation, install one server first, and then batch install all other hosts in the same way.

- 2. Create a host group and add the installed ICAgent host in 1 to the host group.
 - Log in to the Log Tank Service (LTS) console, and choose Host
 Management in the left navigation pane. On the displayed page, click
 Create Host Group in the upper right corner.

- b. In the **Create Host Group** slide-out panel that is displayed, enter a host group name in the **Host Group** field and set **Host OS** to **Windows**.
- c. In the host list, select one or more hosts to add to the group and click **OK**.
 - You can filter hosts by host name or host IP address. You can also click Search by Host IP Address and enter multiple host IP addresses in the displayed search box to search for matches.
 - If your desired hosts are not in the list, click Install ICAgent. In the Install ICAgent slide-out panel displayed, install ICAgent on the hosts as prompted.
- 3. Create a log group.
 - a. Log in to the LTS console, choose **Log Management** in the navigation pane on the left, and click **Create Log Group** in the upper right corner.
 - b. In the **Create Log Group** slide-out panel displayed, enter a log group name. A log group name:
 - Can contain only letters, numbers, hyphens (-), underscores (_), and periods (.).
 - Cannot start with a period (.) or underscore (_), and cannot end with a period (.).
 - Can contain 1 to 64 characters.
 - c. Set **Log Retention Duration** to 1 to 30 days. If this parameter is not specified, logs are retained for 7 days by default. You can change the log retention duration after the log group is created.
 - LTS offers a free quota of 500 MB per month for log read/write, retention, and indexing. When the free quota is used up, you will be billed for excess usage on a pay-per-use basis.
 - d. Click **OK**.
 - In the log group list on the **Log Management** page, you can view details of the log group, including log group name, log retention duration, creation time, creation type, and tags. Log retention duration and tags can be modified. Click **Modify** in the **Operation** column of the log group to modify the duration.
 - Click the log group name to access the log stream details page.
- 4. Create a log stream.
 - a. On the LTS console, click the expansion button of a log group.
 - b. Click **Create Log Stream**. In the **Create Log Stream** slide-out panel displayed, enter a log stream name. A log stream name:
 - Can contain only letters, numbers, hyphens (-), underscores (_), and periods (.).
 - Cannot start with a period (.) or underscore (_), and cannot end with a period (.).
 - Can contain 1 to 64 characters.

- c. Select an enterprise project. You can click **View Enterprise Projects** to view all enterprise projects.
- d. Click OK.

On the log stream page, you can view details of the log stream, including log stream name, enterprise project, log retention duration, creation time, and creation type.

You can configure different log streams for different components.

- 5. Add hosts for log ingestion.
 - a. In the left navigation pane of the LTS console, choose **Log Ingestion**.
 - b. On the All tab page displayed, click Elastic Cloud Server (ECS).
 - c. Add the following configuration to **Collection Path**:

YARN task log path:

/srv/BigData/*/nm/containerlogs/**/container-localizer-syslog

/srv/BigData/*/nm/containerlogs/**/directory.info

/srv/BigData/*/nm/containerlogs/**/launch_container.sh

/srv/BigData/*/nm/containerlogs/**/prelaunch.err

/srv/BigData/*/nm/containerlogs/**/prelaunch.out

/srv/BigData/*/nm/containerlogs/**/stderr

/srv/BigData/*/nm/containerlogs/**/stdout

/srv/BigData/*/nm/containerlogs/**/syslog*

/srv/BigData/*/nm/containerlogs/**/*.log

Path configuration:

- Logs can be collected recursively. A double asterisk (**) can represent up to 5 directory levels in a path.
- You can use an asterisk (*) as a wildcard for fuzzy match. The wildcard (*) can represent one or more characters of a directory or file name.
- If the collection path is set to a directory (such as /var/logs/), only .log, .trace, and .out files in the directory are collected.

Component logs:

All HDFS service logs:

/var/log/Bigdata/audit/hdfs/jn/hdfs-audit-journalnode.log

/var/log/Bigdata/audit/hdfs/jn/SecurityAuth.audit

/var/log/Bigdata/hdfs/*/

Configure log collection paths for other components by referring to HDFS service logs.

12.11 How Do I Install HSS on MRS Cluster Nodes?

You can install Host Security Service (HSS) on your MRS cluster nodes if the OS versions of the nodes are supported by HSS agents.

Perform the following steps to install HSS:

1. Check whether the OS versions of the MRS cluster nodes are supported by HSS agents.

To query the OS versions, perform the following operations:

- a. Log in to the MRS management console.
- b. Choose **Clusters** > **Active Clusters**, select a running cluster, and click the cluster name to access its details page.
- c. Click the **Nodes** tab. Click the **master** or **core** node group, and click any node in the node name list to access the cloud service basic information page.
- d. Click **Basic Information**, view the image in the ECS information, and confirm the EulerOS version in the image.
 - For example, **EulerOS_2.5_x86_64** indicates that the OS version is EulerOS 2.5 (64-bit).
- e. Check whether the OS versions of the MRS nodes are supported by HSS agents.

For details about the OSs supported by HSS agents, see **Supported OSs**.

- If yes, go to 2 to install HSS agents.
- If no, HSS cannot be installed.
- 2. Purchase HSS quotas and log in to each node in the MRS cluster to install HSS agents. After the agents are installed, you can enable HSS.

Ensure you have purchased HSS in your MRS cluster node region and have used the installation package or installation command in the region to install HSS agents on your nodes.

For details about how to purchase HSS quotas, install agents, and enable HSS, see **HSS Getting Started**.

13 Cluster Access

13.1 How Do I Switch the Login Mode of a Node in an MRS Cluster?

Question: How do I switch the login mode (password or key pair) of a node in an MRS cluster?

Answer: Login mode cannot be changed. You can select the login mode when creating the cluster, but cannot change the login mode after you create the cluster.

13.2 How Can I Obtain the IP Address and Port Number of a ZooKeeper Instance?

You can obtain the IP address and port number of a ZooKeeper instance through the MRS console or FusionInsight Manager.

Method 1: Obtaining the IP address and port number of a ZooKeeper through the MRS console

- 1. On the **Dashboard** page, click **Synchronize** on the right side of **IAM User Sync** to synchronize IAM users.
- 2. Click the **Components** tab and choose **ZooKeeper**. On the displayed page, click **Instances** to view the business IP address of a ZooKeeper instance.




Figure 13-1 ZooKeeper addresses

3. Click the **Service Configuration** tab. On the displayed page, search for the **clientPort** parameter to view the port number of the ZooKeeper instance.

Method 2: Obtaining the IP address and port number of a ZooKeeper through FusionInsight Manager

- 1. Log in to FusionInsight Manager. For details, see Accessing Manager.
- 2. Perform the following operations to obtain the IP address and port number of a ZooKeeper instance.
 - For clusters of MRS 3.x or earlier
 - i. Choose Services > ZooKeeper. On the displayed page, click the Instance tab to view the business IP address of a ZooKeeper instance.

Figure 13-2 ZooKeeper addresses



- ii. Click the **Service Configuration** tab. On the displayed page, search for the **clientPort** parameter to view the port number of the ZooKeeper instance.
- For clusters of MRS 3.x or later
 - Choose Cluster > Services > ZooKeeper. On the displayed page, click the Instance tab to view the business IP address of a ZooKeeper instance.
 - Click the Configurations tab. On the displayed page, search for the clientPort parameter to view the port number of the ZooKeeper instance.


13.3 How Do I Access an MRS Cluster from a Node Outside the Cluster?

Creating a Linux ECS Outside the Cluster to Access the MRS Cluster

- Step 1 Create an ECS outside the cluster. For details, see Purchasing an ECS.
 Set AZ, VPC, and Security Group of the ECS to the same values as those of the cluster to be accessed.
- **Step 2** On the VPC management console, apply for an EIP and bind it to the ECS. For details, see **Assigning an EIP and Binding It to an ECS**.
- **Step 3** Configure security group rules for the cluster.
 - On the Dashboard tab page, click Add Security Group Rule. In the Add Security Group Rule dialog box that is displayed, click Manage Security Group Rule.



2. Click the **Inbound Rules** tab, and click **Add Rule**. In the **Add Inbound Rule** dialog box, configure the IP address of the ECS and enable all ports.



- 3. After the security group rule is added, you can download and install the client on the ECS. For details, see **Installing a Client**.
- 4. Use the client.

Log in to the client node as the client installation user and run the following command to switch to the client directory:

cd /opt/hadoopclient

Run the following command to load environment variables:

source bigdata_env

If Kerberos authentication is enabled for the cluster, run the following command to authenticate the user. If Kerberos authentication is disabled for the current cluster, authentication is not required.

kinit MRS cluster user

Example:

kinit admin

Run the client command of a component.

Example:

Run the following command to view files in the HDFS root directory:

hdfs dfs -ls /

```
Found 15 items
drwxrwx--x - hive
                      hive
                                    0 2021-10-26 16:30 /apps
drwxr-xr-x - hdfs
                                     0 2021-10-18 20:54 /datasets
                     hadoop
drwxr-xr-x - hdfs
                     hadoop
                                      0 2021-10-18 20:54 /datastore
drwxrwx---+ - flink
drwxr-x--- - flume
                      hadoop
                                      0 2021-10-18 21:10 /flink
                      hadoop
                                      0 2021-10-18 20:54 /flume
drwxrwx--x - hbase
                                      0 2021-10-30 07:31 /hbase
                     hadoop
```

----End

Creating a Windows ECS Outside the Cluster to Access MRS Manager

Create a Windows ECS on the ECS console to access MRS Manager. For details, see **Accessing MRS Manager Using a Windows ECS**.

14 Big Data Service Development

14.1 Can MRS Run Multiple Flume Tasks at a Time?

The Flume client supports multiple independent data flows. You can configure and link multiple sources, channels, and sinks in the **properties.properties** configuration file. These components can be linked to form multiple flows.

The following is an example of configuring two data flows in a configuration file:

server.sources = source1 source2 server.sinks = sink1 sink2 server.channels = channel1 channel2

#dataflow1

server.sources.source1.channels = channel1 server.sinks.sink1.channel = channel1

#dataflow2

server.sources.source2.channels = channel2 server.sinks.sink2.channel = channel2

14.2 How Do I Change FlumeClient Logs to Standard Logs?

- 1. Log in to the node where the Flume client is installed.
- 2. Go to the Flume client installation directory, for example, /opt/FlumeClient. Run the following command:
 - cd /opt/FlumeClient/fusioninsight-flume-1.9.0/bin
- Run the ./flume-manage.sh stop force command to stop FlumeClient.
- 4. Run the vi ../conf/log4j.properties command to open the log4j.properties file and change the flume.root.logger value to \${flume.log.level},console.
- 5. Run the ./flume-manage.sh start force command to restart FlumeClient.
- 6. After the modification, check whether the Docker configuration is correct.

14.3 Where Are the JAR Files and Environment Variables of Hadoop Stored?

- hadoopstreaming.jar: /opt/share/hadoop-streaming-* (* indicates the Hadoop version.)
- JDK environment variables: /opt/client/JDK/component_env
- Hadoop environment variables: /opt/client/HDFS/component_env
- Hadoop client: /opt/client/HDFS/hadoop

14.4 What Compression Algorithms Does HBase Support?

Question: What compression algorithms does HBase support?

Answer: HBase supports Snappy, LZ4, and Gzip compression algorithms.

14.5 Can MRS Write Data to HBase Through an HBase External Table of Hive?

Question: Can MRS write data to HBase through an HBase external table of Hive? No. Hive on HBase supports only data query.

14.6 How Do I View HBase Logs?

- 1. Log in to the Master node in the cluster as user **root**.
- 2. Run the **su omm** command to switch to user **omm**.
- 3. Run the cd /var/log/Bigdata/hbase/ command to go to the /var/log/Bigdata/hbase/ directory and view HBase logs.

14.7 How Do I Set the TTL for an HBase Table?

Set the time to live (TTL) when creating a table:
 Create the t_task_log table, set the column family to f, and set the TTL to 86400 seconds.

create 't_task_log',{NAME => 'f', TTL=>'86400'}

• Set the TTL for an existing table: alter "t_task_log",NAME=>'data',TTL=>'86400' # Set the TTL value for the column family data.

14.8 How Do I Connect to HBase of MRS Through HappyBase?

ThriftServer1 and ThriftServer2 cannot coexist. The HBase service of the MRS cluster uses ThriftServer2. However, HappyBase can connect to HBase only

through the ThriftServer1 interface. Therefore, use Python to directly connect to HBase. For details, see https://github.com/huaweicloud/huaweicloud-mrs-example/blob/mrs-1.8/src/hbase-examples/hbase-python-example/DemoClient.py.

14.9 How Do I Change the Number of HDFS Replicas?

- 1. Go to the HDFS service configuration page.
 - For MRS 1.8.10 or earlier clusters
 Log in to MRS Manager (see Accessing MRS Manager), choose Services
 HDFS > Service Configuration, and select All from the Basic dropdown list.
 - For MRS 1.8.10 or later and MRS 2.x, click the cluster name. On the cluster details page that is displayed, choose Components > HDFS > Service Configuration, and select All from the Basic drop-down list.

If the **Components** tab is unavailable, complete IAM user synchronization first. (On the **Dashboard** page, click **Synchronize** on the right side of **IAM User Sync** to synchronize IAM users.)

- For MRS cluster version 3.x or later:
 Log in to FusionInsight Manager, and choose Cluster > Name of the desired cluster > Services > HDFS > Configurations > All Configurations.
- 2. Search for **dfs.replication**, change the value (value range: 1 to 16), and restart the HDFS instance.

14.10 How Do I Modify the HDFS Active/Standby Switchover Class?

If the

org.apache.hadoop.hdfs.server.namenode.ha.AdaptiveFailoverProxyProvider class is unavailable when a cluster of MRS 3.x connects to NameNodes using HDFS, the cause is that the HDFS active/standby switchover class of the cluster is configured improperly. To solve the problem, perform the following operations:

- Method 1: Add the **hadoop-plugins-***xxx*.**jar** package to the **classpath** or **lib** directory of your program.
 - The hadoop-plugins-xxx.jar package is stored in the HDFS client directory, for example, \$HADOOP_HOME/share/hadoop/common/lib/hadoop-plugins-8.0.2-302023.jar.
- Method 2: Change the configuration item of HDFS to the corresponding open source class, as shown in the follows:
 - dfs.client.failover.proxy.provider.hacluster=org.apache.hadoop.hdfs.server.name node.ha.ConfiguredFailoverProxyProvider

14.11 What Data Type in Hive Tables Is Recommended for the Number Type of DynamoDB?

Question: What data type in Hive tables is recommended for the number type of DoynamoDB?

Answer: smallint is recommended.

14.12 Can the Hive Driver Be Interconnected with DBCP2?

Question: Can the Hive driver be interconnected with DBCP2?

Answer: The Hive driver cannot be interconnected with the DBCP2 database connection pool. The DBCP2 database connection pool invokes the **isValid** method to check whether a connection is available. However, Hive directly throws an exception when implementing this method.

14.13 How Do I View the Hive Table Created by Another User?

Versions earlier than MRS 3.x.

- 1. Log in to MRS Manager and choose **System** > **Permission** > **Manage Role**.
- 2. Click Create Role, and set Role Name and Description.
- 3. In the **Permission** table, choose **Hive** > **Hive Read Write Privileges**.
- 4. In the database list, click the name of the database where the table created by user B is stored. The table is displayed.
- 5. In the **Permission** column of the table created by user B, select **SELECT**.
- 6. Click **OK**, and return to the **Role** page.
- 7. Choose **System > Manage User**. Locate the row containing user A, click **Modify** to bind the new role to user A, and click **OK**. After about 5 minutes, user A can access the table created by user B.

MRS 3.x or later:

- Log in to FusionInsight Manager and choose Cluster > Services. On the page that is displayed, choose Hive. On the displayed page, choose More, and check whether Enable Ranger is grayed out.
 - If yes, go to 9.
 - If no, perform 2 to 8.
- Log in to FusionInsight Manager and choose System > Permission > Role.
- 3. Click Create Role, and set Role Name and Description.
- 4. In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **Hive** > **Hive Read Write Privileges**.

- 5. In the database list, click the name of the database where the table created by user B is stored. The table is displayed.
- 6. In the **Permission** column of the table created by user B, select **Select**.
- 7. Click **OK**, and return to the **Role** page.
- 8. Choose **Permission** > **User**. On the **Local User** page that is displayed, locate the row containing user A, click **Modify** in the **Operation** column to bind the new role to user A, and click **OK**. After about 5 minutes, user A can access the table created by user B.
- 9. Perform the following steps to add the Ranger access permission policy of Hive:
 - Log in to FusionInsight Manager as a Hive administrator and choose Cluster > Services. On the page that is displayed, choose Ranger. On the displayed page, click the URL next to Ranger WebUI to go to the Ranger management page.
 - b. On the home page, click the component plug-in name in the **HADOOP SQL** area, for example, **Hive**.
 - On the Access tab page, click Add New Policy to add a Hive permission control policy.
 - d. In the **Create Policy** dialog box that is displayed, set the following parameters:
 - Policy Name: Enter a policy name, for example, table test hive.
 - database: Enter or select the database where the table created by user B is stored, for example, default.
 - **table**: Enter or select the table created by user B, for example, **test**.
 - column: Enter and select a column, for example, *.
 - In the Allow Conditions area, click Select User, select user A, click Add Permissions, and select select.
 - Click Add.
- 10. Perform the following steps to add the Ranger access permission policy of HDFS:
 - Log in to FusionInsight Manager as user rangeradmin and choose Cluster > Services. On the page that is displayed, choose Ranger. On the displayed page, click the URL next to Ranger WebUI to go to the Ranger management page.
 - b. On the home page, click the component plug-in name in the **HDFS** area, for example, **hacluster**.
 - c. Click **Add New Policy** to add an HDFS permission control policy.
 - d. In the **Create Policy** dialog box that is displayed, set the following parameters:
 - Policy Name: Enter a policy name, for example, tablehdfs_test.
 - Resource Path: Set this parameter to the HDFS path where the table created by user B is stored, for example, /user/hive/warehouse/ Database name! Table name.

- In the Allow Conditions area, select user A for Select User, click Add Permissions in the Permissions column, and select Read and Execute.
- Click Add.
- 11. View basic information about the policy in the policy list. After the policy takes effect, user A can view the table created by user B.

14.14 Where Can I Download the Dependency Package (com.huawei.gaussc10) in the Hive Sample Project?

Question: Where can I download the dependency package (com.huawei.gaussc10) in the Hive sample project?

Answer: MRS does not have the **com.huawei.gaussc10** dependency package, which is a GaussDB dependency package and does not need to be configured. Exclude this package when building a Maven project.

14.15 Can I Export the Query Result of Hive Data?

Run the following statement to export the query result of Hive data:

insert overwrite local directory "/tmp/out/" row format delimited fields terminated by "\t" select * from table:

14.16 What Should I Do If an Error Occurs When Hive Runs the beeline -e Command to Execute Multiple Statements?

When Hive uses Beeline to run the **beeline -e "use default;show tables;"** command on an MRS 3.x cluster, the following error is reported:

Error while compiling statement: FAILED: ParseException line 1:11 missing EOF at ',' near 'default' (state=42000,code=40000)

Solutions:

- Method 1: Replace the beeline -e " use default; show tables;" command with beeline --entirelineascommand=false -e "use default; show tables;".
- Method 2:
 - a. In the /opt/Bigdata/client/Hive directory on the Hive client, change export CLIENT_HIVE_ENTIRELINEASCOMMAND=true in the component_env file to export CLIENT_HIVE_ENTIRELINEASCOMMAND=false.

Figure 14-1 Changing the component_env file

```
PATH_NEW='echo_SPATH | sed "s|/opt/Bigdata/client/Hive/Beeline/bin:||g" | sed "s|/opt/Bigdata/client/Hive/Beeline/bin:||g" |
PATH_NEW='echo_SPATH_NEW| sed "s|/opt/Bigdata/client/Hive/Hcatalog/bin:||g" | sed "s|/opt/Bigdata/client/Hive/Hcatalog/bin:||g" |
export PATH=/opt/Bigdata/client/Hive/Beeline/bin:/opt/Bigdata/client/Hive/Hcatalog/bin:SPATH_NEW
export LILENT_HIVE_NET-jdec:hive2://192_168.0.88:2181_192_168.0.9:2181_192_168.0.9:2181_/192_168.0.9:2181_/1;serviceDiscoveryMode=zooKeeper\;zooKeeperNamespace=hiveserver2
export HIVE_NET-jopt/Bigdata/client/Hive/Beeline/lib
export HICAT_CONF_DIR-/opt/Bigdata/client/Hive/Beeline/lib
export HICAT_TONF_DIR-/opt/Bigdata/client/Hive/Hcatalog/conf/
export LICAT_TONF_DIR-/opt/Bigdata/client/Hive/Hcatalog/conf/
export LICAT_TONF_DIR-/opt/Bigdata/client/Hive/Hcatalog/conf/
```

Run the following command to verify the configuration:
 source /opt/Bigdata/client/bigdata_env
 beeline -e "use default; show tables;"

14.17 What Should I Do If a HiveSQL/HiveScript Job Fails to be Submitted After Hive Is Added?

This issue occurs because the **MRS CommonOperations** permission bound to the user group to which the user who submits the job belongs does not include the Hive permission after being synchronized to Manager. To solve this issue, perform the following operations:

- Add the Hive service.
- 2. Log in to the IAM console and create a user group. The policy bound to the user group is the same as that of the user group to which the user who submits the job belongs.
- 3. Add the user who submits the job to the new user group.
- 4. Refresh the cluster details page on the MRS console. The status of IAM user synchronization is **Not synchronized**.
- 5. Click **Synchronize** on the right of **IAM User Sync**. Go back to the previous page. In the navigation pane on the left, choose **Operation Logs** and check whether the user is changed.
 - If yes, submit the Hive job again.
 - If no, check whether all the preceding operations are complete.
 - If yes, contact an O&M engineer.
 - If no, submit the Hive job after the preceding operations are complete.

14.18 What Can I Do If the Excel File Downloaded by Hue Cannot Be Opened?

□ NOTE

This section applies only to versions earlier than MRS 3.x.

1. Log in to a Master node as user **root** and switch to user **omm**.


su - omm

2. Check whether the current node is the active OMS node.

sh \${BIGDATA_HOME}/om-0.0.1/sbin/status-oms.sh

If **active** is displayed in the command output, the node is the active node. Otherwise, log in to the other Master node.

Figure 14-2 Active OMS node



- Go to the {BIGDATA_HOME}/Apache-httpd-*/conf directory.
 cd \${BIGDATA_HOME}/Apache-httpd-*/conf
- 4. Open the **httpd.conf** file.

vim httpd.conf

5. Search for **21201** in the file and delete the following content from the file. (The values of *proxy_ip* and *proxy_port* are the same as those in the actual environment.)

```
ProxyHTMLEnable On
SetEnv PROXY_PREFIX=https://[proxy_ip]:[proxy_port]
ProxyHTMLURLMap (https?:\/\[^:]*:[0-9]*.*) ${PROXY_PREFIX}/proxyRedirect=$1 RV
```

Figure 14-3 Content to be deleted

- 6. Save the modification and exit.
- 7. Open the **httpd.conf** file again, search for **proxy_hue_port**, and delete the following content:

```
ProxyHTMLEnable On
SetEnv PROXY_PREFIX=https://[proxy_ip]:[proxy_port]
ProxyHTMLURLMap (https?:\/\[^:]*:[0-9]*.*) ${PROXY_PREFIX}/proxyRedirect=$1 RV
```

Figure 14-4 Content to be deleted

- 8. Save the modification and exit.
- Run the following command to restart the httpd process:
 sh \${BIGDATA_HOME}/Apache-httpd-*/setup/restarthttpd.sh

- 10. Check whether the httpd.conf file on the standby Master node is modified. If the file is modified, no further action is required. If the file is not modified, modify the httpd.conf file on the standby Master node in the same way. You do not need to restart the httpd process.
- 11. Download the Excel file again. You can open the file successfully.

14.19 How Do I Do If Sessions Are Not Released After Hue Connects to HiveServer and the Error Message "over max user connections" Is Displayed?

Applicable versions: MRS 3.1.0 and earlier

- Modify the following file on the two Hue nodes: /opt/Bigdata/FusionInsight_Porter_8.*/install/FusionInsight-Hue-*/hue/apps/beeswax/src/beeswax/models.py
- 2. Change the configurations in lines 396 and 404.

Change q Changed = self.filter(owner=user, application=application).exclude(guid=").exclude(secret=") to q = self.filter(owner=user, application=application).exclude(guid=None).exclude(secret=None).



14.20 How Do I Reset Kafka Data?

You can reset Kafka data by deleting Kafka topics.

- Delete a topic: **kafka-topics.sh --delete --zookeeper** *ZooKeeper Cluster service IP address*:**2181/kafka --topic** *topicname*
- Query all topics: kafka-topics.sh --zookeeper ZooKeeper cluster service IP address:2181/kafka --list

After the deletion command is executed, empty topics will be deleted immediately. If a topic has data, the topic will be marked for deletion and will be deleted by Kafka later.

14.21 What Access Protocols Are Supported by Kafka?

Question: What access protocols are supported by Kafka?

Answer: Kafka supports PLAINTEXT, SSL, SASL_PLAINTEXT, and SASL_SSL.

14.22 What Should I Do If the Error Message "Not Authorized to access group XXX" Is Displayed When Kafka Topics Are Consumed?

This issue is caused by the conflict between the Ranger authentication and ACL authentication of a cluster. If a Kafka cluster uses ACL for permission access control and Ranger authentication is enabled for the Kafka component, all authentications of the component are managed by Ranger. The permissions set by the original authentication plug-in are invalid. As a result, ACL authorization does not take effect. You can disable Ranger authentication of Kafka and restart the Kafka service to rectify the fault. The procedure is as follows:

- 1. Log in to FusionInsight Manager and choose **Cluster > Services > Kafka**.
- 2. In the upper right corner of the **Dashboard** page, click **More** and choose **Disable Ranger**. In the displayed dialog box, enter the password and click **OK**. After the operation is successful, click **Finish**.
- 3. In the upper right corner of the **Dashboard** page, click **More** and choose **Restart Service** to restart the Kafka service.

14.23 What Compression Algorithms Does Kudu Support?

Question: What compression algorithms does Kudu support?

Answer: Kudu supports Snappy, LZ4, and zlib. LZ4 is used by default.

14.24 How Do I View Kudu Logs?

- 1. Log in to the Master node in the cluster.
- 2. Run the **su omm** command to switch to user **omm**.
- 3. Run the cd /var/log/Bigdata/kudu/ command to go to the /var/log/Bigdata/kudu/ directory and view Kudu logs.

14.25 How Do I Handle the Kudu Service Exceptions Generated During Cluster Creation?

Viewing the Kudu Service Exception Logs

- 1. Log in to the MRS console.
- 2. Click the name of the cluster.
- 3. On the page displayed, choose **Components** > **Kudu** > **Instances** and locate the IP address of the abnormal instance.

If the **Components** tab is unavailable, complete IAM user synchronization first. (On the **Dashboard** page, click **Synchronize** on the right side of **IAM User Sync** to synchronize IAM users.)

4. Log in to the node where the abnormal instance resides, and view the Kudu log.

cd /var/log/Bigdata/Kudu [root@node-master1AERu kudu]# ls healthchecklog runninglog startlog

You can find the Kudu health check logs in the **healthchecklog** directory, the startup logs in the **startlog** directory, and the Kudu process run logs in the **runninglog** directory.

[root@node-master1AERu logs]# pwd /var/log/Bigdata/kudu/runninglog/master/logs [root@node-master1AERu logs]# ls -al kudu-master.ERROR kudu-master.INFO kudu-master.WARNING

Run logs are classified into three types: ERROR, INFO, and WARNING. Each type of run logs is recorded in the corresponding file. You can run the **cat** command to view run logs of each type.

Handling Kudu Service Exceptions

The /var/log/Bigdata/kudu/runninglog/master/logs/kudu-master.INFO file contains the following error information:

If this exception occurs when the Kudu service is installed for the first time, the KuduMaster service is not started. Data inconsistency causes the startup failure. To solve the problem, perform the following steps to clear the data directories and restart the Kudu service. If the Kudu service is not installed for the first time, clearing the data directories will cause data loss. In this case, migrate data and clear the data directory.

- Search for the data directories fs_data_dir, fs_wal_dir, and fs_meta_dir.
 find /opt -name master.gflagfile
 cat /opt/Bigdata/FusionInsight_Kudu_*/*_KuduMaster/etc/master.gflagfile
 | grep fs_
- 2. On the cluster details page, choose **Components** > **Kudu** and click **Stop Service**.
- 3. Clear the Kudu data directories on all KuduMaster and KuduTserver nodes. The following command uses two data disks as an example.
 - rm -Rvf /srv/Bigdata/data1/kudu, rm -Rvf /srv/Bigdata/data2/kudu
- On the cluster details page, choose Components > Kudu and choose More > Restart Service.
- 5. Check the Kudu service status and logs.

14.26 Does MRS Support Python Code?

- The sample project and application development in MRS are the same. You can select either of them.
- MRS supports Python code. For details about component sample projects programmed using Python, see the *Developer Guide*.

14.27 Does OpenTSDB Support Python APIs?

Question: Does OpenTSDB support Python APIs?

OpenTSDB supports Python APIs. OpenTSDB provides HTTP-based RESTful APIs that are language-independent. Any language that supports HTTP requests can interconnect to OpenTSDB.

14.28 How Do I Configure Other Data Sources on Presto?

In this section, MySQL is used as an example.

- For MRS 1.x and 3.x clusters, do the following:
 - a. Log in to the MRS management console.
 - b. Click the name of the cluster to go to its details page.
 - c. Click the **Components** tab and then **Presto** in the component list. On the page that is displayed, click the **Configurations** tab then the **All Configurations** sub-tab.
 - d. On the Presto configuration page that is displayed, find **connector-customize**.
 - e. Set Name and Value as follows:

Name: mysql.connector.name

Value: mysql



f. Click the plus sign (+) to add three more fields and set **Name** and **Value** according to the table below. Then click **Save**.



Name	Value	Description
mysql.connection-url	jdbc:mysql:// xxx.xxx.xxx.xxx:3306	Database connection pool

Name	Value	Description
mysql.connection-user	xxxx	Database username
mysql.connection- password	xxxx	Database password

- g. Restart the Presto service.
- h. Run the following command to connect to the Presto Server of the cluster:

presto_cli.sh -- krb5-config-path {krb5.conf path} -- krb5-principal {User principal} -- krb5-keytab-path {user.keytab path} -- user {presto username}

i. Log in to Presto and run the **show catalogs** command to check whether the data source list mysql of Presto can be queried.

Run the **show schemas from mysql** command to query the MySQL database.

- For MRS 2.x clusters, do the following:
 - a. Create the mysql.properties configuration file containing the following content:

connector.name=mysql

connection-url=jdbc:mysql://mysqllp:3306

connection-user=Username

connection-password=Password

- mysqlip indicates the IP address of the MySQL instance, which must be able to communicate with the MRS network.
- The username and password are those used to log in to the MySQL database.
- b. Upload the configuration file to the /opt/Bigdata/MRS_Current/ 1_14_Coordinator/etc/catalog/ directory on the master node (where the Coordinator instance resides) and the /opt/Bigdata/MRS_Current/ 1_14_Worker/etc/catalog/ directory on the core node (depending on the actual directory in the cluster), and change the file owner group to omm:wheel.
- Restart the Presto service.

14.29 How Do I Update the Ranger Certificate in MRS 1.9.3?

MRS 1.9.3 is used as an example. Replace it with the actual cluster version. After the certificate is updated, manually clear the alarm indicating that the certificate file is invalid or about to expire.

Ⅲ NOTE

After the Ranger certificate is updated, its validity period is 10 years.

After the Ranger certificate expires, the Ranger web UI is still accessible, but a message indicating that the certificate is untrusted will be displayed when you access the web UI.

• If Ranger is not installed in the cluster, log in to each master node and run the following command to rename the certificate file:

mv /opt/Bigdata/MRS_1.9.3/install/MRS-Ranger-1.0.1/ranger/ranger-1.0.1-admin/ranger-admin-keystore.jks /opt/Bigdata/MRS_1.9.3/install/MRS-Ranger-1.0.1/ranger/ranger-1.0.1-admin/ranger-admin-keystore.jks_bak

- If Ranger has been installed in the cluster, update the certificate as follows:
 - a. Download MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz from the obs-patch bucket and upload it to the /tmp directory on the node where the active RangerAdmin instance of the cluster runs.

On MRS Manager, choose **Service** > **Ranger** > **Instance** and obtain the IP address of the node where the active RangerAdmin instance runs.

- CN-Hong Kong: https://mrs-patch-ap-southeast-1.obs.ap-southeast-1.myhuaweicloud.com/MRS_Common_Script/ MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz
- AP-Bangkok: https://mrs-patch-ap-southeast-2.obs.ap-southeast-2.myhuaweicloud.com/MRS_Common_Script/ MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz
- AP-Singapore: https://mrs-patch-ap-southeast-3.obs.ap-southeast-3.myhuaweicloud.com/MRS_Common_Script/MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz
- LA-Sao Paulo: https://mrs-container1-patch-sabrazil-1.obs.myhuaweicloud.com/MRS_Common_Script/ MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz
- LA-Mexico City: https://mrs-container1-patch-namexico-1.obs.myhuaweicloud.com/MRS_Common_Script/ MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz
- b. Log in to the node where the active RangerAdmin instance is located and run the following commands:

cd /tmp

chmod 700 MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz chown omm:wheel MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz su - omm

cd /tmp

tar -zxvf MRS_1.9_Patch_UpdateRangerJks_All_20210203.tar.gz

c. Replace the certificate files.

cd updateRangerJks

sh updateRangerJks.sh \${IP address of the active master node} \${IP address of the active RangerAdmin node} \${Certificate password}

○ NOTE

- This script will restart the controller process. During the restart process, the MRS Manager page may not be viewed.
- Obtain the IP address of the active master node from **Hosts** on MRS Manager.
- To obtain the IP address of the active RangerAdmin node, choose **Services** > **Ranger** > **Instances** on MRS Manager.
- *\${Certificate password}* is a user-defined password.
- d. Log in to the MRS console.
- e. Choose **Clusters > Active Clusters** and click a cluster name to go to the cluster details page.
- f. Choose **Components** > **Ranger** > **Service Configuration** and modify the RangerAdmin configuration.
 - i. Search for the policymgr_https_keystore_password and change its value to the certificate password entered in c, that is, \${Certificate password}.
 - You are advised to copy and paste the password. If the passwords are different, Ranger will fail to restart.
 - ii. Save the configuration and perform a rolling restart of RangerAdmin.
- g. Verify that you can log in to the RangerAdmin web UI.
 - i. Choose Components > Ranger > Service Status. In Ranger
 Summary, click RangerAdmin corresponding to Ranger Web UI.
 - ii. On the Ranger web UI login page, the default username for MRS cluster 1.9.2 is **admin** and the password is **admin@12345**. The default username for MRS cluster 1.9.3 or later is **admin** and the password is **ranger@A1!**.
 - After logging in to the Ranger Web UI for the first time, change the password and keep it secure.
- h. Log in to the node where the RangerAdmin instance is located and delete the temporary files.

rm -rf /tmp/updateRangerJks

rm -rf /tmp/updateRangerJks.tar.gz

For a cluster with a custom topology, if the active master and RangerAdmin instances are not on the same node, log in to the active master node and delete temporary files.

14.30 How Do I Connect to Spark Shell from MRS?

- 1. Log in to the Master node in the cluster as user **root**.
- 2. Run the following command to configure environment variables:
 - source Client installation directory/bigdata_env
- 3. If Kerberos authentication is enabled for the cluster, authenticate the user. If Kerberos authentication is disabled, skip this step.

Run the **kinit** MRS cluster user command.

Examples:

- For a machine-machine user, run the kinit -kt user.keytab sparkuser command
- For a human-machine user, run the **kinit** *sparkuser* command.
- 4. Run the following command to connect to Spark shell:

spark-shell

14.31 How Do I Connect to Spark Beeline from MRS?

- 1. Log in to the master node in the cluster as user **root**.
- 2. Run the following command to configure environment variables:
 - source Client installation directory/bigdata_env
- 3. If Kerberos authentication is enabled for the cluster, authenticate the user. If Kerberos authentication is disabled, skip this step.

Run the kinit MRS cluster user command.

Examples:

- For a machine-machine user, run the **kinit** -**kt** *user.keytab sparkuser* command.
- For a human-machine user, run the **kinit** *sparkuser* command.
- 4. Run the following command to connect to Spark Beeline:

spark-beeline

5. Run commands on Spark Beeline. For example, create the table **test** in the **obs://mrs-word001/table/** directory.

create table test(id int) location 'obs://mrs-word001/table/';

Query all tables.

show tables;

If the table **test** is displayed in the command output, OBS is successfully accessed.

Figure 14-5 Returned table name

7. Press **Ctrl+C** to exit the Spark Beeline.

14.32 Where Are the Execution Logs of Spark Jobs Stored?

- Logs of unfinished Spark jobs are stored in the /srv/BigData/hadoop/ data1/nm/containerlogs/ directory on the Core node.
- Logs of finished Spark jobs are stored in the /tmp/logs/username/logs directory of HDFS.

14.33 How Do I Specify a Log Path When Submitting a Task in an MRS Storm Cluster?

You can modify the **/opt/Bigdata/MRS_**XXX **/1_**XX **_Supervisor/etc/worker.xml** file on the streaming Core node of MRS, set the value of **filename** to the path, and restart the corresponding instance on Manager.


You are advised not to modify the default log configuration of MRS. Otherwise, the log system may become abnormal.

14.34 How Do I Check the ResourceManager Configuration of Yarn?

This section applies only to versions earlier than MRS 3.x.

- **Step 1** Log in to MRS Manager and choose **Services** > **Yarn** > **Instance**.
- Step 2 Click the names of the two ResourceManager nodes, choose More > Synchronize Configuration, and deselect Restart services or instances whose configurations have expired. .

Figure 14-6 Synchronizing the configuration



- **Step 3** Click **Yes** to synchronize the configuration.
- **Step 4** Log in to the Master nodes as user **root**.
- Step 5 Run the cd /opt/Bigdata/MRS_Current/*_*_ResourceManager/etc_UPDATED/ command to go to the etc_UPDATED directory.
- **Step 6** Run the **grep '\.queues' capacity-scheduler.xml -A2** command to display all configured queues and check whether the queues are consistent with those displayed on Manager.

root-default is hidden on the Manager page.

```
[omm@node-masterIIIZA etc]$
[omm@node-masterIIIZA etc]$ grep '\.queues' capacity-scheduler.xml -A2
<name>yarn.scheduler.capacity.root.queues</name>
<value>default,root-default,launcher-job,test1,test2,test3,test4</value>
</property>
[omm@node-masterIIIZA etc]$
[omm@node-masterIIIZA etc]$
```

- Step 7 Run the grep '\.capacity</name>' capacity-scheduler.xml -A2 command to display the value of each queue and check whether the value of each queue is the same as that displayed on Manager. Check whether the sum of the values configured for all queues is 100.
 - If the sum is **100**, the configuration is correct.
 - If the sum is not **100**, the configuration is incorrect. Perform the following steps to rectify the fault.

```
[omm@node-master1IlZA etc]$
[omm@node-master1IlZA etc]$ grep '\.capacity</name>' capacity-scheduler.xml -A2
<name>yarn.scheduler.capacity.root.root-default.accessible-node-labels.zhaolu.capacity</name>
<value>0.0</value>
<name>yarn.scheduler.capacity.root.launcher-job.capacity</name><value</pre>
<name>yarn.scheduler.capacity.root.accessible-node-labels.zhaolu.capacity</name>
<value>100</value>
</property>
 <name>yarn.scheduler.capacity.root.testl.capacity</name>
 <value>10</value>
 </property>
<name>yarn.scheduler.capacity.root.test2.capacity</name>
<value*10</value>
<name>yarn.scheduler.capacity.root.test3.capacity</nam
<value>10</value>
 </property>
<name>yarn.scheduler.capacity.root.capacity</name>
<value>100</value>
<name>yarn.scheduler.capacity.root.root-default.capacity</name>
<value>40.0</value>
 </property>
<name>yarn.scheduler.capacity.root.test4.accessible-node-labels.zhaolu.capacity</name>
 <value>100</value>
<name>yarn.scheduler.capacity.root.test4.capacity</name>
 <value>0</value>
 </property>
<name>yarn.scheduler.capacity.root.default.capacity</name>
 <value>20</value>
```

- **Step 8** Log in to MRS Manager, and select **Hosts**.
- **Step 9** Determine the active Master node. The host name of the active Master node starts with a solid pentagon.
- **Step 10** Log in to the active Master node as user **root**.
- **Step 11** Run the **su omm** command to switch to user **omm**.
- **Step 12** Run the **sh /opt/Bigdata/om-0.0.1/sbin/restart-controller.sh** command to restart the controller when no operation is being performed on Manager.
 - Restarting the controller will not affect the big data component services.
- **Step 13** Repeat **Step 1** to **Step 7** to synchronize ResourceManager configurations and check whether the configurations are correct.

If the latest configuration has not been loaded after the configuration synchronization is complete, a message will be displayed on the Manager page indicating that the configuration has expired. However, this will not affect services. The latest configuration will be automatically loaded when the component restarts.

----End

14.35 How Do I Modify the allow_drop_detached Parameter of ClickHouse?

- **Step 1** Log in to the node where the ClickHouse client is located as user **root**.
- **Step 2** Run the following commands to go to the client installation directory and set the environment variables:

cd /opt/Client installation directory

source bigdata_env

Step 3 If Kerberos authentication is enabled for the cluster, run the following command to authenticate the user. If Kerberos authentication is disabled, skip this step.

kinit MRS cluster user

□ NOTE

The user must have the ClickHouse administrator permissions.

Step 4 Run the **clickhouse client --host** *192.168.42.90* **--secure -m** command, in which *192.168.42.90* indicates the IP address of the ClickHouseServer instance node. The command output is as follows:

[root@server-2110082001-0017 hadoopclient]# clickhouse client --host 192.168.42.90 --secure -m ClickHouse client version 21.3.4.25.
Connecting to 192.168.42.90:21427.
Connected to ClickHouse server version 21.3.4 revision 54447.

Step 5 Run the following command to set the value of the **allow_drop_detached** parameter, for example, **1**:

set allow drop detached=1;

Step 6 Run the following command to query the value of the **allow_drop_detached** parameter:

SELECT * FROM system.settings WHERE name = 'allow_drop_detached';



Step 7 Run the **q**; command to exit the ClickHouse client.

----End

14.36 What Should I Do If an Alarm Indicating Insufficient Memory Is Reported During Spark Task Execution?

Symptom

When a Spark task is executed, an alarm indicating insufficient memory is reported. The alarm ID is 18022. As a result, no available memory can be used.

Procedure

Set the executor parameters in the SQL script to limit the number of cores and memory of an executor.

For example, the configuration is as follows:

set hive.execution.engine=spark; set spark.executor.cores=2; set spark.executor.memory=4G; set spark.executor.instances=10;

Change the values of the parameters as required.

14.37 How Do I Add a Periodic Deletion Policy to Prevent Large ClickHouse System Table Logs?

Symptom

ClickHouse logs generated in the system table is too large. Deleting logs at a time takes a long time.

Handling Procedure

To delete the logs periodically, add a deletion policy. On the ClickHouse client, run the following statement to set the TTL for the system table:

alter table *system.Table name* **modify** *TTL event_date* **+ INTERVAL** *Number of days for storing data* **day;**



This statement is used only on a SQL node to configure the TTL of the system table. If the TTL needs to be configured on all nodes, run this statement on each node. Do not run the statement with **on cluster** on each node. Otherwise the ClickHouse will keep running.

Run the preceding statement during off-peak hours. This operation may take a long time if there is a large amount of data.

14.38 How Do I Obtain a Spark JAR File?

Huawei provides Huawei Mirrors for you to download all dependency JAR files of sample projects, but you need to download the open source dependency JAR files from the Maven central repository or other custom repositories.

◯ NOTE

Ensure the following conditions are met before you use a development tool in a local environment to download dependency JAR files:

- The local network is normal.
 - Open a browser and enter the Huawei Mirrors URL in the address box to check whether your access is normal. If the access is abnormal, check whether your local network is accessible.
- Check whether the proxy is enabled for the development tool. If it is enabled, disable it by performing the following operations.

Take IntelliJ IDEA 2020.2 as an example. Choose **File > Settings > Appearance & Behavior > System Settings > HTTP Proxy**, select **No proxy**, and click **OK** to save the configuration.

For details about how to configure an open source mirror, see **Configuring Huawei Open Source Mirrors**.

14.39 What Can I Do If an Alarm is Generated Because the NameNode Is not Restarted on Time After the hdfs-site.xml File Is Modified?

Question: What can I do if an alarm is generated because the NameNode is not restarted on time after the hdfs-site.xml file is modified?

Answer: If you do not restart the NameNode process after modifying the **dfs.namenode.checkpoint.period** parameter, an alarm may be falsely reported. In this case, you need to restart the NameNode process as soon as possible.

14.40 What Should I Do If It Takes a Long Time for Spark SQL to Access Hive Partitioned Tables Before a Job Starts?

Symptom

When Spark SQL is used to access Hive partitioned tables stored in OBS, the access speed is slow and a large number of OBS query APIs are called.

Example SQL:

select a,b,c from test where b=xxx

Fault Locating

According to the configuration, the task should scan only the partition whose b is xxx. However, the task logs show that the task scans all partitions and then calculates the data whose b is xxx. As a result, the task calculation is slow. In addition, a large number of OBS requests are sent because all files need to be scanned.

By default, the execution plan optimization based on partition statistics is enabled on MRS, which is equivalent to automatic execution of Analyze Table. (The default configuration method is to set **spark.sql.statistics.fallBackToHdfs** to **true**. You can set this parameter to **false**.) After this function is enabled, table partition statistics are scanned during SQL execution and used as cost estimation in the execution plan. For example, small tables identified during cost evaluation are broadcast to each node in the memory for join operations, significantly reducing shuffle time. This function greatly optimizes performance in join scenarios, but increases the number of OBS calls.

Procedure

Set the following parameter in Spark SQL and then run the SQL statement:

set spark.sql.statistics.fallBackToHdfs=false;

Alternatively, run the **--conf** command to set this parameter to **false** before startup.

--conf spark.sql.statistics.fallBackToHdfs=false

14.41 What Should I Do If the spark.yarn.executor.memoryOverhead Setting Does Not Take Effect?

Symptom

The overhead memory of the executor needs to be adjusted for Spark tasks. The **spark.yarn.executor.memoryOverhead** parameter is set to **4096**. However, the default value **1024** is used to apply for resources during actual computation.

Fault Locating

In Spark 2.3 and later versions, use the new parameter

spark.executor.memoryOverhead to set the overhead memory of the executor. If both old and new parameters are set, the value of

spark.yarn.executor.memoryOverhead does not take effect, and the value of **spark.executor.memoryOverhead** is used.

Same thing happens if you use **spark.driver.memoryOverhead** to set the overhead memory of driver.

Procedure

Use the new parameter:

14.42 How Do I Change the Time Zone of the ClickHouse Service?

Symptom

When data is inserted to ClickHouse, the time zone is incorrect. The time difference is eight hours.

Fault Locating

The Clickhouse time zone is Europe/Moscow by default. You need to change it to the local time zone.

Procedure

- **Step 1** Log in to FusionInsight Manager, choose **Cluster > Services > ClickHouse**, and click **Configurations** and then **All Configurations**.
- **Step 2** Search for **clickhouse-config-customize** in the search box on the left and add the parameter name **timezone** and value **Asia/Shanghai**.



The value of timezone must be the local time zone. Asia/Shanghai is used as an example.



----End

14.43 What Should I Do If the Connection to the ClickHouse Server Fails and Error Code 516 Is Reported?

Symptom

When the **clickhouse client** command is executed to connect to the ClickHouse server, the following error is reported:

ClickHouse exception, code: 516, host: 192.168.0.198, port: 8443; Code: 516, e.displayText() = DB::Exception: clickDevelopuser: Authentication failed: password is incorrect or there is no user with such name

Fault Locating

The username or password used for connecting the ClickHouse server is incorrect.

Procedure

Enter the correct username or password . For details, see **Using ClickHouse from Scratch**.

15 API

15.1 How Do I Configure the node_id Parameter When Calling the API for Adjusting Cluster Nodes?

Question

How Do I Configure the Request Parameter node_id When Calling the API for Adjusting Cluster Nodes (/v1.1/{project_id}/cluster_infos/{cluster_id})?

Answer

When the API is called, the value of the request parameter **node_id** is fixed to **node_orderadd**.

16 Cluster Management

16.1 How Do I View All Clusters?

You can view all MRS clusters on the **Clusters** page. You can view clusters in different status.

- Active Clusters: all clusters except clusters in Failed and Terminated states.
- Cluster History: clusters in the Terminated state. Only the clusters terminated within the last six months are displayed. If you want to view clusters terminated more than six months ago, contact technical support engineers.
- Failed Tasks: tasks in Failed state. The failed tasks include the following:
 - Tasks failed to create clusters
 - Tasks failed to terminate clusters
 - Tasks failed to scale out clusters
 - Tasks failed to scale in clusters

16.2 How Do I View MRS Operation Logs?

You can view operation logs of clusters and jobs on the **Operation Logs** page. The MRS operation logs record the following operations:

- Cluster operations
 - Create, terminate, and scale out or in clusters
 - Create directories and delete directories or files
- Job operations: Create, stop, and delete jobs
- Data operations: IAM user tasks, add users, and add user groups

Figure 16-1 shows the operation logs.

Figure 16-1 Log information



16.3 How Do I View MRS Cluster Configuration Information?

- After a cluster is created, click the cluster name on the MRS console. On the
 page displayed, you can view basic configuration information about the
 cluster, including the name, ID, billing mode, AZ, creation time, Hadoop
 component version, as well as the instance specifications and capacity of
 node. The instance specifications and node capacity determine the data
 analysis and processing capability. Higher instance specifications and larger
 capacity enable faster data processing at a higher cost.
- On the basic information page, click Access Manager to access the MRS cluster management page. On MRS Manager, you can view and handle alarms, and modify cluster configuration.

16.4 How Do I Add Components to an MRS Cluster?

Question: How do I add services to an existing MRS cluster?

Answer:

You cannot install new components for a created cluster whose version is MRS 3.1.0 or earlier. If you want to use a component that is not installed in your cluster, you need to create a cluster and select the required component.

You can add components to MRS 3.1.2-LTS.3 or later custom clusters. For details, see **Managing Services**.

16.5 Do I Need to Shut Down a Master Node Before Upgrading It?

Question: Do I need to shut down a Master node before upgrading it?

Answer: The Master node automatically shuts down during specifications upgrade, and automatically starts after the upgrade. No manual intervention is required.

16.6 Can I Delete Components Installed in an MRS Cluster?

You cannot delete any component from a created MRS cluster of MRS 3.1.0. If a component is not required, log in to MRS Manager and stop the component on the **Services** page.

You can add components to MRS 3.1.2-LTS.3 or later custom clusters. For details, see **Managing Services**.

16.7 Can I Change MRS Cluster Nodes on the MRS Console?

You cannot change MRS cluster nodes on the MRS console. You are also advised not to change MRS cluster nodes on the ECS console. Manually stopping or deleting an ECS, modifying or reinstalling the ECS OS, or modifying ECS specifications for a cluster node on the ECS console will affect the cluster stability.

If an ECS is deleted, the ECS OS is modified or reinstalled, or the ECS specifications are modified on the ECS console, MRS will automatically identify and delete the node. You can log in to the MRS console and restore the deleted node through scale-out. Do not perform operations on the nodes that are being scaled out.

16.8 How Do I Cancel Message Notification for Cluster Alarms?

- 1. Log in to the MRS console.
- 2. Click the name of the cluster.
- 3. On the page displayed, choose Alarms > Notification Rules.
- 4. Locate the row that contains the rule you want to modify, click **Edit** in the **Operation** column, and deselect the alarm or event severity levels.
- 5. Click **OK**.

16.9 Why Is the Resource Pool Memory Displayed in the MRS Cluster Smaller Than the Actual Cluster Memory?

Question: Why is the resource pool memory displayed in the MRS cluster smaller than the actual cluster memory?

Answer: In an MRS cluster, MRS allocates 50% of the cluster memory to Yarn by default. You manage Yarn nodes logically by resource pool. Therefore, the total memory of the resource pool displayed in the cluster is only 50% of the total memory of the cluster.

16.10 How Do I Configure the knox Memory?

- **Step 1** Log in to a Master node of the cluster as user **root**.
- **Step 2** Run the following command on the Master node to open the **gateway.sh** file:

su omm

vim /opt/knox/bin/gateway.sh

- **Step 3** Change **APP_MEM_OPTS=""** to **APP_MEM_OPTS="-Xms256m -Xmx768m"**, save the file, and exit.
- **Step 4** Run the following command on the Master node to restart the knox process:
 - sh /opt/knox/bin/gateway.sh stop
 - sh /opt/knox/bin/gateway.sh start
- **Step 5** Repeat the preceding steps on each Master node.
- **Step 6** Run the **ps -ef |grep knox** command to check the configured memory.

Figure 16-2 knox memory



----End

16.11 What Is the Python Version Installed for an MRS Cluster?

Log in to a Master node as user **root** and run the **Python3** command to query the Python version.

Table 16-1 Python versions supported by MRS

MRS Cluster Version	Python Version
MRS 3.1.0	Python 3.8.0
MRS 3.0.5	Python 3.7.0
MRS 3.0.2	Python 3.7.0
MRS 2.1.1	Python 3.6.8
MRS 2.1.0	Python 3.6.8
MRS 1.9.3	Python 3.6.8

16.12 How Do I View the Configuration File Directory of Each Component?

The configuration file paths of commonly used components are as follows:

Component	Configuration File Directory	
ClickHouse	Client installation directory/ClickHouse/clickhouse/config	
Flink	Client installation directory/Flink/flink/conf	
Flume	Client installation directory/fusioninsight-flume-xxx/conf	
HBase	Client installation directory/HBase/hbase/conf	
HDFS	Client installation directory/HDFS/hadoop/etc/hadoop	
Hive	Client installation directory/Hive/config	
Hudi	Client installation directory/Hudi/hudi/conf	
Kafka	Client installation directory/Kafka/kafka/config	
Loader	Client installation directory/Loader/loader-tools- xxx/loader-tool/conf	
	Client installation directory/Loader/loader-tools- xxx/schedule-tool/conf	
	Client installation directory/Loader/loader-tools- xxx/shell-client/conf	
	Client installation directory/Loader/loader-tools- xxx/sqoop-shell/conf	
Oozie	Client installation directory/Oozie/oozie-client-xxx/conf	
Spark2x	Client installation directory/Spark2x/spark/conf	
Yarn	Client installation directory/Yarn/config	
ZooKeeper	Client installation directory/Zookeeper/zookeeper/conf	

16.13 How Do I Upload a Local File to a Node Inside a Cluster?

- **Step 1** Log in to the MRS console.
- **Step 2** In the navigation pane on the left, choose **Clusters** > **Active Clusters** and click the name of the target cluster to go to its details page.

- **Step 3** On the **Nodes** page, click a node name to log in to the ECS console.
- **Step 4** Bind an elastic IP address to the cluster node. For details, see **Assigning an EIP** and Binding It to an ECS.
- Step 5 Upload the local file to the cluster node. For details, see How Can I Upload a File to an ECS?

----End

16.14 What Can I Do If the Time Information of an MRS Cluster Node Is Incorrect?

- If the time on a node inside the cluster is incorrect, log in to the node and rectify the fault from 2.
- If the time on a node inside the cluster is different from that on a node outside the cluster, log in to the node and rectify the fault from 1.
- Run the vi /etc/ntp.conf command to edit the NTP client configuration file, add the IP addresses of the master node in the MRS cluster, and comment out the IP address of other servers.

```
server master1_ip prefer
server master2_ip
```

Figure 16-3 Adding the master node IP addresses

```
# Use public servers from the pool.ntp.org project.
# Please consider joining the pool (http://www.pool.ntp.org/join.html).
#server 0.centos.pool.ntp.org iburst
#server 1.centos.pool.ntp.org iburst
#server 2.centos.pool.ntp.org iburst
#server 3.centos.pool.ntp.org iburst
#server 10.9.2.38 prefer
server 10.9.2.39
#broadcast 192.168.1.255 autokey # broadcast server
```

- 2. Run the **service ntpd stop** command to stop the NTP service.
- 3. Run the /usr/sbin/ntpdate IP address of the active master node command to manually synchronize time.
- 4. Run the **service ntpd start** or **systemctl restart ntpd** command to start the NTP service.
- 5. Run the **ntpstat** command to check the time synchronization result:

16.15 How Do I Query the Startup Time of an MRS Node?

Log in to the target node and run the following command to query the startup time:

date -d "\$(awk -F. '{print \$1}' /proc/uptime) second ago" +"%Y-%m-%d %H:%M:%S"

```
[root@server-2110082001-0018 ~]#date -d "$(awk -F. '{print $1}' /proc/uptime) second ago" +"%Y-%m-%d %H:%M':%S" 2021-12-13 15:56:23
```

16.16 How Do I Do If Trust Relationships Between Nodes Are Abnormal?

If "ALM-12066 Inter-Node Mutual Trust Fails" is reported on Manager or there is no SSH trust relationship between nodes, rectify the fault by performing the following operations:

1. Run the **ssh-add -l** command on both nodes of the trusted cluster to check whether there are identities.

2. If no identities are displayed, run the **ps -ef|grep ssh-agent** command to find the ssh-agent process, kill the process, and wait for the process to automatically restart.

3. Run the **ssh-add -l** command to check whether the identities have been added. If yes, manually run the **ssh** command to check whether the trust relationship is normal.

4. If identities exist, check whether the **authorized_keys** file in the / **home/omm/.ssh** directory contains the information in the **id_rsa.pub** file in the /home/omm/.ssh of the peer node. If no, manually add the information about the peer node.

- Check whether the permissions on the files in /home/omm/.ssh directory are correct.
- 6. Check the /var/log/Bigdata/nodeagent/scriptlog/ssh-agent-monitor.log file.
- 7. If the **home** directory of user **omm** is deleted, contact MRS support personnel.

16.17 How Do I Adjust the Memory Size of the manager-executor Process?

Symptom

The **manager-executor** process runs either on the Master1 or Master2 node in the MRS cluster in active/standby mode. This process is used to encapsulate the MRS management and control plane's operations on the MRS cluster, such as job submission, heartbeat reporting, certain alarm reporting, as well as cluster creation, scale-out, and scale-in. When you submit jobs on the MRS management and control plane, the Executor memory may become insufficient as the tasks increase or the number of concurrent tasks increases. As a result, the CPU usage is high and the Executor process experiences out-of-memory (OOM) errors.

Procedure

1. Log in to either the Master1 or Master2 node as user **root** and run the following command to switch to user **omm**:

su - omm

Run the following command to modify the catalina.sh script. Specifically, search for JAVA_OPTS in the script, find the configuration items similar to JAVA_OPTS="-Xms1024m -Xmx4096m, and change the values of the items to desired ones, and save the modification.

vim /opt/executor/bin/catalina.sh

```
JAVA_OPTS="-Xms1024m -Xmx4096m"
JAVA_OPTS="5JAVA_UPTS="5JAVA_UPTS="5JAVA_UPTS="5JAVA_UPTS="5JAVA_UPTS="5JAVA_UPTS="5JAVA_UPTS="$JAVA_UPTS="$JAVA_UPTS="$JAVA_UPTS="$JAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS="SJAVA_UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"UPTS-"
```

- 3. The **manager-executor** process only runs on either the Master1 or Master2 node in active/standby mode. Check whether it exists on the node before restarting it.
 - Log in to the Master1 and Master2 nodes and run the following command to check whether the process exists. If any command output is displayed, the process exists.

ps -ef | grep "/opt/executor" | grep -v grep



b. Run the following command to restart the process:

sh /opt/executor/bin/shutdown.shsh /opt/executor/bin/startup.sh

16.18 Can Master Node Specifications Be Adjusted in an MRS Cluster?

Yes.

You can scale up the specifications of a master node in an existing MRS cluster containing at least two master nodes. For details, see **Scaling Up Master Node Specifications**.

17 Kerberos Usage

17.1 How Do I Enable or Disable Kerberos Authentication for an Existing MRS Cluster?

Question

How Do I Enable or Disable Kerberos Authentication for an Existing MRS Cluster?

Answer

You cannot enable or disable the Kerberos service after the MRS cluster is created. You need to create an MRS cluster, enable or disable the Kerberos service, and migrate data from the original one.

17.2 What Are the Ports of the Kerberos Authentication Service?

Question

What Are the Ports of the Kerberos Authentication Service?

Answer

The Kerberos authentication service uses ports 21730 (TCP), 21731 (TCP/UDP), and 21732 (TCP/UDP).

17.3 How Do I Prevent Kerberos Authentication Expiration?

• Java applications:

Before connecting to HBase, HDFS, or other big data components, call loginUserFromKeytab() to create a UGI. Then, start a scheduled thread to

periodically check whether the Kerberos Authentication expires. Log in to the system again before the Kerberos Authentication expires.

```
private static void startCheckKeytabTgtAndReloginJob() {
    //The credential is checked every 10 minutes, and updated before the expiration time.
    ThreadPool.updateConfigThread.scheduleWithFixedDelay(() -> {
        try {
            UserGroupInformation.getLoginUser().checkTGTAndReloginFromKeytab();
            logger.warn("get tgt:{}", UserGroupInformation.getLoginUser().getTGT());
            logger.warn("Check Kerberos Tgt And Relogin From Keytab Finish.");
        } catch (IOException e) {
            logger.error("Check Kerberos Tgt And Relogin From Keytab Error", e);
        }
        }, 0, 10, TimeUnit.MINUTES);
        logger.warn("Start Check Keytab TGT And Relogin Job Success.");
    }
}
```

- Tasks executed in shell client:
 - a. Run the kinit command to authenticate the user.
 - b. Create a scheduled task of the operating system or any other scheduled task to run the **kinit** command to authenticate the user periodically.
 - c. Submit jobs to execute big data tasks.
- Spark jobs:

If you submit jobs using **spark-shell**, **spark-submit**, or **spark-sql**, you can specify **Keytab** and **Principal** in the command to perform authentication and periodically update the login credential and authorization tokens to prevent authentication expiration.

The following is an example:

spark-shell --principal spark2x/hadoop.<*System domain name*>@<*System domain name*> --keytab \${BIGDATA_HOME}/FusionInsight_Spark2x_XXX/install/FusionInsight-Spark2x-2.4.5/keytab/spark2x/SparkResource/spark2x.keytab --master yarn

18 Metadata Management

18.1 How Do I View MRS Hive Metadata?

- Hive metadata is stored in the GaussDB database of the MRS cluster. You can
 perform the following steps to view the metadata:
 - a. Log in to the DBServer active node as user **root**.
 - b. Log in to the Hive database:

su - omm

source \$DBSERVER_HOME/.dbservice_profile gsql -p 20051 -U *USER* -W *PASSWD* -d hivemeta

c. View all metadata tables in the Hive metadata database:

d+

- d. Run **q** to exit the page for viewing the metadata table.
- e. View data in the metadata table:

select * from Table name;

To query the IP address of the active DBServer node, log in to FusionInsight Manager, choose **Cluster** > **Services** > **DBService**, and click the **Instance** tab.

You can view the default username (USER) and initial password (PASSWD) of the DBservice database in **User Accounts**.

- If Hive metadata is stored in an external relational database, perform the following steps:
 - On the cluster **Dashboard** page, click **Manage** on the right of **Data** Connection.
 - b. On the displayed page, obtain the value of **Data Connection ID**.
 - c. On the MRS console, click **Data Connections**.
 - d. In the data connection list, locate the data connection based on the data connection ID obtained in **b**.
 - e. Click **Edit** in the **Operation** column of the data connection.

The **RDS Instance** and **Database** indicate the relational database in which the Hive metadata is stored.