

Distributed Cache Service

API Reference (Kuala Lumpur Region)

Date **2025-11-14**

Contents

1 Before You Start.....	1
2 API Overview.....	3
3 Calling APIs.....	4
3.1 Making an API Request.....	4
3.2 Authentication.....	7
3.3 Response.....	8
4 APIs V2 (Recommended).....	11
4.1 Lifecycle Management.....	11
4.1.1 Creating a DCS Instance.....	11
4.1.2 Querying All DCS Instances.....	25
4.1.3 Batch Deleting DCS Instances.....	46
4.1.4 Querying a DCS instance.....	51
4.1.5 Deleting an Instance.....	70
4.1.6 Modifying Details of a DCS Instance.....	72
4.1.7 Modifying Instance Specifications.....	82
4.2 Instance Management.....	90
4.2.1 Master/Standby Switchover.....	90
4.2.2 Changing the Password.....	94
4.2.3 Resetting a Password.....	98
4.2.4 Querying DCS Instance Statuses.....	103
4.2.5 Restarting DCS Instances or Clearing DCS Instance Data.....	111
4.2.6 Querying Statistics of All Running Instances.....	114
4.3 Shards and Replicas.....	119
4.3.1 Configuring Replica Priority.....	119
4.3.2 Removing the IP Address.....	123
4.3.3 Querying Details of Shards.....	127
4.3.4 Querying Instance Nodes in Batches.....	134
4.3.5 Querying Instance Nodes.....	142
4.4 Parameter Management.....	148
4.4.1 Querying DCS Instance Configuration Parameters.....	148
4.4.2 Modifying Configuration Parameters.....	155
4.4.3 Querying the List of Instance Parameter Modification Records.....	158

4.5 Backup and Restoration.....	162
4.5.1 Deleting Backup Files.....	162
4.5.2 Restoring a DCS Instance.....	164
4.5.3 Querying DCS Instance Restoration Records.....	167
4.5.4 Obtaining the Backup File URL.....	174
4.5.5 Backing Up a DCS Instance.....	178
4.5.6 Listing DCS Instance Backup Records.....	182
4.6 Data Migration.....	189
4.6.1 Creating a Backup Import Task.....	189
4.6.2 Listing Migration Tasks.....	197
4.6.3 Deleting Data Migration Tasks.....	206
4.6.4 Querying Details of a Data Migration Task.....	211
4.6.5 Configuring Auto-Reconnect for Migration Tasks.....	223
4.6.6 Stopping a Data Migration Task.....	228
4.6.7 Querying the Progress of an Online Migration Task.....	240
4.6.8 Creating an Online Data Migration Task.....	244
4.6.9 Configuring an Online Data Migration Task.....	250
4.6.10 Stopping Data Migration Tasks.....	257
4.6.11 Stopping Synchronization of a Data Migration Task.....	262
4.7 Cache Analysis.....	266
4.7.1 Creating a Big Key Analysis Task.....	266
4.7.2 Listing Big Key Analysis Tasks.....	273
4.7.3 Querying Big Key Analysis Details.....	280
4.7.4 Deleting a Big Key Analysis Task.....	288
4.7.5 Configuring Automatic Big Key Analysis.....	295
4.7.6 Querying the Configurations of Automatic Big Key Analysis.....	301
4.7.7 Creating a Hot Key Analysis Task.....	306
4.7.8 Listing Hot Key Analysis Tasks.....	314
4.7.9 Querying Hot Key Analysis Details.....	321
4.7.10 Deleting a Hot Key Analysis Task.....	329
4.7.11 Configuring Automatic Hot Key Analysis.....	337
4.7.12 Querying the Configurations of Automatic Hot Key Analysis.....	343
4.8 Log Management.....	348
4.8.1 Querying the Slow Log.....	348
4.8.2 Listing Redis Run Logs.....	357
4.8.3 Collecting Redis Run Logs.....	364
4.8.4 Obtaining the Log Download Link.....	368
4.9 Network Security.....	372
4.9.1 Configuring IP Whitelist Groups.....	372
4.9.2 Querying the IP Whitelist of a DCS Instance.....	378
4.10 Background Task Management.....	381
4.10.1 Listing Background Tasks.....	381

4.10.2 Deleting a Background Task.....	393
4.10.3 Querying the Job Execution Result of a Tenant.....	398
4.10.4 Deleting a Task in the Task Center.....	403
4.11 Instance Diagnosis.....	407
4.11.1 Listing Instance Diagnosis Tasks.....	407
4.11.2 Querying a Specified Diagnosis Report.....	412
4.12 Template Management.....	418
4.12.1 Viewing Parameter Templates.....	419
4.12.2 Creating a Custom Template.....	427
4.13 Other APIs.....	432
4.13.1 Querying Product Flavors.....	432
4.13.2 Listing Maintenance Time Windows.....	440
4.13.3 Querying the Tenant Quotas.....	444
4.13.4 Listing Monitored Objects on Secondary Dimensions Under a Primary Dimension.....	449
4.13.5 Listing Monitored Objects on Primary Dimensions.....	457
4.13.6 Querying AZs.....	462
5 Outdated APIs (V1).....	465
5.1 Lifecycle Management APIs.....	465
5.1.1 Creating a DCS Instance.....	465
5.1.2 Deleting a Single DCS Instance.....	474
5.1.3 Batch Deleting DCS Instances.....	475
5.1.4 Querying a DCS Instance.....	478
5.1.5 Querying All DCS Instances of a Tenant.....	483
5.1.6 Modifying Information About a DCS Instance.....	487
5.1.7 Scaling Up a DCS Instance.....	490
5.2 Instance Management APIs.....	492
5.2.1 Restarting DCS Instances or Clearing DCS Instance Data.....	492
5.2.2 Querying Statistics of All Running Instances.....	494
5.2.3 Querying DCS Instance Status.....	496
5.2.4 Changing the Password of a DCS Instance.....	501
5.3 Parameter Management APIs.....	503
5.3.1 Modifying Configuration Parameters.....	503
5.3.2 Querying Configuration Parameters.....	505
5.4 Data Migration APIs.....	517
5.4.1 Creating a Data Migration Task.....	517
5.5 Backup and Restoration APIs.....	522
5.5.1 Backing Up a DCS Instance.....	522
5.5.2 Restoring a DCS Instance.....	523
5.5.3 Querying DCS Instance Backup Records.....	525
5.5.4 Querying DCS Instance Restoration Records.....	529
5.5.5 Deleting Backup Files.....	531
5.6 Tag Management APIs.....	533

5.6.1 Querying All Tags of a Tenant V1.....	533
5.6.2 Adding or Deleting Tags in Batches V1.....	534
5.6.3 Querying Tag of a Specified Instance V1.....	536
5.7 Other APIs.....	537
5.7.1 Querying Service Specifications.....	537
5.7.2 Querying the Quota of a Tenant.....	546
5.7.3 Querying Maintenance Time Window.....	549
5.7.4 Querying AZ Information.....	551
6 Permissions and Supported Actions.....	553
7 Appendix.....	559
7.1 Status Codes.....	559
7.2 Error Codes.....	562
7.3 Obtaining a Project ID.....	596
7.4 Obtaining the Account Name and Account ID.....	597
7.5 DCS Instance Statuses.....	597
7.6 Instance Diagnosis IDs.....	598
A Change History.....	600

1 Before You Start

Welcome to Distributed Cache Service (DCS). DCS is an online, distributed, in-memory cache service compatible with Redis and Memcached. It is reliable, scalable, usable out of the box, and easy to manage, meeting your requirements for high read/write performance and fast data access.

In addition to the web console, you can also invoke APIs for managing your DCS O&M resources. This document describes how to use application programming interfaces (APIs) to perform operations on DCS, such as creating, deleting, and scaling up DCS instances. For details about all supported operations, see [API Overview](#).

DCS supports Representational State Transfer (REST) APIs, allowing you to call APIs using HTTPS. For details about API calling, see [Calling APIs](#).

NOTICE

- Some APIs are supported only in certain regions.
 - DCS is continuously upgraded with new functions, and the existing APIs are inevitably adjusted. For example, new response parameters may be added.
 - To reduce the impact of API changes, DCS is backward compatible with APIs when possible. However, when you use DCS, you should accept and ignore unused parameters and parameter values in returned content (in JSON format).
-

Endpoints


An endpoint is the **request address** for calling an API. Endpoints vary depending on services and regions. For the endpoints of all services, see [Regions and Endpoints](#).

Concepts

- IAM user
A user is created in IAM to use cloud services. Each user has its own identity credentials (password and access keys).
The account name, username, and password will be required for API authentication.

- Regions are geographic areas isolated from each other. Resources are region-specific and cannot be used across regions through internal network connections. For low network latency and quick resource access, select the nearest region.
- An AZ contains one or more physical data centers. Each AZ has independent cooling, fire extinguishing, moisture-proof, and electricity facilities. Within an AZ, compute, network, storage, and other resources are logically divided into multiple clusters. AZs within a region are interconnected by high-speed optical fibers for building cross-AZ high-availability systems.
- Project
A project corresponds to a region. Projects group and isolate resources (including compute, storage, and network resources) across physical regions. Users can be granted permissions in a default project to access all resources in the region associated with the project. For more refined access control, create subprojects under a project and create resources in the subprojects. Users can then be assigned permissions to access only specific resources in the subprojects.

Figure 1-1 Project isolating model



- Enterprise project
Enterprise projects group and manage resources across regions. Resources in enterprise projects are logically isolated. An enterprise project can contain resources of multiple regions, and resources can be added to or removed from enterprise projects.

2 API Overview

Table 2-1 APIs provided by DCS

Type	Description
Lifecycle management APIs	Create, query, delete, modify, and scale instances.
Instance management APIs	Restart instances, query instance status, change passwords, and query instance statistics.
Shard and replica management APIs	Configure replica priority and query shard details.
Parameter management APIs	Query and modify instance configuration parameters.
Data migration APIs	Create data migration tasks.
Backup and restoration APIs	Back up and restore instances, and view backup and restoration records.
Cache analysis APIs	Create big key and hot key analysis tasks.
Log management APIs	Query slow query and Redis run logs.
Network security APIs	Configure and query IP whitelist groups of an instance.
Background task management APIs	Query and delete background tasks.
Template management APIs	Query parameter templates and create custom templates.
Other APIs	Query AZ information, product specifications, and maintenance time window.

3 Calling APIs

3.1 Making an API Request

This section describes the structure of a REST API request, and uses the IAM API for obtaining a user token as an example to demonstrate how to call an API. The obtained token can then be used to authenticate the calling of other APIs.

Request URI

A request URI is in the following format:

{URI-scheme}://{Endpoint}/{resource-path}?{query-string}

Although a request URI is included in the request header, most programming languages or frameworks require the request URI to be transmitted separately.

Table 3-1 Parameters in a URI

Parameter	Description
URI-scheme	Protocol used to transmit requests. All APIs use HTTPS.
Endpoint	Domain name or IP address of the server bearing the REST service endpoint. The endpoint varies between services in different regions. It can be obtained from Regions and Endpoints . For example, the endpoint of IAM in the my-kualalumpur-1 region is iam.my-kualalumpur-1.myhuaweicloud.com .
resource-path	Access path of an API for performing a specified operation. Obtain the path from the URI of an API. For example, the resource-path of the API used to obtain a user token is /v3/auth/tokens .

Parameter	Description
query-string	Query parameter, which is optional. Ensure that a question mark (?) is included before each query parameter that is in the format of " <i>Parameter name=Parameter value</i> ". For example, ? limit=10 indicates that a maximum of 10 data records will be displayed.

NOTE

To simplify the URI display in this document, each API is provided only with a **resource-path** and a request method. The **URI-scheme** of all APIs is **HTTPS**, and the endpoints of all APIs in the same region are identical.

Request Methods

The HTTP protocol defines the following request methods that can be used to send a request to the server:

- **GET**: requests the server to return specified resources.
- **PUT**: requests the server to update specified resources.
- **POST**: requests the server to add resources or perform special operations.
- **DELETE**: requests the server to delete specified resources, for example, an object.
- **HEAD**: same as GET except that the server must return only the response header.
- **PATCH**: requests a server to update a part of a specified resource. If the resource does not exist, a new resource will be created.

For example, in the case of the API used to obtain a user token, the request method is POST. The request is as follows:

```
POST https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/tokens
```

Request Header

You can also add additional fields to a request, such as the fields required by a specified URI or an HTTP method. For example, to request for the authentication information, add **Content-Type**, which specifies the request body type.

Common request headers are as follows:

- **Content-Type**: specifies the request body type or format. This field is mandatory and its default value is **application/json**. Other values of this field will be provided for specific APIs if any.
- **X-Auth-Token**: specifies a user token only for token-based API authentication. The user token is a response to the API used to obtain a user token. This API is the only one that does not require authentication.

NOTE

In addition to supporting token-based authentication, also support authentication using access key ID/secret access key (AK/SK). During AK/SK-based authentication, an SDK is used to sign the request, and the **Authorization** (signature information) and **X-Sdk-Date** (time when the request is sent) header fields are automatically added to the request.

For details, see [AK/SK-based Authentication](#).

The API used to obtain a user token does not require authentication. Therefore, only the **Content-Type** field needs to be added to requests for calling the API. An example of such requests is as follows:

```
POST https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/tokens
Content-Type: application/json
```

Request Body

The body of a request is often sent in a structured format as specified in the **Content-Type** header field. The request body transfers content except the request header.

The request body varies between APIs. Some APIs do not require the request body, such as the APIs requested using the GET and DELETE methods.

In the case of the API used to obtain a user token, the request parameters and parameter description can be obtained from the API request. The following provides an example request with a body included. Set **username** to the name of a user, **domainname** to the name of the account that the user belongs to, ********* to the user's login password, and **xxxxxxxxxxxxxxxxxxxx** to the project name. You can learn more information about projects from [Regions and Endpoints](#).

NOTE

The **scope** parameter specifies where a token takes effect. You can set **scope** to an account or a project under an account. In the following example, the token takes effect only for the resources in a specified project. For more information about this API, see Obtaining a User Token.

```
POST https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/tokens
Content-Type: application/json
```

```
{
  "auth": {
    "identity": {
      "methods": [
        "password"
      ],
      "password": {
        "user": {
          "name": "username",
          "password": "*****",
          "domain": {
            "name": "domainname"
          }
        }
      }
    },
    "scope": {
      "project": {
        "name": "xxxxxxxxxxxxxxxxxxxx"
      }
    }
  }
}
```

```
}  
}  
}
```

If all data required by a request is available, you can send the request to call an API through [curl](#), [Postman](#), or coding. In the response to the API used to obtain a user token, **x-subject-token** is the desired user token. This token can then be used to authenticate the calling of other APIs.

3.2 Authentication

Requests for calling an API can be authenticated using either of the following methods:

- Token-based authentication: Requests are authenticated using a token.
- AK/SK-based authentication: Requests are authenticated by encrypting the request body using an AK/SK pair. AK/SK-based authentication is recommended because it is more secure than token-based authentication.

Token-based Authentication

A token specifies temporary permissions in a computer system. During API authentication using a token, the token is added to requests to get permissions for calling the API.

NOTE

- The validity period of a token is 24 hours. When using a token for authentication, cache it to prevent frequently calling the IAM API used to obtain a user token.
- Ensure that the token is valid while you use it. Using a token that will soon expire may cause API calling failures.

You can obtain a token by [calling an API](#).

When calling the API used for [obtaining a user token](#), you must set **auth.scope** in the request body to **project**.

```
{  
  "auth": {  
    "identity": {  
      "methods": [  
        "password"  
      ],  
      "password": {  
        "user": {  
          "name": "username", //IAM username.  
          "password": "*****#", //IAM user password. You are advised to store it in ciphertext in the  
configuration file or an environment variable.  
          "domain": {  
            "name": "domainname" //Name of the account of the IAM user.  
          }  
        }  
      }  
    },  
    "scope": {  
      "project": {  
        "name": "xxxxxxx" //Project name.  
      }  
    }  
  }  
}
```

After a token is obtained, the **X-Auth-Token** header field must be added to requests to specify the token when calling other APIs. For example, if the token is **ABCDEFJ....**, **X-Auth-Token: ABCDEFJ....** can be added to a request as follows:

```
GET https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/projects
Content-Type: application/json
X-Auth-Token: ABCDEFJ....
```

AK/SK-based Authentication

In AK/SK-based authentication, AK/SK is used to sign requests and the signature is then added to the requests for authentication.

- AK: access key ID, which is a unique identifier used in conjunction with a secret access key to sign requests cryptographically.
- SK: secret access key used in conjunction with an AK to sign requests cryptographically. It identifies a request sender and prevents the request from being modified.

CAUTION

- AK/SK-based authentication supports API requests with a body not larger than 12 MB. For API requests with a larger body, token-based authentication is recommended.
- APIG checks the time format and compares the time with the time when APIG receives the request. If the time difference exceeds 15 minutes, APIG will reject the request. The local time on the client must be synchronized with the clock server to avoid a large offset in the value of the **X-Sdk-Date** request header.

In AK/SK-based authentication, you can use an AK/SK to sign requests based on the signature algorithm or use the signing SDK to sign requests. For details about how to sign requests and use the signing SDK, see [API Request Signing Guide](#).

CAUTION

The signature SDK only supports signature, which is different from the SDKs provided by services.

3.3 Response

Status Code

After sending a request, you will receive a response, including a status code, response header, and response body.

A status code is a group of digits, ranging from 1xx to 5xx. It indicates the status of a request. For more information, see [Status Codes](#).

For example, if status code **201** is returned for calling the API used to obtain a user token, the request is successful.

Response Header

Similar to a request, a response also has a header, for example, **Content-Type**.

Figure 3-1 shows the response header for the API used to obtain a user token. The **x-subject-token** header field is the desired user token. This token can then be used to authenticate the calling of other APIs.

Figure 3-1 Header fields of the response to the request for obtaining a user token

```

connection → keep-alive

content-type → application/json

date → Tue, 12 Feb 2019 06:52:13 GMT

server → Web Server

strict-transport-security → max-age=31536000; includeSubdomains;

transfer-encoding → chunked

via → proxy A

x-content-type-options → nosniff

x-download-options → noopen

x-frame-options → SAMEORIGIN

x-iam-trace-id → 218d45ab-d674-4995-af3a-2d0255ba41b5

x-subject-token
→ MIIYXQYJKoZIhvcNAQCoIITjCCGEoCAQExDTALBglghkgBZQMEAgEwgharBgkqhkiG9w0BBgwGgghacBIIWmHsidG9rZW4iOnsiZmVhX2luc19hdCI6IjwMTktMDItMTNtMUMC
fj3KJsf6YgKnpVNRBwZe25eb78S2OZkqACgkqjCgUeH4KQpdt112oXXt6kz4qgpcCib6H4P4n0V9V9ejaAgZlVeFiytLWT1GSO0zxKZmlQHQj82H8qHdglZ09fuEbL5dMhdavj+33wEI
xHRC9I87o+k9-
j+CMZSEB7bUGd5UjfeRASX1jipPEGA270g1Fruool6jqglFkNPQuFSOU8+uSstVwRtNfsC+qTp22Rko5MCqFGQ8LcuUxC3a+9CMBnOintWW7oeRUVhVpxk8pxiX1wTEboX-
RzT6MUBpyGw-oPNFYxJECkNoH3HROzv0vN--n5d6Nbxg==

x-xss-protection → 1; mode=block;

```

Response Body

The body of a response is often returned in structured format as specified in the **Content-Type** header field. The response body transfers content except the response header.

The following is part of the response body for the API used to obtain a user token.

```
{
  "token": {
    "expires_at": "2019-02-13T06:52:13.855000Z",
    "methods": [
      "password"
    ],
    "catalog": [
      {
        "endpoints": [
          {
            "region_id": "XXXXXXX",

```

If an error occurs during API calling, an error code and a message will be displayed. The following shows an error response body.

```
{
  "error": {
    "code": "111400060",
    "message": "instance name exists."
  }
}
```

In the response body, **error_code** is an error code, and **error_msg** provides information about the error.

4 APIs V2 (Recommended)

4.1 Lifecycle Management

4.1.1 Creating a DCS Instance

Function

This API is used to create a DCS instance which is billed in pay-per-use mode.

URI

POST /v2/{project_id}/instances

Table 4-1 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

Table 4-2 Request body parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Instance name. An instance name can contain letters, digits, underscores (_), and hyphens (-) and must start with a letter or digit. When you create only one instance at a time, the value of this parameter can contain 4 to 64 characters. When you create multiple instances at a time, the value of this parameter can contain 4 to 56 characters. The instances are named in the format of <i>custom name-n</i>, where <i>n</i> starts from 000 and is incremented by 1. For example, if you create two instances and set the custom name to dc_s_demo, the two instances are respectively named dc_s_demo-000 and dc_s_demo-001.
engine	Yes	String	Cache engine: Redis.
engine_version	No	String	Cache version. If the cache engine is Redis, this parameter is mandatory. The version can be 3.0/4.0/5.0/6.0. If the cache engine is Memcached, this parameter is optional and can be left blank.

Parameter	Mandatory	Type	Description
capacity	Yes	Float	Cache capacity (GB). • For a single-node or master/standby DCS Redis 3.0 instance, the value can be 2, 4, 8, 16, 32, or 64. For a Proxy Cluster DCS Redis 3.0 instance, the value can be 64, 128, 256, 512, or 1024. • For a single-node or master/standby DCS Redis 4.0/5.0/6.0/7.0 instance, the value can be 0.125, 0.25, 0.5, 1, 2, 4, 8, 16, 24, 32, 48, or 64. For a cluster instance, the value can be 4, 8, 16, 24, 32, 48, 64, 96, 128, 192, 256, 384, 512, 768, or **1024. • For a single-node or master/standby DCS Memcached instance, the value can be 2, 4, 8, 16, 32, or 64.
spec_code	Yes	String	Product flavor. The query method is as follows: • Method 1: Log in to the DCS console, go to the instance creation page, and check the instance flavor. • Method 2: Call the API used to query product flavors.

Parameter	Mandatory	Type	Description
az_codes	Yes	Array of strings	ID of the AZ where the cache node resides and which has available resources. For details, see Querying AZs. Check whether the desired AZ has available resources. Master/Standby, Proxy Cluster, and Redis Cluster DCS instances support cross-AZ deployment. You can specify an AZ for the replica node. When specifying AZs for nodes, use commas (,) to separate multiple AZs. For details, see the example request.
vpc_id	Yes	String	VPC ID. To obtain the value: • Method 1: Log in to the VPC console and view the VPC ID on the My VPCs page. • Method 2: Call the VPC API. For details, see the API for querying VPCs.
subnet_id	Yes	String	Network ID of the subnet. To obtain the value: • Method 1: Log in to VPC console and click the subnet under the VPC. You can view the network ID on the displayed page. • Method 2: Call the VPC API. For details, see the API for querying subnets.

Parameter	Mandatory	Type	Description
security_group_id	No	String	Security group to which the instance belongs. This parameter is mandatory when the engine is Memcached. Memcached instances support access control based on security groups. This parameter is optional when the engine is Redis and the version is 4.0 or later. This parameter is mandatory when the engine is Redis and the version is 3.0. DCS Redis 4.0 and later instances do not support security groups but whitelists. To obtain the value: - Method 1: Log in to the VPC console and view the security group ID on the security group details page. - Method 2: Call the VPC API. For details, see the API for querying security group details.
publicip_id	No	String	ID of the EIP bound to the DCS Redis instance. This parameter is reserved. Retain the default value.
enterprise_project_id	No	String	Enterprise project ID.
enterprise_project_name	No	String	Enterprise project name.
description	No	String	Instance description. The description can contain a maximum of 1024 characters. NOTE The backslash (\) and quotation mark (") are special characters for JSON messages. When using these characters in a parameter value, add the escape character (\) before the characters, for example, \\ and \".

Parameter	Mandatory	Type	Description
enable_ssl	No	Boolean	This parameter is reserved. Retain the default value.
private_ip	No	String	IP address that is specified for a DCS instance.
instance_num	No	Integer	Number of instances to be created in batches. This parameter is available for DCS Redis instances. Default value: 1 . Value range: 1 to 100
maintain_begin	No	String	UTC time when the maintenance time window starts. The format is <i>HH:mm:ss</i> . • The start time and end time of the maintenance window must be specified time segments. For details, see Listing Maintenance Time Windows. • For example, the start time must be on the hour, such as 18:00:00 and 19:00:00. • The start time and end time must be set in a pair or both left blank. In this case, the system uses a default start time 18:00:00.

Parameter	Mandatory	Type	Description
maintain_end	No	String	UTC time when the maintenance time window ends. The format is <i>HH:mm:ss</i>. - The start time and end time of the maintenance window must be specified time segments. For details, see Listing Maintenance Time Windows. - The end time is one hour later than the start time. For example, if the start time is 18:00:00, the end time is 19:00:00. - The start time and end time must be set in a pair or both left blank. In this case, the system uses a default end time 19:00:00.
password	No	String	Password of a DCS instance. NOTE When no_password_access is set to false or not specified, the request must contain the password parameter. The password of a DCS Redis instance must meet the following complexity requirements: - Contains 8 to 32 characters. - Contains at least three of the following character types: - Lowercase letters - Uppercase letters - Digits - Special characters <code>`~!@#\$%^&*()-_+=+\\{ },<.>/?</code>

Parameter	Mandatory	Type	Description
no_password_access	No	Boolean	Whether the instance can be accessed without a password. true: The instance can be accessed without a password. false: The instance can be accessed only after password authentication. If this parameter is not set, the default value false is used.
bss_param	No	BssParam object	Parameter related to the billing mode. If this parameter is left blank, the default billing mode is pay-per-use. Other billing modes are not supported.
instance_backup_policy	No	BackupPolicy object	Backup policy. This parameter is supported when the instance type is master/standby or cluster.
tags	No	Array of ResourceTag objects	Instance tag key and value.
access_user	No	String	If the cache engine is Redis, leave this parameter empty. If the cache engine is Memcached and no_password_access is set to false, this parameter is required, indicating that you need to access the DCS instance in password mode. A username can contain 1 to 64 characters and must start with a letter. Only letters, digits, underscores (_), and hyphens (-) are allowed. This parameter is optional if the cache engine is Memcached.
enable_publicip	No	Boolean	This parameter is reserved. Retain the default value.

Parameter	Mandatory	Type	Description
port	No	Integer	Port customization. This parameter is supported only by Redis 4.0 and later instances and not by Redis 3.0 and Memcached instances. If this parameter is not sent or is left empty when you create a Redis 4.0 or later instance, the default port 6379 will be used. To customize a port, specify a port number in the range from 1 to 65535.
rename_commands	No	Object	Critical commands can be renamed. This parameter is supported only by Redis 4.0 and later instances and not by Redis 3.0 and Memcached instances. If this parameter is not sent or is left empty when you create a Redis 4.0 or later instance, no critical command will be renamed. Currently, only COMMAND , KEYS , FLUSHDB , FLUSHALL , SCAN , HSCAN , SSCAN , ZSCAN , and HGETALL commands can be renamed.
template_id	No	String	Parameter template ID. If it is not specified, the default parameter template is used. To specify a custom parameter template, obtain the template ID by referring to Querying Parameter Templates

Table 4-3 BssParam

Parameter	Mandatory	Type	Description
is_auto_renew	No	String	This parameter is currently not used.
charging_mode	Yes	String	Billing mode. The default value is postPaid , indicating pay-per-use.

Parameter	Mandatory	Type	Description
is_auto_pay	No	String	This parameter is currently not used.
period_type	No	String	This parameter is currently not used.
period_num	No	Integer	This parameter is currently not used.

Table 4-4 BackupPolicy

Parameter	Mandatory	Type	Description
backup_type	Yes	String	Backup type. • auto: automatic backup • manual: manual backup
save_days	No	Integer	This parameter is mandatory when backup_type is set to auto . Retention period, in days. The value ranges from 1 to 7.
periodical_backup_plan	No	BackupPlan object	Backup schedule. This parameter is mandatory when backup_type is set to auto .

Table 4-5 BackupPlan

Parameter	Mandatory	Type	Description
timezone_offset	No	String	Time zone in which backup is performed. Range: GMT – 12:00 to GMT +12:00. If this parameter is left blank, the current time zone of the DCS-Server VM is used by default.
backup_at	Yes	Array of integers	Day in a week on which backup starts. The value ranges from 1 to 7 , where 1 indicates Monday, and 7 indicates Sunday.
period_type	Yes	String	Interval at which backup is performed, which supports only weekly currently.

Parameter	Mandatory	Type	Description
begin_at	Yes	String	Time at which backup starts. 00:00-01:00 indicates that the backup starts at 00:00. The value must be on the hour. The backup interval is 1 hour.

Table 4-6 ResourceTag

Parameter	Mandatory	Type	Description
key	Yes	String	Tag key. • Must be specified. • Must be unique for each resource. • Can contain a maximum of 36 characters. • Must be unique and cannot be empty.
value	No	String	Tag value. • This parameter is mandatory when action is set to create and is optional when action is set to delete. • It can contain a maximum of 43 characters.

Response Parameters

Status code: 200

Table 4-7 Response body parameters

Parameter	Type	Description
instances	Array of Instances objects	DCS instance ID and name. If multiple DCS instances are created at a time, multiple DCS instance IDs and names will be returned.

Table 4-8 Instances

Parameter	Type	Description
instance_id	String	DCS instance ID.
instance_name	String	DCS instance name.

Status code: 400

Table 4-9 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Status code: 401

Table 4-10 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Status code: 403

Table 4-11 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Status code: 404

Table 4-12 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Status code: 500

Table 4-13 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Example Requests

- Creating a DCS Redis instance

POST https://{dcs_endpoint}/v2/{project_id}/instances

```
{
  "name": "dcs-APItest",
  "description": "Test",
  "engine": "Redis",
  "engine_version": "5.0",
  "enterprise_project_id": 0,
  "enterprise_project_name": "default",
  "vpc_id": "5e37b3be-950a-48e1-b498-65b63d336481",
  "enable_ssl": false,
  "private_ip": "",
  "az_codes": [ "region01" ],
  "capacity": 1,
  "access_user": "",
  "password": "*****",
  "enable_publicip": false,
  "spec_code": "redis.single.xu1.large.1",
  "subnet_id": "a4112635-3ec0-471c-95c3-5cf49b9533af",
  "no_password_access": false,
  "template_id": "b3ecc9c7-1133-4c47-a06a-21366e227d61"
}
```

- Creating a pay-per-use, master/standby DCS Redis instance with a customized port, renamed commands, and cross-AZ deployment

```
{
  "enterprise_project_name": "default",
}
```

```
"vpc_id" : "c5cd009b-9ba9-41f2-9a26-2b8c3f3ffd39",
"description" : "Test",
"port" : 4040,
"enable_ssl" : false,
"private_ip" : "",
"az_codes" : [ "region01", "region02" ],
"capacity" : 2,
"access_user" : "",
"instance_num" : 1,
"enterprise_project_id" : 0,
"password" : "*****",
"enable_publicip" : false,
"engine" : "Redis",
"spec_code" : "redis.ha.au1.large.2",
"name" : "dcs-demo",
"subnet_id" : "7e95c4d6-d7af-424c-a3cf-2be10968fe81",
"engine_version" : "4.0",
"no_password_access" : false,
"rename_commands" : {
  "keys" : "keys001",
  "flushdb" : "flushdb001",
  "flushall" : "flushall001"
}
}
```

Example Responses

Status code: 200

The DCS instance creation task is submitted successfully.

NOTE

If the instance status is **RUNNING**, the DCS instance has been successfully created.

- Example 1

```
{
  "instances" : [ {
    "instance_id" : "3c49fd6b-fc7c-419e-9644-b6cce008653f",
    "instance_name" : "dcs-test005"
  } ]
}
```

- Example 2

```
{
  "instances" : [ {
    "instance_id" : "77284d69-cd51-4bf1-aa30-2e60f055800c",
    "instance_name" : "dcs-APItest1"
  } ]
}
```

Status code: 400

Invalid request.

```
{
  "error_code" : "DCS.1004",
  "error_msg" : "Project ID does not match the token."
}
```

Status code: 401

Invalid authentication information.

```
{
  "error_code" : "DCS.1001",
  "error_msg" : "Invalid token."
}
```

Status code: 403

The request is rejected.

```
{
  "error_code" : "DCS.2003",
  "error_msg" : "This role does not have the permission to perform this operation."
}
```

Status code: 404

The requested resource is not found.

```
{
  "error_code" : "DCS.4001",
  "error_msg" : "The requested URL does not exist."
}
```

Status code: 500

Internal service error.

```
{
  "error_code" : "DCS.5000",
  "error_msg" : "Internal service error."
}
```

Status Codes

Status Code	Description
200	The DCS instance creation task is submitted successfully. NOTE If the instance status is RUNNING , the DCS instance has been successfully created.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.1.2 Querying All DCS Instances

Function

This API is used to query DCS instances of a tenant, and allows you to specify query criteria.

URI

GET /v2/{project_id}/instances

Table 4-14 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Table 4-15 Query Parameters

Parameter	Mandatory	Type	Description
instance_id	No	String	Parameter description: Instance ID, which can be viewed on the instance details page on the DCS console. Constraints: N/A. Value range: N/A. Default value: N/A.
include_failure	No	String	Parameter description: Indicates whether to return the number of instances that fail to be created. Constraints: N/A. Value range: • true: yes • false: no Default value: false

Parameter	Mandatory	Type	Description
include_delete	No	String	Parameter description: Whether to return the number of instances that have been deleted. Constraints: N/A. Value range: • true: yes • false: no Default value: false
name	No	String	Parameter description: Instance name. Constraints: N/A. Value range: N/A. Default value: N/A.
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0

Parameter	Mandatory	Type	Description
limit	No	Integer	Parameter description: Number of records displayed on each page. Constraints: N/A. Value range: 1–1000 Default value: 10
status	No	String	Parameter description: Instance status. Constraints: N/A. Value range: For details, see DCS Instance Statuses . Default value: N/A.
name_equal	No	String	Parameter description: Exact query by instance name. Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
tags	No	String	Parameter description: Query by instance tag key-value pair. <i>{key}</i> indicates the tag key, and <i>{value}</i> indicates the tag value. Constraints: To query instances with multiple tag keys and values, separate key-value pairs with commas (,). Value range: N/A. Default value: N/A.
ip	No	String	Parameter description: IP address of a DCS instance, for example, 192.168.7.146 It can be viewed on the instance details page on the DCS console. Constraints: N/A. Value range: N/A. Default value: N/A.
capacity	No	String	Parameter description: DCS instance memory, in GB. Constraints: N/A. Value range: N/A. Default value: N/A.

Parameter	Mandatory	Type	Description
is_recycle	No	Boolean	Definition: Whether to query instances in the recycle bin. Constraints: N/A Range: • true: The instances in the recycle bin are returned. • false: The DCS instance list is returned. Default Value: false

Request Parameters

None

Response Parameters

Status code: 200

Table 4-16 Response body parameters

Parameter	Type	Description
instance_num	Integer	Parameter description: Number of instances. Value range: N/A.
instances	Array of InstanceListInfo objects	Parameter description: Instance details array. Value range: N/A.

Table 4-17 InstanceListInfo

Parameter	Type	Description
publicip_id	String	Definition ID of the EIP bound to a DCS Redis instance. This parameter is reserved. The value is null . Range N/A
vpc_name	String	Parameter description: VPC name. Value range: N/A.
charging_mode	Integer	Definition Billing mode. Range 0: pay-per-use
vpc_id	String	Parameter description: ID of the VPC where the DCS Redis instance is located. Value range: N/A.
subnet_id	String	Parameter description: ID of the subnet bound to a DCS Redis instance. Value range: N/A.
security_group_id	String	Parameter description: ID of the security group bound to the DCS Redis instance. Value range: N/A.
created_at	String	Parameter description: Instance creation time. For example, 2017-03-31T12:24:46.297Z. Value range: N/A.

Parameter	Type	Description
updated_at	String	Parameter description: Instance update time. Format: 2017-03-31T19:24:46.297Z. Value range: N/A.
enable_ssl	Boolean	Definition This parameter is reserved. Range N/A
max_memory	Integer	Parameter description: Total memory of an instance, in MB. Value range: N/A.
used_memory	Integer	Parameter description: Used memory of an instance, in MB. Value range: N/A.
publicip_address	String	Definition EIP bound to the DCS Redis instance. This parameter is reserved. The value is null . Range N/A
capacity	Integer	Parameter description: Cache size of the instance, in GB. Value range: N/A.
capacity_minor	String	Parameter description: Memory of a DCS instance whose size is less than 1 GB, in GB. Value range: N/A.
order_id	String	Definition Order ID. The value is null when a pay-per-use instance is created. Range N/A

Parameter	Type	Description
maintain_begin	String	Parameter description: UTC time when the maintenance time window starts. The format is <i>HH:mm:ss</i> . Value range: N/A.
maintain_end	String	Parameter description: UTC time when the maintenance time window ends. The format is <i>HH:mm:ss</i> . Value range: N/A.
engine	String	Definition Cache engine. Range • Redis • Memcached
engine_version	String	Definition Cache version. Range The engine version of a DCS Redis instance can be: • 3.0 • 4.0 • 5.0 • 6.0 • 7.0 If the cache engine is Memcached, this parameter is blank.
service_upgrade	Boolean	Parameter description: Whether an upgrade task has been created for an instance. Value range: • true: yes • false: no

Parameter	Type	Description
no_password_access	String	Parameter description: Indicates whether password-protected access is enabled for the instance. Value range: • true: no • false: yes
service_task_id	String	Parameter description: ID of an upgrade task. • This parameter is valid when service_upgrade is set to true. • This parameter is blank when service_upgrade is set to false. Value range: N/A.
ip	String	Parameter description: IP address of the DCS instance. For a cluster instance, multiple IP addresses are returned and separated by commas (,). For example, 192.168.0.1, 192.168.0.2 . Value range: N/A.
access_user	String	Parameter description: Username for accessing a password-protected DCS instance. Value range: N/A.
instance_id	String	Parameter description: Instance ID. Value range: N/A.
enable_publicip	Boolean	Definition This parameter is reserved. Range N/A
port	Integer	Parameter description: Port of a DCS instance. Value range: N/A.

Parameter	Type	Description
user_id	String	Parameter description: ID of the user to which the instance belongs. Value range: N/A.
user_name	String	Parameter description: Username of the instance. Value range: N/A.
domain_name	String	Parameter description: Domain name of a instance. Value range: N/A.
readonly_domain_name	String	Parameter description: Read-only domain name of the instance. This parameter is available only for master/standby instances. Value range: N/A.
name	String	Parameter description: Instance name. Value range: N/A.
spec_code	String	Parameter description: Product flavor code. Value range: N/A.
status	String	Parameter description: Instance status. Value range: For details, see DCS Instance Statuses .
tags	Array of ResourceTags objects	Parameter description: Instance tag key and value. Value range: N/A.

Parameter	Type	Description
enterprise_project_id	String	Parameter description: Enterprise project ID. Value range: N/A.
description	String	Parameter description: Instance description. Value range: N/A.
cpu_type	String	Parameter description: CPU type of the instance. Value range: x86_64: x86-based aarch64: Arm-based
az_codes	Array of strings	Parameter description: AZs where there are available resources. Value range: N/A.
features	Features object	Parameter description: Features supported by the instance. Value range: N/A.
sub_status	String	Parameter description: Instance sub-status. Value range: N/A.
deleted_time	String	Definition: Time when an instance is deleted. This parameter is displayed only for instances in the recycle bin. Format: 2017-03-31T19:24:46.297Z. Range: N/A

Parameter	Type	Description
release_time	String	Definition: Estimated time when an instance in the recycle bin will be released. This parameter is displayed only for instances in the recycle bin. Format: 2017-03-31T19:24:46.297Z. Range: N/A
available_zones	Array of strings	Definition: ID of the AZ where resources are available. This parameter is displayed only for instances in the recycle bin.
backup_id	String	Definition: Backup ID. This parameter is displayed only for instances in the recycle bin. Range: N/A
instance_backup_policy	InstanceBackupPolicy object	Definition: Backup policy. This parameter is supported when the instance type is master/standby or cluster. This parameter is displayed only for instances in the recycle bin. Range: N/A
cache_mode	String	Definition DCS instance type. This parameter is displayed only for instances in the recycle bin. Range • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster
enable_ipv6	Boolean	Definition: Whether IPv4/IPv6 dual-stack access is enabled. This parameter is displayed only for instances in the recycle bin. Range: true: Yes false: No

Parameter	Type	Description
rename_commands	RenameCommandResp object	Definition: Command renaming list, which is displayed only for instances in the recycle bin.

Table 4-18 ResourceTags

Parameter	Type	Description
key	String	Parameter description: Tag key. Value range: N/A
value	String	Definition: Tag value. Range: N/A

Table 4-19 Features

Parameter	Type	Description
support_acl	Boolean	Parameter description: Whether ACL is supported. Value range: • true: Yes • false: No
support_transparent_client_ip	Boolean	Parameter description: Whether client IP pass-through is enabled. Value range: • true: Yes • false: No
support_ssl	Boolean	Parameter description: Whether SSL is supported. Value range: • true: Yes • false: No

Parameter	Type	Description
support_acl_read_policy	Boolean	Definition: Whether the instance supports the ACL read-only routing policy. Range: • true: Yes • false: No
support_audit_log	Boolean	Parameter description: Whether audit logs are supported. Value range: • true: Yes • false: No

Table 4-20 InstanceBackupPolicy

Parameter	Type	Description
backup_policy_id	String	Parameter description: Backup policy ID. Value range: N/A.
created_at	String	Parameter description: Creation time, in the format of 2022-04-11T09:45:24.790Z. Value range: N/A.
updated_at	String	Parameter description: Update time, in the format of 2022-04-12T02:22:03.269Z. Value range: N/A.
policy	BackupPolicyResp object	Parameter description: Backup policy. Value range: N/A.
tenant_id	String	Parameter description: Tenant ID. Value range: N/A.

Table 4-21 BackupPolicyResp

Parameter	Type	Description
backup_type	String	Parameter description: Backup type. Value range: • auto: automatic backup • manual: manual backup
save_days	Integer	Parameter description: Retention period, in days. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: 1-7
periodical_backup_plan	BackupPlan object	Parameter description: Backup plan. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: N/A.

Table 4-22 BackupPlan

Parameter	Type	Description
timezone_offset	String	Parameter description: Time zone of the backup. This parameter is no longer used. Value range: N/A.
backup_at	Array of integers	Parameter description: Day on which the backup starts every week. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: 1-7: Monday to Sunday

Parameter	Type	Description
period_type	String	Parameter description: Interval at which backup is performed, which supports only weekly currently. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: N/A.
begin_at	String	Parameter description: UTC time when the backup starts. For example, 00:00-01:00 indicates that the backup starts at 00:00 (UTC time). The value must be on the hour. The backup interval is 1 hour. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: N/A.

Table 4-23 RenameCommandResp

Parameter	Type	Description
command	String	Definition: Command COMMAND that can be renamed. Range: N/A
flushall	String	Definition: Command FLUSHALL that can be renamed. Range: N/A
flushdb	String	Definition: Command FLUSHDB that can be renamed. Range: N/A

Parameter	Type	Description
hgetall	String	Definition: Command HGETALL that can be renamed. Range: N/A
keys	String	Definition: Command KEYS that can be renamed. Range: N/A

Status code: 400

Table 4-24 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-25 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-26 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-27 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-28 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

- Querying running instances

```
GET https://{dcs_endpoint}/v2/{project_id}/instances?
offset=0&limit=10&name={name}&status={status}&id={id}&include_failure=true&include_delete=true&
name_equal=false
```

- Querying instances in the recycle bin

```
GET https://{dcs_endpoint}/v2/{project_id}/instances?is_recycle=true
```

Example Responses

Status code: 200

All instances are listed successfully.

```
{
  "instance_num" : 1,
  "instances" : [ {
    "publicip_id" : { },
    "vpc_name" : "dcs-beta",
    "charging_mode" : 0,
    "vpc_id" : "5e37b3be-950a-48e1-b498-65b63d336481",
    "subnet_id" : "a4112635-3ec0-471c-95c3-5cf49b9533af",
    "user_name" : "clouduser",
    "created_at" : "2022-08-29T09:00:34.335Z",
    "updated_at" : "2022-08-29T09:00:34.335Z",
    "enable_ssl" : false,
    "max_memory" : 128,
    "publicip_address" : null,
    "capacity" : 0,
    "order_id" : null,
    "maintain_begin" : "18:00:00",
    "engine" : "Redis",
    "maintain_end" : "19:00:00",
    "capacity_minor" : ".125",
    "service_upgrade" : false,
    "no_password_access" : true,
    "service_task_id" : "",
    "ip" : "192.168.0.195",
    "used_memory" : 2,
    "access_user" : null,
    "instance_id" : "c830053e-d5a3-4bc0-b6d6-ca37d1ea9dd5",
    "enable_publicip" : false,
    "port" : 6379,
    "user_id" : "d53977d1adfb49c5b025ba7d33a13fd7",
    "domain_name" : "redis-c830053e-d5a3-4bc0-b6d6-ca37d1ea9dd5.dcs.**cloud.com",
    "name" : "dcs-lpvo0829",
    "spec_code" : "redis.ha.xu1.tiny.r2.128",
    "engine_version" : "5.0",
    "status" : "RUNNING",
    "security_group_id" : "securityGroupId",
    "enterprise_project_id" : 0,
    "tags" : [ {
      "key" : 1,
      "value" : "DCS"
    } ],
    "az_codes" : [ "region01", "region02" ],
    "description" : "Instance description.",
    "cpu_type" : "x86_64",
    "features" : {
      "support_acl" : true,
      "support_transparent_client_ip" : true,
      "support_ssl" : false,
      "support_audit_log" : false
    },
    "sub_status" : "normal"
  } ],
}
```

```
}]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4800",  
  "error_msg" : "Invalid offset in the request."  
}
```

Status Codes

Status Code	Description
200	All instances are listed successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.1.3 Batch Deleting DCS Instances

Function

This API is used to delete multiple DCS instances at a time.

URI

DELETE /v2/{project_id}/instances

Table 4-29 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A

Table 4-30 Query Parameters

Parameter	Mandatory	Type	Description
all_failure	No	Boolean	Definition: Whether to delete all DCS instances that failed to be created. Options: Constraints: N/A Range: • true: all instances that fail to be created are deleted. In this case, the instances parameter in the request can be empty. • false: The DCS instances specified by the instances parameter will be deleted. Default Value: false

Request Parameters

Table 4-31 Request body parameters

Parameter	Mandatory	Type	Description
instances	No	Array of strings	Definition: List of instance IDs. This parameter is set only when the all_failure parameter in the URI is set to false or another value. Constraints: N/A
is_recycle	No	Boolean	Definition Whether to move the deleted instance to the recycle bin. Constraints Redis 4.0 and later instances can be moved to the recycle bin. Range true: Yes false: No, the deleted instance is directly destroyed. Default Value false

Response Parameters

Status code: 200

Table 4-32 Response body parameters

Parameter	Type	Description
results	Array of BatchOpsResult objects	Definition: Result of deleting, restarting, or clearing data of an instance.

Table 4-33 BatchOpsResult

Parameter	Type	Description
result	String	Definition Operation result. Range success: The instance is deleted, restarted, or cleared. failed: The instance fails to be deleted, restarted, or cleared.
instance	String	Definition: DCS instance ID. Range: N/A

Status code: 400

Table 4-34 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-35 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Batch deleting DCS instances

```
DELETE https://{dcs_endpoint}/v2/{project_id}/instances?all_failure={all_failure}
```

```
{
  "instances" : [ "54602a9d-5e22-4239-9123-77e350df4a34", "7166cdea-dbad-4d79-9610-7163e6f8b640" ]
}
```

Example Responses

Status code: 200

DCS instances deleted successfully.

```
{
  "results" : [ {
    "result" : "success",
    "instance" : "54602a9d-5e22-4239-9123-77e350df4a34"
  }, {
    "result" : "success",
    "instance" : "7166cdea-dbad-4d79-9610-7163e6f8b640"
  } ]
}
```

Status Codes

Status Code	Description
200	DCS instances deleted successfully.

Status Code	Description
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.1.4 Querying a DCS instance

Function

This API is used to query the details about a specified DCS instance.

URI

GET /v2/{project_id}/instances/{instance_id}

Table 4-36 Path Parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID, which can be viewed on the instance details page on the DCS console. Constraints: N/A. Value range: N/A. Default value: N/A.
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-37 Response body parameters

Parameter	Type	Description
vpc_name	String	Parameter description: VPC name. Value range: N/A.
charging_mode	Integer	Definition Billing mode. Range 0: pay-per-use
vpc_id	String	Parameter description: ID of the VPC where the DCS Redis instance is located. Value range: N/A.
user_name	String	Parameter description: Username of the instance. Value range: N/A.
created_at	String	Parameter description: Creation completion time, for example, 2017-03-31T12:24:46.297Z Value range: N/A.
description	String	Parameter description: Instance description. Value range: N/A.

Parameter	Type	Description
security_group_id	String	Parameter description: ID of the security group bound to the DCS Redis instance. Value range: N/A.
security_group_name	String	Parameter description: Name of the tenant security group. Value range: N/A.
max_memory	Integer	Parameter description: Total memory size in MB. Value range: N/A.
used_memory	Integer	Parameter description: Used memory size in MB. Value range: N/A.
capacity	Integer	Parameter description: DCS instance memory, in GB. Value range: N/A.
capacity_minor	String	Parameter description: Memory of a DCS instance whose size is less than 1 GB, in GB. Value range: N/A.
maintain_begin	String	Parameter description: UTC time when the maintenance time window starts. The format is <i>HH:mm:ss</i> . Value range: N/A.
maintain_end	String	Parameter description: UTC time when the maintenance time window ends. The format is <i>HH:mm:ss</i> . Value range: N/A.

Parameter	Type	Description
engine	String	Parameter description: DCS instance engine. Value range: N/A.
no_password_access	String	Parameter description: Indicates whether password-protected access is enabled for the instance. Value range: • true: no • false: yes
ip	String	Parameter description: IP address of the DCS instance. For a cluster instance, multiple IP addresses are returned and separated by commas (,). For example, 192.168.0.1, 192.168.0.2 . Value range: N/A.
instance_backup_policy	InstanceBackupPolicy object	Definition Backup policy. This parameter is available for master/standby and cluster instances. Range N/A
az_codes	Array of strings	Parameter description: AZ where the instance is located. The AZ code is returned. Value range: N/A.
available_zones	Array of strings	Parameter description: ID of the AZ where the instance is in. The AZ ID is returned. Value range: N/A.
access_user	String	Parameter description: Username for accessing a password-protected DCS instance. Value range: N/A.

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A.
port	Integer	Parameter description: Port of a DCS instance. Value range: N/A.
user_id	String	Parameter description: ID of the user to which the instance belongs. Value range: N/A.
name	String	Parameter description: Instance name. Value range: N/A.
spec_code	String	Parameter description: Product flavor code. Value range: N/A.
subnet_id	String	Parameter description: ID of the subnet bound to a DCS Redis instance. Value range: N/A.
subnet_name	String	Parameter description: Subnet name. Value range: N/A.
subnet_cidr	String	Parameter description: Subnet CIDR block. Value range: N/A.

Parameter	Type	Description
engine_version	String	Definition Cache version. Range The engine version of a DCS Redis instance can be: • 3.0 • 4.0 • 5.0 • 6.0 • 7.0 If the cache engine is Memcached, this parameter is blank.
order_id	String	Parameter description: Order ID. Value range: N/A.
status	String	Parameter description: DCS instance status. Value range: For details, see DCS Instance Statuses .
domain_name	String	Parameter description: Domain name of an instance. Value range: N/A.
readonly_domain_name	String	Parameter description: Read-only domain name of an instance. This parameter is available only for master/standby instances. Value range: N/A.
enable_publicip	Boolean	Definition This parameter is reserved. Range N/A

Parameter	Type	Description
publicip_id	String	Definition ID of the EIP bound to a DCS Redis instance. This parameter is reserved. The value is null . Range N/A
publicip_address	String	Definition EIP bound to the DCS Redis instance. The value of this parameter is null if public network access is disabled. Range N/A
enable_ssl	Boolean	Definition This parameter is reserved. Range N/A
service_upgrade	Boolean	Parameter description: Whether an upgrade task has been created for an instance. Value range: • true: yes • false: no
service_task_id	String	Parameter description: ID of an upgrade task. • This parameter is valid when service_upgrade is set to true. • This parameter is blank when service_upgrade is set to false. Value range: N/A.
enterprise_project_id	String	Parameter description: Enterprise project ID. Value range: N/A.

Parameter	Type	Description
backend_addrs	String	Parameter description: Backend address of a cluster instance. Value range: N/A.
features	Features object	Parameter description: Features supported by the instance. Value range: N/A.
domain_name_info	DomainNameInfo object	Parameter description: Information about instance domain name update and public domain name resolution. Value range: N/A.
transparent_client_ip_enable	Boolean	Parameter description: Whether client IP pass-through is enabled. Value range: N/A.
sub_status	String	Parameter description: Instance sub-status. Value range: N/A.
tags	Array of ResourceTags objects	Parameter description: Instance tag key and value. Value range: N/A.
cpu_type	String	Parameter description: CPU type of the instance. Value range: x86_64: x86-based aarch64: Arm-based
enterprise_project_name	String	Parameter description: Enterprise project name. Value range: N/A.

Parameter	Type	Description
update_at	String	Parameter description: Update time, for example, 2022-07-06T09:32:16.502Z Value range: N/A.
product_type	String	Definition Product type. Range generic: basic edition
storage_type	String	Parameter description: Storage type. Value range: Memory storage.
launched_at	String	Parameter description: Start time, for example, 2022-07-06T09:32:16.502Z Value range: N/A.
cache_mode	String	Definition DCS instance type. Range • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster
support_slow_log_flag	String	Parameter description: Whether slow query logs are supported. Value range: • true: supported • false: not supported
db_number	Integer	Parameter description: Number of databases. Value range: N/A.

Parameter	Type	Description
replica_count	Integer	Parameter description: Number of replicas. Value range: N/A.
sharding_count	Integer	Parameter description: Number of shards in a cluster instance. Value range: N/A.
bandwidth_info	BandwidthInfo object	Parameter description: Bandwidth information. Value range: N/A.
cloud_service_type_code	String	Parameter description: Cloud service type code. Value range: N/A.
cloud_resource_type_code	String	Parameter description: Cloud resource type code. Value range: N/A.
inquiry_spec_code	String	Parameter description: Specification code in the operations system. Value range: N/A.
free	String	Parameter description: This parameter is the same as if_free , is not enabled, and returns null . Value range: N/A
is_free	String	Parameter description: This parameter is reserved and null is returned. Value range: N/A

Parameter	Type	Description
libos	String	Parameter description: This parameter is reserved and false is returned. Value range: N/A
crr_role	String	Parameter description: This parameter is reserved and null is returned. Value range: N/A
active_active	ActiveActiveInfo object	Parameter description: Instance active-active feature. This parameter is reserved and null is returned. Value range: N/A
task	AnyType	Parameter description: Current instance task. Value range: N/A
proxy_links	Array of ProxyLink objects	Definition Instance proxy connections. This parameter is reserved and null is returned. Range N/A

Table 4-38 InstanceBackupPolicy

Parameter	Type	Description
backup_policy_id	String	Parameter description: Backup policy ID. Value range: N/A.

Parameter	Type	Description
created_at	String	Parameter description: Creation time, in the format of 2022-04-11T09:45:24.790Z. Value range: N/A.
updated_at	String	Parameter description: Update time, in the format of 2022-04-12T02:22:03.269Z. Value range: N/A.
policy	BackupPolicyResp object	Parameter description: Backup policy. Value range: N/A.
tenant_id	String	Parameter description: Tenant ID. Value range: N/A.

Table 4-39 BackupPolicyResp

Parameter	Type	Description
backup_type	String	Parameter description: Backup type. Value range: auto: automatic backup manual: manual backup
save_days	Integer	Parameter description: Retention period, in days. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: 1-7

Parameter	Type	Description
periodical_backup_plan	BackupPlan object	Parameter description: Backup plan. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: N/A.

Table 4-40 BackupPlan

Parameter	Type	Description
timezone_offset	String	Parameter description: Time zone of the backup. This parameter is no longer used. Value range: N/A.
backup_at	Array of integers	Parameter description: Day on which the backup starts every week. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: 1-7: Monday to Sunday
period_type	String	Parameter description: Interval at which backup is performed, which supports only weekly currently. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: N/A.
begin_at	String	Parameter description: UTC time when the backup starts. For example, 00:00-01:00 indicates that the backup starts at 00:00 (UTC time). The value must be on the hour. The backup interval is 1 hour. The automatic backup policy is retained when automatic backup is switched to manual backup. Value range: N/A.

Table 4-41 Features

Parameter	Type	Description
support_acl	Boolean	Parameter description: Whether ACL is supported. Value range: • true: Yes • false: No
support_transparent_client_ip	Boolean	Parameter description: Whether client IP pass-through is enabled. Value range: • true: Yes • false: No
support_ssl	Boolean	Parameter description: Whether SSL is supported. Value range: • true: Yes • false: No
support_acl_read_policy	Boolean	Definition: Whether the instance supports the ACL read-only routing policy. Range: • true: Yes • false: No
support_audit_log	Boolean	Parameter description: Whether audit logs are supported. Value range: • true: Yes • false: No

Table 4-42 DomainNameInfo

Parameter	Type	Description
support_public_resolve	Boolean	Parameter description: Whether to enable public domain name resolution. Value range: • true: yes • false: no
is_latest_rules	Boolean	Parameter description: Whether the current domain name is the latest. Value range: • true: Yes • false: No
zone_name	String	Parameter description: Region suffix of the domain name. Value range: N/A.
history_domain_names	Array of DomainNameEntity objects	Parameter description: Historical domain name information. Value range: N/A.

Table 4-43 DomainNameEntity

Parameter	Type	Description
domain_name	String	Parameter description: Historical domain names of the instance. Value range: N/A.
is_readonly	Boolean	Parameter description: Whether the domain name is read-only. Value range: • true: Yes • false: No

Table 4-44 ResourceTags

Parameter	Type	Description
key	String	Parameter description: Tag key. Value range: N/A
value	String	Definition: Tag value. Range: N/A

Table 4-45 BandwidthInfo

Parameter	Type	Description
begin_time	Long	Parameter description: Start time of temporary increase. Value range: N/A.
end_time	Long	Parameter description: End time of temporary increase. Value range: N/A.
current_time	Long	Parameter description: Current time. Value range: N/A.
bandwidth	Integer	Parameter description: Current bandwidth, in Mbit/s. Value range: N/A
next_expand_time	Long	Parameter description: Next increase time. Value range: N/A.

Parameter	Type	Description
expand_count	Integer	Parameter description: Number of increases. Value range: N/A.
expand_effect_time	Long	Parameter description: Interval between temporary increases. Value range: N/A.
expand_interval_time	Long	Parameter description: Time to the next increase. Value range: N/A.
max_expand_count	Integer	Parameter description: Maximum number of increases. Value range: N/A.
task_running	Boolean	Parameter description: Whether the task is running. Value range: N/A.
assured_bandwidth	Integer	Parameter description: Assured bandwidth, in Mbit/s. Value range: N/A
max_bandwidth_for_node	Integer	Parameter description: Maximum node bandwidth, in Mbit/s. Value range: N/A

Table 4-46 ActiveActiveInfo

Parameter	Type	Description
active_active_status	AnyType	Parameter description: Instance active-active status. Value range: enabled: Can be enabled. disabled: Cannot be enabled. opening: enabled. closing: disabled.
active_cluster_index	AnyType	Parameter description: Instance active-active cluster index. Value range: N/A

Table 4-47 ProxyLink

Parameter	Type	Description
ip	AnyType	Parameter description: Proxy IPv4. Value range: N/A
ipv6_ip	AnyType	Parameter description: Proxy IPv6. Value range: N/A
az_code	AnyType	Parameter description: AZ where the proxy is located. Value range: N/A
role	AnyType	Parameter description: Proxy role. Value range: N/A
domain_name	AnyType	Parameter description: Proxy domain name. Value range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}
```

Example Responses

Status code: 200

The specified instance is queried successfully.

```
{
  "publicip_id" : null,
  "vpc_name" : "dcs-beta",
  "charging_mode" : 0,
  "enterprise_project_name" : "default",
  "vpc_id" : "5e37b3be-950a-48e1-b498-65b63d336481",
  "user_name" : "clouduser",
  "created_at" : "2022-08-29T08:53:47.319Z",
  "description" : null,
  "cache_mode" : "ha",
  "security_group_id" : "securityGroupId",
  "enable_ssl" : false,
  "max_memory" : 128,
  "publicip_address" : null,
  "capacity" : 0,
  "maintain_begin" : "18:00:00",
  "engine" : "Redis",
  "maintain_end" : "19:00:00",
  "capacity_minor" : ".125",
  "service_upgrade" : false,
  "subnet_name" : "dcs-beta",
  "no_password_access" : "true",
  "service_task_id" : null,
  "ip" : "192.168.0.251",
  "subnet_cidr" : "192.168.0.0/24",
  "used_memory" : 2,
  "security_group_name" : "securityGroupId",
  "instance_backup_policy" : null,
  "az_codes" : [ "xx-xxxx-xx" ],
  "available_zones" : [ "d539378ec1314c85b76fefa3f7071458" ],
  "access_user" : null,
  "enterprise_project_id" : "0",
  "instance_id" : "a4c545cd-10b2-4efc-b0ab-a9b554ca0621",
  "enable_publicip" : false,
  "port" : 6379,
  "user_id" : "d53977d1adfb49c5b025ba7d33a13fd7",
  "domain_name" : "redis-a4c545cd-10b2-4efc-b0ab-a9b554ca0621.dcs.example.com",
  "name" : "dcs-billing",
  "spec_code" : "redis.ha.xu1.tiny.r2.128",
  "subnet_id" : "a4112635-3ec0-471c-95c3-5cf49b9533af",
  "engine_version" : "5.0",
  "order_id" : null,
  "status" : "RUNNING",
  "features" : {
    "support_acl" : true,
    "support_transparent_client_ip" : true,
    "support_ssl" : false,
    "support_audit_log" : false
  },
  "domain_name_info" : {
    "support_public_resolve" : true,
    "is_latest_rules" : true,
    "zone_name" : "dcs.example.com",
    "history_domain_names" : null
  },
  "transparent_client_ip_enable" : true,
  "sub_status" : "normal",
  "cpu_type" : "x86_64",
  "cloud_service_type_code" : "hws.service.type.dcs",
}
```

```
"cloud_resource_type_code" : "hws.resource.type.dcs3",
"inquiry_spec_code" : "redis.ha.xu1.tiny.r2.128",
"free" : null,
"is_free" : null,
"libos" : false,
"crr_role" : null,
"active_active" : null,
"task" : "EXTENDING",
"proxy_links" : null
}
```

Status Codes

Status Code	Description
200	The specified instance is queried successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.1.5 Deleting an Instance

Function

This API is used to delete a specified DCS instance to free up all resources occupied by the DCS instance.

NOTE

To delete pay-per-use resources, perform operations in this section..

URI

DELETE /v2/{project_id}/instances/{instance_id}

Table 4-48 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Request Parameters

Table 4-49 Request body parameters

Parameter	Mandatory	Type	Description
is_recycle	No	Boolean	Definition Whether to move the deleted instance to the recycle bin. Constraints Redis 4.0 and later instances can be moved to the recycle bin. Range true: Yes false: No, the deleted instance is directly destroyed. Default Value false

Response Parameters

Status code: 204

Instance deleted successfully.

None

Example Requests

- Deleting a specified instance
DELETE https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}

```
{
  "is_recycle" : false
}
```
- Deleting specified instances and adding them to the recycle bin
DELETE https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}

```
{
  "is_recycle" : true
}
```

Example Responses

None

Status Codes

Status Code	Description
204	Instance deleted successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.1.6 Modifying Details of a DCS Instance

Function

This API is used to modify the information about a DCS instance, including the instance name, description, port, backup policy, start and end time of the maintenance window, and security group.

URI

PUT /v2/{project_id}/instances/{instance_id}

Table 4-50 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

Table 4-51 Request body parameters

Parameter	Mandatory	Type	Description
name	No	String	Definition: Instance name. Constraints: An instance name can contain 4 to 64 characters, including letters, digits, underscores (_), and hyphens (-), and must start with a letter. Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
description	No	String	Definition: Description of an instance. Constraints: 0–1,024 characters NOTE The backslash (\) and quotation mark (") are special characters for JSON messages. When using these characters in a parameter value, add the escape character (\) before the characters, for example, \ and " . Range: N/A Default Value: N/A
port	No	Integer	Definition: Port customization. Constraints: which is supported only by Redis 4.0 and later instances Memcached instances do not support port customization. If this parameter is not sent or is left empty when you create a Redis instance, the default port 6379 will be used. To customize a port, specify a port number in the range from 1 to 65535. Range: 1–65535 Default Value: 6379
rename_commands	No	RenameCommandRequest object	Definition: Command renaming list.

Parameter	Mandatory	Type	Description
maintain_begin	No	String	Definition Start time of the maintenance time window. Constraints The value must be a UTC time in the format of <i>HH:mm:ss</i>. - The start time and end time of the maintenance time window must indicate the time segment of a supported maintenance time window. For details, see [Listing Maintenance Time Windows] (ListMaintenanceWindows.xml). • For example, the start time must be on the hour, such as 18:00:00 and 19:00:00. • The start time and end time must be set in pairs. If the start time is left blank, the end time must also be left blank. Range N/A Default Value 18:00:00

Parameter	Mandatory	Type	Description
maintain_end	No	String	Definition End time of the maintenance time window. Constraints The value must be a UTC time in the format of <i>HH:mm:ss</i>. - The start time and end time of the maintenance time window must indicate the time segment of a supported maintenance time window. For details, see [Listing Maintenance Time Windows] (ListMaintenanceWindows.xml). • For example, the start time must be on the hour, such as 18:00:00 and 19:00:00. • The start time and end time must be set in pairs. If the start time is left blank, the end time must also be left blank. Range N/A Default Value 19:00:00

Parameter	Mandatory	Type	Description
security_group_id	No	String	Definition Security group to which the instance belongs. This parameter is optional when the engine is Redis and the version is 4.0 or later. DCS Redis 4.0 and later instances do not support security groups (default value securityGroupId will be used). They support only whitelist-based access control. To obtain the value: • Method 1: Log in to the VPC console and view the security group ID on the security group details page. • Method 2: Call the VPC API used to query security groups. Constraints N/A Range N/A Default Value N/A
instance_backup_policy	No	BackupPolicy object	Definition: Backup policy. This parameter is supported when the instance type is master/standby or cluster.

Table 4-52 RenameCommandRquest

Parameter	Mandatory	Type	Description
command	No	String	Definition: Command that can be renamed. Constraints: N/A Range: N/A Default Value: N/A
flushall	No	String	Definition: Command FLUSHALL that can be renamed. Constraints: N/A Range: N/A Default Value: N/A
flushdb	No	String	Definition: Command FLUSHDB that can be renamed. Constraints: N/A Range: N/A Default Value: N/A
hgetall	No	String	Definition: Command HGETALL that can be renamed. Constraints: N/A Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
keys	No	String	Definition: Command HGETALL that can be renamed. Constraints: N/A Range: N/A Default Value: N/A

Table 4-53 BackupPolicy

Parameter	Mandatory	Type	Description
backup_type	Yes	String	Definition: Backup type. Constraints: N/A Range: • auto: automatic backup • manual: manual backup Default Value: N/A
save_days	No	Integer	Definition: This parameter is mandatory when backup_type is set to manual . Retention period, in days. The value ranges from 1 to 7. The automatic backup policy is retained when automatic backup is switched to manual backup. Constraints: N/A Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
periodical_backup_plan	No	BackupPlanRequest object	Definition: Backup plan. Constraints: This parameter is mandatory when backup_type is set to manual. The automatic backup policy is retained when automatic backup is switched to manual backup.

Table 4-54 BackupPlanRequest

Parameter	Mandatory	Type	Description
timezone_offset	No	String	Definition: Time zone of the backup. This parameter is no longer used. Constraints: N/A Range: N/A Default Value: N/A
backup_at	Yes	Array of integers	Definition: Day on which the backup starts every week. The automatic backup policy is retained when automatic backup is switched to manual backup. 1-7: Monday to Sunday Constraints: N/A

Parameter	Mandatory	Type	Description
period_type	Yes	String	Definition: Interval at which backup is performed, which supports only weekly currently. The automatic backup policy is retained when automatic backup is switched to manual backup. Constraints: N/A Range: N/A Default Value: N/A
begin_at	Yes	String	Definition: UTC time when the backup starts. For example, 00:00-01:00 indicates that the backup starts at 00:00 (UTC time). The value must be on the hour. The backup interval is 1 hour. The automatic backup policy is retained when automatic backup is switched to manual backup. Constraints: N/A Range: N/A Default Value: N/A

Response Parameters

Status code: 204

DCS instance modified successfully.

None

Example Requests

Changing the name of a specified instance to dcs002 and port to 6379, and configuring an auto backup policy

```
PUT https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}

{
  "name" : "dcs002",
  "description" : "instance description",
  "port" : 6379,
  "maintain_begin" : "18:00:00",
  "maintain_end" : "19:00:00",
  "security_group_id" : "18e9309f-f81a-4749-bb21-f74576292162",
  "instance_backup_policy" : {
    "backup_type" : "auto",
    "save_days" : 1,
    "periodical_backup_plan" : {
      "backup_at" : [ "1", "2", "3", "4", "6", "7" ],
      "period_type" : "weekly",
      "begin_at" : "00:00-01:00"
    }
  }
}
```

Example Responses

None

Status Codes

Status Code	Description
204	DCS instance modified successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.1.7 Modifying Instance Specifications

Function

This API is used to modify specifications of a DCS instance in the **Running** state.

URI

POST /v2/{project_id}/instances/{instance_id}/resize

Table 4-55 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

Table 4-56 Request body parameters

Parameter	Mandatory	Type	Description
spec_code	Yes	String	Definition: Flavor after the modification. The query method is as follows: • Method 1: Log in to the DCS console, go to the instance creation page, and check the instance flavor. • Method 2: Call the API used to query product flavors. Constraints: N/A Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
new_capacity	Yes	Integer	Definition New memory size of the DCS instance, in GB. Constraints For a single-node or master/standby DCS Redis 4.0 or later instance, the value can be 0.125, 0.25, 0.5, 1, 2, 4, 8, 16, 32, or 64. For a cluster DCS Redis 4.0 or later instance, the value can be 4, 8, 16, 24, 32, 48, 64, 96, 128, 192, 256, 384, 512, 768, or 1024. For a single-node or master/standby DCS Memcached instance, the value can be 2, 4, 8, 16, 32, or 64. Currently, the specifications of a Proxy Cluster DCS Redis 3.0 instance cannot be reduced. In addition to integers, 0.125, 0.25, and 0.5 are also supported. Range N/A Default Value N/A
bss_param	No	BssParamEntity object	Definition This parameter does not need to be set for pay-per-use instances.
reserved_ip	No	Array of strings	Definition: IP addresses to retain. Mandatory during cluster scale-in. If this parameter is not set, the system randomly deletes unnecessary shards.

Parameter	Mandatory	Type	Description
change_type	No	String	Definition Modification type. Mandatory when the number of replicas of a DCS Redis instance is modified. Constraints N/A Range • createReplication: adding replicas • deleteReplication: deleting replicas • addSharding: adding shards • instanceType: changing the instance type. Default Value N/A
available_zones	No	Array of strings	Definition: Code of the AZ where each replica is in. This parameter is mandatory when you add replicas to a DCS Redis instance. Before specifying an AZ, ensure that there are available resources in it. This parameter is mandatory when you delete replicas from a cluster instance. For details, see Querying AZs.
node_list	No	Array of strings	Definition: ID of the replica to delete. This parameter is mandatory when you delete replicas of a master/standby or read/write splitting DCS Redis instance. Currently, only one replica can be deleted at a time. For details, see Querying Details of Shards and Replicas.

Parameter	Mandatory	Type	Description
execute_immediately	No	Boolean	Definition: Whether to apply the change immediately. Constraints: N/A Range: true: Yes false: No. Apply the change in the maintenance time window. Default Value: true.
enable_ipv6	No	Boolean	Parameter description: Whether IPv6 is enabled. Constraints: N/A Value range: true: Yes false: No Default value: false
spec_param	No	SpecParam object	Definition: Linear specification definition parameter. Constraints: N/A

Table 4-57 BssParamEntity

Parameter	Mandatory	Type	Description
is_auto_pay	No	String	Definition This parameter is reserved. Constraints N/A Range -true: Fees are automatically deducted from the account balance. • false: The order must be paid manually. This is the default value. Default Value false

Table 4-58 SpecParam

Parameter	Mandatory	Type	Description
sharding_count	No	Integer	Parameter description: Number of instance shards. Constraints: N/A Value range: 1–128 Default value: N/A
replica_count	No	Integer	Definition: Number of instance replicas. Constraints: N/A Range: 1–10 Default Value: N/A

Parameter	Mandatory	Type	Description
cache_mode	No	String	Definition DCS instance type. Constraints N/A Range • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster Default Value N/A

Response Parameters

Status code: 204

DCS instance specifications modified successfully.

None

Example Requests

- Changing to a master/standby instance with 3 replicas and 1 GB

POST https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/resize

```
{
  "spec_code" : "redis.ha.xu1.large.r3.1",
  "new_capacity" : 1,
  "change_type" : "createReplication",
  "available_zones" : [ "e7afd64502d64fe3bfb60c2c82ec0ec6",
"d90ff6d692954373bf53be49cf3900cb" ],
  "execute_immediately" : true
}
```

- Changing to a Redis Cluster instance with 2 replicas and 8 GB

```
{
  "spec_code" : "redis.cluster.xu1.large.r2.8",
  "new_capacity" : 8,
  "reserved_ip" : [ "192.168.0.125" ],
  "change_type" : "deleteReplication",
  "execute_immediately" : true
}
```

Example Responses

None

Status Codes

Status Code	Description
204	DCS instance specifications modified successfully.

Error Codes

See [Error Codes](#).

4.2 Instance Management

4.2.1 Master/Standby Switchover

Function

This API is used to perform a master/standby switchover. Only master/standby instances support this operation.

URI

POST /v2/{project_id}/instances/{instance_id}/swap

Table 4-59 Path Parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID.
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

None

Response Parameters

Status code: 204

Master/standby switchover performed successfully.

Status code: 400

Table 4-60 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-61 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-62 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-63 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-64 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
POST https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/swap
```

Example Responses

Status code: 400

Invalid request.

```
{  
  "error_msg" : "Master standby swap is not supported.",  
  "error_code" : "DCS.4855",  
  "error_ext_msg" : null  
}
```

Status Codes

Status Code	Description
204	Master/standby switchover performed successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.

Status Code	Description
500	Internal service error.

Error Codes

See [Error Codes](#).

4.2.2 Changing the Password

Function

This API is used to change the password of a DCS instance.

URI

PUT /v2/{project_id}/instances/{instance_id}/password

Table 4-65 Path Parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Request Parameters

Table 4-66 Request body parameters

Parameter	Mandatory	Type	Description
old_password	Yes	String	Definition Old instance password. Constraints The password contains 8 to 32 characters. Range Contains at least three types of the following characters: • Lowercase letters • Uppercase letters • Digits • Special characters `~!@#\$%^&*()-_+= {<,.>/? Default Value N/A
new_password	Yes	String	Definition New instance password. Constraints The new password must be different from the old one. It contains 8 to 32 characters. Range Contains at least three types of the following characters: • Lowercase letters • Uppercase letters • Digits • Special characters `~!@#\$%^&*()-_+= {<,.>/? Default Value N/A

Response Parameters

Status code: 200

Table 4-67 Response body parameters

Parameter	Type	Description
lock_time	String	Parameter description: Lockout duration, in minutes. After 5 consecutive incorrect password attempts, the account will be locked. Passwords cannot be changed or reset during the lockout period. Value range: 0-5
result	String	Parameter description: Password change result. Value range: • success: The password is changed successfully. • passwordFailed: The password verification fails. • locked: The account is locked. • failed: The password fails to be changed.
lock_time_left	String	Parameter description: Lockout remaining time, in minutes. Value range: 0-5
retry_times_left	String	Parameter description: Number of remaining password attempts. Value range: N/A
message	String	Parameter description: Modification result description. Value range: N/A

Status code: 400

Table 4-68 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-69 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Changing the password of the DCS instance by entering the old and new passwords

```
PUT https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/password
{
  "old_password" : "XXXXXX",
  "new_password" : "XXXXXX"
}
```

Example Responses

Status code: 200

The password is successfully changed.

```
{
  "lock_time" : "0",
  "result" : "success",
  "lock_time_left" : "0",
  "retry_times_left" : "5",
  "message" : "Modify DCSInstance password success."
}
```

Status Codes

Status Code	Description
200	The password is successfully changed.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.2.3 Resetting a Password

Function

This API is used to reset the password of a DCS instance.

URI

POST /v2/{project_id}/instances/{instance_id}/password/reset

Table 4-70 Path Parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Request Parameters

Table 4-71 Request body parameters

Parameter	Mandatory	Type	Description
new_password	No	String	Definition: New password. When no_password_access is set to false or not specified, the request must contain the password parameter. Constraints: The password contains 8 to 32 characters. Range: Contains at least three types of the following characters: • Lowercase letters • Uppercase letters • Digits • Special characters `~!@#\$%^&*()-_+= {>,.<./? Default Value: N/A
no_password_access	No	Boolean	Parameter description: Whether to change the DCS instance to password-free. Constraints: N/A Value range: • true: Resetting the DCS instance to be password-free. • false: Resetting the DCS instance to be password-protected. Default value: false

Response Parameters

Status code: 200

Table 4-72 Response body parameters

Parameter	Type	Description
retry_times_left	String	Parameter description: Number of remaining password attempts. Resetting the password does not involve password verification. This parameter is deprecated. The default return is 5. Value range: N/A
lock_time	String	Parameter description: Lockout duration, in minutes. Resetting the password does not involve lockout. This parameter is deprecated. The default return is 0. Value range: N/A
lock_time_left	String	Parameter description: Lockout remaining time, in minutes. Resetting the password does not involve lockout. This parameter is deprecated. The default return is 0. Value range: N/A
code	String	Parameter description: Code of a password resetting result. Value range: 1: The password is reset successfully.
message	String	Parameter description: Password resetting result. Value range: success
ext_message	String	Parameter description: Password resetting error. This parameter is null if the password is reset successfully. Value range: N/A

Status code: 400

Table 4-73 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-74 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Resetting the password of the DCS instance by entering a new password

```
POST https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/password/reset
{
  "new_password": "xxxxxx",
  "no_password_access": false
}
```

Example Responses

Status code: 200

The password of the DCS instance is reset.

```
{
  "lock_time": "0",
  "lock_time_left": "0",
  "retry_times_left": "5",
  "code": "1",
  "message": "success",
  "ext_message": null
}
```

Status code: 400

Invalid request.

```
{
  "error_code": "DCS.4839",
  "error_msg": "is not support reset instance password."
}
```

Status Codes

Status Code	Description
200	The password of the DCS instance is reset.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.2.4 Querying DCS Instance Statuses

Function

This API is used to query the number of instances in different states.

URI

GET /v2/{project_id}/instances/status

Table 4-75 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Table 4-76 Query Parameters

Parameter	Mandatory	Type	Description
include_failure	No	String	Parameter description: Whether to return the number of instances that fail to be created. Constraints: N/A. Value range: • true: yes • false: no Default value: false

Request Parameters

None

Response Parameters

Status code: 200

Table 4-77 Response body parameters

Parameter	Type	Description
redis	StatusStatistic object	Parameter description: Redis instance quantity statistics. Value range: N/A.
memcached	StatusStatistic object	Parameter description: Memcached instance quantity statistics. Value range: N/A.
paying_count	Integer	Parameter description: Number of instances for which payment is in progress. Value range: N/A.
freezing_count	Integer	Parameter description: Number of instances that are being frozen. Value range: N/A.
migrating_count	Integer	Parameter description: Number of instances on which data migration is in progress. Value range: N/A.
flushing_count	Integer	Parameter description: Number of instances whose data is being cleared. Value range: N/A.
upgrading_count	Integer	Parameter description: Number of instances that are being upgraded. Value range: N/A.

Parameter	Type	Description
restoring_count	Integer	Parameter description: Number of instances for which data restoration is in progress. Value range: N/A.
extending_count	Integer	Parameter description: Number of instances that are being scaled up. Value range: N/A.
creating_count	Integer	Parameter description: Number of instances that are being created. Value range: N/A.
running_count	Integer	Parameter description: Number of running instances. Value range: N/A.
error_count	Integer	Parameter description: Number of abnormal instances. Value range: N/A.
frozen_count	Integer	Parameter description: Number of frozen instances. Value range: N/A.
createfailed_count	Integer	Parameter description: Number of instances that fail to be created. Value range: N/A.
restarting_count	Integer	Parameter description: Number of instances that are being restarted. Value range: N/A.

Table 4-78 StatusStatistic

Parameter	Type	Description
paying_count	Integer	Parameter description: Number of instances for which payment is in progress. Value range: N/A.
freezing_count	Integer	Parameter description: Number of instances that are being frozen. Value range: N/A.
migrating_count	Integer	Parameter description: Number of instances on which data migration is in progress. Value range: N/A.
flushing_count	Integer	Parameter description: Number of instances whose data is being cleared. Value range: N/A.
upgrading_count	Integer	Parameter description: Number of instances that are being upgraded. Value range: N/A.
restoring_count	Integer	Parameter description: Number of instances for which data restoration is in progress. Value range: N/A.
extending_count	Integer	Parameter description: Number of instances that are being scaled up. Value range: N/A.

Parameter	Type	Description
creating_count	Integer	Parameter description: Number of instances that are being created. Value range: N/A.
running_count	Integer	Parameter description: Number of running instances. Value range: N/A.
error_count	Integer	Parameter description: Number of abnormal instances. Value range: N/A.
frozen_count	Integer	Parameter description: Number of instances that have been frozen. Value range: N/A.
createfailed_count	Integer	Parameter description: Number of instances that fail to be created. Value range: N/A.
restarting_count	Integer	Parameter description: Number of instances that are being restarted. Value range: N/A.

Status code: 400

Table 4-79 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-80 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instances/status?include_failure=true
```

Example Responses

Status code: 200

DCS instance quantity queried successfully.

```
{
  "extending_count" : 0,
  "creating_count" : 0,
  "running_count" : 16,
  "error_count" : 0,
  "frozen_count" : 0,
  "createfailed_count" : 44,
  "restarting_count" : 0,
  "paying_count" : 0,
  "freezing_count" : 0,
  "migrating_count" : 0,
  "flushing_count" : 0,
  "upgrading_count" : 0,
  "redis" : {
    "extending_count" : 0,
    "creating_count" : 0,
    "running_count" : 8,
    "error_count" : 0,
    "frozen_count" : 0,
    "createfailed_count" : 22,
    "restarting_count" : 0,
    "paying_count" : 0,
    "freezing_count" : 0,
    "migrating_count" : 0,
    "flushing_count" : 0,
    "upgrading_count" : 0
  },
  "memcached" : {
    "extending_count" : 0,
    "creating_count" : 0,
    "running_count" : 8,
    "error_count" : 0,
    "frozen_count" : 0,
    "createfailed_count" : 22,
    "restarting_count" : 0,
    "paying_count" : 0,
    "freezing_count" : 0,
    "migrating_count" : 0,
    "flushing_count" : 0,
    "upgrading_count" : 0
  }
}
```

Status Codes

Status Code	Description
200	DCS instance quantity queried successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.2.5 Restarting DCS Instances or Clearing DCS Instance Data

Function

This API is used to restart a running DCS instance.

Data clearance operations cannot be undone on DCS Redis 4.0 and later instances.

URI

PUT /v2/{project_id}/instances/status

Table 4-81 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

Table 4-82 Request body parameters

Parameter	Mandatory	Type	Description
instances	No	Array of strings	Definition: List of instance IDs.

Parameter	Mandatory	Type	Description
action	No	String	Definition: Operation on the instance. Constraints: Only DCS Redis 4.0 and later instances can be flushed. Range: • restart: force restart • soft_restart: restart only the instance process • flush: clear data Default Value: N/A

Response Parameters

Status code: 200

Table 4-83 Response body parameters

Parameter	Type	Description
results	Array of BatchOpsResult objects	Definition: Result of deleting, restarting, or clearing data of an instance.

Table 4-84 BatchOpsResult

Parameter	Type	Description
result	String	Definition: Operation result. Range: success : The instance is deleted, restarted, or cleared. failed : The instance fails to be deleted, restarted, or cleared.
instance	String	Definition: DCS instance ID. Range: N/A

Status code: 400

Table 4-85 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-86 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Force restarting a DCS instance

```
PUT https://{dcs_endpoint}/v2/{project_id}/instances/status
{
  "instances" : [ "2e803f66-fbb0-47ad-b6cb-fb87f5bed4ef" ],
  "action" : "restart"
}
```

Example Responses

Status code: 200

Definition:

DCS instance restarted successfully or the instance data cleared successfully.

```
{
  "results" : [ {
    "instance" : "e3a7019c-8824-4c1a-8289-5300f19b9f64",
    "result" : "success"
  } ]
}
```

Status Codes

Status Code	Description
200	Definition: DCS instance restarted successfully or the instance data cleared successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.2.6 Querying Statistics of All Running Instances

Function

This API is used to query the statistics of all DCS instances that are in the **Running** state.

URI

GET /v2/{project_id}/instances/statistic

Table 4-87 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-88 Response body parameters

Parameter	Type	Description
statistics	Array of InstanceStatistic objects	Parameter description: Statistics of all instances in the Running state. Value range: N/A.

Table 4-89 InstanceStatistic

Parameter	Type	Description
input_kbps	String	Parameter description: Incoming traffic (Kbit/s) of the DCS instance. Value range: N/A.

Parameter	Type	Description
output_kbps	String	Parameter description: Outgoing traffic (Kbit/s) of the DCS instance. Value range: N/A.
instance_id	String	Parameter description: Instance ID. Value range: N/A.
keys	Long	Parameter description: Number of cached data records. Value range: N/A.
used_memory	Long	Parameter description: Used memory size in MB. Value range: N/A.
max_memory	Long	Parameter description: Total memory size in MB. Value range: N/A.
cmd_get_count	Long	Parameter description: Number of times the GET command is run. Value range: N/A.
cmd_set_count	Long	Parameter description: Number of times the SET command is run. Value range: N/A.
used_cpu	String	Parameter description: Accumulated CPU time consumed by the cache in the user state and kernel state, in seconds. Value range: N/A.

Status code: 400

Table 4-90 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-91 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

GET https://{dcs_endpoint}/v2/{project_id}/instances/statistic

Example Responses

Status code: 200

Instance statistics queried successfully.

```
{
  "statistics": [ {
    "output_kbps": "0.0",
    "instance_id": "e008652d-18e0-43ff-924e-072261e0372a",
    "keys": 0,
    "used_memory": 0,
    "cmd_get_count": 0,
    "used_cpu": "0.0",
    "cmd_set_count": 0,
    "input_kbps": "0.0",
    "max_memory": 460
  }, {
    "output_kbps": "0.0",
    "instance_id": "c577a1eb-33b7-42c7-8231-ad32358599ac",
    "keys": 0,
    "used_memory": 0,
    "cmd_get_count": 0,
    "used_cpu": "0.0",
    "cmd_set_count": 0,
    "input_kbps": "0.0",
    "max_memory": 460
  }, {
    "output_kbps": "1.19",
    "instance_id": "e8b98471-55d5-4695-b0bb-8f336a98e207",
    "keys": 0,
    "used_memory": 0,
    "cmd_get_count": 0,
    "used_cpu": "0.0",
    "cmd_set_count": 0,
    "input_kbps": "0.03",
    "max_memory": 460
  }, {
    "output_kbps": "0.0",
    "instance_id": "bc61c690-4b34-4cbe-9ce3-11246aea7aba",
    "keys": 0,
    "used_memory": 0,
    "cmd_get_count": 0,
    "used_cpu": "0.0",
    "cmd_set_count": 0,
    "input_kbps": "0.0",
    "max_memory": 6963
  } ]
}
```

Status Codes

Status Code	Description
200	Instance statistics queried successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.3 Shards and Replicas

4.3.1 Configuring Replica Priority

Function

This API is used to configure the replica priority. When the master node is faulty, a replica with a smaller weight has a higher priority to be promoted to master.

URI

POST /v2/{project_id}/instances/{instance_id}/groups/{group_id}/replications/{node_id}/slave-priority

Table 4-92 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.
group_id	Yes	String	Shard ID.
node_id	Yes	String	Node ID.

Request Parameters

Table 4-93 Request body parameters

Parameter	Mandatory	Type	Description
slave_priority_weight	Yes	Integer	Replica priority. The value ranges from 0 to 100. Value 0 indicates that the promotion is disabled by default.

Response Parameters

Status code: 204

Replica priority configured successfully.

Status code: 400

Table 4-94 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-95 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-96 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-97 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-98 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Setting the replica priority to 100

```
POST https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/groups/{group_id}/replications/{node_id}/slave-priority
{
  "slave_priority_weight" : 100
}
```

Example Responses

None

Status Codes

Status Code	Description
204	Replica priority configured successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.3.2 Removing the IP Address

Function

This API is used to remove the IP address of a read replica from the domain name. After the removal, the read-only domain name will not be resolved to the IP address.

URI

DELETE /v2/{project_id}/instances/{instance_id}/groups/{group_id}/replications/{node_id}/remove-ip

Table 4-99 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.
group_id	Yes	String	Shard ID.
node_id	Yes	String	Node ID.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-100 Response body parameters

Parameter	Type	Description
job_id	String	ID of the IP address removing task.

Status code: 400

Table 4-101 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-102 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-103 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-104 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-105 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

POST https://{dcs_endpoint}/v2/{project_id}/instance/{instance_id}/groups/{group_id}/replications/{node_id}/remove-ip

Example Responses

None

Status Codes

Status Code	Description
200	IP address removed successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.3.3 Querying Details of Shards

Function

This API is used to query information about shards and replicas of Redis 4.0 and later instances (single-node ones not included).

URI

GET /v2/{project_id}/instance/{instance_id}/groups

Table 4-106 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.
instance_id	Yes	String	Parameter description: Instance ID, which can be viewed on the instance details page on the DCS console. Constraints: N/A. Value range: N/A. Default value: N/A.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-107 Response body parameters

Parameter	Type	Description
group_list	Array of InstanceGroupListInfo objects	Parameter description: Instance shard list. Value range: N/A.
group_count	Integer	Parameter description: Total number of shards in the instance. Value range: N/A.

Table 4-108 InstanceGroupListInfo

Parameter	Type	Description
group_id	String	Parameter description: Instance shard ID. Value range: N/A.
group_name	String	Parameter description: Instance shard name. Value range: N/A.
replication_list	Array of InstanceReplicationListInfo objects	Parameter description: List of replicas in the shard. Value range: N/A.

Table 4-109 InstanceReplicationListInfo

Parameter	Type	Description
replication_role	String	Parameter description: Replica role. Value range: • master: master node • slave: standby node.

Parameter	Type	Description
replication_ip	String	Parameter description: Replica IP address. Value range: N/A.
is_replication	Boolean	Parameter description: Whether the replica is newly added. Value range: • true • false
replication_id	String	Parameter description: Replica ID. Value range: N/A.
node_id	String	Parameter description: Node ID. Value range: N/A.
status	String	Parameter description: Replica status. Value range: N/A.
az_code	String	Parameter description: AZ where the replica is in. Value range: N/A.

Parameter	Type	Description
dimensions	Array of InstanceReplicationDimensionsInfo objects	Parameter description: Monitoring metric dimension of the replica used to call the Cloud Eye API for querying monitoring metrics. - Replica monitoring is multi-dimensional. The returned array contains information about two dimensions. When querying monitoring data from Cloud Eye, transfer parameters of multiple dimensions to obtain the metric data. - The first dimension is the primary dimension of the replica. The dimension name is dc_instance_id, and the dimension value corresponds to the ID of the instance to which the replica belongs. - The name of the second dimension is dc_cluster_redis_node, and the dimension value is the ID of the monitored object of the replica, which is different from the replica ID or node ID. Value range: N/A.

Table 4-110 InstanceReplicationDimensionsInfo

Parameter	Type	Description
name	String	Parameter description: Monitoring dimension name. Value range: dc_instance_id: instance dimension dc_cluster_redis_node: data node dimension
value	String	Parameter description: Dimension value. Value range: N/A.

Status code: 500

Table 4-111 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 400

Table 4-112 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instance/{instance_id}/groups
```

Example Responses

Status code: 200

Details of shards and replicas queried successfully.

```
{
  "group_list": [ {
    "group_id": "35e1bed6-7de5-4898-9eb2-c362c783df15",
    "group_name": "group-0",
    "replication_list": [ {
      "az_code": "region01",
      "is_replication": false,
      "node_id": "8abfa7aa73291f15017329e1cda0002d",
      "replication_id": "dfbd3f84-08bc-42f0-b538-01d03e6dc178",
      "replication_ip": "192.168.76.25",
      "replication_role": "master",
      "status": "Active",
      "dimensions": [ {
        "name": "dcs_instance_id",
        "value": "caf2d19f-7783-44b0-be46-8c9da3ef1e94"
      }, {
        "name": "dcs_cluster_redis_node",
        "value": "8263dc69629c5b2d840e9816fa9c6200"
      } ]
    }, {
      "az_code": "region01",
      "is_replication": false,
      "node_id": "8abfa7aa73291f15017329e1cdb0002e",
      "replication_id": "63d4c880-7050-464f-ab19-c8a297474d7d",
      "replication_ip": "192.168.78.207",
      "replication_role": "slave",
      "status": "Active",
      "dimensions": [ {
        "name": "dcs_instance_id",
        "value": "caf2d19f-7783-44b0-be46-8c9da3ef1e94"
      }, {
        "name": "dcs_cluster_redis_node",
        "value": "8263dc69629c5b2d840e9816fa9c6201"
      } ]
    } ]
  }, {
    "group_id": "579a281f-6e63-4822-b0c7-e45c44b7c807",
    "group_name": "group-1",
    "replication_list": [ {
      "az_code": "region01",
      "is_replication": false,
      "node_id": "8abfa7aa73291f15017329e1cbbd002f",
      "replication_id": "6284c192-48d1-462b-8fd9-45dad067c1a2",
      "replication_ip": "192.168.73.164",
      "replication_role": "master",
      "status": "Active",
      "dimensions": [ {
        "name": "dcs_instance_id",
        "value": "caf2d19f-7783-44b0-be46-8c9da3ef1e94"
      }, {
        "name": "dcs_cluster_redis_node",
        "value": "8263dc69629c5b2d840e9816fa9c6202"
      } ]
    }, {
      "az_code": "region01",
      "is_replication": false,
      "node_id": "8abfa7aa73291f15017329e1cdc80030",
      "replication_id": "b927de3b-42f3-45b5-b0e4-8547f0ef6727",
      "replication_ip": "192.168.77.172",
```

```

    "replication_role": "slave",
    "status": "Active",
    "dimensions": [ {
      "name": "dcs_instance_id",
      "value": "caf2d19f-7783-44b0-be46-8c9da3ef1e94"
    }, {
      "name": "dcs_cluster_redis_node",
      "value": "8263dc69629c5b2d840e9816fa9c6203"
    } ]
  } ]
}, {
  "group_id": "c17305c6-6651-42d9-86bf-5a6087076eb7",
  "group_name": "group-2",
  "replication_list": [ {
    "az_code": "region01",
    "is_replication": false,
    "node_id": "8abfa7aa73291f15017329e1cdd90031",
    "replication_id": "caa6636d-a5c1-43b8-990a-3dc134da4522",
    "replication_ip": "192.168.76.143",
    "replication_role": "master",
    "status": "Active",
    "dimensions": [ {
      "name": "dcs_instance_id",
      "value": "caf2d19f-7783-44b0-be46-8c9da3ef1e94"
    }, {
      "name": "dcs_cluster_redis_node",
      "value": "8263dc69629c5b2d840e9816fa9c6204"
    } ]
  }, {
    "az_code": "region01",
    "is_replication": false,
    "node_id": "8abfa7aa73291f15017329e1cde50032",
    "replication_id": "4f46790d-a0b0-4a1b-aa02-1c554fccf62d",
    "replication_ip": "192.168.72.66",
    "replication_role": "slave",
    "status": "Active",
    "dimensions": [ {
      "name": "dcs_instance_id",
      "value": "caf2d19f-7783-44b0-be46-8c9da3ef1e94"
    }, {
      "name": "dcs_cluster_redis_node",
      "value": "8263dc69629c5b2d840e9816fa9c6205"
    } ]
  } ]
} ],
"group_count": 3
}

```

Status Codes

Status Code	Description
200	Details of shards and replicas queried successfully.
500	Internal service error.
400	Invalid request.

Error Codes

See [Error Codes](#).

4.3.4 Querying Instance Nodes in Batches

Function

This API is used to query the node information, number of valid instances, and number of nodes of all instances in a specified project.

No node information will be returned when the instance is being created.

Available for Redis 4.0 and later instances.

Constraints

Available for Redis 4.0 and later instances.

URI

GET /v2/{project_id}/instances-logical-nodes

Table 4-113 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Table 4-114 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0
limit	No	Integer	Parameter description: Number of records displayed on each page. Constraints: N/A. Value range: 1–100 Default value: 10

Request Parameters

None

Response Parameters

Status code: 200

Table 4-115 Response body parameters

Parameter	Type	Description
count	Integer	Parameter description: Total number of instances in the query result. Value range: N/A.

Parameter	Type	Description
instances	Array of InstanceNodesInfoResp objects	Parameter description: Instance list. Value range: N/A.

Table 4-116 InstanceNodesInfoResp

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A.
node_count	Integer	Parameter description: Total number of nodes of the current instance. Value range: N/A.
nodes	Array of NodesInfoResp objects	Parameter description: Node details. Value range: N/A.

Table 4-117 NodesInfoResp

Parameter	Type	Description
logical_node_id	String	Parameter description: Logical node ID. Value range: N/A.
name	String	Parameter description: Node name. Value range: N/A.

Parameter	Type	Description
status	String	Parameter description: Node status. Value range: • Creating • Active: Running • Inactive: Faulty • Deleting • AddSharding: A shard is being added.
az_code	String	Parameter description: AZ code. Value range: N/A.
node_role	String	Parameter description: Node role. Value range: • redis-server: Redis server node • redis-proxy: proxy node
node_type	String	Parameter description: Node master/standby role. Value range: • master: master node • slave: standby node • proxy: node of a Proxy Cluster instance
node_ip	String	Parameter description: Node IP. Value range: N/A.
node_port	String	Parameter description: Node port. Value range: N/A.
node_id	String	Parameter description: Node ID. Value range: N/A.

Parameter	Type	Description
priority_weight	Integer	Parameter description: Replica promotion priority. Value range: Priority ranges from 0 to 100 in descending order. 0 indicates that the replica will never be automatically promoted, 1 indicates the highest priority, and 100 indicates the lowest priority.
is_access	Boolean	Parameter description: Whether the IP address of the node can be directly accessed. Value range: • true • false
group_id	String	Parameter description: Instance shard ID. Value range: N/A.
group_name	String	Parameter description: Instance shard name. Value range: N/A.
is_remove_ip	Boolean	Parameter description: Whether the IP address is removed from the read-only domain name. Value range: • true • false
replication_id	String	Parameter description: Instance replica ID. Value range: N/A.

Parameter	Type	Description
dimensions	Array of InstanceReplicationDimensionsInfo objects	Parameter description: Monitoring metric dimension of the replica used to call the Cloud Eye API for querying monitoring metrics. - Replica monitoring is multi-dimensional. The returned array contains information about two dimensions. When querying monitoring data from Cloud Eye, transfer parameters of multiple dimensions to obtain the metric data. - The first dimension is the primary dimension of the replica. The dimension name is dc_instance_id, and the dimension value is the ID of the instance where the replica is located. - The name of the second dimension is dc_cluster_redis_node, and the dimension value is the ID of the monitored object of the replica, which is different from the replica ID or node ID. Value range: N/A.

Table 4-118 InstanceReplicationDimensionsInfo

Parameter	Type	Description
name	String	Parameter description: Monitoring dimension name. Value range: dc_instance_id: instance dimension dc_cluster_redis_node: data node dimension
value	String	Parameter description: Dimension value. Value range: N/A.

Status code: 500

Table 4-119 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 400

Table 4-120 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instances-logical-nodes?offset={offset}&limit={limit}
```

Example Responses

Status code: 200

Node information queried successfully.

```
{
  "count" : 1,
  "instances" : [ {
    "instance_id" : "b4468cb1-4f75-4866-a49d-86959acc0c9c",
    "node_count" : 2,
    "nodes" : [ {
      "logical_node_id" : "8f997eb512a92834bf5914be52ca8919",
      "name" : "(replica)192.168.0.178",
      "status" : "Active",
      "az_code" : "region01",
      "node_role" : "redis-server",
      "node_type" : "slave",
      "node_ip" : "192.168.0.178",
      "node_port" : "6379",
      "node_id" : "8a2c26c17f4d6516017f4d7b77940030",
      "is_access" : true,
      "group_id" : "ace962d1-7841-4e50-9313-c239fd75dee3",
      "group_name" : "group-0",
      "priority_weight" : 100,
      "is_remove_ip" : false,
      "replication_id" : "e40aa09e-03c2-4319-86eb-5ef4ca637544",
      "dimensions" : [ {
        "name" : "dcs_instance_id",
        "value" : "caf2d19f-7783-44b0-be46-8c9da3ef1e94"
      }, {
        "name" : "dcs_cluster_redis_node",
        "value" : "8263dc69629c5b2d840e9816fa9c6200"
      } ]
    } ]
  } ]
}
```

Status code: 500

Internal service error.

```
{
  "error_code" : "DCS.5000",
  "error_msg" : "Internal service error."
}
```

Status code: 400

Invalid request.

```
{
  "error_code" : "DCS.4800",
  "error_msg" : "Invalid offset in the request."
}
```

Status Codes

Status Code	Description
200	Node information queried successfully.

Status Code	Description
500	Internal service error.
400	Invalid request.

Error Codes

See [Error Codes](#).

4.3.5 Querying Instance Nodes

Function

This API is used to query nodes of a specified instance.

Available for Redis 4.0 and later instances.

No node information will be returned when the instance is being created.

Constraints

Available for Redis 4.0 and later instances.

URI

GET /v2/{project_id}/instances/{instance_id}/logical-nodes

Table 4-121 Path Parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID.
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

None

Response Parameters

Status code: 200

Table 4-122 Response body parameters

Parameter	Type	Description
instance_id	String	Instance ID.
total	Integer	Node quantity.
nodes	Array of NodesInfoResp objects	Node information.

Table 4-123 NodesInfoResp

Parameter	Type	Description
logical_node_id	String	Parameter description: Logical node ID. Value range: N/A.
name	String	Parameter description: Node name. Value range: N/A.
status	String	Parameter description: Node status. Value range: • Creating • Active: Running • Inactive: Faulty • Deleting • AddSharding: A shard is being added.
az_code	String	Parameter description: AZ code. Value range: N/A.
node_role	String	Parameter description: Node role. Value range: • redis-server: Redis server node • redis-proxy: proxy node

Parameter	Type	Description
node_type	String	Parameter description: Node master/standby role. Value range: • master: master node • slave: standby node • proxy: node of a Proxy Cluster instance
node_ip	String	Parameter description: Node IP. Value range: N/A.
node_port	String	Parameter description: Node port. Value range: N/A.
node_id	String	Parameter description: Node ID. Value range: N/A.
priority_weight	Integer	Parameter description: Replica promotion priority. Value range: Priority ranges from 0 to 100 in descending order. 0 indicates that the replica will never be automatically promoted, 1 indicates the highest priority, and 100 indicates the lowest priority.
is_access	Boolean	Parameter description: Whether the IP address of the node can be directly accessed. Value range: • true • false
group_id	String	Parameter description: Instance shard ID. Value range: N/A.

Parameter	Type	Description
group_name	String	Parameter description: Instance shard name. Value range: N/A.
is_remove_ip	Boolean	Parameter description: Whether the IP address is removed from the read-only domain name. Value range: • true • false
replication_id	String	Parameter description: Instance replica ID. Value range: N/A.
dimensions	Array of InstanceReplicationDimensionsInfo objects	Parameter description: Monitoring metric dimension of the replica used to call the Cloud Eye API for querying monitoring metrics. • Replica monitoring is multi-dimensional. The returned array contains information about two dimensions. When querying monitoring data from Cloud Eye, transfer parameters of multiple dimensions to obtain the metric data. • The first dimension is the primary dimension of the replica. The dimension name is dc_instance_id, and the dimension value is the ID of the instance where the replica is located. • The name of the second dimension is dc_cluster_redis_node, and the dimension value is the ID of the monitored object of the replica, which is different from the replica ID or node ID. Value range: N/A.

Table 4-124 InstanceReplicationDimensionsInfo

Parameter	Type	Description
name	String	Parameter description: Monitoring dimension name. Value range: • dc_instance_id: instance dimension • dc_cluster_redis_node: data node dimension
value	String	Parameter description: Dimension value. Value range: N/A.

Status code: 500

Table 4-125 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 400

Table 4-126 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/logical-nodes?status={status}
```

Example Responses

Status code: 200

Node information queried successfully.

```
{
  "instance_id": "11368fbb-de1e-4613-9080-1c374b71a1af",
  "total": 1,
  "nodes": [ {
    "logical_node_id": "79653bcbd0e5c104fefedd188aa372d6",
    "name": "(master)192.168.68.157",
    "status": "Active",
    "az_code": "region01",
    "node_role": "redis-server",
    "node_type": "master",
    "node_ip": "192.168.68.157",
    "node_id": "ff80808189bf92a50189d330303b77aa",
    "is_access": true,
    "group_id": "6e0f6e95-57cd-4baf-86d6-bea8815b25a8",
    "group_name": "group-0",
    "priority_weight": 100,
    "is_remove_ip": false,
    "dimensions": [ {
      "name": "dcs_instance_id",
      "value": "11368fbb-de1e-4613-9080-1c374b71a1af"
    } ],
    "name": "dcs_cluster_redis_node",
    "value": "79653bcbd0e5c104fefedd188aa372d6"
  } ],
  "replication_id": null
}
```


Status code: 500

Internal service error.

```
{
  "error_code" : "DCS.5000",
  "error_msg" : "Internal service error."
}
```

Status code: 400

Invalid request.

```
{
  "error_code" : "DCS.4800",
  "error_msg" : "Invalid offset in the request."
}
```

Status Codes

Status Code	Description
200	Node information queried successfully.
500	Internal service error.
400	Invalid request.

Error Codes

See [Error Codes](#).

4.4 Parameter Management

4.4.1 Querying DCS Instance Configuration Parameters

Function

This API is used to query the configuration parameters of a DCS instance.

URI

GET /v2/{project_id}/instances/{instance_id}/configs

Table 4-127 Path Parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A. Value range: N/A. Default value: N/A.
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-128 Response body parameters

Parameter	Type	Description
config_time	String	Parameter description: Time when the instance was operated on. For example, 2017-03-31T12:24:46.297Z. Value range: N/A.

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A.
redis_config	Array of QueryRedisConfig objects	Parameter description: Array of configuration items of the instance. Value range: N/A.
config_status	String	Parameter description: Instance status that is being modified or has been modified. Value range: • UPDATING: The modification is in progress. • FAILURE: The modification failed. • SUCCESS: The modification succeeded.

Parameter	Type	Description
status	String	Parameter description: Instance status. Value range: • PAYING: The order has not been paid or is being processed. • CREATING: The DCS instance is being created. • RUNNING: The DCS instance is running. • CLOSING: The DCS instance is stopping. • STARTING: The DCS instance is starting. • RESTARTING: The DCS instance is restarting. • CLOSED: The DCS instance has stopped. • DELETING: The DCS instance is being deleted. • DELETED: The DCS instance has been deleted. • ERROR: The DCS instance is not running properly. • FAILURE: The DCS instance fails to be configured. • SUCCESS: The DCS instance is successfully configured. • CREATEFAILED: The DCS instance fails to be created. • DELETEFAILED: The DCS instance fails to be deleted. • FREEZING: The instance is frozen. • EXTENDING: The DCS instance's capacity is being increased. • EXTENDEDFAILED: The instance's capacity fails to be increased. • MIGRATING: The DCS instance is migrating data. • OTHER: other status. • FLUSHING: The instance data is being cleared. • RESTORING: The backup data is being restored.

Parameter	Type	Description
		• UPGRADING: The instance software is being upgraded. • IPEXCHANGING: IP switch is in progress. • IROLLBACKING: IP addresses are being rolled back. • MS_SWAPPING: The master/standby switchover is in progress. • AZMigrating: The AZ is being migrated.

Table 4-129 QueryRedisConfig

Parameter	Type	Description
param_value	String	Parameter description: Configuration parameter value. Value range: N/A.
value_type	String	Parameter description: Type of the configuration parameter value. For example, Integer and String. Value range: N/A.
value_range	String	Parameter description: Range of the configuration parameter value. Value range: N/A.
description	String	Parameter description: Description of the configuration item. Value range: N/A.
default_value	String	Parameter description: Default value of the configuration parameter. Value range: N/A.

Parameter	Type	Description
param_name	String	Parameter description: Configuration parameter name. Value range: N/A.
param_id	String	Parameter description: Configuration parameter ID. Value range: N/A.

Status code: 400

Table 4-130 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-131 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/configs
```

Example Responses

Status code: 200

Instance configuration parameters queried successfully.

```
{
  "instance_id" : "50829e5a-a4fc-4c01-8651-80be8a491602",
  "config_status" : "SUCCESS",
  "config_time" : "2020-07-06T07:04:31.464Z",
  "redis_config" : [ {
    "param_id" : "1",
    "param_name" : "timeout",
    "description" : "Close the connection after a client is idle for N seconds (0 to disable)",
    "param_value" : "101",
    "value_range" : "0-7200",
    "value_type" : "Integer",
    "default_value" : "0"
  } ],
  "status" : "RUNNING"
}
```

Status Codes

Status Code	Description
200	Instance configuration parameters queried successfully.

Status Code	Description
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.4.2 Modifying Configuration Parameters

Function

You can modify the configuration parameters of your DCS instance to optimize DCS performance based on your requirements.

URI

PUT /v2/{project_id}/instances/{instance_id}/configs

Table 4-132 Path Parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID.
project_id	Yes	String	Project ID.

Request Parameters

Table 4-133 Request body parameters

Parameter	Mandatory	Type	Description
redis_config	No	Array of RedisConfig objects	Array of configuration items of the DCS instance.

Table 4-134 RedisConfig

Parameter	Mandatory	Type	Description
param_value	Yes	String	Value of the configuration item.

Parameter	Mandatory	Type	Description
param_name	Yes	String	Configuration item name.
param_id	Yes	String	Configuration item ID.

Response Parameters

Status code: 204

DCS instance configurations modified successfully.

Status code: 400

Table 4-135 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-136 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Modifying the instance configuration parameters. For example, set the **timeout** parameter (maximum amount of idle time after which a client connection is terminated) to 1000 seconds.

```
PUT https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/configs
```

```
{
  "redis_config": [ {
    "param_id": "1",
    "param_name": "timeout",
    "param_value": "1000"
  } ]
}
```

Example Responses

None

Status Codes

Status Code	Description
204	DCS instance configurations modified successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.4.3 Querying the List of Instance Parameter Modification Records

Function

This API is used to query the parameter modification record list of an instance by keyword.

URI

GET /v2/{project_id}/instances/{instance_id}/config-histories

Table 4-137 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Table 4-138 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0
limit	No	Integer	Definition: Number of records displayed on each page. Constraints: N/A Range: 1–1000 Default Value: 10

Request Parameters

None

Response Parameters

Status code: 200

Table 4-139 Response body parameters

Parameter	Type	Description
history_num	Integer	Definition: Number of instance parameter modification records. Range: N/A

Parameter	Type	Description
histories	Array of HistoryInfo objects	Definition: Details of instance parameter modification records.

Table 4-140 HistoryInfo

Parameter	Type	Description
history_id	String	Definition: Modification record ID. Range: N/A
type	String	Definition: Modification type. Range: config_param: instance configuration parameters
created_at	String	Definition: Modification time. Range: N/A
status	String	Definition: Modification status. Range: • SUCCESS: The instance parameter is modified successfully. • FAILURE: The instance parameter fails to be modified. • EXECUTING: The instance parameter is being modified.

Status code: 400

Table 4-141 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-142 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/config-histories?offset=0&limit=10
```

Example Responses

Status code: 200

Definition:

List of instance parameter modification records queried successfully.

```
{
  "history_num" : 1,
  "histories" : [ {
    "history_id" : "4ae8507f-7992-40e2-9928-41ccf1db4bdc",
    "type" : "config_param",
    "created_at" : "2022-10-20T03:37:44.636Z",
    "status" : "SUCCESS"
  } ]
}
```

Status Codes

Status Code	Description
200	Definition: List of instance parameter modification records queried successfully.
400	Definition: Invalid request.
500	Definition: Internal service error.

Error Codes

See [Error Codes](#).

4.5 Backup and Restoration

4.5.1 Deleting Backup Files

Function

This API is used to delete the backup files of a DCS instance.

URI

```
DELETE /v2/{project_id}/instances/{instance_id}/backups/{backup_id}
```

Table 4-143 Path Parameters

Parameter	Mandatory	Type	Description
backup_id	Yes	String	Backup ID.
instance_id	Yes	String	Instance ID.
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

None

Response Parameters

Status code: 204

Backup file deleted successfully.

Status code: 400

Table 4-144 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 500

Table 4-145 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Example Requests

```
DELETE https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/backups/{backup_id}
```

Example Responses

None

Status Codes

Status Code	Description
204	Backup file deleted successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.5.2 Restoring a DCS Instance

Function

This API is used to restore the backup data to a specific DCS instance.

 NOTE

Only master/standby and cluster DCS instances can be backed up and restored, while single-node instances cannot.

URI

POST /v2/{project_id}/instances/{instance_id}/restores

Table 4-146 Path Parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID.
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

Table 4-147 Request body parameters

Parameter	Mandatory	Type	Description
backup_id	Yes	String	Backup ID.
remark	No	String	Description of DCS instance restoration.

Response Parameters

Status code: 200

Table 4-148 Response body parameters

Parameter	Type	Description
restore_id	String	ID of the restoration record.

Status code: 400

Table 4-149 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 500

Table 4-150 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Example Requests

Restoring the backup files of the DCS instance

```
POST https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/restores
{
  "backup_id" : "8ba256cb-e5ac-44f6-a3da-c03d8f0e5029",
  "remark" : "restore instance"
}
```

Example Responses

Status code: 200

Successful

```
{
  "restore_id" : "a6155972-800c-4170-a479-3231e907d2f6"
}
```

Status Codes

Status Code	Description
200	Successful
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.5.3 Querying DCS Instance Restoration Records

Function

This API is used to query the restoration records of a specific DCS instance.

URI

GET /v2/{project_id}/instances/{instance_id}/restores

Table 4-151 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Table 4-152 Query Parameters

Parameter	Mandatory	Type	Description
begin_time	No	String	Definition: Query start time. Constraints: Format: yyyyMMddHHmmss, for example, 20170718235959. Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
end_time	No	String	Definition: Query end time. Constraints: Format: yyyyMMddHHmmss, for example, 20170718235959. Range: N/A Default Value: N/A
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0
limit	No	Integer	Definition: Number of records displayed on each page. Constraints: N/A Range: 1–1000 Default Value: 10

Request Parameters

None

Response Parameters

Status code: 200

Table 4-153 Response body parameters

Parameter	Type	Description
restore_record_response	Array of InstanceRestoreInfo objects	Definition: Array of the restoration records.
total_num	Integer	Definition: Total restoration records. Range: N/A

Table 4-154 InstanceRestoreInfo

Parameter	Type	Description
backup_id	String	Definition: Backup record ID. Range: N/A
restore_id	String	Definition: ID of the restoration record. Range: N/A
backup_name	String	Definition: Backup record name. Range: N/A
updated_at	String	Definition: Time when the restoration completed. Range: N/A
restore_remark	String	Definition: Description of the restoration. Range: N/A
created_at	String	Definition: Time when the restoration task was created. Range: N/A

Parameter	Type	Description
progress	String	Definition: Restoration progress. Range: 0-100
error_code	String	Definition: Error code displayed for a restoration failure. Range: • "dcs.08.0001": Failed to start the backup and restoration tool. • "dcs.08.0002": Execution timed out. • "dcs.08.0003": Failed to delete the bucket. • "dcs.08.0004": Failed to obtain the AK/SK. • "dcs.08.0005": Failed to create a bucket. • "dcs.08.0006": Failed to query the backup data size. • "dcs.08.0007": Failed to synchronize data during restoration. • "dcs.08.0008": The scheduled backup task is not running. The instance is running other tasks.
restore_name	String	Definition: Name of the restoration record. Range: N/A
backup_remark	String	Definition: Description of the backup. Range: N/A
status	String	Definition: Restoration status. Range: • waiting • restoring • succeed • failed

Status code: 204

No instance restoration record found.

Status code: 400

Table 4-155 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 500

Table 4-156 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/restores?
offset={offset}&limit={limit}&begin_Time={begin_Time}&end_Time={end_Time}
```

Example Responses

Status code: 200

DCS instance restoration records queried.

```
{
  "restore_record_response": [ {
    "backup_id": "f4823e9e-fe9b-4ffd-be79-4e5d6de272bb",
    "restore_id": "a6155972-800c-4170-a479-3231e907d2f6",
    "backup_name": "backup_20170718000002",
    "updated_at": "2017-07-18T21:41:35.182Z",
    "restore_remark": "doctest",
    "created_at": "2017-07-18T21:41:20.721Z",
    "progress": "100.00",
    "error_code": { },
    "restore_name": "restore_20170718214120",
    "backup_remark": { },
    "status": "succeed"
  } ],
  "total_num": 1
}
```

Status Codes

Status Code	Description
200	DCS instance restoration records queried.
204	No instance restoration record found.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.5.4 Obtaining the Backup File URL

Function

This API is used to obtain the download links of backup files.

URI

POST /v2/{project_id}/instances/{instance_id}/backups/{backup_id}/links

Table 4-157 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A
backup_id	Yes	String	Definition: Backup record ID. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

Table 4-158 Request body parameters

Parameter	Mandatory	Type	Description
expiration	Yes	Integer	Definition: Validity period of a URL. Constraints: The value must be within 5 minutes and 24 hours. Range: N/A Default Value: N/A

Response Parameters

Status code: 200

Table 4-159 Response body parameters

Parameter	Type	Description
file_path	String	Definition: Paths of files in the OBS bucket. Range: N/A
bucket_name	String	Definition: OBS bucket name. Range: N/A
links	Array of LinksItem objects	Definition: Collection of URLs for downloading backup files. A maximum of 64 links are allowed.

Table 4-160 LinksItem

Parameter	Type	Description
file_name	String	Definition: Backup file name. Range: N/A
link	String	Definition: URL for downloading backup files. Range: N/A

Status code: 400

Table 4-161 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 500

Table 4-162 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Example Requests

Obtaining the download links of backup files with 1800s validity

```
POST https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/backups/{backup_id}/links
{
  "expiration" : 1800
}
```

Example Responses

Status code: 200

Successfully obtained backup file URLs.

```
{
  "file_path" : "42489641-23c4-4855-bc89-befc85e2b7f7/ddfe5f66-a965-43ff-aec7-f3b489dc071b/",
  "bucket_name" : "bucket5da9cf3bfabc4cae9023695b934e5e2b",
  "links" : [ {
    "file_name" : "redis_192.168.63.250_6379_10923-16383_20190820211816.rdb",
    "link" : "https://bucket5da9cf3bfabc4cae9023695b934e5e2b.{obs_endpoint}:443/42489641-23c4-4855-bc89-befc85e2b7f7/ddfe5f66-a965-43ff-aec7-f3b489dc071b/redis_192.168.63.250_6379_10923-16383_20190820211816.rdb?AWSAccessKeyId=VD8CEQNG8VMQODUAAM0D&Expires=1566308915&Signature=s3l%2BrLbo%2BFZw%2BUjVere%2FOQdKEg%3D"
  } ]
}
```

Status Codes

Status Code	Description
200	Successfully obtained backup file URLs.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.5.5 Backing Up a DCS Instance

Function

This API is used to back up a specific DCS instance.

NOTE

Only master/standby and cluster DCS instances can be backed up and restored, while single-node instances cannot.

URI

POST /v2/{project_id}/instances/{instance_id}/backups

Table 4-163 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

Table 4-164 Request body parameters

Parameter	Mandatory	Type	Description
remark	No	String	Definition: Description of DCS instance backup. Constraints: N/A Range: N/A Default Value: N/A
backup_format	No	String	Definition: Format of the DCS instance backup. Constraints: N/A Range: • aof • rdb Default Value: rdb

Response Parameters

Status code: 200

Table 4-165 Response body parameters

Parameter	Type	Description
backup_id	String	Definition: Backup record ID. Range: N/A

Status code: 400

Table 4-166 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 500

Table 4-167 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A

Parameter	Type	Description
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Example Requests

Backing up a specified DCS instance to an AOF file

```
POST https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/backups
{
  "remark" : "Backup instances",
  "backup_format" : "aof"
}
```

Example Responses

Status code: 200

The specified DCS instance is backed up successfully.

```
{
  "backup_id" : "548ceeff-2cbb-47ab-9a1c-7b085a8c08d7"
}
```

Status Codes

Status Code	Description
200	The specified DCS instance is backed up successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.5.6 Listing DCS Instance Backup Records

Function

This API is used to query the backup records of a specific DCS instance.

URI

GET /v2/{project_id}/instances/{instance_id}/backups

Table 4-168 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Table 4-169 Query Parameters

Parameter	Mandatory	Type	Description
begin_time	No	String	Definition: Query start time. Constraints: Format: yyyyMMddHHmmss, for example, 20170718235959. Range: N/A Default Value: N/A
end_time	No	String	Definition: Query end time. Constraints: Format: yyyyMMddHHmmss, for example, 20170718235959. Range: N/A Default Value: N/A
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0

Parameter	Mandatory	Type	Description
limit	No	Integer	Definition: Number of records displayed on each page. Constraints: N/A Range: 1–1000 Default Value: 10

Request Parameters

None

Response Parameters

Status code: 200

Table 4-170 Response body parameters

Parameter	Type	Description
total_num	Integer	Definition: Number of records returned for instance backup. Range: N/A
backup_record_response	Array of BackupRecordResponse objects	Definition: Array of the backup details.

Table 4-171 BackupRecordResponse

Parameter	Type	Description
backup_id	String	Definition: Backup record ID. Range: N/A

Parameter	Type	Description
period	String	Definition: Backup execution time. Range: N/A
backup_name	String	Definition: Backup record name. Range: N/A
instance_id	String	Definition: Instance ID. Range: N/A
size	Long	Definition: Size of the backup file (byte). Range: N/A
backup_type	String	Definition: Backup type. Range: • manual: manual backup • auto: automatic backup
created_at	String	Definition: Time when the backup task is created. Range: N/A
updated_at	String	Definition: Time at which DCS instance backup is completed. Range: N/A
progress	String	Definition: Backup progress. Range: N/A

Parameter	Type	Description
error_code	String	Definition: Error code displayed for a backup failure. Range: • "dcs.08.0001": Failed to start the backup and restoration tool. • "dcs.08.0002": Execution timed out. • "dcs.08.0003": Failed to delete the bucket. • "dcs.08.0004": Failed to obtain the AK/SK. • "dcs.08.0005": Failed to create a bucket. • "dcs.08.0006": Failed to query the backup data size. • "dcs.08.0007": Failed to synchronize data during restoration. • "dcs.08.0008": The scheduled backup task is not running. The instance is running other tasks.
remark	String	Definition: Description of DCS instance backup. Range: N/A
status	String	Definition: Backup status. Range: • waiting: The task is waiting to begin. • backuping: DCS instance backup is in progress. • succeed: DCS instance backup succeeded. • failed: DCS instance backup failed. • expired: The backup file has expired. • deleted: The backup file has been deleted manually.

Parameter	Type	Description
is_support_restore	String	Definition: Whether restoration is supported. Range: • TRUE: Yes • FALSE: No
execution_at	String	Definition: Execution time. Range: N/A
backup_format	String	Definition: Backup type. Range: • aof • rdb

Status code: 204

No DCS instance backup record is found.

Status code: 400

Table 4-172 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 500

Table 4-173 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instances/{instance_id}/backups?
offset={offset}&limit={limit}&beginTime={begin_Time}&end_time={end_Time}
```

Example Responses

Status code: 200

DCS instance backup records queried successfully.

```
{
  "total_num" : 1,
  "backup_record_response" : [ {
    "period" : { },
    "backup_type" : "manual",
    "created_at" : "2019-05-10T08:31:16.166Z",
    "remark" : "001",
    "is_support_restore" : "TRUE",
    "backup_id" : "4631832a-14c6-45b0-a0b3-3abd8f591ad1",
    "backup_name" : "backup_20190510163116",
    "instance_id" : "5560df16-cebf-4473-95c4-d1b573c16e79",
    "size" : 880232,
    "updated_at" : "2019-05-10T08:32:30.546Z",
    "progress" : "100.00",
    "error_code" : { },
    "status" : "succeed",
    "execution_at" : "2019-05-11T08:31:16.166Z",
    "backup_format" : "aof"
  } ]
}
```

Status Codes

Status Code	Description
200	DCS instance backup records queried successfully.
204	No DCS instance backup record is found.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

Data Migration

4.6.1 Creating a Backup Import Task

Function

This API is used to create a backup import task.

URI

POST /v2/{project_id}/migration-task

Table 4-174 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

Table 4-175 Request body parameters

Parameter	Mandatory	Type	Description
task_name	Yes	String	Backup import task name.
description	No	String	Backup import task description.

Parameter	Mandatory	Type	Description
migration_type	Yes	String	Migration mode. Options: • backupfile_import: importing backup files • online_migration: migrating data online This API can no longer be used to create an online migration task. Please call CreateOnlineMigration-Task instead.
migration_method	Yes	String	Type of the migration, which can be full migration or incremental migration. Values: • full_amount_migration: full migration • incremental_migration: incremental migration
backup_files	No	BackupFilesBody object	Backup files to be imported when the migration mode is backup file import.
network_type	No	String	Type of the network for communication between the source and target Redis when the migration mode is online data migration. This API can no longer be used to create an online migration task. Please call CreateOnlineMigration-Task instead.
source_instance	No	SourceInstanceBody object	Source Redis information. This parameter is mandatory when the migration mode is online data migration. This API can no longer be used to create an online migration task. Please call CreateOnlineMigration-Task instead.
target_instance	Yes	TargetInstanceBody object	Target Redis information.

Table 4-176 BackupFilesBody

Parameter	Mandatory	Type	Description
file_source	Yes	String	Data source • self_build_obs: instance backup records • backup_record: OBS bucket data
bucket_name	No	String	OBS bucket name. Mandatory when the data source is an OBS bucket.
files	Yes	Array of Files objects	List of backup files to be imported. This parameter is mandatory when the data source is an OBS bucket.
backup_id	No	String	Backup record ID. This parameter is mandatory when the data source is a backup record.

Table 4-177 Files

Parameter	Mandatory	Type	Description
file_name	Yes	String	Name of a backup file.
size	No	String	File size in bytes.
update_at	No	String	Time when the file was last modified. The format is YYYY-MM-DD HH:MM:SS.

Table 4-178 SourceInstanceBody

Parameter	Mandatory	Type	Description
addr	Yes	String	Source Redis address (specified in the source_instance parameter).
password	No	String	Redis password. If a password is set, this parameter is mandatory.
task_status	No	String	Task status.
id	No	String	Redis instance ID.

Parameter	Mandatory	Type	Description
ip	No	String	Redis IP address.
port	No	String	Redis port.
name	No	String	Redis name.
proxy_multi_db	No	Boolean	Indicates whether multi-DB is enabled for Proxy Cluster DCS instances.
db	No	String	Redis database.

Table 4-179 TargetInstanceBody

Parameter	Mandatory	Type	Description
id	Yes	String	Redis instance ID (mandatory in the target_instance parameter).
name	No	String	Redis instance name (specified in the target_instance parameter).
password	No	String	Redis password. If a password is set, this parameter is mandatory.
task_status	No	String	Task status.
ip	No	String	Redis IP address.
port	No	String	Redis port.
addrs	No	String	Redis instance address.
proxy_multi_db	No	Boolean	Indicates whether multi-DB is enabled for Proxy Cluster DCS instances.
db	No	String	Redis database.

Response Parameters

Status code: 200

Table 4-180 Response body parameters

Parameter	Type	Description
id	String	Migration task ID.

Parameter	Type	Description
name	String	Migration task name.
status	String	Migration status. Options: SUCCESS , FAILED , MIGRATING , TERMINATED .
error	String	Error message.

Status code: 400

Table 4-181 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-182 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-183 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-184 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-185 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Creating a backup import task to migrate data from an OBS bucket

```
POST https://{dcs_endpoint}/v2/{project_id}/migration-task

{
  "task_name" : "migration1",
  "description" : "Test",
  "migration_type" : "backupfile_import",
  "migration_method" : "full_amount_migration",
  "backup_files" : {
    "bucket_name" : "bucketName",
    "file_source" : "self_build_obs",
    "files" : [ {
      "size" : "754.0MB",
      "file_name" : "fileName"
    } ]
  },
  "target_instance" : {
    "id" : "d2c8399f-bdba-43c1-8069-3ff17a1a79d5",
    "name" : "dcs-test",
    "password" : "xxxxxx"
  }
}
```

Example Responses

Status code: 200

Backup import task created.

```
{
  "id" : "8aa6999e71cb638b0171f485f5266ef0",
  "name" : "dcs-test",
  "status" : "MIGRATING",
  "error" : ""
}
```

Status Codes

Status Code	Description
200	Backup import task created.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.2 Listing Migration Tasks

Function

This API is used to query the migration task list.

URI

GET /v2/{project_id}/migration-tasks

Table 4-186 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Table 4-187 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0

Parameter	Mandatory	Type	Description
limit	No	Integer	Parameter description: Number of records displayed on each page. Constraints: N/A. Value range: 1–1,000 Default value: 10
name	No	String	Parameter description: Name of the migration task. Constraints: N/A. Value range: N/A. Default value: N/A.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-188 Response body parameters

Parameter	Type	Description
count	Integer	Parameter description: Number of migration tasks. Value range: N/A.
migration_tasks	Array of MigrationTaskList objects	Parameter description: Migration task list. Value range: N/A.

Table 4-189 MigrationTaskList

Parameter	Type	Description
task_id	String	Parameter description: Migration task ID. Value range: N/A.
task_name	String	Parameter description: Migration task name. Value range: N/A.
status	String	Parameter description: Migration status. Value range: • SUCCESS: The task succeeded. • FAILED: The task failed. • MIGRATING: Migration is in progress. • TERMINATED: The task has stopped.
migration_type	String	Parameter description: Migration mode. Value range: • backupfile_import: backup file import • online_migration: online migration
migration_method	String	Parameter description: Type of the migration. Value range: • full_amount_migration: full migration • incremental_migration: incremental migration
ecs_tenant_private_ip	String	Parameter description: Private IP address of the migration ECS on the tenant side. This IP address can be added to the whitelist if it is in the same VPC as the private IP address of the target or source Redis. Value range: N/A.

Parameter	Type	Description
data_source	String	Parameter description: Source Redis address, which is ip:port or a bucket name. Value range: N/A.
source_instance_name	String	Parameter description: Name of the source instance. If the source Redis is self-hosted, this parameter is left blank. Value range: N/A.
source_instance_id	String	Parameter description: ID of the source instance. If the source Redis is self-hosted, this parameter is left blank. Value range: N/A.
target_instance_addresses	String	Parameter description: Target Redis address. The format is ip:port . Value range: N/A.
target_instance_name	String	Parameter description: Target instance name. Value range: N/A.
target_instance_id	String	Parameter description: Target instance ID. Value range: N/A.
created_at	String	Parameter description: Time when the migration task is created. Value range: N/A.

Parameter	Type	Description
description	String	Parameter description: Description of the migration task. Value range: N/A.
source_instance_status	String	Parameter description: Status of the source instance. If the source Redis is self-hosted, this parameter is left blank. Value range: N/A.
target_instance_status	String	Parameter description: Status of the target instance. Value range: N/A.
source_instance_subnet_id	String	Parameter description: ID of the source instance subnet. If the source Redis is self-hosted, this parameter is left blank. Value range: N/A.
target_instance_subnet_id	String	Parameter description: ID of the target instance subnet. Value range: N/A.
source_instance_spec_code	String	Parameter description: Specification code of the source instance. If the source Redis is self-hosted, this parameter is left blank. Value range: N/A.
target_instance_spec_code	String	Parameter description: Specification code of the target instance. Value range: N/A.

Parameter	Type	Description
error_message	String	Parameter description: Error message. Value range: N/A.
released_at	String	Parameter description: Time when the migration ECS is released. Value range: N/A.
version	String	Parameter description: Migration task version. Value range: N/A.
resume_mode	String	Parameter description: Operation mode of the migration task. Value range: • auto: automatically reconnect • manual: manually reconnect
supported_features	Array of strings	Parameter description: Supported features. Value range: N/A.

Status code: 400

Table 4-190 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-191 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-192 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-193 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-194 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/666486c2d9b948c1bbea57e714d744fa/migration-tasks?offset=0&limit=10&name=dcs-migration-i9qk
```

Example Responses

Status code: 200

Querying the migration task list.

```
{
  "count": 1,
  "migration_tasks": [ {
    "task_id": "2944a563-6f27-4604-9c16-a9a53cd95cc7",
    "task_name": "dcs-migration-test-6-16",
    "status": "TERMINATED",
    "migration_type": "online_migration",
    "migration_method": "incremental_migration",
    "data_source": "192.168.0.200:6379",
    "source_instance_name": "migration-resource",
    "source_instance_id": "132e0017-715b-4556-930a-95c7db7e8f7a",
    "target_instance_addr": "192.168.0.153:6379",
    "target_instance_name": "migration-target",
    "target_instance_id": "eb1a8d1c-9ea6-4fcd-ac43-c3d3c2493f06",
    "created_at": "2021-06-16T06:12:55.508Z",
    "description": "dcs-test",
    "source_instance_status": "RUNNING",
    "target_instance_status": "RUNNING",
    "source_instance_subnet_id": "192.168.0.1",
    "target_instance_subnet_id": "192.168.0.2",
    "source_instance_spec_code": "redis.single.xu1.tiny.128",
    "target_instance_spec_code": "redis.single.xu1.tiny.128",
    "error_message": null,
    "released_at": "202404011057",
    "version": "6.0.21",
  } ]
}
```

```
"resume_mode" : "auto",  
"supported_features" : [ ]  
} ]  
}
```

Status Codes

Status Code	Description
200	Querying the migration task list.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.3 Deleting Data Migration Tasks

Function

This API is used to delete data migration tasks.

URI

DELETE /v2/{project_id}/migration-tasks/delete

Table 4-195 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

Table 4-196 Request body parameters

Parameter	Mandatory	Type	Description
task_id_list	Yes	Array of strings	Definition: List of IDs of the migration tasks to delete. Constraints: N/A

Response Parameters

Status code: 200

Table 4-197 Response body parameters

Parameter	Type	Description
task_id_list	Array of strings	Definition: List of IDs of the migration tasks to delete.

Status code: 400

Table 4-198 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-199 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-200 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-201 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-202 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Deleting data migration tasks

```
DELETE https://{dcs_endpoint}/v2/666486c2d9b948c1bbea57e714d744fa/migration-tasks/delete
{
  "task_id_list" : [ "2fb6b7e2-5eb8-4380-9d60-ce8d12b19aca" ]
}
```

Example Responses

Status code: 200

Data migration task is deleted when the migration task ID exists. No operation is performed when the ID does not exist.

```
{
  "task_id_list" : [ "2fb6b7e2-5eb8-4380-9d60-ce8d12b19aca" ]
}
```

Status Codes

Status Code	Description
200	Data migration task is deleted when the migration task ID exists. No operation is performed when the ID does not exist.
400	Invalid request.
401	Invalid authentication information.

Status Code	Description
403	The request is rejected.
404	The requested resource does not exist. (No response. For details, see status code 200 .)
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.4 Querying Details of a Data Migration Task

Function

This API is used to query migration task details.

URI

GET /v2/{project_id}/migration-task/{task_id}

Table 4-203 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
task_id	Yes	String	Definition: ID of the data migration task. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-204 Response body parameters

Parameter	Type	Description
task_id	String	Definition: Migration task ID. Range: N/A
task_name	String	Definition: Name of the migration task. Range: N/A
description	String	Definition: Description of the migration task. Range: N/A

Parameter	Type	Description
status	String	Definition Status of the migration task. Range • SUCCESS: The task succeeded. • FAILED: The task failed. • MIGRATING: Migration is in progress. • TERMINATED: The task has stopped. • TERMINATING: The task is being stopped. • INCRMIGEATING: Incremental migration is in progress. • FULLMIGRATING: Full migration is in progress. • RUNNING: The task is to be configured. • MIGRATION_FAILED: The migration failed. • RELEASED: The task has been released.
migration_type	String	Definition Description of the migration task. Range • backupfile_import: backup import • online_migration: online migration
migration_method	String	Definition: Type of the migration. Range: • full_amount_migration: full migration • incremental_migration: online migration
ecs_tenant_private_ip	String	Definition: Private IP address of the migration ECS on the tenant side. This IP address can be added to the whitelist if it is in the same VPC as the private IP address of the target or source Redis. Range: N/A

Parameter	Type	Description
backup_files	BackupFilesRespBody object	Definition: Backup files to be imported when the migration mode is backup file import.
network_type	String	Definition: Network type. The value can be vpc or vpn . Range: • vpc • vpn
source_instance	SourceInstanceRespBody object	Definition: Source Redis information.
target_instance	TargetInstanceRespBody object	Definition: Target Redis instance information.
created_at	String	Definition: Time when the migration task is created. Range: N/A
updated_at	String	Definition: Time when the migration task is complete. Range: N/A
released_at	String	Definition: Time when the migration ECS is released. Range: N/A
version	String	Definition: Version of the migration ECS. Range: N/A
resume_mode	String	Definition: Data migration mode. Range: • auto: automatic migration • manual: manual migration

Parameter	Type	Description
supported_features	Array of strings	Definition: Supported features. Range: N/A
tenant_vpc_id	String	Definition: VPC ID. Range: N/A
tenant_subnet_id	String	Definition: Subnet ID. Range: N/A
tenant_security_group_id	String	Definition: Security group ID. Range: N/A
bandwidth_limit_mb	String	Definition: Maximum bandwidth. Range: N/A
task_status	String	Definition: Task status. EXCHANGING is returned only when IP addresses are being switched. Range: EXCHANGING: IP addresses are being switched.

Table 4-205 BackupFilesRespBody

Parameter	Type	Description
file_source	String	Definition: Data source, which can be an OBS bucket or a backup record. Range: self_build_obs: OBS bucket data. backup_record: Redis backup file.

Parameter	Type	Description
bucket_name	String	Definition: OBS bucket name. Range: N/A
files	Array of FilesResp objects	Definition: List of backup files to be imported.
backup_id	String	Definition: Backup record ID. Range: N/A

Table 4-206 FilesResp

Parameter	Type	Description
file_name	String	Definition: Name of a backup file. Range: N/A
size	String	Definition: File size in bytes. Range: N/A
update_at	String	Definition: Time when the file is last modified. The format is YYYY-MM-DD HH:MM:SS. Range: N/A

Table 4-207 SourceInstanceRespBody

Parameter	Type	Description
addrs	String	Definition: IP address and domain name of the Redis instance. Range: N/A
password	String	Definition: Redis password. Range: N/A
id	String	Definition: Redis instance ID. Range: N/A
ip	String	Definition: Redis IP address. Range: N/A
port	String	Definition: Redis port. Range: N/A
name	String	Definition: Redis name. Range: N/A
proxy_multi_db	Boolean	Definition: Indicates whether multi-DB is enabled for Proxy Cluster DCS instances. Range: • true: Yes • false: No
db	String	Definition: Redis database. Range: 0-255

Parameter	Type	Description
withProxy	Boolean	Definition: Indicates whether proxy nodes are available. Range: • true: Yes • false: No

Table 4-208 TargetInstanceRespBody

Parameter	Type	Description
addrs	String	Definition: Source Redis address (specified in the source_instance parameter). Range: N/A
password	String	Definition: Redis password. Range: N/A
id	String	Definition: Redis instance ID. Range: N/A
ip	String	Definition: Redis IP address. Range: N/A
port	String	Definition: Redis port. Range: N/A
name	String	Definition: Redis name. Range: N/A

Parameter	Type	Description
proxy_multi_db	Boolean	Definition: Indicates whether multi-DB is enabled for Proxy Cluster DCS instances. Range: • true: Yes • false: No
db	String	Definition: Redis database. Range: 0–255
withProxy	Boolean	Definition: Indicates whether proxy nodes are available. Range: • true: Yes • false: No

Status code: 400

Table 4-209 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-210 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-211 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-212 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-213 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/254d2280acb74d36a8b839746bcd7352 /migration-task/  
a276c1ffa0a54c2597fc824b917db317
```

Example Responses

Status code: 200

Details of a data migration task queried successfully.

```
{  
  "task_name" : "migration1",  
  "task_id" : "a276c1ffa0a54c2597fc824b917db317",  
  "status" : "TERMINATING",  
  "migration_type" : "incremental_migration",  
  "network_type" : "vpc",  
  "source_instance" : {  
    "addr" : "192.168.1.2:6379",  
    "id" : "86157b69-8a62-47f9-8c55-fa6ddc8927e1",  
    "name" : "dcs-test",  
    "ip" : "192.168.1.2",  
    "port" : "6379",  
    "proxy_multi_db" : false,  
    "password" : "DCStest123",  
    "db" : "0"  
  },  
  "target_instance" : {  
    "addr" : "192.168.1.2:6379",  
    "id" : "86157b69-8a62-47f9-8c55-fa6ddc8927ee",  
    "name" : "test-instance",  
    "ip" : "192.168.1.2",  
    "port" : "6379",  
    "proxy_multi_db" : false,  
    "password" : "DCStest123",  
    "db" : "0"  
  },  
  "created_at" : "2019/10/22 14:44:30",  
  "updated_at" : "2019/10/22 18:00:00"  
}
```

Status Codes

Status Code	Description
200	Details of a data migration task queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.5 Configuring Auto-Reconnect for Migration Tasks

Function

This API is used to configure auto-reconnect for migration tasks.

URI

PUT /v2/{project_id}/migration-task/{task_id}

Table 4-214 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
task_id	Yes	String	Definition: ID of the data migration task. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

Table 4-215 Request body parameters

Parameter	Mandatory	Type	Description
resume_mode	No	String	Definition: Reconnection mode of the migration tasks. Constraints: N/A Range: • auto: automatically reconnect If the source and target instances are disconnected due to network exceptions, automatic reconnections will be performed indefinitely. Full synchronization will be triggered and requires more bandwidth if incremental synchronization becomes unavailable. Exercise caution when enabling this option. • manual: manually reconnect Default Value: auto.

Response Parameters

Status code: 200

Details of the background task queried successfully.

Status code: 400

Table 4-216 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-217 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-218 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-219 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-220 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
PUT https://{dcs_endpoint}/v2/{project_id}/migration-task/{task_id}
{
  "resume_mode" : "auto"
}
```

Example Responses

Status code: 400

Invalid request.

```
{
  "error_code" : "111400063",
  "error_msg" : "Invalid task_id parameter in the request."
}
```

Status Codes

Status Code	Description
200	Details of the background task queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	Request rejected.

Status Code	Description
404	The requested resource could not be found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.6 Stopping a Data Migration Task

Function

This API is used to stop a data migration task.

URI

POST /v2/{project_id}/migration-task/{task_id}/stop

Table 4-221 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
task_id	Yes	String	Definition: ID of the data migration task. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-222 Response body parameters

Parameter	Type	Description
task_id	String	Definition: Migration task ID. Range: N/A
task_name	String	Definition: Name of the migration task. Range: N/A
description	String	Definition: Description of the migration task. Range: N/A

Parameter	Type	Description
status	String	Definition Status of the migration task. Range • SUCCESS: The task succeeded. • FAILED: The task failed. • MIGRATING: Migration is in progress. • TERMINATED: The task has stopped. • TERMINATING: The task is being stopped. • INCRMIGEATING: Incremental migration is in progress. • FULLMIGRATING: Full migration is in progress. • RUNNING: The task is to be configured. • MIGRATION_FAILED: The migration failed. • RELEASED: The task has been released.
migration_type	String	Definition Description of the migration task. Range • backupfile_import: backup import • online_migration: online migration
migration_method	String	Definition: Type of the migration. Range: • full_amount_migration: full migration • incremental_migration: online migration
ecs_tenant_private_ip	String	Definition: Private IP address of the migration ECS on the tenant side. This IP address can be added to the whitelist if it is in the same VPC as the private IP address of the target or source Redis. Range: N/A

Parameter	Type	Description
backup_files	BackupFilesRespBody object	Definition: Backup files to be imported when the migration mode is backup file import.
network_type	String	Definition: Network type. The value can be vpc or vpn . Range: • vpc • vpn
source_instance	SourceInstanceRespBody object	Definition: Source Redis information.
target_instance	TargetInstanceRespBody object	Definition: Target Redis instance information.
created_at	String	Definition: Time when the migration task is created. Range: N/A
updated_at	String	Definition: Time when the migration task is complete. Range: N/A
released_at	String	Definition: Time when the migration ECS is released. Range: N/A
version	String	Definition: Version of the migration ECS. Range: N/A
resume_mode	String	Definition: Data migration mode. Range: • auto: automatic migration • manual: manual migration

Parameter	Type	Description
supported_features	Array of strings	Definition: Supported features. Range: N/A
tenant_vpc_id	String	Definition: VPC ID. Range: N/A
tenant_subnet_id	String	Definition: Subnet ID. Range: N/A
tenant_security_group_id	String	Definition: Security group ID. Range: N/A
bandwidth_limit_mb	String	Definition: Maximum bandwidth. Range: N/A
task_status	String	Definition: Task status. EXCHANGING is returned only when IP addresses are being switched. Range: EXCHANGING: IP addresses are being switched.

Table 4-223 BackupFilesRespBody

Parameter	Type	Description
file_source	String	Definition: Data source, which can be an OBS bucket or a backup record. Range: self_build_obs: OBS bucket data. backup_record: Redis backup file.

Parameter	Type	Description
bucket_name	String	Definition: OBS bucket name. Range: N/A
files	Array of FilesResp objects	Definition: List of backup files to be imported.
backup_id	String	Definition: Backup record ID. Range: N/A

Table 4-224 FilesResp

Parameter	Type	Description
file_name	String	Definition: Name of a backup file. Range: N/A
size	String	Definition: File size in bytes. Range: N/A
update_at	String	Definition: Time when the file is last modified. The format is YYYY-MM-DD HH:MM:SS. Range: N/A

Table 4-225 SourceInstanceRespBody

Parameter	Type	Description
addrs	String	Definition: IP address and domain name of the Redis instance. Range: N/A
password	String	Definition: Redis password. Range: N/A
id	String	Definition: Redis instance ID. Range: N/A
ip	String	Definition: Redis IP address. Range: N/A
port	String	Definition: Redis port. Range: N/A
name	String	Definition: Redis name. Range: N/A
proxy_multi_db	Boolean	Definition: Indicates whether multi-DB is enabled for Proxy Cluster DCS instances. Range: • true: Yes • false: No
db	String	Definition: Redis database. Range: 0-255

Parameter	Type	Description
withProxy	Boolean	Definition: Indicates whether proxy nodes are available. Range: • true: Yes • false: No

Table 4-226 TargetInstanceRespBody

Parameter	Type	Description
addrs	String	Definition: Source Redis address (specified in the source_instance parameter). Range: N/A
password	String	Definition: Redis password. Range: N/A
id	String	Definition: Redis instance ID. Range: N/A
ip	String	Definition: Redis IP address. Range: N/A
port	String	Definition: Redis port. Range: N/A
name	String	Definition: Redis name. Range: N/A

Parameter	Type	Description
proxy_multi_db	Boolean	Definition: Indicates whether multi-DB is enabled for Proxy Cluster DCS instances. Range: • true: Yes • false: No
db	String	Definition: Redis database. Range: 0–255
withProxy	Boolean	Definition: Indicates whether proxy nodes are available. Range: • true: Yes • false: No

Status code: 400

Table 4-227 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-228 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-229 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-230 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-231 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
POST https://{dcs_endpoint}/v2/666486c2d9b948c1bbea57e714d744fa/migration-task/2fb6b7e2-5eb8-4380-9d60-ce8d12b19aca/stop
```

Example Responses

Status code: 200

Data migration task stopped successfully.

```
{
  "task_name" : "migration1",
  "task_id" : "a276c1ffa0a54c2597fc824b917db317",
  "status" : "TERMINATING",
  "migration_type" : "incremental_migration",
  "network_type" : "vpc",
  "source_instance" : {
    "addr" : "192.168.1.2:6379",
    "id" : "86157b69-8a62-47f9-8c55-fa6ddc8927e1",
    "name" : "dcs-test",
    "ip" : "192.168.1.2",
    "port" : "6379",
    "proxy_multi_db" : false,
    "password" : "DCStest123",
    "db" : "0"
  },
  "target_instance" : {
    "addr" : "192.168.1.2:6379",
    "id" : "86157b69-8a62-47f9-8c55-fa6ddc8927ee",
    "name" : "test-instance",
    "ip" : "192.168.1.2",
    "port" : "6379",
    "proxy_multi_db" : false,
    "password" : "DCStest123",
    "db" : "0"
  },
  "created_at" : "2019/10/22 14:44:30",
  "updated_at" : "2019/10/22 18:00:00"
}
```

Status Codes

Status Code	Description
200	Data migration task stopped successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.7 Querying the Progress of an Online Migration Task

Function

This API is used to query progress details about an online migration task.

URI

GET /v2/{project_id}/migration-task/{task_id}/stats

Table 4-232 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
task_id	Yes	String	Task ID.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-233 Response body parameters

Parameter	Type	Description
full_migration_progress	String	Percentage of the full migration progress.
offset	String	Offset of incremental migration, which is the difference between the data volume of the source Redis and the target Redis during the incremental migration. If the offset is 0, there is no data difference between the source and the target Redis during the incremental migration.
source_dbsize	String	Number of keys in the source Redis.
target_dbsize	String	Number of keys in the target Redis.
target_input_kbps	String	Key write traffic of the target Redis, in KB/s.

Parameter	Type	Description
target_ops	String	Number of concurrent operations per second on the target Redis.
is_migrating	Boolean	Whether the migration task is in progress.

Status code: 400

Table 4-234 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-235 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-236 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-237 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-238 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
https://{dcs_endpoint}/v2/666486c2d9b948c1bbea57e714d744fa/migration-task/31c6fd2b-2893-430b-90ff-d1adb8060585/stats
```

Example Responses

Status code: 200

Progress of the online migration task queried successfully.

```
{
  "full_migration_progress" : 100,
  "offset" : 100,
  "source_dbsize" : 531221,
  "target_dbsize" : 531211,
  "target_input_kbps" : 50,
  "target_ops" : 5300,
  "is_migrating" : true
}
```

Status code: 400

Invalid request.

```
{
  "error_code" : "DCS.4133",
  "error_msg" : "Instance job is not found."
}
```

Status Codes

Status Code	Description
200	Progress of the online migration task queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.8 Creating an Online Data Migration Task

Function

This API is used to create an online data migration task.

URI

POST /v2/{project_id}/migration/instance

Table 4-239 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

Table 4-240 Request body parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Name of the online migration task.
description	No	String	Description of the online migration task.
vpc_id	Yes	String	VPC ID. To obtain it, do as follows: • Method 1: Log in to the VPC console and view the VPC ID in the VPC details. • Method 2: Call the VPC API. For details, see the API for querying VPCs.
subnet_id	Yes	String	Network ID of the subnet. To obtain it, do as follows: • Method 1: Log in to VPC console and click the target subnet on the Subnets tab page. You can view the network ID on the displayed page. • Method 2: Call the VPC API. For details, see the API for querying subnets.

Parameter	Mandatory	Type	Description
security_group_id	Yes	String	Security group which the instance belongs to. A security group implements access control for VMs within a security group or in different security groups, enhancing VM security. You can define different access rules for a security group to protect the VMs that are added to this security group. To obtain it, do as follows: - Method 1: Log in to the VPC console and choose Access Control > Security Groups. You can create and configure a security group, and obtain the security group ID. - Method 2: Call the API used to query security group details. For details, see the API for querying security group details.

Response Parameters

Status code: 200

Table 4-241 Response body parameters

Parameter	Type	Description
instance_id	String	Online migration task ID.

Status code: 400

Table 4-242 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-243 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-244 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-245 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-246 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Creating an online migration task and configuring the VPC, subnet, and security group for the migration ECS

```
POST https://{dcs_endpoint}/v2/{project_id}/migration/instance
{
  "name" : "dcs-migration-thrc",
  "description" : "Creating an online data migration task",
  "vpc_id" : "5e37b3be-950a-48e1-b498-65b63d336481",
  "subnet_id" : "40f15ed6-7f85-49d5-ba0e-65b940d4812c",
  "security_group_id" : "9df96622-24b7-4813-84b8-ab74552a21d7"
}
```

Example Responses

Status code: 200

Online data migration task created.

```
{
  "instance_id" : "b21989ec-2889-4b8e-99db-19c073425ec2"
}
```

Status Codes

Status Code	Description
200	Online data migration task created.

Status Code	Description
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.9 Configuring an Online Data Migration Task

Function

This API is used to configure an online data migration task.

URI

POST /v2/{project_id}/migration/{task_id}/task

Table 4-247 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
task_id	Yes	String	Online migration task ID.

Request Parameters

Table 4-248 Request body parameters

Parameter	Mandatory	Type	Description
migration_method	Yes	String	Type of the migration. • Full migration is suitable for scenarios where services can be interrupted. Data is migrated at one time. • Incremental migration is suitable for scenarios requiring minimal service downtime. • full_amount_migration: full migration • incremental_migration: incremental migration Source instance data updated during the migration will not be migrated to the target instance. The incremental migration parses logs to ensure data consistency between the source and target instances. After the full migration is complete, incremental migration starts. Options:

Parameter	Mandatory	Type	Description
resume_mode	Yes	String	Reconnection mode. In automatic reconnection mode, if the source and target instances are disconnected due to network exceptions, automatic reconnections will be performed indefinitely. Full synchronization will be triggered and requires more bandwidth if incremental synchronization becomes unavailable. Exercise caution when enabling this option. Values: • auto: automatically reconnect. • manual: manually reconnect.
bandwidth_limit_mb	No	String	Bandwidth limit. For incremental migration, you can limit the bandwidth to ensure smooth service running. When the data synchronization speed reaches the limit, it can no longer increase. - Unit: MB/s. - Value range: 1–10,240 (an integer greater than 0 and less than 10,241).
source_instance	Yes	ConfigMigrationInstanceBody object	Source Redis information.
target_instance	Yes	ConfigMigrationInstanceBody object	Target Redis information.

Table 4-249 ConfigMigrationInstanceBody

Parameter	Mandatory	Type	Description
id	No	String	Redis instance ID (mandatory if the source Redis address is not specified).

Parameter	Mandatory	Type	Description
addrs	No	String	Source Redis address (mandatory if the Redis instance ID is not specified).
password	No	String	Redis password. If a password is set, this parameter is mandatory.

Response Parameters

Status code: 200

Table 4-250 Response body parameters

Parameter	Type	Description
id	String	Migration task ID.
name	String	Migration task name.
status	String	Migration status. Options: SUCCESS , FAILED , MIGRATING , TERMINATED .
error	String	Error message.

Status code: 400

Table 4-251 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-252 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-253 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-254 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-255 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Configuring an online migration task with migration type set to incremental, auto-reconnect enabled, and source and target instances configured

```
POST https://{dcs_endpoint}/v2/{project_id}/migration/{task_id}/task
```

```
{
  "migration_method" : "incremental_migration",
  "bandwidth_limit_mb" : 123,
  "resume_mode" : "auto",
  "source_instance" : {
    "id" : null,
    "addr" : "192.168.1.1:6379,192.168.0.0:6379",
    "password" : "xxxxxx"
  },
  "target_instance" : {
    "id" : "cf4a05df-1c38-47c5-bb5a-0a7b3673b3bd",
    "addr" : null,
    "password" : null
  }
}
```

Example Responses

Status code: 200

Online data migration task configured.

```
{
  "id" : "90754308-a156-406f-a837-8f852f38a646",
  "name" : "dcs-migration-1db7",
  "status" : "FULLMIGRATING",
  "error" : ""
}
```

Status Codes

Status Code	Description
200	Online data migration task configured.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.10 Stopping Data Migration Tasks

Function

This API is used to stop data migration tasks in batches. If a success response is returned, the request is successfully delivered. The migration tasks are stopped only when their status is **TERMINATED**.

URI

POST /v2/{project_id}/migration-task/batch-stop

Table 4-256 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

Table 4-257 Request body parameters

Parameter	Mandatory	Type	Description
migration_tasks	Yes	Array of strings	Data migration task list.

Response Parameters

Status code: 200

Table 4-258 Response body parameters

Parameter	Type	Description
migration_tasks	Array of StopMigrationTaskResult objects	Data migration task list.

Table 4-259 StopMigrationTaskResult

Parameter	Type	Description
result	String	Result of delivering the request for stopping migration tasks.
task_id	String	ID of the data migration task.

Status code: 400

Table 4-260 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-261 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-262 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-263 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-264 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Stopping data migration tasks in batches

```
POST https://{dcs_endpoint}/v2/{project_id}/migration-task/batch-stop

{
  "migration_tasks": [ "b21989ec-2889-4b8e-99db-19c073425ec2", "5130d57f-640a-435b-
bc3a-0fb1860a5340" ]
}
```

Example Responses

Status code: 200

"Migration tasks are being stopped."

 NOTE

The migration tasks are stopped when their status is **TERMINATED**.

```
{
  "migration_tasks": [ {
    "result": "success",
    "task_id": "b21989ec-2889-4b8e-99db-19c073425ec2"
  }, {
    "result": "failed",
    "task_id": "5130d57f-640a-435b-bc3a-0fb1860a5340"
  } ]
}
```

Status code: 400

Invalid request.

```
{
  "error_msg": "invalid migration task id in the request.",
  "error_code": "DCS.4855"
}
```

Status Codes

Status Code	Description
200	"Migration tasks are being stopped." NOTE The migration tasks are stopped when their status is TERMINATED .
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.6.11 Stopping Synchronization of a Data Migration Task

Function

This API is used to stop synchronization of a data migration task.

URI

POST /v2/{project_id}/migration-task/{task_id}/sync-stop

Table 4-265 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
task_id	Yes	String	Task ID.

Request Parameters

None

Response Parameters

Status code: 204

Synchronization of a data migration task stopped successfully.

Status code: 400

Table 4-266 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-267 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-268 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-269 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-270 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

None

Example Responses

None

Status Codes

Status Code	Description
204	Synchronization of a data migration task stopped successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7 Cache Analysis

4.7.1 Creating a Big Key Analysis Task

Function

This API is used to create a big key analysis task for a DCS Redis instance.

URI

POST /v2/{project_id}/instances/{instance_id}/bigkey-task

Table 4-271 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-272 Response body parameters

Parameter	Type	Description
id	String	Parameter description: ID of the big key analysis task. Value range: N/A
instance_id	String	Parameter description: Instance ID. Value range: N/A
status	String	Parameter description: Status of the big key analysis task. Value range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails.
scan_type	String	Parameter description: Analysis method. Value range: • manual: manual analysis. • auto: automatic analysis.
created_at	String	Parameter description: Time when an analysis task is created. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
started_at	String	Parameter description: Time when an analysis task started. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Parameter	Type	Description
finished_at	String	Parameter description: Time when an analysis task ended. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A
num	Integer	Parameter description: Number of big keys. Value range: N/A
keys	Array of BigkeysBody objects	Parameter description: Big key record. (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Table 4-273 BigkeysBody

Parameter	Type	Description
name	String	Parameter description: Key name. Value range: N/A
type	String	Definition: Key type. Range: • string: string type. • list: list type. • set: set type. • zset: ordered type. • hash: hash type.

Parameter	Type	Description
shard	String	Parameter description: Shard where the big key is located. This parameter is available only when the instance type is cluster. The format is <i>ip:port</i> . Value range: N/A
db	Integer	Parameter description: Database where a big key is located. Value range: 0-255
size	Long	Parameter description: Size of the key value. Value range: N/A
unit	String	Parameter description: Key unit. Value range: count: number of keys. byte: key size.

Status code: 400

Table 4-274 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-275 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-276 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-277 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-278 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
POST https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/bigkey-task
```

Example Responses

Status code: 200

Big key analysis task created successfully.

```
{  
  "id" : "858ee14c-2271-4489-8b82-7bda7459ae3e",  
  "instance_id" : "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "status" : "waiting",  
  "scan_type" : "manual",  
  "created_at" : "2020-06-15T02:21:18.669Z",  
  "num" : 0  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4919",  
  "error_msg" : "Does not support bigkey analyze."  
}
```

Status Codes

Status Code	Description
200	Big key analysis task created successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.2 Listing Big Key Analysis Tasks

Function

This API is used to query the list of big key analysis tasks.

URI

GET /v2/{project_id}/instances/{instance_id}/bigkey-tasks

Table 4-279 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A

Table 4-280 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0
limit	No	Integer	Parameter description: Number of records displayed on each page. Constraints: N/A Value range: 1–1000 Default value: 10

Parameter	Mandatory	Type	Description
status	No	String	Definition: Status of the expired key scan task. Constraints: N/A Range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails. Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-281 Response body parameters

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
count	Integer	Parameter description: Number of times that big keys are analyzed. Value range: N/A
records	Array of RecordsResponse objects	Parameter description: List of big key analysis record. Value range: N/A

Table 4-282 RecordsResponse

Parameter	Type	Description
id	String	Definition: ID of the analysis operation task. Range: N/A
status	String	Parameter description: Status of the hot key analysis task. Value range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails.
scan_type	String	Parameter description: Analysis method. Value range: • manual: manual analysis. • auto: automatic analysis.
created_at	String	Parameter description: Time when an analysis task is created. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
started_at	String	Parameter description: Time when an analysis task started. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
finished_at	String	Parameter description: Time when an analysis task ended. The format is 2020-06-15T02:21:18.669Z . Value range: N/A

Status code: 400

Table 4-283 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-284 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-285 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-286 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-287 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/bigkey-tasks
```

Example Responses

Status code: 200

Big key analysis records queried successfully.

```
{  
  "instance_id" : "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "count" : 1,  
  "records" : [ {  
    "id" : "858ee14c-2271-4489-8b82-7bda7459ae3e",  
    "scan_type" : "manual",  
    "status" : "success",  
    "created_at" : "2020-06-15T02:21:18.669Z",  
    "started_at" : "2020-06-15T02:21:23.534Z",  
    "finished_at" : "2020-06-15T02:21:25.588Z"  
  } ]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4919",  
  "error_msg" : "Does not support bigkey analyze."  
}
```

Status Codes

Status Code	Description
200	Big key analysis records queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.3 Querying Big Key Analysis Details

Function

This API is used to query the big key analysis details.

URI

GET /v2/{project_id}/instances/{instance_id}/bigkey-task/{bigkey_id}

Table 4-288 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A
bigkey_id	Yes	String	Definition: ID of the big key analysis task. The ID can be obtained by calling the Listing Big Key Analysis Tasks API. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-289 Response body parameters

Parameter	Type	Description
id	String	Parameter description: ID of the big key analysis task. Value range: N/A

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
status	String	Parameter description: Status of the big key analysis task. Value range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails.
scan_type	String	Parameter description: Analysis method. Value range: • manual: manual analysis. • auto: automatic analysis.
created_at	String	Parameter description: Time when an analysis task is created. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
started_at	String	Parameter description: Time when an analysis task started. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A
finished_at	String	Parameter description: Time when an analysis task ended. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Parameter	Type	Description
num	Integer	Parameter description: Number of big keys. Value range: N/A
keys	Array of BigkeysBody objects	Parameter description: Big key record. (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Table 4-290 BigkeysBody

Parameter	Type	Description
name	String	Parameter description: Key name. Value range: N/A
type	String	Definition: Key type. Range: • string: string type. • list: list type. • set: set type. • zset: ordered type. • hash: hash type.
shard	String	Parameter description: Shard where the big key is located. This parameter is available only when the instance type is cluster. The format is <i>ip:port</i> . Value range: N/A
db	Integer	Parameter description: Database where a big key is located. Value range: 0-255

Parameter	Type	Description
size	Long	Parameter description: Size of the key value. Value range: N/A
unit	String	Parameter description: Key unit. Value range: • count: number of keys. • byte: key size.

Status code: 400

Table 4-291 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-292 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-293 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-294 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-295 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/bigkey-task/858ee14c-2271-4489-8b82-7bda7459ae3e
```

Example Responses

Status code: 200

Big key analysis details queried successfully.

```
{  
  "id": "858ee14c-2271-4489-8b82-7bda7459ae3e",  
  "instance_id": "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "status": "success",  
  "scan_type": "manual",  
  "created_at": "2020-06-15T02:21:18.669Z",  
  "started_at": "2020-06-15T02:21:23.534Z",  
  "finished_at": "2020-06-15T02:21:25.588Z",  
  "keys": [ {  
    "name": "dcs-bigkey-test",  
    "type": "string",  
    "shard": "192.168.1.134:6379",  
    "db": 0,  
    "size": 3000,  
    "unit": "byte"  
  } ]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code": "DCS.4919",  
  "error_msg": "Does not support bigkey analyze."  
}
```

Status Codes

Status Code	Description
200	Big key analysis details queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.4 Deleting a Big Key Analysis Task

Function

This API is used to delete a big key analysis task.

URI

DELETE /v2/{project_id}/instances/{instance_id}/bigkey-task/{bigkey_id}

Table 4-296 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A
bigkey_id	Yes	String	Definition: ID of the big key analysis task. The ID can be obtained by calling the Listing Big Key Analysis Tasks API. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-297 Response body parameters

Parameter	Type	Description
id	String	Parameter description: ID of the big key analysis task. Value range: N/A
instance_id	String	Parameter description: Instance ID. Value range: N/A
status	String	Parameter description: Status of the big key analysis task. Value range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails.
scan_type	String	Parameter description: Analysis method. Value range: • manual: manual analysis. • auto: automatic analysis.
created_at	String	Parameter description: Time when an analysis task is created. The format is 2020-06-15T02:21:18.669Z . Value range: N/A

Parameter	Type	Description
started_at	String	Parameter description: Time when an analysis task started. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A
finished_at	String	Parameter description: Time when an analysis task ended. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A
num	Integer	Parameter description: Number of big keys. Value range: N/A
keys	Array of BigkeysBody objects	Parameter description: Big key record. (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Table 4-298 BigkeysBody

Parameter	Type	Description
name	String	Parameter description: Key name. Value range: N/A

Parameter	Type	Description
type	String	Definition: Key type. Range: • string: string type. • list: list type. • set: set type. • zset: ordered type. • hash: hash type.
shard	String	Parameter description: Shard where the big key is located. This parameter is available only when the instance type is cluster. The format is <i>ip:port</i> . Value range: N/A
db	Integer	Parameter description: Database where a big key is located. Value range: 0-255
size	Long	Parameter description: Size of the key value. Value range: N/A
unit	String	Parameter description: Key unit. Value range: • count: number of keys. • byte: key size.

Status code: 204

No big key analysis tasks deleted.

Status code: 400

Table 4-299 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-300 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-301 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-302 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-303 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
DELETE https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/bigkey-task/858ee14c-2271-4489-8b82-7bda7459ae3e
```

Example Responses

Status code: 200

Big key analysis task deleted successfully.

```
{  
  "id" : "858ee14c-2271-4489-8b82-7bda7459ae3e",  
  "instance_id" : "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "status" : "success",  
  "scan_type" : "manual",  
  "created_at" : "2020-06-15T02:21:18.669Z",  
  "started_at" : "2020-06-15T02:21:23.534Z",  
  "finished_at" : "2020-06-15T02:21:25.588Z",  
  "keys" : [ {  
    "name" : "dcs-bigkey-test",  
    "type" : "string",  
    "shard" : "192.168.1.134:6379",  
    "db" : 0,  
    "size" : 3000,  
    "unit" : "byte"  
  } ]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4919",  
}
```

```
"error_msg" : "Does not support bigkey analyze."  
}
```

Status Codes

Status Code	Description
200	Big key analysis task deleted successfully.
204	No big key analysis tasks deleted.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.5 Configuring Automatic Big Key Analysis

Function

This API is used to configure automatic big key analysis.

URI

PUT /v2/{project_id}/instances/{instance_id}/bigkey/autoscan

Table 4-304 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A

Request Parameters

Table 4-305 Request body parameters

Parameter	Mandatory	Type	Description
enable_auto_scan	Yes	Boolean	Parameter description: Whether to enable scheduled cache analysis. Constraints: N/A Value range: • true • false Default value: N/A
schedule_at	Yes	Array of strings	Parameter description: UTC time of the day that cache analysis is scheduled for. Example: 21:00 . Constraints: N/A Value range: N/A Default value: N/A

Response Parameters

Status code: 200

Table 4-306 Response body parameters

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
enable_auto_scan	Boolean	Parameter description: Whether to enable scheduled cache analysis. Value range: • true • false
schedule_at	Array of strings	Parameter description: UTC time of the day that analysis is scheduled for. Example: 21:00 . Value range: N/A
updated_at	String	Parameter description: Time when the configuration is updated. The time format is 2020-06-15T02:21:18.669Z . Value range: N/A

Status code: 400

Table 4-307 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-308 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-309 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-310 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-311 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

Scheduling big key analysis tasks to start at 21:00 every day

```
PUT https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/bigkey/autoscan
```

```
{  
  "enable_auto_scan": true,  
  "schedule_at": [ "21:00" ]  
}
```

Example Responses

Status code: 200

Big key analysis task configured successfully.

```
{  
  "instance_id": "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "enable_auto_scan": true,  
  "schedule_at": [ "21:00" ],  
  "updated_at": "2020-06-17T02:42:40.793Z"  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code": "DCS.4919",  
  "error_msg": "Does not support bigkey analyze."  
}
```

Status Codes

Status Code	Description
200	Big key analysis task configured successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.6 Querying the Configurations of Automatic Big Key Analysis

Function

This API is used to query configurations of automatic big key analysis.

URI

GET /v2/{project_id}/instances/{instance_id}/bigkey/autoscan

Table 4-312 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-313 Response body parameters

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
enable_auto_scan	Boolean	Parameter description: Whether to enable scheduled cache analysis. Value range: • true • false
schedule_at	Array of strings	Parameter description: UTC time of the day that analysis is scheduled for. Example: 21:00 . Value range: N/A

Parameter	Type	Description
updated_at	String	Parameter description: Time when the configuration is updated. The time format is 2020-06-15T02:21:18.669Z . Value range: N/A

Status code: 400

Table 4-314 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-315 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-316 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-317 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-318 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/bigkey/autoscan
```

Example Responses

Status code: 200

This API is used to query configurations of automatic big key analysis.

```
{  
  "instance_id" : "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "enable_auto_scan" : true,  
  "schedule_at" : [ "21:00" ],  
  "updated_at" : "2020-06-17T02:42:40.793Z"  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4919",  
  "error_msg" : "Does not support bigkey analyze."  
}
```

Status Codes

Status Code	Description
200	This API is used to query configurations of automatic big key analysis.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.7 Creating a Hot Key Analysis Task

Function

This API is used to create a hot key analysis task. Redis 3.0 does not support hot key analysis.

To perform hot key analysis, the instance's **maxmemory-policy** parameter must be set to **allkeys-lfu** or **volatile-lfu**.

URI

POST /v2/{project_id}/instances/{instance_id}/hotkey-task

Table 4-319 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-320 Response body parameters

Parameter	Type	Description
id	String	Parameter description: ID of the hot key analysis task. Value range: N/A

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
status	String	Parameter description: Status of the hot key analysis task. Value range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails.
scan_type	String	Parameter description: Analysis method. Value range: • manual: manual analysis. • auto: automatic analysis.
created_at	String	Parameter description: Time when an analysis task is created. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
started_at	String	Parameter description: Time when an analysis task started. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A
finished_at	String	Parameter description: Time when an analysis task ended. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Parameter	Type	Description
num	Integer	Parameter description: Number of hot keys. Value range: N/A
keys	Array of HotkeysBody objects	Parameter description: Hot key record. (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Table 4-321 HotkeysBody

Parameter	Type	Description
name	String	Parameter description: Key name. Value range: N/A
type	String	Definition: Key type. Range: • string: string type. • list: list type. • set: set type. • zset: ordered type. • hash: hash type.
shard	String	Parameter description: Shard where the hot key is located. This parameter is supported only when the instance type is cluster. The format is <i>ip:port</i> . Value range: N/A
db	Integer	Parameter description: Database where a hot key is located. Value range: 0-255

Parameter	Type	Description
size	Long	Parameter description: Size of the key value. Value range: N/A
unit	String	Parameter description: Key unit. Value range: count: number of keys. byte: key size.
freq	Integer	Parameter description: Reflects the access frequency of a key within a specific period of time. The value is the logarithmic access frequency counter. The maximum value is 255 , which indicates 1 million access requests. After the frequency reaches 255 , the value will no longer increase even if access requests continue to increase. The value will decrease by 1 for every minute during which the key is not accessed. Value range: N/A

Status code: 400

Table 4-322 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-323 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-324 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-325 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-326 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
POST https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/hotkey-task
```

Example Responses

Status code: 200

Hot key analysis task created successfully.

```
{  
  "id" : "aa735b6f-3d70-44e3-9771-66c6fae7459a",  
  "instance_id" : "5560df16-cebf-4473-95c4-d1b573c16e79",  
  "status" : "waiting",  
  "scan_type" : "manual",  
  "created_at" : "2020-06-15T02:21:18.669Z",  
  "num" : 0  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4922",  
  "error_msg" : "Does not support hotkey analyze."  
}
```

Status Codes

Status Code	Description
200	Hot key analysis task created successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.8 Listing Hot Key Analysis Tasks

Function

This API is used to query the list of hot key analysis tasks.

URI

GET /v2/{project_id}/instances/{instance_id}/hotkey-tasks

Table 4-327 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A

Table 4-328 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0
limit	No	Integer	Parameter description: Number of records displayed on each page. Constraints: N/A Value range: 1-1000 Default value: 10

Parameter	Mandatory	Type	Description
status	No	String	Definition: Status of the expired key scan task. Constraints: N/A Range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails. Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-329 Response body parameters

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
count	Integer	Parameter description: Number of times that hot keys are analyzed. Value range: N/A
records	Array of RecordsResponse objects	Parameter description: List of hot key analysis record. Value range: N/A

Table 4-330 RecordsResponse

Parameter	Type	Description
id	String	Definition: ID of the analysis operation task. Range: N/A
status	String	Parameter description: Status of the hot key analysis task. Value range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails.
scan_type	String	Parameter description: Analysis method. Value range: • manual: manual analysis. • auto: automatic analysis.
created_at	String	Parameter description: Time when an analysis task is created. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
started_at	String	Parameter description: Time when an analysis task started. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
finished_at	String	Parameter description: Time when an analysis task ended. The format is 2020-06-15T02:21:18.669Z . Value range: N/A

Status code: 400

Table 4-331 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-332 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-333 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-334 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-335 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/hotkey-tasks
```

Example Responses

Status code: 200

Hot key analysis tasks listed successfully.

```
{  
  "instance_id" : "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "count" : 1,  
  "records" : [ {  
    "id" : "858ee14c-2271-4489-8b82-7bda7459ae3e",  
    "scan_type" : "manual",  
    "status" : "success",  
    "created_at" : "2020-06-15T02:21:18.669Z",  
    "started_at" : "2020-06-15T02:21:23.534Z",  
    "finished_at" : "2020-06-15T02:21:25.588Z"  
  } ]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4922",  
  "error_msg" : "Does not support hotkey analyze."  
}
```

Status Codes

Status Code	Description
200	Hot key analysis tasks listed successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.9 Querying Hot Key Analysis Details

Function

This API is used to query the hot key analysis details.

URI

GET /v2/{project_id}/instances/{instance_id}/hotkey-task/{hotkey_id}

Table 4-336 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A
hotkey_id	Yes	String	Definition: ID of the hot key analysis task. The ID can be obtained by calling the Listing Hot Key Analysis Tasks API. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-337 Response body parameters

Parameter	Type	Description
id	String	Parameter description: ID of the hot key analysis task. Value range: N/A

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
status	String	Parameter description: Status of the hot key analysis task. Value range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails.
scan_type	String	Parameter description: Analysis method. Value range: • manual: manual analysis. • auto: automatic analysis.
created_at	String	Parameter description: Time when an analysis task is created. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
started_at	String	Parameter description: Time when an analysis task started. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A
finished_at	String	Parameter description: Time when an analysis task ended. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Parameter	Type	Description
num	Integer	Parameter description: Number of hot keys. Value range: N/A
keys	Array of HotkeysBody objects	Parameter description: Hot key record. (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Table 4-338 HotkeysBody

Parameter	Type	Description
name	String	Parameter description: Key name. Value range: N/A
type	String	Definition: Key type. Range: • string: string type. • list: list type. • set: set type. • zset: ordered type. • hash: hash type.
shard	String	Parameter description: Shard where the hot key is located. This parameter is supported only when the instance type is cluster. The format is <i>ip:port</i> . Value range: N/A
db	Integer	Parameter description: Database where a hot key is located. Value range: 0-255

Parameter	Type	Description
size	Long	Parameter description: Size of the key value. Value range: N/A
unit	String	Parameter description: Key unit. Value range: count: number of keys. byte: key size.
freq	Integer	Parameter description: Reflects the access frequency of a key within a specific period of time. The value is the logarithmic access frequency counter. The maximum value is 255 , which indicates 1 million access requests. After the frequency reaches 255 , the value will no longer increase even if access requests continue to increase. The value will decrease by 1 for every minute during which the key is not accessed. Value range: N/A

Status code: 400

Table 4-339 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-340 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-341 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-342 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-343 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/hotkey-task/0ccb25d5-27cf-4188-b5ea-987730a85371
```

Example Responses

Status code: 200

Hot key analysis details queried successfully.

```
{  
  "id" : "858ee14c-2271-4489-8b82-7bda7459ae3e",  
  "instance_id" : "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "status" : "success",  
  "scan_type" : "manual",  
  "created_at" : "2020-06-15T02:21:18.669Z",  
  "started_at" : "2020-06-15T02:21:23.534Z",  
  "finished_at" : "2020-06-15T02:21:25.588Z",  
  "keys" : [{  
    "name" : "dcs-hotkey-test",  
    "type" : "string",  
    "shard" : "192.168.1.134:6379",  
    "db" : 0,  
    "size" : 3000,  
    "unit" : "byte",  
    "freq" : 4  
  }]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4922",  
}
```

```
"error_msg" : "Does not support hotkey analyze."  
}
```

Status Codes

Status Code	Description
200	Hot key analysis details queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.10 Deleting a Hot Key Analysis Task

Function

This API is used to delete a hot key analysis task.

URI

DELETE /v2/{project_id}/instances/{instance_id}/hotkey-task/{hotkey_id}

Table 4-344 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A
hotkey_id	Yes	String	Definition: ID of the hot key analysis task. The ID can be obtained by calling the Listing Hot Key Analysis Tasks API. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-345 Response body parameters

Parameter	Type	Description
id	String	Parameter description: ID of the hot key analysis task. Value range: N/A

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
status	String	Parameter description: Status of the hot key analysis task. Value range: • waiting: The task is to be processed. • running: The task is being processed. • success: The task is successful. • failed: The task fails.
scan_type	String	Parameter description: Analysis method. Value range: • manual: manual analysis. • auto: automatic analysis.
created_at	String	Parameter description: Time when an analysis task is created. The format is 2020-06-15T02:21:18.669Z . Value range: N/A
started_at	String	Parameter description: Time when an analysis task started. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A
finished_at	String	Parameter description: Time when an analysis task ended. The format is 2020-06-15T02:21:18.669Z . (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Parameter	Type	Description
num	Integer	Parameter description: Number of hot keys. Value range: N/A
keys	Array of HotkeysBody objects	Parameter description: Hot key record. (The value is null and is not returned when the analysis task is being created.) Value range: N/A

Table 4-346 HotkeysBody

Parameter	Type	Description
name	String	Parameter description: Key name. Value range: N/A
type	String	Definition: Key type. Range: • string: string type. • list: list type. • set: set type. • zset: ordered type. • hash: hash type.
shard	String	Parameter description: Shard where the hot key is located. This parameter is supported only when the instance type is cluster. The format is <i>ip:port</i> . Value range: N/A
db	Integer	Parameter description: Database where a hot key is located. Value range: 0-255

Parameter	Type	Description
size	Long	Parameter description: Size of the key value. Value range: N/A
unit	String	Parameter description: Key unit. Value range: count: number of keys. byte: key size.
freq	Integer	Parameter description: Reflects the access frequency of a key within a specific period of time. The value is the logarithmic access frequency counter. The maximum value is 255 , which indicates 1 million access requests. After the frequency reaches 255 , the value will no longer increase even if access requests continue to increase. The value will decrease by 1 for every minute during which the key is not accessed. Value range: N/A

Status code: 204

Hot key analysis record not found.

Status code: 400

Table 4-347 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-348 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-349 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-350 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-351 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
DELETE https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/hotkey-task/0ccb25d5-27cf-4188-b5ea-987730a85371
```

Example Responses

Status code: 200

Hot key analysis record deleted.

```
{  
  "id" : "858ee14c-2271-4489-8b82-7bda7459ae3e",  
  "instance_id" : "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "status" : "success",  
  "scan_type" : "manual",  
  "created_at" : "2020-06-15T02:21:18.669Z",  
  "started_at" : "2020-06-15T02:21:23.534Z",  
  "finished_at" : "2020-06-15T02:21:25.588Z",  
  "keys" : [ {  
    "name" : "dcs-hotkey-test",  
    "type" : "string",  
    "shard" : "192.168.1.134:6379",  
    "db" : 0,  
    "size" : 3000,  
    "unit" : "byte",  
    "freq" : 4  
  } ]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4922",  
}
```

```
"error_msg" : "Does not support hotkey analyze."  
}
```

Status Codes

Status Code	Description
200	Hot key analysis record deleted.
204	Hot key analysis record not found.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.11 Configuring Automatic Hot Key Analysis

Function

This API is used to configure automatic hot key analysis.

URI

PUT /v2/{project_id}/instances/{instance_id}/hotkey/autoscan

Table 4-352 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A

Request Parameters

Table 4-353 Request body parameters

Parameter	Mandatory	Type	Description
enable_auto_scan	Yes	Boolean	Parameter description: Whether to enable scheduled cache analysis. Constraints: N/A Value range: • true • false Default value: N/A
schedule_at	Yes	Array of strings	Parameter description: UTC time of the day that cache analysis is scheduled for. Example: 21:00 . Constraints: N/A Value range: N/A Default value: N/A

Response Parameters

Status code: 200

Table 4-354 Response body parameters

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
enable_auto_scan	Boolean	Parameter description: Whether to enable scheduled cache analysis. Value range: • true • false
schedule_at	Array of strings	Parameter description: UTC time of the day that analysis is scheduled for. Example: 21:00 . Value range: N/A
updated_at	String	Parameter description: Time when the configuration is updated. The time format is 2020-06-15T02:21:18.669Z . Value range: N/A

Status code: 400

Table 4-355 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-356 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-357 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-358 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-359 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

Scheduling hot key analysis tasks to start at 21:00 every day

```
PUT https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/hotkey/autoscan
```

```
{  
  "enable_auto_scan": true,  
  "schedule_at": [ "21:00" ]  
}
```

Example Responses

Status code: 200

Automatic hot key analysis configured successfully.

```
{  
  "instance_id": "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "enable_auto_scan": true,  
  "schedule_at": [ "21:00" ],  
  "updated_at": "2020-06-17T02:42:40.793Z"  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code": "DCS.4922",  
  "error_msg": "Does not support hotkey analyze."  
}
```

Status Codes

Status Code	Description
200	Automatic hot key analysis configured successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.7.12 Querying the Configurations of Automatic Hot Key Analysis

Function

This API is used to query configurations of automatic hot key analysis.

URI

GET /v2/{project_id}/instances/{instance_id}/hotkey/autoscan

Table 4-360 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Value range: N/A Default value: N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Value range: N/A Default value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-361 Response body parameters

Parameter	Type	Description
instance_id	String	Parameter description: Instance ID. Value range: N/A
enable_auto_scan	Boolean	Parameter description: Whether to enable scheduled cache analysis. Value range: • true • false
schedule_at	Array of strings	Parameter description: UTC time of the day that analysis is scheduled for. Example: 21:00 . Value range: N/A

Parameter	Type	Description
updated_at	String	Parameter description: Time when the configuration is updated. The time format is 2020-06-15T02:21:18.669Z . Value range: N/A

Status code: 400

Table 4-362 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 401

Table 4-363 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 403

Table 4-364 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 404

Table 4-365 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Status code: 500

Table 4-366 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error information. Value range: N/A
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/hotkey/autoscan
```

Example Responses

Status code: 200

This API is used to query configurations of automatic hot key analysis.

```
{  
  "instance_id" : "5f9057b5-c330-4ee2-8138-7e69896eeec3",  
  "enable_auto_scan" : true,  
  "schedule_at" : [ "21:00" ],  
  "updated_at" : "2020-06-17T02:42:40.793Z"  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4922",  
  "error_msg" : "Does not support hotkey analyze."  
}
```

Status Codes

Status Code	Description
200	This API is used to query configurations of automatic hot key analysis.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.8 Log Management

4.8.1 Querying the Slow Log

Function

This API is used to query slow logs.

URI

GET /v2/{project_id}/instances/{instance_id}/slowlog

Table 4-367 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.
instance_id	Yes	String	Parameter description: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A. Value range: N/A. Default value: N/A.

Table 4-368 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Parameter description: Offset, which is the position where the query starts. Constraints: N/A. Value range: ≥ 0 Default value: 0

Parameter	Mandatory	Type	Description
limit	No	Integer	Parameter description: Number of records displayed on each page. Constraints: N/A. Value range: 1–1,000 Default value: 10
sort_key	No	String	Parameter description: Keyword based on which the returned results are sorted. Constraints: N/A. Value range: • start_time: start time of the slow query log. • duration: duration of the slow query log. Default value: start_time
sort_dir	No	String	Parameter description: Result sorting order. Constraints: N/A. Value range: • desc: descending order • asc: ascending order Default value: desc
start_time	Yes	String	Parameter description: Query start time (UTC). Example: 1598803200000 . Constraints: N/A. Value range: N/A. Default value: N/A.

Parameter	Mandatory	Type	Description
end_time	Yes	String	Parameter description: Query end time (UTC). Example: 1599494399000 . Constraints: N/A. Value range: N/A. Default value: N/A.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-369 Response body parameters

Parameter	Type	Description
total_num	Integer	Parameter description: Total number of slow logs. Value range: N/A.
count	Integer	Parameter description: Total number of slow logs. Value range: N/A.
slowlogs	Array of SlowlogItem objects	Parameter description: Slow log list. Value range: N/A.

Table 4-370 SlowlogItem

Parameter	Type	Description
id	Integer	Parameter description: Unique ID of a slow log. Value range: N/A.
command	String	Parameter description: Slow command. Value range: N/A.
start_time	String	Parameter description: Execution start time. Example: 2020-06-19T07:06:07Z. Value range: N/A.
duration	String	Definition Duration. The unit is μ s. Range N/A
shard_name	String	Parameter description: Name of the shard where the slow command is executed. This parameter is supported only when the instance type is cluster. Value range: N/A.
database_id	Integer	Parameter description: Database ID, which is available only to some customers. Value range: 0-255
username	String	Parameter description: Account name that can operate on slow logs. This parameter is available only to some customers. Value range: N/A.

Parameter	Type	Description
node_role	String	Parameter description: Node type. Value range: N/A
client_ip	String	Parameter description: Client IP address. Value range: N/A

Status code: 400

Table 4-371 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-372 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-373 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-374 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-375 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/slowlog?start_time=1598803200000&end_time=1599494399000
```

Example Responses

Status code: 200

Slow logs queried successfully.

```
{  
  "total_num" : 1,  
  "count" : 1,  
  "slowlogs" : [ {  
    "id" : 1,  
    "start_time" : "2020-06-19T07:06:07Z",  
    "command" : "SLOWLOG GET 128",  
    "duration" : "17",  
    "shard_name" : "group-0",  
    "database_id" : 1,  
    "username" : "default",  
    "node_role" : "master",  
    "client_ip" : "127.0.0.1:6379"  
  } ]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4800",  
  "error_msg" : "Invalid start_time in the request."  
}
```

Status Codes

Status Code	Description
200	Slow logs queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.8.2 Listing Redis Run Logs

Function

This API is used to query the Redis run logs.

URI

GET /v2/{project_id}/instances/{instance_id}/redislog

Table 4-376 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Table 4-377 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0
limit	No	Integer	Definition: Number of records displayed on each page. Constraints: N/A Range: 1–1000 Default Value: 10
log_type	Yes	String	Definition: Type of the return log. Constraints: N/A Range: run: Redis run logs. Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-378 Response body parameters

Parameter	Type	Description
total_num	Integer	Definition: Total number of logs. Range: N/A
file_list	Array of RunlogItem objects	Definition: Run log list.

Table 4-379 RunlogItem

Parameter	Type	Description
id	String	Definition: Unique ID of a run log. Range: N/A
file_name	String	Definition: Run log file name. Range: N/A
group_name	String	Definition: Shard name. Range: N/A
replication_ip	String	Definition: IP address of the replica where the run logs are collected. Range: N/A
status	String	Definition: Run log status. Range: N/A

Parameter	Type	Description
time	String	Definition: Date when run logs are collected. The format is yyyy-MM-dd. Range: N/A
backup_id	String	Definition: Log file ID. Range: N/A

Status code: 204

Queried successfully and no log is found.

Status code: 400

Table 4-380 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-381 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-382 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-383 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-384 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/redislog?  
log_type=run&offset=1&limit=10&replication_id=50fa23b4-74d3-4d5c-98b9-39188a1f2daf
```

Example Responses

Status code: 200

Run logs queried successfully. If there is no log, **204** is returned.

```
{  
  "total_num" : 1,  
  "file_list" : [ {  
    "id" : "e79f2d97-e972-41f2-b51c-d18f65f39a45",  
    "file_name" : "redis_192.168.0.142_2021-04-16.log",  
    "status" : "succeed",  
    "time" : "2021-04-16",  
    "replication_ip" : "192.168.0.142",  
    "group_name" : "group-0",  
    "backup_id" : "e79f2d97-e972-41f2-b51c-d18f65f39a45"  
  } ]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "DCS.4800",  
  "error_msg" : "Invalid logType."  
}
```

Status Codes

Status Code	Description
200	Run logs queried successfully. If there is no log, 204 is returned.
204	Queried successfully and no log is found.
400	Invalid request.
401	Authentication failed.
403	Request rejected.
404	Incorrect path.
500	Internal error.

Error Codes

See [Error Codes](#).

4.8.3 Collecting Redis Run Logs

Function

This API is used to collect Redis run logs.

URI

POST /v2/{project_id}/instances/{instance_id}/redislog

Table 4-385 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Table 4-386 Query Parameters

Parameter	Mandatory	Type	Description
query_time	No	Integer	Date offset, indicating that the query starts from the last <i>n</i> days. The default value is 0 . Value range: 0 , 1 , 3 , and 7 . For example, the value 0 indicates that the logs of the current day are queried, and the value 7 indicates that the logs of the last seven days are queried.
log_type	Yes	String	Log type. Currently, only Redis run logs are supported. The value is run .
replication_id	No	String	Replica ID. You can query the replica ID from Shards and Replicas . This parameter is mandatory when the instance is not single-node.

Request Parameters

None

Response Parameters

Status code: 204

Run logs collected successfully.

Status code: 400

Table 4-387 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-388 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-389 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-390 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-391 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
POST https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-
cebf-4473-95c4-d1b573c16e79/redislog?
log_type=run&query_time=7&replication_id=50fa23b4-74d3-4d5c-98b9-39188a1f2daf
```

Example Responses

Status code: 400

Invalid request.

```
{
  "error_code" : "DCS.4800",
  "error_msg" : "Invalid logType."
}
```

Status Codes

Status Code	Description
204	Run logs collected successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.8.4 Obtaining the Log Download Link

Function

This API is used to obtain the link for downloading logs.

URI

POST /v2/{project_id}/instances/{instance_id}/redislog/{id}/links

Table 4-392 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.
id	Yes	String	Unique ID of a log, which is obtained from the API used to query run logs.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-393 Response body parameters

Parameter	Type	Description
id	String	Log ID.
backup_id	String	Background task ID.
link	String	Log download link. The default validity period is 24 hours.

Status code: 400

Table 4-394 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-395 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.

Parameter	Type	Description
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-396 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-397 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-398 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
POST https://{dcs_endpoint}/v2/0524e839a54847039e9b2b46e8aa788a/instances/5c597ce5-9823-48aa-bf4d-2defb9385b4a/redislog/3ea6ce21-048e-447a-83c3-3fb004b88439/links
```

Example Responses

Status code: 200

Log download link obtained successfully.

```
{
  "id" : "3ea6ce21-048e-447a-83c3-3fb004b88439",
  "backup_id" : "3ea6ce21-048e-447a-83c3-3fb004b88439",
  "link" : "https://bucketxxxxx.{obs_endpoint}:443/xxxxx/redis_192.168.x.x_2021-04-16.log?AWSAccessKeyId=xxxxx"
}
```

Status Codes

Status Code	Description
200	Log download link obtained successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.9 Network Security

4.9.1 Configuring IP Whitelist Groups

Function

This API is used to configure IP address whitelist groups for a specific instance, including creating, disabling, editing, and deleting a whitelist. New whitelist settings will overwrite the existing setting. Therefore, save the existing whitelist before you add a new one.

URI

```
PUT /v2/{project_id}/instance/{instance_id}/whitelist
```

Table 4-399 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

Table 4-400 Request body parameters

Parameter	Mandatory	Type	Description
instance_id	No	String	Definition: Instance ID. Constraints: N/A Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
enable_whitelist	Yes	Boolean	Definition: Whether to enable the whitelist. Constraints: N/A Range: true: Yes false: No Default Value: N/A
whitelist	Yes	Array of Whitelist objects	Definition: IP whitelist group. New whitelist settings will overwrite the existing setting. Therefore, save the existing whitelist before you add a new one. Constraints: N/A

Table 4-401 Whitelist

Parameter	Mandatory	Type	Description
group_name	Yes	String	Definition: Whitelist group name. Constraints: Each instance supports four whitelist groups. The group name must be unique, contain more than four characters, and start with a letter. Only letters, digits, hyphens (-), and underscores (_) are allowed. Range: N/A Default Value: N/A

Parameter	Mandatory	Type	Description
ip_list	Yes	Array of strings	Definition: IP list in a whitelist group. Separate multiple IP addresses or IP address ranges with commas (,). Constraints: An instance's IPs must be unique. IP 0.0.0.0 and CIDR are not supported. Range: N/A Default Value: N/A

Response Parameters

Status code: 204

Definition:

IP whitelist groups configured successfully.

Status code: 400

Table 4-402 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 401

Table 4-403 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 403

Table 4-404 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 404

Table 4-405 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Status code: 500

Table 4-406 Response body parameters

Parameter	Type	Description
error_msg	String	Definition: Error message. Range: N/A
error_code	String	Definition: Error code. Range: For details, see Error Codes .
error_ext_msg	String	Definition: Extended error information. This parameter is not used currently and is set to null . Range: N/A

Example Requests

- Enabling the whitelist and configuring IP addresses allowed to access the instance

PUT https://{dcs_endpoint}/v2/{project_id}/instance/{instance_id}/whitelist

```
{
  "enable_whitelist" : true,
  "whitelist" : [ {
    "group_name" : "test001",
    "ip_list" : [ "10.10.10.1", "10.10.10.2" ]
  } ]
}
```

- Enabling the whitelist and configuring subnet mask allowed to access the instance.

PUT https://{dcs_endpoint}/v2/{project_id}/instance/{instance_id}/whitelist

Example Responses

None

Status Codes

Status Code	Description
204	Definition: IP whitelist groups configured successfully.
400	Definition: Invalid request.
401	Definition: Authentication failed.
403	Definition: Request rejected.
404	Definition: Incorrect path.
500	Definition: Internal error.

Error Codes

See [Error Codes](#).

4.9.2 Querying the IP Whitelist of a DCS Instance

Function

This API is used to query the IP address whitelist of a specific instance.

URI

GET /v2/{project_id}/instance/{instance_id}/whitelist

Table 4-407 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition: Project ID. For details, see Obtaining a Project ID . Constraints: N/A Range: N/A Default Value: N/A
instance_id	Yes	String	Definition: Instance ID. It can be viewed on the instance details page on the DCS console. Constraints: N/A Range: N/A Default Value: N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-408 Response body parameters

Parameter	Type	Description
instance_id	String	Definition: Instance ID. Range: N/A

Parameter	Type	Description
enable_whitelist	Boolean	Definition: Whether the whitelist is enabled. Range: true: Yes false: No
whitelist	Array of WhitelistResp objects	Definition: Current instance IP whitelist.
whitelist_ip_limit_num	String	Definition: Maximum number of IP addresses allowed in the IP whitelist of a tenant instance. Range: N/A

Table 4-409 WhitelistResp

Parameter	Type	Description
group_name	String	Definition: Whitelist group name. Range: N/A
ip_list	Array of strings	Definition: IP list in a whitelist group. Range: N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/instance/{instance_id}/whitelist
```

Example Responses

Status code: 200

Instance whitelist queried successfully.

```
{
  "instance_id" : "5560df16-cebf-4473-95c4-d1b573c16e79",
  "enable_whitelist" : true,
  "whitelist" : [ {
    "group_name" : "test001",
    "ip_list" : [ "10.10.10.1", "10.10.10.2" ]
  } ]
}
```

```
  } ],  
  "whitelist_ip_limit_num" : 20  
}
```

Status Codes

Status Code	Description
200	Instance whitelist queried successfully.

Error Codes

See [Error Codes](#).

4.10 Background Task Management

4.10.1 Listing Background Tasks

Function

This API is used to query background tasks.

URI

GET /v2/{project_id}/instances/{instance_id}/tasks

Table 4-410 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition Project ID. For details, see Obtaining a Project ID . Constraints N/A Range N/A Default Value N/A

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Definition Instance ID. It can be viewed on the instance details page on the DCS console. Constraints N/A Range N/A Default Value N/A

Table 4-411 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints N/A Range ≥ 0 Default Value 0
limit	No	Integer	Definition Number of records displayed on each page. Constraints N/A Range 1–1000 Default Value 10

Parameter	Mandatory	Type	Description
start_time	No	String	Definition Query start time. Constraints The time is in the UTC format. Format: yyyyMMddHHmmss, for example, 20200609160000 . Range N/A Default Value N/A
end_time	No	String	Definition Query end time. Constraints The time is in the UTC format. Format: yyyyMMddHHmmss, for example, 20200609160000 . Range N/A Default Value N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-412 Response body parameters

Parameter	Type	Description
task_count	String	Definition Number of background tasks. Range N/A
tasks	Array of SingleBackgroundTask objects	Definition Task details.

Table 4-413 SingleBackgroundTask

Parameter	Type	Description
id	String	Definition Background task ID. Range N/A
name	String	Definition Background task name. Range • EXTEND: modifying specifications • BindEip: enabling public access • UnBindEip: disabling public access • AddReplica: adding replicas • DelReplica: deleting replicas • AddWhitelist: configuring an IP whitelist • UpdatePort: changing the port • RemoveIpFromDns: removing IP addresses • masterStandbySwapJob: master/standby switchover • modify: changing the password
details	DetailsBody object	Definition Details. Range N/A
user_name	String	Definition Username. Range N/A
user_id	String	Definition User ID. Range N/A

Parameter	Type	Description
params	String	Definition Task parameters. Range N/A
status	String	Definition Task status. Range N/A
created_at	String	Definition Task start time, in the format 2020-06-17T07:38:42.503Z. Range N/A
updated_at	String	Definition Task end time, in the format 2020-06-17T07:38:42.503Z. Range N/A
enable_show	Boolean	Definition Task details that can be expanded. Range N/A

Table 4-414 DetailsBody

Parameter	Type	Description
old_capacity	String	Definition Capacity before the modification. This parameter has a value only when the specifications are modified. Range N/A
new_capacity	String	Definition Capacity after the modification. This parameter has a value only when the specifications are modified. Range N/A

Parameter	Type	Description
enable_public_ip	Boolean	Definition Indicates whether public access has been enabled. Range • true: Yes • false: No
public_ip_id	String	Definition Public IP address ID. Range N/A
public_ip_address	String	Definition Public IP address. Range N/A
enable_ssl	Boolean	Definition Whether SSL is enabled. Range • true: Yes • false: No
old_cache_mode	String	Definition Cache type before the modification. This parameter has a value only when the specifications are modified. Range N/A
new_cache_mode	String	Definition Cache type after the modification. This parameter has a value only when the specifications are modified. Range N/A
old_resource_spec_code	String	Definition Specification parameter before the modification. This parameter has a value only when the specifications are modified. Range N/A

Parameter	Type	Description
new_resource_spec_code	String	Definition Specification parameter after the modification. This parameter has a value only when the specifications are modified. Range N/A
old_replica_num	Integer	Definition Number of replicas before the modification. This parameter has a value only when the specifications are modified. Range N/A
new_replica_num	Integer	Definition Number of replicas after the modification. This parameter has a value only when the specifications are modified. Range N/A
old_cache_type	String	Definition Cache type before the modification. This parameter has a value only when the specifications are modified. Range N/A
new_cache_type	String	Definition Specification type after the modification. This parameter has a value only when the specifications are modified. Range N/A
replica_ip	String	Definition Replica IP address. Range N/A

Parameter	Type	Description
replica_az	String	Definition AZ where the replica is in. Range N/A
group_name	String	Definition Instance shard group name. Range N/A
old_port	Integer	Definition Old port. Range N/A
new_port	Integer	Definition New port. Range N/A
is_only_adjust_charging	Boolean	Definition Indicates whether to only change the billing mode. Range true: Yes false: No. Other changes are made or the billing mode is not changed.
account_name	String	Definition Account name. Range N/A
source_ip	String	Definition Source IP address. Range N/A
target_ip	String	Definition Target IP address. Range N/A

Parameter	Type	Description
node_name	String	Definition Node information. Range N/A
rename_commands	Array of strings	Definition Renamed command.
updated_config_length	Integer	Definition Length of the updated configuration item. Range N/A

Status code: 400

Table 4-415 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 401

Table 4-416 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 403

Table 4-417 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 404

Table 4-418 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 500

Table 4-419 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/tasks?  
offset=0&limit=10&begin_time=20200609160000&end_time=20200617155959
```

Example Responses

Status code: 200

Background tasks listed successfully.

```
{  
  "task_count" : 1,  
  "tasks" : [ {  
    "id" : "8abf6e1e72c12e7c0172c15b508500aa",  
    "name" : "EXTEND",  
    "user_name" : "dcs_000_02",  
    "user_id" : "d53977d1adfb49c5b025ba7d33a13fd7",  
    "details" : {  
      "old_cache_mode" : "single",  
      "new_cache_mode" : "single",  
      "old_capacity" : "0.125",  
      "new_capacity" : "0.25",  
      "old_resource_spec_code" : "redis.single.xu1.tiny.125",  
      "new_resource_spec_code" : "redis.single.xu1.tiny.256",  
      "old_replica_num" : 1,  
      "new_replica_num" : 1,  
      "old_cache_type" : "single",  
      "new_cache_type" : "single",  
      "replica_ip" : "192.192.0.1",  
      "replica_az" : "az01",  
      "group_name" : "group1",  
      "old_port" : 6379,  
      "new_port" : 6379,  
      "is_only_adjust_charging" : false,  
      "account_name" : "account1",  
      "source_ip" : "192.192.0.0",  
      "target_ip" : "192.192.0.1",  
      "node_name" : "node1",  
      "rename_commands" : [ ],  
      "updated_config_length" : 0  
    },  
    "enable_show" : false,  
    "status" : "SUCCESS",  
    "created_at" : "2020-06-17T08:18:06.597Z",  
    "updated_at" : "2020-06-17T08:18:10.106Z"  
  } ]  
}
```

Status Codes

Status Code	Description
200	Background tasks listed successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.

Status Code	Description
500	Internal service error.

Error Codes

See [Error Codes](#).

4.10.2 Deleting a Background Task

Function

Deleting a background task.

URI

DELETE /v2/{project_id}/instances/{instance_id}/tasks/{task_id}

Table 4-420 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition Project ID. For details, see Obtaining a Project ID . Constraints N/A Range N/A Default Value N/A
instance_id	Yes	String	Definition Instance ID. It can be viewed on the instance details page on the DCS console. Constraints N/A Range N/A Default Value N/A

Parameter	Mandatory	Type	Description
task_id	Yes	String	Definition Background task ID. Constraints N/A Range N/A Default Value N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-421 Response body parameters

Parameter	Type	Description
message	String	Definition Returned message. Range N/A

Status code: 204

Background task deleted successfully.

Status code: 400

Table 4-422 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A

Parameter	Type	Description
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 401

Table 4-423 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 403

Table 4-424 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 404

Table 4-425 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 500

Table 4-426 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Example Requests

Deleting a background task.

```
DELETE https://{dcs_endpoint}/v2/a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71/instances/5560df16-  
cebf-4473-95c4-d1b573c16e79/tasks/8abf6e1e72c12e7c0172c15b508500aa
```

Example Responses

Status code: 200

Background task deleted successfully.

```
{  
  "message" : ""  
}
```

Status Codes

Status Code	Description
200	Background task deleted successfully.
204	Background task deleted successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.

Status Code	Description
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.10.3 Querying the Job Execution Result of a Tenant

Function

This API is used to query the task execution result.

URI

GET /v2/{project_id}/jobs/{job_id}

Table 4-427 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition Project ID. For details, see Obtaining a Project ID . Constraints N/A Range N/A Default Value N/A
job_id	Yes	String	Definition Task ID. Constraints N/A Range N/A Default Value N/A

Request Parameters

None

Response Parameters

Status code: 200

Table 4-428 Response body parameters

Parameter	Type	Description
job_id	String	Definition Task ID. Range N/A
job_type	String	Definition Job type. Range • masterStandbySwapJob: switching master and standby nodes • modifyClientIpTransJob: modifying source IP pass-through • modifyBandwidth: modifying bandwidth • createDCSInstance: creating an instance • closeDCSInstance: stopping an instance • deleteDCSInstance: deleting an instance • backupDCSInstance: backing up an instance • restoreDCSInstance: restoring an instance • extendDCSInstance: resizing an instance
status	String	Definition Job status. Range • INIT: To be executed. • RUNNING: Executing. • SUCCESS: Successful. • FAIL: Failed.

Parameter	Type	Description
begin_time	String	Definition Job start timestamp, in ms. The format is 1684191545379. Range N/A
end_time	String	Definition Job start timestamp, in ms. The format is 1684191548248. Range N/A
fail_reason	String	Definition Failure cause. Range N/A

Status code: 400

Table 4-429 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 401

Table 4-430 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 403

Table 4-431 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 404

Table 4-432 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 500

Table 4-433 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/jobs/{job_id}
```

Example Responses

Status code: 200

Details of the background task queried successfully.

```
{
  "job_id" : "ff8080818822bbf70188235afc24141a",
  "job_type" : "masterStandbySwapJob",
  "status" : "SUCCESS",
  "begin_time" : "1684191545379",
  "end_time" : "1684191548248",
  "fail_reason" : null
}
```

Status code: 400

Invalid request.

```
{
  "error_code" : "111400063",
  "error_msg" : "Invalid {0} parameter in the request."
}
```

Status Codes

Status Code	Description
200	Details of the background task queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	Request rejected.
404	The requested resource could not be found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.10.4 Deleting a Task in the Task Center

Function

This API is used to delete a task in the task center.

URI

```
DELETE /v2/{project_id}/tasks/{task_id}
```


Table 4-434 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .
task_id	Yes	String	Background task ID.

Request Parameters

Table 4-435 Request body parameters

Parameter	Mandatory	Type	Description
message	No	String	Deletion result.

Response Parameters

Status code: 200

Background task deleted successfully.

Status code: 400

Table 4-436 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 401

Table 4-437 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 403

Table 4-438 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 404

Table 4-439 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 500

Table 4-440 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Example Requests

```
DELETE https://{dcs_endpoint}/v2/{project_id}/tasks/{task_id}
```

Example Responses

None

Status Codes

Status Code	Description
200	Background task deleted successfully.
400	Invalid request.
401	Invalid authentication information.
403	Request rejected.
404	The requested resource could not be found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.11 Instance Diagnosis

4.11.1 Listing Instance Diagnosis Tasks

Function

This API is used to query the list of diagnosis tasks of a specific DCS instance.

URI

```
GET /v2/{project_id}/instances/{instance_id}/diagnosis
```

Table 4-441 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Definition Project ID. For details, see Obtaining a Project ID . Constraints N/A Range N/A Default Value N/A
instance_id	Yes	String	Definition Instance ID. It can be viewed on the instance details page on the DCS console. Constraints N/A Range N/A Default Value N/A

Table 4-442 Query Parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints N/A Range ≥ 0 Default Value 0

Parameter	Mandatory	Type	Description
limit	No	Integer	Definition Number of records displayed on each page. Constraints N/A Range 1–1000 Default Value 10

Request Parameters

None

Response Parameters

Status code: 200

Table 4-443 Response body parameters

Parameter	Type	Description
diagnosis_report_list	Array of DiagnosisReportInfo objects	Definition Diagnosis report list.
total_num	Integer	Definition Total number of diagnosis reports. Range N/A

Table 4-444 DiagnosisReportInfo

Parameter	Type	Description
report_id	String	Definition Diagnosis report ID. Range N/A

Parameter	Type	Description
status	String	Definition Diagnosis task status. Range • diagnosing • finished
begin_time	String	Definition Start time of a diagnosis period. For example, 2017-03-31T12:24:46.297Z. Range N/A
end_time	String	Definition End time of a diagnosis period. For example, 2017-03-31T12:24:46.297Z. Range N/A
created_at	String	Definition Time when the diagnosis report is created. Range N/A
node_num	Integer	Definition Number of diagnosed nodes. Range N/A
abnormal_item_sum	Integer	Definition Total number of abnormal diagnosis items. Range N/A
failed_item_sum	Integer	Definition Total number of failed diagnosis items. Range N/A

Status code: 400

Table 4-445 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 500

Table 4-446 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Example Requests

None

Example Responses

Status code: 200

Instance diagnosis reports listed successfully.

```
{
  "diagnosis_report_list" : [ {
    "report_id" : "fb98e37a-3cd9-4c7a-96b1-d878266019e2",
    "status" : "finished",
    "begin_time" : "2021-04-15T06:02:00.000Z",
    "end_time" : "2021-04-15T06:12:00.000Z",
    "created_at" : "2021-04-15T06:12:06.641Z",
    "abnormal_item_sum" : 2,
    "failed_item_sum" : 0,
    "node_num" : 2
  } ],
  "total_num" : 1
}
```

Status Codes

Status Code	Description
200	Instance diagnosis reports listed successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.11.2 Querying a Specified Diagnosis Report

Function

This API is used to query details about a diagnosis report based on the report ID.

URI

GET /v2/{project_id}/diagnosis/{report_id}

Table 4-447 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Parameter	Mandatory	Type	Description
report_id	Yes	String	Diagnosis report ID.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-448 Response body parameters

Parameter	Type	Description
abnormal_item_sum	Integer	Total number of abnormal diagnosis items.
failed_item_sum	Integer	Total number of failed diagnosis items.
diagnosis_node_report_list	Array of DiagnosisNodeReport objects	Node diagnosis report list.

Table 4-449 DiagnosisNodeReport

Parameter	Type	Description
node_ip	String	Node IP address, for example, 192.168.0.234:6379.
az_code	String	Code of the AZ where the node is.
group_name	String	Name of the shard where the node is.
abnormal_sum	Integer	Total number of abnormal diagnosis items.
failed_sum	Integer	Total number of failed diagnosis items.
role	String	Node roles: master and slave .
diagnosis_dimension_list	Array of DiagnosisDimension objects	Diagnosis dimension list.
command_time_taken_list	CommandTimeTakenList object	Command execution duration list.

Table 4-450 DiagnosisDimension

Parameter	Type	Description
name	String	Diagnosis dimension name.
abnormal_num	Integer	Total number of abnormal diagnosis items.
failed_num	Integer	Total number of failed diagnosis items.
diagnosis_item_list	Array of DiagnosisItem objects	Diagnosis items.

Table 4-451 DiagnosisItem

Parameter	Type	Description
name	String	Diagnosis item name.
cause_ids	Array of ConclusionItem objects	List of cause IDs. For details about the IDs, see Instance Diagnosis IDs .
impact_ids	Array of ConclusionItem objects	List of impact IDs. For details about the IDs, see Instance Diagnosis IDs .
advice_ids	Array of ConclusionItem objects	List of suggestion IDs. For details about the IDs, see Instance Diagnosis IDs .
result	String	Diagnosis result.

Table 4-452 ConclusionItem

Parameter	Type	Description
id	Integer	Conclusion ID.
params	Map<String,String>	Conclusion parameters.

Table 4-453 CommandTimeTakenList

Parameter	Type	Description
total_num	Integer	Total number of times that commands are executed.

Parameter	Type	Description
total_usec_sum	Double	Total duration of command execution.
result	String	Command execution latency result.
command_list	Array of CommandTimeTaken objects	Command execution latency statistics.

Table 4-454 CommandTimeTaken

Parameter	Type	Description
calls_sum	Integer	Number of calls.
usec_sum	Double	Total time consumed.
command_name	String	Command name.
per_usec	String	Duration percentage.
average_usec	Double	Average duration of calls.

Status code: 400

Table 4-455 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Status code: 500

Table 4-456 Response body parameters

Parameter	Type	Description
error_msg	String	Definition Error information. Range N/A
error_code	String	Definition Error code. Range For details, see Error Codes .
error_ext_msg	String	Definition Extended error information. This parameter is not used currently and is set to null . Range N/A

Example Requests

None

Example Responses

Status code: 200

The specified report is queried successfully.

```
{
  "abnormal_item_sum" : 1,
  "failed_item_sum" : 0,
  "diagnosis_node_report_list" : [ {
    "group_name" : "group-0",
    "az_code" : "region01",
    "node_ip" : "192.168.0.170:6379",
    "abnormal_sum" : 1,
    "failed_sum" : 0,
    "role" : "master",
    "command_time_taken_list" : {
      "command_list" : [ {
        "calls_sum" : 329,
        "usec_sum" : 20.732,
        "command_name" : "info",
        "per_usec" : "68.61%",
        "average_usec" : 0.063
      }, {
        "calls_sum" : 1788,
        "usec_sum" : 1.787,
        "command_name" : "ping",
        "per_usec" : "5.91%",
        "average_usec" : 0.001
      }, {
        "calls_sum" : 2,
```

```
"usec_sum" : 0.025,
"command_name" : "config",
"per_usec" : "0.08%",
"average_usec" : 0.013
}, {
  "calls_sum" : 60,
  "usec_sum" : 0.186,
  "command_name" : "slowlog",
  "per_usec" : "0.62%",
  "average_usec" : 0.003
}, {
  "calls_sum" : 1764,
  "usec_sum" : 7.485,
  "command_name" : "publish",
  "per_usec" : "24.77%",
  "average_usec" : 0.004
} ],
"result" : "succeed",
"error_code" : null,
"total_num" : 5,
"total_usec_sum" : 30.215
},
"diagnosis_dimension_list" : [ {
  "name" : "load",
  "abnormal_num" : 0,
  "failed_num" : 0,
  "diagnosis_item_list" : [ {
    "name" : "cpu_usage",
    "result" : "normal",
    "cause_ids" : null,
    "impact_ids" : null,
    "advice_ids" : null,
    "error_code" : null
  }, {
    "name" : "time_consuming_commands",
    "result" : "normal",
    "cause_ids" : null,
    "impact_ids" : null,
    "advice_ids" : null,
    "error_code" : null
  } ]
}, {
  "name" : "storage",
  "abnormal_num" : 1,
  "failed_num" : 0,
  "diagnosis_item_list" : [ {
    "name" : "inner_memory_fragmentation",
    "result" : "normal",
    "cause_ids" : [ {
      "id" : 7,
      "params" : null
    } ],
    "impact_ids" : [ {
      "id" : 3,
      "params" : null
    } ],
    "advice_ids" : [ {
      "id" : 4,
      "params" : null
    } ],
    "error_code" : null
  }, {
    "name" : "persistence",
    "result" : "normal",
    "cause_ids" : null,
    "impact_ids" : null,
    "advice_ids" : null,
    "error_code" : null
  } ],
  "error_code" : null
}, {
  "name" : "persistence",
  "result" : "normal",
  "cause_ids" : null,
  "impact_ids" : null,
  "advice_ids" : null,
  "error_code" : null
}, {
```

```
{
  "name": "centralized_expiration",
  "result": "normal",
  "cause_ids": null,
  "impact_ids": null,
  "advice_ids": null,
  "error_code": null
}, {
  "name": "memory_usage",
  "result": "normal",
  "cause_ids": null,
  "impact_ids": null,
  "advice_ids": null,
  "error_code": null
}, {
  "name": "hit_ratio",
  "result": "normal",
  "cause_ids": null,
  "impact_ids": null,
  "advice_ids": null,
  "error_code": null
}]
}, {
  "name": "network",
  "abnormal_num": 0,
  "failed_num": 0,
  "diagnosis_item_list": [ {
    "name": "connection_num",
    "result": "normal",
    "cause_ids": null,
    "impact_ids": null,
    "advice_ids": null,
    "error_code": null
  }, {
    "name": "rx_controlled",
    "result": "normal",
    "cause_ids": null,
    "impact_ids": null,
    "advice_ids": null,
    "error_code": null
  }
]
}]
}
```

Status Codes

Status Code	Description
200	The specified report is queried successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.12 Template Management

4.12.1 Viewing Parameter Templates

Function

This API is used to query parameter templates of a tenant, and allows you to specify query criteria.

URI

GET /v2/{project_id}/config-templates

Table 4-457 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Table 4-458 Query Parameters

Parameter	Mandatory	Type	Description
name	No	String	Parameter description: Parameter template name. Fuzzy search is supported. Constraints: N/A. Value range: N/A. Default value: N/A.

Parameter	Mandatory	Type	Description
type	Yes	String	Parameter description: Template type. Constraints: N/A. Value range: • sys: default template • user: custom template Default value: N/A.
engine	No	String	Parameter description: Cache engine. Constraints: N/A. Value range: • Redis • Memcached Default value: N/A.
engine_version	No	String	Definition Cache version. Constraints N/A Range If the cache engine is Redis, the version can be 3.0/4.0/5.0/6.0. If the cache engine is Memcached, this parameter is optional and can be left blank. Default Value N/A

Parameter	Mandatory	Type	Description
cache_mode	No	String	Parameter description: DCS instance type. Constraints: N/A. Value range: • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster Default value: N/A.
offset	No	Integer	Parameter description: Offset, which is the position where the query starts. Constraints: N/A. Value range: ≥ 0 Default value: 0
limit	No	Integer	Parameter description: Number of records displayed on each page. Constraints: N/A. Value range: 1–1,000 Default value: 10

Request Parameters

None

Response Parameters

Status code: 200

Table 4-459 Response body parameters

Parameter	Type	Description
template_num	Integer	Parameter description: Number of templates. Value range: N/A.
templates	Array of ConfigTemplatesListInfo objects	Parameter description: Template details array. Value range: N/A.

Table 4-460 ConfigTemplatesListInfo

Parameter	Type	Description
template_id	String	Parameter description: Template ID. Value range: N/A.
cache_mode	String	Definition DCS instance type. Range • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster
description	String	Parameter description: Template description. Value range: N/A.
engine	String	Definition Cache engine. Range • Redis • Memcached

Parameter	Type	Description
engine_version	String	Definition Cache version. Range If the cache engine is Redis, the version can be 3.0/4.0/5.0/6.0. If the cache engine is Memcached, this parameter is optional and can be left blank.
name	String	Parameter description: Template name. Value range: N/A.
product_type	String	Definition Product type. Range Only the basic edition is supported. Value: generic .
storage_type	String	Parameter description: Storage type. Value range: • DRAM • SSD
type	String	Parameter description: Template type. Value range: • sys: default template • user: custom template
created_at	String	Parameter description: Time when the template is created. This parameter is valid only in custom parameter templates. The format is 2023-05-10T11:09:35.802Z. Value range: N/A.

Status code: 400

Table 4-461 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-462 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-463 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-464 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-465 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/{project_id}/config-templates?  
type=sys&engine=Redis&engine_version=5.0&cache_mode=ha&offset=0&limit=10
```

Example Responses

Status code: 200

Parameter templates listed.

```
{  
  "template_num" : 1,  
  "templates" : [ {  
    "template_id" : "6",  
    "cache_mode" : "single",  
    "description" : null,  
    "engine" : "Redis",  
    "engine_version" : "4.0",  
    "name" : "Default-Redis-4.0-single-generic-DRAM",  
    "product_type" : "generic",  
    "storage_type" : "DRAM",  
    "type" : "sys"  
  } ]  
}
```

Status code: 400

Invalid request.

```
{  
  "error_code" : "111400063",  
  "error_msg" : "Invalid {0} parameter in the request."  
}
```

Status Codes

Status Code	Description
200	Parameter templates listed.
400	Invalid request.
401	Invalid authentication information.
403	Request rejected.
404	The requested resource could not be found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.12.2 Creating a Custom Template

Function

This API is used to create a custom template.

URI

POST /v2/{project_id}/config-templates

Table 4-466 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Request Parameters

Table 4-467 Request body parameters

Parameter	Mandatory	Type	Description
template_id	Yes	String	Default template ID.
name	Yes	String	Template name.

Parameter	Mandatory	Type	Description
type	Yes	String	Template type. Options: • sys: default template • user: custom template
engine	No	String	Cache engine: Redis or Memcached.
cache_mode	No	String	DCS instance type. Value range: • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster
description	No	String	Template description.
engine_version	No	String	Cache version. If the cache engine is Redis, the version can be 3.0/4.0/5.0/6.0. If the cache engine is Memcached, this parameter is optional and can be left blank.
params	Yes	Map<String,String>	Parameter configuration.

Response Parameters

Status code: 200

Table 4-468 Response body parameters

Parameter	Type	Description
id	String	Template ID.

Status code: 400

Table 4-469 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 401

Table 4-470 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 403

Table 4-471 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 404

Table 4-472 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-473 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

Creating a single-node, Redis 5.0 custom template

```
POST https://{dcs_endpoint}/v2/{project_id}/config-templates
```

```
{
  "name" : "Test",
  "cache_mode" : "single",
  "description" : "Test",
  "engine" : "Redis",
  "engine_version" : "5.0",
  "params" : {
    "latency-monitor-threshold" : 15
  },
  "template_id" : "11",
  "type" : "sys"
}
```

Example Responses

Status code: 200

The custom template is created successfully.

```
{
  "id" : "efb1ba06-d3cd-4a77-9173-16f70f2d1343"
}
```

Status code: 400

Invalid request.

```
{
  "error_code" : "111400063",
}
```

```
"error_msg" : "Invalid {0} parameter in the request."  
}
```

Status Codes

Status Code	Description
200	The custom template is created successfully.
400	Invalid request.
401	Invalid authentication information.
403	Request rejected.
404	The requested resource could not be found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.13 Other APIs

4.13.1 Querying Product Flavors

Function

This API is used to query the product flavor (parameter **spec_code**) required for configuring a new DCS instance. If no search criterion is specified, all product specifications will be queried by default.

URI

GET /v2/{project_id}/flavors

Table 4-474 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details, see Obtaining a Project ID .

Table 4-475 Query Parameters

Parameter	Mandatory	Type	Description
spec_code	No	String	Product flavor.
cache_mode	No	String	DCS instance type. Options: • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster
engine	No	String	Cache engine. Options: • Redis • Memcached
engine_version	No	String	Cache engine version. If the cache engine is Redis, the options are as follows: • 4.0 • 5.0 • 6.0 • 7.0
cpu_type	No	String	CPU architecture. The options are as follows: • x86_64: x86 architecture • aarch64: Arm architecture
capacity	No	String	Cache capacity (GB). • For a single-node or master/standby DCS Redis 4.0/5.0/6.0/7.0 instance, the value can be 0.125, 0.25, 0.5, 1, 2, 4, 8, 16, 24, 32, 48, or 64. For a cluster DCS Redis 4.0 or later instance, the value can be 4, 8, 16, 24, 32, 48, 64, 96, 128, 192, 256, 384, 512, 768, or 1024.
spec_type	No	String	Product flavor type: instance : instance flavor node : node flavor

Request Parameters

None

Response Parameters

Status code: 200

Table 4-476 Response body parameters

Parameter	Type	Description
flavors	Array of FlavorsItems objects	Product flavor details.
billing_factor	String	Billing mode. This parameter is an internal parameter of the service and does not need to be concerned.
spec_type	String	Product flavor type: instance : instance flavor node : node flavor

Table 4-477 FlavorsItems

Parameter	Type	Description
spec_code	String	Product flavor.
cloud_service_type_code	String	Code of the cloud service type.
cloud_resource_type_code	String	Code of the cloud resource type.
cache_mode	String	DCS instance type. Options: • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster
engine	String	Cache engine.
engine_version	String	Cache engine version. If the cache engine is Redis, the value can be 4.0 , 5.0 , 7.0 , or 6.0 .
product_type	String	Edition of DCS for Redis. Value: generic : basic edition
cpu_type	String	CPU architecture. The options are as follows: • x86_64: x86 architecture • aarch64: Arm architecture

Parameter	Type	Description
storage_type	String	Storage type. Currently, only the following value is supported: DRAM : in-memory storage
capacity	Array of strings	Cache capacity (GB).
billing_mode	Array of strings	Billing mode. The value can be: • Hourly: pay-per-use
tenant_ip_count	Integer	Number of tenant IP addresses.
pricing_type	String	Pricing type. The options are as follows: • tier: Tiered pricing. One flavor corresponds to multiple capacity options. • normal: One flavor corresponds to one capacity option.
is_dec	Boolean	Whether Dedicated Cloud (DeC) is supported.
dec	Boolean	Whether to support Redis 3.0 Dedicated Cloud (DeC).
attrs	Array of AttrObject objects	Other information about the flavor.
flavors_available_zones	Array of FlavorAzObject objects	AZs where there are available resources.
replica_count	Integer	Replicas.
inquiry_spec_code	String	Product flavor code. This parameter is an internal parameter of the service and does not need to be concerned.
billing_factor	String	Billing mode. This parameter is an internal parameter of the service and does not need to be concerned.

Table 4-478 AttrObject

Parameter	Type	Description
capacity	String	Cache capacity (GB).

Parameter	Type	Description
name	String	Additional information items. The options are as follows: • sharding_num: Number of shards supported by the flavor. • proxy_num: Number of proxies supported by Proxy Cluster instances of the specified flavor. If the instance is not a Proxy Cluster instance, the value of this parameter is 0. • db_number: Number of DBs of the flavor. • max_memory: Maximum available memory. • max_connections: Maximum number of connections supported by the flavor. • max_clients: Maximum number of clients supported by the flavor, which is usually equal to the maximum number of connections. • max_bandwidth: Maximum bandwidth supported by the flavor. • max_in_bandwidth: Maximum inbound bandwidth supported by the flavor, which is usually equal to the maximum bandwidth.
value	String	Additional information value.

Table 4-479 FlavorAzObject

Parameter	Type	Description
capacity	String	Cache capacity (value).
unit	String	Cache capacity (unit).
available_zones	Array of strings	AZ information.
az_codes	Array of strings	AZs where there are available resources.

Status code: 400

Table 4-480 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Status code: 401

Table 4-481 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Status code: 403

Table 4-482 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Status code: 404

Table 4-483 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.

Parameter	Type	Description
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Status code: 500

Table 4-484 Response body parameters

Parameter	Type	Description
error_msg	String	Error message.
error_code	String	Error code.
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null.

Example Requests

```
GET https://{dcs_endpoint}/v2/flavors?
cache_mode={cache_mode}&engine={engine}&engine_version={engine_version}&cpu_type={cpu_type}&capa
city={capacity}&spec_type={spec_type}
```

Example Responses

Status code: 200

Product flavors queried successfully.

```
{
  "flavors": [ {
    "spec_code": "redis.single.au1.large.1",
    "cloud_service_type_code": "hws.resource.type.dcs3",
    "cloud_resource_type_code": "hws.resource.type.dcs3",
    "cache_mode": "single",
    "engine": "redis",
    "engine_version": "4.0;5.0",
    "product_type": "generic",
    "cpu_type": "aarch64",
    "storage_type": "DRAM",
    "capacity": [ "1" ],
    "billing_mode": [ "Hourly" ],
    "tenant_ip_count": 1,
    "pricing_type": "normal",
    "is_dec": false,
    "attrs": [ {
      "capacity": "1",
      "name": "max_memory",
      "value": "1"
    }, {
      "capacity": "1",
      "name": "max_connections",
      "value": "10000"
    }, {
      "capacity": "1",
```

```
{
  "name": "sharding_num",
  "value": "1"
}, {
  "capacity": "1",
  "name": "proxy_num",
  "value": "0"
}, {
  "capacity": "1",
  "name": "db_number",
  "value": "256"
}, {
  "capacity": "1",
  "name": "max_clients",
  "value": "10000"
}, {
  "capacity": "1",
  "name": "max_bandwidth",
  "value": "80"
} ],
"flavors_available_zones": [ {
  "capacity": "1",
  "unit": "GB",
  "available_zones": [ "d539378ec1324c85b76fefa3f7071458" ],
  "az_codes": [ "region01" ]
} ],
"replica_count": 1,
"inquiry_spec_code": "redis.single.au1.large.1",
"billing_factor": "Duration"
} ]
}
```

Status code: 400

Invalid request.

```
{
  "error_code": "DCS.1004",
  "error_msg": "Project ID does not match the token."
}
```

Status code: 401

Invalid authentication information.

```
{
  "error_code": "DCS.1001",
  "error_msg": "Invalid token."
}
```

Status code: 403

The request is rejected.

```
{
  "error_code": "DCS.2003",
  "error_msg": "This role does not have the permission to perform this operation."
}
```

Status code: 404

The requested resource is not found.

```
{
  "error_code": "DCS.4001",
  "error_msg": "The requested URL does not exist."
}
```

Status code: 500

Internal service error.

```
{
  "error_code" : "DCS.5000",
  "error_msg" : "Internal service error."
}
```

Status Codes

Status Code	Description
200	Product flavors queried successfully.
400	Invalid request.
401	Invalid authentication information.
403	The request is rejected.
404	The requested resource is not found.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.13.2 Listing Maintenance Time Windows

Function

This API is used to query the start time and end time of maintenance windows.

URI

GET /v2/instances/maintain-windows

Request Parameters

None

Response Parameters

Status code: 200

Table 4-485 Response body parameters

Parameter	Type	Description
maintain_windows	Array of MaintainWindowsEntity objects	Parameter description: List of supported maintenance time windows. Value range: N/A.

Table 4-486 MaintainWindowsEntity

Parameter	Type	Description
seq	Integer	Parameter description: Sequence number. Value range: N/A.
default	Boolean	Parameter description: Whether a maintenance time window is set to the default time segment. Value range: • true • false
begin	String	Parameter description: UTC time when the maintenance time window starts. The format is HH:mm:ss. Value range: N/A.
end	String	Parameter description: UTC time when the maintenance time window ends. The format is HH:mm:ss. Value range: N/A.

Status code: 500

Table 4-487 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

```
GET https://{dcs_endpoint}/v2/instances/maintain-windows
```

Example Responses

Status code: 200

Maintenance time windows queried successfully.

```
{
  "maintain_windows" : [ {
    "default" : true,
    "end" : "19",
    "begin" : "18",
    "seq" : 1
  }, {
    "default" : false,
    "end" : "20",
    "begin" : "19",
    "seq" : 2
  }, {
    "default" : false,
    "end" : "21",
    "begin" : "20",
    "seq" : 3
  }, {
    "default" : false,
    "end" : "22",
    "begin" : "21",
    "seq" : 4
  }, {
    "default" : false,
    "end" : "23",
    "begin" : "22",
    "seq" : 5
  }
]
```

```
}, {  
  "default" : false,  
  "end" : "00",  
  "begin" : "23",  
  "seq" : 6  
}, {  
  "default" : false,  
  "end" : "01",  
  "begin" : "00",  
  "seq" : 1  
}, {  
  "default" : false,  
  "end" : "02",  
  "begin" : "01",  
  "seq" : 2  
}, {  
  "default" : false,  
  "end" : "03",  
  "begin" : "02",  
  "seq" : 3  
}, {  
  "default" : false,  
  "end" : "04",  
  "begin" : "03",  
  "seq" : 3  
}, {  
  "default" : false,  
  "end" : "05",  
  "begin" : "04",  
  "seq" : 4  
}, {  
  "default" : false,  
  "end" : "06",  
  "begin" : "05",  
  "seq" : 5  
}, {  
  "default" : false,  
  "end" : "07",  
  "begin" : "06",  
  "seq" : 6  
}, {  
  "default" : false,  
  "end" : "08",  
  "begin" : "07",  
  "seq" : 1  
}, {  
  "default" : true,  
  "end" : "09",  
  "begin" : "08",  
  "seq" : 2  
}, {  
  "default" : false,  
  "end" : "10",  
  "begin" : "09",  
  "seq" : 3  
}, {  
  "default" : false,  
  "end" : "11",  
  "begin" : "10",  
  "seq" : 4  
}, {  
  "default" : false,  
  "end" : "12",  
  "begin" : "11",  
  "seq" : 5  
}, {  
  "default" : false,  
  "end" : "13",  
  "begin" : "12",
```



```
"seq" : 6
}, {
  "default" : false,
  "end" : "14",
  "begin" : "13",
  "seq" : 1
}, {
  "default" : true,
  "end" : "15",
  "begin" : "14",
  "seq" : 2
}, {
  "default" : false,
  "end" : "16",
  "begin" : "15",
  "seq" : 3
}, {
  "default" : false,
  "end" : "17",
  "begin" : "16",
  "seq" : 4
}, {
  "default" : false,
  "end" : "18",
  "begin" : "17",
  "seq" : 5
} ]
}
```

Status Codes

Status Code	Description
200	Maintenance time windows queried successfully.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.13.3 Querying the Tenant Quotas

Function

This API is used to query the default instance quota and total memory quota of a tenant and the maximum and minimum quotas a tenant can apply for. Different tenants have different quotas in different regions.

URI

GET /v2/{project_id}/quota

Table 4-488 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-489 Response body parameters

Parameter	Type	Description
quotas	quotas object	Parameter description: Quota information. Value range: N/A.

Table 4-490 quotas

Parameter	Type	Description
resources	Array of Resources objects	Parameter description: Quota list. Value range: N/A.

Table 4-491 Resources

Parameter	Type	Description
unit	String	Parameter description: Resource unit. - When type is set to instance, no value is returned. - When type is set to ram, GB is returned. Value range: N/A.
min	Integer	Parameter description: - Minimum limit of instance quota when type is set to instance. - Minimum limit of memory quota when type is set to ram. Value range: N/A.
max	Integer	Parameter description: - Maximum limit of instance quota when type is set to instance. - Maximum limit of memory quota when type is set to ram. Value range: N/A.
quota	Integer	Parameter description: Maximum number of instances that can be created and maximum allowed total memory. Value range: N/A.
used	Integer	Parameter description: Number of created instances and used memory. Value range: N/A.
type	String	Parameter description: Quota type. Value range: instances: instance quota ram: memory quota

Status code: 400

Table 4-492 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Status code: 500

Table 4-493 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .

Parameter	Type	Description
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

GET https://{dcs_endpoint}/v2/{project_id}/quota

Example Responses

Status code: 200

Tenant quota queried successfully.

```
{
  "quotas": {
    "resources": [ {
      "unit": { },
      "min": 1,
      "max": 10,
      "quota": 10,
      "used": 3,
      "type": "instance"
    }, {
      "unit": "GB",
      "min": 1,
      "max": 800,
      "quota": 800,
      "used": 22,
      "type": "ram"
    } ]
  }
}
```

Status Codes

Status Code	Description
200	Tenant quota queried successfully.
400	Invalid request.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.13.4 Listing Monitored Objects on Secondary Dimensions Under a Primary Dimension

Function

This API is used to query the monitored objects on secondary dimensions under primary dimension **dc_instance_id**.

URI

GET /v2/{project_id}/dims/monitored-objects/{instance_id}

Table 4-494 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.
instance_id	Yes	String	Parameter description: ID of the monitored object on the primary dimension, which is the instance ID. Constraints: N/A. Value range: N/A. Default value: N/A.

Table 4-495 Query Parameters

Parameter	Mandatory	Type	Description
dim_name	Yes	String	Parameter description: ID of the primary dimension, which can be dc_instance_id . Constraints: N/A. Value range: N/A. Default value: N/A.

Request Parameters

None

Response Parameters

Status code: 200

Table 4-496 Response body parameters

Parameter	Type	Description
router	Array of strings	Parameter description: Route of the specified dimension. If the dimension is the primary dimension, the array contains its ID. Value range: N/A.
children	Array of DimChild objects	Parameter description: Secondary dimensions under the specified dimension. This parameter is valid only when the dimension is dc_instance_id . Value range: - The secondary dimension of a Proxy Cluster instance can be dc_cluster_redis_node or dc_cluster_proxy_node. - The secondary dimension of a Redis Cluster instance can be dc_cluster_proxy_node.

Parameter	Type	Description
instances	Array of InstancesMonitoredObject objects	Parameter description: Monitored objects of the specified dimension. Value range: N/A.
dcs_cluster_redis_node	Array of ClusterRedisNodeMonitoredObject objects	Parameter description: Monitored objects of the Redis Server. This parameter is valid for Proxy Cluster and Redis Cluster instances. The field name is the same as the secondary dimension object name under children. Value range: N/A.
dcs_cluster_proxy_node	Array of ProxyNodeMonitoredObject objects	Definition Monitored objects of the Proxy. This parameter is valid only for Proxy Cluster DCS Redis 3.0 instances. The field name is the same as the secondary dimension object name under children. Range N/A
dcs_cluster_proxy2_node	Array of Proxy2NodeMonitoredObject objects	Parameter description: Monitored objects of the Proxy. This parameter is valid only for Proxy Cluster DCS Redis 4.0 and 5.0 instances. The field name is the same as the secondary dimension object name under children. Value range: N/A.
total	Integer	Parameter description: Total number of monitored objects on the primary dimension. Value range: N/A.

Table 4-497 DimChild

Parameter	Type	Description
dim_name	String	Definition Dimension name. Range • dc_instance_id: Redis instance • dc_cluster_redis_node: data node • dc_cluster_proxy_node/ dc_cluster_proxy2_node: proxy node • dc_memcached_instance_id
dim_route	String	Parameter description: Dimension route. Format: <i>Primary dimension name,Secondary dimension name</i> . For example, if dim_name is dc_cluster_redis_node , the value of this field is dc_instance_id,dc_cluster_redis_node . Value range: N/A.

Table 4-498 InstancesMonitoredObject

Parameter	Type	Description
dc_instance_id	String	Parameter description: ID of the monitored object, which is the instance ID. Value range: N/A.
name	String	Parameter description: Name of the monitored object, which is the instance name. Value range: N/A.

Parameter	Type	Description
status	String	Parameter description: Status of the monitored object, which is the instance status. Value range: N/A.

Table 4-499 ClusterRedisNodeMonitoredObject

Parameter	Type	Description
dcs_instance_id	String	Parameter description: ID of the monitored object, which is the node ID. Value range: N/A.
name	String	Parameter description: Name of the monitored object, which is the node IP address. Value range: N/A.
dcs_cluster_redis_node	String	Parameter description: ID of the monitored object on the dcs_cluster_redis_node dimension. Value range: N/A.
status	String	Parameter description: Status of the monitored object, which is the node status. Value range: N/A.

Table 4-500 ProxyNodeMonitoredObject

Parameter	Type	Description
dc_instance_id	String	Parameter description: ID of the monitored object, which is the node ID. Value range: N/A.
name	String	Parameter description: Name of the monitored object, which is the node IP address. Value range: N/A.
dc_cluster_proxy_node	String	Parameter description: ID of the monitored object on the dc_cluster_proxy_node dimension. Value range: N/A.
status	String	Parameter description: Status of the monitored object, which is the node status. Value range: N/A.

Table 4-501 Proxy2NodeMonitoredObject

Parameter	Type	Description
dc_instance_id	String	Parameter description: ID of the monitored object, which is the node ID. Value range: N/A.
name	String	Parameter description: Name of the monitored object, which is the node IP address. Value range: N/A.

Parameter	Type	Description
dcsc_cluster_proxy2_node	String	Parameter description: ID of the monitored object on the dcsc_cluster_proxy2_node dimension. Value range: N/A.
status	String	Parameter description: Status of the monitored object, which is the node status. Value range: N/A.

Status code: 500

Table 4-502 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

GET https://{dcs_endpoint}/v2/{project_id}/dims/monitored-objects/{instance_id}?dim_name={dim_name}

Example Responses

Status code: 200

Successfully queried the monitored objects on the primary dimension.

```
{
  "router" : [ "dcs_instance_id" ],
  "total" : 1,
  "children" : [ {
    "dim_name" : "dcs_cluster_redis_node",
    "dim_route" : "dcs_instance_id,dcs_cluster_redis_node"
  } ],
  "instances" : [ {
    "name" : "dcs-test001",
    "status" : "RUNNING",
    "dcs_instance_id" : "03ca9da0-1104-40a5-b49d-5ef8e41bfd19"
  } ],
  "dcs_cluster_redis_node" : [ {
    "name" : "(master)192.168.2.145",
    "status" : "RUNNING",
    "dcs_instance_id" : "03ca9da0-1104-40a5-b49d-5ef8e41bfd19",
    "dcs_cluster_redis_node" : "b1f4aa9e4dae50888e58c9caecdfc108"
  }, {
    "name" : "(replica)192.168.2.199",
    "status" : "RUNNING",
    "dcs_instance_id" : "03ca9da0-1104-40a5-b49d-5ef8e41bfd19",
    "dcs_cluster_redis_node" : "e0e10e489a73487147928167396474bc"
  }, {
    "name" : "(master)192.168.2.243",
    "status" : "RUNNING",
    "dcs_instance_id" : "03ca9da0-1104-40a5-b49d-5ef8e41bfd19",
    "dcs_cluster_redis_node" : "e797c3ba8bee782e25cdd4a90eb00517"
  }, {
    "name" : "(replica)192.168.2.164",
    "status" : "RUNNING",
    "dcs_instance_id" : "03ca9da0-1104-40a5-b49d-5ef8e41bfd19",
    "dcs_cluster_redis_node" : "d810fb44f9f7a359e000cf277a824c43"
  }, {
    "name" : "(master)192.168.2.95",
    "status" : "RUNNING",
    "dcs_instance_id" : "03ca9da0-1104-40a5-b49d-5ef8e41bfd19",
    "dcs_cluster_redis_node" : "f25c37a4654d50b07e629fc2adfbfa60f"
  }, {
    "name" : "(replica)192.168.2.51",
    "status" : "RUNNING",
    "dcs_instance_id" : "03ca9da0-1104-40a5-b49d-5ef8e41bfd19",
    "dcs_cluster_redis_node" : "da5149a20dc7caf35587e4d2433fe452"
  } ]
}
```

Status Codes

Status Code	Description
200	Successfully queried the monitored objects on the primary dimension.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.13.5 Listing Monitored Objects on Primary Dimensions

Function

This API is used to query the monitored objects on the primary dimension **dc_instance_id** or **dc_memcached_instance_id**.

URI

GET /v2/{project_id}/dims/monitored-objects

Table 4-503 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Parameter description: Project ID. For details, see Obtaining a Project ID . Constraints: N/A. Value range: N/A. Default value: N/A.

Table 4-504 Query Parameters

Parameter	Mandatory	Type	Description
dim_name	Yes	String	Parameter description: Primary dimension ID. Constraints: N/A. Value range: It can be dc_instance_id or dc_memcached_instance_id . Default value: N/A.

Parameter	Mandatory	Type	Description
offset	No	Integer	Definition: Offset, which indicates that the generated list is displayed from this offset. For example, if the offset is 3, the generated list is displayed from the fourth record. Constraints: N/A Range: ≥ 0 Default Value: 0
limit	No	Integer	Parameter description: Number of records displayed on each page. Constraints: N/A. Value range: 1–1,000 Default value: 10

Request Parameters

None

Response Parameters

Status code: 200

Table 4-505 Response body parameters

Parameter	Type	Description
router	Array of strings	Parameter description: Route of the specified dimension. If the dimension is the primary dimension, the array contains its ID. Value range: N/A.

Parameter	Type	Description
children	Array of DimChild objects	Parameter description: Secondary dimensions under the specified dimension. This parameter is valid only when the dimension is dc_instance_id. Value range: - The secondary dimension of a Proxy Cluster instance can be dc_cluster_redis_node or dc_cluster_proxy_node. - The secondary dimension of a Redis Cluster instance can be dc_cluster_proxy_node.
instances	Array of InstancesMonitoredObject objects	Parameter description: Monitored objects of the specified dimension. Value range: N/A.
total	Integer	Parameter description: Total number of monitored objects on the primary dimension. Value range: N/A.

Table 4-506 DimChild

Parameter	Type	Description
dim_name	String	Definition Dimension name. Range dc_instance_id: Redis instance dc_cluster_redis_node: data node dc_cluster_proxy_node/ dc_cluster_proxy2_node: proxy node dc_memcached_instance_id

Parameter	Type	Description
dim_route	String	Parameter description: Dimension route. Format: <i>Primary dimension name,Secondary dimension name</i> . For example, if dim_name is dcsc_cluster_redis_node , the value of this field is dcsc_instance_id,dcsc_cluster_redis_node . Value range: N/A.

Table 4-507 InstancesMonitoredObject

Parameter	Type	Description
dcsc_instance_id	String	Parameter description: ID of the monitored object, which is the instance ID. Value range: N/A.
name	String	Parameter description: Name of the monitored object, which is the instance name. Value range: N/A.
status	String	Parameter description: Status of the monitored object, which is the instance status. Value range: N/A.

Status code: 500

Table 4-508 Response body parameters

Parameter	Type	Description
error_msg	String	Parameter description: Error message. Value range: N/A.
error_code	String	Parameter description: Error code. Value range: For details, see Error Codes .
error_ext_msg	String	Parameter description: Extended error information. This parameter is not used currently and is set to null . Value range: N/A.

Example Requests

GET https://{dcs_endpoint}}/v2/{project_id}/dims/monitored-objects?dim_name={dim_name}

Example Responses

Status code: 200

Successfully listed the monitored objects on the primary dimension.

```
{
  "router": [ "dcs_instance_id" ],
  "total": 3,
  "children": [ {
    "dim_name": "dcs_cluster_redis_node",
    "dim_route": "dcs_instance_id,dcs_cluster_redis_node"
  }, {
    "dim_name": "dcs_cluster_proxy_node",
    "dim_route": "dcs_instance_id,dcs_cluster_proxy_node"
  } ],
  "instances": [ {
    "name": "dcs-redis-single-node",
    "status": "RUNNING",
    "dcs_instance_id": "fe909c47-8990-44a0-9154-d0a1e95e78fe"
  }, {
    "name": "dcs-redis-master-standby",
    "status": "RUNNING",
    "dcs_instance_id": "877e5ae3-482e-4c38-88a0-030a0fa6f399"
  }, {
    "name": "dcs-proxy-cluster",
    "status": "RUNNING",
    "dcs_instance_id": "448ee851-1366-47f2-913a-e21032e690c4"
  } ]
}
```

Status Codes

Status Code	Description
200	Successfully listed the monitored objects on the primary dimension.
500	Internal service error.

Error Codes

See [Error Codes](#).

4.13.6 Querying AZs

Function

This API is used to query the AZ information of the current region.

URI

GET /v2/available-zones

Request Parameters

None

Response Parameters

Status code: 200

Table 4-509 Response body parameters

Parameter	Type	Description
region_id	String	Parameter description: Region ID. Value range: N/A.
available_zones	Array of AvailableZones objects	Parameter description: Array of AZs. Value range: N/A.

Table 4-510 AvailableZones

Parameter	Type	Description
code	String	Parameter description: AZ code. Value range: N/A.
port	String	Parameter description: AZ port. Value range: N/A.
name	String	Parameter description: AZ name Value range: N/A.
id	String	Parameter description: AZ ID. Value range: N/A.
resource_availability	String	Parameter description: Whether the AZ has available resources. Value range: • true: There are available resources in the AZ. • false: No resource is available.

Example Requests

GET https://{dcs_endpoint}/v2/available-zones

Example Responses

Status code: 200

The query is successful.

```
{
  "region_id" : "region00",
  "available_zones" : [ {
    "code" : "region01",
    "port" : "8403",
    "name" : "AZ 1.",
    "id" : "effdcbc7d4d64a02aa1fa26b42f56533",
    "resource_availability" : "true"
  }, {
    "code" : "region02",
```

```
"port" : "8404",
"name" : "AZ 2.",
"id" : "a0865121f83b41cbafce65930a22a6e8",
"resource_availability" : "true"
}, {
"code" : "region03",
"port" : "8408",
"name" : "AZ 3.",
"id" : "2dc154ac2724a6d92e9bcc859657c1e",
"resource_availability" : "true"
}]
}
```

Status Codes

Status Code	Description
200	The query is successful.

Error Codes

See [Error Codes](#).

5 Outdated APIs (V1)

5.1 Lifecycle Management APIs

5.1.1 Creating a DCS Instance

Function

This API is used to create a DCS instance.

URI

POST /v1.0/{project_id}/instances

[Table 5-1](#) describes the parameter.

Table 5-1 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .

Request

Request parameters

[Table 5-2](#) describes the request parameters.

Table 5-2 Parameter description

Parameter	Type	Mandatory	Description
name	String	Yes	DCS instance name. An instance name can contain 4 to 64 characters and must start with a letter. Only letters, digits, underscores (_), and hyphens (-) are allowed.
description	String	No	Brief description of the DCS instance. The description supports up to 1024 characters. NOTE The backslash (\) and quotation mark (") are special characters for JSON messages. When using these characters in a parameter value, add the escape character (\) before the characters, for example, \\ and \".
engine	String	Yes	Cache engine. Value: Redis .
engine_version	String	Yes	Cache engine version. If the cache engine is Redis, the value can be 4.0 , 5.0 , 7.0 , or 6.0 .
spec_code	String	Yes	DCS instance specification code. To obtain the value, go to the instance creation page on the DCS console, and view Flavor Name in the Instance Specification table.
capacity	Float	Yes	Cache capacity. Unit: GB. - For a single-node or master/standby DCS Redis 3.0 instance, the value can be 2, 4, 8, 16, 32, or 64. For a Proxy Cluster DCS Redis 3.0 instance, the value can be 64, 128, 256, 512, or 1024. - For a single-node or master/standby DCS Redis 4.0 or later instance, the value can be 0.125, 0.25, 0.5, 1, 2, 4, 8, 16, 32, 24, 48, or 64. For a cluster DCS Redis instance, the value can be 4, 8, 16, 24, 32, 48, 64, 96, 128, 192, 256, 384, 512, 768, or 1024. - For a single-node or master/standby DCS Memcached instance, the value can be 2, 4, 8, 16, 32, or 64.
no_password_access	String	Yes	An indicator of whether a DCS instance can be accessed in password-free mode. true: indicates that a DCS instance can be accessed without a password. false: indicates that a DCS instance can be accessed only after password authentication. Default value: false .

Parameter	Type	Mandatory	Description
password	String	No	Password of a DCS instance. NOTE If no_password_access is set to false or not set, the request must contain the password parameter. The password of a DCS Redis instance must meet the following complexity requirements: • Must be a string consisting of 8 to 64 characters. • Must be different from the old password. • Contains at least three of the following character types: – Lowercase letters – Uppercase letters – Digits – Special characters (~!@#\$%^&*()-_+=+ {}<.>/?)
access_username	String	No	If the cache engine is Redis, you do not need to set this parameter. If the cache engine is Memcached, this parameter is available only when no_password_access is set to false, indicating that you need to access the DCS instance in password mode. A username can contain 1 to 64 characters, including letters, digits, underscores (_), and hyphens (-), and must start with a letter. NOTE • This parameter is optional when the cache engine is Memcached. • If the cache engine is Redis, you do not need to set this parameter.
vpc_id	String	Yes	VPC ID. Obtain the value by using either of the following methods: • Method 1: Log in to VPC console and view the VPC ID in the VPC details. • Method 2: Call the API for querying VPCs. For details, see the "Querying VPCs" section in the <i>Virtual Private Cloud API Reference</i>.

Parameter	Type	Mandatory	Description
security_group_id	String	Yes	ID of the security group which the instance belongs to. This parameter is mandatory when the engine is Redis and engine_version is 3.0, or when engine is Memcached. DCS Redis 3.0 and Memcached instances support access control by security groups. Redis 4.0 and later instances do not support access control by security groups. Obtain the value by using either of the following methods: - Method 1: Log in to the VPC console and view the security group ID on the security group details page. - Method 2: Call the API for querying security groups. For details, see the "Querying Security Groups" section in the <i>Virtual Private Cloud API Reference</i>.
subnet_id	String	Yes	Network ID of the subnet. Obtain the value by using either of the following methods: - Method 1: Log in to VPC console and click the target subnet on the Subnets tab page. You can view the network ID on the displayed page. - Method 2: Call the API for querying subnets. For details, see the "Querying Subnets" section in the <i>Virtual Private Cloud API Reference</i>.
available_zones	Array	Yes	ID of the AZ where the cache node resides and which has available resources. For details on how to obtain the value, see Querying AZ Information. Check whether the AZ has available resources. Master/Standby, Proxy Cluster, and Redis Cluster DCS instances support cross-AZ deployment. You can specify an AZ for the standby node. When specifying AZs for nodes, use commas (,) to separate multiple AZs. For details, see the example request.
instance_backup_policy	Object	No	Backup policy. This parameter is available for master/standby and cluster DCS instances. For details, see Table 5-4 and Table 5-5.

Parameter	Type	Mandatory	Description
maintain_begin	String	No	Time at which the maintenance time window starts. Format: hh:mm:ss. - The start time and end time of the maintenance time window must indicate the time segment of a supported maintenance time window. For details on how to query the time segments of supported maintenance time windows, see Querying Maintenance Time Window. - The start time must be set to 22:00:00, 02:00:00, 06:00:00, 10:00:00, 14:00:00, or 18:00:00. - Parameters maintain_begin and maintain_end must be set in pairs. If parameter maintain_start is left blank, parameter maintain_end is also blank. In this case, the system automatically set the start time to 02:00:00.
maintain_end	String	No	Time at which the maintenance time window ends. Format: hh:mm:ss. - The start time and end time of the maintenance time window must indicate the time segment of a supported maintenance time window. For details on how to query the time segments of supported maintenance time windows, see Querying Maintenance Time Window. - The end time is four hours later than the start time. For example, if the start time is 22:00:00, the end time is 02:00:00. - Parameters maintain_begin and maintain_end must be set in pairs. If parameter maintain_end is left blank, parameter maintain_start is also blank. In this case, the system automatically set the end time to 06:00:00.
tags	Array of Objects	No	Instance tag key and value. For details, see Table 5-3.

Parameter	Type	Mandatory	Description
port	Integer	No	Port customization , which is supported only by Redis 4.0 and later instances and not by Redis 3.0 and Memcached instances. If this parameter is not sent or is left empty when you create a Redis instance, the default port 6379 will be used. To customize a port, specify a port number in the range from 1 to 65535.
rename_commands	Object	No	Critical command renaming , which is supported only by Redis 4.0 and later instances. If this parameter is not sent or is left empty when you create a Redis instance, no critical command will be renamed. Currently, you can rename the COMMAND , KEYS , FLUSHDB , FLUSHALL , HGETALL , SCAN , HSCAN , SSCAN , and ZSCAN commands.

Table 5-3 tags parameter description

Parameter	Mandatory	Type	Description
key	No	String	Tag key, which • Cannot be left blank. • Must be unique. • Can contain a maximum of 36 characters.
value	No	String	Tag value, which • Is mandatory when action is set to create and optional when action is set to delete. • Can contain a maximum of 43 characters.

Table 5-4 instance_backup_policy parameter description

Parameter	Type	Mandatory	Description
save_days	Integer	No	This parameter is mandatory when backup_type is set to manual . Retention period. Unit: day. Value range: 1–7.
backup_type	String	No	Backup type. Options: • auto: automatic backup. • manual: manual backup. The default value is manual .
periodical_backup_plan	Object	Yes	Backup plan. For details, see Table 5-5 .

Table 5-5 periodical_backup_plan parameter description

Parameter	Type	Mandatory	Description
begin_at	String	Yes	Time at which backup starts. "00:00-01:00" indicates that backup starts at 00:00:00.
period_type	String	Yes	Interval at which backup is performed. Currently, only weekly backup is supported.
backup_at	Array	Yes	Day in a week on which backup starts. Value range: 1–7, where 1 indicates Monday and 7 indicates Sunday.
timezone_offset	String	No	Time zone in which backup is performed. Value range: GMT–12:00 to GMT+12:00. If this parameter is left blank, the current time zone of the DCS-Server VM is used by default.

Example request

- Request URL:
POST https://{dcs_endpoint}/v1.0/{project_id}/instances

- Example:

```
{
  "name": "dcs-a11e",
  "description": "Create an instance",
  "engine": "Redis",
  "engine_version": "3.0",
  "capacity": 2,
  "spec_code": "XXXXXX",
  "password": "XXXXXX",
  "vpc_id": "27d99e17-42f2-4751-818f-5c8c6c03ff15",
  "security_group_id": "1477393a-29c9-4de5-843f-18ef51257c7e",
  "subnet_id": "ec2f34b9-20eb-4872-85bd-bea9fc943128",
  "available_zones":
["ae04cf9d61544df3806a3feeb401b204","d573142f24894ef3bd3664de068b44b0"],
  "product_id": "XXXXXX",
  "instance_backup_policy": {
    "save_days": 1,
    "backup_type": "auto",
    "periodical_backup_plan": {
      "begin_at": "00:00-01:00",
      "period_type": "weekly",
      "backup_at": [
        1,
        2,
        3,
        4,
        5,
        6,
        7
      ]
    }
  },
  "maintain_begin": "22:00:00",
  "maintain_end": "02:00:00"
}
```

- Example:

Creating a pay-per-use, master/standby DCS Redis instance with tags, a customized port, renamed commands, and cross-AZ deployment

```
{
  "name": "dcs-demo",
  "engine": "Redis",
  "engine_version": "4.0",
  "capacity": 2,
  "spec_code": "redis.ha.au1.large.**",
  "no_password_access": true,
  "vpc_id": "c5cd009b-9ba9-41f2-9a26-2b8c3f3ffd39",
  "subnet_id": "7e95c4d6-d7af-424c-a3cf-2be10968fe81",
  "product_id": "redis.ha.au1.large.**-h",
  "available_zones": ["ae04cf9d61544df3806a3feeb401b204",
"d573142f24894ef3bd3664de068b44b0"],
  "security_group_id": "d57fad27-e3e9-43b7-9498-0a698ab63b27",
  "port": "4040",
  "rename_commands":
  {
    "keys":"keys001",
    "flushdb":"flushdb001",
    "flushall":"flushall001"
  },
  "tags": [{
    "key": "dcs001",
    "value": "002"
  },
  {
    "key": "dcs003",
    "value": "004"
  }
]
```

- Example:

Creating a master/standby DCS Memcached instance with backup policies

```
{
  "name": "dcs-a11b",
  "description": "Create an instance",
  "engine": "Memcached",
  "engine_version": "",
  "capacity": 2,
  "password": "XXXXXX",
  "vpc_id": "27d99e17-42f2-4751-818f-5c8c6c03ff16",
  "security_group_id": "1477393a-29c9-4de5-843f-18ef51257c8e",
  "subnet_id": "ec2f34b9-20eb-4872-85bd-bea9fc943129",
  "available_zones": [
    "1d7b939b382c4c3bb3481a8ca10da769"
  ],
  "product_id": "XXXXXX",
  "instance_backup_policy": {
    "save_days": 1,
    "backup_type": "auto",
    "periodical_backup_plan": {
      "begin_at": "00:00-01:00",
      "period_type": "weekly",
      "backup_at": [
        1,
        2,
        3,
        4,
        5,
        6,
        7
      ]
    }
  },
  "maintain_begin": "22:00:00",
  "maintain_end": "02:00:00",
  "no_password_access": "false",
  "access_user": "",
  "timezone_offset": ""
}
```

Response

Response parameters

[Table 5-6](#) describes the response parameters.

Table 5-6 Parameter description

Parameter	Type	Description
instance_id	String	DCS instance ID.
instances	Array of Objects	DCS instance list. For details, see Table 5-7 .

Table 5-7 instances parameters

Parameter	Type	Description
instance_id	String	DCS instance ID.

Parameter	Type	Description
instance_name	String	DCS instance name.

Example response

```
{
  "instances": [
    {
      "instance_id": "3c49fd6b-fc7c-419e-9644-b6cce008653f",
      "instance_name": "dcs-demo"
    }
  ],
  "instance_id": "3c49fd6b-fc7c-419e-9644-b6cce008653f"
}
```

Status Code

[Table 5-8](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-8 Status code

Status Code	Description
200	DCS instance created successfully.

5.1.2 Deleting a Single DCS Instance

Function

This API is used to delete a specified DCS instance to free up all resources occupied by the DCS instance.

URI

DELETE /v1.0/{project_id}/instances/{instance_id}

[Table 5-9](#) describes the parameter.

Table 5-9 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	Instance ID.

Request

Request parameters

None

Example request

Request URL:

```
DELETE https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}
```

Response

Response parameters

None

Example response

None

Status Code

[Table 5-10](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-10 Status code

Status Code	Description
204	DCS instances deleted successfully.

5.1.3 Batch Deleting DCS Instances

Function

This API is used to delete multiple DCS instances at a time.

URI

DELETE /v1.0/{project_id}/instances?allFailure={allFailure}

[Table 5-11](#) describes the parameters.

Table 5-11 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
allFailure	String	No	An indicator of whether all DCS instances failed to be created will be deleted. Options: Options: • true: all instances that fail to be created are deleted. In this case, the instances parameter in the request can be empty. • false or other values: The DCS instances specified by the instances parameter in the API request will be deleted.

Request

Request parameters

[Table 5-12](#) describes the request parameters.

Table 5-12 Parameter description

Parameter	Type	Mandatory	Description
instances	Array	No	IDs of DCS instances to be deleted. This parameter is set only when the allFailure parameter in the URI is set to false or another value. A maximum of 50 instances can be deleted at a time.

Request URL:

DELETE https://{dcs_endpoint}/v1.0/{project_id}/instances?allFailure={allFailure}

Example request with **allFailure** set to **false**:

```
{
  "instances": [
    "54602a9d-5e22-4239-9123-77e350df4a34",
    "7166cdea-dbad-4d79-9610-7163e6f8b640"
  ]
}
```

Response

Response parameters

If the value of the **allFailure** parameter in the URI is **false**, an empty response is then returned. If the value of the **allFailure** parameter in the URI is **true**, a response containing the parameter in [Table 5-13](#) is returned.

Table 5-13 Parameter description

Parameter	Type	Description
results	Array	For details about how to delete an instance, see Table 5-14 .

Table 5-14 results parameter description

Parameter	Type	Description
instance	String	DCS instance ID.
result	String	Instance deletion result. Options: success and failed

Example response

```
{
  "results": [
    {
      "instance": "54602a9d-5e22-4239-9123-77e350df4a34",
      "result": "success"
    },
    {
      "instance": "7166cdea-dbad-4d79-9610-7163e6f8b640",
      "result": "success"
    }
  ]
}
```

Status Code

[Table 5-15](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-15 Status codes

Status Code	Description
200	DCS instances deleted successfully.
204	DCS instances that failed to be created are cleared successfully.

5.1.4 Querying a DCS Instance

Function

This API is used to query the details about a specified DCS instance.

URI

GET /v1.0/{project_id}/instances/{instance_id}

[Table 5-16](#) describes the parameters.

Table 5-16 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	ID of the instance to be queried

Request

Request parameters

None

Example request

Request URL:

GET https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}

Response

Response parameters

[Table 5-17](#) describes the response parameters.

Table 5-17 Parameter description

Parameter	Type	Description
name	String	DCS instance name.
engine	String	DCS instance engine.
capacity	Integer	DCS instance cache capacity. Unit: GB.
ip	String	IP address for connecting to the DCS instance For a cluster instance, multiple IP addresses are returned and separated by commas (,). For example, 192.168.0.1,192.168.0.2.
domainName	String	Domain name of the instance.
port	Integer	Port number of the cache node.
status	String	Cache instance status. For details about status, see DCS Instance Statuses .
libos	Boolean	true: This instance is a libos instance. false: This instance is not a libos instance.
description	String	Brief description of the DCS instance.
max_memory	Integer	Total memory size. Unit: MB.
used_memory	Integer	Size of the used memory. Unit: MB.
instance_id	String	DCS instance ID.
resource_spec_code	String	Resource specifications. For example: dc.single_node: indicates a DCS instance in single-node mode. dc.master_standby: indicates a DCS instance in master/standby mode. dc.cluster: indicates a DCS instance in cluster mode.
engine_version	String	Cache engine version.
internal_version	String	Internal DCS version.
charging_mode	Integer	Billing mode. 0 : pay-per-use.
capacity_minor	String	Cache capacity of a small-scale, single-node DCS instance.
vpc_id	String	VPC ID.

Parameter	Type	Description
vpc_name	String	VPC name.
created_at	String	Time at which the DCS instance is created. For example, 2017-03-31T12:24:46.297Z.
error_code	String	Error code returned when the DCS instance fails to be created or is abnormal. For details about error codes, see Error Codes .
user_id	String	User ID.
user_name	String	Username.
maintain_begin	String	Time at which the maintenance time window starts. Format: hh:mm:ss.
maintain_end	String	Time at which the maintenance time window ends. Format: hh:mm:ss.
product_type	String	Edition of DCS for Redis. Options: • generic: standard edition • libos: high-performance edition
cpu_type	String	CPU architecture. The value can be x86_64 or aarch_64 .
storage_type	String	Memory type. Options: DRAM and SCM .
cache_mode	String	DCS instance type. Options: • single: single-node • ha: master/standby • cluster: Redis Cluster • proxy: Proxy Cluster
launched_at	String	Time when the instance started running.
available_zones	Array	AZ where a cache node resides. The value of this parameter in the response contains an AZ ID.
subnet_id	String	Subnet ID.
security_group_id	String	Security group ID.
cloud_service_type_code	String	Cloud service type code.

Parameter	Type	Description
cloud_resource_type_code	String	Cloud resource type code.
product_id	String	Product ID.
security_group_name	String	Security group name.
subnet_name	String	Subnet name.
subnet_cidr	String	Subnet segment.
order_id	String	Order ID.
instance_backup_policy	Object	Backup policy. This parameter is available for master/standby and cluster DCS instances. For details, see Table 5-18 .
tags	Array of Objects	Instance tag key and value.

Table 5-18 instance_backup_policy

Parameter	Type	Description
backup_policy_id	String	Backup policy ID.
created_at	String	Creation time.
updated_at	String	Update time.
policy	Object	For details, see Table 5-4 and Table 5-5 .
tenant_id	String	Tenant ID.

Example response

```
{
  "name": "dcs-125d",
  "engine": "Redis",
  "capacity": 64,
  "ip": "192.168.1.48",
  "domainName": "XXXXXX",
  "port": 6379,
  "status": "RUNNING",
  "libos": false,
  "description": null,
  "task": null,
  "max_memory": 65536,
  "used_memory": 33,
  "instance_id": "979e9a6b-e2f5-4b5d-8e98-fea495ea27a1",
  "resource_spec_code": "dcs.cluster",
  "engine_version": "3.0",
}
```

```

"internal_version": null,
"charging_mode": 0,
"capacity_minor": null,
"vpc_id": "d1e8008d-8182-4c86-a142-1ae9349bdc64",
"vpc_name": "vpc-807d",
"task_status": null,
"created_at": "2018-12-11T07:24:18.149Z",
"error_code": null,
"user_id": "9bfac09d9bcd4eb7bb1465a7bcff815b",
"user_name": "user",
"maintain_begin": "02:00:00",
"maintain_end": "06:00:00",
"no_password_access": "true",
"access_user": null,
"enable_publicip": false,
"publicip_id": null,
"publicip_address": null,
"enable_ssl": false,
"service_upgrade": false,
"service_task_id": null,
"is_free": null,
"enterprise_project_id": "0",
"available_zones": ["f84448fd537f46078dd8bd776747f573"],
"subnet_id": "9b32218f-6389-485a-912e-076fe9df6fa7",
"security_group_id": "ecefda9-c8be-42aa-9d5d-9ab46a221240",
"backend_addrs": ["192.168.1.136:6379",
"192.168.1.224:6379"],
"product_id": "00301-17063-0--0",
"security_group_name": "sg--test-hanwang",
"subnet_name": "subnet-7e46",
"order_id": null,
"subnet_cidr": "192.168.1.0/24",
"instance_backup_policy": null,
"tags": [
  {
    "key": "dcs001",
    "value": "001"
  },
  {
    "key": "dcs002",
    "value": "002"
  }
],
"enterprise_project_name": null
}

```

Status Code

Table 5-19 describes the status code of successful operations. For details about other status codes, see **Table 7-1**.

Table 5-19 Status code

Status Code	Description
200	Specified instance queried successfully.

5.1.5 Querying All DCS Instances of a Tenant

Function

This API is used to query DCS instances of a tenant, and allows you to specify query criteria.

URI

GET /v1.0/{project_id}/instances?
start={start}&limit={limit}&name={name}&status={status}&id={id}&include_failure={include_failure}&ip={ip}&tags={key}={value}

Table 5-20 describes the parameters.

Table 5-20 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
start	Integer	No	Start number for querying DCS instances. It cannot be lower than 1. By default, the start number is 1.
limit	Integer	No	Number of DCS instances displayed on each page. Minimum value: 1 Maximum value: 2000 If this parameter is left unspecified, a maximum of 1000 DCS instances are displayed on each page.
name	String	No	DCS instance name.
id	String	No	Instance ID.
status	String	No	DCS instance status. For details about status, see DCS Instance Statuses .
ip	String	No	IP address for connecting to the DCS instance

Parameter	Type	Mandatory	Description
include_failure	String	No	An indicator of whether the number of DCS instances that failed to be created will be returned to the API caller. Options: true: The number of DCS instances that failed to be created will be returned to the API caller. false or others: The number of DCS instances that failed to be created will not be returned to the API caller.
tags	Array of Objects	No	Query based on the instance tag key and value. <i>{key}</i> indicates the tag key, and <i>{value}</i> indicates the tag value. To query instances with multiple tag keys and values, separate key-value pairs with commas (,).

Example

GET https://{dcs_endpoint}/v1.0/bd6b78e2ff9e4e47bc260803ddcc7a21/instances?start=1&limit=10&name=&status=&id=&include_failure=true

Or

GET https://{dcs_endpoint}/v1.0/bd6b78e2ff9e4e47bc260803ddcc7a21/instances?tags=dc001=001,dc002=002

Request

Request parameters

None

Example request

None

Response

Response parameters

[Table 5-21](#) describes the response parameters.

Table 5-21 Parameter description

Parameter	Type	Description
instances	Array	Array of DCS instance details.

Parameter	Type	Description
instance_num	Integer	Number of DCS instances.

Table 5-22 instances parameters

Parameter	Type	Description
name	String	DCS instance name.
engine	String	Cache engine.
capacity	Integer	Cache capacity. Unit: GB.
ip	String	IP address for connecting to the DCS instance For a cluster instance, multiple IP addresses are returned and separated by commas (,). For example, 192.168.0.1,192.168.0.2.
port	Integer	Port number of the cache node.
status	String	Cache instance status. For details about status, see DCS Instance Statuses .
max_memory	Integer	Overall memory size. Unit: MB.
used_memory	Integer	Size of the used memory. Unit: MB.
instance_id	String	DCS instance ID.
resource_spec_code	String	Resource specifications. For example: dc.single_node: indicates a DCS instance in single-node mode. dc.master_standby: indicates a DCS instance in master/standby mode. dc.cluster: indicates a DCS instance in cluster mode.
engine_version	String	Cache engine version.
internal_version	String	Internal DCS version.
charging_mode	Integer	Billing mode. 0 : pay-per-use.
capacity_minor	String	Small-scale cache capacity. Unit: GB.
vpc_id	String	VPC ID.

Parameter	Type	Description
vpc_name	String	VPC name.
created_at	String	Time at which the DCS instance is created. For example, 2017-03-31T12:24:46.297Z.
error_code	String	Error code returned when the DCS instance fails to be created or is abnormal. For details about error codes, see Error Codes .
user_id	String	User ID.
user_name	String	Username.
maintain_begin	String	Time at which the maintenance time window starts. Format: hh:mm:ss.
maintain_end	String	Time at which the maintenance time window ends. Format: hh:mm:ss.
security_group_id	String	Security group name.
tags	Array of Objects	Instance tag key and value.

Example response

```
{
  "instances": [
    {
      "name": "dcs-lxy",
      "engine": "Redis",
      "capacity": 4,
      "ip": "192.168.7.146",

      "port": 6379,
      "status": "CREATING",
      "max_memory": 3277,
      "used_memory": 0,
      "instance_id": "a4d31cb6-3d72-4fdc-8ec9-6e3a41e47f71",
      "resource_spec_code": "dcs.master_standby",
      "engine_version": "3.0",
      "internal_version": null,
      "charging_mode": 0,
      "capacity_minor": null,
      "vpc_id": "c71d9731-9b0c-43e9-ab2a-716af9d9fd55",
      "vpc_name": "CCE-AutoCreate-VPC-7qvs1",
      "created_at": "2019-09-23T02:40:06.123Z",
      "error_code": null,
      "user_id": "50a4156d334a4a82b8745dc730dc1e00",
      "user_name": "user",
      "maintain_begin": "02:00:00",
      "maintain_end": "06:00:00",
      "enable_ssl": false,
      "tags": [
        {
          "key": "dcs001",
          "value": "001"
        }
      ],
    }
  ],
}
```

```
{
  {
    "key": "dcs002",
    "value": "002"
  },
  "security_group_id": "0cc8fdb7-872a-49da-a062-88ccc39463b5"
},
"instance_num": 1
}
```

Status Code

[Table 5-23](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-23 Status code

Status Code	Description
200	All DCS instances of the tenant queried successfully.

5.1.6 Modifying Information About a DCS Instance

Function

This API is used to modify the information about a DCS instance, including the instance name, description, backup policy, start and end time of the maintenance window, and security group.

URI

PUT /v1.0/{project_id}/instances/{instance_id}

[Table 5-24](#) describes the parameters.

Table 5-24 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	DCS instance ID.

Request

Request parameters

Table 5-25 describes the request parameters.

Table 5-25 Parameter description

Parameter	Type	Mandatory	Description
name	String	No	DCS instance name. An instance name can contain 4 to 64 characters, including letters, digits, underscores (_), and hyphens (-), and must start with a letter.
description	String	No	Brief description of the DCS instance. A brief description supports up to 1024 characters. NOTE "\" is defined as an escape character in the queue description. If you need to enter a backward slash (\) or a double quotation mark (") in the queue description, enter \\ or \".
instance_backup_policy	Object	No	Backup policy. This parameter is available for master/standby and cluster DCS instances. For details, see Table 5-4 and Table 5-5 .
maintain_begin	String	No	Time at which the maintenance time window starts. Format: hh:mm:ss. - The start time and end time of the maintenance time window must indicate the time segment of a supported maintenance time window. For details on how to query the time segments of supported maintenance time windows, see Querying Maintenance Time Window. - The start time must be set to 22:00:00, 02:00:00, 06:00:00, 10:00:00, 14:00:00, or 18:00:00. - Parameters maintain_begin and maintain_end must be set in pairs. If parameter maintain_begin is left blank, parameter maintain_end is also blank.

Parameter	Type	Mandatory	Description
maintain_end	String	No	Time at which the maintenance time window ends. Format: hh:mm:ss. - The start time and end time of the maintenance time window must indicate the time segment of a supported maintenance time window. For details on how to query the time segments of supported maintenance time windows, see Querying Maintenance Time Window. - The end time is four hours later than the start time. For example, if the start time is 22:00:00, the end time is 02:00:00. - Parameters maintain_begin and maintain_end must be set in pairs. If parameter maintain_end is left blank, parameter maintain_start is also blank.
security_group_id	String	No	Security group ID. The value can be obtained from the VPC console or the API. This parameter is supported only by DCS Redis 3.0 instances.

Example request

Request URL:

PUT https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}

- Example 1

```
{
  "description": "instance description"
}
```

- Example 2

```
{
  "name": "dcs002",
  "description": "instance description",
  "instance_backup_policy": {
    "backup_type": "auto",
    "save_days": 1,
    "periodical_backup_plan": {
      "begin_at": "00:00-01:00",
      "period_type": "weekly",
      "backup_at": [
        "1",
        "2",
        "3",

```

```
        "4",  
        "6",  
        "7"  
    ]  
  },  
  "security_group_id": "18e9309f-f81a-4749-bb21-f74576292162",  
  "maintain_begin": "02:00:00",  
  "maintain_end": "06:00:00"  
}
```

Response

Response parameters

None

Example response

None

Status Code

[Table 5-26](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-26 Status code

Status Code	Description
204	DCS instance modified successfully.

5.1.7 Scaling Up a DCS Instance

Function

This API is used to scale up a DCS Redis or Memcached instance in the **Running** state.

URI

POST /v1.0/{project_id}/instances/{instance_id}/extend

[Table 5-27](#) describes the parameters.

Table 5-27 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	Instance ID.

Request

Request parameters

[Table 5-28](#) describes the request parameters.

Table 5-28 Parameter description

Parameter	Type	Mandatory	Description
new_capacity	Integer	Yes	New specification (memory space) of the DCS instance. The new specification to which the DCS instance will be scaled up must be greater than the current specification. Unit: GB. The value must be supported specifications. For details, see the Total Memory (GB) column in the "DCS Instance Specifications" section in <i>Distributed Cache Service User Guide</i> .
spec_code	String	Yes	DCS instance specification code. This parameter is optional for DCS Redis 3.0 instances. This parameter is mandatory for DCS Redis 4.0 and later instances.

Example request

- Request URL:
POST `https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/extend`
- Example:

```
{
  "spec_code": "redis.single.au1.large.4",
  "new_capacity": 4,
}
```


Response

Response parameters

None

Example response

None

Status Code

[Table 5-29](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-29 Status code

Status Code	Description
204	Scale-up task submitted successfully.

5.2 Instance Management APIs

5.2.1 Restarting DCS Instances or Clearing DCS Instance Data

Function

This API is used to restart a running DCS instance.

Data clearance operations cannot be undone on DCS Redis 4.0 and 5.0 instances.

URI

PUT /v1.0/{project_id}/instances/status

[Table 5-30](#) describes the parameter.

Table 5-30 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .

Request

Request parameters

[Table 5-31](#) describes the request parameters.

Table 5-31 Parameter description

Parameter	Type	Mandatory	Description
action	String	Yes	Action performed on DCS instances. Options: restart , and flush . NOTE Only DCS Redis 4.0 and 5.0 instances can be flushed.
instances	Array	Yes	List of DCS instance IDs.

Example request

- Request URL:
PUT https://{dcs_endpoint}/v1.0/{project_id}/instances/status
- Example:

```
{  "action": "restart",  "instances": [    "2e803f66-fbb0-47ad-b6cb-fb87f5bed4ef"  ]}
```

Response

Response parameters

[Table 5-32](#) describes the response parameter.

Table 5-32 Parameter description

Parameter	Type	Description
results	Array	Indicates the result of instance modification.

Table 5-33 results parameter description

Parameter	Type	Description
instance	String	DCS instance ID.
result	String	Instance modification result. Options: success or failed

Example response

```
{
  "results": [
    {
      "result": "success",
      "instance": "2e803f66-fbb0-47ad-b6cb-fb87f5bed4ef"
    }
  ]
}
```

Status Code

[Table 5-34](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-34 Status code

Status Code	Description
200	Successfully restarted DCS instance or cleared DCS instance data.

5.2.2 Querying Statistics of All Running Instances

Function

This API is used to query the statistics of all DCS instances that are in the **Running** state.

URI

GET /v1.0/{project_id}/instances/statistic

[Table 5-35](#) describes the parameter.

Table 5-35 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .

Request

Request parameters

None

Example request

```
GET https://{dcs_endpoint}/v1.0/{project_id}/instances/statistic
```

Response

Response parameters

[Table 5-36](#) describes the response parameter.

Table 5-36 Parameter description

Parameter	Type	Description
statistics	Array	Statistics of all instances in the Running state. For details, see Table 5-37 .

Table 5-37 statistics parameter description

Parameter	Type	Description
keys	Integer	Number of cached data records
instance_id	String	DCS instance ID
used_memory	Integer	Size of the used memory in MB
max_memory	Integer	Overall memory size in MB
cmd_get_count	Integer	Number of times the GET command is run
cmd_set_count	Integer	Number of times the SET command is run
used_cpu	String	Percentage of CPU usage
input_kbps	String	Incoming traffic (kbit/s) of the DCS instance
output_kbps	String	Outgoing traffic (kbit/s) of the DCS instance

Example response

```
{
  "statistics": [{
    "keys": 0,
    "instance_id": "e008652d-18e0-43ff-924e-072261e0372a",
    "used_memory": 0,
    "max_memory": 460,
    "cmd_get_count": 0,
    "cmd_set_count": 0,
    "used_cpu": "0.0",
    "input_kbps": "0.0",
    "output_kbps": "0.0"
  ]
}
```

```
    }, {
      "keys": 0,
      "instance_id": "c577a1eb-33b7-42c7-8231-ad32358599ac",
      "used_memory": 0,
      "max_memory": 460,
      "cmd_get_count": 0,
      "cmd_set_count": 0,
      "used_cpu": "0.0",
      "input_kbps": "0.0",
      "output_kbps": "0.0"
    }, {
      "keys": 0,
      "instance_id": "e8b98471-55d5-4695-b0bb-8f336a98e207",
      "used_memory": 0,
      "max_memory": 460,
      "cmd_get_count": 0,
      "cmd_set_count": 0,
      "used_cpu": "0.0",
      "input_kbps": "0.03",
      "output_kbps": "1.19"
    }, {
      "keys": 0,
      "instance_id": "bc61c690-4b34-4cbe-9ce3-11246aea7aba",
      "used_memory": 0,
      "max_memory": 6963,
      "cmd_get_count": 0,
      "cmd_set_count": 0,
      "used_cpu": "0.0",
      "input_kbps": "0.0",
      "output_kbps": "0.0"
    }
  ]
}
```

Status Code

Table 5-38 describes the status code of successful operations. For details about other status codes, see **Table 7-1**.

Table 5-38 Status code

Status Code	Description
200	Statistics of all instances queried successfully.

5.2.3 Querying DCS Instance Status

Function

This API is used to query the number of instances in different states.

URI

GET /v1.0/{project_id}/instances/status?include_failure={include_failure}

Table 5-39 describes the parameters.

Table 5-39 Parameter description

Parameter	Type	Mandator y	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
include_failure	String	No	An indicator of whether the number of DCS instances that failed to be created will be returned to the API caller. Options: • true: The number of DCS instances that failed to be created will be returned to the API caller. • false or others: The number of DCS instances that failed to be created will not be returned to the API caller.

Request

Request parameters

None

Example request

```
GET https://{dcs_endpoint}/v1.0/{project_id}/instances/status?include_failure=true
```

Response

Response parameters

[Table 5-40](#) describes the response parameters.

Table 5-40 Parameter description

Parameter	Type	Description
redis	StatusStatistic object	Redis instance quantity statistics.
memcached	StatusStatistic object	Memcached instance quantity statistics.
creating_count	Integer	Number of instances that are being created.

Parameter	Type	Description
deleting_count	Integer	Number of instances that are being deleted.
running_count	Integer	Number of running instances.
error_count	Integer	Number of abnormal instances.
restarting_count	Integer	Number of instances that are being restarted.
createfailed_count	Integer	Number of instances that fail to be created.
extending_count	Integer	Number of instances that are being scaled up.
upgrading_count	Integer	Number of instances that are being upgraded.
paying_count	Integer	Number of instances for which payment is in progress.
migrating_count	Integer	Number of instances on which data migration is in progress.
flushing_count	Integer	Number of instances whose data is being cleared.
closed_count	Integer	Number of instances that have been stopped.
starting_count	Integer	Number of instances that are being started.
closing_count	Integer	Number of instances that are being stopped.
restoring_count	Integer	Number of instances for which data restoration is in progress.

Table 5-41 StatusStatistic

Parameter	Type	Description
paying_count	Integer	Number of instances for which payment is in progress.
migrating_count	Integer	Number of instances on which data migration is in progress.
flushing_count	Integer	Number of instances whose data is being cleared.

Parameter	Type	Description
upgrading_count	Integer	Number of instances that are being upgraded.
restoring_count	Integer	Number of instances for which data restoration is in progress.
extending_count	Integer	Number of instances that are being scaled up.
creating_count	Integer	Number of instances that are being created.
running_count	Integer	Number of running instances.
error_count	Integer	Number of abnormal instances.
createfailed_count	Integer	Number of instances that fail to be created.
restarting_count	Integer	Number of instances that are being restarted.

Status code: 400

Table 5-42 Response body parameters

Parameter	Type	Description
error_msg	String	Error message. Maximum length: 1024 characters
error_code	String	Error code. Maximum length: 9 characters
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null. Maximum length: 1024 characters

Status code: 500

Table 5-43 Response body parameters

Parameter	Type	Description
error_msg	String	Error message. Maximum length: 1024 characters

Parameter	Type	Description
error_code	String	Error code. Maximum length: 9 characters
error_ext_msg	String	Extended error information. This parameter is not used currently and is set to null. Maximum length: 1024 characters

Example response

```
{
  "memcached": {
    "paying_count": 0,
    "migrating_count": 0,
    "error_count": 0,
    "restarting_count": 0,
    "createfailed_count": 0,
    "flushing_count": 0,
    "closed_count": 0,
    "extending_count": 0,
    "creating_count": 0,
    "starting_count": 0,
    "closing_count": 0,
    "running_count": 0,
    "upgrading_count": 0,
    "restoring_count": 0
  },
  "paying_count": 0,
  "migrating_count": 0,
  "error_count": 0,
  "restarting_count": 0,
  "createfailed_count": 0,
  "flushing_count": 0,
  "redis": {
    "paying_count": 0,
    "migrating_count": 0,
    "error_count": 0,
    "restarting_count": 0,
    "createfailed_count": 0,
    "flushing_count": 0,
    "closed_count": 0,
    "extending_count": 2,
    "creating_count": 0,
    "starting_count": 0,
    "closing_count": 0,
    "running_count": 1,
    "upgrading_count": 0,
    "restoring_count": 0
  },
  "closed_count": 0,
  "extending_count": 2,
  "creating_count": 0,
  "starting_count": 0,
  "closing_count": 0,
  "running_count": 1,
  "upgrading_count": 0,
  "restoring_count": 0
}
```

Status Code

[Table 5-44](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-44 Status code

Status Code	Description
200	Quantities of DCS instances in different statuses queried successfully.
400	The request is invalid.
500	Internal service error.

5.2.4 Changing the Password of a DCS Instance

Function

This API is used to change the password of a DCS instance.

URI

PUT /v1.0/{project_id}/instances/{instance_id}/password

[Table 5-45](#) describes the parameters.

Table 5-45 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	DCS instance ID.

Request

Request parameters

[Table 5-46](#) describes the request parameters.

Table 5-46 Parameter description

Parameter	Type	Mandatory	Description
old_password	String	Yes	Old password.
new_password	String	Yes	New password. Password complexity requirements: • Cannot be empty. • Cannot be the username or the username spelled backwards. • Can contain 8 to 64 characters. • Contain at least three of the following character types: – Lowercase letters – Uppercase letters – Digits – Special characters (~!@#\$%^&*()-_+=\ {};,<.>/?)

Example request

- Request URL:
PUT https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/password
- Example:

```
{  "old_password": "XXXXXX",  "new_password": "XXXXXX"}
```

Response

Response parameters

Table 5-47 describes the response parameters.

Table 5-47 Parameter description

Parameter	Type	Description
result	String	An indicator of whether the password is successfully changed: Options: • Success: Password changed successfully. • passwordFailed: The old password is incorrect. • Locked: This account has been locked. • Failed: Failed to change the password.
message	String	Result of password change.

Parameter	Type	Description
retry_times_left	String	Number of remaining password attempts. If the old password is incorrect, the value of this parameter is not null .
lock_time	String	Account lockout duration. If the old password is incorrect or the account is locked, the value of this parameter is not null .
lock_time_left	String	Remaining time before the account is unlocked. If the account is locked, the value of this parameter is not null .

Example response

```
//Change password success.
{
  "result" : "Success",
  "message" : "Modify DCSInstance password success.",
  "retry_times_left" : "5",
  "lock_time" : "0",
  "lock_time_left" : "0"
}
//Change password failed.
{
  "result" : "passwordFailed",
  "message" : "verify password failed.",
  "retry_times_left" : "4",
  "lock_time" : "5",
  "lock_time_left" : "5"
}
```

Status Code

[Table 5-48](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-48 Status code

Status Code	Description
200	Password changed successfully.

5.3 Parameter Management APIs

5.3.1 Modifying Configuration Parameters

Function

You can modify the configuration parameters of your DCS instance to optimize DCS performance based on your requirements.

URI

PUT /v1.0/{*project_id*}/instances/{*instance_id*}/configs

[Table 5-49](#) describes the parameters.

Table 5-49 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	ID of the instance to be modified.

Request

Request parameters

[Table 5-50](#) describes the request parameters.

Table 5-50 Parameter description

Parameter	Type	Mandatory	Description
redis_config	Array	Yes	Array of configuration items of the DCS instance.

Table 5-51 redis_config parameter description

Parameter	Type	Mandatory	Description
param_id	String	Yes	Configuration item ID.
param_name	String	Yes	Configuration item name.
param_value	String	Yes	Value of the configuration item.

For possible values of parameters in [Table 5-51](#), see [Table 5-56](#).

Example request

- Request URL:
PUT `https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/configs`
- Example:

```
{
  "redis_config": [
    {
      "param_id": "1",
      "param_name": "timeout",
      "param_value": "100"
    }
  ]
}
```

Response

Response parameters

None

Example response

None

Status Code

[Table 5-52](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-52 Status code

Status Code	Description
204	DCS instance configurations modified successfully.

5.3.2 Querying Configuration Parameters

Function

This API is used to query the configuration parameters of a DCS instance.

URI

GET `/v1.0/{project_id}/instances/{instance_id}/configs`

[Table 5-53](#) describes the parameters.

Table 5-53 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	ID of the instance to be queried.

Request

Request parameters

None

Example request

```
GET https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/configs
```

Response

Response parameters

[Table 5-54](#) describes the response parameters.

Table 5-54 Parameter description

Parameter	Type	Description
status	String	Current status of a DCS instance.
instance_id	String	DCS instance ID.
redis_config	Array	Array of configuration items of the DCS instance. For details, see Table 5-55 .
config_status	String	DCS instance status that is being modified or has been modified. Options: • UPDATING • FAILURE • SUCCESS
config_time	String	Time at which the DCS instance is operated on. For example, 2017-03-31T12:24:46.297Z.
cluster_v1	Boolean	Instance type. If true is returned, the instance is a Proxy Cluster DCS Redis 3.0 instance. If false is returned, the instance is not a Proxy Cluster DCS Redis 3.0 instance.

Table 5-55 redis_config parameter description

Parameter	Type	Description
description	String	Configuration item description.
param_id	String	Configuration parameter ID. For the possible values, see the Parameter ID column in Table 5-56 .
param_name	String	Configuration parameter name. For the possible values, see the Parameter Name column in Table 5-56 .
param_value	String	Configuration parameter value.
default_value	String	Default value of the configuration parameter. For the possible values, see the Default Value column in Table 5-56 .
value_type	String	Type of the configuration parameter value. For the possible values, see the Value Type column in Table 5-56 .
value_range	String	Range of the configuration parameter value. For the possible values, see the Value Range column in Table 5-56 .
node_role	String	If null or empty is returned, the node is a default node, that is, the Redis Server node. If proxy is returned, the node is a proxy node.

[Table 5-56](#) describes the configuration parameters of a DCS instance.

Table 5-56 Configuration parameters of a DCS instance

Parameter ID	Parameter Name	Applicable Engine	Type	Description	Value Range	Default Value
1	timeout	Redis and Memcached	Integer	Connection between the client and server (DCS instance) will be closed if the client is idle for the timeout period (measured in seconds). A timeout period of 0 seconds indicates that the timeout function is disabled.	0–7200 seconds	0
2	maxmemory-policy	Redis and Memcached	String	How Redis will select what to remove when maxmemory is reached. For details about key eviction, see the Redis official website .	volatile-lru allkeys-lru volatile-random allkeys-random volatile-ttl noeviction volatile-lfu allkeys-lfu	noeviction or volatile-lru The value range and default value depend on the instance version and type.

Parameter ID	Parameter Name	Applicable Engine	Type	Description	Value Range	Default Value
3	hash-max-ziplist-entries	Redis	Integer	When the number of entries in hashes is less than the value of this parameter, hashes are encoded using ziplist to save memory.	1-10,000	512
4	hash-max-ziplist-value	Redis	Integer	When the biggest entry in hashes does not exceed the length threshold indicated by this parameter, hashes are encoded using ziplist to save memory.	1-10,000	64
5	list-max-ziplist-entries	Redis	Integer	When the number of entries in lists is less than the value of this parameter, lists are encoded using ziplist to save memory.	1-10,000	512
6	list-max-ziplist-value	Redis	Integer	When the biggest entry in lists does not exceed the length threshold indicated by this parameter, lists are encoded using ziplist to save memory.	1-10,000	64
7	set-max-intset-entries	Redis	Integer	When a set is composed entirely of strings and the number of integers does not exceed the length threshold indicated by this parameter, the set is encoded using intset to save memory.	1-10,000	512

Parameter ID	Parameter Name	Applicable Engine	Type	Description	Value Range	Default Value
8	zset-max-ziplist-entries	Redis	Integer	When the number of entries in sorted sets is less than the value of this parameter, sorted sets are encoded using a ziplist to save memory.	1-10,000	128
9	zset-max-ziplist-value	Redis	Integer	When the biggest entry in sorted sets does not exceed the length threshold indicated by this parameter, sorted sets are encoded using ziplist to save memory.	1-10,000	64

Parameter ID	Parameter Name	Applicable Engine	Type	Description	Value Range	Default Value
10	latency-monitor-threshold	Redis	Integer	The minimum amount of latency that will be logged as latency spikes If this parameter is set to 0, latency monitoring is disabled. If this parameter is set to a value greater than 0, all events blocking the server for a time greater than the configured value will be logged. By running the LATENCY command, you can perform operations related to latency monitoring, such as obtaining statistical data, and configuring and enabling latency monitoring. For more information about the latency-monitor-threshold, visit the Redis official website.	0–86,400,000 ms	0

Parameter ID	Parameter Name	Applicable Engine	Type	Description	Value Range	Default Value
12	reserved-memory	Redis	Integer	Reserved memory, which is the number of megabytes reserved for the backend to perform internal processing such as persistence and master/standby replication. This parameter is available only for master/standby instances. The size of the reserved memory can be adjusted, but must be in the value range described in the next column. NOTE: For more information about maximum available memory of each instance type, see <i>DCS Service Overview</i>.	0% to 50% of maximum memory space initially available to the instance and below the current free memory space. Unit: MB.	0

Parameter ID	Parameter Name	Applicable Engine	Type	Description	Value Range	Default Value
13	notify-keyspace-events	Redis	String	Keyspace event notification. If this parameter is configured, the Redis Sub/Pub feature will allow clients to receive an event when a Redis data set is modified.	If the parameter value is an empty character string or null, the default value Ex is used. If the parameter value contains multiple characters, keyspace event notification is enabled and each character identifies a class of keyspace events for which Redis will send notifications. K: Keyspace events, published with the <code>__keyspace@__</code> prefix E: Keyevent events, published with the <code>__keyevent@__</code> prefix g: Generic commands (non-type specific)	Ex

Parameter ID	Parameter Name	Applicable Engine	Type	Description	Value Range	Default Value
					such as DEL, EXPIRE, and RENAME \$: String commands l: List commands s: Set commands h: Hash commands z: Sorted set commands x: Expired events (events generated every time a key expires) e: Evicted events (events generated when a key is evicted for maxmemory) For more information, see the following note.	

NOTE

More about the **notify-keyspace-events** parameter:

- Allowed characters are K, E, KE, A, g, l, s, h, z, x, e, and \$. The parameter value must contain either **K** or **E**.
- A** is an alias for **g\$lshzxe** and cannot be used together with any of the characters in g\$lshzxe.
- For example, the value **kl** means that Redis will notify Pub/Sub clients about keyspace events and list commands. The value **AKE** means Redis will notify Pub/Sub clients about all events.

Example response

```
{
  "status": "RUNNING",
  "instance_id": "c08fdc6e-5c25-4185-ab57-c0a5529b727f",
  "redis_config": [
    {
      "description": "How Redis will select what to remove when maxmemory is reached, You can select among five behaviors: volatile-lru : remove the key with an expire set using an LRU algorithm allkeys-lru : remove any key according to the LRU algorithm volatile-random: remove a random key with an expire set allkeys-random: remove a random key, any key volatile-ttl : remove the key with the nearest expire time (minor TTL) noeviction : don't expire at all, just return an error on write operations",
      "param_id": 2,
      "param_name": "maxmemory-policy",
      "param_value": "noeviction",
      "default_value": "noeviction",
      "value_type": "String",
      "value_range": "volatile-lru,allkeys-lru,volatile-random,allkeys-random,volatile-ttl,noeviction"
    },
    {
      "description": "Hashes are encoded using a memory efficient data structure when they have a small number of entries",
      "param_id": 3,
      "param_name": "hash-max-ziplist-entries",
      "param_value": "512",
      "default_value": "512",
      "value_type": "Integer",
      "value_range": "1-10000"
    },
    {
      "description": "Hashes are encoded using a memory efficient data structure when the biggest entry does not exceed a given threshold",
      "param_id": 4,
      "param_name": "hash-max-ziplist-value",
      "param_value": "64",
      "default_value": "64",
      "value_type": "Integer",
      "value_range": "1-10000"
    },
    {
      "description": "Lists are encoded using a memory efficient data structure when they have a small number of entries",
      "param_id": 5,
      "param_name": "list-max-ziplist-entries",
      "param_value": "512",
      "default_value": "512",
      "value_type": "Integer",
      "value_range": "1-10000"
    },
    {
      "description": "Lists are encoded using a memory efficient data structure when the biggest entry does not exceed a given threshold",
      "param_id": 6,
      "param_name": "list-max-ziplist-value",
      "param_value": "64",
      "default_value": "64",
      "value_type": "Integer",
      "value_range": "1-10000"
    },
    {
      "description": "When a set is composed of just strings that happen to be integers in radix 10 in the range of 64 bit signed integers.",
      "param_id": 7,
      "param_name": "set-max-intset-entries",
      "param_value": "512",
      "default_value": "512",
      "value_type": "Integer",
      "value_range": "1-10000"
    }
  ]
}
```



```
    "description": "Sorted sets are encoded using a memory efficient data structure when they have a  
small number of entries",  
    "param_id": 8,  
    "param_name": "zset-max-ziplist-entries",  
    "param_value": "128",  
    "default_value": "128",  
    "value_type": "Integer",  
    "value_range": "1-10000"  
  },  
  {  
    "description": "Sorted sets are encoded using a memory efficient data structure when the biggest  
entry does not exceed a given threshold",  
    "param_id": 9,  
    "param_name": "zset-max-ziplist-value",  
    "param_value": "64",  
    "default_value": "64",  
    "value_type": "Integer",  
    "value_range": "1-10000"  
  },  
  {  
    "description": "Close the connection after a client is idle for N seconds (0 to disable)",  
    "param_id": 1,  
    "param_name": "timeout",  
    "param_value": "0",  
    "default_value": "0",  
    "value_type": "Integer",  
    "value_range": "0-7200"  
  },  
  {  
    "description": "Only events that run in more time than the configured latency-monitor-threshold  
will be logged as latency spikes. If latency-monitor-threshold is set to 0, latency monitoring is disabled. If  
latency-monitor-threshold is set to a value greater than 0, all events blocking the server for a time equal to  
or greater than the configured latency-monitor-threshold will be logged.",  
    "param_id": 10,  
    "param_name": "latency-monitor-threshold",  
    "param_value": "0",  
    "default_value": "0",  
    "value_type": "Integer",  
    "value_range": "0-86400000"  
  },  
  {  
    "description": "The total memory, in bytes, reserved for non-data usage.",  
    "param_id": 12,  
    "param_name": "reserved-memory",  
    "param_value": "0",  
    "default_value": "0",  
    "value_type": "Integer",  
    "value_range": "0-6553"  
  },  
  {  
    "description": "Redis can notify Pub or Sub clients about events happening in the key space",  
    "param_id": 13,  
    "param_name": "notify-keyspace-events",  
    "param_value": null,  
    "default_value": null,  
    "value_type": "regular",  
    "value_range": "([KE]+([A])(g$!shzxe)+)){0,11}"  
  }  
],  
"config_status": "SUCCESS",  
"config_time": ""  
}
```

Status Code

Table 5-57 describes the status code of successful operations. For details about other status codes, see **Table 7-1**.

Table 5-57 Status code

Status Code	Description
200	Instance configurations queried successfully.

5.4 Data Migration APIs

5.4.1 Creating a Data Migration Task

Function

This API is used to create a data migration task.

Constraints

None

URI

POST /v2/{project_id}/migration-task

Table 5-58 URI parameter

Parameter	Man dator y	Type	Description
project_id	Yes	String	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .

Request

Table 5-59 Request body parameter description

Parameter	Man dator y	Type	Description
task_name	Yes	String	Name of the migration task.
description	No	String	Description of the migration task.

Parameter	Mandatory	Type	Description
migration_type	Yes	String	Mode of the migration. Options: • backupfile_import: indicates importing backup files. • online_migration: indicates migrating data online.
migration_method	Yes	String	Type of the migration. Options: • full_amount_migration: indicates a full migration. • incremental_migration: indicates an incremental migration.
backup_files	No	BackupFilesBody Object	Backup files to be imported when the migration mode is importing backup files.
network_type	No	String	Type of the network for communication between the source and destination Redis when the migration mode is online data migration. Options: • vpc • vpn
source_instance	No	SourceInstanceBody Object	Source Redis information. This parameter is mandatory when the migration mode is online data migration.
target_instance	Yes	TargetInstanceBody Object	Destination Redis instance information.

Table 5-60 BackupFilesBody

Parameter	Mandatory	Type	Description
file_source	No	String	Data source. Currently, only OBS buckets are supported. The value is self_build_obs .

Parameter	Mandatory	Type	Description
bucket_name	Yes	String	OBS bucket name.
files	Yes	Array of Files Objects	List of backup files to be imported.

Table 5-61 Files

Parameter	Mandatory	Type	Description
file_name	Yes	String	Name of a backup file.
size	No	String	File size in bytes.
update_at	No	String	Time when the file is last modified. The format is YYYY-MM-DD HH:MM:SS.

Table 5-62 SourceInstanceBody

Parameter	Mandatory	Type	Description
addr	Yes	String	Source Redis name (specified in the source_instance parameter).
password	No	String	Redis password. If a password is set, this parameter is mandatory.

Table 5-63 TargetInstanceBody

Parameter	Mandatory	Type	Description
id	Yes	String	Destination Redis instance ID (mandatory in the target_instance parameter).
name	No	String	Destination Redis instance name (specified in the target_instance parameter).

Parameter	Mandatory	Type	Description
password	No	String	Redis password. If a password is set, this parameter is mandatory.

Response

If the status code is 200, the following parameters are returned:

Table 5-64 Parameter description

Parameter	Type	Description
id	String	ID of the migration task.
name	String	Name of the migration task.
status	String	Migration task status. The value can be: • SUCCESS: Migration succeeded. • FAILED: Migration failed. • MIGRATING: Migration is in progress. • TERMINATED: Migration has been stopped. • TERMINATING: Migration is being stopped. • RUNNING: The migration task has been created and is waiting to be executed. • CREATING: The migration task is being created. • FULLMIGRATING: Full migration is in progress. • INCRMIGEATING: Incremental migration is in progress. • ERROR: faulty • DELETED: faulty • RELEASED: automatically released • MIGRATION_SUCCESS: The migration is successful, and resources are to be cleared. • MIGRATION_FAILED: The migration failed, and resources are to be cleared.

Example Request

- Example request URL:
POST https://{dcs_endpoint}/v2/{project_id}/migration-task

- Example request 1 (online migration)

```
{
  "task_name": "lmd-test",
  "description": "Test",
  "migration_type": "online_migration",
  "migration_method": "full_amount_migration",
  "network_type": "vpc",
  "source_instance": {
    "addr": "192.168.1.135:6379",
    "password": "xxxxxx"
  },
  "target_instance": {
    "name": "dcs-test",
    "id": "4cd5dbb8-aacd-4603-b817-3e97d48c7a20"
  }
}
```

- Example request 2 (importing a backup file)

```
{
  "backup_files": {
    "bucket_name": "bucket-lmz",
    "file_source": "self_build_obs",
    "files": [
      {
        "file_name": "appendonly03.aof"
      }
    ]
  },
  "migration_method": "full_amount_migration",
  "migration_type": "backupfile_import",
  "target_instance": {
    "id": "318ed365-3c1b-42d7-a5b6-663dded628a0"
  },
  "task_name": "lmd-test"
}
```

Example Response

If the status code is 200, the data migration task is successfully created.

```
{
  "id": "8aa6999e71cb638b0171f485f5266ef0",
  "name": "lmd-test",
  "status": "MIGRATING"
}
```

Status Code

Status Code	Description
200	Data migration task created successfully.
400	Invalid request.
500	Internal service error.

Error Codes

For details, see [Error Codes](#).

5.5 Backup and Restoration APIs

5.5.1 Backing Up a DCS Instance

Function

This API is used to back up a specified DCS instance.

NOTE

Only master/standby and cluster DCS instances can be backed up and restored, while single-node instances cannot.

URI

POST /v1.0/{project_id}/instances/{instance_id}/backups

[Table 5-65](#) describes the parameters.

Table 5-65 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	DCS instance ID.

Request

Request parameters

[Table 5-66](#) describes the request parameters.

Table 5-66 Parameter description

Parameter	Type	Mandatory	Description
remark	String	No	Description of DCS instance backup.

Example request

- Request URL:
POST `https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/backups`

- Example:

```
{  "remark": "Backup instances"}
```

Response

Response parameters

[Table 5-67](#) describes the response parameter.

Table 5-67 Parameter description

Parameter	Type	Description
backup_id	String	ID of the backup record

Example response

```
{  "backup_id": "548ceeff-2cbb-47ab-9a1c-7b085a8c08d7"}
```

Status Code

[Table 5-68](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-68 Status code

Status Code	Description
200	Backup task created successfully.

5.5.2 Restoring a DCS Instance

Function

This API is used to restore a specified DCS instance.

NOTE

Only master/standby and cluster DCS instances can be backed up and restored, while single-node instances cannot.

URI

POST /v1.0/{project_id}/instances/{instance_id}/restores

[Table 5-69](#) describes the parameters.

Table 5-69 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	DCS instance ID.

Request

Request parameters

[Table 5-70](#) describes the request parameters.

Table 5-70 Parameter description

Parameter	Type	Mandatory	Description
remark	String	No	Description of DCS instance restoration
backup_id	String	Yes	ID of the backup record

Example request

Request URL:

```
POST https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/restores
```

Example:

```
{
  "remark": "restore instance",
  "backup_id": "8ba256cb-e5ac-44f6-a3da-c03d8f0e5029"
}
```

Response

Response parameters

[Table 5-71](#) describes the response parameter.

Table 5-71 Parameter description

Parameter	Type	Description
restore_id	String	ID of the restoration record

Example response

```
{
  "restore_id": "a6155972-800c-4170-a479-3231e907d2f6"
}
```

Status Code

[Table 5-72](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-72 Status code

Status Code	Description
200	Restoration task created successfully.

5.5.3 Querying DCS Instance Backup Records

Function

This API is used to query the backup records of a specified DCS instance.

URI

GET /v1.0/{project_id}/instances/{instance_id}/backups?
start={start}&limit={limit}&beginTime={beginTime}&endTime={endTime}

[Table 5-73](#) describes the parameters.

Table 5-73 Parameter description

Parameter	Type	Mandator y	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	DCS instance ID.
start	Integer	No	Start sequence number of the backup record that is to be queried. By default, this parameter is set to 1 .

Parameter	Type	Man dator y	Description
limit	Integer	No	Number of backup records displayed on each page. The minimum value of this parameter is 1 . If this parameter is not set, 10 backup records are displayed on each page by default.
beginTime	String	No	Start time of the period to be queried. Format: yyyyMMddHHmmss, for example, 20170718235959.
endTime	String	No	End time of the period to be queried. Format: yyyyMMddHHmmss, for example, 20170718235959.

Request

Request parameters

None

Example request

```
GET https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/backups?  
start={start}&limit={limit}&beginTime={beginTime}&endTime={endTime}
```

Response

Response parameters

[Table 5-74](#) describes the response parameters.

Table 5-74 Parameter description

Parameter	Type	Description
backup_record_response	Array	Array of the backup records. For details about backup_record_response, see Table 5-75 .
total_num	Integer	Number of obtained backup records.

Table 5-75 backup_record_response parameter description

Parameter	Type	Description
status	String	Backup status. Options: • waiting: DCS instance restoration is waiting to begin. • backucing: DCS instance backup is in progress. • succeed: DCS instance backup succeeded. • failed: DCS instance backup failed. • expired: The backup file expires. • deleted: The backup file has been deleted manually.
remark	String	Description of DCS instance backup
period	String	Time segment in which DCS instance backup was performed
progress	String	Backup progress
size	Long	Size of the backup file. Unit: byte.
instance_id	String	DCS instance ID
backup_id	String	ID of the backup record
created_at	String	Time at which the backup task is created
updated_at	String	Time at which DCS instance backup is completed
execution_at	String	Time at which the backup starts.
backup_type	String	Backup type. Options: • manual: manual backup • auto: automatic backup
backup_name	String	Name of the backup record
error_code	String	Error code returned if DCS instance backup fails. For details about error codes, see Table 5-76 .
is_support_restore	String	An indicator of whether restoration is supported. Options: TRUE or FALSE .

Table 5-76 Error codes returned in case of a backup or restoration failure

Error Code	Description
dcs.08.0001	Failed to start the backup and restore tool.
dcs.08.0002	Operation timed out.

Error Code	Description
dcs.08.0003	Failed to delete bucket.
dcs.08.0004	Failed to obtain AK/SK.
dcs.08.0005	Failed to create bucket.
dcs.08.0006	Failed to obtain backup file size.
dcs.08.0007	Data synchronization failed during instance restoration.
dcs.08.0008	Automatic backup of the instance cannot start because the instance is running other jobs.

Example response

```
{
  "backup_record_response": [
    {
      "status": "succeed",
      "remark": "001",
      "period": null,
      "progress": "100.00",
      "size": 880232,
      "instance_id": "5560df16-cebf-4473-95c4-d1b573c16e79",
      "backup_id": "4631832a-14c6-45b0-a0b3-3abd8f591ad1",
      "created_at": "2019-05-10T08:31:16.166Z",
      "updated_at": "2019-05-10T08:32:30.546Z",
      "execution_at": "2019-05-10T08:31:21.461Z",
      "backup_type": "manual",

      "backup_name": "backup_20190510163116",
      "error_code": null,
      "is_support_restore": "TRUE"
    }
  ],
  "total_num": 1
}
```

Status Code

[Table 5-77](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-77 Status code

Status Code	Description
200	DCS instance backup records queried successfully.

5.5.4 Querying DCS Instance Restoration Records

Function

This API is used to query the restoration records of a specified DCS instance.

URI

GET /v1.0/{project_id}/instances/{instance_id}/restores?
start={start}&limit={limit}&beginTime={beginTime}&endTime={endTime}

[Table 5-78](#) describes the parameters.

Table 5-78 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	DCS instance ID.
start	Integer	No	Start sequence number of the restoration record to be queried. By default, this parameter is set to 1 .
limit	Integer	No	Number of restoration records displayed on each page. The minimum value of this parameter is 1 . If this parameter is not specified, 10 restoration records are displayed on each page by default.
beginTime	String	No	Start time of the period to be queried. Format: yyyyMMddHHmmss, for example, 20170718235959.
endTime	String	No	End time of the period to be queried. Format: yyyyMMddHHmmss, for example, 20170718235959.

Request

Request parameters

None

Example request

```
GET https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/restores?  
start={start}&limit={limit}&beginTime={beginTime}&endTime={endTime}
```

Response

Response parameters

[Table 5-79](#) describes the response parameters.

Table 5-79 Parameter description

Parameter	Type	Description
restore_record_response	Array	Array of the restoration records.
total_num	Integer	Number of obtained backup records.

Table 5-80 restore_record_response parameter description

Parameter	Type	Description
status	String	Restoration status • waiting: DCS instance restoration is waiting to begin. • restoring: DCS instance restoration is in progress. • succeed: DCS instance restoration succeeded. • failed: DCS instance restoration failed.
progress	String	Restoration progress
restore_id	String	ID of the restoration record
backup_id	String	ID of the backup record
restore_remark	String	Description of DCS instance restoration
backup_remark	String	Description of DCS instance backup
created_at	String	Time at which the restoration task is created
updated_at	String	Time at which DCS instance restoration completed
restore_name	String	Name of the restoration record
backup_name	String	Name of the backup record
error_code	String	Error code returned if DCS instance restoration fails. For details about error codes, see Table 5-76 .

Example response

```
{
  "restore_record_response": [
    {
      "status": "succeed",
      "progress": "100.00",
      "restore_id": "a6155972-800c-4170-a479-3231e907d2f6",
      "backup_id": "f4823e9e-fe9b-4ffd-be79-4e5d6de272bb",
      "restore_remark": "doctest",
      "backup_remark": null,
      "created_at": "2017-07-18T21:41:20.721Z",
      "updated_at": "2017-07-18T21:41:35.182Z",
      "restore_name": "restore_20170718214120",
      "backup_name": "backup_20170718000002",
      "sourceInstanceId": "dcb96c22-fd6f-41c0-88b5-544784558dd9",
      "sourceInstanceName": "Test-DCS-MS-3-f79a983f",
      "error_code": null
    }
  ],
  "total_num": 1
}
```

Status Code

[Table 5-81](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-81 Status code

Status Code	Description
200	DCS instance restoration record queried successfully.

5.5.5 Deleting Backup Files

Function

This API is used to delete the files backed up by a DCS instance.

URI

DELETE /v1.0/{project_id}/instances/{instance_id}/backups/{backup_id}

[Table 5-82](#) describes the parameters.

Table 5-82 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	String	Yes	DCS instance ID
backup_id	String	Yes	ID of the backup record

Request

Request parameters

None

Example request

Request URL:

```
DELETE https://{dcs_endpoint}/v1.0/{project_id}/instances/{instance_id}/backups/{backup_id}
```

Response

Response parameters

[Table 5-83](#) describes the response parameters.

Table 5-83 Parameter description

Parameter	Type	Description
message	String	Result of deleting the backup file

Example response

```
{
  "message": ""
}
```

Status Code

[Table 5-84](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-84 Status code

Status Code	Description
200	Backup file deleted successfully.

5.6 Tag Management APIs

5.6.1 Querying All Tags of a Tenant V1

Function

This API is used to query the tags of all resources owned by a tenant in a specified project.

URI

GET /v1.0/{project_id}/dcs/tags

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .

Request

None

Response

When the status code is **200**, the response parameters are as follows.

Parameter	Type	Description
key	String	Tag key, which Contains a maximum of 36 Unicode characters.
values	Array of strings	Tag value, which - Contains a maximum of 43 Unicode characters. - Can be an empty string.

Example response

```
{
  "tags": [
    {
      "key": "001",
      "values": [
        "002"
      ]
    },
    {
      "key": "003",
      "values": [
        "004"
      ]
    }
  ]
}
```

Return Value

Return Value	Description
200	Successfully queried all tags of a tenant.

Error Codes

None

5.6.2 Adding or Deleting Tags in Batches V1

Function

This API is used to add or delete tags in batches for a DCS instance.

URI

POST /v1.0/{project_id}/dcs/{instance_id}/tags/action

Parameter	Man dator y	Type	Description
project_id	Yes	String	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Example

Post https://{dcs_endpoint}/v1.0/{project_id}/dcs/{instance_id}/tags/action

Request

Request parameters

Table 5-85 Request

Parameter	Mandatory	Type	Description
action	Yes	String	Operation to be performed. The value can be create or delete only.
tags	Yes	Array of Objects	List of tags. For details, see Table 5-86 .

Table 5-86 tags parameters

Parameter	Mandatory	Type	Description
key	Yes	String	Tag key, which • Cannot be left blank. • Must be unique. • Can contain a maximum of 36 characters.
value	No	String	Tag value, which • Is mandatory when action is set to create and optional when action is set to delete. • Can contain a maximum of 43 characters.

Example request

```
{
  "action": "create",
  "tags": [
    {
      "key": "dcs001",
      "value": "002"
    },
    {
      "key": "dcs003",
      "value": "004"
    }
  ]
}
```

Response parameters

None

Return Value

Return Value	Description
200	Tags added/deleted successfully.

Error Codes

None

5.6.3 Querying Tag of a Specified Instance V1

Function

This API is used to query the tags of an instance by its instance ID.

URI

GET /v1.0/{project_id}/instances/{instance_id}/tags

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Request

None

Response

When the status code is **200**, the response parameters are as follows.

Table 5-87 Parameter description

Parameter	Type	Description
tags	Array of Objects	List of tags. For details, see Table 5-88 .

Table 5-88 tags parameters

Parameter	Type	Description
key	String	Tag key, which • Cannot be left blank. • Must be unique. • Can contain a maximum of 36 characters.
value	String	Tag value, which • Can contain a maximum of 43 characters. • Can be an empty string.

Example response

When the status code is **200**, the response parameters are as follows.

```
{
  "tags": [
    {
      "key": "001",
      "value": "002"
    },
    {
      "key": "003",
      "value": "004"
    }
  ]
}
```

Return Value

Return Value	Description
200	Instance tags queried successfully.

Error Codes

None

5.7 Other APIs

5.7.1 Querying Service Specifications

Function

This API is used to query the product ID (parameter **product_id**) which indicates the specifications of the DCS service you created.

URI

GET /v1.0/products

Request

Request parameters

None

Example request

None

Response

Response parameters

[Table 5-89](#) describes the response parameters.

Table 5-89 Parameter description

Parameter	Type	Description
products	Array	List of specifications of the DCS service to which you can subscribe.

Table 5-90 products parameter description

Parameter	Type	Description
product_id	String	Product ID used to differentiate DCS specifications.

Parameter	Type	Description
spec_code	String	DCS instance specification code. Options: • dcs.single_node • dcs.master_standby • dcs.cluster • redis.ha.xu1.tiny.r4.512 • redis.ha.xu1.tiny.r2.128 • redis.cluster.xu1.large.r5.4 • redis.ha.xu1.tiny.r4.256 • redis.ha.xu1.tiny.r2.512 • redis.cluster.xu1.large.r1.32 • redis.cluster.xu1.large.r4.768 • redis.ha.xu1.large.r3.2 • redis.single.xu1.large.64 • redis.cluster.xu1.large.r5.8 • redis.ha.xu1.large.r3.32 • redis.cluster.xu1.large.r2.8 • redis.ha.xu1.large.r4.1 • redis.ha.xu1.tiny.r2.256 • redis.cluster.xu1.large.r4.1024 • redis.ha.xu1.large.r5.16 • redis.cluster.xu1.large.r4.32 • redis.ha.xu1.large.r5.24 • redis.ha.xu1.large.r4.64 • redis.cluster.xu1.large.r2.1024 • redis.ha.xu1.large.r2.48 • redis.ha.xu1.large.r2.24 • redis.ha.xu1.large.r5.64 • redis.ha.xu1.tiny.r5.512 • redis.ha.xu1.large.r3.8 • redis.cluster.xu1.large.r1.768 • redis.ha.xu1.large.r3.24 • redis.cluster.xu1.large.r3.512 • redis.ha.xu1.large.r3.1 • redis.cluster.xu1.large.r4.4 • redis.cluster.xu1.large.r1.24 • redis.ha.xu1.large.r4.2 • redis.cluster.xu1.large.r5.192 • redis.single.xu1.large.16 • redis.cluster.xu1.large.r3.1024

Parameter	Type	Description
		- redis.ha.xu1.large.r4.24 - redis.cluster.xu1.large.r2.48 - redis.ha.xu1.large.r2.1 - redis.ha.xu1.large.r3.48 - redis.single.xu1.large.4 - redis.cluster.xu1.large.r4.48 - redis.cluster.xu1.large.r3.768 - redis.ha.xu1.tiny.r4.128 - redis.ha.xu1.large.r5.1 - redis.cluster.xu1.large.r2.96 - redis.cluster.xu1.large.r3.4 - redis.cluster.xu1.large.r1.128 - redis.single.xu1.large.2 - redis.ha.xu1.tiny.r3.128 - redis.cluster.xu1.large.r2.512 - redis.cluster.xu1.large.r3.8 - redis.cluster.xu1.large.r4.128 - redis.cluster.xu1.large.r3.96 - redis.ha.xu1.large.r4.8 - redis.ha.xu1.large.r5.48 - redis.single.xu1.large.8 - redis.cluster.xu1.large.r2.24 - redis.cluster.xu1.large.r1.4 - redis.cluster.xu1.large.r5.32 - redis.cluster.xu1.large.r1.64 - redis.cluster.xu1.large.r4.96 - redis.single.xu1.tiny.256 - redis.cluster.xu1.large.r5.128 - redis.cluster.xu1.large.r2.16 - redis.cluster.xu1.large.r4.8 - redis.cluster.xu1.large.r4.512 - redis.cluster.xu1.large.r1.384 - redis.cluster.xu1.large.r5.768 - redis.cluster.xu1.large.r3.256 - redis.cluster.xu1.large.r1.256 - redis.cluster.xu1.large.r4.64 - redis.cluster.xu1.large.r5.256 - redis.cluster.xu1.large.r4.384 - redis.ha.xu1.tiny.r5.128

Parameter	Type	Description
		- redis.cluster.xu1.large.r3.24 - redis.cluster.xu1.large.r4.192 - redis.cluster.xu1.large.r1.96 - redis.ha.xu1.large.r2.2 - redis.single.xu1.large.24 - redis.ha.xu1.large.r4.4 - redis.cluster.xu1.large.r1.1024 - redis.ha.xu1.large.r2.16 - redis.ha.xu1.large.r4.16 - redis.cluster.xu1.large.r5.96 - redis.cluster.xu1.large.r5.384 - redis.cluster.xu1.large.r3.16 - redis.ha.xu1.large.r3.16 - redis.ha.xu1.large.r4.32 - redis.ha.xu1.tiny.r5.256 - redis.single.xu1.large.32 - redis.ha.xu1.large.r5.2 - redis.cluster.xu1.large.r1.16 - redis.cluster.xu1.large.r2.384 - redis.cluster.xu1.large.r2.192 - redis.cluster.xu1.large.r1.48 - redis.ha.xu1.large.r5.8 - redis.cluster.xu1.large.r5.16 - redis.cluster.xu1.large.r3.128 - redis.ha.xu1.large.r3.4 - redis.cluster.xu1.large.r1.192 - redis.cluster.xu1.large.r3.384 - redis.cluster.xu1.large.r2.4 - redis.ha.xu1.large.r2.4 - redis.single.xu1.tiny.128 - redis.cluster.xu1.large.r1.512 - redis.ha.xu1.large.r2.64 - redis.cluster.xu1.large.r2.128 - redis.cluster.xu1.large.r2.768 - redis.cluster.xu1.large.r5.64 - redis.cluster.xu1.large.r3.48 - redis.single.xu1.tiny.512 - redis.cluster.xu1.large.r5.48 - redis.ha.xu1.large.r4.48

Parameter	Type	Description
		- redis.cluster.xu1.large.r4.24 - redis.ha.xu1.large.r5.4 - redis.ha.xu1.large.r2.8 - redis.ha.xu1.large.r3.64 - redis.cluster.xu1.large.r2.64 - redis.cluster.xu1.large.r2.32 - redis.cluster.xu1.large.r4.16 - redis.cluster.xu1.large.r4.256 - redis.single.xu1.large.1 - redis.cluster.xu1.large.r1.8 - redis.cluster.xu1.large.r3.32 - redis.single.xu1.large.48 - redis.cluster.xu1.large.r5.1024 - redis.cluster.xu1.large.r3.192 - redis.cluster.xu1.large.r2.256 - redis.ha.xu1.tiny.r3.256 - redis.cluster.xu1.large.r5.24 - redis.ha.xu1.tiny.r3.512 - redis.cluster.xu1.large.r5.512 - redis.ha.xu1.large.r5.32 - redis.cluster.xu1.large.r3.64 - redis.ha.xu1.large.r2.32 - redis.ha.xu1.large.p2.16 - redis.ha.xu1.large.p2.32 - redis.ha.xu1.large.p2.64 - redis.ha.xu1.large.p2.8 - redis.ha.xu1.large.p3.16 - redis.ha.xu1.large.p3.32 - redis.ha.xu1.large.p3.64 - redis.ha.xu1.large.p3.8 - redis.ha.xu1.large.p4.16 - redis.ha.xu1.large.p4.32 - redis.ha.xu1.large.p4.64 - redis.ha.xu1.large.p4.8 - redis.ha.xu1.large.p5.16 - redis.ha.xu1.large.p5.32 - redis.ha.xu1.large.p5.64 - redis.ha.xu1.large.p5.8 - redis.ha.xu1.large.p6.16

Parameter	Type	Description
		- redis.ha.xu1.large.p6.32 - redis.ha.xu1.large.p6.64 - redis.ha.xu1.large.p6.8
cache_mode	String	DCS instance type. Options: single: single-node ha: master/standby cluster: Redis Cluster proxy: Proxy Cluster
product_type	String	Edition of DCS for Redis.
cpu_type	String	CPU architecture.
storage_type	String	Storage type.
details	Array of Object	Details of the specifications. Table 5-91 describes the parameters in this array.
engine	String	Cache engine.
engine_versions	String	Cache engine version.
spec_details	String	DCS specifications. The value subjects to the returned specifications.
spec_details2	String	Detailed DCS specifications, including the maximum number of connections and maximum memory size.
charging_type	String	Billing mode. Value: Hourly .
price	Double	Price of the DCS service to which you can subscribe. (This parameter has been abandoned.)
currency	String	Currency.
prod_type	String	Product type. Options: instance and obs_space .
cloud_service_type_code	String	Cloud service type code.
cloud_resource_type_code	String	Cloud resource type code.
flavors	Array	AZs with available resources. Table 5-92 describes the parameters in this array.

Table 5-91 details parameter description

Parameter	Type	Description
capacity	String	Specification (total memory) of the DCS instance.
max_bandwidth	String	Maximum bandwidth supported by the specification.
max_clients	String	Maximum number of clients supported by the specification, which is usually equal to the maximum number of connections.
max_connections	String	Maximum number of connections supported by the specification.
max_in_bandwidth	String	Maximum inbound bandwidth supported by the specification, which is usually equal to the maximum bandwidth.
max_memory	String	Maximum available memory.
tenant_ip_count	String	Number of tenant IP addresses corresponding to the specifications.
sharding_num	String	Number of shards supported by the specifications.
proxy_num	String	Number of proxies supported by Proxy Cluster instances of the specified specifications. If the instance is not a Proxy Cluster instance, the value of this parameter is 0 .
db_number	String	Number of DBs of the specifications.

Table 5-92 flavors parameter description

Parameter	Type	Description
capacity	String	Specification (total memory) of the DCS instance.
unit	String	Capacity unit.
available_zones	Array	AZ ID.

Example response

```
{
  "products": [
    {
      "details": {
        "capacity": 64,
        "max_memory": 64,
        "max_connections": 20000,
```

```
        "max_clients": 80000,
        "max_bandwidth": 2000,
        "max_in_bandwidth": 600,
        "proc_num": 8
    },
    "engine": "redis",
    "price": 0.04,
    "currency": "1",
    "flavors": [
        {
            "capacity": "64",
            "unit": "GB",
            "available_zones": [
                "ae04cf9d61544df3806a3feeb401b204",
                "882f6e449e3245dbb8c1c0fafa494c89"
            ]
        },
        {
            "capacity": "128",
            "unit": "GB",
            "available_zones": [
                "ae04cf9d61544df3806a3feeb401b204",
                "882f6e449e3245dbb8c1c0fafa494c89"
            ]
        },
        {
            "capacity": "256",
            "unit": "GB",
            "available_zones": [
                "ae04cf9d61544df3806a3feeb401b204",
                "882f6e449e3245dbb8c1c0fafa494c89"
            ]
        }
    ],
    "product_id": "00301-30112-0--0",
    "spec_code": "dcs.cluster",
    "cache_mode": "cluster",
    "product_type": "generic",
    "cpu_type": "x86_64",
    "storage_type": "DRAM",
    "engine_versions": "3.0",
    "spec_details": "[{"mem": "64,128,256"}]",
    "spec_details2": "[{"capacity": 64, "max_memory": 64, "max_connections": 20000, "max_clients": 80000, "max_bandwidth": 2000, "max_in_bandwidth": 600, "proc_num": 8}, {"capacity": 128, "max_memory": 128, "max_connections": 20000, "max_clients": 160000, "max_bandwidth": 2000, "max_in_bandwidth": 600, "proc_num": 16}, {"capacity": 256, "max_memory": 256, "max_connections": 20000, "max_clients": 160000, "max_bandwidth": 2000, "max_in_bandwidth": 600, "proc_num": 32}, {"capacity": 512, "max_memory": 512, "max_connections": 20000, "max_clients": 160000, "max_bandwidth": 2000, "max_in_bandwidth": 600, "proc_num": 64}, {"capacity": 1024, "max_memory": 1024, "max_connections": 20000, "max_clients": 160000, "max_bandwidth": 2000, "max_in_bandwidth": 600, "proc_num": 128}]",
    "charging_type": "Hourly",
    "prod_type": "instance",
    "cloud_service_type_code": "XXXX",
    "cloud_resource_type_code": "XXXX"
    },
}
```

Status Code

Table 5-93 describes the status code of successful operations. For details about other status codes, see **Table 7-1**.

Table 5-93 Status code

Status Code	Description
200	Service specifications queried successfully.

5.7.2 Querying the Quota of a Tenant

Function

This API is used to query the default instance quota and total memory quota of a tenant and the maximum and minimum quotas a tenant can apply for. Different tenants have different quotas in different regions.

URI

GET /v1.0/{project_id}/quota

[Table 5-94](#) describes the parameter.

Table 5-94 Parameter description

Parameter	Type	Mandatory	Description
project_id	String	Yes	Project ID. For details on how to obtain the value of this parameter, see Obtaining a Project ID .

Request

Request parameters

None

Example request

None

Response

Response parameters

[Table 5-95](#) describes the response parameters.

Table 5-95 Parameter description

Parameter	Type	Mandatory	Description
quotas	Object	Yes	Quota information. For details, see Table 5-96 .

Table 5-96 quotas parameter description

Parameter	Type	Mandatory	Description
resources	Array	Yes	List of quotas. For details, see Table 5-97 .
resource_user	Object	Yes	Information about a resource tenant For details, see Table 5-98 .

Table 5-97 resources parameter description

Parameter	Type	Description
quota	Integer	Maximum number of instances that can be created and maximum allowed total memory.
used	Integer	Number of created instances and used memory.
type	String	Values: instances: indicates the instance quota. ram: indicates the memory quota.
unit	String	Resource unit. - When type is set to instance, no value is returned. - When type is set to ram, GB is returned.
max	Integer	- Indicates the maximum limit of instance quota when type is set to instance. - Indicates the maximum limit of memory quota when type is set to ram.

Parameter	Type	Description
min	Integer	- Indicates the minimum limit of instance quota when type is set to instance. - Indicates the minimum limit of memory quota when type is set to ram.

Table 5-98 resource_user parameter description

Parameter	Type	Description
tenant_id	String	Resource tenant ID
tenant_name	String	Resource tenant name

Example response

```
{
  "quotas": {
    "resources": [
      {
        "quota": 10,
        "used": 3,
        "type": "instance",
        "min": 1,
        "max": 10,
        "unit": null
      },
      {
        "quota": 800,
        "used": 22,
        "type": "ram",
        "min": 1,
        "max": 800,
        "unit": "GB"
      }
    ],
    "resource_user": {
      "tenant_id": "836152f9838a44089f40f3cf6fd432bf",
      "tenant_name": "op_svc_dcs_003"
    }
  }
}
```

Status Code

Table 5-99 describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-99 Status code

Status Code	Description
200	Tenant quota queried successfully.

5.7.3 Querying Maintenance Time Window

Function

The API is used to query the start time and end time of the maintenance time window.

URI

GET /v1.0/instances/maintain-windows

Request

Request parameters

None

Example request

None

Response

Response parameters

[Table 5-100](#) describes the response parameters.

Table 5-100 Parameter description

Parameter	Type	Description
maintain_windows	Array	List of supported maintenance time windows.

Table 5-101 maintain_windows parameter description

Parameter	Type	Description
seq	Integer	Sequence number of the maintenance time window.
begin	String	Start time of the maintenance time window.

Parameter	Type	Description
end	String	End time of the maintenance time window.
default	Boolean	An indicator of whether the maintenance time window is set to the default time segment.

Example response

```
{
  "maintain_windows": [
    {
      "seq": 1,
      "begin": "22",
      "end": "02",
      "default": false
    },
    {
      "seq": 2,
      "begin": "02",
      "end": "06",
      "default": true
    },
    {
      "seq": 3,
      "begin": "06",
      "end": "10",
      "default": false
    },
    {
      "seq": 4,
      "begin": "10",
      "end": "14",
      "default": false
    },
    {
      "seq": 5,
      "begin": "14",
      "end": "18",
      "default": false
    },
    {
      "seq": 6,
      "begin": "18",
      "end": "22",
      "default": false
    }
  ]
}
```

Status Code

[Table 5-102](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-102 Status code

Status Code	Description
200	Successfully queried the maintenance time window.

5.7.4 Querying AZ Information

Function

This API is used to query the ID of the AZ where a DCS instance resides.

URI

GET /v1.0/availableZones

Request

Request parameters

None

Example request

None

Response

Response parameters

[Table 5-103](#) describes the response parameters.

Table 5-103 Parameter description

Parameter	Type	Description
region_id	String	Region ID.
available_zones	Array	Array of AZs. For details, see Table 5-104 .

Table 5-104 Parameter description of the available_zones array

Parameter	Type	Description
id	String	AZ ID.
code	String	AZ code.
name	String	AZ name.

Parameter	Type	Description
port	String	Port number of the AZ.
resource_availability	String	An indicator of whether there are available resources in the AZ. • true: There are available resources in the AZ. • false: There are no available resources in the AZ.

Example response

```
{
  "regionId": "XXXXXX",
  "available_zones": [
    {
      "id": "f84448fd537f46078dd8bd776747f573",
      "code": "XXXXXX",
      "name": "XXXXXX",
      "port": "8003",
      "resource_availability": "true"
    },
    {
      "id": "12c47a78666b4e438cd0c692b9860387",
      "code": "XXXXXX",
      "name": "XXXXXX",
      "port": "8002",
      "resource_availability": "true"
    },
    {
      "id": "0725858e0d26434f9aa3dc5fc40d5697",
      "code": "XXXXXX",
      "name": "XXXXXX",
      "port": "8009",
      "resource_availability": "true"
    }
  ]
}
```

Status Code

[Table 5-105](#) describes the status code of successful operations. For details about other status codes, see [Table 7-1](#).

Table 5-105 Status code

Status Code	Description
200	AZ information queried successfully.

6 Permissions and Supported Actions

This chapter describes fine-grained permissions management for your DCS. If your account does not need individual IAM users, you can skip the configurations described in this chapter.

By default, new IAM users do not have any permissions assigned. You need to add a user to one or more groups, and assign policies or roles to these groups. The user then inherits permissions from the groups it is a member of. This process is called authorization. After authorization, the user can perform specified operations on cloud services based on the permissions.

You can grant users permissions by using roles and policies. Roles are a type of coarse-grained authorization mechanism that defines permissions related to user responsibilities. Policies define API-based permissions for operations on specific resources under certain conditions, allowing for more fine-grained, secure access control of cloud resources.

NOTE

You can use policies to allow or deny access to specific APIs.

An account has all of the permissions required to call all APIs, but IAM users must have the required permissions specifically assigned. The permissions required for calling an API are determined by the actions supported by the API. Only users who have been granted permissions allowing the actions can call the API successfully. For example, if an IAM user wants to query ECSs using an API, the user must have been granted permissions that allow the **dc:servers:list** action.

Supported Actions

DCS provides system-defined policies, which can be directly used in IAM. You can also create custom policies to supplement system-defined policies for more refined access control. Actions supported by policies are specific to APIs. Common concepts related to policies include:

- Permissions: Allow or deny certain operations.
- APIs: REST APIs that can be called in a custom policy.
- Actions: Added to a custom policy to control permissions for specific operations.

- Dependent actions: When assigning permissions for an action, you also need to assign permissions for the dependent actions.
- IAM and enterprise projects: Type of projects for which an action will take effect. Policies that contain actions supporting both IAM and enterprise projects can be assigned to user groups and take effect in both IAM and Enterprise Management. Policies that only contain actions supporting IAM projects can be assigned to user groups and only take effect for IAM. Such policies will not take effect if they are assigned to user groups in Enterprise Project. Administrators can check whether an action supports IAM projects or enterprise projects in the action list. The check mark (√) indicates that the action supports the project and the cross symbol (×) indicates that the action does not support the project.

The following table lists the API actions supported by DCS.

Table 6-1 DCS actions

Permissions	Action	API	IAM Project	Enterprise Project
Creating DCS instances	dcs:instance:create	POST /v1.0/{project_id}/instances	√	√
Querying an instance	dcs:instance:get	GET /v1.0/{project_id}/instances/{instance_id}	√	√
Modifying the information about an instance	dcs:instance:modify	PUT /v1.0/{project_id}/instances/{instance_id}	√	√
Deleting an instance	dcs:instance:delete	DELETE /v1.0/{project_id}/instances/{instance_id}	√	√
Expanding instance capacity	dcs:instance:scale	POST /v1.0/{project_id}/instances/{instance_id}/extend	√	√
Querying all instances	dcs:instance:list	GET /v1.0/{project_id}/instances	√	√
Querying instance configuration parameters	dcs:instance:getConf igation	GET /v1.0/{project_id}/instances/{instance_id}/configs	√	√
Modifying instance configuration parameters	dcs:instance:modify Configuration	PUT /v1.0/{project_id}/instances/{instance_id}/configs	√	√

Permissions	Action	API	IA M Pro ject	Ent erp ris e Pro jec t
Restarting an instance or clearing instance data	dc:instance:modifyStatus	PUT /v1.0/{project_id}/instances/status	√	√
Changing the instance password	dc:instance:modifyAuthInfo	PUT /v1.0/{project_id}/instances/{instance_id}/password	√	√
Backing up an instance	dc:instance:backupData	POST /v1.0/{project_id}/instances/{instance_id}/backups	√	√
Restoring an instance	dc:instance:restoreData	POST /v1.0/{project_id}/instances/{instance_id}/restores	√	√
Querying backup records	dc:instance:getDataBackupLog	GET /v1.0/{project_id}/instances/{instance_id}/backups	√	√
Querying restoration records	dc:instance:getDataRestoreLog	GET /v1.0/{project_id}/instances/{instance_id}/restores	√	√
Deleting backup files	dc:instance:deleteDataBackupFile	DELETE /v1.0/{project_id}/instances/{instance_id}/backups/{backup_id}	√	√
Listing background tasks	dc:instance:getBackgroundTask	GET /v1.0/{project_id}/instances/{instance_id}/tasks	√	√
Deleting a background task	dc:instance:deleteBackgroundTask	DELETE /v1.0/{project_id}/instances/{instance_id}/tasks/{task_id}	√	√
Resetting the instance password	dc:instance:resetAuthInfo	-	√	√
Downloading backup files	dc:instance:downloadBackupData	-	√	√
Migrating data	dc:instance:migrateData	-	√	√
Web CLI	dc:instance:webcli	-	√	√

Permissions	Action	API	IAM Project	Enterprise Project
Creating a migration task	dcsmigrationTask:create	POST /v2/{project_id}/migration-task	✓	X
Modifying migration task configurations or stopping a migration task	dcsmigrationTask:modify	-	✓	X
Deleting a migration task	dcsmigrationTask:delete	-	✓	X
Listing migration tasks	dcsmigrationTask:list	-	✓	X
Querying details of a data migration task	dcsmigrationTask:get	-	✓	X
Diagnosing an instance	dcsinstance:diagnosis	-	✓	✓
Viewing parameter templates	dcstemplate:list	-	✓	X
Creating a parameter template	dcstemplate:create	-	✓	X
Performing a master/standby switchover	dcsinstance:swap	-	✓	✓
Modifying the whitelist of an instance	dcswitelist:modify	-	✓	✓
Obtaining the whitelist of an instance	dcswitelist:list	-	✓	✓

Permissions	Action	API	IA M Pro ject	Ent erp ris e Pro jec t
Creating a user for accessing an instance	dc:aclaccount:create	-	√	√
Deleting an instance user	dc:aclaccount:delete	-	√	√
Modifying the information about an instance user	dc:aclaccount:modify	-	√	√
Obtaining the list of instance users	dc:aclaccount:list	-	√	√
Querying slow logs	dc:slowlog:list	-	√	√
Viewing parameter templates	dc:template:get	-	√	X
Viewing the task progress	dc:job:get	-	√	√
Viewing audit logs	dc:auditlog:get	-	√	√
Querying instance upgrade information	dc:instance:getUpgradeInfo	-	√	√
Querying SSL encryption of an instance	dc:ssl:get	-	√	√
Updating domain names	dc:domainname:rebuild	-	√	√
Switching IP addresses	dc:migrationTask:exchangeIp	-	√	X
Rolling back IP address switching	dc:migrationTask:rollbackIp	-	√	X

Permissions	Action	API	IA M Pro ject	Ent erp ris e Pro jec t
Killing Redis sessions	dcsc:clients:kill	-	✓	✓
Modifying a parameter template	dcsc:template:modify	-	✓	X
Enabling or disabling public domain name resolution	dcsc:publicdomainname:update	-	✓	✓
Deleting a parameter template	dcsc:template:delete	-	✓	X
Releasing historical domain names	dcsc:histroyd domainname:release	-	✓	✓
Upgrading the instance version	dcsc:instance:upgrade	-	✓	✓
Analyzing big or hot keys	dcsc:instance:analyze	-	✓	✓
Enabling or disabling audit logging	dcsc:auditlog:modify	-	✓	✓
Enabling or disabling client IP pass-through	dcsc:clientiptrans:modify	-	✓	✓
Modifying SSL encryption for an instance	dcsc:ssl:modify	-	✓	✓
Querying the Redis session list	dcsc:clients:list	-	✓	✓

7 Appendix

7.1 Status Codes

Table 7-1 describes the status codes.

Table 7-1 Status codes

Status Code	Name	Description
100	Continue	The server has received the initial part of the request and the client should continue to send the remaining part. This provisional response informs the client that part of the request has been received and has not yet been rejected by the server.
101	Switching Protocols	The requester has asked the server to switch protocols and the server has agreed to do so. The target protocol must be more advanced than the source protocol. For example, the current HTTP protocol is switched to a later version of HTTP.
201	Created	The request has been fulfilled, resulting in the creation of a new resource.
202	Accepted	The request has been accepted for processing, but the processing has not been completed.
203	Non-Authoritative Information	The server successfully processed the request, but is returning information that may be from another source.

Status Code	Name	Description
204	NoContent	The server has successfully processed the request, but does not return any content. The status code is returned in response to an HTTP OPTIONS request.
205	Reset Content	The server successfully processed the request, but is not returning any content.
206	Partial Content	The server has successfully processed a part of the GET request.
300	Multiple Choices	There are multiple options for the requested resource. For example, this code could be used to present a list of resource characteristics and addresses from which the client such as a browser may choose.
301	Moved Permanently	This and all future requests should be permanently directed to the given URI indicated in this response.
302	Found	The requested resource was temporarily moved.
303	See Other	The response to the request can be found under a different URI, and should be retrieved using a GET or POST method.
304	Not Modified	The requested resource has not been modified. In such case, there is no need to retransmit the resource since the client still has a previously downloaded copy.
305	Use Proxy	The requested resource is available only through a proxy.
306	Unused	This HTTP status code is no longer used.
400	BadRequest	The request is invalid. The client should modify the request instead of re-initiating it.
401	Unauthorized	The authentication information is incorrect or invalid.
402	Payment Required	Reserved for future use.
403	Forbidden	The request is rejected. The server has received the request and understood it, but the server is refusing to respond to it. The client should not repeat the request without modifications.

Status Code	Name	Description
404	NotFound	The requested resource could not be found. The client should modify the request instead of re-initiating it.
405	MethodNotAllowed	A request method is not supported for the requested resource. The client should modify the request instead of re-initiating it.
406	Not Acceptable	The server could not fulfil the request according to the content characteristics of the request.
407	Proxy Authentication Required	This code is similar to 401, but indicates that the client must first authenticate itself with the proxy.
408	Request Time-out	The server timed out waiting for the request. The client may re-initiate the request without modifications at any later time.
409	Conflict	The request cannot be processed due to a conflict. This status code indicates that the resource that the client attempts to create already exists, or the request fails to be processed because of the update of the conflict request.
410	Gone	The requested resource is no longer available. The requested resource has been deleted permanently.
411	Length Required	The server refused to process the request because the request does not specify the length of its content.
412	Precondition Failed	The server does not meet one of the preconditions that the requester puts on the request.
413	Request Entity Too Large	The request is larger than the server is willing or able to process. The server may close the connection to prevent the client from continuing the request. If the server temporarily cannot process the request, the response will contain a Retry-After header field.
414	Request-URI Too Large	The URI provided was too long for the server to process.
415	Unsupported Media Type	The server does not support the media type in the request.

Status Code	Name	Description
416	Requested range not satisfiable	The requested range is invalid.
417	Expectation Failed	The server fails to meet the requirements of the Expect request-header field.
422	UnprocessableEntity	The request was well-formed but was unable to be followed due to semantic errors.
429	TooManyRequests	The client has sent more requests than its rate limit is allowed within a given amount of time, or the server has received more requests than it is able to process within a given amount of time. In this case, it is advisable for the client to re-initiate requests after the time specified in the Retry-After header of the response expires.
500	InternalServerError	The server is able to receive the request, but it could not understand the request.
501	Not Implemented	The server does not support the requested function.
502	Bad Gateway	The server was acting as a gateway or proxy and received an invalid request from a remote server.
503	ServiceUnavailable	The requested service is invalid. It is advisable for the client to modify the request instead of re-initiating the request.
504	ServerTimeout	The server could not return a timely response. The response will reach the client only if the request carries a timeout parameter.
505	HTTP Version not supported	The server does not support the HTTP protocol version used in the request.

7.2 Error Codes

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.3053	Incorrect node ID.	Incorrect node ID.	Check whether the Node ID is valid.
400	DCS.4202	ssl request params are invalid.	ssl request params are invalid.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4933	The param available_zones is invalid.	Check available_zones are valid.	Check whether the request parameters are valid.
400	DCS.5050	Shared VPCs are not supported.	Not Supported shared vpc.	Check whether the request parameters are valid.
400	111400002	Invalid project ID format.	Invalid project ID format.	Check whether the project ID is valid.
400	111400004	Empty request body.	Empty request body.	Check whether mandatory parameters in the request are set.
400	111400005	The message body contains invalid characters or is not in JSON format.	The message body contains invalid characters or is not in JSON format.	Check whether the request parameters are valid.
400	111400007	The selected cache engine type is not supported.	The selected cache engine type is not supported.	Check whether the request parameters are valid.
400	111400008	The selected cache engine version is not supported.	The selected cache engine version is not supported.	Check whether the request parameters are valid.
400	111400009	Invalid product ID in the request.	Invalid product ID in the request.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	111400010	Invalid DCS instance name. The name must be 4 to 64 characters in length. Only letters (case-insensitive), digits, underscores (_), and hyphens (-) are allowed.	Invalid instance name. The name can contain 4 to 64 characters. Only letters, digits, underscores (_), and hyphens (-) are allowed.	Check whether the request parameters are valid.
400	111400011	DCS instance description cannot exceed 1024 characters.	DCS instance description cannot exceed 1024 characters.	Check whether the request parameters are valid.
400	111400012	Invalid capacity parameter in the request.	Invalid capacity parameter in the request.	Check whether the request parameters are valid.
400	111400013	Invalid vpc_id in the request.	Invalid vpc_id in the request.	Check whether the request parameters are valid.
400	111400014	Invalid security_group_id in the request.	Invalid security_group_id in the request.	Check whether the request parameters are valid.
400	111400016	Invalid subnet_id in the request.	Invalid subnet_id in the request.	Check whether the request parameters are valid.
400	111400017	This DCS instance job task is still running.	This DCS instance job task is still running.	Try again later.
400	111400018	This subnet must exist in the VPC.	This subnet must exist in the VPC.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	111400019	The password does not meet complexity requirements.	The password does not meet complexity requirements.	Check whether the request parameters are valid.
400	111400020	DHCP must be enabled for this subnet.	DHCP must be enabled for this subnet.	Check whether DHCP has been enabled.
400	111400021	The isAutoRenew parameter in the request must be either 0 or 1.	The isAutoRenew parameter in the request must be either 0 or 1.	Check whether the request parameters are valid.
400	111400022	Engine does not match the product id.	The cache engine does not match the product ID.	Check whether the request parameters are valid.
400	111400026	This operation is not allowed when the DCS instance is in the current state.	This operation is not allowed when the DCS instance is in the current state.	Try again later or contact technical support.
400	111400027	This operation is not supported on this node.	This operation is not supported on this node.	Try again later or contact technical support.
400	111400035	DCS instance quota of the tenant is insufficient.	DCS instance quota of the tenant is insufficient.	Contact technical support.
400	111400036	Memory quota of the tenant is insufficient.	Memory quota of the tenant is insufficient.	Contact technical support.

Status Code	Error Codes	Error Message	Description	Solution
400	111400037	The instanceParams parameter in the request contains invalid characters or is not in JSON format.	The instanceParams parameter in the request contains invalid characters or is not in JSON format.	Check whether the request parameters are valid.
400	111400038	The periodNum parameter in the request must be an integer.	The periodNum parameter in the request must be an integer.	Check whether the request parameters are valid.
400	111400039	The quota limit has been reached.	The quota limit has been reached.	Check whether the request parameters are valid.
400	111400042	This AZ does not exist.	This AZ does not exist.	Check whether the request parameters are valid.
400	111400045	This DCS instance is already unfrozen.	This DCS instance is already unfrozen.	Check whether the request parameters are valid.
400	111400046	This security group does not exist.	This security group does not exist.	Check whether the request parameters are valid.
400	111400047	The periodType parameter in the request must be either 2 or 3.	The periodType parameter in the request must be either 2 or 3.	Check whether the request parameters are valid.
400	111400048	The security group must have both outbound and inbound rules with protocols set to ANY.	The security group must have both outbound and inbound rules with protocols set to ANY.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	111400053	the upgrade instance version equals to current version.	The targetVersion parameter in the request cannot be the same as the source version.	Check whether the request parameters are valid.
400	111400054	the selected available zone quota not enough.	DCS resources in the selected AZ have been sold out.	Select another AZ or contact technical support.
400	111400060	This DCS instance name already exists.	This DCS instance name already exists.	Check whether the request parameters are valid.
400	111400061	Invalid instance ID format.	Invalid instance ID format.	Check whether the request parameters are valid.
400	111400062	Invalid {0} parameter in the request.	Invalid {0} parameter in the request.	Check whether the request parameters are valid.
400	111400063	Invalid {0} parameter in the request.	Invalid {0} parameter in the request.	Check whether the request parameters are valid.
400	111400064	The action parameter in the request must be start, stop, or restart.	The action parameter in the request must be start, stop, or restart.	Check whether the request parameters are valid.
400	111400065	The instances parameter in the request cannot be a null value or left unspecified.	The instances parameter in the request cannot be a null value or left unspecified.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	111400066	Invalid value of the configure parameter {0}.	Invalid value of the configure parameter {0}.	Check whether the request parameters are valid.
400	111400067	The available_zones parameter in the request must an array that contains only one AZ ID.	The available_zones parameter in the request must an array that contains only one AZ ID.	Check whether the request parameters are valid.
400	111400068	This VPC does not exist.	This VPC does not exist.	Check whether the request parameters are valid.
400	111400070	Invalid task ID format.	Invalid task ID format.	Check whether the request parameters are valid.
400	111400072	Invalid saveDays instance backup policy parameter in the request.	Invalid saveDays instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	111400073	Invalid backupType instance backup policy parameter in the request.	Invalid backupType instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	111400074	Invalid periodType instance backup policy parameter in the request.	Invalid periodType instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	111400075	Invalid backupAt instance backup policy parameter in the request.	Invalid backupAt instance backup policy parameter in the request.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	111400076	Invalid beginAt instance backup policy parameter in the request.	Invalid beginAt instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	111400080	Instance password verify failed.	Instance password verify failed.	Check whether the request parameters are valid.
400	111400086	only master standby instance is support this action	This operation is allowed only for master/standby instances.	Operation not allowed.
400	111400087	the backup record status is err when restore this instance	The restoration operation is allowed only when the backup task succeeded.	Try again later or contact technical support.
400	111400094	the system is not support dcs job.	The system does not support the background task function.	Operation not allowed.
400	111400095	the system is not support backup and restore.	The system does not support the backup and restoration function.	Operation not allowed.
400	111400096	the instance is backuping.	Backing up the instance. Please try again later.	Try again later.
400	111400097	the instance is restoring.	Restoring the instance. Please try again later.	Try again later.

Status Code	Error Codes	Error Message	Description	Solution
400	111400098	The value of the remark parameter must be 0 to 128 characters in length.	The value of the remark parameter must be 0 to 128 characters in length.	Check whether the request parameters are valid.
400	111400099	DCS instances in the Creating, Starting, Stopping, or Restarting state cannot be deleted.	DCS instances in the Creating, Starting, Stopping, or Restarting state cannot be deleted.	Try again later.
400	111400100	The number of instance IDs in an instances array cannot exceed 50.	The number of instance IDs in an instances array cannot exceed 50.	Check whether the request parameters are valid.
400	111400102	The system is not support resize.	Scale-up is not supported.	Operation not allowed.
400	111400103	The system is not support resize.	The capacity to which the instance is scaled up must be greater than the original capacity.	Check whether the request parameters are valid.
400	111400104	The DCS instance is recovering from an internal fault. Please try again later or contact customer service.	The DCS instance is recovering from an internal fault. Please try again later or contact customer service.	Try again later or contact technical support.

Status Code	Error Codes	Error Message	Description	Solution
400	111400105	The value of reserved-memory cannot be greater than the free memory size of this DCS instance.	The value of reserved-memory cannot be greater than the free memory size of this DCS instance.	Check whether the request parameters are valid.
400	111400106	The value of maintain time illegal.	Invalid maintenance time window.	Check whether the request parameters are valid.
400	111400107	The instance exists for unpaid scale up orders. Please process non payment orders first.	This instance has unpaid scale-up orders. Please process the orders before continuing.	Process unpaid orders before continuing.
400	111400108	The Instance exists for processing scale up order. Please try again later.	Scaling up the instance. Please try again later.	Try again later or contact technical support.
400	111400111	the instance is restarting.	Restarting the instance. Please try again later.	Try again later or contact technical support.
400	111400113	the instance is extending.	Scaling up the instance. Please try again later.	Try again later or contact technical support.
400	111400114	the instance is configuring.	Modifying instance configuration. Please try again later.	Try again later or contact technical support.
400	111400115	the instance is changing the password.	The password is being changed. Try again later.	Try again later or contact technical support.

Status Code	Error Codes	Error Message	Description	Solution
400	111400116	the instance is upgrading.	Upgrading the instance. Please try again later.	Try again later or contact technical support.
400	111400117	the instance is rollbacking the version.	Rolling back the instance. Please try again later.	Try again later or contact technical support.
400	111400118	the instance is creating.	Creating the instance. Please try again later.	Try again later or contact technical support.
400	111400119	Query Bill Sample failed	The instance does not exist.	Check whether the request parameters are valid.
400	111400120	the instance is Freezing.	Freezing the instance. Please try again later.	Try again later or contact technical support.
400	111400800	Invalid {0} in the request.	Invalid {0} in the request.	Check whether the request parameters are valid.
400	111400843	The no_password_access parameter is missing or its value is invalid.	The no_password_access parameter is missing or its value is invalid.	Check whether the request parameters are valid.
400	111400844	The access_user parameter is missing or its value is invalid.	The access_user parameter is missing or its value is invalid.	Check whether the request parameters are valid.
400	111400845	The password parameter is missing or its value is invalid.	The password parameter is missing or its value is invalid.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	111400849	The request parameter new_password should not exist.	The request parameter new_password should not exist.	Check whether the request parameters are valid.
400	111400850	This operation is not supported when Password-Free Access is enabled for the instance.	This operation is not supported when Password-Free Access is enabled for the instance.	Reset the instance password.
400	DCS. 4855	Master standby swap is not supported.	Master/standby switchover is not supported.	Operation not allowed.
400	DCS.4002	Invalid project ID format.	Invalid project ID format.	Check whether the request parameters are valid.
400	DCS.4004	Empty request body.	Empty request body.	Check whether the request parameters are valid.
400	DCS.4005	The message body contains invalid characters or is not in JSON format.	The message body contains invalid characters or is not in JSON format.	Check whether the request parameters are valid.
400	DCS.4006	The selected cache engine type is not supported.	The selected cache engine type is not supported.	Check whether the request parameters are valid.
400	DCS.4007	Instance type is not supported.	Instance type is not supported.	Check whether the request parameters are valid.
400	DCS.4008	The selected cache engine version is not supported.	The selected cache engine version is not supported.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4009	Invalid product ID in the request.	Invalid product ID in the request.	Check whether the request parameters are valid.
400	DCS.4010	Invalid DCS instance name. The name must be 4 to 64 characters in length. Only letters (case-insensitive), digits, underscores (_), and hyphens (-) are allowed.	Invalid DCS instance name. The name must be 4 to 64 characters in length. Only letters (case-insensitive), digits, underscores (_), and hyphens (-) are allowed.	Check whether the request parameters are valid.
400	DCS.4011	DCS instance description cannot exceed 1024 characters.	DCS instance description cannot exceed 1024 characters.	Check whether the request parameters are valid.
400	DCS.4012	Invalid capacity parameter in the request.	Invalid capacity parameter in the request.	Check whether the request parameters are valid.
400	DCS.4013	Invalid vpc_id in the request.	Invalid vpc_id in the request.	Check whether the request parameters are valid.
400	DCS.4014	Invalid security_group_id in the request.	Invalid security_group_id in the request.	Check whether the request parameters are valid.
400	DCS.4016	Invalid subnet_id in the request.	Invalid subnet_id in the request.	Check whether the request parameters are valid.
400	DCS.4017	This DCS instance job task is still running.	This DCS instance job task is still running.	Try again later.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4018	This subnet must exist in the VPC.	This subnet must exist in the VPC.	Check whether the request parameters are valid.
400	DCS.4019	The password does not meet complexity requirements.	The password does not meet complexity requirements.	Check whether the request parameters are valid.
400	DCS.4020	DHCP must be enabled for this subnet.	DHCP must be enabled for this subnet.	Check whether DHCP has been enabled.
400	DCS.4021	The isAutoRenew parameter in the request must be either 0 or 1.	The isAutoRenew parameter in the request must be either 0 or 1.	Check whether the request parameters are valid.
400	DCS.4022	Engine does not match the product id.	The cache engine does not match the product ID.	Check whether the request parameters are valid.
400	DCS.4025	The end time must be after the start time.	The end time must be after the start time.	Check whether the request parameters are valid.
400	DCS.4026	This operation is not allowed when the DCS instance is in the current state.	This operation is not allowed when the DCS instance is in the current state.	Try again later or contact technical support.
400	DCS.4027	This operation is not supported on this node.	This operation is not supported on this node.	Try again later or contact technical support.
400	DCS.4028	The diagnosis time range is max 10 minutes.	The diagnosis time range is max 10 minutes.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4030	The start time must be within the last seven days.	The start time must be within the last seven days.	Check whether the request parameters are valid.
400	DCS.4031	The start time must be before than the current server time.	The start time must be before than the current server time.	Check whether the request parameters are valid.
400	DCS.4033	The start time must be after the instance start time.	The start time must be after the instance start time.	Check whether the request parameters are valid.
400	DCS.4035	DCS instance quota of the tenant is insufficient.	DCS instance quota of the tenant is insufficient.	Contact technical support.
400	DCS.4036	Memory quota of the tenant is insufficient.	Memory quota of the tenant is insufficient.	Contact technical support.
400	DCS.4037	The instanceParams parameter in the request contains invalid characters or is not in JSON format.	The instanceParams parameter in the request contains invalid characters or is not in JSON format.	Check whether the request parameters are valid.
400	DCS.4038	The periodNum parameter in the request must be an integer.	The periodNum parameter in the request must be an integer.	Check whether the request parameters are valid.
400	DCS.4039	The quota limit has been reached.	The quota limit has been reached.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4042	This AZ does not exist.	This AZ does not exist.	Check whether the request parameters are valid.
400	DCS.4045	This DCS instance is already unfrozen.	This DCS instance is already unfrozen.	Try again later or contact technical support.
400	DCS.4046	This security group does not exist.	This security group does not exist.	Check whether the request parameters are valid.
400	DCS.4047	The periodType parameter in the request must be either 2 or 3.	The periodType parameter in the request must be either 2 or 3.	Check whether the request parameters are valid.
400	DCS.4048	The security group must have both outbound and inbound rules with protocols set to ANY.	The security group must have both outbound and inbound rules with protocols set to ANY.	Check whether the request parameters are valid.
400	DCS.4049	The instance status is not running.	The instance status is not running.	Contact technical support.
400	DCS.4053	the upgrade instance version equals to current version.	The targetVersion parameter in the request cannot be the same as the source version.	Check whether the request parameters are valid.
400	DCS.4054	the selected available zone quota not enough.	DCS resources in the selected AZ have been sold out.	Select another AZ or contact technical support.
400	DCS.4060	This DCS instance name already exists.	This DCS instance name already exists.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4061	Invalid instance ID format.	Invalid instance ID format.	Check whether the request parameters are valid.
400	DCS.4062	Invalid {0} parameter in the request.	Invalid {0} parameter in the request.	Check whether the request parameters are valid.
400	DCS.4063	Invalid {0} parameter in the request.	Invalid {0} parameter in the request.	Check whether the request parameters are valid.
400	DCS.4064	The action parameter in the request must be start, stop, or restart.	The action parameter in the request must be start, stop, or restart.	Check whether the request parameters are valid.
400	DCS.4065	The instances parameter in the request cannot be a null value or left unspecified.	The instances parameter in the request cannot be a null value or left unspecified.	Check whether the request parameters are valid.
400	DCS.4066	Invalid value of the configure parameter {0}.	Invalid value of the configure parameter {0}.	Check whether the request parameters are valid.
400	DCS.4067	The available_zones parameter in the request must an array that contains only one AZ ID.	The available_zones parameter in the request must an array that contains only one AZ ID.	Check whether the request parameters are valid.
400	DCS.4068	This VPC does not exist.	This VPC does not exist.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4070	Invalid task ID format.	Invalid task ID format.	Check whether the request parameters are valid.
400	DCS.4072	Invalid saveDays instance backup policy parameter in the request.	Invalid saveDays instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	DCS.4073	Invalid backupType instance backup policy parameter in the request.	Invalid backupType instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	DCS.4074	Invalid periodType instance backup policy parameter in the request.	Invalid periodType instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	DCS.4075	Invalid backupAt instance backup policy parameter in the request.	Invalid backupAt instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	DCS.4076	Invalid beginAt instance backup policy parameter in the request.	Invalid beginAt instance backup policy parameter in the request.	Check whether the request parameters are valid.
400	DCS.4080	Instance password verify failed.	Instance password verify failed.	Check whether the request parameters are valid.
400	DCS.4086	only master standby instance is support this action	This operation is allowed only for master/standby instances.	Operation not allowed.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4087	the backup record status is err when restore this instance	The restoration operation is allowed only when the backup task succeeded.	Try again later or contact technical support.
400	DCS.4094	the system is not support dcs job.	The system does not support the background task function.	Operation not allowed.
400	DCS.4095	the system is not support backup and restore.	The system does not support the backup and restoration function.	Operation not allowed.
400	DCS.4096	the instance is backuping.	Backing up the instance. Please try again later.	Try again later or contact technical support.
400	DCS.4097	the instance is restoring.	Restoring the instance. Please try again later.	Try again later or contact technical support.
400	DCS.4098	The value of the remark parameter must be 0 to 128 characters in length.	The value of the remark parameter must be 0 to 128 characters in length.	Check whether the request parameters are valid.
400	DCS.4099	DCS instances in the Creating, Starting, Stopping, or Restarting state cannot be deleted.	DCS instances in the Creating, Starting, Stopping, or Restarting state cannot be deleted.	Try again later.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4100	The number of instance IDs in an instances array cannot exceed 50.	The number of instance IDs in an instances array cannot exceed 50.	Check whether the request parameters are valid.
400	DCS.4102	The system is not support resize.	The system is not support resize.	Operation not allowed.
400	DCS.4103	The system is not support resize.	The system is not support resize.	Check whether the request parameters are valid.
400	DCS.4104	The DCS instance is recovering from an internal fault. Please try again later or contact customer service.	The DCS instance is recovering from an internal fault. Please try again later or contact customer service.	Try again later or contact technical support.
400	DCS.4105	The value of reserved-memory cannot be greater than the free memory size of this DCS instance.	The value of reserved-memory cannot be greater than the free memory size of this DCS instance.	Check whether the request parameters are valid.
400	DCS.4106	The value of maintain time illegal.	The value of maintain time illegal.	Check whether the request parameters are valid.
400	DCS.4107	The instance exists for unpaid scale up orders. Please process non payment orders first.	The instance exists for unpaid scale up orders. Please process non payment orders first.	Process unpaid orders before continuing.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4108	The Instance exists for processing scale up order. Please try again later.	The Instance exists for processing scale up order. Please try again later.	Try again later or contact technical support.
400	DCS.4111	the instance is restarting.	Restarting the instance. Please try again later.	Try again later or contact technical support.
400	DCS.4113	the instance is extending.	Scaling up the instance. Please try again later.	Try again later or contact technical support.
400	DCS.4114	the instance is configuring.	Modifying instance configuration. Please try again later.	Try again later or contact technical support.
400	DCS.4115	the instance is changing the password.	The password is being changed. Try again later.	Try again later or contact technical support.
400	DCS.4116	the instance is upgrading.	Upgrading the instance. Please try again later.	Try again later or contact technical support.
400	DCS.4117	the instance is rollbacking the version.	Rolling back the instance. Please try again later.	Try again later or contact technical support.
400	DCS.4118	the instance is creating.	Creating the instance. Please try again later.	Try again later or contact technical support.
400	DCS.4119	Query Bill Sample failed	The instance does not exist.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4120	the instance is Freezing.	Freezing the instance. Please try again later.	Try again later or contact technical support.
400	DCS.4200	Instance type cannot be changed.	Instance type cannot be changed.	Check whether the request parameters are valid.
400	DCS.4253	All replicas have a priority of 0.	All replicas have a priority of 0.	Check whether the request parameters are valid.
400	DCS.4300	Client IP transparent transmission is being processed, please do not submit it repeatedly.	Client IP transparent transmission is being processed, please do not submit it repeatedly.	Client IP pass-through is being enabled or disabled.
400	DCS.4800	Invalid {0} in the request.	Invalid {0} in the request.	Check whether the request parameters are valid.
400	DCS.4819	The first_scan_at parameter is invalid. Its must be ISO format utc date-time. The time must be later than the current time.	first_scan_at must be ISO format utc date-time. The time must be later than the current time.	Check whether the request parameters are valid. Example of the ISO UTC format: "2021-08-18T07:33:00.000Z".
400	DCS.4820	The interval parameter is invalid. must Greater than or equal to 0.	The value of interval is invalid. It must be greater than or equal to 0 seconds.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4821	The timeout parameter is invalid. Its must Greater than or equal to interval * 2, if interval is 0, timeout must Greater than 1 second.	The value of the timeout parameter is invalid. The value must be greater than 0 and at least twice the scanning interval.	Check whether the request parameters are valid.
400	DCS.4822	The scan_keys_count parameter is invalid. Its must Greater than or equal to 10, and Less than or equal to 1000.	The value of the scan_keys_count parameter is invalid. The value range is from 10 to 1000.	Check whether the request parameters are valid.
400	DCS.4838	Do not support feature client ip transparent transmission.	Client IP pass-through is not supported.	Client IP pass-through is not enabled.
400	DCS.4839	Do not support feature public dns.	Public domain name resolution is not supported.	Public domain name resolution is not enabled.
400	DCS.4840	Do not support feature dns.	Domain name resolution is not supported.	Domain name resolution is disabled.
400	DCS.4841	Instance do not support client ip transparent transmission.	The instance does not support client IP pass-through.	The instance version does not support client IP pass-through.
400	DCS.4843	The no_password_access parameter is missing or its value is invalid.	The no_password_access parameter is missing or its value is invalid.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4844	The access_user parameter is missing or its value is invalid.	The access_user parameter is missing or its value is invalid.	Check whether the request parameters are valid.
400	DCS.4845	The password parameter is missing or its value is invalid.	The password parameter is missing or its value is invalid.	Check whether the request parameters are valid.
400	DCS.4846	Client ip transparent transmission is already closed,please do not repeat the operation.	Client IP pass-through is already disabled.	Client IP pass-through is disabled.
400	DCS.4847	Client ip transparent transmission is already opened,please do not repeat the operation.	Client IP pass-through is already enabled.	Client IP pass-through is enabled.
400	DCS.4848	Client Management is not supported.	Session management is not supported.	Operation not allowed.
400	DCS.4849	The request parameter new_password should not exist.	The request parameter new_password should not exist.	Check whether the request parameters are valid.
400	DCS.4850	This operation is not supported when Password-Free Access is enabled for the instance.	This operation is not supported when Password-Free Access is enabled for the instance.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4875	Create replication number exceed max number limit.	The maximum number of replicas that can be created has been reached.	Check whether the request parameters are valid.
400	DCS.4879	r/w instance have only one repl can not remove ip from dns.	The IP address cannot be removed because a master/standby instance must have at least one replica IP address.	Check whether the request parameters are valid.
400	DCS.4911	The network ip insufficient.	The subnet does not have sufficient IP addresses.	Check the quantity of IP addresses in the subnet. Release IP addresses that are no longer used, or use another subnet that has sufficient IP addresses.
400	DCS.4918	Instance bigkey analyze is running.	The big key analysis is in progress.	Try again later.
400	DCS.4919	Does not support bigkey analyze.	Big key analysis is not supported.	Operation not allowed.
400	DCS.4927	The param spec_code is invalid	The param spec_code is invalid	Check whether the request parameters are valid.
400	DCS.4930	The request param node_list is invalid	Invalid node_list parameter in the request.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4931	Node is not replica, can't delete.	The replica cannot be deleted because it is not a read-only replica.	Check whether the request parameters are valid.
400	DCS.4935	Only one slave replication has dns ip, can not delete	The replica cannot be deleted because at least one DNS IP address must be retained.	Check whether the request parameters are valid.
400	DCS.4936	The master node cannot be deleted	The master node cannot be deleted.	Check whether the request parameters are valid.
400	DCS.4937	Only has one slave node,can not delete	Retain at least one replica in addition to the master.	Check whether the request parameters are valid.
400	DCS.4939	The param slave_priority_weight is invalid.	Invalid slave_priority_weight parameter in the parameter.	Check whether the request parameters are valid.
400	DCS.4941	The hotkey id does not exist.	The hot key analysis task ID does not exist.	Check whether the request parameters are valid.
400	DCS.4942	The bigkey id does not exist.	The big key analysis task ID does not exist.	Check whether the request parameters are valid.
400	DCS.4957	This operation is not allowed when the task is in the current state.	This operation is not allowed when the task is in the current state.	Only tasks in the successful state support this operation.
400	DCS.4998	Domain names are up to date.	The domain name has already been updated.	The domain name has already been updated.

Status Code	Error Codes	Error Message	Description	Solution
400	DCS.4999	Do not support feature update domain name.	Domain name update is not supported.	Domain name optimization is not enabled.
400	DCS.5009	The number of manual backups exceeds the limit.	The number of manual backups exceeds the limit.	Please delete some manual backup records before proceeding with the backup.
401	111401001	Invalid token.	Invalid token.	Check whether the request parameters are valid.
401	111401002	Token expired.	Token expired.	Check whether the request parameters are valid.
401	111401003	No token in the request.	No token in the request.	Check whether the request parameters are valid.
401	111401004	Project ID does not match the token.	Project ID does not match the token.	Check whether the request parameters are valid.
401	DCS.1001	Invalid token.	Invalid token.	Check whether the request parameters are valid.
401	DCS.1002	Token expired.	Token expired.	Check whether the request parameters are valid.
401	DCS.1003	No token in the request.	No token in the request.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
401	DCS.1004	Project ID does not match the token.	Project ID does not match the token.	Check whether the request parameters are valid.
403	111403002	This tenant has read permission only and cannot perform this operation.	This tenant has read permission only and cannot perform this operation.	Check whether the request parameters are valid.
403	111403003	This role does not have the permission to perform this operation.	This role does not have the permission to perform this operation.	Check whether the request parameters are valid.
403	DCS.2003	This role does not have the permission to perform this operation.	This role does not have the permission to perform this operation.	Check whether the request parameters are valid.
403	DCS.2007	Policy does not allow {} to be performed.	Insufficient permissions.	Check whether the account has the required operation permissions.
403	DCS.3002	This tenant has read permission only and cannot perform this operation.	This tenant has read permission only and cannot perform this operation.	Check whether the request parameters are valid.
403	DCS.3003	This role does not have the permission to perform this operation.	This role does not have the permission to perform this operation.	Check whether the request parameters are valid.
404	111404001	The requested URL does not exist.	The requested URL does not exist.	Check whether the request parameters are valid.

Status Code	Error Codes	Error Message	Description	Solution
404	111404022	This DCS instance does not exist.	This DCS instance does not exist.	Check whether the request parameters are valid.
404	111404023	This DCS order does not exist.	This DCS order does not exist.	Check whether the request parameters are valid.
404	DCS.3022	This DCS instance does not exist.	This DCS instance does not exist.	Check whether the request parameters are valid.
404	DCS.4001	The requested URL does not exist.	The requested URL does not exist.	Check whether the request parameters are valid.
404	DCS.4023	This DCS order does not exist.	This DCS order does not exist.	Check whether the request parameters are valid.
404	DCS.5101	Create agency failed.	Create agency failed.	Try again later or contact technical support.
405	111405001	This request method is not allowed.	This request method is not allowed.	Check whether the request parameters are valid.
405	DCS.5001	This request method is not allowed.	This request method is not allowed.	Check whether the request parameters are valid.
500	111400069	Another user is modifying configuration parameters of the DCS instance. Please try again later.	Another user is modifying configuration parameters of the DCS instance. Please try again later.	Try again later.

Status Code	Error Codes	Error Message	Description	Solution
500	111400101	Delete instance backup file failed.	The instance backup file fails to be deleted.	Contact technical support.
500	111400842	job execution status failed.	Failed to run the task.	Contact technical support.
500	111500000	Internal service error.	Internal service error.	Contact technical support.
500	111500006	Internal service error.	Internal service error.	Contact technical support.
500	111500017	Internal service error.	Internal service error.	Contact technical support.
500	111500020	vm add port fail	Failed to add a port for the VM.	Contact technical support.
500	111500024	Internal service error.	Internal service error.	Contact technical support.
500	111500031	create instance fail	Failed to create a DCS instance.	Contact technical support.
500	111500032	Internal service error.	Internal service error.	Contact technical support.
500	111500037	query order info fail	query order info fail	Try again later or contact technical support.
500	111500041	No resource tenant available.	No resource tenant available.	Try again later or contact technical support.
500	111500044	update resource status fail	Failed to update the status of the instance.	Try again later or contact technical support.

Status Code	Error Codes	Error Message	Description	Solution
500	111500053	Internal service error.	Internal service error.	Contact technical support.
500	111500054	Internal service error.	Internal service error.	Contact technical support.
500	111500070	Internal service error.	Internal service error.	Contact technical support.
500	111500071	Internal service error.	Internal service error.	Contact technical support.
500	111500077	Internal service error.	Internal service error.	Contact technical support.
500	111500078	Internal service error.	Internal service error.	Contact technical support.
500	111500079	Internal service error.	Internal service error.	Contact technical support.
500	111500082	Internal service error.	Internal service error.	Contact technical support.
500	111500083	Internal service error.	Internal service error.	Contact technical support.
500	111500085	Internal service error.	Internal service error.	Contact technical support.
500	111500090	Internal service error.	Internal service error.	Contact technical support.
500	111500091	Internal service error.	Internal service error.	Contact technical support.
500	111500092	Internal service error.	Internal service error.	Contact technical support.

Status Code	Error Codes	Error Message	Description	Solution
500	111500095	Internal service error.	Internal service error.	Contact technical support.
500	111500104	Internal service error.	Internal service error.	Contact technical support.
500	DCS. 5094	Master standby swap failed.	Master/standby switchover failed.	Contact technical support.
500	DCS.4069	Another user is modifying configuration parameters of the DCS instance. Please try again later.	Another user is modifying configuration parameters of the DCS instance. Please try again later.	Try again later.
500	DCS.4101	Delete instance backup file failed.	The instance backup file fails to be deleted.	Contact technical support.
500	DCS.4842	job execution status failed.	Failed to run the task.	Contact technical support.
500	DCS.5000	Internal service error.	Internal service error.	Contact technical support.
500	DCS.5006	Submit job failed.	Submission failed.	Contact technical support.
500	DCS.5017	Failed to save instance information.	Failed to save the instance information.	Contact technical support.
500	DCS.5020	vm add port fail	Failed to add a port for the VM.	Contact technical support.
500	DCS.5024	Query instance failed.	Failed to query the instance.	Contact technical support.
500	DCS.5031	create instance fail	Failed to create a DCS instance.	Contact technical support.

Status Code	Error Codes	Error Message	Description	Solution
500	DCS.5032	Failed to create order.	Failed to create the order.	Contact technical support.
500	DCS.5037	query order info fail	Failed to query the order details.	Contact technical support.
500	DCS.5039	Obtain IAM service failed.	Obtain IAM service failed.	Contact technical support.
500	DCS.5040	Call IAM API for querying agency failed.	Call IAM API for querying agency failed.	Contact technical support.
500	DCS.5041	No resource tenant available.	No resource tenant available.	Contact technical support.
500	DCS.5042	Call IAM API for creating agency failed.	Call IAM API for creating agency failed.	Contact technical support.
500	DCS.5043	Call IAM API for querying permission failed.	Call IAM API for querying permission failed.	Contact technical support.
500	DCS.5044	update resource status fail	Failed to update the status of the instance.	Contact technical support.
500	DCS.5045	Call IAM API for adding project-level agency permissions failed.	Call IAM API for adding project-level agency permissions failed.	Contact technical support.
500	DCS.5053	Instance node not found.	Instance node not found.	Contact technical support.
500	DCS.5054	Failed to generate password.	Failed to generate a password.	Contact technical support.
500	DCS.5070	Internal service error.	Internal service error.	Contact technical support.

Status Code	Error Codes	Error Message	Description	Solution
500	DCS.5071	Failed to create instance backup strategy.	Failed to create the instance backup policy.	Contact technical support.
500	DCS.5077	Query instance failed.	Failed to query the instance backup policy.	Contact technical support.
500	DCS.5078	Query backup record failed.	Failed to query the backup record.	Contact technical support.
500	DCS.5079	Query group node failed.	Failed to query the restoration record.	Contact technical support.
500	DCS.5081	The resource tenant does not exist.	The resource tenant does not exist.	Contact technical support.
500	DCS.5082	Failed to register resource tenant backup user.	Failed to register the resource tenant backup user.	Contact technical support.
500	DCS.5083	Failed to save backup user.	The backup user fails to be saved.	Contact technical support.
500	DCS.5085	Failed to update backup strategy.	The backup policy fails to be updated.	Contact technical support.
500	DCS.5090	Failed to save backup information.	The backup information fails to be saved.	Contact technical support.
500	DCS.5091	Script execution failed.	Script execution failed.	Contact technical support.
500	DCS.5092	Failed to save and restore data.	Failed to save and restore data.	Contact technical support.

Status Code	Error Codes	Error Message	Description	Solution
500	DCS.5095	The script execution failed and needs to be retried.	Script execution failed and needs to be retried.	Contact technical support.
500	DCS.5104	Failed to modify order.	Failed to modify the order.	Contact technical support.

7.3 Obtaining a Project ID

Obtaining a Project ID by Calling an API

You can obtain a project ID by calling the API used to query project information based on the specified criteria.

The API used to obtain a project ID is **GET [https://{Endpoint}/v3/projects](#)**. {Endpoint} is the IAM endpoint and can be obtained from [Regions and Endpoints](#). For details on API calling authentication, see [Authentication](#).

The following is an example response. The value of **id** in the **projects** section is the project ID.

```
{
  "projects": [
    {
      "domain_id": "65382450e8f64ac0870cd180d14e684b",
      "is_domain": false,
      "parent_id": "65382450e8f64ac0870cd180d14e684b",
      "name": "project_name",
      "description": "",
      "links": {
        "next": null,
        "previous": null,
        "self": "https://www.example.com/v3/projects/a4a5d4098fb4474fa22cd05f897d6b99"
      },
      "id": "a4a5d4098fb4474fa22cd05f897d6b99",
      "enabled": true
    }
  ],
  "links": {
    "next": null,
    "previous": null,
    "self": "https://www.example.com/v3/projects"
  }
}
```

Obtaining a Project ID from the Console

A project ID is required for some URLs when an API is called.

To obtain a project ID, perform the following operations:

- Step 1** Sign up and log in to the management console.
- Step 2** Click the username in the upper right corner and choose **My Credentials** from the drop-down list.
- Step 3** On the **My Credentials** page, view project IDs in the project list.

----End

7.4 Obtaining the Account Name and Account ID

The account name and account ID are required for some URLs when an API is called. To obtain the account name and account ID, perform the following operations:

1. Register an account and log in to the console.
2. Click the username and choose **My Credentials** from the drop-down list.
3. On the **My Credentials** page, view the **Account Name** and **Account ID**.

7.5 DCS Instance Statuses

Table 7-2 DCS instance statuses

State	Description
CREATING	Creating is the status before the Running state.
CREATEFAILED	The DCS instance failed to be created.
RUNNING	The instance is running properly. Only instances in the Running state can provide in-memory cache service.
ERROR	The instance is not running properly.
RESTARTING	The instance is being restarted.
FROZEN	The instance is frozen.
EXTENDING	The instance is being scaled up.
RESTORING	The instance data is being restored.
FLUSHING	The DCS instance is being cleared.

7.6 Instance Diagnosis IDs

Table 7-3 cause_ids

ID	Type	Description
1	cause	The number of connected clients exceeds {THRESHOLD}.
2	cause	The instantaneous traffic is too high.
3	cause	The underlying disk is abnormal.
4	cause	Data persistence failed.
5	cause	Memory usage exceeds {THRESHOLD}.
6	cause	RDB persistence is enabled. Memory usage exceeds {THRESHOLD}.
7	cause	Excessive memory fragmentation.
8	cause	Cache hit rate is lower than {THRESHOLD}.
9	cause	Too many keys have expired at the same time.
10	cause	The following commands with time complexity $O(N)$ are executed: {COMMANDS}
11	cause	CPU usage exceeds {THRESHOLD}.
12	cause	Data is persisted.
13	cause	QPS has increased.

Table 7-4 impact_ids

ID	Type	Description
1	impact	Redis connections will be refused.

ID	Type	Description
2	impact	Redis will be disconnected.
3	impact	Redis responses will slow down.
4	impact	RDB persistence will fail.
5	impact	Cache hit ratio will decrease.
6	impact	AOF persistence will fail.

Table 7-5 advice_ids

ID	Type	Description
1	advice	Retrieve connections from the connection pool.
2	advice	Use read/write splitting or a cluster.
3	advice	Expand the capacity of the instance.
4	advice	Manually run the MEMORY PURGE command during low-demand hours.
5	advice	Check the Redis usage or reduce the cache granularity to avoid memory eviction.
6	advice	Set different expiration time for the keys.
7	advice	Do not use commands with time complexity of $O(N)$.

A Change History

Table A-1 Change history

Released On	Description
2025-06-04	Updated the API for creating a DCS instance. Added APIs described in APIs V2 (Recommended) and moved APIs to Outdated APIs (V1) .
2023-05-15	Updated the supported actions in Permissions and Supported Actions .
2023-04-18	Updated Obtaining the Account Name and Account ID .
2022-12-20	- Added parameter include_failure and deleted parameter isExactMatchName in the API for querying the list of all DCS instances. - Added redis and other parameters and updated parameter includeFailure to include_failure in the API for querying the instance status. - Updated parameter regionID to region_id in the API for querying AZ information.
2022-04-30	This issue is the first official release.