

**Virtual Private Cloud**

# Getting Started

**Issue**            01  
**Date**             2024-07-08



**Copyright © Huawei Cloud Computing Technologies Co., Ltd. 2024. All rights reserved.**

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Cloud Computing Technologies Co., Ltd.

## **Trademarks and Permissions**



HUAWEI and other Huawei trademarks are the property of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

## **Notice**

The purchased products, services and features are stipulated by the contract made between Huawei Cloud and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

## **Huawei Cloud Computing Technologies Co., Ltd.**

Address: Huawei Cloud Data Center Jiaoxinggong Road  
Qianzhong Avenue  
Gui'an New District  
Gui Zhou 550029  
People's Republic of China

Website: <https://www.huaweicloud.com/intl/en-us/>

---

# Contents

---

<b>1 Setting Up an IPv4 Network in a VPC.....</b>	<b>1</b>
<b>2 Quickly Setting Up an IPv4/IPv6 Dual-Stack Network In a VPC.....</b>	<b>11</b>


# 1 Setting Up an IPv4 Network in a VPC

---

This topic describes how to create a VPC with an IPv4 CIDR block and bind an EIP to an ECS in the VPC to allow the ECS to access the Internet.

**Figure 1-1** shows the architecture of an IPv4 network. In this network, security group **sg-A** protects **ecs-A01** in it. You can configure security group rules to control access to and from **ecs-A01**.

**Figure 1-1** The architecture of an IPv4 network (VPC/ECS/EIP)



- To allow users to remotely log in to **ecs-A01** from the local PC (IP address: 10.1.0.7) and perform operations on this ECS, you need to configure the following inbound rules:
  - Rule A01: allows ping traffic to **ecs-A01** in **vpc-A** over all ICMP ports to verify network connectivity.
  - Rule A02: allows the local PC to remotely log in to Linux **ecs-A01** over TCP port 22.
  - Rule A03: allows the local PC to remotely log in to Windows **ecs-A01** over TCP port 3389.
  - Rule A04: allows ECSs in **sg-A** to communicate with other.
- To allow **ecs-A01** to access the Internet, you need to EIP **eip-A** to it and add outbound rule A05.

## Precautions

The network planning in this topic is only for your reference. Once a VPC and subnet are created, the CIDR blocks cannot be changed. Before creating VPCs, determine how many VPCs, the number of subnets, and what CIDR blocks or connectivity options you will need.

For details, see [VPC and Subnet Planning Suggestions](#).

## Procedure

Procedure	What to Do
<a href="#">Preparations</a>	Before using cloud services, sign up for a HUAWEI ID, enable Huawei Cloud services, complete real-name authentication, and top up your account.
<a href="#">Step 1: Create a VPC and Subnet</a>	Create a VPC, specify an IPv4 CIDR block (for example, 192.168.0.0/16), and create a subnet with the CIDR block of 192.168.0.0/24 in the VPC.
<a href="#">Step 2: Buy an ECS</a>	Buy an ECS in the subnet you have created and configure security group rules for the ECS.
<a href="#">Step 3: Buy an EIP and Bind It to ecs-A01</a>	Buy an EIP and bind it to the ECS so that the ECS can access the Internet.
<a href="#">Step 4: Verify Network Connectivity</a>	To test ECS connectivity, you can: <ul style="list-style-type: none"><li>• Log in to the ECS from the local PC.</li><li>• Access the Internet from the ECS using an EIP.</li></ul>

## Preparations


Before creating resources such as VPCs and ECSs, you need to sign up for a HUAWEI ID, enable Huawei Cloud services, complete real-name authentication, and top up your account. Ensure that your account has sufficient balance.

1. You have created a HUAWEI ID, enabled Huawei Cloud services, and completed real-name authentication.  
If you already have a HUAWEI ID, skip this part. If you do not have a HUAWEI ID, perform the following operations to create one:
  - a. [Sign up for a HUAWEI ID and enable Huawei Cloud services](#).
  - b. Complete [real-name authentication](#).
2. You need to ensure that your account has sufficient balance. [Top up your account](#) if your account has insufficient balance.


## Step 1: Create a VPC and Subnet

1. Go to the [Create VPC](#) page.
2. On the [Create VPC](#) page, set parameters as needed.  
In this example, you need to create a VPC and a subnet.

**Figure 1-2** Creating a VPC



**Figure 1-3** Creating a subnet



**Table 1-1** VPC parameter descriptions

Parameter	Example Value	Description
Region	CN-Hong Kong	The region where <b>vpc-A</b> belongs. Select the region nearest to you to ensure the lowest possible latency. The VPC, ECS, and EIP used in this example must be in the same region.  The region cannot be changed after <b>vpc-A</b> is created.
Name	vpc-A	The VPC name. Set it to <b>vpc-A</b> .  The name can be modified after <b>vpc-A</b> is created.

Parameter	Example Value	Description
IPv4 CIDR Block	192.168.0.0/16	<p>The IPv4 CIDR block of <b>vpc-A</b>. You are advised to select from the following CIDR blocks:</p> <ul style="list-style-type: none"><li>• 10.0.0.0/8-24: The IP address ranges from 10.0.0.0 to 10.255.255.255, and the netmask ranges from 8 to 24.</li><li>• 172.16.0.0/12-24: The IP address ranges from 172.16.0.0 to 172.31.255.255, and the netmask ranges from 12 to 24.</li><li>• 192.168.0.0/16-24: The IP address ranges from 192.168.0.0 to 192.168.255.255, and the netmask ranges from 16 to 24.</li></ul> <p>The IPv4 CIDR block cannot be changed after the <b>vpc-A</b> is created.</p>
Enterprise Project	default	<p>The enterprise project by which VPCs are centrally managed. Select an existing enterprise project for <b>vpc-A</b>.</p> <p>The enterprise project cannot be changed after the <b>vpc-A</b> is created.</p>
Advanced Settings (Optional) > Tag	Tag key: test Tag value: 01	<p>The tag that is used to classify and identify resources. Add tags to <b>vpc-A</b> as required.</p> <p>After <b>vpc-A</b> is created, you can add additional tags to <b>vpc-A</b> or delete existing tags from it.</p>
Advanced Settings (Optional) > Description	-	<p>Supplementary information about <b>vpc-A</b>. Enter the description as required.</p> <p>The description can be modified after <b>vpc-A</b> is created.</p>



**Table 1-2** Subnet parameter descriptions

Parameter	Example Value	Description
AZ	AZ4	<p>An AZ is a geographic location with independent power supply and network facilities in a region. Each region contains multiple AZs. AZs are physically isolated but connected through an internal network. Subnets of a VPC can be located in different AZs without affecting communications. You can select any AZ in a region.</p> <p>The ECS and VPC can be in different AZs. For example, you can select AZ1 for the ECS and AZ3 for the VPC subnet.</p> <p>The AZ cannot be changed after <b>subnet-A01</b> is created.</p> <p>You can select an AZ for a subnet only in certain regions. See the available regions on the management console.</p>
Subnet Name	subnet-A01	<p>The subnet name. Set it to <b>subnet-A01</b>.</p> <p>The name can be modified after <b>subnet-A01</b> is created.</p>
IPv4 CIDR Block	192.168.0.0/24	<p>The IPv4 CIDR block of <b>subnet-A01</b>, which is a unique CIDR block with a range of IP addresses in <b>vpc-A</b>.</p> <p>The CIDR block cannot be changed after <b>subnet-A01</b> is created.</p>
IPv6 CIDR Block (Optional)	Disabled	<p>Whether to assign IPv6 addresses.</p> <p>You can enable or disable this option after <b>subnet-A01</b> is created.</p>
Associated Route Table	Default	<p>The default route table that <b>subnet-A01</b> is associated with. Each VPC comes with a default route table. Subnets in the VPC are then automatically associated with the default route table.</p> <p>The default route table has a preset system route that allows subnets in a VPC to communicate with each other.</p> <p>After <b>subnet-A01</b> is created, you can create a custom route table and associate <b>subnet-A01</b> with it.</p>

Parameter	Example Value	Description
Advanced Settings (Optional) > Gateway	192.168.0.1	The gateway address of <b>subnet-A01</b> . You are advised to retain the default address. The gateway address cannot be changed after <b>subnet-A01</b> is created.
Advanced Settings (Optional) <ul style="list-style-type: none"><li>• DNS Server Address</li><li>• Domain Name</li><li>• NTP Server Address</li><li>• IPv4 DHCP Lease Time</li></ul>	Not required	The parameters are configured for the <b>ecs-A01</b> in <b>vpc-A</b> . In this example, retain the default values or leave them empty. You can change the values after <b>subnet-A01</b> is created.
Advanced Settings (Optional) > Tag	Tag key: test Tag value: 01	The tag that is used to classify and identify resources. Add tags to <b>subnet-A01</b> as required. After <b>subnet-A01</b> is created, you can add additional tags to <b>subnet-A01</b> or delete existing tags from it.
Advanced Settings (Optional) > Description	-	Supplementary information about <b>subnet-A01</b> . Enter the description as required. The description can be modified after <b>subnet-A01</b> is created.

3. Click **Create Now**.

Return to the VPC list to view **vpc-A** you have created.


## Step 2: Buy an ECS

1. Go to the [Buy ECS](#) page.
2. On the **Buy ECS** page, set parameters as required.

In this example, set the ECS name to **ecs-A01** and configure other parameters as follows:

- **Network:** Select **vpc-A** and **subnet-A01** you have created.

Figure 1-4 Network settings



- **Security Group:** Create security group **sg-A** and add inbound and outbound rules to it. Each security group comes with system rules. You need to check and modify the rules as required to ensure that all rules in **Table 1-3** are added.

Figure 1-5 Inbound rules of **sg-A**




Figure 1-6 The outbound rule of **sg-A**





Table 1-3 **sg-A** rules

Direction	Action	Type	Protocol & Port	Source/Destination	Description
Inbound	Allow	IPv4	TCP: 22	Source: 10.1.0.7/32	Allows the local PC (10.1.0.7/32) to remotely log in to Linux <b>ecs-A01</b> over SSH port 22.
Inbound	Allow	IPv4	TCP: 3389	Source: 10.1.0.7/32	Allows the local PC (10.1.0.7/32) to remotely log in to Windows <b>ecs-A01</b> over RDP port 3389.
Inbound	Allow	IPv4	ICMP: All	Source: 0.0.0.0/0	Allows ping traffic to <b>ecs-A01</b> in <b>vpc-A</b> over all ICMP ports to verify network connectivity.
Inbound	Allow	IPv4	All	Source: current security group ( <b>sg-A</b> )	Allows the ECSs in <b>sg-A</b> to communicate with each other.

Direction	Action	Type	Protocol & Port	Source/Destination	Description
Outbound	Allow	IPv4	All	Destination: 0.0.0.0/0	Allows <b>ecs-A01</b> in <b>sg-A</b> to access the Internet.

- **EIP:** Select **Not required**.

**Figure 1-7** Selecting **Not required**




You can configure other ECS parameters as required. For details, see [Buying an ECS](#).

3. Click **Submit**.  
Return to the ECS list to view **ecs-A01** you have bought.

### Step 3: Buy an EIP and Bind It to ecs-A01

1. Go to the [Buy EIP](#) page.
2. On the **Buy EIP** page, set the EIP name to **eip-A**.  
You can configure other EIP parameters as required. For details, see [Buying an EIP](#).
3. Click **Next**.  
Return to the EIP list to view **eip-A** you have bought.
4. In the EIP list, locate **eip-A** and click **Bind** in the **Operation** column.  
The **Bind EIP** dialog box is displayed.


**Figure 1-8** Binding **eip-A** to **ecs-A01**



5. In the displayed dialog box, select **ecs-A01** and click **OK**.

Return to the EIP list. You can see that **ecs-A01** is displayed in the **Associated Instance** column in the EIP list.

**Figure 1-9 eip-A bound to ecs-A01**



EIP	Monit...	Status	Secu...	EIP Type	Bandwidth	Bandwidth De...	Associated Inst...	Billing Mode	Enterpr...	Tags	Operation
<input type="checkbox"/> eip-A Ma22689-9154-4500-6773-69c44c52449f	1.95.44.200	Bound		Dynamic BGP	bandwidth-756	Traffic 5 Mbits	ecs-A01 ECS	Pay-per-use Created at 19:20...	default	-	Bind Unbind More

## Step 4: Verify Network Connectivity

1. Use the local PC to remotely log in to **ecs-A01**.  
Multiple methods are available for logging in to an ECS. For details, see [Logging In to an ECS](#).
2. Run the following command to verify the network connectivity between **ecs-A01** and Internet:

**ping IPv4 EIP or Domain name**

Example command:

**ping support.huaweicloud.com**

If information similar to the following is displayed, **ecs-A01** can communicate with the Internet.

```
[root@ecs-a01 ~]# ping support.huaweicloud.com
PING hcdnw.cbg-notzj.c.cdnhwc2.com (203.193.226.103) 56(84) bytes of data:
64 bytes from 203.193.226.103 (203.193.226.103): icmp_seq=1 ttl=51 time=2.17 ms
64 bytes from 203.193.226.103 (203.193.226.103): icmp_seq=2 ttl=51 time=2.13 ms
64 bytes from 203.193.226.103 (203.193.226.103): icmp_seq=3 ttl=51 time=2.10 ms
64 bytes from 203.193.226.103 (203.193.226.103): icmp_seq=4 ttl=51 time=2.09 ms
...
--- hcdnw.cbg-notzj.c.cdnhwc2.com ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 3004ms
rtt min/avg/max/mdev = 2.092/2.119/2.165/0.063 ms
```


# 2 Quickly Setting Up an IPv4/IPv6 Dual-Stack Network In a VPC

---

This topic describes how to create a VPC with an IPv4 and IPv6 CIDR block and create an ECS with both IPv4 and IPv6 addresses in the VPC. You can bind an EIP and add the IPv6 address of the ECS to a shared bandwidth to enable the ECS to communicate with the Internet over both IPv4 and IPv6 networks.

**Figure 2-1** shows the architecture of an IPv4/IPv6 dual-stack network. In this network, security group **sg-A** protects **ecs-A01** in it. You can configure security group rules to control access to and from **ecs-A01**.

Figure 2-1 The architecture of an IPv4/IPv6 dual-stack network




- To allow users to remotely log in to **ecs-A01** from the local PC (IPv4 address: 10.1.0.7; IPv6 address: 2002:20::44) and perform operations on this ECS, you need to configure the following inbound rules:
  - Rules A01 and A02: allow ping traffic to **ecs-A01** in **vpc-A** over all ICMP ports to verify network connectivity.
  - Rules A03 and A04: allow the local PC to remotely log in to Linux **ecs-A01** over TCP port 22.
  - Rules A05 and A06: allow the local PC to remotely log in to Windows **ecs-A01** over TCP port 3389.
  - Rules A07 and A08: allow ECSs in **sg-A** to communicate with other.
- To allow **ecs-A01** to access the Internet, you need to bind EIP **eip-A** to it and add IPv6 address **2407:c080:1200:2075::a** to a shared bandwidth. Then add rules A09 and A10 to allow outbound traffic.

## Precautions

- The IPv4/IPv6 dual-stack function is free for now, but will be billed at a later date (price yet to be determined).
- The IPv6 function is now available for open beta test in **uncertain regions**. You can use the IPv6 function only after obtaining the OBT permission.
- Only certain ECS specifications support IPv6 networks. You need to select such ECSs in supported regions.

On the ECS console, click **Buy ECS**. On the displayed page, check the ECS specifications. If **Yes** is shown in the **IPv6** column, the ECS with this specification supports IPv6.

**Figure 2-2** ECS specifications



- The network planning in this example is for your reference only. Once a VPC and subnet are created, the CIDR blocks cannot be changed. Before creating VPCs, determine how many VPCs, the number of subnets, and what CIDR blocks or connectivity options you will need.

For details, see [VPC and Subnet Planning Suggestions](#).

## Procedure

Procedure	What to Do
<b>Preparations</b>	Before using cloud services, sign up for a HUAWEI ID, enable Huawei Cloud services, complete real-name authentication, and top up your account.
<b>Step 1: Create a VPC and Subnet</b>	<p>Create a VPC with an IPv4 CIDR block and create a subnet with IPv6 enabled in the VPC.</p> <ul style="list-style-type: none"> <li>• VPC IPv4 CIDR block: 192.168.0.0/16</li> <li>• Subnet IPv4 CIDR block: 192.168.0.0/24</li> <li>• Subnet IPv6 CIDR block: In this example, 2407:c080:1200:2075::/64 is automatically assigned.</li> </ul>
<b>Step 2: Buy an ECS</b>	Buy an ECS in the subnet you have created and configure security group rules for the ECS.
<b>Step 3: Buy an EIP and Bind It to ecs-A01</b>	Buy an EIP and bind it to the ECS so that the ECS can communicate with the Internet using an IPv4 address.



Procedure	What to Do
<b>Step 4: Buy a Shared Bandwidth and Add the ECS IPv6 Address to It</b>	Buy a shared bandwidth and add the IPv6 address of the ECS to the shared bandwidth so that the ECS can communicate with Internet using an IPv6 address.
<b>Step 5: Verify Network Connectivity</b>	To test ECS connectivity, you can: <ul style="list-style-type: none"> <li>Log in to the ECS from the local PC through an IPv4 EIP or IPv6 address.</li> <li>Verify whether the ECS can communicate with the Internet over IPv4 and IPv6 networks.</li> </ul>

## Preparations

Before creating resources such as VPCs and ECSs, you need to sign up for a HUAWEI ID, enable Huawei Cloud services, complete real-name authentication, and top up your account. Ensure that your account has sufficient balance.

1. You have created a HUAWEI ID, enabled Huawei Cloud services, and completed real-name authentication.

If you already have a HUAWEI ID, skip this part. If you do not have a HUAWEI ID, perform the following operations to create one:


- a. [Sign up for a HUAWEI ID and enable Huawei Cloud services.](#)
  - b. Complete [real-name authentication](#).
2. You need to ensure that your account has sufficient balance. [Top up your account](#) if your account has insufficient balance.

## Step 1: Create a VPC and Subnet

1. Go to the [Create VPC](#) page.
2. On the **Create VPC** page, set parameters as needed.

In this example, you need to create a VPC and subnet, and enable IPv6 for this subnet.

**Figure 2-3** Creating a VPC



**Figure 2-4** Setting a subnet

**Subnet Setting1**

Subnet Name:

AZ:

IPv4 CIDR Block:  /    
 Available IP Addresses: 251

⚠ The CIDR block cannot be modified after the subnet has been created.

IPv6 CIDR Block (Optional):  Enable

Associated Route Table:

Advanced Settings (Optional):

Gateway: 192.168.0.1   DNS Server Address: 100.125.1.250,100.125.129.250   Domain Name   NTP Server Address   IPv4 DHCP Lease Time: Limited,1250day   Tag   Description

**Table 2-1** VPC parameter descriptions

Parameter	Example Value	Description
Region	CN-Hong Kong	The region where <b>vpc-A</b> belongs. Select the region nearest to you to ensure the lowest possible latency. The VPC, ECS, and EIP used in this example must be in the same region.  The region cannot be changed after <b>vpc-A</b> is created.
Name	vpc-A	The VPC name. Set it to <b>vpc-A</b> .  The name can be modified after <b>vpc-A</b> is created.
IPv4 CIDR Block	192.168.0.0/16	The IPv4 CIDR block of <b>vpc-A</b> . You are advised to select from the following CIDR blocks: <ul style="list-style-type: none"> <li>10.0.0.0/8-24: The IP address ranges from 10.0.0.0 to 10.255.255.255, and the netmask ranges from 8 to 24.</li> <li>172.16.0.0/12-24: The IP address ranges from 172.16.0.0 to 172.31.255.255, and the netmask ranges from 12 to 24.</li> <li>192.168.0.0/16-24: The IP address ranges from 192.168.0.0 to 192.168.255.255, and the netmask ranges from 16 to 24.</li> </ul> The IPv4 CIDR block cannot be changed after the <b>vpc-A</b> is created.

Parameter	Example Value	Description
Enterprise Project	default	The enterprise project by which VPCs are centrally managed. Select an existing enterprise project for <b>vpc-A</b> . The enterprise project cannot be changed after the <b>vpc-A</b> is created.
Advanced Settings (Optional) > Tag	Tag key: test Tag value: 01	The tag that is used to classify and identify resources. Add tags to <b>vpc-A</b> as required. After <b>vpc-A</b> is created, you can add additional tags to <b>vpc-A</b> or delete existing tags from it.
Advanced Settings (Optional) > Description	-	Supplementary information about <b>vpc-A</b> . Enter the description as required. The description can be modified after <b>vpc-A</b> is created.

**Table 2-2** Subnet parameter descriptions

Parameter	Example Value	Description
AZ	AZ4	An AZ is a geographic location with independent power supply and network facilities in a region. Each region contains multiple AZs. AZs are physically isolated but connected through an internal network. Subnets of a VPC can be located in different AZs without affecting communications. You can select any AZ in a region. The ECS and VPC can be in different AZs. For example, you can select AZ1 for the ECS and AZ3 for the VPC subnet. The AZ cannot be changed after the VPC is created. You can select an AZ for a subnet only in certain regions. See the available regions on the management console.
Subnet Name	subnet-A01	The subnet name. Set it to <b>subnet-A01</b> . The name can be modified after <b>subnet-A01</b> is created.

Parameter	Example Value	Description
IPv4 CIDR Block	192.168.0.0/24	The IPv4 CIDR block of <b>subnet-A01</b> , which is a unique CIDR block with a range of IP addresses in <b>vpc-A</b> . The CIDR block cannot be changed after <b>subnet-A01</b> is created.
IPv6 CIDR Block (Optional)	Enabled	Whether to assign IPv6 addresses. After this option is enabled, IPv6 addresses can be assigned to <b>subnet-A01</b> the ECS. You can enable or disable this option after <b>subnet-A01</b> is created.
Associated Route Table	Default	The default route table that <b>subnet-A01</b> is associated with. Each VPC comes with a default route table. Subnets in the VPC are then automatically associated with the default route table. The default route table has a preset system route that allows subnets in a VPC to communicate with each other. After <b>subnet-A01</b> is created, you can create a custom route table and associate <b>subnet-A01</b> with it.
Advanced Settings (Optional) > Gateway	192.168.0.1	The gateway address of <b>subnet-A01</b> . You are advised to retain the default address. The gateway address cannot be changed after <b>subnet-A01</b> is created.
Advanced Settings (Optional) <ul style="list-style-type: none"><li>• DNS Server Address</li><li>• Domain Name</li><li>• NTP Server Address</li><li>• IPv4 DHCP Lease Time</li></ul>	Not required	The parameters are configured for the <b>ecs-A01</b> in <b>vpc-A</b> . In this example, retain the default values or leave them empty. You can change the values after <b>subnet-A01</b> is created.
Advanced Settings (Optional) > Tag	Tag key: test Tag value: 01	The tag that is used to classify and identify resources. Add tags to <b>subnet-A01</b> as required. After <b>subnet-A01</b> is created, you can add additional tags to <b>subnet-A01</b> or delete existing tags from it.

Parameter	Example Value	Description
Advanced Settings (Optional) > Description	-	Supplementary information about <b>subnet-A01</b> . Enter the description as required. The description can be modified after <b>subnet-A01</b> is created.

3. Click **Create Now**.

Return to the VPC list to view **vpc-A** you have created.


## Step 2: Buy an ECS

- Go to the [Buy ECS](#) page.
- On the **Buy ECS** page, set parameters as required.

In this example, set the ECS name to **ecs-A01** and configure other parameters as follows:

- Network:** Select **vpc-A** and **subnet-A01** you have created. Select **Automatically assign address**. An IPv4 address and an IPv6 address will be assigned to **ecs-A01**.

Figure 2-5 Network settings



- Security Group:** Create security group **sg-A** and add inbound and outbound rules to it. Each security group comes with system rules. You need to check and modify the rules as required to ensure that all rules in [Table 2-3](#) are added.

Figure 2-6 Inbound rules of sg-A




Figure 2-7 Outbound rules of sg-A




Table 2-3 sg-A rules

Direction	Action	Type	Protocol & Port	Source/Destination	Description
Inbound	Allow	IPv4	TCP: 22	Source: 10.1.0.7/32	Allows the local PC (10.1.0.7/32) to remotely log in to Linux <b>ecs-A01</b> over SSH port 22.
Inbound	Allow	IPv6	TCP: 22	Source: 2002:20::44/128	Allows the local PC (2002:20::44/128) to remotely log in to Linux <b>ecs-A01</b> over SSH port 22.
Inbound	Allow	IPv4	TCP: 3389	Source: 10.1.0.7/32	Allows the local PC (10.1.0.7/32) to remotely log in to Windows <b>ecs-A01</b> over RDP port 3389.
Inbound	Allow	IPv6	TCP: 3389	Source: 2002:20::44/128	Allows the local PC (2002:20::44/128) to remotely log in to Windows <b>ecs-A01</b> over RDP port 3389.
Inbound	Allow	IPv4	ICMP: All	Source: 0.0.0.0/0	Allows IPv4 ping traffic to <b>ecs-A01</b> in <b>vpc-A</b> over all ICMP ports to verify network connectivity.
Inbound	Allow	IPv6	ICMPV6: All	Source: ::/0	Allows IPv6 ping traffic to <b>ecs-A01</b> in <b>vpc-A</b> over all ICMP ports to verify network connectivity.
Inbound	Allow	IPv4	All	Source: current security group ( <b>sg-A</b> )	Allows the ECSs in <b>sg-A</b> to communicate with each other using IPv4 addresses.
Inbound	Allow	IPv6	All	Source: current security group ( <b>sg-A</b> )	Allows the ECSs in <b>sg-A</b> to communicate with each other using IPv6 addresses.
Outbound	Allow	IPv4	All	Destination: 0.0.0.0/0	Allows <b>ecs-A01</b> in <b>sg-A</b> to access the Internet using the IPv4 address.
Outbound	Allow	IPv4	All	Destination: ::/0	Allows <b>ecs-A01</b> in <b>sg-A</b> to access the Internet using the IPv6 address.

- **EIP**: Select **Not required**.

**Figure 2-8** Selecting **Not required**

EIP  Auto assign  Use existing  Not required ⓘ

An ECS without an EIP cannot access the Internet. However, it can still be used as a service ECS deployed in a cluster or on a private network.

You can configure other ECS parameters as required. For details, see [Buying an ECS](#).

3. Click **Submit**.  
Return to the ECS list to view **ecs-A01** you have bought.
4. Log in to **ecs-A01** and check whether the ECS has obtained an IPv6 address.
  - By default, dynamic IPv6 address assignment is enabled for Windows public images.
  - Before enabling dynamic IPv6 address assignment for a Linux public image, check whether IPv6 is supported first.


Currently, all Linux public images support IPv6. By default, dynamic IPv6 address assignment is enabled for Ubuntu 16. For other Linux public images, you need to enable this function.

If an IPv6 address fails to be automatically assigned or the selected image cannot obtain an IPv6 address automatically, [manually obtain the IPv6 address](#). Otherwise, ECSs cannot communicate with each other using IPv6 addresses.

### Step 3: Buy an EIP and Bind It to **ecs-A01**

Buy an EIP and bind it to **ecs-A01** so that it can communicate with the Internet using an IPv4 address.

1. Go to the [Buy EIP](#) page.
2. On the **Buy EIP** page, set the EIP name to **eip-A**.  
You can configure other EIP parameters as required. For details, see [Buying an EIP](#).
3. Click **Next**.  
Return to the EIP list to view **eip-A** you have bought.
4. In the EIP list, locate **eip-A** and click **Bind** in the **Operation** column.  
The **Bind EIP** dialog box is displayed.

**Figure 2-9** Binding **eip-A** to **ecs-A01**

- In the displayed dialog box, select **ecs-A01** and click **OK**.  
Return to the EIP list. You can see that **ecs-A01** is displayed in the **Associated Instance** column in the EIP list.

**Figure 2-10** **eip-A** bound to **ecs-A01**

EIP	Monit...	Status	Secu...	EIP Type	Bandwidth	Bandwidth De...	Associated Insta...	Billing Mode	Enterpr...	Tags	Operation
1.95.44 eip-A 6faa2889-915e-4590-b773-d6c44c52448f		Bound		Dynamic BGP	bandwidth-786	Traffic 5 Mbits	ecs-A01 ECS	Pay-per-use Created at May, 20...	default	--	Bind Unbind More

## Step 4: Buy a Shared Bandwidth and Add the ECS IPv6 Address to It

Buy a shared bandwidth and add the IPv6 address to the shared bandwidth so that **ecs-A01** can communicate with Internet.

- Go to the [Buy Shared Bandwidth](#) page.
- On the displayed page, set the shared bandwidth name to **bandwidth-A** and configure other parameters as required.  
For details, see [Assigning a Shared Bandwidth](#).
- Click **Next**.  
Return to the shared bandwidth list to view **bandwidth-A** you have assigned.
- Click **Add Public IP Address** in the **Operation** column.  
The **Add Public IP Address** dialog box is displayed.



**Figure 2-11** Adding the IPv6 address to **bandwidth-A**

**Add Public IP Address**

After you add an EIP or IPv6 address to shared bandwidth, the EIP or IPv6 address will use the shared bandwidth of 5 Mbit/s. When an EIP or IPv6 address uses a shared bandwidth, the EIP or IPv6 address will not be billed for traffic or bandwidth. Yearly/monthly EIPs cannot be added to a shared bandwidth. Current shared bandwidth type: Standard; EIP types that can use this bandwidth: Dynamic BGP, Static BGP

Shared Bandwidth: **bandwidth-A**  
You can add 20 more public IP addresses to the shared bandwidth. A maximum of 20 public IP addresses can be added to the shared bandwidth. [Increase quota](#)

Public IP Address:  EIP  IPv6 Address

VPC:

Subnet:

Select a property or enter a keyword.

IPv6 Address	VPC	Subnet	Instance
<input checked="" type="checkbox"/> 2407:c080:1880:6f8:f81d:5cab:79d1:e857	vpc-A	subnet-A01(192.168.0.0/24)	ecs-A01 ECS

Total Records: 1  < 1 >

1 items selected

2407:c080:1880:6f8:f81d:5cab:79d1:e857

5. Configure the parameters and click **OK**.
  - **Public IP Address:** Select **IPv6 Address**.
  - **VPC:** Select **vpc-A**.
  - **Subnet:** Select **subnet-A01**.
  - **IPv6 Address:** Select the IPv6 address assigned to **ecs-A01**.


## Step 5: Verify Network Connectivity

1. Use the local PC to log in to **ecs-A01** using the IPv4 EIP and IPv6 address. Multiple methods are available for logging in to an ECS. For details, see [Logging In to an ECS](#).

To remotely log in to **ecs-A01** using PuTTY:

- Enter the EIP of **ecs-A01** under **Host Name (or IP address)**, for example, **1.95.44.XX**.
- Enter the IPv6 address of **ecs-A01** under **Host Name (or IP address)**, for example, **2407:XXX:e857**.

Figure 2-12 PuTTY configurations



2. Verify whether **ecs-A01** can communicate with the Internet over IPv4 and IPv6 networks.

- Run the following command to verify IPv4 public network connectivity:

**ping** *IPv4 EIP or Domain name*

Example command:

**ping support.huaweicloud.com**

If information similar to the following is displayed, **ecs-A01** can communicate with the Internet over the IPv4 network.

```
[root@ecs-a01 ~]# ping support.huaweicloud.com
PING hcdnw.cbg-notzj.c.cdnhwc2.com (203.193.226.103) 56(84) bytes of data:
64 bytes from 203.193.226.103 (203.193.226.103): icmp_seq=1 ttl=51 time=2.17 ms
64 bytes from 203.193.226.103 (203.193.226.103): icmp_seq=2 ttl=51 time=2.13 ms
64 bytes from 203.193.226.103 (203.193.226.103): icmp_seq=3 ttl=51 time=2.10 ms
64 bytes from 203.193.226.103 (203.193.226.103): icmp_seq=4 ttl=51 time=2.09 ms
...
--- hcdnw.cbg-notzj.c.cdnhwc2.com ping statistics ---
4 packets transmitted, 4 received, 0% packet loss, time 3004ms
rtt min/avg/max/mdev = 2.092/2.119/2.165/0.063 ms
```

- Run the following command to verify IPv6 public network connectivity:

**ping6** *IPv6 public address*

In this example, **2002:20::45** is used as a public IP address. An example command is as follows:

**ping6 2002:20::45**

If information similar to the following is displayed, **ecs-A01** can communicate with the Internet over the IPv6 network.

```
[root@ecs-a01 ~]# ping6 2002:20::45
PING 2002:20::45(2002:20::45) from 2002:20::45 : 56 data bytes
```

```
64 bytes from 2002:20::45: icmp_seq=1 ttl=64 time=0.770 ms
64 bytes from 2002:20::45: icmp_seq=2 ttl=64 time=0.295 ms
64 bytes from 2002:20::45: icmp_seq=3 ttl=64 time=0.245 ms
^C
--- 2002:20::45 ping statistics ---
3 packets transmitted, 3 received, 0% packet loss, time 2080ms
rtt min/avg/max/mdev = 0.245/0.436/0.770/0.237 ms
```