TaurusDB

Best Practices

Issue 01

Date 2025-07-11





Copyright © Huawei Cloud Computing Technologies Co., Ltd. 2025. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Cloud Computing Technologies Co., Ltd.

Trademarks and Permissions

HUAWEI and other Huawei trademarks are the property of Huawei Technologies Co., Ltd. All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei Cloud and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, quarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Huawei Cloud Computing Technologies Co., Ltd.

Address: Huawei Cloud Data Center Jiaoxinggong Road

Qianzhong Avenue Gui'an New District Gui Zhou 550029

People's Republic of China

Website: https://www.huaweicloud.com/intl/en-us/

i

Contents

1 From ECS-hosted MySQL to TaurusDB	
1.1 Overview	1
1.2 Resource Planning	3
1.3 Operation Process	4
1.4 Procedure	5
1.4.1 ECS-hosted MySQL Server	5
1.4.1.1 Creating a VPC and Security Group	5
1.4.1.2 Creating an ECS (MySQL Server)	7
1.4.1.3 Installing a MySQL Database (Community Edition)	8
1.4.1.4 Creating an ECS and Installing a MySQL Client on It	10
1.4.2 Cloud Migration	10
1.4.2.1 Creating a TaurusDB Instance	10
1.4.2.2 Creating a DRS Migration Task	11
1.4.2.3 Checking the Migration Results	12
2 From Other Cloud MySQL to TaurusDB	14
2.1 Overview	14
2.2 Resource Planning	15
2.3 Creating a VPC and Security Group	16
2.4 Creating a TaurusDB Instance	17
2.5 Configuring a MySQL Instance on Other Clouds	18
2.6 Creating a DRS Migration Task	18
2.7 Checking Migration Results	20
3 Enabling Read/Write Splitting	22
3.1 User Authentication	22
3.2 Connection Pool Configuration	25
3.3 Routing Read Requests to the Primary Node	25

From ECS-hosted MySQL to TaurusDB

1.1 Overview

This practice describes how to install a MySQL database (community edition) on a Huawei Cloud ECS and create a TaurusDB instance, and use DRS to migrate data from MySQL to TaurusDB. With DRS, you can perform real-time migration tasks with minimal downtime.

Scenarios

- With the rapid increase of enterprise workloads, traditional databases have poor scalability and require distributed reconstruction.
- Building traditional databases requires purchasing and installing servers, systems, databases, and other software. Its O&M is expensive and difficult.
- Traditional databases are poor in complex gueries.
- It is hard for traditional databases to smoothly migrate data with no downtime.

Prerequisites

- You have completed real-name authentication.
- Your account balance is at least \$0 USD.

Solution Architecture

In this practice, the source database is an ECS-hosted MySQL instance and the destination database is a TaurusDB instance. Figure 1-1 shows the deployment architecture when the ECS-hosted MySQL and TaurusDB instances are in the same VPC.

If the ECS-hosted MySQL and TaurusDB instances are not in the same VPC, you need to configure a **VPC peering connection** between the two VPCs. For details about the deployment architecture, see **Figure 1-2**.





Figure 1-1 Deployment architecture in the same VPC

Figure 1-2 Deployment architecture in different VPCs



TaurusDB Advantages

- Robust performance: TaurusDB decouples compute from storage and uses a "log as database" architecture and remote direct memory access (RDMA). It can deliver seven times the performance of open-source MySQL for certain service loads.
- Elastic scaling: In addition to a primary node, you can add up to 15 read replicas for a DB instance within minutes. You can also scale up or down CPU and memory specifications for a DB instance as needed.
- High reliability: DB instances can be deployed across AZs and there are three
 data copies under the shared distributed storage layer. A DB instance failover
 can be complete within seconds with a zero RPO.
- High security: With shared distributed storage, TaurusDB ensures zero data loss and fault recovery within seconds. VPCs, security groups, SSL connections, and data encryption are used to strictly control secure access.
- High compatibility: TaurusDB is fully compatible with MySQL. You can easily migrate your MySQL databases to TaurusDB without refactoring existing applications.

• Mass storage: Based on Data Function Virtualization (DFV) distributed storage, TaurusDB supports up to 128 TB of storage.

Service List

- Virtual Private Cloud (VPC)
- Elastic Cloud Server (ECS)
- TaurusDB
- Data Replication Service (DRS)

Notes on Usage

The resources and test data in this practice are for demonstration only. Adjust them as needed.

For more information about TaurusDB data migration, see **From MySQL to TaurusDB**.

1.2 Resource Planning

Table 1-1 Resource planning


Category	Subcategory	Planned Value	Remarks
VPC	VPC name	vpc-mysql	Customize a name for easy identification.
	Region	EU-Dublin	Currently, only Europe-Dublin is supported.
	AZ	AZ3	-
	Subnet	10.0.0.0/24	Select a subnet with sufficient network resources.
	Subnet name	subnet-mysql	Customize a name for easy identification.
ECS (MySQL	ECS name	ecs-mysql	Customize a name for easy identification.
server)	Specifications	s6.xlarge.2 4 vCPUs 8 GiB	Select specification based on service requirements.
	OS	CentOS 7.6 64	-
	System disk	General purpose SSD 40 GiB	-
	Data disk	Ultra-high I/O, 100 GiB	-
	EIP	Auto assign	Buy an EIP because the public network is selected for the migration task.

Category	Subcategory	Planned Value	Remarks
ECS (MySQL client)	ECS name	ecs-client	Customize a name for easy identification.
	Specifications	s6.xlarge.2 4 vCPUs 8 GiB	Select specification based on service requirements.
	OS	CentOS 7.6 64	-
	System disk	General purpose SSD 40 GiB	-
	Data disk	Not required	-
	EIP	Auto assign	Buy an EIP as needed. If you do not need to access the client through a public network, you do not buy an EIP.
TaurusDB	Instance name	gauss-mysql	Customize a name for easy identification.
	DB engine	TaurusDB	-
	DB engine version	MySQL 8.0	-
	AZ type	Single-AZ	-
	AZ	AZ6	-
	Instance specifications	Dedicated Edition	-
	CPU architecture	x86 8 vCPUs 32 GB	-
DRS	Task name	DRS-TaurusDB	Customize a name.
migration task	Source DB engine	MySQL	In this example, take a MySQL instance (community edition) installed on an ECS as the source database.
	Destination DB engine	TaurusDB	In this example, take a TaurusDB instance as the destination database.
	Network type	Public	In this example, select the public network.

1.3 Operation Process

The process involves creating an ECS, installing a MySQL database on it, buying a TaurusDB instance, and migrating data from the database to the TaurusDB instance.

Figure 1-3 shows the main operation flowchart.



i__.

1.4 Procedure

1.4.1 ECS-hosted MySQL Server

1.4.1.1 Creating a VPC and Security Group

This section describes how to create a VPC and security group for your MySQL server and TaurusDB instance.

Creating a VPC

- **Step 1** Log in to the management console.
- Step 2 Click in the upper left corner of the management console and select EU-Dublin.

Step 3 Click in the upper left corner of the page and choose Network > Virtual Private Cloud VPC.

The VPC console is displayed.

- **Step 4** On the displayed page, click **Create VPC** in the upper right corner.
- **Step 5** Configure required parameters.
- Step 6 Click Create Now.
- **Step 7** Return to the VPC list and check whether the VPC is created.

 If the VPC status becomes available, the VPC has been created.


----End

Creating a Security Group

- **Step 1** Log in to the management console.
- Step 2 Click in the upper left corner of the management console and select EU-Dublin.
- Step 3 Click in the upper left corner of the page and choose Network > Virtual Private Cloud VPC.

The VPC console is displayed.

- **Step 4** In the navigation pane on the left, choose **Access Control** > **Security Groups**.
- **Step 5** Click **Create Security Group** in the upper right corner of the page.
- **Step 6** In the displayed dialog box, configure parameters as needed.
- Step 7 Click OK.
- **Step 8** Return to the security group list, locate the security group **sg-mysql**, and click its name.
- Step 9 Click the Inbound Rules tab, and then click Add Rule.
- **Step 10** Configure an inbound rule to allow access from database port **3306**.



Step 11 Perform **Step 9** to **Step 10** to allow access from database port **22**.

After the rules were configured, the figure similar to the following is displayed.



----End

1.4.1.2 Creating an ECS (MySQL Server)

This section describes how to buy an ECS for installing a MySQL database (community edition).

- **Step 1** Log in to the management console.
- Step 2 Click in the upper left corner of the management console and select EU-Dublin.
- Step 3 Click in the upper left corner of the page and choose Compute > Elastic Cloud Server.
- Step 4 Click Buy ECS.
- **Step 5** Configure ECS parameters.
 - Set Specifications to General computing and select s6.xlarge.2 with 4 vCPUs and 8 GiB.
 - 2. Select the image and disk specifications.

Step 6 Click Next: Configure Network.

- Select the VPC and security group created in Creating a VPC and Security Group.
- 2. Set **EIP** to **Auto assign**, **Billed by** to **Traffic**, and **Bandwidth Size** to **20**. The bandwidth size can be changed as required.

Step 7 Click Next: Configure Advanced Settings.

Specify **ECS Name** and **Password**.

- Step 8 Click Next: Confirm.
- **Step 9** Select an enterprise project and click **Submit**.
- **Step 10** Return to the ECS list page and view the creation progress.

When the ECS status changes to **Running**, the ECS has been created.

----End

1.4.1.3 Installing a MySQL Database (Community Edition)

This section describes how to initialize disks and install a MySQL database (community edition).

Log In to the ECS

- **Step 1** Log in to the management console.
- Step 2 Click in the upper left corner of the management console and select EU-Dublin.
- Step 3 Click in the upper left corner of the page and choose Compute > Elastic Cloud Server
- **Step 4** Locate the ECS **ecs-mysql** and click **Remote Login** in the **Operation** column.
- Step 5 Select CloudShell-based Login.
- **Step 6** Enter the password of user **root**.
 - □ NOTE

The password is the one you specified during the ECS creation.

----End

Initializing Disks

Step 1 Create the **mysql** folder.

mkdir /mysql

Step 2 View data disk information.

fdisk -l

The command output is as follows.

```
[root@ecs-mysql ~]# fdisk -l
Disk /dev/vda: 42.9 GB, 42949672960 bytes, 83886080 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
Disk label type: dos
Disk identifier: 0x000e3a31
   Device Boot
                   Start
                                 End
                                          Blocks
                                                   Id System
/dev/vda1
                     2048
                            83886079
                                        41942016
                                                   83 Linux
Disk /dev/vdb: 107.4 GB, 107374182400 bytes, 209715200 sectors
Units = sectors of 1 * 512 = 512 bytes
Sector size (logical/physical): 512 bytes / 512 bytes
I/O size (minimum/optimal): 512 bytes / 512 bytes
```

Step 3 Initialize the data disk.

mkfs.ext4 /dev/vdb

Step 4 Attach the disk.

mount /dev/vdb /mysql

Step 5 Check whether the disk has been attached.

df -h

If the following output is returned, the disk has been attached.

```
[root@ecs-mysql ~]# df -h
Filesystem
                 Size
                       Used Avail Use% Mounted on
devtmpfs
                 3.9G
                          0
                             3.9G
                                    0% /dev
tmpfs
                 3.9G
                          0
                             3.9G
                                    0% /dev/shm
tmpfs
                 3.9G
                       8.6M
                             3.9G
                                    1% /run
tmpfs
                 3.9G
                          0
                             3.9G
                                    0% /sys/fs/cgroup
/dev/vda1
                       2.2G
                              36G
                                    6% /
                 40G
tmpfs
                          0 783M
                                    0% /run/user/0
                 783M
/dev/vdb
                 99G
                        61M 94G
                                    1% /mysql
```

Step 6 Create a folder and switch to the **install** folder.

mkdir -p /mysql/install/data

mkdir -p /mysql/install/tmp

mkdir -p /mysql/install/file

mkdir -p /mysql/install/log

cd /mysql/install

- Step 7 Download and install the MySQL client.
- **Step 8** Initialize the MySQL client.

/mysql/install/mysql-8.0.22/bin/mysqld --defaults-file= /etc/my.cnf -- initialize-insecure

Step 9 Start the MySQL client.

nohup /mysql/install/mysql-8.0.22/bin/mysqld --defaults-file= /etc/my.cnf &

Step 10 Connect to the MySQL client.

/mysql/install/mysql-8.0.22/bin/mysql

Step 11 Create user **root** and assign the required permissions to it.

grant all privileges on *.* to 'root'@'%' identified by 'xxx' with grant option;FLUSH PRIVILEGES;

----End

1.4.1.4 Creating an ECS and Installing a MySQL Client on It

Step 1 Create an ECS for installing a MySQL client by referring to **Creating an ECS** (MySQL Server).

□ NOTE

- This ECS must be in the same region, AZ, VPC, and security group as the ECS where the MySQL server is deployed.
- · Data disks are not required.
- This ECS name is ecs-client.
- Other parameters are the same as those of the ECS where the MySQL server is deployed.
- **Step 2** Download and install the MySQL client. For details, see **How Can I Install the MySQL Client?**

----End

1.4.2 Cloud Migration

This chapter describes how to create a TaurusDB instance, create a DRS migration task, and migrate data from the ECS-hosted MySQL server to the TaurusDB instance.

1.4.2.1 Creating a TaurusDB Instance

This section describes how to create a TaurusDB instance that is in the same VPC and security group as the ECS-hosted MySQL server.

- **Step 1** Log in to the management console.
- Step 2 Click in the upper left corner of the management console and select EU-Dublin.
- Step 3 Click = in the upper left corner of the page and choose Databases > TaurusDB.
- **Step 4** In the upper right corner, click **Buy DB Instance**.
- **Step 5** Configure the instance name and basic information.
- **Step 6** Configure instance specifications.
- **Step 7** Select the VPC and security group.

The VPC and security group have been created in **Creating a VPC and Security Group**.

- **Step 8** Configure the instance password.
- **Step 9** Configure an enterprise project.

- Step 10 Click Next.
- **Step 11** After confirming the settings, click **Submit**.
- **Step 12** Return to the instance list.

If the instance status becomes **Available**, the instance has been created.

----End

1.4.2.2 Creating a DRS Migration Task

This section describes how to create a DRS migration task to migrate the **sbtest** database from the ECS-hosted MySQL server to the TaurusDB instance.

- **Step 1** Log in to the management console.
- Step 2 Click in the upper left corner of the management console and select EU-Dublin.
- Step 3 Click in the upper left corner of the page and choose Database > Data Replication Service.
- **Step 4** In the upper right corner, click **Create Migration Task**.
- **Step 5** Configure parameters as needed.
 - 1. Specify a task name.
 - Configure replication instance details as needed.
 Set Destination DB Instance to the TaurusDB instance created in Creating a TaurusDB Instance.
 - 3. Set Enterprise Project to default.

Step 6 Click Create Now.

It takes about 5 to 10 minutes to create a replication instance.

- **Step 7** Configure source and destination database information.
 - 1. Configure source database information.
 - 2. Click **Test Connection**.

If a successful connection message is returned, you have logged in to the source database.

- 3. Configure the username and password for the destination database.
- 4. Click Test Connection.

If a successful connection message is returned, you have logged in to the destination database.

- Step 8 Click Next.
- **Step 9** Confirm the users, snapshots, and migration objects to be migrated.

Set Migrate Object to All.

- Step 10 Click Next.
- **Step 11** View pre-check results.
- **Step 12** If the check is complete and the check success rate is 100%, click **Next**.
- Step 13 Click Submit.

Return to the **Online Migration Management** page and check the migration task status.

It takes several minutes to complete.

If the status changes to **Completed**, the migration task has been created.

----End

1.4.2.3 Checking the Migration Results

You can check the migration results with either of the following methods:

Method 1: (Automatically) Check the migration results on the DRS console. DRS can compare migration objects, users, and data of source and destination databases and obtain the migration results.

Method 2: (Manually) Check the migration results on the TaurusDB console. Log in to the destination database to check whether the databases, tables, and data are migrated. Manually confirm the data migration status.

Checking the Migration Results on the DRS Console

- **Step 1** Log in to the management console.
- Step 2 Click in the upper left corner of the management console and select **EU-Dublin**.
- Step 3 Click in the upper left corner of the page and choose Databases > Data Replication Service.
- **Step 4** Click the DRS instance name.
- Step 5 Click Migration Comparison.
- Step 6 Under the Compare Data Validate ALL Rows/Values and Compare Data Double Check During Cutover tabs, check whether the objects of the source database have been migrated to destination database.

----End

Checking the Migration Results on the TaurusDB Console

- **Step 1** Log in to the management console.
- Step 2 Click in the upper left corner of the management console and select EU-

- Step 3 Click = in the upper left corner of the page and choose Databases > TaurusDB.
- **Step 4** Locate the required TaurusDB instance and choose **More** > **Log In** in the **Operation** column.
- **Step 5** In the displayed dialog box, enter the password and click **Test Connection**.
- **Step 6** After the connection test is successful, click **Log In**.
- **Step 7** Check and confirm the destination database name and table name. Check whether the data migration is complete.

----End

Testing TaurusDB Performance

After the migration is complete, test TaurusDB performance by referring to **Performance White Paper**.

2 From Other Cloud MySQL to TaurusDB

2.1 Overview

Description

This section includes the following content:

- Create a TaurusDB instance.
- Migrate data from MySQL on other clouds to TaurusDB.


Prerequisites

- You have registered with Huawei Cloud.
- Your account balance is greater than or equal to \$0 USD.

Deployment Architecture

In this example, the source is a MySQL database on other cloud platforms and the destination is a Huawei Cloud TaurusDB instance. Data is migrated from the source to the destination over a public network. For details about the deployment architecture, see **Figure 2-1**.

Figure 2-1 Deployment architecture



Service List

- Virtual Private Cloud (VPC)
- TaurusDB
- Data Replication Service (DRS)

Before You Start

- The resource planning in this best practice is for demonstration only. Adjust it as needed.
- All settings in this best practice are for reference only. For more information about MySQL migration, see From MySQL to GaussDB(for MySQL) Primary/ Standby.

2.2 Resource Planning

Table 2-1 Resource planning

Categor y	Subcatego ry	Plan	Description
VPC	VPC name	vpc-DRStest	Specify a name that is easy to identify.
	Region	EU-Dublin	To achieve lower network latency, select the region nearest to you.
	AZ	AZ 1	-
	Subnet	10.0.0.0/24	Select a subnet with sufficient network resources.
	Subnet name	subnet-drs01	Specify a name that is easy to identify.
Other cloud MySQL	DB engine version	MySQL 5.7	-
	IP address	10.154.217.42	Enter an IP address.
	Port	3306	-
TaurusD B	Instance name	gauss-drstar	Specify a name that is easy to identify.
instance	DB engine version	MySQL 8.0	-
	AZ type	Single AZ	In this example, a single AZ is used.
			To improve service reliability, select multiple AZs.

Categor y	Subcatego ry	Plan	Description
	AZ	AZ1	AZ1 is selected in this example. To improve service reliability, deploy the instance across multiple AZs.
	Instance class	Dedicated 4 vCPUs 16 GB	-
DRS migratio	Task name	DRS-test-migrate	Specify a name that is easy to identify.
n task	Source DB engine	MySQL	-
	Destinatio n DB engine	TaurusDB	-
	Network type	Public network	Public network is used in this example.

2.3 Creating a VPC and Security Group

Create a VPC and security group for a TaurusDB instance.

Creating a VPC

- **Step 1** Log in to the management console.
- **Step 2** Click in the upper left corner of the management console and select region EU-Dublin.
- **Step 3** Under the service list, choose **Networking** > **Virtual Private Cloud**.
- Step 4 Click Create VPC.
- **Step 5** Configure parameters as needed and click **Create Now**.
- **Step 6** Return to the VPC list and check whether the VPC is created.


 If the VPC status becomes available, the VPC has been created.

----End

Creating a Security Group

- **Step 1** Log in to the management console.
- **Step 2** Click ^ℚ in the upper left corner of the management console and select region EU-Dublin.

- **Step 3** Under the service list, choose **Networking** > **Virtual Private Cloud**.
- **Step 4** In the navigation pane, choose **Access Control** > **Security Groups**.
- **Step 5** Click **Create Security Group**.
- **Step 6** Configure parameters as needed.
- Step 7 Click OK.
- **Step 8** Return to the security group list and click the security group name (**sg-DRS01** in this example).
- Step 9 Click the Inbound Rules tab, and then click Add Rule.
- **Step 10** Configure an inbound rule to allow access from database port **3306**.



----End

2.4 Creating a TaurusDB Instance

This section describes how to create a Huawei Cloud TaurusDB instance.

- **Step 1** Log in to the management console.
- **Step 2** Click in the upper left corner of the management console and select region EU-Dublin.
- **Step 3** Under the service list, choose **Databases** > **TaurusDB**.
- **Step 4** On the **Instances** page, click **Buy DB Instance**.
- **Step 5** Configure the instance name and basic information.
- **Step 6** Configure instance specifications.
- Step 7 Select a VPC and security group for the instance and configure the database port.
 The VPC and security group have been created in Creating a VPC and Security Group.
- **Step 8** Configure the instance password.

- **Step 9** Configure an enterprise project.
- **Step 10** Click **Next**. If you do not need to modify your settings, click **Submit**.
- **Step 11** Return to the instance list. If the instance becomes **Available**, the instance has been created.

----End

2.5 Configuring a MySQL Instance on Other Clouds

Prerequisites

- You have purchased a MySQL instance on other platforms.
- The MySQL account has the migration permissions listed in Permission Requirements.

Permission Requirements

To migrate data from a MySQL database on other clouds to a TaurusDB instance, the following permissions are required.

Table 2-2 Required permissions

Database	Full Migration Permission	Full+Incremental Migration Permission
Source DB (MySQL)	SELECT, SHOW VIEW, and EVENT	SELECT, SHOW VIEW, EVENT, LOCK TABLES, REPLICATION SLAVE, and REPLICATION CLIENT

For details about MySQL authorization operations, see **operation guide**.

Network Configuration

Enable public accessibility for the source database. The method for enabling public accessibility depends on the cloud database vendor. For details, see the official documents of the corresponding cloud database vendor.

2.6 Creating a DRS Migration Task

This section describes how to create a DRS instance and migrate data from a MySQL database on other clouds to a TaurusDB instance.


Pre-migration Check

Before creating a migration task, check the migration environment.

This section describes how to migrate data from a MySQL database to TaurusDB. For details, see **Before You Start**.

Creating a Migration Task


- **Step 1** Log in to the management console.
- **Step 2** Click in the upper left corner of the management console and select region EU-Dublin.
- **Step 3** Under the service list, choose **Databases** > **Data Replication Service**.
- **Step 4** In the upper right corner, click **Create Migration Task**.
- **Step 5** Configure parameters as needed.
 - 1. Specify a migration task name.



2. Configure replication instance details as needed.

Select the TaurusDB instance created in **Creating a TaurusDB Instance** as the destination database.

Figure 2-2 Replication instance information



Step 6 Click Create Now.

It takes about 5 to 10 minutes to create a replication instance.

Step 7 Configure a whitelist for the source database to manage network access.

Add the EIP of the DRS replication instance to the whitelist of the source MySQL database to ensure that the source database can communicate with the DRS instance.

The method for configuring the whitelist depends on the cloud database vendor. For details, see the official documents of the corresponding cloud database vendor.

Step 8 Configure source and destination database information.

- 1. Configure the source database information and click **Test Connection**. If a successful test message is returned, login to the destination is successful.
- 2. Configure destination database information and click **Test Connection**. If a successful test message is returned, login to the destination is successful.

Step 9 Click Next.

Step 10 On the **Set Task** page, select migration accounts and objects.

- Select **No** for **Migrate Account**.
- Select All for Migrate Object.

Step 11 Click **Next**. On the **Check Task** page, check the migration task.

- If any check fails, review the cause and rectify the fault. After the fault is rectified, click **Check Again**.
- If all check items are successful, click Next.

Step 12 Click Submit.

Return to the **Online Migration Management** page and check the migration task status.

It takes several minutes to complete.

If the status changes to **Completed**, the migration task has been created.

□ NOTE

- Currently, MySQL to TaurusDB migration supports two modes: full migration and full +incremental migration.
- If you create a full migration task, the task automatically stops after the full data is migrated to the destination.
- If you create a full+incremental migration task, a full migration is executed first. After the full migration is complete, an incremental migration starts.
- During the incremental migration, data is continuously migrated so the task will not automatically stop.

----End

2.7 Checking Migration Results

You can use either of the following methods to check the migration results:

- DRS compares migration objects, users, and data and provide comparison results. For details, see Checking the Migration Results on the DRS Console.
- 2. Log in to the destination side to check whether the databases, tables, and data are migrated. Confirm the data migration status. For details, see Checking the Migration Results on the TaurusDB Console.

Checking the Migration Results on the DRS Console

- **Step 1** Log in to the management console.
- **Step 2** Click in the upper left corner of the management console and select region EU-Dublin.
- **Step 3** Under the service list, choose **Databases** > **Data Replication Service**.
- **Step 4** Click the DRS instance name.
- **Step 5** Choose **Migration Comparison** and select **Object-Level Comparison** to check whether database objects are missing.
- **Step 6** Click **Data-Level Comparison** and check whether the number of rows of migrated objects is consistent.
- **Step 7** Click **Account-Level Comparison** and check whether the accounts and permissions of the source and destination instances are the same.

----End

Checking the Migration Results on the TaurusDB Console

- **Step 1** Log in to the management console.
- **Step 2** Click in the upper left corner of the management console and select region EU-Dublin.
- **Step 3** Under the service list, choose **Databases** > **TaurusDB**.
- **Step 4** On the **Instances** page, locate the destination instance, and click **Log In** in the **Operation** column.



- **Step 5** In the dialog box that is displayed, enter the password and click **Test Connection**.
- **Step 6** After the connection is successful, click **Log In**.
- **Step 7** Check whether the destination databases and tables are the same as the source instance. Check whether migration is complete.

----End

3 Enabling Read/Write Splitting

3.1 User Authentication

You must have the remote login permission before using a database proxy to log in to databases.

Procedure

- **Step 1** Connect to a TaurusDB instance.
- **Step 2** Check whether the host of the used account contains a proxy address.

SELECT user, host FROM mysql.user;




Obtaining a proxy address:

- 1. Log in to the management console.
- 2. Click $^{\bigcirc}$ in the upper left corner and select a region and a project.
- 3. Click \equiv in the upper left corner of the page, choose **Database** > **TaurusDB**.
- 4. On the **Instances** page, click the instance name.
- 5. In the navigation pane, choose **Database Proxy**. Obtain the proxy address in either of the following ways:


Method 1: In the proxy instance list, locate the proxy instance and view the value in the **Proxy Address** column.

Figure 3-1 Viewing the proxy address in the proxy instance list page



Method 2: In the proxy instance list, click the name of the proxy instance to go to the **Basic Information** page. In the **Proxy Instance Information** area, view the **Proxy Address** field.

Figure 3-2 Viewing the proxy address in the proxy instance information page



Step 3 If the host does not contain the CIDR block where the proxy instance is located, assign the remote access permission to the host.

For example, allowing user **root** to access the TaurusDB server from the IP address range starting with 192.168.0.


Alternatively, set **Host** on the **User Management** page of the DAS console. For details, see .



- **Step 4** When modifying a security group, ensure that the inbound and outbound rules allow access of the proxy address. The default port is **3306**.
 - Log in to the management console.
 - 2. Click \bigcirc in the upper left corner and select a region and a project.
 - 3. Click = in the upper left corner of the page, choose **Database** > **TaurusDB**.
 - 4. On the **Instances** page, click the instance name to go to the **Basic Information** page.


- 5. In the **Network Information** area, click the security group name.
- 6. On the **Inbound Rules** tab, check whether access through port **3306** is allowed by default.

Figure 3-3 Allowing access through port 3306



If this rule does not exist, click **Fast-Add Rule**. In the displayed dialog box, select **MySQL (3306)** and click **OK**.

Figure 3-4 Fast adding port 3306



◯ NOTE

When you use the MySQL 8.0 client to access the read/write splitting of the database, the error message "auth user failed" may be displayed.

Add --default-auth=mysql_native_password when connecting to the database.

----End

3.2 Connection Pool Configuration

When the connection pool is used, you need to configure the following parameters to ensure that some connections will not be used even though they are disconnected due to timeout.

For JDBC connection pool and Druid connection pool:

testOnBorrow = true

• For HikariCP connection pool:

connectionTestQuery = SELECT 1

3.3 Routing Read Requests to the Primary Node

- If there are SELECT statements in transactions, the transaction requests are routed to the primary node. If **SET AUTOCOMMIT=0** is added before a SELECT statement, the transaction requests are routed to the primary node.
- If all read replicas are abnormal or the read weights allocated to the read replicas are 0, requests will be routed to the primary node. You can set read weights allocated to read replicas and primary node after read/write splitting is enabled.
- During the execution of SQL statements:
 - If multi-statements (for example, insert xxx;select xxx) are executed, all subsequent requests will be routed to the primary node. To restore the read/write splitting function, disconnect the connection from your applications and establish a connection again.
 - Read operations with locks (for example, SELECT for UPDATE) will be routed to the primary node.
 - When /*FORCE_MASTER*/ is used, requests will be routed to the primary node.
 - If the HANDLER statement is executed, all subsequent requests will be routed to the primary node by default. To restore read/write splitting, disconnect the connection and reestablish a connection.