

Object Storage Service

.NET SDK Developer Guide

Issue 08
Date 2020-02-18



Copyright © Huawei Technologies Co., Ltd. 2021. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Contents

1 SDK Download Links.....	1
2 Example Programs.....	2
3 Quick Start.....	3
3.1 Before You Start.....	3
3.2 Setting Up an OBS Environment.....	3
3.3 Preparing a Development Environment.....	5
3.4 Installing the SDK.....	5
3.5 Obtaining Endpoints.....	6
3.6 Initializing an Instance of ObsClient.....	6
3.7 Creating a Bucket.....	6
3.8 Uploading an Object.....	7
3.9 Downloading an Object.....	8
3.10 Listing Objects.....	8
3.11 Deleting an Object.....	9
3.12 General Examples of ObsClient.....	9
4 Initialization.....	11
4.1 Configuring the AK/SK.....	11
4.2 Creating an Instance of ObsClient.....	11
4.3 Configuring an Instance of ObsClient.....	12
4.4 Configuring SDK Logging.....	14
5 Bucket Management.....	15
5.1 Creating a Bucket.....	15
5.2 Listing Buckets.....	17
5.3 Deleting a Bucket.....	17
5.4 Identifying Whether a Bucket Exists.....	18
5.5 Obtaining Bucket Metadata.....	18
5.6 Managing Bucket ACLs.....	19
5.7 Management Bucket Policies.....	24
5.8 Obtaining a Bucket Location.....	25
5.9 Obtaining Storage Information About a Bucket.....	26
5.10 Setting or Obtaining a Bucket Quota.....	26
5.11 Setting or Obtaining the Storage Class of a Bucket.....	27

6 Object Upload	30
6.1 Object Upload Overview	30
6.2 Performing a Streaming Upload	31
6.3 Performing a File-Based Upload	31
6.4 Performing an Asynchronous Upload	32
6.5 Obtaining Upload Progress	33
6.6 Creating a Folder	34
6.7 Setting Object Properties	34
6.8 Performing a Multipart Upload	37
6.9 Configuring Lifecycle Management	44
6.10 Performing an Appendable Upload	45
6.11 Performing a Multipart Copy	46
6.12 Performing a Resumable Upload	47
7 Object Download	50
7.1 Object Download Overview	50
7.2 Performing a Streaming Download	50
7.3 Performing a Partial Download	51
7.4 Performing an Asynchronous Download	52
7.5 Obtaining Download Progress	53
7.6 Performing a Conditioned Download	54
7.7 Rewriting Response Headers	55
7.8 Obtaining Customized Metadata	56
7.9 Downloading an Archive Object	57
7.10 Performing a Resumable Download	58
7.11 Processing an Image	61
8 Object Management	62
8.1 Obtaining Object Properties	62
8.2 Managing Object ACLs	63
8.3 Listing Objects	65
8.4 Deleting Objects	68
8.5 Copying an Object	70
8.6 HEAD Object	72
9 Temporarily Authorized Access	74
9.1 Using a Temporary URL for Authorized Access	74
10 Versioning Management	85
10.1 Versioning Overview	85
10.2 Setting Versioning Status for a Bucket	85
10.3 Viewing Versioning Status of a Bucket	88
10.4 Obtaining a Versioning Object	88
10.5 Copying a Versioning Object	89
10.6 Restoring an Archive Object with a Specified Version ID	90

10.7 Listing Versioning Objects.....	90
10.8 Setting or Obtaining a Versioning Object ACL.....	94
10.9 Deleting Versioning Objects.....	96
11 Lifecycle Management.....	97
11.1 Lifecycle Management Overview.....	97
11.2 Setting Lifecycle Rules.....	98
11.3 Viewing Lifecycle Rules.....	99
11.4 Deleting Lifecycle Rules.....	100
12 CORS.....	101
12.1 CORS Overview.....	101
12.2 Setting CORS Rules.....	101
12.3 Viewing CORS Rules.....	102
12.4 Deleting CORS Rules.....	103
13 Access Logging.....	104
13.1 Logging Overview.....	104
13.2 Enabling Bucket Logging.....	104
13.3 Viewing Bucket Logging.....	105
13.4 Disabling Bucket Logging.....	106
14 Static Website Hosting.....	107
14.1 Static Website Hosting Overview.....	107
14.2 Website File Hosting.....	107
14.3 Setting Website Hosting.....	108
14.4 Viewing Website Hosting Settings.....	110
14.5 Deleting Website Hosting Settings.....	110
15 Tag Management.....	112
15.1 Tagging Overview.....	112
15.2 Setting Bucket Tags.....	112
15.3 Viewing Bucket Tags.....	113
15.4 Deleting Bucket Tags.....	114
16 Event Notification.....	115
16.1 Event Notification Overview.....	115
16.2 Configuring Event Notification.....	115
16.3 Viewing Event Notification Settings.....	116
16.4 Disabling Event Notification.....	117
17 Server-Side Encryption.....	119
17.1 Server-Side Encryption Overview.....	119
17.2 Encryption Description.....	119
17.3 Example of Encryption.....	120
18 Troubleshooting.....	123

18.1 OBS Server-Side Error Codes.....	123
18.2 Log Analysis.....	131
18.3 Connection Timeout.....	132
18.4 Unmatched Signatures.....	132
18.5 SDK Custom Exceptions.....	132
18.6 SDK Common Response Headers.....	132
19 FAQ.....	134
19.1 How Can I Perform a Multipart Upload?.....	134
19.2 How Can I Create a Folder?.....	134
19.3 How Can I List All Objects in a Bucket?.....	134
19.4 How Can I Use a URL for Authorized Access?.....	134
19.5 How Can I Upload a Large Object in Multipart Mode?.....	134
19.6 How Can I Set an Object to Be Accessible to Anonymous Users?.....	134
19.7 How Can I Identify the Endpoint and Location of OBS?.....	135
19.8 How Can I Obtain the AK/SK?.....	135
A API Reference.....	136
B Change History.....	137

1 SDK Download Links

SDK Source Codes and API Documentation

- Latest version of OBS .NET SDK source code: Click [here](#) to download.
- Earlier version of OBS .NET SDK: Click [here](#) to download.
- OBS .NET SDK API document: [OBS .NET SDK API Reference](#)

Compatibility

- For details about the version revision records, see [ChangeLog](#).
- Recommended .NET versions: .NET Framework 3.5, 4.0, 4.5, as well as .NET Core 2.0 and 3.1.
- Namespaces: The namespaces used in earlier versions (2.x.x) are reorganized and all public APIs are in namespaces **OBS** and **OBS.Model**.
- API functions: Are redesigned and not compatible with those provided by earlier versions (2.x.x).

2 Example Programs

OBS .NET SDK provides abundant example programs for user reference and direct use. You can obtain example programs from folder **demo** in the OBS .NET SDK development package.

Example programs include:

Sample Code	Describes
BucketOperationsSample	How to use bucket-related APIs.
ObjectOperationsSample	How to use object-related APIs.
TemporarySignatureSample	How to use URLs for authorized access.

3 Quick Start

3.1 Before You Start

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

- Ensure that you are familiar with OBS basic concepts, such as [bucket](#), [object](#), and [AK and SK](#).
- You can see [General Examples of ObsClient](#) to learn how to call OBS .NET SDK APIs in a general manner.
- After an API calling is complete using an instance of **ObsClient**, view whether an exception is thrown. If no, the return value is valid. If yes, the operation fails and you need to obtain the error information from an instance of [SDK custom exceptions](#).
- After an API is successfully called by an instance of **ObsClient**, an instance of [SDK common response headers](#) containing the response headers will be returned.

3.2 Setting Up an OBS Environment

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Step 1 Register a cloud service account.

Before using OBS, ensure that you have a cloud service account.

1. Open a browser.
2. Visit www.huaweicloud.com/en-us/.
3. In the upper right corner of the page, click **Register**.
4. Enter the registration information and click **Register**.

Step 2 Subscribe to OBS.

Ensure that your account balance is sufficient before using OBS.

1. Log in to OBS Console.
2. Click **Billing** in the upper right corner of the page to go to the billing center.
3. Click **Top Up**. The dialog box for top-up is displayed.
4. Top up the account as prompted.
5. After the top-up is successful, close the window and go back to the homepage of the management console.
6. Click **Object Storage Service** to subscribe to OBS and enter OBS Console.

Step 3 Create access keys.

OBS uses AKs and SKs in user accounts for signature verification to ensure that only authorized accounts can access specified OBS resources. Detailed explanations about AK and SK are as follows:

- An access key ID (AK) defines a user who accesses the OBS system. An AK belongs to only one user, but one user can have multiple AKs. The OBS system recognizes the users who access the system by their access key IDs.
- A secret access key (SK) is the key used by users to access OBS. It is the authentication information generated based on the AK and the request header. An SK matches an AK, and they group into a pair.

The procedure is as follows:

1. Log in to OBS Console.
2. In the upper right corner of the page, hover the cursor over the username and choose **My Credentials**.
3. On the **My Credentials** page, select **Access Keys** in the navigation pane on the left.
4. On the **Access Keys** page, click **Create Access Key**.
5. In the **Create Access Key** dialog box that is displayed, enter the password and verification code.

 **NOTE**

- If you have not bound an email address or mobile number, you need to enter only the login password.
 - If you have bound an email address and a mobile number, you can select the verification by either email or mobile phone.
6. Click **OK**.
 7. In the **Download Access Key** dialog box that is displayed, click **OK** to save the access keys to your browser's default download path.
 8. Open the downloaded **credentials.csv** file to obtain the access keys (AK and SK).

 NOTE

- A user can create a maximum of two valid access keys.
- Keep the access key properly. If you click **Cancel** in the dialog box, the access keys will not be downloaded, and cannot be obtained later. You can re-create access keys if you need to use them.

----End

3.3 Preparing a Development Environment

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Download Visual Studio of the latest version from [Microsoft's official website](#) and install it.

3.4 Installing the SDK

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

The following uses OBS .NET SDK of the latest version as an example:

- Step 1** [Download](#) OBS .NET SDK development package.
- Step 2** Decompress the development package to obtain folder **demo** (sample code), folder **cn**, folder **en** (third-party log library **log4net.dll** and SDK library **esdk_obs_.net.dll**), and file **Log4Net.config** (log configuration file).
- Step 3** Start Visual Studio and choose **FILE > New > Project > Templates > Visual C# > Console Application** to create a Console Application project.
- Step 4** Right-click the new project and choose **References > Add Reference** and import file **esdk_obs_.net.dll**.

----End

3.5 Obtaining Endpoints

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

- You can click [here](#) to view the endpoints and regions enabled for OBS.

NOTICE

The SDK allows you to pass endpoints with or without the protocol name. Suppose the endpoint you obtained is **your-endpoint**. The endpoint passed when initializing an instance of **ObsClient** can be **http://your-endpoint**, **https://your-endpoint**, or **your-endpoint**.

3.6 Initializing an Instance of ObsClient

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Each time you want to send an HTTP/HTTPS request to OBS, you must create an instance of **ObsClient**. Sample code is as follows:

```
//Initialize configuration parameters.  
ObsConfig config = new ObsConfig();  
config.Endpoint = "https://your-endpoint";  
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", config);  
// Use the instance to access OBS.
```

NOTE

For more information, see chapter "Initialization."

3.7 Creating a Bucket

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

A bucket is a global namespace of OBS and is a data container. It functions as a root directory of a file system and can store objects. The following code shows how to create a bucket:

```
CreateBucketRequest request = new CreateBucketRequest();  
request.BucketName = "bucketname";  
client.CreateBucket(request);
```

NOTE

- Bucket names are globally unique. Ensure that the bucket you create is named differently from any other bucket.
- A bucket name must comply with the following rules:
 - Contains 3 to 63 characters, chosen from lowercase letters, digits, hyphens (-), and periods (.), and starts with a digit or letter.
 - Cannot be an IP address or similar.
 - Cannot start or end with a hyphen (-) or period (.)
 - Cannot contain two consecutive periods (.), for example, **my..bucket**.
 - Cannot contain periods (.) and hyphens (-) adjacent to each other, for example, **my-.bucket** or **my.-bucket**.
- If you create buckets of the same name, no error will be reported and the bucket properties comply with those set in the first creation request.
- For more information, see [Creating a Bucket](#).

NOTICE

- This parameter is not required if the endpoint belongs to the default region (cn-north-1). Otherwise, set this parameter to the region to which the endpoint belongs. Click [here](#) to query currently valid regions.
 - When creating a bucket, you can specify its region. For details, see [Creating a Bucket with Parameters Specified](#).
-

3.8 Uploading an Object

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Sample code:

```
PutObjectRequest request = new PutObjectRequest  
{  
    BucketName = "bucketname",  
    ObjectKey = "objectname",  
    InputStream = new MemoryStream(Encoding.UTF8.GetBytes("Hello OBS"))  
};  
client.PutObject(request);
```

NOTE

For more information, see [Object Upload Overview](#).

3.9 Downloading an Object

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Sample code:

```
GetObjectRequest request = new GetObjectRequest()
{
    BucketName = "bucketname",
    ObjectKey = "objectname",
};
using (GetObjectResponse response = client.GetObject(request))
{
    //Save the object locally.
    string dest = "savepath";
    if (!File.Exists(dest))
    {
        response.WriteResponseStreamToFile(dest);
    }
}
```

NOTE

For more information, see [Object Download Overview](#).

3.10 Listing Objects

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

After objects are uploaded, you may want to view the objects contained in a bucket. Sample code is as follows:

```
ListObjectsRequest request = new ListObjectsRequest();
request.BucketName = "bucketname";
ListObjectsResponse response = client.ListObjects(request);
foreach (ObsObject Object in response.ObsObjects)
{
    Console.WriteLine("ObjectKey={0}, Size={1}", Object.ObjectKey, Object.Size);
}
```

NOTE

- You can call **ListObjectsResponse.ObsObjects** to obtain the descriptions of all objects.
- In the previous sample code, 1000 objects will be listed, by default.
- For more information, see [Listing Objects](#).

3.11 Deleting an Object

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Sample code:

```
DeleteObjectRequest request = new DeleteObjectRequest()
{
    BucketName = "bucketname",
    ObjectKey = "objectname",
};
client.DeleteObject(request);
```

3.12 General Examples of ObsClient

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

When you call an API in an instance of **ObsClient**, if no exception is thrown, the return value is valid and an instance or a sub-class instance of the **ObsWebServiceResponse** (SDK common response header) is returned. If any exception is thrown, obtain the error information from the instance of **ObsException** (SDK custom exception). **ObsClient** supports synchronous and asynchronous API callings. Examples are as follows:

Synchronous Call

Sample code:

```
ObsClient client;
ObsConfig config = new ObsConfig();
config.Endpoint = "https://your-endpoint";
// Create an instance of ObsClient.
client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", config);
// Call the API for creating a bucket in synchronous mode.
try
{
    CreateBucketRequest request = new CreateBucketRequest
    {
        BucketName = "bucketname",
    };
    CreateBucketResponse response = client.CreateBucket(request);

    Console.WriteLine("Create bucket response: {0}", response.StatusCode);
}
catch (ObsException ex)
```

```
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

Asynchronous Call

Sample code:

```
ObsClient client;  
ObsConfig config = new ObsConfig();  
config.Endpoint = "https://your-endpoint";  
// Create an instance of ObsClient.  
client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", config);  
// Call the API for creating a bucket in asynchronous mode.  
CreateBucketRequest request = new CreateBucketRequest  
{  
    BucketName = "bucketname",  
};  
client.BeginCreateBucket(request, delegate(IAsyncResult ar){  
    try  
    {  
        CreateBucketResponse response = client.EndCreateBucket(ar);  
        Console.WriteLine("Create bucket response: {0}", response.StatusCode);  
    }  
    catch (ObsException ex)  
    {  
        Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
        Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
    }  
}, null);
```

4 Initialization

4.1 Configuring the AK/SK

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

To use OBS, you need a valid pair of AK and SK for signature authentication. For details, see [Setting Up an OBS Environment](#).

After obtaining the AK/SK, you can start initialization.

4.2 Creating an Instance of ObsClient

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

ObsClient functions as the .NET client for accessing OBS. It offers callers a series of APIs for interaction with OBS and is used for managing and operating resources, such as buckets and objects, stored in OBS. To use OBS .NET SDK to send a request to OBS, you need to initialize an instance of **ObsClient** and modify the default configurations in **ObsConfig** based on needs.

- If you use the endpoint to create an instance of **ObsClient**, all parameters are in their default values and cannot be modified.

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
```

```
your-endpoint");
// Use the instance to access OBS.
```

- If you use the **ObsConfig** configuration class to create an instance of **ObsClient**, you can set any parameters as needed during the creation. After the instance has been created, the parameters cannot be modified. For parameter details, see [Configuring an Instance of ObsClient](#)

```
// Create an instance of ObsConfig.
ObsConfig config = new ObsConfig();
config.Endpoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", config);
// Use the instance to access OBS.
```

 **NOTE**

- The project can contain one or more instances of **ObsClient**.
- **ObsClient** is thread-safe and can be simultaneously used by multiple threads.

4.3 Configuring an Instance of ObsClient

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

When you call the **ObsConfig** configuration class to create an instance of **ObsClient**, you can configure the agent, timeout duration, maximum allowed number of connections, and some other parameters listed in the following table.

Parameter	Description	Recommended Value
Endpoint	Endpoint for accessing OBS, which contains the protocol type, domain name (or IP address), and port number. For example, https://your-endpoint:443. For security purposes, you are advised to use HTTPS.	N/A
Timeout	Timeout duration for synchronous callings, in ms. The default value is -1 , which indicates no timeout limitations.	N/A
ReadWriteTimeout	Timeout duration for transmitting data at the Socket layer, in ms. The default value is 60,000.	[10000, 60000]

Parameter	Description	Recommended Value
AsyncSocketTime-out	Timeout duration for asynchronous callings, in ms. The default value is -1 , which indicates no timeout limitations.	N/A
MaxIdleTime	Allowed connection idle time, in ms. If a connection exceeds the specified value, the connection will be closed. The default value is 30,000.	Default
ConnectionLimit	Maximum number of concurrently opened HTTP connections. The default value is 1000.	Default
MaxErrorRetry	Maximum number of retry attempts (caused by abnormal requests, 500 errors, and 503 errors). The default value is 3 .	[1, 5]
ReceiveBufferSize	Size of the socket reception buffer. The default value is 8192 .	[8192, 65536]
SecurityProtocol-Type	Encryption protocol type when HTTPS is used.	N/A
ProxyHost	Host address of the proxy server.	N/A
ProxyPort	Port ID of the proxy server.	N/A
ProxyUserName	User name used for connecting to the proxy server.	N/A
ProxyPassword	Password used for connecting to the proxy server.	N/A
ProxyDomain	Domain to which the proxy belongs	N/A
ValidateCertificate	Whether to verify the server certificate. The default value is false .	N/A
BufferSize	Read or write cache size used for uploading an object to the socket stream, in bytes. The default value is 8192 bytes.	Default
KeepAlive	Whether to use persistent connections to access OBS. The default value is true .	N/A

 NOTE

- Parameters whose recommended value is **N/A** need to be set based on your needs.
- If the network is unstable, you are advised to set larger values for **Timeout AsyncSocketTimeout**, and **ReadWriteTimeout**.
- If the value of **Endpoint** does not contain any protocol, HTTPS is used by default.
- For the sake of high DNS resolution performance and OBS reliability, you can set **Endpoint** only to the domain name of OBS, instead of the IP address.

4.4 Configuring SDK Logging

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

OBS .NET SDK provides the logging function, based on the Apache Log4net open library. You can add log configuration files to enable the logging function. The procedure is as follows:

- Step 1** Add a reference to **log4net.dll** in the project.
- Step 2** Copy configuration file **Log4Net.config** to **Debug** or **Release** under directory **bin** of the project, to ensure that the configuration file and the project's executable files are in the same directory.
- Step 3** Modify log levels in file **Log4Net.config** based on needs.

----End

 NOTE

- Without these operations, the logging function is in the disabled state and no logs will be generated.
- For details about SDK logs, see [Log Analysis](#).
- The save path of log files defaults to be that of the project's executable files and can be changed in **Log4Net.config**.

5 Bucket Management

5.1 Creating a Bucket

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.CreateBucket** to create a bucket.

Creating a Bucket Directly

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("*** Provide your Access Key ***", "*** Provide your Secret Key ***", "https://
your-endpoint");
// Create a bucket.
try
{
    CreateBucketRequest request = new CreateBucketRequest
    {
        BucketName = "bucketname",
    };
    CreateBucketResponse response = client.CreateBucket(request);
    Console.WriteLine("Create bucket response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

 NOTE

- Bucket names are globally unique. Ensure that the bucket you create is named differently from any other bucket.
- A bucket name must comply with the following rules:
 - Contains 3 to 63 characters, chosen from lowercase letters, digits, hyphens (-), and periods (.), and starts with a digit or letter.
 - Cannot be an IP address or similar.
 - Cannot start or end with a hyphen (-) or period (.)
 - Cannot contain two consecutive periods (.), for example, **my.bucket**.
 - Cannot contain periods (.) and hyphens (-) adjacent to each other, for example, **my-.bucket** or **my.bucket**.
- If you create buckets of the same name in a region, no error will be reported and the bucket properties comply with those set in the first creation request.
- The bucket created in the previous example is of the default **ACL (private)**, in the OBS Standard storage class, and in the default region.

NOTICE

- This parameter is not required if the endpoint belongs to the default region (cn-north-1). If the endpoint belongs to a region other than the default one, set this parameter to the region to which the endpoint belongs. Click [here](#) to query currently valid regions.
- When creating a bucket, you can specify its region. For details, see [Creating a Bucket with Parameters Specified](#).

Creating a Bucket with Parameters Specified

When creating a bucket, you can specify the ACL, storage class, and location for the bucket. OBS provides three storage classes for buckets. For details, see [Setting or Obtaining the Storage Class of a Bucket](#). Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Create a bucket.
try
{
    CreateBucketRequest request = new CreateBucketRequest
    {
        BucketName = "bucketname",
        // Set the bucket location.
        Location = "bucketLocation",
        // Set the storage class to OBS Archive.
        StorageClass = StorageClassEnum.Cold,
        // Set the ACL for the bucket to public-read. (The default ACL is private.)
        CannedAcl = CannedAclEnum.Private
    };
    CreateBucketResponse response = client.CreateBucket(request);
    Console.WriteLine("Create bucket response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

5.2 Listing Buckets

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.ListBuckets** to list buckets. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// List buckets.
try
{
    ListBucketsRequest request = new ListBucketsRequest();
    ListBucketsResponse response = client.ListBuckets(request);
    request.IsQueryLocation = true;
    foreach (ObsBucket bucket in response.Buckets)
    {
        Console.WriteLine("Bucket name is : {0}", bucket.BucketName);
        Console.WriteLine("Bucket creationDate is : {0}", bucket.CreationDate);
        Console.WriteLine("Bucket location is : {0}", bucket.Location);
        Console.WriteLine("\n");
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- Obtained bucket names are listed in the lexicographical order.
- Set **ListBucketsRequest.IsQueryLocation** to **true** and then you can query the bucket location when listing buckets.

5.3 Deleting a Bucket

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.DeleteBucket** to delete a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//Delete a bucket.
try
```

```
{
    DeleteBucketRequest request = new DeleteBucketRequest
    {
        BucketName = "bucketname",
    };
    DeleteBucketResponse response = client.DeleteBucket(request);
    Console.WriteLine("Delete bucket response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

 **NOTE**

- Only empty buckets (without objects and part fragments) can be deleted.
- Bucket deletion is a non-idempotence operation and an error will be reported if the to-be-deleted bucket does not exist.

5.4 Identifying Whether a Bucket Exists

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.HeadBucket** to identify whether a bucket exists. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Identify whether a bucket exists.
try
{
    HeadBucketRequest request = new HeadBucketRequest
    {
        BucketName = "bucketname",
    };
    bool exists = client.HeadBucket(request);
    Console.WriteLine("Bucket exists: {0}", exists);
}
catch (ObsException ex)
{
    Console.WriteLine("StatusCode: {0}", ex.StatusCode);
}
```

5.5 Obtaining Bucket Metadata

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketMetadata** to obtain the metadata of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Obtain the bucket metadata.
try
{
    List<string> headers = new List<string>();
    headers.Add("x-obs-header");
    GetBucketMetadataRequest request = new GetBucketMetadataRequest
    {
        BucketName = "bucketname",
        Origin = "http://www.a.com",
        AccessControlRequestHeaders = headers,
    };
    GetBucketMetadataResponse response = client.GetBucketMetadata(request);
    Console.WriteLine("StorageClass: {0}", response.StorageClass);
    Console.WriteLine("Location: {0}", response.Location);
}
catch (ObsException ex)
{
    Console.WriteLine("StatusCode: {0}", ex.StatusCode);
}
```

5.6 Managing Bucket ACLs

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

A bucket [ACL](#) can be configured in three modes:

1. Specify a pre-defined access policy during bucket creation.
2. Call **ObsClient.SetBucketAcl** to specify a pre-defined access policy.
3. Call **ObsClient.SetBucketAcl** to set the ACL directly.

The following table lists the five permission types supported by OBS.

Permission	Description	Value in OBS .NET SDK
READ	A grantee with this permission for a bucket can obtain the list of objects in the bucket and the metadata of the bucket. A grantee with this permission for an object can obtain the object content and metadata.	PermissionEnum.Read

Permission	Description	Value in OBS .NET SDK
WRITE	A grantee with this permission for a bucket can upload, overwrite, and delete any object in the bucket. Such permission for an object is not applicable.	PermissionEnum.Write
READ_ACP	A grantee with this permission can obtain the ACL of a bucket or object. A bucket or object owner has this permission permanently.	PermissionEnum.ReadAcp
WRITE_ACP	A grantee with this permission can update the ACL of a bucket or object. A bucket or object owner has this permission permanently. A grantee with this permission can modify the access control policy and thus the grantee obtains full access permissions.	PermissionEnum.WriteAcp
FULL_CONTROL	A grantee with this permission for a bucket has READ, WRITE, READ_ACP, and WRITE_ACP permissions for the bucket. A grantee with this permission for an object has READ, WRITE, READ_ACP, and WRITE_ACP permissions for the object.	PermissionEnum.FullControl

There are five access control policies pre-defined in OBS, as described in the following table:

Policy	Description	Value in OBS .NET SDK
private	The owner of a bucket or object has the FULL_CONTROL permission for the bucket or object. Other users have no permission to access the bucket or object.	CannedAclEnum.Private

Policy	Description	Value in OBS .NET SDK
public-read	If this permission is set for a bucket, everyone can obtain the list of objects, multipart uploads, and object versions in the bucket, as well as metadata of the bucket. If this permission is set for an object, everyone can obtain the content and metadata of the object.	CannedAclEnum.PublicRead
public-read-write	If this permission is set for a bucket, everyone can obtain the object list in the bucket, multipart uploads in the bucket, metadata of the bucket; upload objects; delete objects; initialize multipart uploads; upload parts; combine parts; copy parts; and abort multipart uploads. If this permission is set for an object, everyone can obtain the content and metadata of the object.	CannedAclEnum.PublicReadWrite
public-read-delivered	If this permission is set for a bucket, everyone can obtain the object list, multipart uploads, and bucket metadata in the bucket, and obtain the content and metadata of the objects in the bucket. This permission cannot be set for objects.	CannedAclEnum.PublicReadDelivered
public-read-write-delivered	If this permission is set for a bucket, everyone can obtain the object list in the bucket, multipart uploads in the bucket, metadata of the bucket; upload objects; delete objects; initialize multipart uploads; upload parts; combine parts; copy parts; abort multipart uploads; and obtain content and metadata of objects in the bucket. This permission cannot be set for objects.	CannedAclEnum.PublicReadWriteDelivered

Specifying a Pre-defined Access Control Policy During Bucket Creation

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
```

```
// Create a bucket.
try
{
    CreateBucketRequest request = new CreateBucketRequest
    {
        BucketName = "bucketname",
        // Set the bucket ACL to public-read-write.
        CannedAcl = CannedAclEnum.PublicReadWrite,
    };
    CreateBucketResponse response = client.CreateBucket(request);
    Console.WriteLine("StatusCode: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Setting a Pre-defined Access Control Policy for the Bucket

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//Set the bucket ACL.
try
{
    SetBucketAclRequest request = new SetBucketAclRequest
    {
        BucketName = "bucketname",
        // Set the bucket ACL to private.
        CannedAcl = CannedAclEnum.Private
    };
    SetBucketAclResponse response = client.SetBucketAcl(request);
    Console.WriteLine("Set bucket acl response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Directly Setting a Bucket ACL

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//Set a bucket ACL.
try
{
    //Set the bucket owner.
    Owner owner = new Owner
    {
        Id = "ownerid", //ID of the domain to which the owner belongs
    };
    AccessControlList acl = new AccessControlList();
    acl.Owner = owner ;

    Grant item = new Grant()
    {
        Grantee = new GroupGrantee()
        {
            GroupGranteeType = GroupGranteeEnum.AllUsers
        },
        Permission = PermissionEnum.FullControl
    };
}
```

```
};

IList<Grant> grants = new List<Grant>();
grants.Add(item);
acl.Grants = grants;

SetBucketAclRequest request = new SetBucketAclRequest()
{
    BucketName = "bucketname",
    AccessControlList = acl
};

SetBucketAclResponse response = client.SetBucketAcl(request);
Console.WriteLine("Set bucket acl response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

The owner or grantee ID needed in the ACL indicates the account ID, which can be viewed on the **My Credentials** page of OBS Console.

Obtaining a Bucket ACL

You can call **ObsClient.GetBucketAcl** to obtain the bucket ACL. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("*** Provide your Access Key ***", "*** Provide your Secret Key ***", "https://your-endpoint");
//Obtain the bucket ACL.
try
{
    GetBucketAclRequest request = new GetBucketAclRequest
    {
        BucketName = "bucketname",
    };
    GetBucketAclResponse response = client.GetBucketAcl(request);
    Console.WriteLine("Get bucket acl response: {0}", response.StatusCode);
    foreach (Grant grant in response.AccessControlList.Grants)
    {
        if (grant.Grantee is CanonicalGrantee)
        {
            Console.WriteLine("Grantee id: {0}", (grant.Grantee as CanonicalGrantee).Id);
        } else if (grant.Grantee is GroupGrantee)
        {
            Console.WriteLine("Grantee type: {0}", (grant.Grantee as GroupGrantee).GroupGranteeType);
        }
        Console.WriteLine("Grant permission: {0}", grant.Permission);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

5.7 Management Bucket Policies

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Besides bucket ACLs, bucket owners can use bucket policies to centrally control access to buckets and objects in buckets.

For more information, see [Bucket Policy](#).

Setting a Bucket Policy

You can call **ObsClient.SetBucketPolicy** to set a bucket policy. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
try
{
    SetBucketPolicyRequest request = new SetBucketPolicyRequest
    {
        BucketName = "bucketname",
        Policy = "your policy",
    };
    SetBucketPolicyResponse response = client.SetBucketPolicy(request);
    Console.WriteLine("Set bucket policy response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

For details about the format (JSON character string) of bucket policies, see the *Object Storage Service API Reference*.

Obtaining a Bucket Policy

You can call **ObsClient.GetBucketPolicy** to obtain a bucket policy. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
try
{
    GetBucketPolicyRequest request = new GetBucketPolicyRequest
    {
        BucketName = "bucketname",
    };
    GetBucketPolicyResponse response = client.GetBucketPolicy(request);
    Console.WriteLine("Get bucket policy response: {0}", response.StatusCode);
}
```

```
    Console.WriteLine("Policy: {0}", response.Policy);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Deleting a Bucket Policy

You can call **ObsClient.DeleteBucketPolicy** to delete a bucket policy. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
try
{
    DeleteBucketPolicyRequest request = new DeleteBucketPolicyRequest
    {
        BucketName = "bucketname",
    };
    DeleteBucketPolicyResponse response = client.DeleteBucketPolicy(request);
    Console.WriteLine("Delete bucket policy response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

5.8 Obtaining a Bucket Location

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketLocation** to obtain the location of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Obtain the bucket location.
try
{
    GetBucketLocationRequest request = new GetBucketLocationRequest
    {
        BucketName = "bucketname",
    };
    GetBucketLocationResponse response = client.GetBucketLocation(request);
    Console.WriteLine("Get bucket location response: {0}", response.StatusCode);
    Console.WriteLine("Location: {0}", response.Location);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

 NOTE

When creating a bucket, you can specify its location. For details, see [Creating a Bucket](#).

5.9 Obtaining Storage Information About a Bucket

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

The storage information about a bucket includes the used capacity of and the number of objects in the bucket. You can call **ObsClient.GetBucketStorageInfo** to obtain the bucket storage information. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("*** Provide your Access Key ***", "*** Provide your Secret Key ***", "https://
your-endpoint");
// Obtain the storage information about a bucket.
try
{
    GetBucketStorageInfoRequest request = new GetBucketStorageInfoRequest
    {
        BucketName = "bucketname",
    };
    GetBucketStorageInfoResponse response = client.GetBucketStorageInfo(request);
    Console.WriteLine("Get bucket storageinfo response: {0}", response.StatusCode);
    Console.WriteLine("ObjectNumber: {0}", response.ObjectNumber);
    Console.WriteLine("Size: {0}", response.Size);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

5.10 Setting or Obtaining a Bucket Quota

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Setting a Bucket Quota

You can call **ObsClient.SetBucketQuota** to set the bucket quota. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("*** Provide your Access Key ***", "*** Provide your Secret Key ***", "https://
your-endpoint");
// Set the bucket quota.
```

```
try
{
    SetBucketQuotaRequest request = new SetBucketQuotaRequest
    {
        BucketName = "bucketname",
        StorageQuota = 0L,
    };
    SetBucketQuotaResponse response = client.SetBucketQuota(request);
    Console.WriteLine("Set bucket quota response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

A bucket quota must be a non-negative integer expressed in bytes. The maximum value is $2^{63} - 1$.

Obtaining the Bucket Quota

You can call **ObsClient.GetBucketQuota** to obtain the bucket quota. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Obtain the bucket quota.
try
{
    GetBucketQuotaRequest request = new GetBucketQuotaRequest
    {
        BucketName = "bucketname",
    };
    GetBucketQuotaResponse response = client.GetBucketQuota(request);
    Console.WriteLine("Get bucket quota response: {0}", response.StatusCode);
    Console.WriteLine("StorageQuota: {0}", response.StorageQuota);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

5.11 Setting or Obtaining the Storage Class of a Bucket

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

OBS allows you to set storage classes for buckets. The storage class of an object defaults to be that of its residing bucket. Different storage classes meet different needs for storage performance and costs. There are three types of storage class for buckets, as described in the following table:

Storage Class	Description	Value in OBS .NET SDK
OBS Standard	Features low access latency and high throughput and is applicable to storing frequently-accessed (multiple times per month) hotspot or small objects (< 1 MB) requiring quick response.	StorageClassEnum.Standard
OBS Infrequent Access	Is applicable to storing semi-frequently accessed (less than 12 times a year) data requiring quick response.	StorageClassEnum.Warm
OBS Archive	Is applicable to archiving rarely-accessed (once a year) data.	StorageClassEnum.Cold

For more information, see [Bucket Storage Classes](#).

Setting the Storage Class for a Bucket

You can call **ObsClient.SetBucketStoragePolicy** to set the storage class for a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Set the storage class for a bucket.
try
{
    SetBucketStoragePolicyRequest request = new SetBucketStoragePolicyRequest
    {
        BucketName = "bucketname",
        StorageClass = StorageClassEnum.Cold,
    };
    SetBucketStoragePolicyResponse response = client.SetBucketStoragePolicy(request);
    Console.WriteLine("Set bucket storage policy response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Obtaining the Storage Class of a Bucket

You can call **ObsClient.GetBucketStoragePolicy** to obtain the storage class. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Obtain the storage class of a bucket.
try
{
    GetBucketStoragePolicyRequest request = new GetBucketStoragePolicyRequest()
    {
        BucketName = "bucketName",
    };
}
```

```
};  
GetBucketStoragePolicyResponse response = client.GetBucketStoragePolicy(request);  
Console.WriteLine("Get bucket storage policy response: {0}", response.StatusCode);  
Console.WriteLine("StorageClass: {0}", response.StorageClass);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

6 Object Upload

6.1 Object Upload Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

In OBS, objects are basic data units that users can perform operations on. OBS .NET SDK provides abundant APIs for object upload in the following methods:

- [Performing a Streaming Upload](#)
- [Performing a File-Based Upload](#)
- [Performing an Asynchronous Upload](#)
- [Performing a Multipart Upload](#)
- [Performing an Appendable Upload](#)
- [Performing a Resumable Upload](#)

The SDK supports the upload of objects whose size ranges from 0 KB to 5 GB. If a file is smaller than 5 GB, streaming upload, appendable upload, and file-based upload are applicable. If the file is larger than 5 GB, multipart upload (whose part size is smaller than 5 GB) is suitable.

If the uploaded object can be read by anonymous users. After the upload succeeds, anonymous users can access the object data through the object URL. The object URL is in the format of **`https://bucket name.domain name/directory levels/object name`**. If the object resides in the root directory of the bucket, its URL does not contain directory levels.

6.2 Performing a Streaming Upload

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Streaming upload uses **System.IO.Stream** as the data source of an object. You can call **ObsClient.PutObject** to upload the data streams to OBS. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Upload a stream.
try
{
    String str = "Hello OBS";
    Stream stream = new MemoryStream(System.Text.Encoding.Default.GetBytes(str));
    PutObjectRequest request = new PutObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        InputStream = stream,
    };
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("put object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- To upload a large file, you are advised to use [multipart upload](#).
- The content to be uploaded cannot exceed 5 GB.

6.3 Performing a File-Based Upload

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

File-based upload uses local files as the data source of objects. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
```

```
// Upload a file.
try
{
    PutObjectRequest request = new PutObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        FilePath = "localfile", // Path of the local file to be uploaded. The file name must be specified.
    };
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("put object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

The content to be uploaded cannot exceed 5 GB.

6.4 Performing an Asynchronous Upload

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.BeginPutObject** and **ObsClient.EndPutObject** to upload an object in asynchronous mode. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Upload a file in asynchronous mode.
try
{
    PutObjectRequest request = new PutObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        FilePath = "localfile", // Path of the local file to be uploaded. The file name must be specified.
    };
    client.BeginPutObject(request, delegate(IAsyncResult ar){
        try
        {
            PutObjectResponse response = client.EndPutObject(ar);
            Console.WriteLine("put object response: {0}", response.StatusCode);
        }
        catch (ObsException ex)
        {
            Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
            Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
        }
    }, null);
}
catch (ObsException ex)
{
    Console.WriteLine("Message: {0}", ex.Message);
}
```

6.5 Obtaining Upload Progress

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **PutObjectRequest.UploadProgress** to register with the **System.EventHandler** callback function to obtain upload progress. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Upload a file.
try
{
    PutObjectRequest request = new PutObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        FilePath = "localfile", // Path of the local file uploaded. The file name must be specified.
    };
    // Represent the progress by showing how many bytes have been uploaded.
    request.ProgressType = ProgressTypeEnum.ByBytes;
    // Refresh the upload progress each time 1 MB data is uploaded.
    request.ProgressInterval = 1024 * 1024;

    // Register the upload progress callback function.
    request.UploadProgress += delegate(object sender, TransferStatus status){
        // Obtain the average upload rate.
        Console.WriteLine("AverageSpeed: {0}", status.AverageSpeed / 1024 + "KB/S");
        // Obtain the upload progress in percentage.
        Console.WriteLine("TransferPercentage: {0}", status.TransferPercentage);
    };
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("put object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

You can query the upload progress when uploading an object in streaming, file-based, asynchronous, resumable, or appendable mode, or uploading a part.

6.6 Creating a Folder

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

There is no folder concept in OBS. All elements in buckets are objects. To create a folder in OBS is essentially to create an object whose size is 0 and whose name ends with a slash (/). Such objects have no difference from other objects and can be downloaded and deleted, except that they are displayed as folders in OBS Console.

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Create a folder.
try
{
    PutObjectRequest request = new PutObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "dir/",
    };
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("put object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- To create a folder in OBS is to create an object whose size is 0 and whose name ends with a slash (/), in essential.
- To create a multi-level folder, you only need to create the folder with the last level. For example, if you want to create a folder named **src1/src2/src3/**, create it directly, no matter whether the **src1/** and **src1/src2/** folders exist.

6.7 Setting Object Properties

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can set properties for an object when uploading it. Object properties include the MIME type, MD5 value (for verification), storage class, and customized

metadata. You can set properties for an object that is being uploaded in streaming, file-based, or multipart mode or when **copying the object**.

The following table describes object properties.

Property Name	Description	Default Value
Content-Type	Indicates the MIME type of the object, which defines the type and network code of the object as well as in which mode and coding will the browser read the object.	binary/octet-stream
Content-MD5	Indicates the base64-encoded digest of the object data. It is provided to the OBS server to verify data integrity.	N/A
Storage class	Indicates the storage class of the object. Different storage classes meet different needs for storage performance and costs. The value defaults to be the same as the object's residing bucket and can be changed.	N/A
Customized metadata	Indicates the user-defined description of the object. It is used to facilitate the customized management on the object.	N/A

Setting the MIME Type for an Object

You can call **PutObjectRequest.ContentType** to set the MIME type for an object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Upload a file.
try
{
    PutObjectRequest request = new PutObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        FilePath = "localfile", // Path of the local file uploaded. The file name must be specified.
        ContentType = "image/jpeg", // MIME type of the object
    };
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("put object response: {0}", response.StatusCode);
}
catch (ObsException ex)
```

```
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

NOTE

If the MIME type is not specified, the SDK will automatically identify the MIME type according to the name suffix of the uploaded object. For example, if the name suffix of an object is `.xml` (`.html`), the object will be identified as an `application/xml` (`text/html`) file.

Setting the MD5 Value for an Object

You can call `PutObjectRequest.ContentMd5` to set the MD5 value for an object. Sample code is as follows:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
// Upload a file.  
try  
{  
    PutObjectRequest request = new PutObjectRequest  
    {  
        BucketName = "bucketname",  
        ObjectKey = "objectname",  
        FilePath = "localfile", // Path of the local file uploaded. The file name must be specified.  
        ContentMd5 = "your md5 which should be encoded by base64"  
    };  
    PutObjectResponse response = client.PutObject(request);  
    Console.WriteLine("put object response: {0}", response.StatusCode);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

NOTE

- The MD5 value of an object must be a base64-encoded digest.
- The OBS server will compare this MD5 value with the MD5 value obtained by object data calculation. If the two values are not the same, the upload fails with HTTP status code **400** returned.
- If the MD5 value is not specified, the OBS server will skip MD5 value verification.

Setting the Storage Class for an Object

You can call `PutObjectRequest.StorageClass` to set the storage class for an object. Sample code is as follows:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
// Upload a file.  
try  
{  
    PutObjectRequest request = new PutObjectRequest  
    {  
        BucketName = "bucketname",  
        ObjectKey = "objectname",  
        FilePath = "localfile", // Path of the local file uploaded. The file name must be specified.  
        StorageClass = StorageClassEnum.Warm, // Object storage class  
    };  
}
```

```
PutObjectResponse response = client.PutObject(request);
Console.WriteLine("put object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- If you have not set the storage class for an object, the storage class of the object will be the same as that of its residing bucket.
- OBS provides objects with three storage classes which are consistent with [those](#) provided for buckets.
- Before downloading an Archive object, you must restore it.

Customizing Metadata for an Object

You can call **PutObjectRequest.Metadata** to customize metadata for an object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Upload a file.
try
{
    PutObjectRequest request = new PutObjectRequest
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        FilePath = "localfile", // Path of the local file uploaded. The file name must be specified.
    };
    request.Metadata.Add("meta1", "value1");
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("put object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- An object can have multiple pieces of metadata. The total metadata size cannot exceed 8 KB.
- The customized object metadata can be obtained by using **ObsClient.GetObjectMetadata**. For details, see [Obtaining Object Properties](#).
- When you call **ObsClient.GetObject** to download an object, its customized metadata will also be downloaded.

6.8 Performing a Multipart Upload

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

To upload a large file, multipart upload is recommended. Multipart upload is applicable to many scenarios, including:

- Files to be uploaded are larger than 100 MB.
- The network condition is poor. Connection to the OBS server is constantly down.
- Sizes of files to be uploaded are uncertain.

Multipart upload consists of three phases:

Step 1 Initialize a multipart upload (**ObsClient.InitiateMultipartUpload**).

Step 2 Upload parts one by one or concurrently (**ObsClient.UploadPart**).

Step 3 Combine parts (**ObsClient.CompleteMultipartUpload**) or abort the multipart upload (**ObsClient.AbortMultipartUpload**).

----End

Initializing a Multipart Upload

Before upload, you need to notify OBS of initializing a multipart upload. This operation will return an upload ID (globally unique identifier) created by the OBS server to identify the multipart upload. You can use this upload ID to initiate related operations, such as aborting a multipart upload, listing multipart uploads, and listing uploaded parts.

You can call **ObsClient.InitiateMultipartUpload** to initialize a multipart upload.

NOTE

- Call **InitiateMultipartUploadRequest** to specify the name and owning bucket of the uploaded object.
- In **InitiateMultipartUploadRequest**, you can specify the MIME type, storage class, and customized metadata for the object.
- The upload ID of the multipart upload returned by **InitiateMultipartUploadResponse.UploadId** will be used in follow-up operations.

Uploading Parts

After initializing a multipart upload, you can specify the object name and upload ID to upload a part. Each upload part has a part number (ranging from 1 to 10000). For parts with the same upload ID, their part numbers are unique and identify their comparative locations in the object. If you use the same part number to upload two parts, the latter one being uploaded will overwrite the former. Except for the last uploaded part whose size ranges from 0 to 5 GB, sizes of the other parts range from 100 KB to 5 GB. Parts are uploaded in random order and can be uploaded through different processes or machines. OBS will combine them into the object based on their part numbers.

You can call **ObsClient.UploadPart** to upload a part.

 NOTE

- Except the part last uploaded, other parts must be larger than 100 KB. Part sizes will not be verified during upload because which one is last uploaded is not identified until parts are combined.
- OBS will return ETags (MD5 values) of the received parts to users.
- Part numbers range from 1 to 10000. If a part number exceeds this range, OBS will return error **400 Bad Request**.
- The minimum part size supported by an OBS 3.0 bucket is 100 KB, and the minimum part size supported by an OBS 2.0 bucket is 5 MB. You are advised to perform multipart upload to OBS 3.0 buckets.

Combining Parts

After all parts are uploaded, call the API for combining parts to generate the object. Before this operation, valid part numbers and ETags of all parts must be sent to OBS. After receiving this information, OBS verifies the validity of each part one by one. After all parts pass the verification, OBS combines these parts to form the final object.

You can call **ObsClient.CompleteMultipartUpload** to combine parts.

 NOTE

Part numbers can be inconsecutive.

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
try
{
    // 1. Initialize a multipart upload.
    InitiateMultipartUploadRequest initiateRequest = new InitiateMultipartUploadRequest
    {
        BucketName = "bucketname",
        ObjectKey = "objectname"
    };

    InitiateMultipartUploadResponse initResponse = client.InitiateMultipartUpload(initiateRequest);
    Console.WriteLine("InitiateMultipartUpload status: {0}", initResponse.StatusCode);
    Console.WriteLine("InitiateMultipartUpload UploadId: {0}", initResponse.UploadId);

    // 2. Upload parts.
    string filePath = "localfile";// Path of the local file uploaded. The file name must be specified.
    long contentLength = new FileInfo(filePath).Length;
    long partSize = 15 * (long)Math.Pow(2, 20); // The part size is 15 MB.
    List<UploadPartResponse> uploadResponses = new List<UploadPartResponse>();
    long filePosition = 0;
    for (int i = 1; filePosition < contentLength; i++)
    {
        UploadPartRequest uploadRequest = new UploadPartRequest
        {
            BucketName = "bucketname",
            ObjectKey = "objectname",
            UploadId = initResponse.UploadId,
            PartNumber = i,
            PartSize = partSize,
            Offset = filePosition,
            FilePath = filePath
        };
        uploadResponses.Add(client.UploadPart(uploadRequest));
    }
}
```

```
        Console.WriteLine("UploadPart count: {0}", uploadResponses.Count);
        filePosition += partSize;
    }

    // 3. Combine parts.

    CompleteMultipartUploadRequest completeRequest = new CompleteMultipartUploadRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        UploadId = initResponse.UploadId,
    };
    completeRequest.AddPartETags(uploadResponses);
    CompleteMultipartUploadResponse completeUploadResponse =
client.CompleteMultipartUpload(completeRequest);
    Console.WriteLine("CompleteMultipartUpload status: {0}", completeUploadResponse.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("Exception:{0}", ex.ErrorCode);
    Console.WriteLine("Exception Message:{0}", ex.ErrorMessage);
}
```

Aborting a Multipart Upload

After a multipart upload is aborted, you cannot use its upload ID to perform any operation and the uploaded parts will be deleted by OBS.

When an object is being uploaded in multi-part mode or an object fails to be uploaded, parts are generated in the bucket. These parts occupy your storage space. You can cancel the multi-part uploading task to delete unnecessary parts, thereby saving the storage space.

You can call **ObsClient.AbortMultipartUpload** to abort a multipart upload. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//Abort a multipart upload.
try
{
    AbortMultipartUploadRequest request = new AbortMultipartUploadRequest
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        UploadId = "uploadId", //ID of the multipart upload to be aborted
    };
    AbortMultipartUploadResponse response = client.AbortMultipartUpload(request);
    Console.WriteLine("Abort multipart upload response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing Uploaded Parts

You can call **ObsClient.ListParts** to list successfully uploaded parts of a multipart upload.

The following table describes the parameters involved in this API.

Parameter	Description	Property in OBS .NET SDK
BucketName	Bucket name	ListPartsRequest.BucketName
ObjectKey	Object name	ListPartsRequest.ObjectKey
UploadId	Upload ID, which globally identifies a multipart upload. The value is in the returned result of InitiateMultipartUpload .	ListPartsRequest.UploadId
MaxParts	Maximum number of parts that can be listed per page.	ListPartsRequest.MaxParts
PartNumberMarker	Part number after which listing parts begins. Only parts whose part numbers are larger than this value will be listed.	ListPartsRequest.PartNumberMarker

- Listing parts in simple mode

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Simple listing
try
{
    ListPartsRequest request = new ListPartsRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    request.UploadId = "uploadId";
    ListPartsResponse response = client.ListParts(request);
    Console.WriteLine("List parts response: {0}", response.StatusCode);
    foreach (PartDetail part in response.Parts)
    {
        Console.WriteLine("PartNumber: " + part.PartNumber);
        Console.WriteLine("Size: " + part.Size);
        Console.WriteLine("ETag: " + part.ETag);
        Console.WriteLine("LastModified: " + part.LastModified);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

 **NOTE**

Information about a maximum of 1000 parts can be listed each time. If an upload of the specific upload ID contains more than 1000 parts and **ListPartsResult.isTruncated** is **true** in the returned result, not all parts are listed. In such cases, you can use **ListPartsRespon.NextPartNumberMarker** to obtain the start position for next listing.

- Listing all parts

If the number of parts of a multipart upload is larger than 1000, you can use the following sample code to list all parts.

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// List all parts.
try
{
    ListPartsRequest request = new ListPartsRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    request.UploadId = "uploadId";
    ListPartsResponse response;
    do
    {
        response = client.ListParts(request);
        Console.WriteLine("List parts response: {0}", response.StatusCode);
        foreach (PartDetail part in response.Parts)
        {
            Console.WriteLine("PartNumber: " + part.PartNumber);
            Console.WriteLine("Size: " + part.Size);
            Console.WriteLine("ETag: " + part.ETag);
            Console.WriteLine("LastModified: " + part.LastModified);
        }
        request.PartNumberMarker = response.NextPartNumberMarker;
    }
    while (response.IsTruncated);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing Multipart Uploads

You can call **ObsClient.ListMultipartUploads** to list multipart uploads. The following table describes related parameters.

Parameter	Description	Property in OBS .NET SDK
BucketName	Bucket name	ListMultipartUploadsRequest.BucketName
Prefix	Prefix that the object names in the multipart uploads to be listed must contain	ListMultipartUploadsRequest.Prefix
Delimiter	Character used to group object names involved in multipart uploads. If the object name contains the Delimiter parameter, the character string from the first character to the first delimiter in the object name is grouped under a single result element, CommonPrefix . (If a prefix is specified in the request, the prefix must be removed from the object name.)	ListMultipartUploadsRequest.Delimiter

Parameter	Description	Property in OBS .NET SDK
MaxUploads	Maximum number of listed multipart uploads. The value ranges from 1 to 1000. If the value is not in this range, 1000 parts are listed by default.	ListMultipartUploadsRequest.MaxUploads
KeyMarker	Object name to start with when listing multipart uploads	ListMultipartUploadsRequest.KeyMarker
UploadIdMarker	Upload ID after which the multipart upload listing begins. It is effective only when used with KeyMarker so that multipart uploads after UploadIdMarker of KeyMarker will be listed.	ListMultipartUploadsRequest.UploadIdMarker

- Listing multipart uploads in simple mode

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
//List multipart uploads in simple mode.
try
{
    ListMultipartUploadsRequest listMultipartUploadsRequest = new ListMultipartUploadsRequest();
    listMultipartUploadsRequest.BucketName = "bucketname";
    ListMultipartUploadsResponse listMultipartUploadsResponse =
client.ListMultipartUploads(listMultipartUploadsRequest);
    Console.WriteLine("ListMultipartUploadsResponse status code: " +
listMultipartUploadsResponse.StatusCode);
    foreach (MultipartUpload upload in listMultipartUploadsResponse.MultipartUploads)
    {
        Console.WriteLine("ObjectKey {0}: ", upload.ObjectKey);
        Console.WriteLine("Initiated {0}: ", upload.Initiated);
        Console.WriteLine("\n");
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

 **NOTE**

- Information about a maximum of 1000 multipart uploads can be listed each time. If a bucket contains more than 1000 multipart uploads and **ListMultipartUploadsResponse.isTruncated** is **true**, not all uploads are listed. In such cases, you can use **ListMultipartUploadsResponse.NextKeyMarker** and **ListMultipartUploadsResponse.NextUploadIdMarker** to obtain the start position for next listing.
- If you want to obtain all multipart uploads in a bucket, you can list them in paging mode.
- Listing all multipart uploads in paging mode

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
```

```
your-endpoint");
//List all multipart uploads.
try
{
    ListMultipartUploadsRequest request = new ListMultipartUploadsRequest();
    request.BucketName = "bucketname";
    ListMultipartUploadsResponse response;
    do
    {
        response = client.ListMultipartUploads(request);
        Console.WriteLine("ListMultipartUploadsResponse status code: " + response.StatusCode);
        foreach (MultipartUpload upload in response.MultipartUploads)
        {
            Console.WriteLine("ObjectKey {0}: ", upload.ObjectKey);
            Console.WriteLine("Initiated {0}: ", upload.Initiated);
            Console.WriteLine("\n");
        }
        request.KeyMarker = response.NextKeyMarker;
        request.UploadIdMarker = response.NextUploadIdMarker;
    }
    while (response.IsTruncated);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

6.9 Configuring Lifecycle Management

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

When uploading an object or initializing a multipart upload, you can directly set the expiration time for the object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");

try
{
    PutObjectRequest request = new PutObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        FilePath = "localfile", // Path of the local file uploaded. The file name must be specified.
        Expires = 30 // When uploading an object, set the object to expire after 30 days.
    };
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("put object response: {0}", response.StatusCode);

    InitiateMultipartUploadRequest initiateRequest = new InitiateMultipartUploadRequest
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        // When initializing a multipart upload, set the object to expire 60 days after combination.
        Expires = 60
    };
};
```

```
InitiateMultipartUploadResponse initResponse = client.InitiateMultipartUpload(initiateRequest);
Console.WriteLine("InitiateMultipartUpload status: {0}", initResponse.StatusCode);
Console.WriteLine("InitiateMultipartUpload UploadId: {0}", initResponse.UploadId);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- The previous mode specifies the time duration in days after which an object will expire. The OBS server automatically clears expired objects.
- The object expiration time set in the preceding method takes precedence over the bucket lifecycle rule.

6.10 Performing an Appendable Upload

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Appendable upload allows you to upload an object in appendable mode and then append data to the object. You can call **ObsClient.AppendObject** to perform an appendable upload. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
try
{
    // Upload an object in appendable mode.
    AppendObjectRequest request = new AppendObjectRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectkey";
    request.InputStream = new MemoryStream(Encoding.UTF8.GetBytes("Hello OBS"));

    AppendObjectResponse response = client.AppendObject(request);

    // Append data to the object.
    request.Position = response.NextPosition;
    request.InputStream = new MemoryStream(Encoding.UTF8.GetBytes("Hello OBS Again"));
    response = client.AppendObject(request);
    Console.WriteLine("NextPosition:{0}", response.NextPosition);
    Console.WriteLine("ETag:{0}", response.ETag);

    // Use the API for obtaining object properties to get the start position for next appending.
    GetObjectMetadataResponse metadataResponse = client.GetObjectMetadata("bucketname", "objectkey");
    Console.WriteLine("NextPosition from metadata:{0}", metadataResponse.NextPosition);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

 NOTE

- Objects uploaded using **ObsClient.PutObject**, referred to as normal objects, can overwrite objects uploaded using **ObsClient.AppendObject**, referred to as appendable objects. Data cannot be appended to an appendable object once the object has been overwritten by a normal object.
- When you upload an object for the first time in appendable mode, an exception will be thrown (status code **409**) if a normal object with the same name exists.
- The ETag returned for each append upload is the ETag for the uploaded content, rather than that of the whole object.
- Data appended each time can be up to 5 GB, and 10000 times of appendable uploads can be performed on a single object.
- After an appendable upload is successful, you can use **AppendObjectResponse.NextPosition** or call **ObsClient.GetObjectMetadata** to get the start position for next appending.

6.11 Performing a Multipart Copy

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

As a special case of multipart upload, multipart copy implements multipart upload by copying the whole or part of an object in a bucket. You can call **ObsClient.CopyPart** to copy parts. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Copy parts.
try
{
    CopyPartRequest request = new CopyPartRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    request.UploadId = "uploadId";
    request.PartNumber = 1;
    request.SourceBucketName = "sourcebucketname";
    request.SourceObjectKey = "sourceobjectname";
    CopyPartResponse response = client.CopyPart(request);
    Console.WriteLine("Copy part response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

6.12 Performing a Resumable Upload

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Uploading large files often fails due to poor network conditions or program breakdowns. It is a waste of resources to restart the upload process upon an upload failure, and the restarted upload process may still suffer from the unstable network. To resolve such issues, you can use the API for resumable upload, whose working principle is to divide the to-be-uploaded file into multiple parts and upload them separately. The upload result of each part is recorded in a checkpoint file in real time. Only when all parts are successfully uploaded, the result indicating a successful upload is returned. Otherwise, an exception is thrown to remind you of calling the API again for re-uploading. Based on the upload status of each part recorded in the checkpoint file, the re-uploading will upload the parts failed to be uploaded previously, instead of uploading all parts. By virtue of this, resources are saved and efficiency is improved.

You can call **ObsClient.UploadFile** to perform a resumable upload. The following table describes the parameters involved in this API.

Parameter	Description	Property in OBS .NET SDK
BucketName	(Mandatory) Bucket name	UploadFileRequest.BucketName
ObjectKey	(Mandatory) Object name	UploadFileRequest.ObjectKey
UploadFile	(Mandatory) Path to the local file to be uploaded	UploadFileRequest.UploadFile
UploadPartSize	Part size, in bytes. The value ranges from 5 MB (default) to 5 GB.	UploadFileRequest.UploadPartSize
EnableCheckpoint	Whether to enable the resumable upload mode. The default value is false , which indicates that this mode is disabled.	UploadFileRequest.EnableCheckpoint

Parameter	Description	Property in OBS .NET SDK
CheckpointFile	File used to record the upload progress. This parameter is effective only in the resumable upload mode. If the value is null, the file is in the same directory as the local file to be uploaded.	UploadFileRequest.CheckpointFile
Metadata	Customized metadata of the object	UploadFileRequest.Metadata
EnableCheckSum	Whether to verify the content of the to-be-uploaded file. This parameter is effective only in the resumable upload mode. The default value is false , which indicates that the content will not be verified.	UploadFileRequest.EnableCheckSum
TaskNum	Maximum number of parts that can be concurrently uploaded. The default value is 1 .	UploadFileRequest.TaskNum
UploadProgress	Upload progress callback function	UploadFileRequest.UploadProgress
ProgressType	Mode for representing the upload progress	UploadFileRequest.ProgressType
ProgressInterval	Interval for refreshing the upload progress	UploadFileRequest.ProgressInterval
UploadEventHandler	Upload event callback function	UploadFileRequest.UploadEventHandler

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Perform a resumable upload.
try
{
    UploadFileRequest request = new UploadFileRequest
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        // Specify the local file to be uploaded.
        UploadFile = "localpath",
        // Set the part size to 10 MB.
        UploadPartSize = 10 * 1024 * 1024,
        // Enable the resumable download mode.
        EnableCheckpoint = true,
    };
};
```

```
// Represent the progress by showing how many bytes has been uploaded.
request.ProgressType = ProgressTypeEnum.ByBytes;
// Refresh the upload progress each time 1 MB data is uploaded.
request.ProgressInterval = 1024 * 1024;

// Register the upload progress callback function.
request.UploadProgress += delegate(object sender, TransferStatus status){
    // Obtain the average upload rate.
    Console.WriteLine("AverageSpeed: {0}", status.AverageSpeed / 1024 + "KB/S");
    // Obtain the upload progress in percentage.
    Console.WriteLine("TransferPercentage: {0}", status.TransferPercentage);
};

// Register the upload event callback function.
request.UploadEventHandler += delegate(object sender, ResumableUploadEvent e){
    // Obtain the upload events.
    Console.WriteLine("EventType: {0}", e.EventType);
};

CompleteMultipartUploadResponse response = client.UploadFile(request);
Console.WriteLine("Upload File response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- The API for resumable upload, which is implemented based on [multipart upload](#), is an encapsulated and enhanced version of multipart upload.
- This API saves resources and improves efficiency upon the re-upload, and speeds up the upload process by concurrently uploading parts. Because this API is transparent to users, users are free from concerns about internal service details, such as the creation and deletion of checkpoint files, division of objects, and concurrent upload of parts.
- The default value of the **EnableCheckpoint** parameter is **false**, which indicates that the resumable upload mode is disabled. In such cases, the API for resumable upload degrades to the simple encapsulation of multipart upload, and no checkpoint file will be generated.
- The **CheckpointFile** and **EnableChecksum** parameters are valid only when **EnableCheckpoint** is **true**.

7 Object Download

7.1 Object Download Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

OBS .NET SDK provides abundant APIs for downloading objects in the following modes:

- [Performing a Streaming Download](#)
- [Performing a Partial Download](#)
- [Performing an Asynchronous Download](#)
- [Performing a Conditioned Download](#)
- [Performing a Resumable Download](#)

You can call `ObsClient.GetObject` to download an object.

7.2 Performing a Streaming Download

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Sample code:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");
```

```
// Download an object.
try
{
    GetObjectRequest request = new GetObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
    };
    using (GetObjectResponse response = client.GetObject(request))
    {
        string dest = "savepath";
        if (!File.Exists(dest))
        {
            // Write the data streams into the file.
            response.WriteResponseStreamToFile(dest);
        }
        Console.WriteLine("Get object response: {0}", response.StatusCode);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

GetObjectResponse.OutputStream (**System.IO.Stream** type) is the response stream in **GetObjectResponse**. You can obtain the object content to a local file or memory via **GetObjectResponse.OutputStream**. Alternatively, you can call **GetObjectResponse.WriteResponseStreamToFile** provided by OBS .NET SDK to download the object content to a local file.

NOTICE

Object response streams obtained by **GetObjectResponse.OutputStream** must be closed explicitly. Otherwise, resource leakage may occur.

7.3 Performing a Partial Download

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

When only partial data of an object is required, you can download data falling within a specific range. If the specified range is 0 to 1000, data at the 0th to the 1000th bytes, 1001 bytes in total, will be returned. If the specified range is invalid, data of the whole object will be returned. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Download an object.
try
{
    ByteRange byteRange = new ByteRange(10, 200);
```

```
GetObjectRequest request = new GetObjectRequest()
{
    BucketName = "bucketname",
    ObjectKey = "objectname",
    ByteRange = byteRange,
};
using (GetObjectResponse response = client.GetObject(request))
{
    string dest = "savepath";
    if (!File.Exists(dest))
    {
        response.WriteResponseStreamToFile(dest);
    }
    Console.WriteLine("Get object response: {0}", response.StatusCode);
}
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

7.4 Performing an Asynchronous Download

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.BeginGetObject** and **ObsClient.EndGetObject** to download an object in asynchronous mode. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Download an object in asynchronous mode.
try
{
    GetObjectRequest request = new GetObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
    };
    client.BeginGetObject(request, delegate(IAsyncResult ar){
        try
        {
            using (GetObjectResponse response = client.EndGetObject(ar))
            {
                string dest = "savepath";
                if (!File.Exists(dest))
                {
                    // Write the data streams into the file.
                    response.WriteResponseStreamToFile(dest);
                }
                Console.WriteLine("Get object response: {0}", response.StatusCode);
            }
        }
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

```
    }, null);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("Message: {0}", ex.Message);  
}
```

7.5 Obtaining Download Progress

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **GetObjectRequest.DownloadProgress** to register the **System.EventHandler** callback function to obtain download progress. Sample code is as follows:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
// Download an object.  
try  
{  
    GetObjectRequest request = new GetObjectRequest()  
    {  
        BucketName = "bucketname",  
        ObjectKey = "objectname",  
    };  
    // Represent the progress by showing how many bytes has been downloaded.  
    request.ProgressType = ProgressTypeEnum.ByBytes;  
    // Refresh the download progress each time 1 MB data is downloaded.  
    request.ProgressInterval = 1024 * 1024;  
  
    // Register the download progress callback function.  
    request.DownloadProgress += delegate(object sender, TransferStatus status){  
        // Obtain the average download rate.  
        Console.WriteLine("AverageSpeed: {0}", status.AverageSpeed / 1024 + "KB/S");  
        // Obtain the download progress in percentage.  
        Console.WriteLine("TransferPercentage: {0}", status.TransferPercentage);  
    };  
    using (GetObjectResponse response = client.GetObject(request))  
    {  
        string dest = "savepath";  
        if (!File.Exists(dest))  
        {  
            // Write the data streams into the file.  
            response.WriteResponseStreamToFile(dest);  
        }  
        Console.WriteLine("Get object response: {0}", response.StatusCode);  
    }  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

 NOTE

You can obtain the download progress when downloading an object in streaming, partial, asynchronous, or resumable mode.

7.6 Performing a Conditioned Download

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

When downloading an object, you can specify one or more conditions. Only when the conditions are met, the object will be downloaded. Otherwise, an exception indicating a download failure will be thrown.

You can set the following conditions:

Parameter	Description	Property in OBS .NET SDK
If-Modified-Since	Returns the object if it is modified after the time specified by this parameter; otherwise, an exception is thrown.	GetObjectRequest.IfModifiedSince
If-Unmodified-Since	Returns the object if it remains unchanged since the time specified by this parameter; otherwise, an exception is thrown.	GetObjectRequest.IfUnmodifiedSince
If-Match	Returns the source object if its ETag is the same as the one specified by this parameter; otherwise, an exception is thrown.	GetObjectRequest.IfMatch
If-None-Match	Returns the source object if its ETag is different from the one specified by this parameter; otherwise, an exception is thrown.	GetObjectRequest.IfNoneMatch

 **NOTE**

- The ETag of an object is the MD5 check value of the object.
- If the download request includes **IfUnmodifiedSince** or **IfMatch** and the specified condition is not met, an exception will be thrown with HTTP status code **412 Precondition Failed** returned.
- If the download request includes **IfModifiedSince** or **IfNoneMatch** and the specified condition is not met, an exception will be thrown with HTTP status code **304 Not Modified** returned.

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Download an object in conditioned mode.
try
{
    DateTime datetime = new DateTime(2018, 3, 10, 12, 00, 00);
    GetObjectRequest request = new GetObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        IfModifiedSince = datetime,
    };
    using (GetObjectResponse response = client.GetObject(request))
    {
        string dest = "savepath";
        if (!File.Exists(dest))
        {
            response.WriteResponseStreamToFile(dest);
        }
        Console.WriteLine("Get object response: {0}", response.StatusCode);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

7.7 Rewriting Response Headers

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

When downloading an object, you can rewrite some HTTP/HTTPS response headers. The following table lists rewritable response headers.

Parameter	Description	Property in OBS .NET SDK
ContentType	Rewrites Content-Type in HTTP/HTTPS responses.	GetObjectRequest.ResponseHeaderOverrides.ContentType

Parameter	Description	Property in OBS .NET SDK
ContentLanguage	Rewrites Content-Language in HTTP/HTTPS responses.	GetObjectRequest.ResponseHeaderOverrides.ContentLanguage
Expires	Rewrites Expires in HTTP/HTTPS responses.	ObjectReplaceMetadata.Expires
CacheControl	Rewrites Cache-Control in HTTP/HTTPS responses.	GetObjectRequest.ResponseHeaderOverrides.CacheControl
ContentDisposition	Rewrites Content-Disposition in HTTP/HTTPS responses.	GetObjectRequest.ResponseHeaderOverrides.ContentDisposition
ContentEncoding	Rewrites Content-Encoding in HTTP/HTTPS responses.	GetObjectRequest.ResponseHeaderOverrides.ContentEncoding

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Rewrite response headers when downloading an object.
try
{
    ResponseHeaderOverrides responseHeaderOverrides = new ResponseHeaderOverrides();
    responseHeaderOverrides.ContentType = "image/jpeg";
    GetObjectRequest request = new GetObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        ResponseHeaderOverrides = responseHeaderOverrides,
    };
    GetObjectResponse response = client.GetObject(request);
    Console.WriteLine("Get object response: {0}", response.StatusCode);
    Console.WriteLine("ContentType: {0}", response.ContentType);
    response.Dispose();
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

7.8 Obtaining Customized Metadata

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

After an object is successfully downloaded, its customized data is returned. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Download an object.
try
{
    GetObjectRequest request = new GetObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
    };
    using (GetObjectResponse response = client.GetObject(request))
    {
        //Obtain the customized metadata of the object.
        foreach (string key in response.Metadata.Keys)
        {
            Console.WriteLine("key is :"+ key + " value is: " + response.Metadata[key]);
        }
        string dest = "savepath";
        if (!File.Exists(dest))
        {
            response.WriteResponseStreamToFile(dest);
        }
        Console.WriteLine("Get object response: {0}", response.StatusCode);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

7.9 Downloading an Archive Object

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

If you want to download an object in this storage class, you need to restore the object first. Two restore options are supported, as described in the following table.

Option	Description	Value in OBS .NET SDK
Expedited	Data can be restored within 1 to 5 minutes.	RestoreTierEnum.Expedited
Standard	Data can be restored within 3 to 5 hours. This is the default option.	RestoreTierEnum.Standard

You can call **ObsClient.RestoreObject** to restore Archive objects. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");

try
{
    RestoreObjectRequest request = new RestoreObjectRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    request.Days = 5;
    request.Tier = RestoreTierEnum.Expedited;
    request.VersionId = "versionId";
    RestoreObjectResponse response = client.RestoreObject(request);
    Console.WriteLine("Restore object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- The object specified in **ObsClient.RestoreObject** must be in the OBS Archive storage class. Otherwise, an exception will be thrown when you call this API.
- **RestoreObjectRequest.Days** specifies the retention period of restored object, ranging from 1 to 30.
- **RestoreObjectRequest.Tier** specifies the restore option, which indicates the time spend on restoring an object.

7.10 Performing a Resumable Download

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Downloading large files often fails due to poor network conditions or program breakdowns. It is a waste of resources to restart the download process upon a download failure, and the restarted download process may still suffer from the unstable network. To resolve such issues, you can use the API for resumable download, whose working principle is to divide the to-be-downloaded file into multiple parts and download them separately. The download result of each part is recorded in a checkpoint file in real time. Only when all parts are successfully downloaded, the result indicating a successful download is returned. Otherwise, an exception is thrown to remind you of calling the API again for re-downloading. Based on the download status of each part recorded in the checkpoint file, the re-downloading will download the parts failed to be downloaded previously, instead of downloading all parts. By virtue of this, resources are saved and efficiency is improved.

You can call **ObsClient.DownloadFile** to perform a resumable download. The following table describes the parameters involved in this API.

Parameter	Description	Property in OBS .NET SDK
BucketName	(Mandatory) Bucket name	DownloadFileRequest.BucketName
ObjectKey	(Mandatory) Object name	DownloadFileRequest.ObjectKey
DownloadFile	Full path of the local directory to which the object is downloaded. If the value is null, the downloaded object is saved in the directory where the program is executed.	DownloadFileRequest.DownloadFile
DownloadPartSize	Part size, in bytes. The value ranges from 5 MB (default) to 5 GB.	DownloadFileRequest.DownloadPartSize
EnableCheckpoint	Whether to enable the resumable upload mode. The default value is false , which indicates that this mode is disabled.	DownloadFileRequest.EnableCheckpoint
CheckpointFile	File used to record the download progress. This parameter is effective only in the resumable download mode. If the value is null, the file is in the same local directory as the downloaded object.	DownloadFileRequest.CheckpointFile
VersionId	Object version ID	DownloadFileRequest.VersionId
TaskNum	Maximum number of parts that can be concurrently downloaded. The default value is 1 .	DownloadFileRequest.TaskNum
DownloadProgress	Download progress callback function	DownloadFileRequest.DownloadProgress
ProgressType	Mode for representing the download progress	DownloadFileRequest.ProgressType
ProgressInterval	Interval for refreshing the download progress	DownloadFileRequest.ProgressInterval
DownloadEventHandler	Download event callback function	DownloadFileRequest.DownloadEventHandler

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Perform a resumable download.
try
{
    DownloadFileRequest request = new DownloadFileRequest
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        // Specify the local file to be downloaded.
        DownloadFile = "savepath",
        // Set the part size to 10 MB.
        DownloadPartSize = 1024 * 1024 * 10,
        // Enable the resumable download mode.
        EnableCheckpoint = true,
    };

    // Represent the progress by showing how many bytes has been downloaded.
    request.ProgressType = ProgressTypeEnum.ByBytes;
    // Refresh the download progress each time 1 MB data is downloaded.
    request.ProgressInterval = 1024 * 1024;

    // Register the download progress callback function.
    request.DownloadProgress += delegate(object sender, TransferStatus status){
        // Obtain the average download rate.
        Console.WriteLine("AverageSpeed: {0}", status.AverageSpeed / 1024 + "KB/S");
        // Obtain the download progress in percentage.
        Console.WriteLine("TransferPercentage: {0}", status.TransferPercentage);
    };

    // Register the download event callback function.
    request.DownloadEventHandler += delegate(object sender, ResumableDownloadEvent e){
        // Obtain the download events.
        Console.WriteLine("EventType: {0}", e.EventType);
    };

    GetObjectMetadataResponse response = client.DownloadFile(request);
    Console.WriteLine("Download File response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

 NOTE

- The API for resumable download, which is implemented based on **partial download**, is an encapsulated and enhanced version of partial download.
- This API saves resources and improves efficiency upon the re-download, and speeds up the download process by concurrently downloading parts. Because this API is transparent to users, users are free from concerns about internal service details, such as the creation and deletion of checkpoint files, division of objects, and concurrent download of parts.
- The default value of the **EnableCheckpoint** parameter is **false**, which indicates that the resumable download mode is disabled. In such cases, the API for resumable download degrades to the simple encapsulation of partial download, and no checkpoint file will be generated.
- **CheckpointFile** is effective only when **EnableCheckpoint** is **true**.

7.11 Processing an Image

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

OBS can be used to process images in a stable, secure, efficient, easy to use, and cost-efficient manner. If the object to be downloaded is an image, you can pass the image processing parameters to operate it, including cutting and resizing it as well as putting a watermark and converting the format.

For more information, see the [Image Processing Feature Guide](#).

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");

try
{
    GetObjectRequest request = new GetObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        // Resize and rotate the image in sequence.
        ImageProcess = "image/resize,m_fixed,w_100,h_100/rotate,90",
    };
    GetObjectResponse response = client.GetObject(request);
    Console.WriteLine("Get object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- Use **GetObjectRequest.ImageProcess** to specify the image processing parameters.
- Image processing parameters can be processed in cascading mode. This indicates that multiple commands can be performed on an image in sequence.

8 Object Management

8.1 Obtaining Object Properties

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetObjectMetadata** to obtain object properties, including the last modification time, version ID, and customized metadata. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Obtain the bucket metadata.
try
{
    GetObjectMetadataRequest request = new GetObjectMetadataRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    GetObjectMetadataResponse response = client.GetObjectMetadata(request);
    Console.WriteLine("Get object metadata response: {0}", response.StatusCode);
    Console.WriteLine("Object etag {0} : ", response.ETag);
    Console.WriteLine("Object versionId {0} : ", response.VersionId);
    Console.WriteLine("Object contentLength {0} : ", response.ContentLength);
}
catch (ObsException ex)
{
    Console.WriteLine("Message: {0}", ex.Message);
}
```

8.2 Managing Object ACLs

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Object ACLs, similar to bucket ACLs, support pre-defined access control policies and direct configuration. For details, see [Managing Bucket ACLs](#).

An object [ACL](#) can be configured in three modes:

1. Specify a pre-defined access control policy during object upload.
2. Call `ObsClient.SetObjectAcl` to specify a pre-defined access control policy.
3. Call `ObsClient.SetObjectAcl` to set the ACL directly.

Specifying a Pre-defined Access Control Policy During Object Upload

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Specify a pre-defined access control policy for the to-be-uploaded object.
try
{
    PutObjectRequest request = new PutObjectRequest
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        // Set the ACL to public-read-write.
        CannedAcl = CannedAclEnum.PublicReadWrite,
    };
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("Set object ac response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Setting a Pre-defined Access Control Policy for the Object

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Set a pre-defined access control policy for the object.
try
{
    SetObjectAclRequest request = new SetObjectAclRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    request.CannedACL = CannedAclEnum.PublicRead;
    SetObjectAclResponse response = client.SetObjectAcl(request);
}
```

```
        Console.WriteLine("Set object acl response: {0}", response.StatusCode);
    }
    catch (ObsException ex)
    {
        Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
        Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
    }
}
```

Directly Setting the Object ACL

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Set the object ACL directly.
try
{
    SetObjectAclRequest request = new SetObjectAclRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    request.AccessControlList = new AccessControlList();
    Owner owner = new Owner();
    owner.Id = "ownerid";
    request.AccessControlList.Owner = owner;
    Grant item = new Grant();
    item.Permission = PermissionEnum.FullControl;
    item.Grantee = new GroupGrantee(GroupGranteeEnum.AllUsers);
    request.AccessControlList.Grants.Add(item);
    SetObjectAclResponse response = client.SetObjectAcl(request);
    Console.WriteLine("Set object acl response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
}
```

NOTE

The owner or grantee ID needed in the ACL indicates the account ID, which can be viewed on the **My Credentials** page of OBS Console.

Obtaining an Object ACL

You can call **ObsClient.GetObjectAcl** to obtain an object ACL. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Obtain the object ACL.
try
{
    GetObjectAclRequest request = new GetObjectAclRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    GetObjectAclResponse response = client.GetObjectAcl(request);
    Console.WriteLine("Get bucket acl response: {0}", response.StatusCode);
    foreach (Grant grant in response.AccessControlList.Grants)
    {
        if (grant.Grantee is CanonicalGrantee)
        {
            Console.WriteLine("Grantee id: {0}", (grant.Grantee as CanonicalGrantee).Id);
        }
        else if (grant.Grantee is GroupGrantee)
        {
            Console.WriteLine("Grantee type: {0}", (grant.Grantee as GroupGrantee).GroupGranteeType);
        }
    }
}
}
```

```

        Console.WriteLine("Grant permission: {0}", grant.Permission);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}

```

8.3 Listing Objects

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.ListObjects** to list objects in a bucket.

The following table describes the parameters involved in this API.

Parameter	Description	Property in OBS .NET SDK
BucketName	Bucket name	ListObjectsRequest.BucketName
Prefix	Name prefix that the objects to be listed must contain	ListObjectsRequest.Prefix
Marker	Object name to start with when listing objects in a bucket. All objects are listed in the lexicographical order.	ListObjectsRequest.Marker
MaxKeys	Maximum number of objects listed in the response. The value ranges from 1 to 1000. If the value is not in this range, 1000 objects are listed by default.	ListObjectsRequest.MaxKeys
Delimiter	Character used to group object names. If the object name contains the Delimiter parameter, the character string from the first character to the first delimiter in the object name is grouped under a single result element, CommonPrefix . (If a prefix is specified in the request, the prefix must be removed from the object name.)	ListObjectsRequest.Delimiter

Listing Objects in Simple Mode

The following sample code shows how to list objects in simple mode. A maximum of 1000 objects can be returned.

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Simple listing
try
{
    ListObjectsRequest request = new ListObjectsRequest();
    request.BucketName = "bucketname";
    ListObjectsResponse response = client.ListObjects(request);
    foreach (ObsObject entry in response.ObsObjects)
    {
        Console.WriteLine("key = {0} size = {1}", entry.ObjectKey, entry.Size);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

Information about a maximum of 1000 objects can be listed each time. If a bucket contains more than 1000 objects and **ListObjectsResponse.IsTruncated** is **true** in the returned result, not all objects are listed. In such cases, you can use **ListObjectsResponse.NextMarker** to obtain the start position for next listing.

Listing Objects by Specifying the Number

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Specify the number.
try
{
    ListObjectsRequest request = new ListObjectsRequest();
    request.BucketName = "bucketname";
    // Set the number of objects to be listed to 100.
    request.MaxKeys = 100;
    ListObjectsResponse response = client.ListObjects(request);
    foreach (ObsObject entry in response.ObsObjects)
    {
        Console.WriteLine("key = {0} size = {1}", entry.ObjectKey, entry.Size);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing Objects by Specifying a Prefix

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// List objects by specifying a prefix.
```

```
try
{
    ListObjectsRequest request = new ListObjectsRequest();
    request.BucketName = "bucketname";
    //Specify the prefix.
    request.Prefix = "prefix"; ;
    ListObjectsResponse response = client.ListObjects(request);
    foreach (ObsObject entry in response.ObsObjects)
    {
        Console.WriteLine("key = {0} size = {1}", entry.ObjectKey, entry.Size);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing Objects by Specifying the Start Position

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// List objects by specifying the start position.
try
{
    ListObjectsRequest request = new ListObjectsRequest();
    request.BucketName = "bucketname";
    //Specify the start position for listing.
    request.Marker = "marker";
    ListObjectsResponse response = client.ListObjects(request);
    foreach (ObsObject entry in response.ObsObjects)
    {
        Console.WriteLine("key = {0} size = {1}", entry.ObjectKey, entry.Size);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing All Objects in Paging Mode

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//List all objects in paging mode.
try
{
    ListObjectsRequest request = new ListObjectsRequest();
    ListObjectsResponse response;
    request.BucketName = "bucketname";
    request.MaxKeys = 100;
    do
    {
        response = client.ListObjects(request);
        foreach (ObsObject entry in response.ObsObjects)
        {
            Console.WriteLine("key = {0} size = {1}", entry.ObjectKey, entry.Size);
        }
        request.Marker = response.NextMarker;
    }
    while (response.IsTruncated);
}
```

```
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

Listing All Objects in a Folder

There is no folder concept in OBS. All elements in buckets are objects. Folders are actually objects whose sizes are 0 and whose names end with a slash (/). When you set a folder name as the prefix, objects in this folder will be listed. Sample code is as follows:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
//List all objects in a folder.  
try  
{  
    ListObjectsRequest request = new ListObjectsRequest();  
    ListObjectsResponse response;  
    request.BucketName = "bucketname";  
    request.MaxKeys = 1000;  
    // Set the prefix to dir/.  
    request.Prefix = "dir/";  
    do  
    {  
        response = client.ListObjects(request);  
        foreach (ObsObject entry in response.ObsObjects)  
        {  
            Console.WriteLine("key = {0} size = {1}", entry.ObjectKey, entry.Size);  
        }  
        request.Marker = response.NextMarker;  
    }  
    while (response.IsTruncated);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

8.4 Deleting Objects

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

NOTE

Exercise caution when performing this operation. If the versioning function is disabled for the bucket where the object is located, the object cannot be restored after being deleted.

Deleting a Single Object

You can call **ObsClient.DeleteObject** to delete a single object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Delete an object.
try
{
    DeleteObjectRequest request = new DeleteObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
    };
    DeleteObjectResponse response = client.DeleteObject(request);
    Console.WriteLine("Delete object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Batch Deleting Objects

You can call **ObsClient.DeleteObjects** to delete objects in a batch.

A maximum of 1000 objects can be deleted each time. Two response modes are supported: **verbose** (detailed) and **quiet** (brief).

- In verbose mode (default mode), the returned response includes the deletion result of each requested object.
- In quiet mode, the returned response includes only results of objects failed to be deleted.

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Delete objects in a batch.
try
{
    DeleteObjectsRequest request = new DeleteObjectsRequest();
    request.BucketName = "bucketname";
    request.Quiet = true;
    request.AddKey("objectname1");
    request.AddKey("objectname2");
    DeleteObjectsResponse response = client.DeleteObjects(request);
    Console.WriteLine("Delete objects response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

8.5 Copying an Object

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

The object copy operation can create a copy for an existing object in OBS.

You can call **ObsClient.CopyObject** to copy an object. When copying an object, you can specify properties and ACL for it.

NOTE

- If the source object is an Archive object, you must restore it before copying it.

Copying an Object in Simple Mode

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");

// Copy an object.
try
{
    CopyObjectRequest request = new CopyObjectRequest();
    request.SourceBucketName = "sourcebucketname";
    request.SourceObjectKey = "sourceobjectname";
    request.BucketName = "destbucketname";
    request.ObjectKey = "destobjectName";
    CopyObjectResponse response = client.CopyObject(request);
    Console.WriteLine("Copy object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Rewriting Object Properties

The following sample code shows how to rewrite object properties.

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//Rewrite object properties.
try
{
    CopyObjectRequest request = new CopyObjectRequest();
    request.SourceBucketName = "sourcebucketname";
    request.SourceObjectKey = "sourceobjectname";
    request.BucketName = "destbucketname";
    request.ObjectKey = "destobjectName";
    request.StorageClass = StorageClassEnum.Warm;
}
```

```

request.ContentType = "image/jpeg";
request.MetadataDirective = MetadataDirectiveEnum.Replace;
CopyObjectResponse response = client.CopyObject(request);
Console.WriteLine("Copy object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}

```

Copying an Object by Specifying Conditions

When copying an object, you can specify one or more restriction conditions. If the conditions are met, the object will be copied. Otherwise, an exception will be thrown and the copy will fail.

You can set the following conditions:

Parameter	Description	Property in OBS .NET SDK
Copy-Source-If-Modified-Since	Copies the source object if it is changed after the time specified by this parameter; otherwise, an exception is thrown.	CopyObjectRequest.IfModifiedSince
Copy-Source-If-Unmodified-Since	Copies the source object if it is changed before the time specified by this parameter; otherwise, an exception is thrown.	CopyObjectRequest.IfUnmodifiedSince
Copy-Source-If-Match	Copies the source object if its ETag is the same as the one specified by this parameter; otherwise, an exception is thrown.	CopyObjectRequest.IfMatch
Copy-Source-If-None-Match	Copies the source object if its ETag is different from the one specified by this parameter; otherwise, an exception is thrown.	CopyObjectRequest.IfNoneMatch

NOTE

- The ETag of the source object is the MD5 check value of the source object.
- If the object copy request includes **IfUnmodifiedSince**, **IfMatch**, **IfModifiedSince**, or **IfNoneMatch**, and the specified condition is not met, the copy will fail and an exception will be thrown with HTTP status code **412 Precondition Failed** returned.
- **IfModifiedSince** and **IfNoneMatch** can be used together and so do **IfUnmodifiedSince** and **IfMatch**.

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");

// Set the condition for restricting the copy.
try
{
    CopyObjectRequest request = new CopyObjectRequest();
    request.SourceBucketName = "sourcebucketname";
    request.SourceObjectKey = "sourceobjectname";
    request.BucketName = "destbucketname";
    request.ObjectKey = "destobjectName";

    request.IfModifiedSince = new DateTime(2018, 3, 10, 12, 00, 00);
    CopyObjectResponse response = client.CopyObject(request);
    Console.WriteLine("Copy object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Modifying the Object ACL

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Rewrite the object ACL.
try
{
    CopyObjectRequest request = new CopyObjectRequest();
    request.SourceBucketName = "sourcebucketname";
    request.SourceObjectKey = "sourceobjectname";
    request.BucketName = "destbucketname";
    request.ObjectKey = "destobjectName";
    request.CannedAcl = CannedAclEnum.PublicRead;
    CopyObjectResponse response = client.CopyObject(request);
    Console.WriteLine("Copy object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

8.6 HEAD Object

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.HeadObject** to check whether a specified object exists. The following code shows how to use the function:

```
// // Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
```

```
your-endpoint");
// Check whether the specified object exists.
try
{
    HeadObjectRequest request = new HeadObjectRequest()
    {
        BucketName = "bucketName",
        ObjectKey = "objectKey"
    };
    bool response = client.HeadObject(request);
    Console.WriteLine("Head object response: {0}", response);
}
catch (ObsException ex)
{
    Console.WriteLine("Exception errorcode: {0}, when head object.", ex.ErrorCode);
    Console.WriteLine("Exception errormessage: {0}", ex.ErrorMessage);
}
```

9 Temporarily Authorized Access

9.1 Using a Temporary URL for Authorized Access

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

ObsClient allows you to create a URL whose **Query** parameters are carried with authentication information by specifying the AK and SK, HTTP method, and request parameters. You can provide other users with this URL for temporary access. When generating a URL, you need to specify the validity period of the URL to restrict the access duration of visitors.

If you want to grant other users the permission to perform other operations on buckets or objects (for example, upload or download objects), generate a URL with the corresponding request (for example, to upload an object using the URL that generates the PUT request) and provide the URL for other users.

The following table lists operations can be performed through a signed URL.

Operation	HTTP Request Method (Value in OBS .NET SDK)	Sub-resource (Value in OBS .NET SDK)	Bucket Name Required	Object Name Required
PUT Bucket	HttpVerb.PUT	N/A	Yes	No
GET Buckets	HttpVerb.GET	N/A	No	No
DELETE Bucket	HttpVerb.DELETE	N/A	Yes	No

Operation	HTTP Request Method (Value in OBS .NET SDK)	Sub-resource (Value in OBS .NET SDK)	Bucket Name Required	Object Name Required
GET Objects	HttpVerb.GET	N/A	Yes	No
GET Object versions	HttpVerb.GET	SubResourceEnum.Versions	Yes	No
List Multipart uploads	HttpVerb.GET	SubResourceEnum.Uploads	Yes	No
Obtain Bucket Metadata	HttpVerb.HEAD	N/A	Yes	No
GET Bucket location	HttpVerb.GET	SubResourceEnum.Location	Yes	No
GET Bucket storage info	HttpVerb.GET	SubResourceEnum.StorageInfo	Yes	No
PUT Bucket quota	HttpVerb.PUT	SubResourceEnum.Quota	Yes	No
GET Bucket quota	HttpVerb.GET	SubResourceEnum.Quota	Yes	No
PUT Bucket storage Policy	HttpVerb.PUT	SubResourceEnum.StoragePolicy	Yes	No
GET Bucket storage Policy	HttpVerb.GET	SubResourceEnum.StoragePolicy	Yes	No
PUT Bucket acl	HttpVerb.PUT	SubResourceEnum.Acl	Yes	No

Operation	HTTP Request Method (Value in OBS .NET SDK)	Sub-resource (Value in OBS .NET SDK)	Bucket Name Required	Object Name Required
GET Bucket acl	HttpVerb.GET	SubResourceEnum.Acl	Yes	No
PUT Bucket logging	HttpVerb.PUT	SubResourceEnum.Logging	Yes	No
GET Bucket logging	HttpVerb.GET	SubResourceEnum.Logging	Yes	No
PUT Bucket policy	HttpVerb.PUT	SubResourceEnum.Policy	Yes	No
GET Bucket policy	HttpVerb.GET	SubResourceEnum.Policy	Yes	No
DELETE Bucket policy	HttpVerb.DELETE	SubResourceEnum.Policy	Yes	No
PUT Bucket lifecycle	HttpVerb.PUT	SubResourceEnum.Lifecycle	Yes	No
GET Bucket lifecycle	HttpVerb.GET	SubResourceEnum.Lifecycle	Yes	No
DELETE Bucket lifecycle	HttpVerb.DELETE	SubResourceEnum.Lifecycle	Yes	No
PUT Bucket website	HttpVerb.PUT	SubResourceEnum.Website	Yes	No
GET Bucket website	HttpVerb.GET	SubResourceEnum.Website	Yes	No
DELETE Bucket website	HttpVerb.DELETE	SubResourceEnum.Website	Yes	No

Operation	HTTP Request Method (Value in OBS .NET SDK)	Sub-resource (Value in OBS .NET SDK)	Bucket Name Required	Object Name Required
PUT Bucket versioning	HttpVerb.PUT	SubResourceEnum.Versioning	Yes	No
GET Bucket versioning	HttpVerb.GET	SubResourceEnum.Versioning	Yes	No
PUT Bucket cors	HttpVerb.PUT	SubResourceEnum.Cors	Yes	No
GET Bucket cors	HttpVerb.GET	SubResourceEnum.Cors	Yes	No
DELETE Bucket cors	HttpVerb.DELETE	SubResourceEnum.Cors	Yes	No
PUT Bucket notification	HttpVerb.PUT	SubResourceEnum.Notification	Yes	No
GET Bucket notification	HttpVerb.GET	SubResourceEnum.Notification	Yes	No
PUT Bucket tagging	HttpVerb.PUT	SubResourceEnum.Tagging	Yes	No
GET Bucket tagging	HttpVerb.GET	SubResourceEnum.Tagging	Yes	No
DELETE Bucket tagging	HttpVerb.DELETE	SubResourceEnum.Tagging	Yes	No
PUT Object	HttpVerb.PUT	N/A	Yes	Yes
Append Object	HttpVerb.POST	SubResourceEnum.Append	Yes	Yes

Operation	HTTP Request Method (Value in OBS .NET SDK)	Sub-resource (Value in OBS .NET SDK)	Bucket Name Required	Object Name Required
GET Object	HttpVerb.GET	N/A	Yes	Yes
PUT Object - Copy	HttpVerb.PUT	N/A	Yes	Yes
DELETE Object	HttpVerb.DELETE	N/A	Yes	Yes
DELETE Objects	HttpVerb.POST	SubResourceEnum.Delete	Yes	Yes
Obtain Object Metadata	HttpVerb.HEAD	N/A	Yes	Yes
PUT Object acl	HttpVerb.PUT	SubResourceEnum.Acl	Yes	Yes
GET Object acl	HttpVerb.GET	SubResourceEnum.Acl	Yes	Yes
Initiate Multipart Upload	HttpVerb.POST	SubResourceEnum.Uploads	Yes	Yes
Upload Part	HttpVerb.PUT	N/A	Yes	Yes
Upload Part - Copy	HttpVerb.PUT	N/A	Yes	Yes
List Parts	HttpVerb.GET	N/A	Yes	Yes
Complete Multipart Upload	HttpVerb.POST	N/A	Yes	Yes
Abort Multipart Upload	HttpVerb.DELETE	N/A	Yes	Yes

Operation	HTTP Request Method (Value in OBS .NET SDK)	Sub-resource (Value in OBS .NET SDK)	Bucket Name Required	Object Name Required
POST Object restore	HttpVerb.POST	SubResourceEnum.Restore	Yes	Yes

To access OBS using a temporary URL generated by the OBS .NET SDK, perform the following steps:

Step 1 Call `ObsClient.CreateTemporarySignature` to generate a signed URL.

Step 2 Use any HTTP library to make an HTTP/HTTPS request to OBS.

----End

The following content provides examples of accessing OBS using a temporary URL, including bucket creation, as well as object upload, download, listing, and deletion.

Creating a Bucket

```
string endpoint = "http://your-endpoint";
string AK = "**** Provide your Access Key ****";
string SK = "**** Provide your Secret Key ****";

ObsConfig config = new ObsConfig();
config.Endpoint = endpoint;
// Create an instance of ObsClient.
ObsClient client = new ObsClient(AK, SK, config);

// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600;

CreateTemporarySignatureRequest request = new CreateTemporarySignatureRequest();
request.BucketName = "bucketname";
request.Method = HttpVerb.PUT;
request.Expires = expireSeconds;

CreateTemporarySignatureResponse response = client.CreateTemporarySignature(request);
Console.WriteLine("Creating bucket using temporary signature url:");
Console.WriteLine("\t" + response.SignUrl);

// Use a PUT request to create a bucket.
HttpRequest webRequest = WebRequest.Create(response.SignUrl) as HttpRequest;
webRequest.Method = "PUT";

foreach (KeyValuePair<string, string> header in response.ActualSignedRequestHeaders)
{
    if (!header.Key.Equals("host", StringComparison.OrdinalIgnoreCase))
    {
        webRequest.Headers.Add(header.Key, header.Value);
    }
}

string location = "your bucket location";

webRequest.SendChunked = true;
webRequest.AllowWriteStreamBuffering = false;
using (Stream requestStream = webRequest.GetRequestStream())
```

```
{
    byte[] buffer = Encoding.UTF8.GetBytes("<CreateBucketConfiguration><LocationConstraint>" + location
+ "</LocationConstraint></CreateBucketConfiguration>");
    requestStream.Write(buffer, 0, buffer.Length);
}

HttpWebResponse webResponse = null;
try
{
    webResponse = webRequest.GetResponse() as HttpWebResponse;
}
catch (WebException ex)
{
    webResponse = ex.Response as HttpWebResponse;
}
Console.WriteLine("Response Status:" + Convert.ToInt32(webResponse.StatusCode));
using (MemoryStream dest = new MemoryStream())
{
    using (Stream stream = webResponse.GetResponseStream())
    {
        byte[] buffer = new byte[8192];
        int bytesRead;
        while ((bytesRead = stream.Read(buffer, 0, buffer.Length)) > 0)
        {
            dest.Write(buffer, 0, bytesRead);
        }
    }
    Console.WriteLine("Response Content:");
    Console.WriteLine(Encoding.UTF8.GetString(dest.ToArray()));
}
```

Uploading an Object

```
string endpoint = "http://your-endpoint";
string AK = "**** Provide your Access Key ****";
string SK = "**** Provide your Secret Key ****";

ObsConfig config = new ObsConfig();
config.Endpoint = endpoint;
// Create an instance of ObsClient.
ObsClient client = new ObsClient(AK, SK, config);

// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600;

CreateTemporarySignatureRequest request = new CreateTemporarySignatureRequest();
request.BucketName = "bucketname";
request.ObjectKey = "objectkey";
request.Method = HttpVerb.PUT;
request.Expires = expireSeconds;

CreateTemporarySignatureResponse response = client.CreateTemporarySignature(request);
Console.WriteLine("Creating object using temporary signature url:");
Console.WriteLine("\t" + response.SignUrl);

// Use a PUT request to upload an object.
HttpRequest webRequest = WebRequest.Create(response.SignUrl) as HttpRequest;
webRequest.Method = "PUT";

foreach (KeyValuePair<string, string> header in response.ActualSignedRequestHeaders)
{
    if (!header.Key.Equals("host", StringComparison.OrdinalIgnoreCase))
    {
        webRequest.Headers.Add(header.Key, header.Value);
    }
}
```

```
webRequest.SendChunked = true;
webRequest.AllowWriteStreamBuffering = false;
using (Stream requestStream = webRequest.GetRequestStream())
{
    byte[] buffer = Encoding.UTF8.GetBytes("Hello OBS");
    requestStream.Write(buffer, 0, buffer.Length);
}

HttpWebResponse webResponse = null;
try
{
    webResponse = webRequest.GetResponse() as HttpWebResponse;
}
catch (WebException ex)
{
    webResponse = ex.Response as HttpWebResponse;
}
Console.WriteLine("Response Status:" + Convert.ToInt32(webResponse.StatusCode));
using (MemoryStream dest = new MemoryStream())
{
    using (Stream stream = webResponse.GetResponseStream())
    {
        byte[] buffer = new byte[8192];
        int bytesRead;
        while ((bytesRead = stream.Read(buffer, 0, buffer.Length)) > 0)
        {
            dest.Write(buffer, 0, bytesRead);
        }
    }
    Console.WriteLine("Response Content:");
    Console.WriteLine(Encoding.UTF8.GetString(dest.ToArray()));
}
```

Downloading an Object

```
string endpoint = "http://your-endpoint";
string AK = "**** Provide your Access Key ****";
string SK = "**** Provide your Secret Key ****";

ObsConfig config = new ObsConfig();
config.Endpoint = endpoint;
// Create an instance of ObsClient.
ObsClient client = new ObsClient(AK, SK, config);

// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600;

CreateTemporarySignatureRequest request = new CreateTemporarySignatureRequest();
request.BucketName = "bucketname";
request.ObjectKey = "objectkey";
request.Method = HttpVerb.GET;
request.Expires = expireSeconds;

CreateTemporarySignatureResponse response = client.CreateTemporarySignature(request);
Console.WriteLine("Getting object using temporary signature url:");
Console.WriteLine("\t" + response.SignUrl);

// Make a GET request to download an object.
HttpRequest webRequest = WebRequest.Create(response.SignUrl) as HttpRequest;
webRequest.Method = "GET";

foreach (KeyValuePair<string, string> header in response.ActualSignedRequestHeaders)
{
    if (!header.Key.Equals("host", StringComparison.OrdinalIgnoreCase))
    {
        webRequest.Headers.Add(header.Key, header.Value);
    }
}
```

```
}  
  
HttpWebResponse webResponse = null;  
try  
{  
    webResponse = webRequest.GetResponse() as HttpWebResponse;  
}  
catch (WebException ex)  
{  
    webResponse = ex.Response as HttpWebResponse;  
}  
Console.WriteLine("Response Status:" + Convert.ToInt32(webResponse.StatusCode));  
using (MemoryStream dest = new MemoryStream())  
{  
    using (Stream stream = webResponse.GetResponseStream())  
    {  
        byte[] buffer = new byte[8192];  
        int bytesRead;  
        while ((bytesRead = stream.Read(buffer, 0, buffer.Length)) > 0)  
        {  
            dest.Write(buffer, 0, bytesRead);  
        }  
    }  
}  
Console.WriteLine("Response Content:");  
Console.WriteLine(Encoding.UTF8.GetString(dest.ToArray()));  
}
```

Listing Objects

```
string endpoint = "http://your-endpoint";  
string AK = "**** Provide your Access Key ****";  
string SK = "**** Provide your Secret Key ****";  
  
ObsConfig config = new ObsConfig();  
config.Endpoint = endpoint;  
// Create an instance of ObsClient.  
ObsClient client = new ObsClient(AK, SK, config);  
  
// Specify the validity period of the URL to 3600 seconds.  
long expireSeconds = 3600;  
  
CreateTemporarySignatureRequest request = new CreateTemporarySignatureRequest();  
request.BucketName = "bucketname";  
request.Method = HttpVerb.GET;  
request.Expires = expireSeconds;  
  
CreateTemporarySignatureResponse response = client.CreateTemporarySignature(request);  
Console.WriteLine("Getting object list using temporary signature url:");  
Console.WriteLine("\t" + response.SignUrl);  
  
// Use a GET request to obtain the object list.  
HttpRequest webRequest = WebRequest.Create(response.SignUrl) as HttpRequest;  
webRequest.Method = "GET";  
  
foreach (KeyValuePair<string, string> header in response.ActualSignedRequestHeaders)  
{  
    if (!header.Key.Equals("host", StringComparison.OrdinalIgnoreCase))  
    {  
        webRequest.Headers.Add(header.Key, header.Value);  
    }  
}  
  
HttpWebResponse webResponse = null;  
try  
{  
    webResponse = webRequest.GetResponse() as HttpWebResponse;  
}
```

```
catch (WebException ex)
{
    webResponse = ex.Response as HttpWebResponse;
}
Console.WriteLine("Response Status:" + Convert.ToInt32(webResponse.StatusCode));
using (MemoryStream dest = new MemoryStream())
{
    using (Stream stream = webResponse.GetResponseStream())
    {
        byte[] buffer = new byte[8192];
        int bytesRead;
        while ((bytesRead = stream.Read(buffer, 0, buffer.Length)) > 0)
        {
            dest.Write(buffer, 0, bytesRead);
        }
    }
    Console.WriteLine("Response Content:");
    Console.WriteLine(Encoding.UTF8.GetString(dest.ToArray()));
}
```

Deleting an Object

```
string endpoint = "http://your-endpoint";
string AK = "**** Provide your Access Key ****";
string SK = "**** Provide your Secret Key ****";

ObsConfig config = new ObsConfig();
config.Endpoint = endpoint;
// Create an instance of ObsClient.
ObsClient client = new ObsClient(AK, SK, config);

// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600;

CreateTemporarySignatureRequest request = new CreateTemporarySignatureRequest();
request.BucketName = "bucketname";
request.ObjectKey = "objectkey";
request.Method = HttpVerb.DELETE;
request.Expires = expireSeconds;

CreateTemporarySignatureResponse response = client.CreateTemporarySignature(request);
Console.WriteLine("Deleting object using temporary signature url:");
Console.WriteLine("\t" + response.SignUrl);

// Use a DELETE request to delete an object.
HttpRequest webRequest = WebRequest.Create(response.SignUrl) as HttpRequest;
webRequest.Method = "DELETE";

foreach (KeyValuePair<string, string> header in response.ActualSignedRequestHeaders)
{
    if (!header.Key.Equals("host", StringComparison.OrdinalIgnoreCase))
    {
        webRequest.Headers.Add(header.Key, header.Value);
    }
}

HttpWebResponse webResponse = null;
try
{
    webResponse = webRequest.GetResponse() as HttpWebResponse;
}
catch (WebException ex)
{
    webResponse = ex.Response as HttpWebResponse;
}
Console.WriteLine("Response Status:" + Convert.ToInt32(webResponse.StatusCode));
using (MemoryStream dest = new MemoryStream())
```

```
{
    using (Stream stream = webResponse.GetResponseStream())
    {
        byte[] buffer = new byte[8192];
        int bytesRead;
        while ((bytesRead = stream.Read(buffer, 0, buffer.Length)) > 0)
        {
            dest.Write(buffer, 0, bytesRead);
        }
    }
    Console.WriteLine("Response Content:");
    Console.WriteLine(Encoding.UTF8.GetString(dest.ToArray()));
}
```

 **NOTE**

HttpVerb is an enumeration type defined in OBS .NET SDK, whose value indicates the request method types.

10 Versioning Management

10.1 Versioning Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

OBS can store multiple versions of an object. You can quickly search for and restore different versions as well as restore data in the event of misoperations or application faults.

For details, see [Versioning](#).

10.2 Setting Versioning Status for a Bucket

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.SetBucketVersioning** to set the versioning status for a bucket. OBS supports two versioning statuses.

Versioning Status	Description	Value in OBS .NET SDK
Enabled	<ol style="list-style-type: none"> 1. OBS creates a unique version ID for each uploaded object. Namesake objects are not overwritten and are distinguished by their own version IDs. 2. Objects can be downloaded by specifying the version ID. By default, the latest object is downloaded if no version ID is specified. 3. Objects can be deleted by specifying the version ID. If an object is deleted with no version ID specified, the object will generate a delete marker with a unique version ID but is not physically deleted. 4. Objects of the latest version in a bucket are returned by default after ObsClient.ListObjects is called. You can call ObsClient.ListVersions to list a bucket's objects with all version IDs. 5. Except for delete markers, storage space occupied by objects with all version IDs is billed. 	VersionStatusEnum.Enabled

Versioning Status	Description	Value in OBS .NET SDK
Suspended	<ol style="list-style-type: none"> 1. Existing objects with version IDs are not affected. 2. OBS creates version ID null to an uploaded object and the object will be overwritten after a namesake one is uploaded 3. Objects can be downloaded by specifying the version ID. By default, the latest object is downloaded if no version ID is specified. 4. Objects can be deleted by version ID. If an object is deleted with no version ID specified, the object is only attached with a deletion mark and version ID null. Objects with version ID null are physically deleted. 5. Except for delete markers, storage space occupied by objects with all version IDs is billed. 	VersionStatusEnum.Suspended

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Set the versioning status.
try
{
    SetBucketVersioningRequest request = new SetBucketVersioningRequest();
    request.BucketName = "bucketname";
    request.Configuration = new VersioningConfiguration();
    //Enabling versioning.
    request.VersioningConfig.Status = VersionStatusEnum.Enabled;
    SetBucketVersioningResponse response = client.SetBucketVersioning(request);
    Console.WriteLine("Set bucket version response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

10.3 Viewing Versioning Status of a Bucket

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketVersioning** to view the versioning status of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// View the versioning status.
try
{
    GetBucketVersioningRequest request = new GetBucketVersioningRequest();
    request.BucketName = "bucketname";
    GetBucketVersioningResponse response = client.GetBucketVersioning(request);
    Console.WriteLine("Get bucket version response: {0}", response.StatusCode);
    Console.WriteLine("Status: {0}", response.Configuration.Status);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

10.4 Obtaining a Versioning Object

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetObject** to pass the version ID (**VersionId**) to obtain a versioning object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Obtain versioning objects.
try
{
    GetObjectRequest getObjectRequest = new GetObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        VersionId = "versionId",
    };
    using (GetObjectResponse response = client.GetObject(getObjectRequest))
    {
        Console.WriteLine("Get object response: {0}", response.StatusCode);
    }
}
```

```
//Save the file locally.
if (!File.Exists("savePath"))
{
    response.WriteResponseStreamToFile("savePath");
}
}
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

If the version ID is null, the object of the latest version will be downloaded, by default.

10.5 Copying a Versioning Object

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.CopyObject** to pass the version ID (**SourceVersionId**) to copy a versioning object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Copy a versioning object.
try
{
    CopyObjectRequest request = new CopyObjectRequest();
    request.SourceBucketName = "sourcebucketname";
    request.SourceObjectKey = "sourceobjectname";
    request.BucketName = "destbucketname";
    request.ObjectKey = "destobjectName";
    request.SourceVersionId = "sourceversionId";
    CopyObjectResponse response = client.CopyObject(request);
    Console.WriteLine("copy object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

10.6 Restoring an Archive Object with a Specified Version ID

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.RestoreObject** to pass the version ID (**VersionId**) to restore an Archive object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Restore a versioning Archive object.
try
{
    RestoreObjectRequest request = new RestoreObjectRequest();
    request.BucketName = "bucekname";
    request.ObjectKey = "objectname";
    request.Days = 5;
    // Restore a versioning object in the Expedited mode.
    request.Tier = RestoreTierEnum.Expedited;
    request.VersionId = "versionId";
    RestoreObjectResponse response = client.RestoreObject(request);
    Console.WriteLine("Restore object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

10.7 Listing Versioning Objects

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.ListVersions** to list versioning objects.

The following table describes the parameters involved in this API.

Parameter	Description	Property in OBS .NET SDK
BucketName	Bucket name	ListVersionsRequest.BucketName

Parameter	Description	Property in OBS .NET SDK
Prefix	Name prefix that the objects to be listed must contain	ListVersionsRequest.Prefix
KeyMarker	Object name to start with when listing versioning objects in a bucket. All versioning objects following this parameter are listed in the lexicographical order.	ListVersionsRequest.KeyMarker
MaxKeys	Maximum number of listed versioning objects. The value ranges from 1 to 1000. If the value is not in this range, 1000 versioning objects are returned by default.	ListVersionsRequest.MaxKeys
Delimiter	Character used to group object names. If the object name contains the Delimiter parameter, the character string from the first character to the first delimiter in the object name is grouped under a single result element, CommonPrefix . (If a prefix is specified in the request, the prefix must be removed from the object name.)	ListVersionsRequest.Delimiter
VersionIdMarker	Object name to start with when listing versioning objects in a bucket. All versioning objects are listed in the lexicographical order by object name and version ID. This parameter must be used together with KeyMarker .	ListVersionsRequest.VersionIdMarker

 **NOTE**

- If the value of **VersionIdMarker** is not a version ID specified by **KeyMarker**, **VersionIdMarker** is ineffective.
- The returned result of **ObsClient.ListVersions** includes the versioning objects and delete markers.

Listing Versioning Objects in Simple Mode

The following sample code shows how to list versioning objects in simple mode. A maximum of 1000 versioning objects can be returned.

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
//List versioning objects.
```

```
try
{
    ListVersionsRequest request = new ListVersionsRequest();
    request.BucketName = "bucketname";
    ListVersionsResponse response = client.ListVersions(request);
    foreach (ObsObjectVersion objectVersion in response.Versions)
    {
        Console.WriteLine("Key: {0}", objectVersion.ObjectKey);
        Console.WriteLine("VersionId: {0}", objectVersion.VersionId);
    }
    Console.WriteLine("List versions response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

Information about a maximum of 1000 versioning objects can be listed each time. If a bucket contains more than 1000 objects and **ListVersionsResponse.IsTruncated** is **true** in the returned result, not all versioning objects are listed. In such cases, you can use **ListVersionsResponse.NextKeyMarker** and **ListVersionsResponse.NextVersionIdMarker** to obtain the start position for next listing.

Listing Versioning Objects by Specifying the Number

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//List versioning objects by specifying the number.
try
{
    ListVersionsRequest request = new ListVersionsRequest();
    request.BucketName = "bucketname";
    request.MaxKeys = 100;
    ListVersionsResponse response = client.ListVersions(request);
    foreach (ObsObjectVersion objectVersion in response.Versions)
    {
        Console.WriteLine("Key: {0}", objectVersion.ObjectKey);
        Console.WriteLine("VersionId: {0}", objectVersion.VersionId);
    }
    Console.WriteLine("List versions response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing Versioning Objects by Specifying a Prefix

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//List versioning objects by specifying a prefix.
try
{
    ListVersionsRequest request = new ListVersionsRequest();
    request.BucketName = "bucketname";
    request.MaxKeys = 100;
    request.Prefix = "prefix";
```

```
ListVersionsResponse response = client.ListVersions(request);
foreach (ObsObjectVersion objectVersion in response.Versions)
{
    Console.WriteLine("Key: {0}", objectVersion.ObjectKey);
    Console.WriteLine("VersionId: {0}", objectVersion.VersionId);
}
Console.WriteLine("List versions response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing Versioning Objects by Specifying the Start Position

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//Specify the start position for listing.
try
{
    ListVersionsRequest request = new ListVersionsRequest();
    request.BucketName = "bucketname";
    request.MaxKeys = 100;
    request.Prefix = "prefix";
    request.KeyMarker = "keyMarker";
    ListVersionsResponse response = client.ListVersions(request);
    foreach (ObsObjectVersion objectVersion in response.Versions)
    {
        Console.WriteLine("Key: {0}", objectVersion.ObjectKey);
        Console.WriteLine("VersionId: {0}", objectVersion.VersionId);
    }
    Console.WriteLine("List versions response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing All Versioning Objects in Paging Mode

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//List all versioning objects in paging mode.
try
{
    ListVersionsRequest request = new ListVersionsRequest();
    request.BucketName = "bucketname";
    request.MaxKeys = 100;
    ListVersionsResponse response;
    do
    {
        response = client.ListVersions(request);
        Console.WriteLine("List versions response: {0}", response.StatusCode);
        foreach (ObsObjectVersion objectVersion in response.Versions)
        {
            Console.WriteLine("Key: {0}", objectVersion.ObjectKey);
            Console.WriteLine("VersionId: {0}", objectVersion.VersionId);
        }
        request.KeyMarker = response.NextKeyMarker;
        request.VersionIdMarker = response.NextVersionIdMarker;
    }
}
```

```
    }
    while (response.IsTruncated);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Listing All Versioning Objects in a Folder

There is no folder concept in OBS. All elements in buckets are objects. Folders are actually objects whose sizes are 0 and whose names end with a slash (/). When you set a folder name as the prefix, objects in this folder will be listed. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//List all versioning objects in paging mode.
try
{
    ListVersionsRequest request = new ListVersionsRequest();
    request.BucketName = "bucketname";
    request.MaxKeys = 1000;
    // Set the prefix to dir/.
    request.Prefix = "dir/";
    ListVersionsResponse response;
    do
    {
        response = client.ListVersions(request);
        Console.WriteLine("List versions response: {0}", response.StatusCode);
        foreach (ObsObjectVersion objectVersion in response.Versions)
        {
            Console.WriteLine("Key: {0}", objectVersion.ObjectKey);
            Console.WriteLine("VersionId: {0}", objectVersion.VersionId);
        }
        request.KeyMarker = response.NextKeyMarker;
        request.VersionIdMarker = response.NextVersionIdMarker;
    }
    while (response.IsTruncated);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

10.8 Setting or Obtaining a Versioning Object ACL

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Directly Setting a Versioning Object ACL

You can call **ObsClient.SetObjectAcl** to pass the version ID (**VersionId**) to set the ACL for a versioning object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Set the ACL for a versioning object.
try
{
    SetObjectAclRequest request = new SetObjectAclRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    request.VersionId = "versionId";
    request.AccessControlList = new AccessControlList();
    Owner owner = new Owner();
    owner.Id = "ownerid";
    request.AccessControlList.Owner = owner;
    Grant item = new Grant();
    item.Permission = PermissionEnum.FullControl;
    item.Grantee = new GroupGrantee(GroupGranteeEnum.AllUsers);
    request.AccessControlList.Grants.Add(item);
    SetObjectAclResponse response = client.SetObjectAcl(request);
    Console.WriteLine("Set object acl response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

The owner or grantee ID needed in the ACL indicates the account ID, which can be viewed on the **My Credentials** page of OBS Console.

Obtaining a Versioning Object ACL

You can call **ObsClient.GetObjectAcl** to pass the version ID (**VersionId**) to obtain the ACL of a versioning object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Obtain the ACL of a versioning object.
try
{
    GetObjectAclRequest request = new GetObjectAclRequest();
    request.BucketName = "bucketname";
    request.ObjectKey = "objectname";
    request.VersionId = "versionId";
    GetObjectAclResponse response = client.GetObjectAcl(request);
    Console.WriteLine("GetObjectAcl grant account: {0}", response.AccessControlList.Grants.Count);
    Console.WriteLine("GetObjectAcl owner id: {0}", response.AccessControlList.Owner.Id);
    foreach (Grant grant in response.AccessControlList.Grants)
    {
        if(grant.Grantee is CanonicalGrantee)
        {
            Console.WriteLine("Grantee id: {0}", (grant.Grantee as CanonicalGrantee).Id);
        }else if(grant.Grantee is GroupGrantee)
        {
            Console.WriteLine("Grantee type: {0}", (grant.Grantee as GroupGrantee).GroupGranteeType);
        }
        Console.WriteLine("Grant permission: {0}", grant.Permission);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

10.9 Deleting Versioning Objects

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Deleting a Single Versioning Object

You can call **ObsClient.DeleteObject** to pass the version ID (**VersionId**) to delete a versioning object. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Delete a versioning object.
try
{
    DeleteObjectRequest request = new DeleteObjectRequest()
    {
        BucketName = "bucketname",
        ObjectKey = "objectname",
        VersionId = "versionId"
    };
    DeleteObjectResponse response = client.DeleteObject(request);
    Console.WriteLine("Delete object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Deleting Versioning Objects in a Batch

You can call **ObsClient.DeleteObjects** to pass the version ID (**VersionId**) of each to-be-deleted object to delete them. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Delete two versioning objects.
try
{
    DeleteObjectsRequest request = new DeleteObjectsRequest();
    request.BucketName = "bucketname";
    request.Quiet = true;
    request.AddKey("objectName1", "versionId1");
    request.AddKey("objectName2", "versionId2");
    DeleteObjectsResponse response = client.DeleteObjects(request);
    Console.WriteLine("Delete objects response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

11 Lifecycle Management

11.1 Lifecycle Management Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

OBS allows you to set lifecycle rules for buckets to automatically transit the storage class of objects and delete expired objects, to effectively use storage features and optimize the storage space. You can set multiple lifecycle rules to match different object name prefixes. A lifecycle rule must contain:

- Rule ID, which uniquely identifies the rule
- A shared prefix of object names that are under the control of this rule
- Transition policy of an object of the latest version, which can be specified in either mode:
 - a. How many days after the object is created
 - b. Transition date
- Expiration time of an object with the latest version, which can be specified in either mode:
 - a. How many days after the object is created
 - b. Expiration date
- Transition policy of a noncurrent object version, which can be specified in the following mode:
 - How many days after the object becomes a noncurrent object version
- Expiration time of a noncurrent object version, which can be specified in the following mode:
 - How many days after the object becomes a noncurrent object version
- Identifier specifying whether the setting is effective

For more information, see [Lifecycle Management](#).

 NOTE

- An object will be automatically deleted by the OBS server once it expires.
- The time set in the transition policy of an object must be earlier than its expiration time, and the time set in the transition policy of a noncurrent object version must be earlier than its expiration time.
- The configured expiration time and transition policy for a noncurrent object version will take effect only when the versioning is enabled or suspended for a bucket.

11.2 Setting Lifecycle Rules

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call `ObsClient.SetBucketLifecycle` to set lifecycle rules.

Setting an Object Transition Policy

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//Set an object transition policy.
try
{
    SetBucketLifecycleRequest request = new SetBucketLifecycleRequest();
    request.BucketName = "bucketname";
    request.Configuration = new LifecycleConfiguration();
    LifecycleRule rule1 = new LifecycleRule();
    rule1.Id = "rule1";
    rule1.Prefix = "prefix";
    rule1.Status = RuleStatusEnum.Enabled;
    Transition transition = new Transition();
    rule1.Transitions.Add(transition);
    // Specify that objects whose names contain the prefix will be transited 30 days after creation.
    transition.Days = 30;
    // Specify the storage class that the object will be transited to.
    transition.StorageClass = StorageClassEnum.Warm;
    NoncurrentVersionTransition noncurrentVersionTransition = new NoncurrentVersionTransition()
    rule1.NoncurrentVersionTransitions.Add(noncurrentVersionTransition);
    // Specify that objects whose names contain the prefix will be transited 60 days after changing into
    noncurrent versions.
    noncurrentVersionTransition.NoncurrentDays = 60;
    // Specify the storage class that a noncurrent version will be transited to.
    noncurrentVersionTransition.StorageClass = StorageClassEnum.Warm;
    request.Configuration.Rules.Add(rule1);
    SetBucketLifecycleResponse response = client.SetBucketLifecycle(request);
    Console.WriteLine("Set bucket lifecycle response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Setting an Object Expiration Time

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Set the object expiration time.
try
{
    SetBucketLifecycleRequest request = new SetBucketLifecycleRequest();
    request.BucketName = "bucketname";
    request.Configuration = new LifecycleConfiguration();
    LifecycleRule rule1 = new LifecycleRule();
    rule1.Id = "rule1";
    rule1.Prefix = "prefix";
    rule1.Status = RuleStatusEnum.Enabled;
    rule1.Expiration = new Expiration();
    //Specify that objects whose names contain the prefix will expire 60 days after creation.
    rule1.Expiration.Days = 60;
    // Specify that objects whose names contain the prefix will expire 60 days after changing into noncurrent
versions.
    rule1.NoncurrentVersionExpiration = new NoncurrentVersionExpiration();
    rule1.NoncurrentVersionExpiration.NoncurrentDays = 60;
    request.Configuration.Rules.Add(rule1);
    SetBucketLifecycleResponse response = client.SetBucketLifecycle(request);
    Console.WriteLine("Set bucket lifecycle response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

11.3 Viewing Lifecycle Rules

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketLifecycle** to view lifecycle rules. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// View the bucket lifecycle.
try
{
    GetBucketLifecycleRequest request = new GetBucketLifecycleRequest();
    request.BucketName = "bucketname";
    GetBucketLifecycleResponse response = client.GetBucketLifecycle(request);
    foreach (LifecycleRule lifecycleRule in response.Configuration.Rules)
    {
        Console.WriteLine("Lifecycle rule id: {0}", lifecycleRule.Id);
        Console.WriteLine("Lifecycle rule prefix: {0}", lifecycleRule.Prefix);
        Console.WriteLine("Lifecycle rule status: {0}", lifecycleRule.Status);
        if (null != lifecycleRule.Expiration)
        {
            Console.WriteLine("expiration days: {0}", lifecycleRule.Expiration.Days);
        }
    }
}
```

```
        if (null != lifecycleRule.NoncurrentVersionExpiration)
        {
            Console.WriteLine("NoncurrentVersionExpiration NoncurrentDays: {0}",
lifecycleRule.NoncurrentVersionExpiration.NoncurrentDays);
        }
        foreach (Transition transition in lifecycleRule.Transitions)
        {
            Console.WriteLine("Transition Days : {0}", transition.Days);
            Console.WriteLine("Transition StorageClass : {0}", transition.StorageClass);
        }
        foreach (NonCurrentVersionTransition noncurrentVersionTransition in
lifecycleRule.NoncurrentVersionTransitions)
        {
            Console.WriteLine("NoncurrentVersionTransition NoncurrentDays: {0}",
noncurrentVersionTransition.NoncurrentDays);
            Console.WriteLine("NoncurrentVersionTransition StorageClass : {0}",
noncurrentVersionTransition.StorageClass);
        }
        Console.WriteLine("Get bucket lifecycle response: {0}", response.StatusCode);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

11.4 Deleting Lifecycle Rules

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.DeleteBucketLifecycle** to delete lifecycle rules. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Delete bucket lifecycles.
try
{
    DeleteBucketLifecycleRequest request = new DeleteBucketLifecycleRequest();
    request.BucketName = "bucketname";
    DeleteBucketLifecycleResponse response = client.DeleteBucketLifecycle(request);
    Console.WriteLine("Delete bucket lifecycle response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

12 CORS

12.1 CORS Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

CORS allows web application programs to access resources in other domains. OBS provides developers with APIs for facilitating cross-origin resource access.

For more information, see [CORS](#).

12.2 Setting CORS Rules

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.SetBucketCors** to set CORS rules for a bucket. If the bucket is configured with CORS rules, the newly set ones will overwrite the existing ones. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("*** Provide your Access Key ***", "*** Provide your Secret Key ***", "https://your-endpoint");
// Set the CORS rules for a bucket.
try
{
    SetBucketCorsRequest request = new SetBucketCorsRequest();
    request.BucketName = "bucketname";
}
```

```
request.Configuration = new CorsConfiguration();
CorsRule rule = new CorsRule();
rule.Id = "20170820";
// Specify the origin of the cross-domain request.
rule.AllowedOrigins.Add("http://www.a.com");
rule.AllowedOrigins.Add("http://www.b.com");
// Specify whether headers specified in Access-Control-Request-Headers in the OPTIONS request can
be used.
rule.AllowedHeaders.Add("x-obs-header");
// Specify the request method, which can be GET, PUT, DELETE, POST, or HEAD.
rule.AllowedMethods.Add(HttpVerb.HEAD);
rule.AllowedMethods.Add(HttpVerb.PUT);
rule.AllowedMethods.Add(HttpVerb.GET);
rule.AllowedMethods.Add(HttpVerb.POST);
rule.AllowedMethods.Add(HttpVerb.DELETE);
// Specify response headers that users can access using application programs.
rule.ExposeHeaders.Add("x-obs-test1");
rule.ExposeHeaders.Add("x-obs-test2");
rule.MaxAgeSeconds = 100;
request.Configuration.Rules.Add(rule);
SetBucketCorsResponse response = client.SetBucketCors(request);
Console.WriteLine("Set bucket cors response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

AllowedOrigins, **AllowedMethods**, and **AllowedHeaders**, respectively, can contain up to one wildcard character (*). Wildcard characters (*) indicate that all origins, operations, or headers are allowed.

12.3 Viewing CORS Rules

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketCors** to view CORS rules of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// View CORS rules.
try
{
    GetBucketCorsConfigurationRequest request = new GetBucketCorsConfigurationRequest();
    request.BucketName = "bucketname";
    GetBucketCorsResponse response = client.GetBucketCors(request);
    foreach (CorsRule rule in response.Configuration.Rules)
    {
        Console.WriteLine("rule id is: {0}\n", rule.Id);
        foreach (string allowOrigin in rule.AllowedOrigins)
        {
            Console.WriteLine("allowOrigin is: {0}\n", allowOrigin);
        }
        foreach (string allowHeader in rule.AllowedHeaders)
```

```
{
    Console.WriteLine("allowHeader is: {0}\n", allowHeader);
}
foreach (HttpVerb allowMethod in rule.AllowedMethods)
{
    Console.WriteLine("allowMethod is: {0}\n", allowMethod);
}
foreach (string exposeHeader in rule.ExposeHeaders)
{
    Console.WriteLine("exposeHeader is: {0}\n", exposeHeader);
}
Console.WriteLine("rule maxAgeSeconds is: {0}\n", rule.MaxAgeSeconds);
}
}
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

12.4 Deleting CORS Rules

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.DeleteBucketCors** to delete CORS rules of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Delete CORS rules.
try
{
    DeleteBucketCorsRequest request = new DeleteBucketCorsRequest();
    request.BucketName = "bucketname";
    DeleteBucketCorsResponse response = client.DeleteBucketCors(request);
    Console.WriteLine("Delete bucket cors response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

13 Access Logging

13.1 Logging Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

OBS allows you to configure access logging for buckets. After the configuration, access to buckets will be recorded in the format of logs. These logs will be saved in specific buckets in OBS.

For more information, see [Logging](#).

13.2 Enabling Bucket Logging

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call `ObsClient.SetBucketLogging` to enable bucket logging

NOTICE

The source bucket and target bucket of logging must be in the same region.

 NOTE

If the bucket is in the OBS Infrequent Access or Archive storage class, it cannot be used as the target bucket.

The **Agency** field indicates the name of the IAM agency for OBS created by the owner of the target bucket. For details about how to create an IAM agency, see the *IAM User Guide*.

Enabling Bucket Logging

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
try
{
    // Set the source bucket logging.
    SetBucketLoggingRequest putrequest = new SetBucketLoggingRequest();
    putrequest.BucketName = "bucketname";
    putrequest.Configuration = new LoggingConfiguration();
    putrequest.Configuration.TargetBucketName = "targetbucketname";
    putrequest.Configuration.TargetPrefix = "access-log.";
    putrequest.Configuration.Agency = "your agency";
    SetBucketLoggingResponse putresponse = client.SetBucketLogging(putrequest);
    Console.WriteLine("Set bucket logging response: {0}", putresponse.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

13.3 Viewing Bucket Logging

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketLogging** to view the logging configuration of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// View bucket logging.
try
{
    GetBucketLoggingRequest request = new GetBucketLoggingRequest
    {
        BucketName = "bucketname",
    };
    GetBucketLoggingResponse response = client.GetBucketLogging(request);
    Console.WriteLine("TargetBucketName is : " + response.Configuration.TargetBucketName);
    Console.WriteLine("TargetPrefix is : " + response.Configuration.TargetPrefix);
    Console.WriteLine("Get bucket logging response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
}
```

```
Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

13.4 Disabling Bucket Logging

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.SetBucketLogging** to delete all logs of a bucket so as to disable logging of the bucket. Sample code is as follows:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
try  
{  
    SetBucketLoggingRequest putrequest = new SetBucketLoggingRequest();  
    putrequest.BucketName = "bucketname";//Source bucket  
    putrequest.Configuration = new LoggingConfiguration();  
    SetBucketLoggingResponse putresponse = client.SetBucketLogging(putrequest);  
    Console.WriteLine("Delete bucket logging response: {0}", putresponse.StatusCode);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

14 Static Website Hosting

14.1 Static Website Hosting Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can upload the content files of the static website to your bucket in OBS as objects and configure the **public-read** permission on the files, and then configure the static website hosting mode for your bucket to host your static websites in OBS. After this, when third-party users access your websites, they actually access the objects in your bucket in OBS. When using static website hosting, you can configure request redirection to redirect specific or all requests.

For more information, see [Static Website Hosting](#).

14.2 Website File Hosting

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can perform the following to implement website file hosting:

- Step 1** Upload the website files to your bucket in OBS as objects and set the MIME type for the objects.
- Step 2** Set the object ACL to **public-read**.

Step 3 Access the objects using a browser.

----End

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
try
{
    //Set the MIME type for an object.
    PutObjectRequest request = new PutObjectRequest
    {
        BucketName = "bucketname",
        ObjectKey = "test.html",
        FilePath = "localfile.html", // Path of the local file uploaded. The file name must be specified.
        CannedAcl = CannedAclEnum.PublicRead, //Set the object ACL to public-read.
        ContentType = "text/html",
    };
    // Upload an object.
    PutObjectResponse response = client.PutObject(request);
    Console.WriteLine("put object response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

You can use `https://bucketname.your-endpoint/test.html` in a browser to access files hosted using the sample code.

14.3 Setting Website Hosting

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call `ObsClient.SetBucketWebsite` to set website hosting on a bucket.

Configuring the Default Homepage and Error Pages

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
//Configure the homepage and error pages.
try
{
    SetBucketWebsiteRequest request = new SetBucketWebsiteRequest();
    request.BucketName = "bucketname";
    request.Configuration = new WebsiteConfiguration();
    //Configure the default homepage.
    request.Configuration.IndexDocument = "index.html";
}
```

```
//Configure the error pages.  
request.Configuration.ErrorDocument = "error.html";  
SetBucketWebsiteResponse response = client.SetBucketWebsite(request);  
Console.WriteLine("Set bucket website response: {0}", response.StatusCode);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

Configuring the Redirection Rules

Sample code:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
// Set the redirection rule.  
try  
{  
    SetBucketWebsiteRequest request = new SetBucketWebsiteRequest();  
    request.BucketName = "bucketname";  
    request.Configuration = new WebsiteConfiguration(); //Configure the default homepage.  
    request.Configuration.IndexDocument = "index.html";  
    //Configure the error pages.  
    request.Configuration.ErrorDocument = "error.html";  
    RoutingRule routingRule = new RoutingRule();  
    routingRule.Redirect = new Redirect();  
    routingRule.Redirect.HostName = "www.example.com";  
    routingRule.Redirect.HttpRedirectCode = "305";  
    routingRule.Redirect.Protocol = ProtocolEnum.Http;  
    routingRule.Redirect.ReplaceKeyPrefixWith = "replacekeyprefix";  
    routingRule.Condition = new Condition();  
    routingRule.Condition.HttpErrorCodeReturnedEquals = "404";  
    routingRule.Condition.KeyPrefixEquals = "keyprefix";  
    request.Configuration.RoutingRules.Add(routingRule);  
    SetBucketWebsiteResponse response = client.SetBucketWebsite(request);  
    Console.WriteLine("Set bucket website response: {0}", response.StatusCode);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

Configuring Redirection for All Requests

Sample code:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
// Configure that all requests will be redirected.  
try  
{  
    SetBucketWebsiteRequest request = new SetBucketWebsiteRequest();  
    request.BucketName = "bucketname";  
    request.Configuration = new WebsiteConfiguration();  
    request.Configuration.RedirectAllRequestsTo = new RedirectBasic();  
    request.Configuration.RedirectAllRequestsTo.HostName = "www.example.com";  
    request.Configuration.RedirectAllRequestsTo.Protocol = ProtocolEnum.Https;  
    SetBucketWebsiteResponse response = client.SetBucketWebsite(request);  
    Console.WriteLine("Set bucket website response: {0}", response.StatusCode);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
}
```

```
Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

14.4 Viewing Website Hosting Settings

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketWebsite** to view the hosting settings of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
// View hosting settings.  
try  
{  
    GetBucketWebsiteRequest request = new GetBucketWebsiteRequest();  
    request.BucketName = "bucketname";  
    GetBucketWebsiteResponse response = client.GetBucketWebsite(request);  
    Console.WriteLine("GetBucketWebsite website configuration error document: {0}",  
response.Configuration.ErrorDocument);  
    Console.WriteLine("GetBucketWebsite website configuration index document: {0}",  
response.Configuration.IndexDocument);  
    Console.WriteLine("Get bucket website response: {0}", response.StatusCode);  
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

14.5 Deleting Website Hosting Settings

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.DeleteBucketWebsite** to delete the hosting settings of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.  
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://  
your-endpoint");  
// View hosting settings.  
try  
{  
    DeleteBucketWebsiteRequest request = new DeleteBucketWebsiteRequest();  
    request.BucketName = "bucketname";  
    DeleteBucketWebsiteResponse response = client.DeleteBucketWebsite(request);  
    Console.WriteLine("Delete bucket website response: {0}", response.StatusCode);  
}
```

```
}  
catch (ObsException ex)  
{  
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);  
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

15 Tag Management

15.1 Tagging Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Tags are used to identify and classify OBS buckets.

For more information, see [Tags](#).

15.2 Setting Bucket Tags

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.SetBucketTagging** to set bucket tags. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Set bucket tags.
try
{
    SetBucketTaggingRequest request = new SetBucketTaggingRequest();
    request.BucketName = "bucketname";
    Tag tag1 = new Tag();
    tag1.Key = "tag1";
    tag1.Value = "value1";
```

```
Tag tag2 = new Tag();
tag2.Key = "tag2";
tag2.Value = "value2";
request.Tags.Add(tag2);
request.Tags.Add(tag1);
SetBucketTaggingResponse response = client.SetBucketTagging(request);
Console.WriteLine("Set bucket tag response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

NOTE

- A bucket can have up to 10 tags.
- The key and value pair of a tag can be composed of Unicode characters.

15.3 Viewing Bucket Tags

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketTagging** to view bucket tags. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Obtain bucket tags.
try
{
    GetBucketTaggingRequest request = new GetBucketTaggingRequest
    {
        BucketName = "bucketname",
    };
    GetBucketTaggingResponse response = client.GetBucketTagging(request);
    foreach (Tag tag in response.Tags)
    {
        Console.WriteLine("Get bucket Tagging response Key: {0}" + tag.Key);
        Console.WriteLine("Get bucket Tagging response Value:{0} " + tag.Value);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

15.4 Deleting Bucket Tags

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.DeleteBucketTagging** to delete bucket tags. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// Delete bucket tags.
try
{
    DeleteBucketTaggingRequest request = new DeleteBucketTaggingRequest
    {
        BucketName = "bucketname",
    };
    DeleteBucketTaggingResponse response = client.DeleteBucketTagging(request);
    Console.WriteLine("Delete bucket tag response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

16 Event Notification

16.1 Event Notification Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

The event notification function allows users to be notified of their operations on buckets, ensuring users know events happened on buckets in a timely manner. Currently, OBS supports event notifications through Simple Message Notification (SMN) and FunctionGraph.

For more information, see [Event Notification](#).

16.2 Configuring Event Notification

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.SetBucketNotification** to set event notification for a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Configure event notification.
try
{
    FilterRule filterRule1 = new FilterRule();
```

```
filterRule1.Name = FilterNameEnum.Prefix;
filterRule1.Value = "smn";
TopicConfiguration topicConfiguration1 = new TopicConfiguration();
topicConfiguration1.Id = "Id001";
topicConfiguration1.Topic = "your topic1 URN";
topicConfiguration1.Events.Add(EventTypeEnum.ObjectCreatedAll);
topicConfiguration1.FilterRules.Add(filterRule1);
FilterRule filterRule2 = new FilterRule();
filterRule2.Name = FilterNameEnum.Suffix;
filterRule2.Value = ".jpg";
TopicConfiguration topicConfiguration2 = new TopicConfiguration();
topicConfiguration2.Id = "Id002";
topicConfiguration2.Topic = "your topic2 URN";
topicConfiguration2.Events.Add(EventTypeEnum.ObjectCreatedAll);
topicConfiguration2.FilterRules.Add(filterRule2);
NotificationConfiguration notificationConfiguration = new NotificationConfiguration();
notificationConfiguration.TopicConfigurations.Add(topicConfiguration1);
notificationConfiguration.TopicConfigurations.Add(topicConfiguration2);

FilterRule filterRule3 = new FilterRule();
filterRule3.Name = FilterNameEnum.Prefix;
filterRule3.Value = "xxx";
FunctionGraphConfiguration functionGraphConfiguration = new FunctionGraphConfiguration();
functionGraphConfiguration.Id = "Id001";
functionGraphConfiguration.Topic = "your function graph URN";
functionGraphConfiguration.Events.Add(EventTypeEnum.ObjectCreatedAll);
functionGraphConfiguration.FilterRules.Add(filterRule3);
notificationConfiguration.FunctionGraphConfigurations.Add(functionGraphConfiguration);
SetBucketNotificationRequest request = new SetBucketNotificationRequest
{
    BucketName = "bucketname",
    Configuration = notificationConfiguration,
};
SetBucketNotificationResponse response = client.SetBucketNotification(request);
Console.WriteLine("Set bucket notification response: {0}", response.StatusCode);
}

catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

16.3 Viewing Event Notification Settings

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

You can call **ObsClient.GetBucketNotification** to view event notification settings of a bucket. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://your-endpoint");
// View event notification settings.
try
{
    GetBucketNotificationRequest request = new GetBucketNotificationRequest
    {
        BucketName = "bucketname",
```

```
};
GetBucketNotificationReponse response = client.GetBucketNotification(request);
if (response.Configuration.FunctionGraphConfigurations.Count > 0)
{
    foreach (FunctionGraphConfiguration functionGraphConfig in
response.NotificationConfiguration.FunctionGraphConfigurations)
    {
        Console.WriteLine("ID is : {0}", functionGraphConfig.Id);
        Console.WriteLine("Topic is : {0}", functionGraphConfig.Topic);
        foreach (EventTypeEnum e in functionGraphConfig.Events)
        {
            Console.WriteLine("Event is : {0}", e);
        }
        foreach (FilterRule filterRule in functionGraphConfig.FilterRules)
        {
            Console.WriteLine("Name is : {0}", filterRule.Name);
            Console.WriteLine("Value is : {0}", filterRule.Value);
        }
    }
}
if (response.Configuration.TopicConfigurations.Count > 0)
{
    foreach (TopicConfiguration topicConfig in response.NotificationConfiguration.TopicConfigurations)
    {
        Console.WriteLine("ID is : {0}", topicConfig.Id);
        Console.WriteLine("TopicConfiguration is : {0}", topicConfig.Topic);
        foreach (EventTypeEnum e in topicConfig.Events)
        {
            Console.WriteLine("Event is : {0}", e);
        }
        foreach (FilterRule filterRule in topicConfig.FilterRules)
        {
            Console.WriteLine("Name is : {0}", filterRule.Name);
            Console.WriteLine("Value is : {0}", filterRule.Value);
        }
    }
}
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

16.4 Disabling Event Notification

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

To disable event notification on buckets is to call **ObsClient.SetBucketNotification** to clear all event notification settings. Sample code is as follows:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Disable event notification.
try
{
    PutBucketNotificationRequest request = new PutBucketNotificationRequest()
```

```
{
    BucketName = "bucketname",
    Configuration = new NotificationConfiguration(),
};
PutBucketNotificationResponse response = client.SetBucketNotification(request);
Console.WriteLine("Delete bucket notification response: {0}", response.StatusCode);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

17 Server-Side Encryption

17.1 Server-Side Encryption Overview

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

OBS supports server-side encryption.

For more information, see [Server-Side Encryption](#).

17.2 Encryption Description

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

The following table lists APIs related to server-side encryption:

OBS .NET SDK API Function	Description	Supported Encryption Type
ObsClient.PutObject	Sets the encryption algorithm and key during object upload to enable server-side encryption.	SSE-KMS SSE-C

OBS .NET SDK API Function	Description	Supported Encryption Type
ObsClient.GetObject	Sets the decryption algorithm and key during object upload to decrypt the object.	SSE-C
ObsClient.CopyObject	<ol style="list-style-type: none"> 1. Sets the decryption algorithm and key for decrypting the source object during object copy. 2. Sets the encryption algorithm and key during object copy to enable the encryption algorithm for the target object. 	SSE-KMS SSE-C
ObsClient.GetObjectMetadata	Sets the decryption algorithm and key when obtaining the object metadata to decrypt the object.	SSE-C
ObsClient.InitiateMultipartUpload	Sets the encryption algorithm and key when initializing a multipart upload to enable server-side encryption for the final object generated.	SSE-KMS SSE-C
ObsClient.UploadPart	Sets the encryption algorithm and key during multipart upload to enable server-side encryption for parts.	SSE-C
ObsClient.CopyPart	<ol style="list-style-type: none"> 1. Sets the decryption algorithm and key for decrypting the source object during partial object copy. 2. Sets the encryption algorithm and key during partial object copy to enable the encryption algorithm for the target object part. 	SSE-C

17.3 Example of Encryption

NOTICE

If you have any questions during development, post them on the [Issues](#) page of GitHub. For details about parameters and usage of each API, see the [API Reference](#)

Encrypting an Object to Be Uploaded

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Generate an encryption key.
System.Security.Cryptography.Aes aesEncryption = System.Security.Cryptography.Aes.Create();
aesEncryption.KeySize = 256;
aesEncryption.GenerateKey();
string customerkey = Convert.ToBase64String(aesEncryption.Key);
// Upload an object.
try
{
    // When uploading an object, use the SSE-KMS algorithm to encrypt the object.
    SseKmsHeader kms = new SseKmsHeader();
    kms.Algorithm = SseKmsAlgorithmEnum.Kms;
    PutObjectRequest request1 = new PutObjectRequest
    {
        BucketName = "bucketname",
        Key = "objectname1",
        FilePath = "filePath1",
        SseHeader = kms,
    };
    client.PutObject(request1);
    // When uploading an object, use the SSE-C algorithm to encrypt the object.
    PutObjectRequest request2 = new PutObjectRequest
    {
        BucketName = "bucketname",
        Key = "objectname2",
        FilePath = "filePath2",
        SseHeader = new SseCHeader()
        {
            Algorithm = SseCAlgorithmEnum.Aes256,
            KeyBase64 = customerkey
        }
    };
    client.PutObject(request2);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

Decrypting a To-Be-Download Object

Sample code:

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Download an object.
try
{
    // When downloading an object, use the SSE-C algorithm to decrypt it.
    GetObjectRequest request = new GetObjectRequest
    {
        BucketName = "bucketname",
        Key = "objectname2",
        // The key used here must be the one used for uploading the object.
        SseCHeader = new SseCHeader()
        {
            Algorithm = SseCAlgorithmEnum.Aes256,
            KeyBase64 = "customerkey"
        }
    };
    client.GetObject(request);
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
}
```

```
Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);  
}
```

18 Troubleshooting

18.1 OBS Server-Side Error Codes

If the OBS server encounters an error when processing a request, a response containing the error code and error description is returned. The following table lists details about each error code and HTTP status code.

Error Code	Description	HTTP Status Code
AccessDenied	Access denied.	403 Forbidden
AccessForbidden	Insufficient permission.	403 Forbidden
AccountProblem	Your account encounters a problem that prevents the operation from completing. The account may be expired or frozen.	403 Forbidden
AllAccessDisabled	The user has no permission to perform a specific operation.	403 Forbidden
AmbiguousGrantByEmailAddress	Multiple accounts share one email address.	400 Bad Request
BadDigest	The specified value of Content-MD5 does not match the value received by OBS.	400 Bad Request
BadDomainName	Invalid domain name.	400 Bad Request
BadRequest	Invalid request parameter.	400 Bad Request

Error Code	Description	HTTP Status Code
BucketAlreadyExists	The requested bucket name already exists. The bucket namespace is shared by all users of OBS. Try again with another bucket name.	409 Conflict
BucketAlreadyOwnedByYou	Your previous request for creating the named bucket succeeded and you already own it.	409 Conflict
BucketNotEmpty	The bucket that you tried to delete is not empty.	409 Conflict
CredentialsNotSupported	This request does not support security credentials.	400 Bad Request
CustomDomainAlreadyExist	The configured domain already exists.	400 Bad Request
CustomDomainNotExist	The domain to be operated does not exist.	400 Bad Request
DeregisterUserId	The user has been deregistered.	403 Forbidden
EntityTooSmall	The size of the object to be uploaded is smaller than the lower limit.	400 Bad Request
EntityTooLarge	The size of the object to be uploaded exceeds the upper limit.	400 Bad Request
FrozenUserId	The user has been frozen.	403 Forbidden
IllegalVersioningConfigurationException	Invalid versioning configuration in the request	400 Bad Request
IllegalLocationConstraintException	The configured region limitation is inconsistent with the region where it resides.	400 Bad Request
InArrearOrInsufficientBalance	The subscriber owes fees or the account balance is insufficient, and the subscriber does not have the permission to perform an operation.	403 Forbidden

Error Code	Description	HTTP Status Code
IncompleteBody	Incomplete request body.	400 Bad Request
IncorrectNumberOfFilesInPost Request	Each POST request must contain one file to be uploaded.	400 Bad Request
InlineDataTooLarge	The size of inline data exceeds the upper limit.	400 Bad Request
InsufficientStorageSpace	Insufficient storage space.	403 Forbidden
InternalServerError	An internal error occurs. Try again later.	500 Internal Server Error
InvalidAccessKeyId	The access key ID provided by the customer does not exist in the system.	403 Forbidden
InvalidAddressingHeader	The anonymous role must be specified.	N/A
InvalidArgument	Invalid parameter.	400 Bad Request
InvalidBucketName	The specified bucket name in the request is invalid.	400 Bad Request
InvalidBucket	The bucket to be accessed does not exist.	400 Bad Request
InvalidBucketState	Invalid bucket status.	409 Conflict
InvalidBucketStoragePolicy	An invalid new policy is specified during bucket policy modification.	400 Bad Request
InvalidDigest	The specified Content-MD5 in the HTTP header is invalid.	400 Bad Request
InvalidEncryptionAlgorithmError	Incorrect encryption algorithm.	400 Bad Request
InvalidLocationConstraint	The location specified during bucket creation is invalid.	400 Bad Request
InvalidPart	One or more specified parts are not found. The parts may not be uploaded or the specified entity tags (ETags) do not match the parts' ETags.	400 Bad Request

Error Code	Description	HTTP Status Code
InvalidPartOrder	Parts are not listed in ascending order by part number.	400 Bad Request
InvalidPayer	All accesses to this object are disabled.	403 Forbidden
InvalidPolicyDocument	The content of the form does not meet the conditions specified in the policy document.	400 Bad Request
InvalidRange	The requested range cannot be obtained.	416 Client Requested Range Not Satisfiable
InvalidRedirectLocation	Invalid redirect location.	400 Bad Request
InvalidRequest	Invalid request.	400 Bad Request
InvalidRequestBody	Invalid POST request body.	400 Bad Request
InvalidSecurity	Invalid security credentials.	403 Forbidden
InvalidStorageClass	The specified storage class is invalid.	400 Bad Request
InvalidTargetBucketForLogging	The delivery group has no ACL permission for the target bucket.	400 Bad Request
InvalidURI	The specified URI cannot be resolved.	400 Bad Request
KeyTooLong	The provided key is too long.	400 Bad Request
MalformedACLError	The provided XML file is in an incorrect format or does not meet format requirements.	400 Bad Request
MalformedError	The XML format in the request is incorrect.	400 Bad Request
MalformedLoggingStatus	The XML format of Logging is incorrect.	400 Bad Request
MalformedPolicy	The bucket policy does not pass.	400 Bad Request

Error Code	Description	HTTP Status Code
MalformedPOSTRequest	The body of the POST request is in an incorrect format.	400 Bad Request
MalformedQuotaError	The Quota XML format is incorrect.	400 Bad Request
MalformedXML	An XML file of a configuration item is in incorrect format. The error message states: "The XML you provided was not well-formed or did not validate against our published schema."	400 Bad Request
MaxMessageLengthExceeded	The request is too long.	400 Bad Request
MaxPostPreDataLengthExceeded Error	The POST request fields prior to the file to be uploaded are too large.	400 Bad Request
MetadataTooLarge	The size of the metadata header has exceeded the upper limit.	400 Bad Request
MethodNotAllowed	The specified method is not allowed against the requested resource.	405 Method Not Allowed
MissingContentLength	The HTTP header Content-Length is not provided.	411 Length Required
MissingRegion	The region information is missing in the request, and the default region is required in the system.	400 Bad Request
MissingRequestBodyError	An empty XML file is sent as a request. The error message states: "Request body is empty."	400 Bad Request
MissingRequiredHeader	A required header is missing in the request.	400 Bad Request
MissingSecurityHeader	A required header is missing in the request.	400 Bad Request
NoSuchBucket	The bucket does not exist.	404 Not Found
NoSuchBucketPolicy	No bucket policy exists.	404 Not Found

Error Code	Description	HTTP Status Code
NoSuchCORSConfiguration	No CORS configuration exists.	404 Not Found
NoSuchCustomDomain	The requested user domain does not exist.	404 Not Found
NoSuchKey	The specified key does not exist.	404 Not Found
NoSuchLifecycleConfiguration	The requested Lifecycle does not exist.	404 Not Found
NoSuchPolicy	The specified policy name does not exist.	404 Not Found
NoSuchUpload	The specified multipart upload does not exist. The upload ID does not exist or the multipart upload job has been aborted or completed.	404 Not Found
NoSuchVersion	The specified version ID does not match any existing version.	404 Not Found
NoSuchWebsiteConfiguration	The requested website does not exist.	404 Not Found
NotImplemented	The provided header implies a function that is unavailable.	501 Not Implemented
NotSignedUp	Your account is not signed up for OBS. OBS is available only after you sign up.	403 Forbidden
OperationAborted	A conflicting operation is being performed on this resource. Try again later.	409 Conflict
PermanentRedirect	The requested bucket must be addressed using a specified endpoint. Send all future requests to the endpoint.	301 Moved Permanently
PreconditionFailed	At least one of the specified preconditions is not met.	412 Precondition Failed

Error Code	Description	HTTP Status Code
Redirect	The request is temporarily redirected.	307 Moved Temporarily
RequestIsNotMultiPartContent	A bucket POST request must contain an enclosure-type multipart or the form-data.	400 Bad Request
RequestTimeout	No read or write operation has been performed within the timeout period of the socket connection between the user and the server.	400 Bad Request
RequestTimeTooSkewed	The request time and the server's time differ a lot.	403 Forbidden
RequestTorrentOfBucketError	Requesting the bucket's torrent file is not allowed.	400 Bad Request
ServiceNotImplemented	The request method is not implemented by the server.	501 Not Implemented
ServiceNotSupported	The request method is not supported by the server.	409 Conflict
ServiceUnavailable	The server is overloaded or has internal errors.	503 Service Unavailable
SignatureDoesNotMatch	The provided signature in the request does not match the signature calculated by OBS. Check your AK and SK and signature calculation method.	403 Forbidden
SlowDown	Reduce your request frequency.	503 Service Unavailable
System Capacity Not enough	Insufficient system space.	403 Forbidden
TooManyCustomDomains	Too many user domains are configured.	400 Bad Request
TemporaryRedirect	The request is redirected to the bucket while the domain name server (DNS) is being updated.	307 Moved Temporarily
TooManyBuckets	You have attempted to create more buckets than allowed.	400 Bad Request

Error Code	Description	HTTP Status Code
TooManyObjectCopied	The number of copies of a single object exceeds the upper limit.	400 Bad Request
TooManyWrongSignature	The request is rejected due to high-frequency errors.	400 Bad Request
UnexpectedContent	This request does not support fields with content.	400 Bad Request
UnresolvableGrantByEmailAddress	The provided email address does not match any recorded accounts.	400 Bad Request
UserKeyMustBeSpecified	The user's AK is not carried in the request.	400 Bad Request
WebsiteRedirect	The website request lacks bucketName .	301 Moved Permanently
KMS.DisabledException	The master key is disabled in the SSE-KMS mode.	400 Bad Request
KMS.NotFoundException	The customer master key (CMK) does not exist in SSE-KMS mode.	400 Bad Request
RestoreAlreadyInProgress	The Archive object is being restored. The request conflicts with another one.	409 Conflict
ObjectHasAlreadyRestored	The objects have been restored and the retention period of the objects cannot be shortened.	409 Conflict
InvalidObjectState	The restored object is not an Archive object.	403 Forbidden
InvalidTagError	An invalid tag is provided when configuring the bucket tag.	400 Bad Request
NoSuchTagSet	The specified bucket does not have a tag.	404 Not Found

18.2 Log Analysis

Log Path

Log files of OBS .NET SDK are saved in the path, usually the save directory of executable files of the project, specified in configuration file **Log4Net.config**.

Log Level

When current logs cannot be used to troubleshoot system faults, you can change the log level to obtain more information. You can obtain the most information in **DEBUG** logs and the least information in **ERROR** logs.

Log level description:

- **DEBUG**: debugging level
- **INFO**: information level
- **WARN**: warning level
- **ERROR**: error level

Analysis Method

To analyze and locate a problem or view the running status, you can find the related log file based on the date and view the running status or view logs in the log file for troubleshooting.

The procedure is as follows:

Step 1 Find related logs.

Find related API logs in the log file directory based on the time when the exception occurred and the operation. The following is an example of error logs:

```
2018-05-23 21:55:02,103 [9] INFO - ListObjectsRequest begin.
2018-05-23 21:55:02,526 [9] INFO - Send http request end, cost 385 ms
2018-05-23 21:55:02,536 [9] ERROR - Rethrowing as a ObsException error in PerformRequest
Request error, StatusCode:404, ErrorCode:NoSuchBucket, ErrorMessage:The specified bucket does not exist,
RequestId:0403000001638D4819383F2D4A2B2C50, HostId:N8OMsHew7O/
LMHua8qpm49geWphVJI6I2mnnzUIYwQwHAuzJw/kmV+O4ilcf0GRR
2018-05-23 21:55:02,548 [9] ERROR - ListObjectsRequest exception code: NoSuchBucket, with message:
Request error
2018-05-23 21:55:02,553 [9] INFO - ListObjectsRequest end, cost 449 ms
```

Step 2 Analyze the cause based on the error logs.

Assuming that the error code you obtain from the log file is **NoSuchBucket**, you can check it from the table in **OBS Server-Side Error Codes** and know the error information is "The specified bucket does not exist."

----End

18.3 Connection Timeout

A connection times out if **System.Net.WebException: Unable to connect to the remote server** ---> **System.Net.Sockets.SocketException: A connection attempt failed because the connected party did not properly respond after a period of time, or established connection failed because connected host has failed to respond** is displayed.

Such an error is often caused by an incorrect endpoint or network disconnection. Check whether the endpoint is correct or whether the network connection is normal.

18.4 Unmatched Signatures

If the HTTP status code obtained from **ObsException** is **403** and the OBS server-side error code is **SignatureDoesNotMatch**, check whether the AK/SK is correct.

18.5 SDK Custom Exceptions

SDK custom exceptions (**ObsException**) are thrown by **ObsClient**. Exceptions are usually OBS server-side errors, including **OBS error codes** and error information and aim to help users locate problems and troubleshoot faults.

ObsException contains the following error information:

- **ObsException.StatusCode**: HTTP status code
- **ObsException.ErrorCode**: OBS server-side error code
- **ObsException.ErrorMessage**: Error description returned by the OBS server
- **ObsException.RequestId**: Request ID returned by the OBS server
- **ObsException.HostId**: Requested server ID

18.6 SDK Common Response Headers

After you call an API in an instance of **ObsClient**, a sub-class of **ObsWebServiceResponse** will be returned. The sub-class contains information about HTTP/HTTPS response headers.

```
// Create an instance of ObsClient.
ObsClient client = new ObsClient("**** Provide your Access Key ****", "**** Provide your Secret Key ****", "https://
your-endpoint");
// Create a bucket.
try
{
    CreateBucketRequest request = new CreateBucketRequest()
    {
        BucketName = "bucketname",
    };
    ObsWebServiceResponse response = client.CreateBucket(request);
    // Obtain the request ID from the public response headers.
    Console.WriteLine("RequestId: {0}", response.RequestId);
    foreach(KeyValuePair<string,string> entry in res.Headers)
    {
```

```
        Console.WriteLine("{0}:{1}", entry.Key, entry.Value);
    }
}
catch (ObsException ex)
{
    Console.WriteLine("ErrorCode: {0}", ex.ErrorCode);
    Console.WriteLine("ErrorMessage: {0}", ex.ErrorMessage);
}
```

19 FAQ

19.1 How Can I Perform a Multipart Upload?

For details, see [Performing a Multipart Upload](#).

19.2 How Can I Create a Folder?

For details, see [Creating a Folder](#).

19.3 How Can I List All Objects in a Bucket?

For details, see [Listing Objects](#) and [Listing Versioning Objects](#).

19.4 How Can I Use a URL for Authorized Access?

See [Using a Temporary URL for Authorized Access](#).

19.5 How Can I Upload a Large Object in Multipart Mode?

For details, see [Performing a Partial Download](#).

19.6 How Can I Set an Object to Be Accessible to Anonymous Users?

For details, see [Website File Hosting](#).

19.7 How Can I Identify the Endpoint and Location of OBS?

For details, see [Obtaining Endpoints](#).

19.8 How Can I Obtain the AK/SK?

For details, see [Setting Up an OBS Environment](#).

A API Reference

For details about all parameters and definitions of APIs in the OBS .NET SDK, see the [Object Storage Service .NET SDK API Reference](#).

B Change History

Release Date	What's New
2020-02-18	This is the eighth official release. Modified the following section: <ul style="list-style-type: none">Optimized the description in Enabling Bucket Logging.
2019-11-20	This is the seventh official release. Reorganized the positions of the following sections: <ul style="list-style-type: none">Example ProgramsTechnical Support Channels
2019-08-21	This is the sixth official release. Modified the following section: Updated the addresses to download historical versions and change history in SDK Download Links .
2019-03-30	This is the fifth official release. Added the following section: API Reference
2019-03-05	This is the fourth official release. Modified the following section: <ul style="list-style-type: none">Added the description and code example for the function workflow service in each section of "Event Notification."Added rules for combining object link address formats in Object Upload Overview.Optimized the description in Using a Temporary URL for Authorized Access.
2018-08-31	This is the third official release. Added the following sections: <ul style="list-style-type: none">"Obtaining Upload Progress""Obtaining Download Progress"

Release Date	What's New
2018-06-11	This is the second official release. Reconstructed APIs.
2018-03-31	This is the first official release.