

Image Management Service User Guide

Image Management Service User Guide

Issue	01
Date	2025-05-12



Copyright © Huawei Cloud Computing Technologies Co., Ltd. 2025. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Cloud Computing Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are the property of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei Cloud and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Huawei Cloud Computing Technologies Co., Ltd.

Address: Huawei Cloud Data Center Jiaoxinggong Road
Qianzhong Avenue
Gui'an New District
Gui Zhou 550029
People's Republic of China

Website: <https://www.huaweicloud.com/intl/en-us/>

Contents

1 Scenario 1: Creating a System Disk Image from a Windows ECS..... 1

2 Scenario 2: Creating a Linux System Disk Image from an External Image File..... 4

1

Scenario 1: Creating a System Disk Image from a Windows ECS

If you have created and configured an ECS based on your service requirements (such as installing software and deploying an application environment), you can create a system disk image from the configured ECS. Then, any new ECSs created from this image will come with all the same software and other details preconfigured.

This guide describes how to create a system disk image from a Windows ECS.

Preparations

1. Sign up for Huawei Cloud and complete real-name authentication.
Before using IMS, [sign up for a HUAWEI ID and enable Huawei Cloud services](#) and [complete real-name authentication](#).
If you have enabled Huawei Cloud services and completed real-name authentication, skip this step.
2. Create an ECS.

Step 1: Check the ECS

1. Log in to the management console. In the service list, choose **Compute > Elastic Cloud Server**.
2. Locate the ECS and click **Remote Login**.
3. Perform the following operations on the ECS:
 - Delete sensitive data from the ECS to prevent data leaks.
 - Check the network configuration of the ECS and ensure that DHCP is configured for the ECS NICs. Enable remote desktop connection if needed. For details, see [Configuring DHCP](#) and [Enabling Remote Desktop Connection](#).
 - Check whether Cloudbase-Init has been installed in the ECS. After Cloudbase-Init is installed, user data can be injected into the new ECSs created from the image of this ECS. For example, you can use data injection to set the password of a new ECS. For details, see [Installing and Configuring Cloudbase-Init](#).

- Check and install PV and VirtIO drivers in the ECS so that the new ECSs created from the image of this ECS support both KVM and XEN virtualization and that the network performance will be improved. For details, see [Installing PV Drivers](#) and [Installing VirtIO Drivers](#).
- Run Sysprep on the ECS so that each of the new ECSs created from the image of this ECS has a unique SID in a domain. In a cluster, each ECS must have a unique SID. For details, see [Running Sysprep](#).

Step 2: Create a Windows System Disk Image

1. Select the ECS and in the **Operation** column choose **More > Manage Image > Create Image**.
2. In the **Image Type and Source** area, select **Create Image** for **Type** and **System disk image** for **Image Type**. Then, select the ECS.
3. In the **Image Information** area, enter basic information about the image.

Table 1-1 Image parameters

Parameter	Example Value	Description
Name	win-image	Enter a name for the image.
Enterprise Project	default	Select an enterprise project from the drop-down list. This parameter is available only if you have enabled enterprise projects or your account is an enterprise account. To enable this function, contact your customer manager. An enterprise project provides central management of cloud resources on a project.
Tag	Key: usage Value: project	(Optional) Set a tag key and a tag value for the image to make identification and management of your images easier.
Description	imageTest	(Optional) Describe the image.

4. Read and agree to the image disclaimer. Click **Next**.
5. Confirm the parameter settings and click **Submit**.
6. Go back to the private image list and view the image status.

NOTE

The time required for creating an image depends on the image file size, network status, and number of concurrent tasks. When the image status changes to **Normal**, the image is created successfully.

Follow-up Procedure

After a system disk image is created, you can use it to create an ECS or change the OS of an existing ECS. This way, you can migrate data from a server to another. For details, see:

- [Creating an ECS from an Image](#)
- [Changing the OS](#)

For more information, see [Creating a System Disk Image from a Windows ECS](#).

2

Scenario 2: Creating a Linux System Disk Image from an External Image File

You can import a local image or a system disk image from another cloud platform. After an image is imported, you can use it to create an ECS or reinstall the OS of an existing ECS.

This guide describes how to create a Linux system disk image from an external image file.

Preparations

1. Sign up for Huawei Cloud and complete real-name authentication.
Before using IMS, [sign up for a HUAWEI ID and enable Huawei Cloud services](#) and [complete real-name authentication](#).
If you have enabled Huawei Cloud services and completed real-name authentication, skip this step.

Step1: Prepare an Image File

You need to prepare an image file that meets the following requirements:

- OS: SUSE, Oracle Linux, Red Hat, Ubuntu, etc. (32-bit or 64-bit)
- Image format: VMDK, VHD, QCOW2, RAW, VHDX, QED, VDI, QCOW, ZVHD2, or ZVHD
- Image size: no larger than 128 GB. If the image size is between 128 GB and 1 TB, convert the image file into RAW or ZVHD2 and import it using fast import.
- Network: Files in the network rule directory are deleted and DHCP is configured for the NICs.
- Tools: Cloud-Init has been installed.
- Drivers: Native Xen and KVM drivers have been installed.
- File system: Disk identifiers in the GRUB and fstab files are changed to UUID.

NOTE


Click [here](#) to learn more about the file restrictions and how to check and configure an image file.

Step 2: Upload the Image File

You are advised to use OBS Browser+ to upload external image files to an OBS bucket. For details, see [OBS Browser+ Best Practices](#).

For how to download OBS Browser+, see [Downloading OBS Browser+](#).

Figure 2-1 Uploading an image file




Step 3: Register the Image File as a Private Image

1. Log in to the management console. In the service list, choose **Compute > Image Management Service**.
2. In the image list, click **Create Image** in the upper right corner.
3. In the **Image Type and Source** area, select **Import Image** for **Type** and **System disk image** for **Image Type**. Select the bucket storing the image file from the list and then select the image file.

Table 2-1 Image parameters

Parameter	Example Value	Description
Enable automatic configuration	Enable	If you select this option, the system will automatically check and optimize the image file. For details, see What Will the System Do to an Image File When I Use the File to Register a Private Image?
Function	ECS system disk image	This parameter specifies whether the image is used to create ECSs or BMSs. The value can be ECS system disk image or BMS system disk image .

Parameter	Example Value	Description
Architecture	x86	<p>The value can be x86 or ARM.</p> <ul style="list-style-type: none">• If the system identifies that the architecture in the image file is different from what you set here, the identified architecture prevails.• If the system fails to identify an architecture, the architecture you set will be used.
Boot Mode	BIOS	<p>This parameter is optional. The value can be BIOS or UEFI. For details about the differences between them, see How Is BIOS Different from UEFI?</p> <p>For details about which OSs support UEFI boot, see OSs supporting UEFI Boot Mode.</p> <p>The boot mode must be the same as that in the image file. You need to confirm which boot mode is used in the image file. After you select the right boot mode, the boot mode will be configured for the image at the background. Select the right boot mode, or ECSs created from the image will not be able to boot up.</p>
OS	Ubuntu 20.04 server 64bit	<p>To ensure that the image can be created and used properly, select an OS consistent with that in the image file. If you do not select an OS, the system attempts to automatically identify the OS in the image file.</p> <p>NOTE</p> <ul style="list-style-type: none">• If the system identifies that the OS in the image file is different from the one you select here, the identified OS prevails.• If the system fails to identify an OS, the OS you select will be used.• If the OS you selected or identified by the system is inconsistent with the actual one, ECSs created from the image file may not work properly.

Parameter	Example Value	Description
System Disk (GB)	40	<p>The system disk capacity (value range: 40 GB to 1024 GB). Ensure that this value is not less than the system disk capacity in the image file.</p> <p>NOTE</p> <p>If the uploaded VHD image is generated using qemu-img or similar tools, check the system disk capacity based on What Do I Do If the System Disk Capacity in a VHD Image File Exceeds the One I Have Specified on the Management Console When I Use This File to Register a Private Image?</p>
Data Disk (GB)	Not add	<p>You can also add data disks to the image. You need to obtain an image file containing data disks in advance. This function is used to migrate VMs and data disks from other platforms to the current platform.</p> <p>To add data disks, click , configure the data disk capacity, and click Select Image File. In the displayed dialog box, select the target bucket and then the target image file containing the data disk.</p> <p>A maximum of three data disks can be added.</p>
Name	Ubuntulma ge	Enter a name for the image.
Encryption	Not select	<p>(Optional) If you want to encrypt the image, select KMS encryption and select the key to be used from the key list. After you select KMS encryption, the system will create a default key ims/default for you. You can also select a key from the key list.</p> <p>For how to encrypt an image, see Creating an Encrypted Image.</p> <p>NOTE</p> <p>If the encrypted image needs to be shared with other tenants, use a custom key to encrypt it. Otherwise, the key cannot be authorized to other tenants, causing the sharing failure.</p>
Enterprise Project	default	<p>Select an enterprise project from the drop-down list. This parameter is available only if you have enabled enterprise projects or your account is an enterprise account.</p> <p>An enterprise project provides central management of cloud resources on a project.</p>

Parameter	Example Value	Description
Tag	Key: usage Value: project	(Optional) Set a tag key and a tag value for the image to make identification and management of your images easier. You are advised to create predefined tags in TMS. For details, see Creating Predefined Tags . NOTE If your organization has configured tag policies for images, you need to add tags to your images based on the policies. If you add a tag that does not comply with the tag policies, images may fail to be created. Contact the organization administrator to learn more about the tag policies. <ul style="list-style-type: none">Each tag consists of a key and a value. The key contains a maximum of 36 characters, and the value contains a maximum of 43 characters. The key cannot be left blank or be an empty string. The value cannot be left blank but can be an empty string.An image can have a maximum of 10 tags.
Description	imageTest	(Optional) Describe the image.

4. Read and agree to the image disclaimer. Click **Next**.
5. Confirm the parameter settings and click **Submit**.
6. Go back to the private image list. When the image status changes to **Normal**, the image is created successfully.

Follow-up Procedure

After a system disk image is created, you can use it to create an ECS or change the OS of an existing ECS. This way, you can migrate data from a server to another. For details, see:

- [Creating an ECS from an Image](#)
- [Changing the OS](#)

For more information, see [Creating a System Disk Image from an Image File](#).