

Resource Formation Service

User Guide

Issue 01
Date 2025-02-10



Copyright © Huawei Technologies Co., Ltd. 2025. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Huawei Technologies Co., Ltd.

Address: Huawei Industrial Base
Bantian, Longgang
Shenzhen 518129
People's Republic of China

Website: <https://www.huawei.com>

Email: support@huawei.com

Security Declaration

Vulnerability

Huawei's regulations on product vulnerability management are subject to the *Vul. Response Process*. For details about this process, visit the following web page:

<https://www.huawei.com/en/psirt/vul-response-process>

For vulnerability information, enterprise customers can visit the following web page:

<https://securitybulletin.huawei.com/enterprise/en/security-advisory>

Contents

1 Getting Started.....	1
1.1 Accessing Resource Formation Service.....	1
1.2 Viewing the Stack Status.....	1
1.3 Creating a Stack.....	2
1.4 Querying a Stack.....	11
1.5 Updating a Template or Parameter.....	12
1.6 Creating an Execution Plan.....	14
1.7 Viewing Estimated Fees.....	15
1.8 Deleting a Stack.....	18
1.9 Viewing Stack Details.....	19
2 Visual Designer.....	22
2.1 Introduction.....	22
2.2 Visual Designer UI.....	23
2.3 Cloud Services or Elements.....	24
2.4 Shortcut Keys of Visual Designer.....	28
2.5 Compiling a Template to Create an EVS Disk.....	28
3 Managing a Stack.....	33
4 Auditing.....	35
4.1 RFS Operations Supported by CTS.....	35
4.2 Viewing RFS Logs in CTS.....	36
5 IAM Agency.....	38

1 Getting Started

[1.1 Accessing Resource Formation Service](#)

[1.2 Viewing the Stack Status](#)

[1.3 Creating a Stack](#)

[1.4 Querying a Stack](#)

[1.5 Updating a Template or Parameter](#)

[1.6 Creating an Execution Plan](#)

[1.7 Viewing Estimated Fees](#)

[1.8 Deleting a Stack](#)

[1.9 Viewing Stack Details](#)

1.1 Accessing Resource Formation Service

1. Log in to the [Huawei Cloud console](#) and choose **Service List > Management & Governance > Resource Formation Service**.

The following table outlines the Huawei Cloud regions where Resource Formation Service (RFS) is available.

Site	Region Name	Region Code
Huawei Cloud European website	EU-Dublin	eu-west-101

1.2 Viewing the Stack Status

You can manage stack lifecycle (such as creation, update, deletion, and query) and the lifecycle of execution plans of a stack (such as creation, deletion, and query).

Table 1 describes stack statuses.

Table 2 describes execution plan statuses.

Table 1-1 Stack statuses

Status	Description
Creation Complete	The stack has been created but not yet deployed.
Deployment In Progress	Stack deployment is in progress.
Deployment Complete	The stack has been deployed.
Deployment Failed	The stack deployment failed.
Deletion In Progress	Stack deletion is in progress.
Deletion Failed	Stack deletion failed.
Rollback In Progress	Stack rollback is in progress.
Rollback Failed	Stack rollback failed.
Rollback Complete	The stack has been rolled back.


Table 1-2 Execution plan statuses

Status	Description
Creation In Progress	Execution plan creation is in progress.
Creation Failed	Execution plan creation failed.
Available	The execution plan is created and to be applied.
Applied	The execution plan has been applied.

1.3 Creating a Stack

On the **Stacks** page, click **Create Stack** in the upper right corner, as shown in **Figure 1-1**.

Figure 1-1 Creating a stack




Procedure:

1. Select a template.

There are two ways to select a template, as shown in [Figure 1-2](#): (1) Enter a URL of an OBS template. (2) Upload a local template file. (3) Select a template from **My Templates**.

Figure 1-2 Selecting a template



You can upload template files in either **.tf** or **.tf.json** format.

Sample of the **.tf** template for creating a VPC and an ECS:

```
terraform {
  required_providers {
    huaweicloud = {
      source = "huawei.com/provider/huaweicloud"
      version = "1.41.0"
    }
  }
}

provider "huaweicloud" {
  cloud = "myhuaweicloud.com"
  endpoints = {
    iam = "iam.cn-north-4.myhuaweicloud.com"
  }
  insecure = true
  region = "cn-north-4"
  auth_url = "https://iam.cn-north-4.myhuaweicloud.com:31943/v3"
}

variable "vpc_name" {
  type = string
  description = "vpc name"
  default = "rf_teststack_vpc"
  sensitive = true
  nullable = false
}

variable "subnet_name" {
  type = string
  description = "subnet name"
  default = "rf_teststack_subnet"
}

variable "ecs_name" {
  type = string
  description = "ecs name"
  default = "rf_teststack_ecs"
}

variable "ecs_admin_passwd" {
  type = string
  description = "ecs passwd"
}

resource "huaweicloud_vpc" "rf_doc_vpc" {
  name = var.vpc_name
  cidr = "192.168.0.0/16"
}
```

```
}

resource "huaweicloud_vpc_subnet" "rf_doc_subnet" {
  name      = var.subnet_name
  vpc_id    = huaweicloud_vpc.rf_doc_vpc.id
  cidr      = "192.168.1.0/24"
  gateway_ip = "192.168.1.1"
}

resource "huaweicloud_compute_instance" "rf_doc_ecs" {
  name          = var.ecs_name
  flavor_id     = "c7.large.2"
  admin_pass   = var.ecs_admin_passwd
  image_id     = "cecc4bcf-b055-4d35-bd5f-693d4412eaef"
  network {
    uuid = huaweicloud_vpc_subnet.rf_doc_subnet.id
  }
  system_disk_type = "SAS"
  system_disk_size = 100
  stop_before_destroy = false
  delete_disks_on_termination = true
  charging_mode     = "postPaid"
  auto_renew       = false
}

output "ecs_address" {
  value = huaweicloud_compute_instance.rf_doc_ecs.access_ip_v4
  description = "The ecs private address."
}

output "ecs_id" {
  value = huaweicloud_compute_instance.rf_doc_ecs.id
  description = "The ecs resource id."
}
```

Sample of the **.tf.json** template for creating a VPC and an ECS:

```
{
  "terraform": {
    "required_providers": {
      "huaweicloud": {
        "source": "huawei.com/provider/huaweicloud",
        "version": "1.41.0"
      }
    }
  },
  "provider": {
    "huaweicloud": {
      "cloud": "myhuaweicloud.com",
      "endpoints": {
        "iam": "iam.cn-north-4.myhuaweicloud.com"
      },
      "insecure": true,
      "region": "cn-north-4",
      "auth_url": "https://iam.cn-north-4.myhuaweicloud.com:31943/v3"
    }
  },
  "variable": {
    "vpc_name": {
      "type": "string",
      "description": "vpc name",
      "default": "rf_teststack_vpc",
      "sensitive": true,
      "nullable": false
    },
    "subnet_name": {
      "type": "string",
      "description": "subnet name",
      "default": "rf_teststack_subnet"
    }
  },
}
```



```
"ecs_name": {
  "type": "string",
  "description": "ecs name",
  "default": "rf_teststack_ecs"
},
"ecs_admin_passwd": {
  "type": "string",
  "description": "ecs passwd"
}
},
"resource": {
  "huaweicloud_vpc": {
    "rf_doc_vpc": {
      "name": "${var.vpc_name}",
      "cidr": "192.168.0.0/16"
    }
  },
  "huaweicloud_vpc_subnet": {
    "rf_doc_subnet": {
      "name": "${var.subnet_name}",
      "vpc_id": "${huaweicloud_vpc.rf_doc_vpc.id}",
      "cidr": "192.168.1.0/24",
      "gateway_ip": "192.168.1.1"
    }
  },
  "huaweicloud_compute_instance": {
    "rf_doc_ecs": {
      "name": "${var.ecs_name}",
      "flavor_id": "c7.large.2",
      "admin_pass": "${var.ecs_admin_passwd}",
      "image_id": "cecc4bcf-b055-4d35-bd5f-693d4412eaef",
      "network": {
        "uuid": "${huaweicloud_vpc_subnet.rf_doc_subnet.id}"
      },
      "system_disk_type": "SAS",
      "system_disk_size": 100,
      "stop_before_destroy": false,
      "delete_disks_on_termination": true,
      "charging_mode": "postPaid",
      "auto_renew": false
    }
  }
},
"output": {
  "ecs_address": {
    "value": "${huaweicloud_compute_instance.rf_doc_ecs.access_ip_v4}",
    "description": "The ecs private address."
  },
  "ecs_id": {
    "value": "${huaweicloud_compute_instance.rf_doc_ecs.id}",
    "description": "The ecs resource id."
  }
}
}
```

 **CAUTION**

The sample template contains charged resources. Check whether resources need to be enabled before using the template.

This template consists of five parts:

- a. **huaweicloud_vpc** in **resource** indicates VPC information.

- b. **huaweicloud_vpc_subnet** in **resource** indicates information about a subnet defined in the VPC. A subnet is a segment within the IP address range of the VPC.
 - c. **huaweicloud_compute_instance** in **resource** indicates information about an ECS defined in the template.
 - d. **variable** indicates variables defined by users in templates during stack creation and deployment.
 - e. **output** defines the outputs of templates. After a stack is created, its output is generated based on the definition and displayed on the **Outputs** tab page.
2. Configure parameters.
- Click **Next** to go to the **Configure Parameters** page, where you can modify the stack name and description, as shown in **Figure 1-3**.

CAUTION

The stack name must start with a letter and can contain a maximum of 128 characters, including letters, digits, underscores (_), and hyphens (-). The name must be unique.

A stack description can contain a maximum of 1,024 characters.

Figure 1-3 Configuring parameters

Parameter	Value	Type	Description
* vpc_name	rf_teststack_vpc	string	vpc name
subnet_name	rf_teststack_subnet	string	subnet name
ecs_name	rf_teststack_ecs	string	ecs name
ecs_admin_passwd		string	ecs passwd

Parameters marked with a red asterisk (*) are mandatory. Set these parameters to valid values.

If you enter an invalid value, the text box will turn red (as shown in **Figure 1-4**) and clicking **Next** will not redirect you to the next page.

Figure 1-4 Text box with an invalid value

Parameter	Value
* vpc_name	

Click **Next**. The **Configure Stack** page is displayed.


CAUTION

If the stack name or description is imported using a URL and contains special characters, the characters must be encoded following the HTTP encoding rules first.

Check whether the default VPC, subnet, and ECS names used on this page already exist on the corresponding consoles. If the names already exist, change them to unique ones to prevent creation failures.

3. Configure the stack.
Click **Next** to go to the **Advanced Settings** page, as shown in [Figure 1-5](#).

Figure 1-5 Configuring the stack



Mandatory parameter (marked with *)

Agency: An agency can clearly define operation permissions of RFS (such as creation, update, and deletion) on stack resources. If the agency permissions are insufficient, subsequent operations may fail.

Optional parameters:


Deletion Protection: prevents the stack from being deleted accidentally. After a stack is created, you can update this configuration by clicking **Update** in the **Operation** column.

Auto-Rollback: Enabling auto-rollback will revert the stack to the last successful resource status in the event of a failed operation.

Click **Next** to go to the **Confirm Configurations** page.


4. Confirm the configurations.
After you confirm the configurations, you can click either **Create Execution Plan** or **Directly Deploy Stack**.
 - a. If you click **Directly Deploy Stack**, a confirmation dialog box will be displayed.

Figure 1-6 Directly deploy stack



Click **Yes**. A new stack is generated and its status is **Deployment In Progress**, as shown in [Figure 1-7](#).

Figure 1-7 Deployment in progress




Then, the status changes to **Deployment Complete**, as shown in [Figure 1-8](#).

Figure 1-8 Deployment complete



- b. Clicking **Create Execution Plan** will open a dialog box where you can name and describe the execution plan, as shown in [Figure 1-9](#).


Figure 1-9 Create Execution Plan dialog box



Click **OK**. The **Execution Plans** tab page is displayed.


Wait until the execution plan is created and refresh the page. The execution plan status changes to **Available**, as shown in [Figure 1-10](#).

Figure 1-10 Available



Return to the stack list page. The stack status is **Creation Complete**, as shown in [Figure 1-11](#).

Figure 1-11 Stack list




CAUTION

Creating an execution plan can preview the resource attribute changes of the entire stack and evaluate the impact. If the execution plan meets your expectations, you can apply the plan. Creating an execution plan does not incur fees. The system changes your stack only when you execute the plan.


Click **Deploy** in the **Operation** column of the execution plan to deploy it, as shown in [Figure 1-12](#).

Figure 1-12 Execution plan dialog box




In the **Execution Plan** dialog box, click **Execute**. A message is displayed in the upper right corner, indicating that the execution plan is being deployed. Return to the stack list page. A new stack is generated and its status is **Deployment In Progress**, as shown in [Figure 1-13](#).

Figure 1-13 Deployment in progress




Then, the stack status changes to **Deployment Complete**, as shown in [Figure 1-14](#).

Figure 1-14 Deployment complete




On the **Execution Plans** tab page of the stack details page, the execution plan status is **Applied**, as shown in [Figure 1-15](#).

Figure 1-15 Applied



Click the **Events** tab. The event list shows that resources of the stack are deployed, as shown in [Figure 1-16](#).

Figure 1-16 Resources deployed




Time	Type	Description	Resource Name/Type	Associated Resource ID
2023/08/15 11:34:10 GMT+08:00	Log	Apply required resource success.	--	--
2023/08/15 11:34:15 GMT+08:00	--	Apply complete! Resources: 4 added, 0 changed, 0 destroyed.	--	--
2023/08/15 11:34:15 GMT+08:00	Creation Complete	huaweicloud_compute_instance: Creation complete after 1m5s [id-df99de86c4e14edc-aab7-955e063d86c]	Instance ECS	df99de86-c4e1-4edc-aab7-955e063d86c
2023/08/15 11:34:10 GMT+08:00	Creation In Progress	huaweicloud_compute_instance: Still creating. [1m0s elapsed]	Instance ECS	--
2023/08/15 11:34:30 GMT+08:00	Creation In Progress	huaweicloud_compute_instance: Still creating. [50s elapsed]	Instance ECS	--
2023/08/15 11:33:50 GMT+08:00	Creation In Progress	huaweicloud_compute_instance: Still creating. [40s elapsed]	Instance ECS	--
2023/08/15 11:33:40 GMT+08:00	Creation In Progress	huaweicloud_compute_instance: Still creating. [30s elapsed]	Instance ECS	--
2023/08/15 11:33:30 GMT+08:00	Creation In Progress	huaweicloud_compute_instance: Still creating. [20s elapsed]	Instance ECS	--
2023/08/15 11:33:20 GMT+08:00	Creation In Progress	huaweicloud_compute_instance: Still creating. [10s elapsed]	Instance ECS	--
2023/08/15 11:33:10 GMT+08:00	Creation In Progress	huaweicloud_compute_instance: Creating.	Instance ECS	--

You can view details on the console of the corresponding cloud service.

- i. In the service list, locate and click **Elastic Cloud Server**. On the displayed page, view the deployed ECS, as shown in [Figure 1-17](#).

Figure 1-17 ECS



Name/ID	Monitoring	AZ	Status	Specifications/Image	IP Address	Billing Mode	Tag	Operation
rt_teststack_ecs1 ecs0ee4bf-3f16-47a3-9696-9d549b...		AZ3	Running	1 vCPU 1 GB \$6... Public-CAD-HCE-B...	192.168.0.166 (Priv...	Pay-per-use	--	Remote Login More


Resources of the stack are deployed.

1.4 Querying a Stack

Log in to the RFS console and click **Stacks** in the navigation pane on the left. The stack list page is displayed.

In the search box above the stack list, enter the name of the target stack and click the search button, as shown in [Figure 1-18](#).

Figure 1-18 Querying a stack



Stack Name	Status	Description	Created	Updated	Operation
stack_20230210_1046_2mc 920184bf-89b0-44c9-8150-5e30a097e532	Deployment Complete	--	2023/02/10 10:47:01 GMT+08:00	2023/02/10 10:57:21 GMT+08:00	Delete Update


1.5 Updating a Template or Parameter

 **CAUTION**

Stack change records are not available. If you want to view change details, you are recommended to create an execution plan.

You can add cloud service resources or change resource specifications in either of the following ways: Go to the stack list page, locate the target stack, and click **Update** in the **Operation** column. Alternatively, go to the stack details page and click **Update Template/Parameter** in the upper right corner to enter the page for updating the stack, as shown in [Figure 1-19](#).

Figure 1-19 Selecting a template




You can select **Current Template** or **Replace Current Template** (use a new template) to update the stack.

Solution 1: Using the Current Template


1. Click **Next** to go to the **Configure Parameters** page and modify parameters on it, as shown in [Figure 1-20](#).

Figure 1-20 Configuring parameters



2. Click **Next** to go to the **Confirm Configurations** page, as shown in [Figure 1-21](#).

Figure 1-21 Confirming configurations



3. Click **Directly Deploy Stack**. The **Events** page is displayed. The status changes to **Update Complete**, as shown in [Figure 1-22](#).

Figure 1-22 Update complete


Time	Type	Description	Resource Name/Type	Associated Resource ID
2023/02/10 10:57:21 GMT+08:00	LOG	Apply required resource success.	--	--
2023/02/10 10:57:18 GMT+08:00	--	Apply complete Resources: 0 added, 3 changed, 0 destroyed.	--	--
2023/02/10 10:57:18 GMT+08:00	Update Complete	huaweicloud_compute_instance-ecs-1b0a1: Modifications complete after 2s [d1ec0ee48f-3f16-47a3-99f5-9d54956a342]	ecs-1b0a1 ECS	ec0ee48f-3f16-47a3-99f5-9d54956a342
2023/02/10 10:57:16 GMT+08:00	Update In Progress	huaweicloud_compute_instance-ecs-1b0a1: Modifying... [d1ec0ee48f-3f16-47a3-99f5-9d54956a342]	ecs-1b0a1 ECS	ec0ee48f-3f16-47a3-99f5-9d54956a342
2023/02/10 10:57:16 GMT+08:00	Update Complete	huaweicloud_vpc_subnet-vpc-subnet-upppp: Modifications complete after 1s [d1c35c3a47-6821-4164-916c-9455773a092]	vpc-subnet-upppp Subnet	c35c3a47-6821-4164-916c-9455773a092
2023/02/10 10:57:15 GMT+08:00	Update In Progress	huaweicloud_vpc_subnet-vpc-subnet-upppp: Modifying... [d1c35c3a47-6821-4164-916c-9455773a092]	vpc-subnet-upppp Subnet	c35c3a47-6821-4164-916c-9455773a092
2023/02/10 10:57:15 GMT+08:00	Update Complete	huaweicloud_vpc-vpc-ghnfv: Modifications complete after 1s [d133375627-9909-40e7-9be8-85af8448d74]	vpc-ghnfv VPC	33375627-9909-40e7-9be8-85af8448d74
2023/02/10 10:57:14 GMT+08:00	Update In Progress	huaweicloud_vpc-vpc-ghnfv: Modifying... [d133375627-9909-40e7-9be8-85af8448d74]	vpc-ghnfv VPC	33375627-9909-40e7-9be8-85af8448d74
2023/02/10 10:57:12 GMT+08:00	LOG	Creating required resource now.	--	--
2023/02/10 10:48:31 GMT+08:00	LOG	Apply required resource success.	--	--

Solution 2: Replacing the Current Template (see [Creating a Stack](#))

1.6 Creating an Execution Plan

On the stack list page, click the name of the stack to go to its details page. Click **Update Template/Parameter** in the upper right corner to go to the page for creating an execution plan, as shown in [Figure 1-23](#).

Figure 1-23 Page for creating an execution plan



The subsequent steps are the same as those for creating a stack, except for one difference that you need to click **Create Execution Plan** instead of **Directly Deploy Stack**.

Then, an execution plan is generated, but the stack is not directly deployed. If you create multiple execution plans, they will exist in the same stack, as shown in [Figure 1-24](#).


Figure 1-24 Execution plan list

Execution Plan Name/ID	Status	Estimated Price	Created	Description	Operation
executionPlan_20230210_1111_1p0f 82354e4c-1121-4609-96a9-23a205c29292	Available	View Details	2023/02/10 11:11:02 GMT+08:00	--	Delete Deploy
executionPlan_20230210_1110_7p0f 601272ac-0a99-4a03-b0a1-d87600c23768	Available	View Details	2023/02/10 11:10:40 GMT+08:00	--	Delete Deploy

Locate the row that contains the generated execution plan and click **Deploy** in the **Operation** column if you want to apply it.

If an execution plan is no longer used, click **Delete** in the **Operation** column. In the displayed dialog box, click **OK**, as shown in [Figure 1-25](#).

Figure 1-25 Deleting an execution plan



1.7 Viewing Estimated Fees

On the **Execution Plans** page, find the row where the created execution plan resides. Click **View Details** (as shown in [Figure 1-26](#)). The **Price Details** dialog box is displayed and you can see the estimated price, as shown in [Figure 1-27](#).

Figure 1-26 Viewing price details



Figure 1-27 Price details




Figure 1-28 shows the estimated price of yearly/monthly-billed resources. **Figure 1-29** shows the estimated price of pay-per-use resources. **Figure 1-30** shows the resources that do not support price inquiry.

Table 1-3 lists the resources that support price inquiry.

Figure 1-28 Yearly/Monthly

Price Details ✕

ⓘ This price is an estimate and may differ from the final price. [Pricing Details](#). Price inquiry is not supported for some resources. Go to [Price Calculator](#) to calculate the fees.

Total price Estimated yearly/monthly price: **\$1.46** Estimated pay-per-use price: **\$0.01/hour(s)**

Yearly/Monthly Pay-per-Use Export Price List

Cloud Pro...	Logical Name <small>?</small>	Region	Duration	Q...	Original Price	Discount Details	Estimated Sale Price
Elastic Volume	myvolume3	AP-Singapore	2month(s)	1	\$1.46	\$0.00	\$1.46

Close

Figure 1-29 Pay-per-use

Price Details ✕

ⓘ This price is an estimate and may differ from the final price. [Pricing Details](#). Price inquiry is not supported for some resources. Go to [Price Calculator](#) to calculate the fees.

Total price Estimated yearly/monthly price: **\$1.46** Estimated pay-per-use price: **\$0.01/hour(s)**

Yearly/Monthly Pay-per-Use Export Price List

Cloud Product	Logical Name <small>?</small>	Region	Qua...	Original Price	Discount Details	Estimated Sale Price
Elastic Volume Sen	myvolume2	AP-Singapore	1	\$0.01 /hour(s)	\$0.00 /hour(s)	\$0.01 /hour(s)

Close

Figure 1-30 To be supported

Price Details ✕

ⓘ This price is an estimate and may differ from the final price. [Pricing Details](#). Price inquiry is not supported for some resources. Go to [Price Calculator](#) to calculate the fees.

Total price ▲ Price inquiry is not supported for some resources. For details, see the "To Be Supported" tab page.

To Be Supported ? Export Price List

Cloud Product	Logical Name <small>?</small>	Cause
Virtual Private Cloud	sg-rxib3	Not supported

Close

Table 1-3 Cloud services/Resources that support price inquiry and billing modes

Cloud Service	Resource Type	Billing Mode
Elastic Cloud Server (ECS)	huaweicloud_compute_instance	Yearly/ Monthly and pay- per-use
Elastic Volume Service (EVS)	huaweicloud_evs_volume	Yearly/ Monthly and pay- per-use
Elastic IP (EIP)	huaweicloud_vpc_eip	Yearly/ Monthly and pay- per-use
Bandwidth	huaweicloud_vpc_bandwidth	Pay-per-use
Elastic Load Balance (ELB)	huaweicloud_elb_loadbalancer	Pay-per-use
NAT Gateway	huaweicloud_nat_gateway	Pay-per-use
Relational Database Service (RDS)	huaweicloud_rds_instance	Yearly/ Monthly and pay- per-use
Cloud Container Engine (CCE)	huaweicloud_cce_cluster	Yearly/ Monthly and pay- per-use
Cloud Search Service (CSS)	huaweicloud_css_cluster	Pay-per-use
GaussDB(for Redis)	huaweicloud_gaussdb_redis_instance	Yearly/ Monthly and pay- per-use
GaussDB(for MySQL)	huaweicloud_gaussdb_mysql_instance	Yearly/ Monthly and pay- per-use
Scalable File Service (SFS)	huaweicloud_sfs_turbo	Pay-per-use
Distributed Cache Service (DCS)	huaweicloud_dcs_instance	Yearly/ Monthly and pay- per-use


Cloud Service	Resource Type	Billing Mode
Distributed Message Service (DMS) for Kafka	huaweicloud_dms_kafka_instance	Pay-per-use

CAUTION

Price estimation will fail if mandatory fields are not specified or a field is invalid in the template used for price estimation.

After the price inquiry completes, the estimated price is displayed in the basic information on the execution plan details page, as shown in [Figure 1-31](#).

Figure 1-31 Execution plan details




1.8 Deleting a Stack

1. When **Deletion Protection** is disabled:

On the stack list page, find the created stack and click **Delete** in the **Operation** column. In the displayed dialog box, enter **Delete** in the text box and click **OK**.

Alternatively, go to the stack details page and click **Delete** in the upper right corner, as shown in [Figure 1-32](#).


Figure 1-32 Dialog box for deleting a stack



2. When **Deletion Protection** is enabled:


Figure 1-33 shows that the **Enabled** status of **Deletion Protection**.

Figure 1-33 Deletion protection



If you delete a resource stack with deletion protection enabled, an error message will be displayed, as shown in **Figure 1-34**.

Figure 1-34 Deletion failed




1.9 Viewing Stack Details

1. Viewing Stack Details

There are six function modules on the stack details page (The stack named **stack_20221206_0933_uiyn** is an example here.):


- a. **Basic Information:** displays basic information about the stack, as shown in **Figure 1**.

Figure 1-35 Basic information




- b. **Resources:** displays information about cloud services or resources generated during plan execution and stack deployment, as shown in [Figure 1-36](#).

Figure 1-36 Resources




- c. **Events:** displays log information generated during plan execution and stack deployment. Events are updated in real time based on the stack status. For example, [Figure 1-37](#) shows that three resources are created.

Figure 1-37 Events




- d. **Outputs:** displays output parameters in the template, as shown in [Figure 1-38](#):

Figure 1-38 Outputs




- e. **Template:** displays the template content used for creating a stack, as shown in [Figure 1-39](#).

Figure 1-39 Template




- f. **Execution Plans:** displays different execution plans. After an execution plan is generated, you need to click **Deploy** to create resources in the template. After an execution plan is applied, its status changes from **Available** to **Applied** and the **Deploy** button disappears, as shown in **Execution plans**.

Figure 1-40 Execution plans



Click the execution plan name. The execution plan details page is displayed, as shown in **Figure 1-41**.

Figure 1-41 Execution plan details



2 Visual Designer

[2.1 Introduction](#)

[2.2 Visual Designer UI](#)

[2.3 Cloud Services or Elements](#)

[2.4 Shortcut Keys of Visual Designer](#)

[2.5 Compiling a Template to Create an EVS Disk](#)

2.1 Introduction

The RFS Visual Designer is a graphic tool for creating, viewing, and modifying templates. Using the designer, you can drag elements to the canvas, directly connect them, and then edit their details in a visual form.

The designer can help you quickly understand the relationships between elements in templates and modify templates easily.

The designer has the following advantages:

- **Visualizing template resources**
The Visual Designer visualizes template resources to offer you a better insight. The Visual Designer defines resources in the template metadata, such as resource size. When you open a template, the designer automatically adds the metadata and the layout is saved. Therefore, when you re-open the template, the last-saved template is displayed.
- **Simplifying template compiling**
When you compile template resources in a JSON or TF file, the process is complex and error-prone. In the designer, you can add resources to the template by dragging resources to the canvas and drawing lines between resources to create a relationship.
- **Simplifying editing with the Visual Designer**
The designer allows you to modify templates. Text designer is not required. The designer also supports autocomplete and lists all property names for a resource.

2.2 Visual Designer UI

The RFS Visual Designer UI includes six parts: control pane, resource bar, log area, design console, template pane, and attribute pane. For details about each part, see .




Table 2-1 Visual Designer UI description

No. (in the Above Figure)	Description
1	Control pane, which displays the control operation shortcuts of the design console.
2	Resource pane, which displays available resources for orchestration. Resources are categorized by service. You can drag resources and orchestrate them on the canvas and use lines to connect them and define their relationships.
3	Design console, which is the canvas for you to design templates and connect resources.
4	Attribute panel, which displays the attribute name and type of the selected resource.
5	Template area, which allows you to modify templates and define attributes.
6	Log area, which displays error information and messages triggered during your operation. For example, non-compliant parameters are displayed during syntax verification.

2.3 Cloud Services or Elements


A cloud service is an element and a basic unit to be orchestrated in Visual Designer. Each element contains all attributes of the resource type it belongs to.

Resources are classified on the left of the designer UI and can be dragged to the canvas on the right.

Copying or Deleting a Cloud Service

Drag a cloud service to the canvas. Right-click the cloud service.

Figure 2-1 Right-clicking the cloud service




Two icons are displayed. Click **Clone** to copy the cloud service. Click **Delete** to delete the cloud service.

Cloud Service Block Diagrams

There are two types of cloud service resource block diagrams in Visual Designer:

- Type 1: Non-scalable elements
A non-scalable element generally represents a terminal service or an entity resource. The block diagram size is fixed.

Figure 2-2 Non-scalable elements



- Type 2: Scalable elements
A scalable element is a container element. The containers and elements can be put into containers. You can adjust the size of the block diagram by dragging.

Figure 2-3 Scalable elements




Connecting Resources Using Hollow Points/Lines

When some elements are dragged to the canvas, a hollow point is displayed on the resource. There are **green hollow points** and **gray hollow points**.

Hollow points can be used to connect resources. The connection line between two resources represents their association or dependency. There are green lines and gray lines.


- Green hollow points
A resource displayed with a green hollow point can depend on other resources.
You can connect resources as required and the resources to be depended on are created by RFS first.
For example, when you drag an RDS resource to the canvas, a green hollow point is displayed as shown in the following figure.

Figure 2-4 RDS green hollow point




When you move the cursor to the green hollow point of the left resource and click the green hollow point, an arrow is displayed. Drag the cursor to the resource on the right and release the cursor. The left resource depends on the right resource.

Figure 2-5 Green hollow point: an element to be connected




- **Gray hollow point**
A resource with a gray hollow point can be associated with other resources. For example, when you drag a CCE resource to the canvas, a gray hollow point is displayed as shown in the following figure.

Figure 2-6 CCE gray hollow point




When you move the cursor to the gray hollow point, you can view an attribute value as shown in the following figure, which indicates that the CCE resource can only be connected to the EIP resource.

Figure 2-7 CCE attribute




Assume that the CCE resource needs to be connected to a VPC resource. Drag the VPC element to the canvas first.

Figure 2-8 EIP




Move the cursor to the gray hollow point of the CCE resource and click the gray hollow point. An arrow is displayed. Drag the mouse to move the arrow to the EIP resource. When the hollow point of EIP resource turns green, release the mouse. The two resources are associated.

Figure 2-9 Hollow point: an element to be connected



- **Green hollow points and connection lines**
The line from a resource with a green hollow point to another resource represents the dependencies between two resources. For more information, see [Green hollow points](#).


Figure 2-10 Green hollow points and connection lines



- **Gray hollow points and connection lines**
The line from a resource with a hollow gray point to another resource indicates that the two resources are associated using an attribute value. In addition, a dependency relationship exists between the two resources. For more information, see [Green hollow points](#).

A resource with a gray hollow point can be associated with other resources. For example, when you drag a CCE resource to the canvas, a gray hollow point is displayed as shown in the following figure. When you move the cursor to the gray hollow point, you can view an attribute value as shown in the following figure, which indicates that the CCE resource can only be connected to the EIP resource. Assume that the CCE resource needs to be connected to a EIP resource. Drag the EIP element to the canvas first. Move the cursor to the gray hollow point of the CCE resource and click the gray hollow point. An arrow is displayed. Drag the mouse to move the arrow to the EIP resource. When the hollow point of EIP resource turns green, release the mouse. The two resources are associated. Hollow point: an element to be connected

Figure 2-11 Gray hollow points and connection lines




2.4 Shortcut Keys of Visual Designer

Operation	Windows OS	macOS
Copy	Ctrl-C	Command-C
Paste	Ctrl-V	Command-V
Cut	Ctrl-X	Command-X
All	Ctrl-A	Command-A
Find	Ctrl-F	Command-F
Go to the beginning of the text	Ctrl-Home	Command-Home Command-Up
Go to the previous line	Up	Up Ctrl-P
Go to the end of the text	Ctrl-End	Command-End Command-Down
Go to the next line	Down	Down Ctrl-N
Go to the end of the current page	PageDown	PageDown Ctrl-V
Copy the current element	Ctrl-D	Command-D
Undo	Ctrl-Z	Command-Z
Delete	Delete	Delete Ctrl-D Shift-Delete
Zoom in	Ctrl-=	Command-=
Zoom out	Ctrl--	Command--

2.5 Compiling a Template to Create an EVS Disk

This section describes how to **compile a template on the Visual Designer** to create an EVS disk. At the end of this walkthrough, you will see the newly created EVS disk on the Cloud Server Console, as shown in [Figure 2-12](#).

Figure 2-12 Created EVS disk



1. **Step 1: Use the Visual Designer to Compile a Template:** Use the Visual Designer to add elements and configure parameters for each element.


2. **Step 2: Create an EVS Disk:** Use the Visual Designer to create an ECS, a VPC, and a subnet.
3. **Step 3: Delete Unnecessary Resources:** Delete unnecessary stacks to avoid unwanted charges.

Step 1: Use the Visual Designer to Compile a Template

Step 1 Log in to the RFS console. In the navigation pane on the left, click **Visual Designer**.

Step 2 Add and connect elements. Drag elements, such as VPC, VPC subnet, and EVS, to the canvas, and establish relationships between them, as shown in [Figure 2-13](#).


Figure 2-13 Adding an element



Step 3 Configure the template parameters. Set the attributes in the **Attribute Editing Panel** on the right.

1. Click the **vpc** element in the canvas. The attributes of the element will be automatically displayed in the attribute pane. The CIDR can use the default value **192.168.0.0/16**.
2. Click the **subnet** element in the canvas. The attributes of the element will be automatically displayed in the attribute pane. You can set the default value for the attributes.
3. Click the **evs** element in the canvas. The attributes of the element will be automatically displayed in the attribute pane. The attributes with red text boxes are mandatory, as shown in [Figure 2-14](#).

Figure 2-14 Mandatory attributes




NOTE

To facilitate parameter setting and modification, you are advised to set parameters whose value needs to be frequently changed as input parameters. **get_input** indicates input parameters. You can define the values behind **get_input**.


- Click **+** on the right of the attribute editing panel to generate an input parameter, as shown in **Figure 2-15**.

Figure 2-15 Generating an input parameter



- Click **Save Template** in the upper right corner of the Visual Designer to save the template. If the message "Template saved. You can view and manage it in My Templates." is displayed, the template is saved.

Figure 2-16 Saving a template



----End

Step 2: Create an EVS Disk

- Step 1** Close the Visual Designer and go to the RFS console.
- Step 2** In the navigation pane on the left, click **Templates > My Templates**. The template is displayed in the template list.
- Step 3** Click **Create Stack** in the **Operation** column of the template.

Step 4 Click **Next** to view the stack information. After confirming the information, click **Next**, select an agency, click **Next**, and click **Create Execution Plan**.

The **Execution Plans** tab page is displayed, click **Deploy** in the **Operation** column of the execution plan.

Step 5 When the status of the plan is **Applied**, you can view that three cloud services exist in the **Resources** tab page. A VPC, a subnet, and an EVS disk have been created.

Figure 2-17 Crested stack

Cloud Product Name	Physical Resource NameID	Logical Name	Resource Type	Resource Status
Elastic Cloud Server	tf_stack_ecs1 ec09440f-3f16-47a3-90b5-9d549d56a342	ecs-100a1	huaweicloud_compute_instance	Creation Complete
Virtual Private Cloud	tf_stack_vpc1 36375d27-990f-40e7-9be9-85d8448d974	vpc-gthhr	huaweicloud_vpc	Creation Complete
Virtual Private Cloud	tf_stack_subnet1 c35c3e47-6921-416a-916c-94557f3a0062	vpc-subnet-ug9op	huaweicloud_vpc_subnet	Creation Complete

Step 6 View the created cloud services.

1. Log in to the Huawei Cloud management console.
2. Choose **Cloud Server Console > Elastic Volume Service**. You can see the newly created EVS disk.

Figure 2-18 EVS created

Disk Name	Status	Disk Specific...	Function	Server Name	Disk Sharing...	Device Type	Encrypted	AZ	Billing Mode	Operation
evs-volume-5cc3l 09e383b4-e679-48da-a131-4c9b97b1dcb	Available	Ultra-high I/O 10 GB	Data disk	--	Disabled	VBD	No	AZ3	Pay-per-use Created on...	Attach Expand Capacity Create Backup More

3. Choose **Service List > Networking > Virtual Private Cloud**. You will see the newly created VPC on the VPC list.

Figure 2-19 Created VPC

NameID	IPv4 CIDR Block	Status	Subnets	Route Tables	Owner Project ID	Operation
vpc-ldc0l cc00440b-6755-4f68-a131-4c9b97b1dcb	192.168.0.0/16 (Primary CIDR block)	Available	1	1	47df611e638c4a73806e2731cc79a471	Edit CIDR Block Delete

4. Click the VPC name to show more details about the VPC. On the VPC details page, you will see that the subnet has been created in the VPC.

Figure 2-20 Created subnet

NameID	VPC	IPv4 CIDR Block	IPv6 CIDR ...	Status	AZ	Network ACL	Route Table	Owner Project ID	Operation
subnet-6z9by 07226224-03da-41...	vpc-ldc0l	192.168.0.0/24	-- Enable IPv6	Available	--	--	rtb-vpc-ldc0l Default	47df611e638c4a73806e2731cc79a471	Change Route Table Delete

----End

Step 3: Delete Unnecessary Resources

You are advised to delete unnecessary stacks to avoid unwanted charges.

Step 1 Log in to the RFS console.

Step 2 In the navigation pane on the left, click **Stacks**.

Step 3 Locate the created stack, click **Delete** in the **Operation** column, and delete the stack as prompted.

----**End**

3 Managing a Stack

Stack management consists of two aspects. One is lifecycle management of created stacks, including deleting and changing. The other is viewing stack details to obtain their running statuses.

Modifying a Stack

After a stack is created successfully (that is, in the normal status), you can change the parameters of the stack as needed.

- Step 1** Log in to the RFS console.
- Step 2** In the navigation pane on the left, click **Stacks**.
- Step 3** In the stack list, click the stack to be changed.
- Step 4** On the stack details page, click **Update Template/Parameter**.
- Step 5** Change the template version or input parameters, and click **Next**.
- Step 6** Confirm the configurations and then click **Create Execution Plan**.
- Step 7** On the **Execution Plans** tab page of the stack details page, select the created execution plan and click **Deploy** in the **Operation** column.

On the **Events** tab page, you can view the detailed operation events related to stack changes.

----End

Deleting a Stack

Deleted stacks cannot be restored. Exercise caution when deleting a stack.

- Step 1** Log in to the RFS console.
- Step 2** In the navigation pane on the left, click **Stacks**.
- Step 3** In the stack list, select the stack to be deleted and click **Delete** in the **Operation** column.
- Step 4** In the dialog box displayed, enter **Delete** and click **OK**.

Check the stack name carefully. The deletion cannot be revoked.

On the **Events** tab page, you can view the detailed operation events related to stack deletion.

----End

Viewing Stack Details

After a stack is created, you can view its data and resources on the stack details page.

- Resources
Elements of a stack, such as applications and cloud services
- Outputs
Output parameters and their values in the stack template
- Template
Details of the template used to create the stack
- Events
You can view stack events to monitor the stack operation progress. For example, when you create a stack, all important steps during the stack creation are displayed on the **Events** tab page. The events are sorted in chronological order with the latest event being displayed at the top.

4 Auditing

[4.1 RFS Operations Supported by CTS](#)

[4.2 Viewing RFS Logs in CTS](#)

4.1 RFS Operations Supported by CTS

Cloud Trace Service (CTS) records all operations performed on cloud services, providing data support for customers in fault locating, resource management, and security auditing. When you enable CTS, it begins to record operations performed on RFS resources.

Table 4-1 RFS operations supported by CTS

Operation	Description
createStack	Creating a stack
deployStack	Deploying a stack
deleteStack	Deleting a stack
updateStack	Updating a stack
parseTemplateVariables	Parsing template variables
continueRollback-Stack	Continuing to roll back a stack
continuedeployStack	Continuing to deploy a stack
createExecution-Plan	Creating an execution plan
applyExecutionPlan	Executing an execution plan

Operation	Description
deleteExecution-Plan	Deleting an execution plan
createTemplate	Creating a template
deleteTemplate	Deleting a template
updateTemplate	Updating a template
createTemplateVersion	Creating a template version
deleteTemplateVersion	Deleting a template version
useAgency	Recording user agency
createStackSet	Creating a stack set
deleteStackSet	Deleting a stack set
deployStackSet	Deploying a stack set
updateStackSet	Updating a stack set
createStackInstances	Creating stack instances
deleteStackInstances	Deleting stack instances
updateStackInstances	Updating stack instances

4.2 Viewing RFS Logs in CTS

When you enable CTS, it begins to record operations performed on RFS resources. On the CTS console, you can query operation records from the last 7 days by performing the following operations.

Procedure

- Step 1** Log in to the CTS console.
- Step 2** In the navigation pane, click **Trace List**.
- Step 3** Filter the desired operation events.


The trace list supports four filter types:

- **Trace Source, Resource Type, and Search By**

Select the search criteria from the drop-down lists. For example, select **RFS** from the **Trace Source** drop-down list box.

From the **Search By** drop-down list, select a trace name. From the **Search By** drop-down list, select or enter a specific resource ID. From the **Search By** drop-down list, select or enter a specific resource name.

- **Trace Status:** Select one of **All trace statuses**, **Normal**, **Warning**, and **Incident**.
- **Operator:** Select a specific operator (a user other than an account).
- **Time Range:** You can query traces generated during any time range of the last seven days.

Step 4 Click  on the left of a trace to expand its details.

Step 5 Click **View Trace** in the **Operation** column. A dialog box is displayed to show trace structure details.

```
{
  "trace_id": "4073d5e1-6ee6-11ed-bb00-61c31199dcbc",
  "code": "200",
  "trace_name": "parseTemplateVariables",
  "resource_type": "template",
  "trace_rating": "normal",
  "source_ip": "10.172.131.218",
  "trace_type": "ApiCall",
  "service_type": "RFS",
  "event_type": "system",
  "project_id": "47cf611e636c4a73806e2731cc7fa471",
  "response": "{\n  \"variables\": {\n    \"default\": \"jiaoyue_test_ecs\",\n    \"description\": \"Your ECS name\",\n    \"name\": \"ecs_name\",\n    \"type\": \"string\"\n  }\n}",
  "resource_id": "",
  "tracker_name": "system",
  "time": "2022/11/28 14:31:12 GMT+08:00",
  "resource_name": "",
  "user": {
    "domain": {
      "name": "iaas_aos_n30000772_01",
      "id": "fcc06b017704dfcb36dcf1b2a29d151"
    },
    "name": "cto_c30031067_dev",
    "id": "155ad09309994f92a5147529aa0ceb2f"
  },
  "record_time": "2022/11/28 14:31:12 GMT+08:00"
}
```

----End

5 IAM Agency

By creating an agency, you can share your resources with another account, or delegate an individual or team to manage your resources. You do not need to share your security credentials (the password and access keys) with the delegated party. Instead, the delegated party can log in with its own account credentials and then switches the role to your account and manage your resources.


With RFS, you can create a stack to bind an agency with a provider and update the binding relationship by updating the stack.

RFS uses an agency only in resource operation requests, such as creating a stack (triggering deployment), creating an execution plan, deploying a stack, and deleting a stack. The agency applies only to resource operations performed by the bound provider. If the permissions provided by the agency are insufficient, resource operations may fail.

Procedure

1. Log in to the IAM console.
2. On the IAM console, choose **Agencies** from the navigation pane on the left, and click **Create Agency** in the upper right corner.

Figure 5-1 Creating an agency



3. Enter an agency name.
Set **Cloud Service** to **RFS**.

Figure 5-2 Creating an agency

Agencies / Create Agency

* Agency Name

* Agency Type Account
Delegate another HUAWEI CLOUD account to perform operations on your resources.
 Cloud service
Delegate a cloud service to access your resources in other cloud services.

* Cloud Service

* Validity Period

Description
0/255

CAUTION

The agency name is user-defined.

If `op_svc_iac` has been used for registration, you are advised to change it to **RFS**.

4. Click **Next**. The **Authorize Agency** page is displayed. You can grant permissions to the agency on this page.

Figure 5-3 Agency authorization

Agencies / `op_svc_iac`

Basic Information **Permissions**


Administration records (IAM projects): 1 (enterprise projects): 0

Search by policy name:

Policy Name	Policy Description	Project (Report)	Principal	Principal Description	Principal Type	Operation
<input checked="" type="checkbox"/> <code>op_svc_iac</code>	Task administration (Exclude IAM)	All resources (Existing and future projects)	<code>op_svc_iac</code>		agency	Deny

5. Filter specific permissions and grant them to the agency.


Figure 5-4 Selecting policies



You can determine the permissions to be granted to an agency. Huawei Cloud best practices do not advise you to automatically create agencies with the Tenant Administrator permission for users. The best practice is to grant management permissions (including read and write operations) to resources that may be used in a stack.

- Set the authorization scope. You can select **All resources** or **Region-specific projects**.

Figure 5-5 Authorization scope



- Click **OK**. The agency is created.

Figure 5-6

