

GaussDB(for MySQL)

API Reference

Issue 19

Date 2024-02-20



HUAWEI TECHNOLOGIES CO., LTD.



Copyright © Huawei Technologies Co., Ltd. 2024. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Security Declaration

Product Lifecycle

Huawei's regulations on product lifecycle are subject to the *Product End of Life Policy*. For details about this policy, visit the following web page:

<https://support.huawei.com/ecolumnsweb/en/warranty-policy>

Vulnerability

Huawei's regulations on product vulnerability management are subject to the *Vul. Response Process*. For details about this process, visit the following web page:

<https://www.huawei.com/en/psirt/vul-response-process>

For vulnerability information, enterprise customers can visit the following web page:

<https://securitybulletin.huawei.com/enterprise/en/security-advisory>

Preconfigured Digital Certificate

The digital certificates preconfigured on Huawei devices are subject to the *Rights and Responsibilities of Preconfigured Digital Certificates on Huawei Devices*. For details about this document, visit the following web page:

<https://support.huawei.com/enterprise/en/bulletins-service/ENEWS2000015789>

Huawei Enterprise End User License Agreement

This agreement is the end user license agreement between you (an individual, company, or any other entity) and Huawei for the use of the Huawei Software. Your use of the Huawei Software will be deemed as your acceptance of the terms mentioned in this agreement. For details about this agreement, visit the following web page:

<https://e.huawei.com/en/about/eula>

Lifecycle of Product Documentation

Huawei after-sales user documentation is subject to the *Product Documentation Lifecycle Policy*. For details about this policy, visit the following web page:

<https://support.huawei.com/enterprise/en/bulletins-website/ENEWS2000017761>

Contents

1 Before You Start.....	1
1.1 Overview.....	1
1.2 API Calling.....	1
1.3 Endpoints.....	1
1.4 Constraints.....	1
1.5 Concepts.....	2
2 API Overview.....	4
3 Calling APIs.....	6
3.1 Making an API Request.....	6
3.2 Authentication.....	10
3.3 Response.....	12
4 APIs (Recommended).....	14
4.1 DB Engine Version Queries.....	14
4.1.1 Querying Version Information About a DB Engine.....	14
4.2 Database Specification Queries.....	16
4.2.1 Querying Database Specifications.....	17
4.3 Instance Management.....	20
4.3.1 Creating a DB Instance.....	20
4.3.2 Querying DB instances.....	36
4.3.3 Rebooting a DB Instance.....	45
4.3.4 Deleting or Unsubscribing from a DB Instance.....	47
4.3.5 Querying Details of a DB Instance.....	50
4.3.6 Querying Details of DB Instances in Batches.....	59
4.3.7 Creating a Read Replica.....	68
4.3.8 Deleting or Unsubscribing from a Read Replica.....	72
4.3.9 Scaling up Storage of a Yearly/Monthly DB Instance.....	74
4.3.10 Changing a DB Instance Name.....	77
4.3.11 Resetting a Database Password.....	79
4.3.12 Changing DB Instance Specifications.....	82
4.3.13 Querying Dedicated Resource Pools.....	85
4.3.14 Querying Dedicated Resources.....	88
4.3.15 Configuring the Monitoring By Seconds Function.....	92

4.3.16 Querying the Configuration of Monitoring by Seconds.....	94
4.3.17 Rebooting a Node.....	97
4.3.18 Upgrading the Kernel Version of a DB Instance.....	99
4.3.19 Enabling or Disabling SSL.....	102
4.3.20 Binding an EIP.....	104
4.3.21 Unbinding an EIP.....	107
4.3.22 Promoting a Read Replica to Primary.....	109
4.3.23 Changing a Maintenance Window.....	111
4.3.24 Modifying a Security Group.....	113
4.3.25 Changing a Private IP Address.....	116
4.3.26 Changing a Database Port.....	118
4.3.27 Changing a DB Instance Description.....	120
4.3.28 Applying for a Private Domain Name.....	123
4.3.29 Changing a Private Domain Name.....	125
4.3.30 Querying the Kernel Version.....	128
4.3.31 Modifying Auto Scaling Policies.....	131
4.3.32 Querying Auto Scaling Policies.....	136
4.3.33 Pre-Checking Resources.....	140
4.4 Backup Management.....	145
4.4.1 Configuring a Same-Region Backup Policy.....	145
4.4.2 Creating a Manual Backup.....	149
4.4.3 Querying Full Backups.....	153
4.4.4 Querying an Automated Backup Policy.....	158
4.4.5 Deleting a Manual Backup.....	161
4.4.6 Restoring Data to the Original Instance or an Existing Instance.....	163
4.4.7 Querying the Restoration Time Range.....	167
4.4.8 Enabling or Disabling Encrypted Backup.....	169
4.4.9 Checking Whether Encrypted Backup Is Enabled.....	173
4.4.10 Querying Incremental Backups.....	175
4.4.11 Configuring a Cross-Region Backup Policy.....	179
4.4.12 Restoring Tables to a Specified Point in Time.....	182
4.4.13 Querying Tables for Table-level Point-in-Time Recovery.....	185
4.5 Parameter Template Management.....	188
4.5.1 Querying Parameter Templates.....	189
4.5.2 Creating a Parameter Template.....	192
4.5.3 Deleting a Parameter Template.....	197
4.5.4 Obtaining Details About a Parameter Template.....	199
4.5.5 Modifying Parameters in a Parameter Template.....	203
4.5.6 Applying a Parameter Template.....	206
4.5.7 Replicating a Parameter Template.....	209
4.5.8 Comparing Parameter Templates.....	212
4.5.9 Querying Instances That a Parameter Template Can Be Applied To.....	215

4.5.10 Viewing Parameter Change History.....	218
4.5.11 Obtaining Parameter Information of a Specified DB Instance.....	222
4.5.12 Modifying Parameters of a Specified DB Instance.....	227
4.5.13 Replicating the Parameter Template of a DB Instance.....	229
4.6 Quota Management.....	233
4.6.1 Querying the Instance Quotas of a Tenant.....	233
4.6.2 Querying the Resource Quotas of a Specified Enterprise Project.....	236
4.6.3 Configuring Resource Quotas for a Specified Enterprise Project.....	239
4.6.4 Modifying the Resource Quotas of a Specified Enterprise Project.....	242
4.6.5 Querying Enterprise Projects.....	246
4.7 Database Proxy.....	249
4.7.1 Creating a Proxy Instance.....	249
4.7.2 Deleting a Proxy Instance.....	254
4.7.3 Querying Proxy Instances.....	256
4.7.4 Querying Proxy Instance Specifications.....	264
4.7.5 Adding Proxy Nodes.....	267
4.7.6 Deleting Proxy Nodes.....	270
4.7.7 Changing Specifications of a Proxy Instance.....	273
4.7.8 Assigning Read Weights.....	275
4.7.9 Changing the Routing Policy of a Proxy Instance.....	278
4.7.10 Enabling or Disabling Transaction Splitting of a Proxy Instance.....	283
4.7.11 Enabling or Disabling Association of New Nodes with Proxy Instances.....	285
4.7.12 Changing Session Consistency of a Proxy Instance.....	288
4.7.13 Changing the Connection Pool Type of a Proxy Instance.....	291
4.7.14 Changing the Port of a Proxy Instance.....	294
4.7.15 Modifying Parameters of a Proxy Instance.....	296
4.7.16 Enabling or Disabling Access Control.....	299
4.7.17 Configuring Access Control Rules.....	302
4.7.18 Enabling or Disabling SSL for a Proxy Instance.....	305
4.8 Log Management.....	308
4.8.1 Enabling or Disabling SQL Explorer.....	308
4.8.2 Querying Whether SQL Explorer Is Enabled.....	310
4.8.3 Querying Slow Query Logs.....	313
4.8.4 Querying Error Logs.....	317
4.8.5 Obtaining the Temporary Link for Downloading Full SQL.....	321
4.9 Tag Management.....	325
4.9.1 Querying Resource Tags.....	325
4.9.2 Querying Project Tags.....	328
4.9.3 Adding or Deleting Tags in Batches.....	331
4.10 Database User Management.....	334
4.10.1 Creating a Database Account.....	334
4.10.2 Querying Database Users.....	338

4.10.3 Deleting a Database User.....	342
4.10.4 Modifying Remarks of a Database User.....	345
4.10.5 Changing Password of a Database User.....	348
4.10.6 Granting Permissions to a Database User.....	351
4.10.7 Deleting Permissions of a Database User.....	354
4.11 Database Management.....	356
4.11.1 Querying Available Database Character Sets.....	356
4.11.2 Creating a Database.....	359
4.11.3 Modifying Database Remarks.....	362
4.11.4 Querying Databases.....	365
4.11.5 Deleting a Database.....	368
4.12 SQL Statement Concurrency Control.....	371
4.12.1 Enabling or Disabling SQL Statement Concurrency Control.....	371
4.12.2 Querying Whether SQL Statement Concurrency Control Is Enabled.....	374
4.12.3 Configuring Concurrency Control Rules of SQL Statements.....	376
4.12.4 Querying Concurrency Control Rules of SQL Statements.....	380
4.12.5 Deleting Concurrency Control Rules of SQL Statements.....	384
4.13 Task Center.....	387
4.13.1 Obtaining Information About a Task with a Specified ID.....	387
4.13.2 Obtaining Instant Tasks.....	391
4.13.3 Obtaining Scheduled Tasks.....	398
4.13.4 Canceling a Scheduled Task.....	405
4.13.5 Deleting a Task Record.....	407
4.13.6 Deleting a Scheduled Task Record.....	409
4.14 Intelligent Diagnosis.....	412
4.14.1 Querying Abnormal Instances by Each Metric.....	412
4.14.2 Querying Abnormal Instance Information by a Specific Metric.....	415
5 APIs (Unavailable Soon).....	419
5.1 DB Engine Version Queries.....	419
5.1.1 Querying Version Information About a DB Engine.....	419
5.2 Database Specification Queries.....	421
5.2.1 Querying Database Specifications.....	421
5.3 Instance Management.....	423
5.3.1 Creating a DB Instance.....	424
5.3.2 Querying DB Instances.....	435
5.3.3 Querying DB Instances.....	440
5.3.4 Deleting a DB Instance.....	448
5.3.5 Querying Details of a DB Instance.....	450
5.3.6 Querying Details of DB Instances in Batches.....	459
5.3.7 Querying Details of a DB Instance.....	469
5.3.8 Creating a Read Replica.....	476
5.3.9 Deleting a Read Replica.....	478

5.3.10 Scaling up Storage of a Yearly/Monthly DB Instance.....	480
5.3.11 Changing a DB Instance Name.....	482
5.3.12 Resetting a Database Password.....	484
5.3.13 Modifying DB Instance Specifications.....	486
5.4 Backup Management.....	488
5.4.1 Modifying the Automated Backup Policy.....	488
5.4.2 Creating a Manual Backup.....	491
5.4.3 Querying Backups.....	494
5.4.4 Querying an Automated Backup Policy.....	497
5.5 Parameter Template Management.....	499
5.5.1 Querying Parameter Templates.....	500
5.6 Quota Management.....	502
5.6.1 Querying the Instance Quotas of a Tenant.....	502
5.6.2 Querying Resource Quotas.....	505
5.6.3 Configuring Resource Quotas.....	507
5.6.4 Modifying Resource Quotas.....	509
5.7 Database Proxy.....	512
5.7.1 Creating Proxy Instance.....	512
5.7.2 Deleting a Proxy Instance.....	514
5.7.3 Querying Information About a Proxy Instance.....	515
5.7.4 Querying Proxy Instance Information.....	520
5.7.5 Querying Proxy Instance Specifications.....	524
5.7.6 Adding Proxy Nodes.....	527
5.8 Log Management.....	529
5.8.1 Querying Database Error Logs.....	529
5.8.2 Querying Database Error Logs.....	532
5.8.3 Querying Database Slow Logs.....	536
5.8.4 Querying Database Slow Logs.....	539
5.9 Task Information Queries.....	543
5.9.1 Obtaining Information About a Task.....	543
6 Permissions Policies and Supported Actions.....	548
6.1 Permissions Policies and Supported Actions.....	548
6.2 GaussDB(for MySQL) Actions.....	549
A Appendix.....	553
A.1 Abnormal Request Results.....	553
A.2 Status Codes.....	553
A.3 Error Codes.....	557
A.4 Obtaining a Project ID.....	591
A.5 GaussDB(for MySQL) Monitoring Metrics.....	592
B Change History.....	603

1

Before You Start

1.1 Overview

GaussDB(for MySQL) is a MySQL-compatible, enterprise-grade database service. Data functions virtualization (DFV) is used to decouple storage from compute and can auto scale up to 128 TB per DB instance. There is zero data loss. It provides the superior performance of a commercial database at the price of an open-source database.

NOTE

Data Function Virtualization (DFV) is a high-performance and high-reliability distributed storage system that is vertically integrated with databases. Storage clusters are deployed in pools to improve storage utilization.

This document describes how to use application programming interfaces (APIs) to perform operations on DB instances. For details about all supported operations, see [API Overview](#).

1.2 API Calling

GaussDB(for MySQL) supports Representational State Transfer (REST) APIs, allowing you to call APIs using HTTPS. For details about API calling, see [Calling APIs](#).

1.3 Endpoints

An endpoint is the **request address** for calling an API. Endpoints vary depending on services and regions. For the endpoints of all services, see [Regions and Endpoints](#).


1.4 Constraints

- For more constraints, see API description.

1.5 Concepts

- Account
An account is created upon successful registration. An account has full access permissions for all of its cloud services and resources. It can be used to reset user passwords and grant user permissions. The account is a payment entity and should not be used directly to perform routine management. For security purposes, create users and grant them permissions for routine management.
- IAM User
An IAM user is created by an account to use cloud services. Each IAM user has its own identity credentials (password and access keys).
API authentication requires information such as the account, username, and password.
- Region
A region is a geographic area in which cloud resources are deployed. Availability zones (AZs) in the same region can communicate with each other over an intranet, while AZs in different regions are isolated from each other. Deploying cloud resources in different regions can better suit certain user requirements or comply with local laws or regulations.
- AZ
An AZ contains one or more physical data centers. Each AZ has independent cooling, fire extinguishing, moisture-proof, and electricity facilities. Within an AZ, computing, network, storage, and other resources are logically divided into multiple clusters. AZs within a region are interconnected using high-speed optical fibers to support cross-AZ high-availability systems.
- Project
Projects group and isolate compute, storage, and network resources across physical regions. A default project is provided for each region, and subprojects can be created under each default project. Users can be granted permissions to access all resources in a specific project. For more refined access control, create subprojects under a project and purchase resources in the subprojects. Users can then be assigned permissions to access only specific resources in the subprojects.

Figure 1-1 Project isolating model



- Enterprise Project
Enterprise projects group and manage resources across regions. Resources in enterprise projects are logically isolated from each other. An enterprise project

can contain resources in multiple regions, and resources can be directly transferred between enterprise projects.

For more information about enterprise projects and how to obtain enterprise project IDs, see [*Enterprise Management User Guide*](#).

2 API Overview

With GaussDB(for MySQL) APIs, you can query, set, and modify resource quotas.

Type	Description
DB engine version query	Query the DB version information of a specified DB engine.
DB specifications query	Query the DB specifications of a specified DB engine version.
DB instance management	Create instances, query instance lists, query instance details, delete instances, create read replicas, delete read replicas, scale storage space of yearly/monthly instances, change instance names, reset database passwords, and change instance specifications.
Backup management	Create manual backups, query backup lists, query automated backup policies, and modify automated backup policies.
Parameter template management	Query parameter templates.
Quota management	Query, set, and modify resource quotas.
Database proxy	Query database proxy information and specifications, and enable or disable database proxy.
Log management	Obtain log information, including database error logs and slow logs.
Tag management	Manage tags, including adding tags in batches, deleting tags in batches, and querying project tags.
Database user management	Create a database user, query database users, delete a database user, authorize permissions to a database user, and delete permissions of a database user.

Type	Description
Database management	Create a database, query the databases, delete a database, and modify database remarks.
SQL statement concurrency control	Query, configure and delete concurrency control rules of SQL statements.
Task information query	Obtain task information about the task center.

3 Calling APIs

3.1 Making an API Request

This section describes the structure of a REST API, and uses the IAM API for [obtaining a user token](#) as an example to describe how to call an API. The obtained token is used to authenticate the calling of other APIs.

Request URI

A request URI consists of the following:

{URI-scheme}://{Endpoint}/{resource-path}?{query-string}

Although a request URI is included in a request header, most programming languages or frameworks require the request URI to be separately transmitted, rather than being conveyed in a request message.

Table 3-1 Parameters in a URI


Parameter	Description
URI-scheme	Protocol used to transmit requests. All APIs use HTTPS.
Endpoint	Domain name or IP address of the server bearing the REST service. The endpoint varies between services in different regions. It can be obtained from Regions and Endpoints . For example, the endpoint of IAM in the CN North-Beijing1 region is iam.cn-north-1.myhuaweicloud.com .
resource-path	Access path of an API for performing a specified operation. Obtain the path from the URI of an API. For example, the resource-path of the API used to obtain a user token is /v3/auth/tokens .

Parameter	Description
query-string	Query parameter, which is optional. Ensure that a question mark (?) is included before each query parameter that is in the format of "Parameter name=Parameter value". For example, ? limit=10 indicates that a maximum of 10 data records will be displayed.

For example, to obtain an IAM token in the **CN North-Beijing1** region, obtain the endpoint (**iam.cn-north-1.myhuaweicloud.com**) for this region and the resource-path (**/v3/auth/tokens**) in the URI of the API used to [obtain a user token](#). Then, construct the URI as follows:

```
https://iam.cn-north-1.myhuaweicloud.com/v3/auth/tokens
```

Figure 3-1 Example URI



NOTE

To simplify the URI display in this document, each API is provided only with a resource-path and a request method. The **URI-scheme** of all APIs is **HTTPS**, and the endpoints of all APIs in the same region are identical.

Request Methods

The HTTP protocol defines the following request methods that can be used to send a request to the server:

Table 3-2 HTTP methods

Method	Description
GET	Requests the server to return specified resources.
PUT	Requests the server to update specified resources.
POST	Requests the server to add resources or perform special operations.

For example, in the case of the API used to [obtain a user token](#), the request method is POST. The request is as follows:

```
POST https://iam.cn-north-1.myhuaweicloud.com/v3/auth/tokens
```

Request Header

You can also add additional fields to a request, such as the fields required by a specified URI or an HTTP method. For example, to request for the authentication information, add **Content-Type**, which specifies the request body type.

Table 3-3 lists common request header fields.

Table 3-3 Common request headers

Name	Description	Mandatory	Example
Content-Type	Specifies the MIME type of the request body. You are advised to use the default value application/json . For APIs used to upload objects or images, the value can vary depending on the flow type.	Yes	application/json
Host	Specifies the requested server information, which can be obtained from the URL of the service API. The value is in the <i>hostname[:port]</i> format. If the port number is not specified, the default port is used. The default port number for https is 443 .	No This parameter is mandatory for AK/SK authentication.	code.test.com or code.test.com:443
Content-Length	Specifies the length of the request body. The unit is byte.	No	3495
X-Project-Id	Specifies the project ID. Obtain the project ID by following the instructions in Obtaining a Project ID .	No	e9993fc787d94b6c886cb aa340f9c0f4

Name	Description	Mandatory	Example
X-Auth-Token	<p>Specifies the user token.</p> <p>The user token is a response to the API used to obtain a user token. This API is the only one that does not require authentication.</p> <p>After the request is processed, the value of X-Subject-Token in the message header is the token value.</p>	No This parameter is mandatory for token authentication.	The following is part of an example token: MIIPAgYJKoZIhvcNAQc-Co...ggg1BBIINPXsidG9rZ
X-Language	<p>Request language type. The default value is en-us.</p> <p>Value:</p> <ul style="list-style-type: none"> • en-us • zh-cn 	No	en-us

The API used to [obtain a user token](#) does not require authentication. Therefore, only the **Content-Type** field needs to be added to requests for calling the API. An example of such requests is as follows:

```
POST https://iam.cn-north-1.myhuaweicloud.com/v3/auth/tokens
Content-Type: application/json
```

(Optional) Request Body

This part is optional. The body of a request is often sent in a structured format (for example, JSON or XML) as specified in the **Content-Type** header field. If the request body contains full-width characters, these characters must be coded in UTF-8.

The request body varies between APIs. Some APIs do not require the request body, such as the APIs requested using the GET and DELETE methods.

In the case of the API used to [obtain a user token](#), the request parameters and parameter description can be obtained from the API request. The following provides an example request with a body included. Replace **username**, **domainname**, ********* (login password), and **xxxxxxxxxxxxxxxxxxxx** (project name, such as cn-north-1) with actual values. It can be obtained from [Regions and Endpoints](#).

 NOTE

The **scope** parameter specifies where a token takes effect. You can set **scope** to an account or a project under an account. In the following example, the token takes effect only for the resources in a specified project. For more information about this API, see [Obtaining a User Token](#).

```
POST https://iam.cn-north-1.myhuaweicloud.com/v3/auth/tokens  
Content-Type: application/json
```

```
{  
    "auth": {  
        "identity": {  
            "methods": [  
                "password"  
            ],  
            "password": {  
                "user": {  
                    "name": "username",  
                    "password": "*****",  
                    "domain": {  
                        "name": "domainname"  
                    }  
                }  
            }  
        },  
        "scope": {  
            "project": {  
                "name": "xxxxxxxxxxxxxxxx"  
            }  
        }  
    }  
}
```

If all data required for the API request is available, you can send the request to call the API through [curl](#), [Postman](#), or coding. In the response to the API used to obtain a user token, **x-subject-token** is the desired user token. This token can then be used to authenticate the calling of other APIs.

3.2 Authentication

Requests for calling an API can be authenticated using either of the following methods:

- **Token-based authentication:** Requests are authenticated using a token.
- **AK/SK-based authentication:** Requests are authenticated by encrypting the request body using an AK/SK pair. Authentication using AK/SK is recommended because it is more secure than authentication using tokens.

Token-based Authentication

 NOTE

The validity period of a token is 24 hours. When using a token for authentication, cache it to prevent frequently calling the IAM API used to obtain a user token.

A token specifies temporary permissions in a computer system. During API authentication using a token, the token is added to requests to get permissions for calling the API.

When [calling an API to obtain a user token](#), you must set **auth.scope** in the request body to **project**.

```
{  
    "auth": {  
        "identity": {  
            "methods": [  
                "password"  
            ],  
            "password": {  
                "user": {  
                    "name": "username",  
                    "password": "*****",  
                    "domain": {  
                        "name": "domainname"  
                    }  
                }  
            }  
        }  
    },  
    "scope": {  
        "project": {  
            "name": "xxxxxxx"  
        }  
    }  
}
```

In [Making an API Request](#), the process of calling the API used to [obtain a user token](#) is described.

After a token is obtained, add the **X-Auth-Token** header field must be added to requests to specify the token when calling other APIs. For example, if the token is **ABCDEFJ....**, **X-Auth-Token: ABCDEFJ....** can be added to a request as follows:

```
Content-Type: application/json  
X-Auth-Token: ABCDEFJ....
```

AK/SK-based Authentication

NOTE

AK/SK-based authentication supports API requests with a body not larger than 12 MB. For API requests with a larger body, token-based authentication is recommended.

In AK/SK-based authentication, AK/SK is used to sign requests and the signature is then added to the requests for authentication.

- AK: access key ID, which is a unique identifier associated with a secret access key and is used in conjunction with a secret access key to sign requests cryptographically.
- SK: secret access key used in conjunction with an AK to sign requests cryptographically. It identifies a request sender and prevents the request from being modified.

In AK/SK-based authentication, you can use an AK/SK to sign requests based on the signature algorithm or use the signing SDK to sign requests. For details about how to sign requests or use the signing SDK, see [API Request Signing Guide](#).

NOTICE

The signing SDK is only used for signing requests and is different from the SDKs provided by services.

3.3 Response

Status Code

After sending a request, you will receive a response, including the status code, response header, and response body.

A status code is a group of digits ranging from 1xx to 5xx. It indicates the status of a response. For more information, see [Status Codes](#).

For example, if status code **201** is returned for calling the API used to [obtain a user token](#), the request is successful.

Response Header

Similar to a request, a response also has a header, for example, **Content-Type**.

Figure 3-2 shows the response header for the API used to [obtain a user token](#). The **x-subject-token** header field is the desired user token. This token can then be used to authenticate the calling of other APIs.

Figure 3-2 Header fields of the response to the request for obtaining a user token

```
connection → keep-alive
content-type → application/json
date → Tue, 12 Feb 2019 06:52:13 GMT
server → Web Server
strict-transport-security → max-age=31536000; includeSubdomains;
transfer-encoding → chunked
via → proxy A
x-content-type-options → nosniff
x-download-options → noopener
x-frame-options → SAMEORIGIN
x-iam-trace-id → 218d45ab-d674-4995-af3a-2d0255ba41b5
x-subject-token
→ MIIYXQVJKoZhvcNAQcCollYTjCCGEoCAQEExDTALBgIghkgBZQMEAgEwgharBqkqhkiG9w0BBwGgg hacBIIWmHsidG9rZW4iOnsiZXhwaxJlc19hdCI6ljlwMTktMDItMTNUMDfj3Kjs6YgKnpVNRbW2eZ5eb78SZOkqjACgkIqO1wi4JIGzrp d18LGXK5bxldfq4lqHCYb8P4NaY0NYejcAgzJveFIYtLWT1GSO0zxKZmlQHQj82H8qHdgIZO9fuEbL5dMhdavj+33wElxHRC9187b+k9-j+CMZSEB7bUJgd5Uj6eRASX1jipPEGA270g1Fruc0LbjqglFkNPQuFSOLU8+uSsttVwRtNfsC+qTp22Rkd5MCqFGQ8LcuUxC3a+9CMBnOintWW7oeRUvHvpxk8pxiX1wTEboXRzT6MUbpvGw-oPNFYxJECKnoH3HRozv0vN--n5d6Nbvg==
x-xss-protection → 1; mode=block;
```

(Optional) Response Body

This part is optional. The body of a response is often returned in structured format (for example, JSON or XML) as specified in the **Content-Type** header field. The response body transfers content except the response header.

The following is part of the response body for the API used to [obtain a user token](#).

```
{
  "token": {
    "expires_at": "2019-02-13T06:52:13.855000Z",
```

```
"methods": [  
    "password"  
],  
"catalog": [  
    {  
        "endpoints": [  
            {  
                "region_id": "az-01",  
.....
```

If an error occurs during API calling, an error code and a message will be displayed. The following shows an error response body.

```
{  
    "error_code": "AS.0001",  
    "error_msg": "The format of message is error"  
}
```

In the response body, **error_code** is an error code, and **error_msg** provides information about the error.

4 APIs (Recommended)

4.1 DB Engine Version Queries

4.1.1 Querying Version Information About a DB Engine

Function

This API is used to query the version information of a specified DB engine. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/datastores/{database_name}

Table 4-1 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
database_name	Yes	String	DB engine. Its value is case-insensitive and can be: gaussdb-mysql .

Request Parameters

Table 4-2 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-3 Response body parameters

Parameter	Type	Description
datastores	Array of MysqlEngineVersionInfo objects	DB versions.

Table 4-4 MysqlEngineVersionInfo

Parameter	Type	Description
id	String	DB version ID. Its value is unique.
name	String	DB version number. Only the major version number with two digits is returned.
version	String	Compatible open-source DB version. A three-digit open-source version is returned.
kernel_version	String	DB kernel version. A complete four-digit version is returned.

Status code: 400

Table 4-5 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-6 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying version information about a GaussDB(for MySQL) instance

```
GET https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/datastores/gaussdb-mysql
```

Example Response

Status code: 200

Success.

```
{  
  "datastores": [ {  
    "id": "87620726-6802-46c0-9028-a8785e1f1921",  
    "name": "8.0",  
    "version": "8.0.22",  
    "kernel_version": "2.0.28.18"  
  } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.2 Database Specification Queries

4.2.1 Querying Database Specifications

Function

This API is used to query the database specifications of a specified DB engine version. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/flavors/{database_name}

Table 4-7 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
database_name	Yes	String	DB engine name.

Table 4-8 Query parameters

Parameter	Mandatory	Type	Description
availability_zone_mode	Yes	String	AZ mode. Value: <ul style="list-style-type: none">• single: single AZ• multi: multiple AZs
version_name	No	String	DB version number. To obtain this value, see Querying Version Information About a DB Engine . Currently, only MySQL 8.0 is supported.
spec_code	No	String	Specification code.

Request Parameters

Table 4-9 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 202

Table 4-10 Response body parameters

Parameter	Type	Description
flavors	Array of MysqlFlavorsInfo objects	Instance specifications.

Table 4-11 MysqlFlavorsInfo

Parameter	Type	Description
vcpus	String	Number of vCPUs. For example, the value 1 indicates 1 vCPU.
ram	String	Memory size in GB.

Parameter	Type	Description
type	String	CPU architecture. Value: <ul style="list-style-type: none">• arm: exclusive Arm• x86: exclusive x86• generalX86: general-purpose x86
id	String	Specification ID. The value must be unique.
spec_code	String	Resource specification code. Its value is same as the value of flavor_ref . For example: gaussdb.mysql.xlarge.x86.4.
version_name	String	DB version number.
instance_mode	String	DB instance type. Currently, only the cluster type is supported.
az_status	Map<String, String>	Status of the AZ where the specification belongs. Its value can be any of the following: <ul style="list-style-type: none">• normal: on sale• unsupported: not supported• sellout: sold out

Status code: 400**Table 4-12** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-13** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying specific specifications of a GaussDB(for MySQL) instance

GET https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/flavors/gaussdb-mysql?
version_name=8.0&spec_code=gaussdb.mysql.xlarge.x86.4&availability_zone_mode=single

Example Response

Status code: 202

Success.

```
{  
  "flavors": [ {  
    "vcpus": "4",  
    "ram": "16",  
    "type": "x86",  
    "id": "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",  
    "spec_code": "gaussdb.mysql.xlarge.x86.4",  
    "instance_mode": "Cluster",  
    "version_name": "8.0",  
    "az_status": {  
      "az1": "normal",  
      "az2": "normal"  
    }  
  } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3 Instance Management

4.3.1 Creating a DB Instance

Function

This API is used to create a GaussDB(for MySQL) DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances

Table 4-14 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-15 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-16 Request body parameters

Parameter	Mandatory	Type	Description
region	Yes	String	Region ID. The value cannot be empty. To obtain this value, see Regions and Endpoints .

Parameter	Mandatory	Type	Description
name	Yes	String	DB instance name. Instances of the same type can have same names under the same tenant. The name must start with a letter and consist of 4 to 64 characters. Only letters (case-sensitive), digits, hyphens (-), and underscores (_) are allowed.
datastore	Yes	MysqlDatastoreInReq object	Database information.
mode	Yes	String	Instance type. Currently, only the cluster type is supported.
flavor_ref	Yes	String	Specification code.
vpc_id	Yes	String	VPC ID. To obtain this value, use either of the following methods: <ul style="list-style-type: none">Method 1: Log in to the VPC console and view the VPC ID on the VPC details page.Method 2: See "Querying VPCs" in the <i>Virtual Private Cloud API Reference</i>.
subnet_id	Yes	String	Network ID. To obtain this value, use either of the following methods: <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the network ID on the displayed page.Method 2: See "Querying Subnets" in the <i>Virtual Private Cloud API Reference</i>.

Parameter	Mandatory	Type	Description
password	Yes	String	Database password. The password consists of 8 to 32 characters and contains at least three types of the following: uppercase letters, lowercase letters, digits, and special characters (~!@#\$%^*-_=+?,()&). You are advised to enter a strong password to improve security and prevent security risks such as brute force cracking. If you enter a weak password, the system automatically determines that the password is invalid.
availability_zone_mode	Yes	String	AZ type. Value: <ul style="list-style-type: none">• single: single AZ• multi: multiple AZs
slave_count	Yes	Integer	Number of read replicas. A maximum of nine read replicas can be created at a time.
charge_info	No	MysqlChargeInfo object	Billing mode, which is yearly/monthly or pay-per-use (default setting). Note: You cannot create yearly/monthly instances in a DeC.

Parameter	Mandatory	Type	Description
security_group_id	No	String	<p>Security group ID.</p> <p>If network ACL is enabled, this parameter cannot be specified. If network ACL is disabled, this parameter is mandatory.</p> <ul style="list-style-type: none">Method 1: Log in to VPC console. Choose Access Control > Security Groups in the navigation pane on the left. On the displayed page, click the target security group. You can view the security group ID on the displayed page.Method 2: See "Querying Security Groups" in the <i>Virtual Private Cloud API Reference</i>.
configuration_id	No	String	Parameter template ID.
backup_strategy	No	MysqlBackupStrategy object	Automated backup policy.
time_zone	No	String	Time zone. The default time zone is UTC.
master_availability_zone	No	String	<p>Primary AZ.</p> <ul style="list-style-type: none">If availability_zone_mode is set to multi, this parameter is mandatory.If availability_zone_mode is set to single, this parameter cannot be specified.
volume	No	MysqlVolume object	Volume information. This parameter is optional during the creation of yearly/monthly instances.

Parameter	Mandatory	Type	Description
tags	No	Array of MysqlTags objects	<p>Tag list. Instances are created based on tag keys and values.</p> <ul style="list-style-type: none">• <i>{key}</i> indicates the tag key. It must be unique and cannot be empty.• <i>{value}</i> indicates the tag value, which can be empty. <p>To create instances with multiple tag keys and values, separate key-value pairs with commas (,). Up to 10 key-value pairs can be added.</p>
lower_case_table_names	No	Integer	<p>Whether table names are case sensitive. The default value is 1.</p> <p>Value:</p> <ul style="list-style-type: none">• 0: Table names are fixed and case-sensitive.• 1: Table names are stored in lowercase and are case-insensitive.
enterprise_project_id	No	String	Enterprise project ID. This parameter is mandatory when the enterprise project is enabled.
dedicated_resource_id	No	String	Dedicated resource pool ID. This parameter is displayed only when the dedicated resource pool is enabled.
restore_point	No	MysqlRestorePoint object	Backup information.
tde_info	No	MysqlTdeInfo object	<p>TDE configuration. The AES 256 and SM4 algorithms are supported.</p> <p>TDE is in the open beta test (OBT) phase. To use it, submit a service ticket.</p>

Table 4-17 MysqlDatastoreInReq

Parameter	Mandatory	Type	Description
type	Yes	String	DB engine. Currently, only gaussdb-mysql is supported.
version	Yes	String	DB version. A two-digit major version is returned. For details about how to obtain the version, see the name field returned by the Querying Version Information About a DB Engine .
kernel_version	No	String	DB kernel version. If you need to specify a kernel version, contact customer service. A complete 4-digital kernel version is returned. For details about how to obtain the value, see the kernel_version field returned by Querying Version Information About a DB Engine .

Table 4-18 MysqlChargeInfo

Parameter	Mandatory	Type	Description
charge_mode	Yes	String	Billing mode. Valid value: <ul style="list-style-type: none">• prePaid: indicates the yearly/monthly billing mode.• postPaid: indicates the pay-per-use billing mode.
period_type	No	String	Subscription period. Valid value: <ul style="list-style-type: none">• month: The service is subscribed by month.• year: The service is subscribed by year. <p>NOTE This parameter is valid and mandatory if charge_mode is set to prePaid.</p>

Parameter	Mandatory	Type	Description
period_num	No	Integer	<p>Subscription duration. This parameter is valid and mandatory if charge_mode is set to prePaid.</p> <p>Valid value:</p> <ul style="list-style-type: none">• When period_type is set to month, the parameter value ranges from 1 to 9.• When period_type is set to year, the parameter value ranges from 1 to 3.
is_auto_renew	No	String	<p>Whether automatic renewal is enabled for yearly/monthly DB instances. The renewal period is the same as the original period and the order will be automatically paid during the subscription renewal.</p> <ul style="list-style-type: none">• true: indicates that automatic renewal is enabled.• false: indicates that automatic renewal is disabled. The default value is false.
is_auto_pay	No	String	<p>Whether the order will be automatically paid after yearly/monthly instances are created. This parameter does not affect the payment method of automatic renewal.</p> <ul style="list-style-type: none">• true: indicates the order will be automatically paid.• false: indicates the order will be manually paid. The default value is false.

Table 4-19 MysqlBackupStrategy

Parameter	Mandatory	Type	Description
start_time	Yes	String	<p>Automated backup start time. The automated backup will be triggered within one hour after the time specified by this parameter.</p> <p>The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format.</p> <ul style="list-style-type: none">• The HH value must be 1 greater than the hh value.• The values of mm and MM must be the same and must be set to 00. <p>Example value: 21:00-22:00</p>
keep_days	No	String	Retention period of automated backups. Value: 1 to 732

Table 4-20 MysqlVolume

Parameter	Mandatory	Type	Description
size	Yes	String	<p>Disk size. The default value is 10 GB.</p> <p>Value: 10 to 128000. The value must be a multiple of 10.</p>

Table 4-21 MySqlTags

Parameter	Mandatory	Type	Description
key	Yes	String	<p>Tag key. It contains a maximum of 36 Unicode characters.</p> <p>The value cannot be an empty string, a space, or left blank.</p> <p>Only uppercase letters, lowercase letters, digits, hyphens (-), and underscores (_) are allowed.</p>
value	Yes	String	<p>Tag value. It contains a maximum of 43 Unicode characters.</p> <p>It can be an empty string.</p> <p>Only uppercase letters, lowercase letters, digits, periods (.), hyphens (-), and underscores (_) are allowed.</p>

Table 4-22 MySqlRestorePoint

Parameter	Mandatory	Type	Description
source_instance_id	Yes	String	Source instance ID.
restore_time	No	Long	Point in time that data is restored to.
backup_id	No	String	Backup file ID.
type	No	String	<p>Backup type.</p> <ul style="list-style-type: none">If this parameter is left blank, backup_id cannot be left blank and data is restored using backup files by default.When the parameter is not empty, the value can be:<ul style="list-style-type: none">backup: indicates that data is restored using backup files.timestamp: indicates that data is restored to a specified point of time.

Table 4-23 MysqlTdeInfo

Parameter	Mandatory	Type	Description
enable_tde	Yes	Boolean	Whether to enable TDE.
encryption_type	Yes	String	TDE algorithm. The AES 256 and SM4 algorithms are supported.

Response Parameters

Status code: 201

Table 4-24 Response body parameters

Parameter	Type	Description
instance	MysqlInstanceResponse object	Instance information.
job_id	String	ID of the task for creating a DB instance. This parameter is returned only when pay-per-use DB instances are created.
order_id	String	Order ID. This parameter is returned only when yearly/monthly instances are created.

Table 4-25 MysqlInstanceResponse

Parameter	Type	Description
id	String	Instance ID.
name	String	DB instance name.
status	String	DB instance status.
datastore	MysqlDatastore object	Database information.
mode	String	DB instance type. Currently, only the cluster type is supported.
configuration_id	String	Parameter template ID.
port	String	Database port.

Parameter	Type	Description
backup_strategy	MysqlBackupStrategy object	Automated backup policy.
enterprise_project_id	String	Enterprise project ID.
region	String	Region ID, which is the same as the request parameter.
availability_zone_mode	String	AZ mode, which is the same as the request parameter.
master_availability_zone	String	Primary AZ ID.
vpc_id	String	VPC ID, which is the same as the request parameter.
security_group_id	String	Security group ID, which is the same as the request parameter.
subnet_id	String	Subnet ID, which is the same as the request parameter.
flavor_ref	String	Specification code, which is the same as the request parameter.
charge_info	MysqlChargeInfo object	Billing mode, which is yearly/monthly or pay-per-use. By default, pay-per-use is used.
volume	MysqlVolumeResp object	Volume information. This parameter is returned when a yearly/monthly DB instance is created.

Table 4-26 MysqlDatastore

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.
version	String	DB version. A two-digit major version is returned. For details about how to obtain the version, see the name field returned by the Querying Version Information About a DB Engine .

Parameter	Type	Description
kernel_version	String	DB kernel version. A complete 4-digital kernel version is returned. For details about how to obtain the version, see the kernel_version field returned by the Querying Version Information About a DB Engine .

Table 4-27 MysqlBackupStrategy

Parameter	Type	Description
start_time	String	Automated backup start time. The automated backup will be triggered within one hour after the time specified by this parameter. The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format. <ol style="list-style-type: none">1. The HH value must be 1 greater than the hh value.2. The values of mm and MM must be the same and must be set to 00.
keep_days	String	Automated backup retention days. Value: 1-732.

Table 4-28 MysqlChargeInfo

Parameter	Type	Description
charge_mode	String	Billing mode, which is yearly/monthly or pay-per-use.

period_type String Subscription period.
Valid value:

- **month**: The service is subscribed by month.
- **year**: The service is subscribed by year.

This parameter is valid and mandatory only when **charge_mode** is set to **prePaid**.
Valid value:

- **month**
- **year**

Parameter	Type	Description
period_num	Integer	<p>This parameter is valid and mandatory only when charge_mode is set to prePaid.</p> <p>Valid value:</p> <ul style="list-style-type: none"> When period_type is set to month, the parameter value ranges from 1 to 9. When period_type is set to year, the parameter value ranges from 1 to 3.
is_auto_renew	String	<p>Whether automatic renewal is enabled for yearly/monthly DB instances. The renewal period is the same as the original period and the order will be automatically paid during the subscription renewal.</p> <ul style="list-style-type: none"> true: indicates that automatic renewal is enabled. false: indicates that automatic renewal is disabled. The default value is false.
is_auto_pay	String	<p>Whether the order will be automatically paid after yearly/monthly instances are created. This parameter does not affect the payment method of automatic renewal.</p> <ul style="list-style-type: none"> true: indicates the order will be automatically paid from your account. The default value is true. false: indicates the order will be manually paid.

Table 4-29 MysqlVolumeResp

Parameter	Type	Description
size	Integer	<p>Storage space in GB.</p> <p>Value: 10 to 128000. The value must be a multiple of 10.</p>

Status code: 400**Table 4-30** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-31** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

NOTE

The value of **region** is used as an example.

- Creating a DB instance billed at a pay-per-use basis (An automated backup is created during 08:00-09:00.)

```
POST https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances
{
    "name" : "gaussdb-mysql-instance1",
    "region" : "br-iaas-odin1",
    "charge_info" : {
        "charge_mode" : "postPaid"
    },
    "datastore" : {
        "type" : "gaussdb-mysql",
        "version" : "8.0"
    },
    "mode" : "Cluster",
    "flavor_ref" : "gaussdb.mysql.xlarge.arm.4",
    "vpc_id" : "3cedfc54-b105-4652-a4e0-847b11576b58",
    "subnet_id" : "c1cfa53c-65d3-431e-8552-326bf310c7ad",
    "security_group_id" : "fc577a1a-f202-424a-977f-24faec3fdd55",
    "configuration_id" : "43570e0de32e40c5a15f831aa5ce4176pr07",
    "password" : "xxxxx",
    "backup_strategy" : {
        "start_time" : "08:00-09:00"
    },
    "availability_zone_mode" : "single",
    "slave_count" : 1,
    "enterprise_project_id" : 0
}
```

- Restoring data to a new pay-per-use DB instance using backups

```
POST https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances
{
    "name" : "gaussdb-mysql-instance2",
    "region" : "br-iaas-odin1",
    "charge_info" : {
        "charge_mode" : "postPaid"
    },
    "datastore" : {
        "type" : "gaussdb-mysql",
        "version" : "8.0"
    },
    "mode" : "Cluster",
    "flavor_ref" : "gaussdb.mysql.xlarge.arm.4",
    "vpc_id" : "3cedfc54-b105-4652-a4e0-847b11576b58",
    "subnet_id" : "c1cfa53c-65d3-431e-8552-326bf310c7ad",
    "security_group_id" : "fc577a1a-f202-424a-977f-24faec3fdd55",
    "configuration_id" : "43570e0de32e40c5a15f831aa5ce4176pr07",
    "password" : "****",
    "backup_strategy" : {
```

```

        "start_time" : "08:00-09:00"
    },
    "availability_zone_mode" : "single",
    "slave_count" : 1,
    "enterprise_project_id" : 0,
    "restore_point" : {
        "source_instance_id" : "7033e7c3cf93438797d44ad7ae0a7d95in07",
        "backup_id" : "7ffbf305376b4cbea0ae491257b6aaf9br07",
        "type" : "backup"
    }
}

```

- Restoring data to a new pay-per-use instance through PITR

```

POST https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances
{
    "name" : "gaussdb-mysql-instance3",
    "region" : "br-iaas-odin1",
    "charge_info" : {
        "charge_mode" : "postPaid"
    },
    "datastore" : {
        "type" : "gaussdb-mysql",
        "version" : "8.0"
    },
    "mode" : "Cluster",
    "flavor_ref" : "gaussdb.mysql.xlarge.arm.4",
    "vpc_id" : "3cedfc54-b105-4652-a4e0-847b11576b58",
    "subnet_id" : "c1cfa53c-65d3-431e-8552-326bf310c7ad",
    "security_group_id" : "fc577a1a-f202-424a-977f-24faec3fdd55",
    "configuration_id" : "43570e0de32e40c5a15f831aa5ce4176pr07",
    "password" : "xxxxx",
    "backup_strategy" : {
        "start_time" : "08:00-09:00"
    },
    "availability_zone_mode" : "single",
    "slave_count" : 1,
    "enterprise_project_id" : 0,
    "restore_point" : {
        "source_instance_id" : "7033e7c3cf93438797d44ad7ae0a7d95in07",
        "restore_time" : 1673852043000,
        "type" : "timestamp"
    }
}

```

Example Response

Status code: 201



The values of **region** and **master_availability_zone** are used as examples.

Success.

```
{
    "instance" : {
        "id" : "5eebbb4c0f9f4a99b42ed1b6334569aain07",
        "name" : "gaussdb-mysql-instance1",
        "status" : "BUILD",
        "region" : "br-iaas-odin1",
        "charge_info" : {
            "charge_mode" : "postPaid"
        },
        "datastore" : {
            "type" : "gaussdb-mysql",
            "version" : "8.0"
        },
        "mode" : "Cluster",
    }
}
```

```
"port" : "3306",
"enterprise_project_id" : 0,
"flavor_ref" : "gaussdb.mysql.xlarge.arm.4",
"vpc_id" : "3cedfc54-b105-4652-a4e0-847b11576b58",
"subnet_id" : "c1cfa53c-65d3-431e-8552-326bf310c7ad",
"security_group_id" : "fc577a1a-f202-424a-977f-24faec3fdd55",
"configuration_id" : "43570e0de32e40c5a15f831aa5ce4176pr07",
"backup_strategy" : {
    "start_time" : "08:00-09:00",
    "keep_days" : 7
},
"availability_zone_mode" : "single"
},
"job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.2 Querying DB instances

Function

This API is used to query DB instances according to search criteria. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3.1/{project_id}/instances

Table 4-32 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-33 Query parameters

Parameter	Mandatory	Type	Description
id	No	String	Instance ID. The asterisk (*) is reserved for the system. If the instance ID starts with *, it indicates that fuzzy match is performed based on the value following *. Otherwise, the exact match is performed based on the instance ID. The value cannot contain only asterisks (*).
name	No	String	Instance name. The asterisk (*) is reserved for the system. If the instance name starts with *, it indicates that fuzzy match is performed based on the value following *. Otherwise, the exact match is performed based on the instance name. The value cannot contain only asterisks (*).
type	No	String	Instance type to be queried. Currently, only the cluster type is supported.
datastore_type	No	String	DB type. Currently, only gaussdb-mysql is supported.
vpc_id	No	String	VPC ID.
subnet_id	No	String	Network ID of the subnet.
private_ip	No	String	Private IP address.
readonly_private_ip	No	String	Private IP address for read.
proxy_ip	No	String	Read/write splitting IP address.
offset	No	Integer	Index offset. If offset is set to N, the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.

Parameter	Mandatory	Type	Description
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
tags	No	String	Queries based on the instance tag keys and values. <ul style="list-style-type: none">• <i>{key}</i> indicates the tag key.• <i>{value}</i> indicates the tag value. To query instances with multiple tag keys and values, separate key-value pairs with commas (,). The key must be unique. Multiple keys are in AND relationship.

Request Parameters

Table 4-34 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-35 Response body parameters

Parameter	Type	Description
instances	Array of MysqlInstanceListInfoUnifyStatus objects	Instance list information.
total_count	Integer	Total number of records.

Table 4-36 MysqlInstanceListInfoUnifyStatus

Parameter	Type	Description
id	String	Instance ID, which is compliant with the UUID format.
name	String	Instance name.
status	String	Instance status. Value: <ul style="list-style-type: none">• creating: The DB instance is being created.• normal: The instance is running properly.• abnormal: The instance is abnormal.• createfail: The instance failed to be created.
private_ips	Array of strings	Private IP addresses for write. It is left blank until an ECS is created.
proxy_ips	Array of strings	Read/write splitting IP addresses. It is left blank until proxy instances are created for a DB instance.
readonly_private_ips	Array of strings	Private IP addresses for read. It is left blank until an ECS is created.
public_ips	Array of strings	EIPs.
port	String	Database port.
type	String	Instance type. The value is Cluster .
region	String	Region where the DB instance is deployed.
datastore	MysqlDatastoreWithKernelVersion object	Database information.

Parameter	Type	Description
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
updated	String	Update time. The format is the same as that of the created field.
db_user_name	String	Default username.
vpc_id	String	VPC ID.
subnet_id	String	Network ID of the subnet.
security_group_id	String	Security group ID.
flavor_ref	String	Specification code.
flavor_info	MysqlFlavorInfo object	Flavor information.
volume	MysqlVolumeInfo object	Storage disk information.
backup_strategy	MysqlBackupStrategy object	Automated backup policy.
enterprise_project_id	String	Enterprise project ID.
time_zone	String	Time zone.
charge_info	MysqlChargeInfo object	Billing mode, which is yearly/monthly or pay-per-use (default setting).
dedicated_resource_id	String	Dedicated resource pool ID. This parameter is returned only when the instance belongs to a dedicated resource pool.
tags	Array of InstanceTagItem objects	Tag list.

Table 4-37 MysqlDatastoreWithKernelVersion

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.
version	String	DB version.
kernel_version	String	Database kernel version.

Table 4-38 MysqlFlavorInfo

Parameter	Type	Description
vcpus	String	Number of vCPUs.
ram	String	Memory size in GB.

Table 4-39 MysqlVolumeInfo

Parameter	Type	Description
type	String	Disk type.
size	String	Used disk size in GB.

Table 4-40 MysqlBackupStrategy

Parameter	Type	Description
start_time	String	Automated backup start time. The creation of an automated backup will be triggered within one hour after the time specified by this parameter. The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format. 1. The HH value must be 1 greater than the hh value. 2. The values of mm and MM must be the same and must be set to 00 .
keep_days	String	Automated backup retention days. Value: 1-732 .

Table 4-41 MysqlChargeInfo

Parameter	Type	Description
charge_mode	String	<p>Billing mode.</p> <p>Value:</p> <ul style="list-style-type: none">• prePaid: indicates the yearly/monthly billing mode.• postPaid: indicates the pay-per-use billing mode. <p>Value:</p> <ul style="list-style-type: none">• prePaid• postPaid
period_type	String	<p>Subscription period.</p> <p>Value:</p> <ul style="list-style-type: none">• month: The service is subscribed by month.• year: The service is subscribed by year. <p>This parameter is valid and mandatory only when charge_mode is set to prePaid.</p> <p>Value:</p> <ul style="list-style-type: none">• month• year
period_num	Integer	<p>This parameter is valid and mandatory only when charge_mode is set to prePaid.</p> <p>Value:</p> <ul style="list-style-type: none">• When period_type is set to month, the parameter value ranges from 1 to 9.• When period_type is set to year, the parameter value ranges from 1 to 3.
is_auto_renew	String	<p>Whether automatic renewal is enabled for yearly/monthly DB instances. The renewal period is the same as the original period and the order will be automatically paid during the subscription renewal.</p> <ul style="list-style-type: none">• true: indicates that automatic renewal is enabled.• false: indicates that automatic renewal is disabled. The default value is false.

Parameter	Type	Description
is_auto_pay	String	<p>Whether the order will be automatically paid after yearly/monthly instances are created. This parameter does not affect the payment method of automatic renewal.</p> <ul style="list-style-type: none">• true: indicates the order will be automatically paid from your account. The default value is true.• false: indicates the order will be manually paid.

Table 4-42 InstanceTagItem

Parameter	Type	Description
key	String	Tag key.
value	String	Tag value.

Status code: 400**Table 4-43** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-44** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying GaussDB(for MySQL) instances whose private IP addresses are 192.168.0.142

```
GET https://[endpoint]/v3.1/054e292c9880d4992f02c0196d3ea468/instances?  
id=61a4ea66210545909d74a05c27a7179ein07&name=gaussdb-mysql-
```

```
instance01&type=Cluster&datastore_type=gaussdb-mysql&vpc_id=3cedfc54-b105-4652-a4e0-847b11576b58&subnet_id=c1cfa53c-65d3-431e-8552-326bf310c7ad&private_ip=192.168.0.142&offset=0&limit=10&tags=taurusKey1=value1
```

Example Response

Status code: 200

Success.

```
{  
    "total_count": 1,  
    "instances": [ {  
        "id": "61a4ea66210545909d74a05c27a7179ein07",  
        "name": "gaussdb-mysql-instance01",  
        "status": "normal",  
        "port": 3306,  
        "type": "Cluster",  
        "private_ips": [ "192.168.0.142" ],  
        "readonly_private_ips": [ "192.168.0.228", "192.168.0.165" ],  
        "proxy_ips": [ "192.168.0.15" ],  
        "db_user_name": "root",  
        "region": "cn-north-4",  
        "datastore": {  
            "type": "gaussdb-mysql",  
            "version": "8.0",  
            "kernel_version": "2.0.29.1"  
        },  
        "created": "2018-08-20T02:33:49_0800",  
        "updated": "2018-08-20T02:33:49_0800",  
        "volume": {  
            "type": "POOL",  
            "size": 100  
        },  
        "vpc_id": "3cedfc54-b105-4652-a4e0-847b11576b58",  
        "subnet_id": "c1cfa53c-65d3-431e-8552-326bf310c7ad",  
        "security_group_id": "fc577a1a-f202-424a-977f-24faec3fdd55",  
        "flavor_ref": "gaussdb.mysql.c3.small.4",  
        "flavor_info": {  
            "vcpus": 8,  
            "ram": 16  
        },  
        "backup_strategy": {  
            "start_time": "19:00-20:00",  
            "keep_days": 7  
        },  
        "charge_info": {  
            "charge_mode": "postPaid"  
        },  
        "enterprise_project_id": 0,  
        "time_zone": "UTC",  
        "tags": [ {  
            "key": "taurusKey1",  
            "value": "value1"  
        } ]  
    } ]  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.

Status Code	Description
500	Server error.

Error Code

For details, see [Error Codes](#).

4.3.3 Rebooting a DB Instance

Function

This API is used to reboot a DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/restart

Table 4-45 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-46 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-47 Request body parameters

Parameter	Mandatory	Type	Description
delay	No	Boolean	Whether the instance will be rebooted with a delay. <ul style="list-style-type: none">• true: The instance will be rebooted during the specified maintenance window.• false (default value): The instance will be rebooted immediately.

Response Parameters

Status code: 200

Table 4-48 Response body parameter

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400**Table 4-49** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-50** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Rebooting a GaussDB(for MySQL) instance in the maintenance window

```
POST https://{endpoint}/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/restart  
{  
    "delay" : true  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "e0fbbfc8-1ac4-4721-b9e9-7dd685c5bdd7"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.4 Deleting or Unsubscribing from a DB Instance

Function

This API is used to delete a DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/instances/{instance_id}

Table 4-51 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-52 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-53 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.
order_id	String	Order ID. This parameter is returned only for yearly/monthly instances.

Status code: 400**Table 4-54** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-55** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- Deleting a pay-per-use DB instance
`DELETE https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/096c0fc43e804757b59946b80dc27f8bin07`
- Unsubscribe from a yearly/monthly DB instance
`DELETE https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/096c0fc43e804757b59946b80dc27f8bin07`

Example Response

Status code: 200

Success.

- Pay-per-use DB instance
`{
 "job_id" : "04efe8e2-9255-44ae-a98b-d87cae411890"
}`
- Yearly/monthly DB instance
`{
 "job_id" : "04efe8e2-9255-44ae-a98b-d87cae411890",
}`

```
        "order_id" : "CS2305230939BMXV8"  
    }
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.5 Querying Details of a DB Instance

Function

This API is used to query the details of a specified DB instance. Before using this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3.1/{project_id}/instances/{instance_id}

Table 4-56 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-57 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-58 Response body parameters

Parameter	Type	Description
instance	MysqlInstanceInfoDetailUnifyStatus object	Instance information.

Table 4-59 MysqlInstanceInfoDetailUnifyStatus

Parameter	Type	Description
id	String	Instance ID, which is compliant with the UUID format.
name	String	Instance name.
project_id	String	Project ID of a tenant in a region.

Parameter	Type	Description
status	String	Instance status. Value: <ul style="list-style-type: none">• creating: The DB instance is being created.• normal: The instance is running properly.• abnormal: The instance is abnormal.• createfail: The instance failed to be created.
port	String	Database port.
alias	String	Instance description.
type	String	Instance type. The value is Cluster .
charge_info	MysqlInstanceChargeInfo object	Billing mode, which is yearly/monthly or pay-per-use (default setting).
node_count	Integer	Number of nodes.
datastore	MysqlDatastoreWithKernelVersion object	Database information.
backup_used_space	Double	Used backup space in GB.
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
updated	String	Update time. The format is the same as that of the created field.
private_write_ips	Array of strings	Private IP address list.
private_dns_names	Array of strings	Private domain name list. After a DB instance is created, you need to manually apply for a private domain name, or the private domain name is left blank.
public_ips	String	EIP list.
db_user_name	String	Default username.
vpc_id	String	VPC ID.
subnet_id	String	Network ID of the subnet.

Parameter	Type	Description
security_group_id	String	Security group ID.
configuration_id	String	ID of the parameter template used for creating a DB instance or ID of the latest parameter template that is applied to a DB instance.
backup_strategy	MysqlBackupStrategy object	Automated backup policy.
nodes	Array of MysqlInstanceNodeInfo objects	Node information.
enterprise_project_id	String	Enterprise project ID.
time_zone	String	Time zone.
az_mode	String	AZ type. Value: <ul style="list-style-type: none">• single: single AZ• multi: multiple AZs
master_az_code	String	Primary AZ.
maintenance_window	String	Maintenance window in the UTC format.
tags	Array of MysqlTags objects	Instance tags.
dedicated_resource_id	String	Dedicated resource pool ID. This parameter is returned only when the instance belongs to a dedicated resource pool.
proxies	Array of MysqlProxyInfo objects	Proxy information.
tde_info	MysqlTdeInfo object	TDE configuration. The AES 256 and SM4 algorithms are supported. TDE is in the open beta test (OBT) phase. To use it, submit a service ticket.

Table 4-60 MysqlInstanceChargeInfo

Parameter	Type	Description
charge_mode	String	Billing mode.
order_id	String	Order ID. This parameter is returned only for yearly/monthly instances.

Table 4-61 MySqlDatastoreWithKernelVersion

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.
version	String	DB version.
kernel_version	String	Database kernel version.

Table 4-62 MySqlBackupStrategy

Parameter	Type	Description
start_time	String	Automated backup start time. The creation of an automated backup will be triggered within one hour after the time specified by this parameter. The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format. <ol style="list-style-type: none">1. The HH value must be 1 greater than the hh value.2. The values of mm and MM must be the same and must be set to 00.
keep_days	String	Automated backup retention days. Value: 1-732 .

Table 4-63 MysqlInstanceNodeInfo

Parameter	Type	Description
id	String	Instance ID, which is compliant with the UUID format.
name	String	Node name.

Parameter	Type	Description
type	String	Node type. Value: <ul style="list-style-type: none">• master: primary node• slave: read replica
status	String	Node status.
port	Integer	Database port.
private_read_ips	Array of strings	Private IP addresses for read of nodes.
volume	MysqlInstanceNodeVolumeInfo object	Storage disk information.
az_code	String	AZ.
region_code	String	Region where the instance is located.
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
updated	String	Update time. The format is the same as that of the created field.
flavor_id	String	Specification ID.
flavor_ref	String	Specification code.
max_connections	String	Maximum number of connections.
vcpus	String	Number of vCPUs.
ram	String	Memory size in GB.
need_restart	Boolean	Whether to reboot the instance for the parameter modifications to take effect.
priority	Integer	Failover priority.

Table 4-64 MysqlInstanceNodeVolumeInfo

Parameter	Type	Description
type	String	Disk type.

Parameter	Type	Description
used	String	Used disk size in GB.
size	Long	Disk size of the yearly/monthly instance in GB.

Table 4-65 MysqlTags

Parameter	Type	Description
key	String	Tag key. The value can contain a maximum of 36 Unicode characters. The value cannot be an empty string, a space, or left blank. Only uppercase letters, lowercase letters, digits, hyphens (-), and underscores (_) are allowed.
value	String	Tag value. It can contain up to 43 Unicode characters and can be an empty string. Only uppercase letters, lowercase letters, digits, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-66 MysqlProxyInfo

Parameter	Type	Description
pool_id	String	Proxy instance ID.
name	String	Proxy instance name.
address	String	Proxy read/write splitting address.

Table 4-67 MysqlTdeInfo

Parameter	Type	Description
enable_tde	Boolean	Whether to enable TDE.
encryption_type	String	TDE algorithm. The AES 256 and SM4 algorithms are supported.

Status code: 400

Table 4-68 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-69 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying details of a specified DB instance

GET https://{{endpoint}}/v3.1/3cedfc54-b105-4652-a4e0-847b11576628/instances/d738399de028480fabbb2b8120d4e01a4in07

Example Response

Status code: 200

Success.

```
"subnet_id" : "c1cfaf53c-65d3-431e-8552-326bf310c7ad",
"security_group_id" : "fc577a1a-f202-424a-977f-24faec3fdd55",
"backup_strategy" : {
    "start_time" : "19:00-20:00",
    "keep_days" : 7
},
"nodes" : [ {
    "id" : "799a0f2fa49a4151bf9f7063c1fbba36no07",
    "name" : "gauss-d616-lb07_node01",
    "type" : "master",
    "status" : "normal",
    "port" : 3306,
    "private_read_ips" : [ "192.168.0.163" ],
    "volume" : {
        "type" : "POOL",
        "used" : 0.07
    },
    "az_code" : "az1xahz",
    "region_code" : "cn-xianhz-1",
    "flavor_id" : "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
    "flavor_ref" : "gaussdb.mysql.xlarge.arm.4",
    "max_connections" : 1500,
    "vcpus" : 1,
    "ram" : 4,
    "need_restart" : false,
    "priority" : 1,
    "created" : "2022-07-14T16:26:58+0800",
    "updated" : "2022-07-18T09:24:18+0800"
}, {
    "id" : "799a0f2fa49a4151bf9f7063c1fbba35no07",
    "name" : "gauss-d616-lb07_node02",
    "type" : "slave",
    "status" : "normal",
    "port" : 3306,
    "private_read_ips" : [ "192.168.0.162" ],
    "volume" : {
        "type" : "POOL",
        "used" : 0.07
    },
    "az_code" : "az1xahz",
    "region_code" : "cn-xianhz-1",
    "flavor_id" : "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
    "flavor_ref" : "gaussdb.mysql.xlarge.arm.4",
    "max_connections" : 1500,
    "vcpus" : 1,
    "ram" : 4,
    "need_restart" : false,
    "priority" : 1,
    "created" : "2022-07-14T16:26:58+0800",
    "updated" : "2022-07-18T09:36:18+0800"
} ],
"time_zone" : "UTC+08:00",
"backup_used_space" : 0.24,
"az_mode" : "single",
"master_az_code" : "az1",
"maintenance_window" : "18:00-22:00",
"tags" : [ ],
"configuration_id" : "53570e0de54e40c5a15f331aa5sd2176pr07",
"dedicated_resource_id" : "",
"proxies" : [ {
    "pool_id" : "dab1fcf5150c4d1ca0e8c6596bfc0d8cpo01",
    "address" : "192.168.10.76",
    "name" : "proxy-name"
} ]
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.3.6 Querying Details of DB Instances in Batches

Function

This API is used to query details of DB instances in batches. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3.1/{project_id}/instances/details

Table 4-70 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-71 Query parameters

Parameter	Mandatory	Type	Description
instance_ids	Yes	String	Instance ID, which is compliant with the UUID format. A maximum of 20 instance IDs can be entered at a time. Separate them with commas (,).

Request Parameters

Table 4-72 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-73 Response body parameters

Parameter	Type	Description
instances	Array of MysqlInstanceInfoDetailUnifyStatus objects	Instance details.

Table 4-74 MysqlInstanceInfoDetailUnifyStatus

Parameter	Type	Description
id	String	Instance ID, which is compliant with the UUID format.
name	String	Instance name.
project_id	String	Project ID of a tenant in a region.

Parameter	Type	Description
status	String	Instance status. Value: <ul style="list-style-type: none">• creating: The DB instance is being created.• normal: The instance is running properly.• abnormal: The instance is abnormal.• createfail: The instance failed to be created.
port	String	Database port.
alias	String	Instance description.
type	String	Instance type. The value is Cluster .
charge_info	MysqlInstanceChargeInfo object	Billing mode, which is yearly/monthly or pay-per-use (default setting).
node_count	Integer	Number of nodes.
datastore	MysqlDatastoreWithKernelVersion object	Database information.
backup_used_space	Double	Used backup space in GB.
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
updated	String	Update time. The format is the same as that of the created field.
private_write_ips	Array of strings	Private IP address list.
private_dns_names	Array of strings	Private domain name list. After a DB instance is created, you need to manually apply for a private domain name, or the private domain name is left blank.
public_ips	String	EIP list.
db_user_name	String	Default username.
vpc_id	String	VPC ID.
subnet_id	String	Network ID of the subnet.

Parameter	Type	Description
security_group_id	String	Security group ID.
configuration_id	String	ID of the parameter template used for creating a DB instance or ID of the latest parameter template that is applied to a DB instance.
backup_strategy	MysqlBackupStrategy object	Automated backup policy.
nodes	Array of MysqlInstanceNodeInfo objects	Node information.
enterprise_project_id	String	Enterprise project ID.
time_zone	String	Time zone.
az_mode	String	AZ type. Value: <ul style="list-style-type: none">• single: single AZ• multi: multiple AZs
master_az_code	String	Primary AZ.
maintenance_window	String	Maintenance window in the UTC format.
tags	Array of MysqlTags objects	Instance tags.
dedicated_resource_id	String	Dedicated resource pool ID. This parameter is returned only when the instance belongs to a dedicated resource pool.
proxies	Array of MysqlProxyInfo objects	Proxy information.
tde_info	MysqlTdeInfo object	TDE configuration. The AES 256 and SM4 algorithms are supported. TDE is in the open beta test (OBT) phase. To use it, submit a service ticket.

Table 4-75 MysqlInstanceChargeInfo

Parameter	Type	Description
charge_mode	String	Billing mode.
order_id	String	Order ID. This parameter is returned only for yearly/monthly instances.

Table 4-76 MysqlDatastoreWithKernelVersion

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.
version	String	DB version.
kernel_version	String	Database kernel version.

Table 4-77 MysqlBackupStrategy

Parameter	Type	Description
start_time	String	Automated backup start time. The creation of an automated backup will be triggered within one hour after the time specified by this parameter. The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format. <ol style="list-style-type: none">1. The HH value must be 1 greater than the hh value.2. The values of mm and MM must be the same and must be set to 00.
keep_days	String	Automated backup retention days. Value: 1-732 .

Table 4-78 MysqlInstanceNodeInfo

Parameter	Type	Description
id	String	Instance ID, which is compliant with the UUID format.
name	String	Node name.

Parameter	Type	Description
type	String	Node type. Value: <ul style="list-style-type: none">• master: primary node• slave: read replica
status	String	Node status.
port	Integer	Database port.
private_read_ips	Array of strings	Private IP addresses for read of nodes.
volume	MysqlInstanceNodeVolumeInfo object	Storage disk information.
az_code	String	AZ.
region_code	String	Region where the instance is located.
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
updated	String	Update time. The format is the same as that of the created field.
flavor_id	String	Specification ID.
flavor_ref	String	Specification code.
max_connections	String	Maximum number of connections.
vcpus	String	Number of vCPUs.
ram	String	Memory size in GB.
need_restart	Boolean	Whether to reboot the instance for the parameter modifications to take effect.
priority	Integer	Failover priority.

Table 4-79 MysqlInstanceNodeVolumeInfo

Parameter	Type	Description
type	String	Disk type.

Parameter	Type	Description
used	String	Used disk size in GB.
size	Long	Disk size of the yearly/monthly instance in GB.

Table 4-80 MysqlTags

Parameter	Type	Description
key	String	Tag key. The value can contain a maximum of 36 Unicode characters. The value cannot be an empty string, a space, or left blank. Only uppercase letters, lowercase letters, digits, hyphens (-), and underscores (_) are allowed.
value	String	Tag value. It can contain up to 43 Unicode characters and can be an empty string. Only uppercase letters, lowercase letters, digits, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-81 MysqlProxyInfo

Parameter	Type	Description
pool_id	String	Proxy instance ID.
name	String	Proxy instance name.
address	String	Proxy read/write splitting address.

Table 4-82 MysqlTdeInfo

Parameter	Type	Description
enable_tde	Boolean	Whether to enable TDE.
encryption_type	String	TDE algorithm. The AES 256 and SM4 algorithms are supported.

Status code: 400

Table 4-83 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-84** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying details of DB instances in batches

```
GET https://[endpoint]/v3.1/97b026aa9cc4417888c14c84a1ad9860/instances/details?  
instance_ids=11684a0e59e94bceba7880d58cfb07b5in07
```

Example Response

Status code: 200

Success.

```
{  
    "instances": [ {  
        "id": "11684a0e59e94bceba7880d58cfb07b5in07",  
        "name": "gaussdb-mysql-instance01",  
        "alias": "",  
        "status": "normal",  
        "project_id": "3cedfc54-b105-4652-a4e0-847b11576628",  
        "enterprise_project_id": 0,  
        "type": "Cluster",  
        "charge_info": {  
            "charge_mode": "postPaid",  
            "order_id": ""  
        },  
        "node_count": 2,  
        "datastore": {  
            "type": "gaussdb-mysql",  
            "version": "8.0",  
            "kernel_version": "2.0.29.1"  
        },  
        "created": "2022-07-14T16:58+0800",  
        "updated": "2022-07-18T14:20:33+0800",  
        "public_ips": "10.154.219.187",  
        "private_write_ips": [ "192.168.0.142" ],  
        "private_dns_names": [ "11684a0e59e94bceba7880d58cfb07b5in07.internal.cn-xianhz-1.gaussdbformysql.myhuaweicloud.com" ],  
        "db_user_name": "root",  
        "port": 3306,  
        "vpc_id": "3cedfc54-b105-4652-a4e0-847b11576b58",  
        "vpc_name": "gaussdb-mysql",  
        "vpc_ip": "10.154.219.187",  
        "vpc_subnet": "10.154.219.0/24",  
        "vpc_gateway": "10.154.219.1",  
        "vpc_dhcp": "10.154.219.1",  
        "vpc_dhcp_start": "10.154.219.100",  
        "vpc_dhcp_end": "10.154.219.140",  
        "vpc_dhcp_lease_time": 21600  
    }  
}
```

```
"subnet_id" : "c1cfaf53c-65d3-431e-8552-326bf310c7ad",
"security_group_id" : "fc577a1a-f202-424a-977f-24faec3fdd55",
"backup_strategy" : {
    "start_time" : "19:00-20:00",
    "keep_days" : 7
},
"nodes" : [ {
    "id" : "799a0f2fa49a4151bf9f7063c1fbba36no07",
    "name" : "gauss-d616-lb07_node01",
    "type" : "master",
    "status" : "normal",
    "port" : 3306,
    "private_read_ips" : [ "192.168.0.163" ],
    "volume" : {
        "type" : "POOL",
        "used" : 0.07
    },
    "az_code" : "az1xahz",
    "region_code" : "cn-xianhz-1",
    "flavor_id" : "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
    "flavor_ref" : "gaussdb.mysql.xlarge.arm.4",
    "max_connections" : 1500,
    "vcpus" : 1,
    "ram" : 4,
    "need_restart" : false,
    "priority" : 1,
    "created" : "2022-07-14T16:26:58+0800",
    "updated" : "2022-07-18T09:24:18+0800"
}, {
    "id" : "799a0f2fa49a4151bf9f7063c1fbba35no07",
    "name" : "gauss-d616-lb07_node02",
    "type" : "slave",
    "status" : "normal",
    "port" : 3306,
    "private_read_ips" : [ "192.168.0.162" ],
    "volume" : {
        "type" : "POOL",
        "used" : 0.07
    },
    "az_code" : "az1xahz",
    "region_code" : "cn-xianhz-1",
    "flavor_id" : "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
    "flavor_ref" : "gaussdb.mysql.xlarge.arm.4",
    "max_connections" : 1500,
    "vcpus" : 1,
    "ram" : 4,
    "need_restart" : false,
    "priority" : 1,
    "created" : "2022-07-14T16:26:58+0800",
    "updated" : "2022-07-18T09:36:18+0800"
} ],
"time_zone" : "UTC+08:00",
"backup_used_space" : 0.24,
"az_mode" : "single",
"master_az_code" : "az1",
"maintenance_window" : "18:00-22:00",
"tags" : [ ],
"configuration_id" : "53570e0de54e40c5a15f331aa5sd2176pr07",
"dedicated_resource_id" : "",
"proxies" : [ {
    "pool_id" : "dab1fcf5150c4d1ca0e8c6596bfc0d8cpo01",
    "address" : "192.168.10.76",
    "name" : "proxy-name"
} ]
} ]
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.3.7 Creating a Read Replica

Function

This API is used to create a read replica. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/nodes/enlarge

Table 4-85 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-86 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-87 Request body parameters

Parameter	Mandatory	Type	Description
priorities	Yes	Array of integers	Failover priority of a read replica. Failover priority ranges from 1 for the first priority to 16 for the last priority. This priority determines the order in which read replicas are promoted when recovering from a primary node failure. Read replicas with the same priority have a same probability of being promoted to the new primary node.

Parameter	Mandatory	Type	Description
is_auto_pay	No	String	<p>Whether the order will be automatically paid after yearly/monthly instances are created. This parameter does not affect the payment method of automatic renewal.</p> <ul style="list-style-type: none">• true: indicates the order will be automatically paid from your account. The default value is true.• false: indicates the order will be manually paid.
availability_zones	No	Array of strings	<p>AZ. You can specify an AZ to create a read replica. If this parameter is not specified, an AZ is automatically assigned by default.</p> <p>The function is in the open beta test (OBT) phase. To use it, submit a service ticket.</p> <p>To obtain the value, see the key availability_zone in az_status of Querying Database Specifications.</p> <p>Note: Creating a read replica in a specified AZ may fail due to insufficient resources.</p>

Response Parameters

Status code: 201

Table 4-88 Response body parameters

Parameter	Type	Description
instance_id	String	Instance ID.
node_names	Array of strings	Node name list
job_id	String	ID of the task for creating a read replica. This parameter is returned only when a pay-per-use read replica is created.
order_id	String	Order ID. This parameter is returned when yearly/monthly read replicas are created.

Status code: 400**Table 4-89** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-90** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Creating a read replica for a DB instance

```
POST https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
ba62a0b83a1b42bfab275829d86ac0fdin07/nodes/enlarge  
{  
    "priorities" : [ 1, 2 ]  
}
```

Example Response

Status code: 201

Success.

```
{  
    "instance_id" : "ba62a0b83a1b42bfab275829d86ac0fdin07",  
    "node_names" : [ "gauss-ccf5_node03" ],  
    "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.8 Deleting or Unsubscribing from a Read Replica

Function

This API is used to delete a read replica. For multi-AZ deployment, the primary node and remaining read replicas must be located in different AZs after read replicas are deleted. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/instances/{instance_id}/nodes/{node_id}

Table 4-91 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
node_id	Yes	String	Node ID, which is compliant with the UUID format.

Request Parameters

Table 4-92 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-93 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.
order_id	String	Order ID. This parameter is returned only for yearly/monthly instances.

Status code: 400

Table 4-94 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-95 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- Deleting a read replica of a pay-per-use DB instance
`DELETE https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/3d39c18788b54a919bab633874c159df1n01/nodes/096c0fc43e804757b59946b80dc27f8bin07`

- Unsubscribing from a read replica of a yearly/monthly DB instance
`DELETE https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/3d39c18788b54a919bab633874c159df1n01/nodes/096c0fc43e804757b59946b80dc27f8bin07`

Example Response

Status code: 200

Success.

- Pay-per-use DB instance
`{
 "job_id" : "04efe8e2-9255-44ae-a98b-d87cae411890"
}`
- Yearly/monthly DB instance
`{
 "job_id" : "04efe8e2-9255-44ae-a98b-d87cae411890",
 "order_id" : "CS2305230939BMXV8"
}`

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.9 Scaling up Storage of a Yearly/Monthly DB Instance

Function

This API is used to scale up the storage of a yearly/monthly DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

`POST /v3/{project_id}/instances/{instance_id}/volume/extend`

Table 4-96 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-97 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-98 Request body parameters

Parameter	Mandatory	Type	Description
size	Yes	Integer	Storage space after scaling. The initial minimum storage of a yearly/monthly instance is 10 GB. The new storage must be a multiple of 10 and greater than the used storage. The maximum storage is 128,000 GB. Value: <ul style="list-style-type: none">• The storage must be at least 20 GB during scale-up.• The storage must be at least 10 GB during scale-down.

Parameter	Mandatory	Type	Description
is_auto_pay	No	String	Whether the order will be automatically paid. <ul style="list-style-type: none">• true: indicates the order will be automatically paid from your account. The default value is true.• false: indicates the order will be manually paid.

Response Parameters

Status code: 201

Table 4-99 Response body parameters

Parameter	Type	Description
size	Integer	New storage in GB.
order_id	String	Order ID.

Status code: 400

Table 4-100 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-101 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Scaling up the storage of a yearly/monthly DB instance to 50 GB

```
POST https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
ba62a0b83a1b42bfab275829d86ac0fdin07/volume/extend  
{  
    "size" : 50  
}
```

Example Response

Status code: 201

Success.

```
{  
    "size" : 50,  
    "order_id" : "CS2001221129LVGUU"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.10 Changing a DB Instance Name

Function

This API is used to change a DB instance name. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/name

Table 4-102 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-103 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-104 Request body parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Instance name. Instances of the same type can have same names under the same tenant. The name must start with a letter and consist of 4 to 64 characters. Only letters (case-sensitive), digits, hyphens (-), and underscores (_) are allowed.

Response Parameters

Status code: 200

Table 4-105 Response body parameters

Parameter	Type	Description
job_id	String	Task ID for changing a DB instance name.

Status code: 400

Table 4-106 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-107** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the instance name to gaussdb-name

```
PUT https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
ba62a0b83a1b42bfab275829d86ac0fdin07/name  
{  
    "name" : "gaussdb-name"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "0f6b6a9e-bd39-4e95-9374-e4d134e5a3d1"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.11 Resetting a Database Password

Function

This API is used to reset a database password. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/password

Table 4-108 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-109 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-110 Request body parameters

Parameter	Mandatory	Type	Description
password	Yes	String	<p>Database password. Value: The password consists of 8 to 32 characters and contains at least three types of the following: uppercase letters, lowercase letters, digits, and special characters (~!@#\$%^*-_=+?,()&).</p> <p>NOTE You are advised to enter a strong password to improve security and prevent security risks such as brute force cracking. If you enter a weak password, the system automatically determines that the password is invalid.</p>

Response Parameters

Status code: 400

Table 4-111 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-112 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Resetting a database password

```
POST https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
ba62a0b83a1b42bfab275829d86ac0fdin07/password
```

```
{  
    "password" : "Test_345612"  
}
```

Example Response

None

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.12 Changing DB Instance Specifications

Function

This API is used to change DB instance specifications. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/action

Table 4-113 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-114 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-115 Request body parameters

Parameter	Mandatory	Type	Description
resize_flavor	Yes	MysqlResizeFlavor object	Specification change information.
is_auto_pay	No	String	Whether the order will be automatically paid when the specifications of yearly/monthly instances are changed. <ul style="list-style-type: none">• true: indicates the order will be automatically paid from your account. The default value is true.• false: indicates the order will be manually paid.

Table 4-116 MysqlResizeFlavor

Parameter	Mandatory	Type	Description
spec_code	Yes	String	Specification code.

Response Parameters

Status code: 200

Table 4-117 Response body parameters

Parameter	Type	Description
job_id	String	Job ID for changing DB instance specifications. This parameter is returned only when you change the specifications of a pay-per-use DB instance.
order_id	String	Order ID. This parameter is returned only when DB instances are billed at a yearly/monthly basis.

Status code: 400

Table 4-118 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-119 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the specifications of a DB instance to 4 vCPUs and 32 GB memory

```
{  
  "resize_flavor": {  
    "spec_code": "gaussdb.mysql.xlarge.arm.8"  
  }  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.13 Querying Dedicated Resource Pools

Function

This API is used to obtain information about all dedicated resource pools you created. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/dedicated-resources

Table 4-120 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-121 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.

Parameter	Mandatory	Type	Description
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-122 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200**Table 4-123** Response body parameters

Parameter	Type	Description
resources	Array of DedicatedResource objects	Dedicated resource pool information.
total_count	Integer	Number of dedicated resource pools.

Table 4-124 DedicatedResource

Parameter	Type	Description
id	String	ID of the dedicated resource pool.
resource_name	String	Name of the dedicated resource pool.
engine_name	String	DB engine.
architecture	String	CPU architecture.
status	String	Status of the dedicated resource pool. Value: <ul style="list-style-type: none">• NORMAL• BUILDING• EXTENDING• DELETED
capacity	DedicatedResourceCapacity object	Capacity of the dedicated resource pool.
availability_zone	Array of strings	AZ where the dedicated resource pool is deployed.

Table 4-125 DedicatedResourceCapacity

Parameter	Type	Description
ram	Integer	Memory size in GB.
volume	Long	Disk capacity in GB.
vcpus	Integer	Number of vCPUs.

Status code: 400**Table 4-126** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-127 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying dedicated resource pools

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/dedicated-resources
```

Example Response

Status code: 200

Success.

```
{  
  "resources" : [ {  
    "id" : "1d07f7ba-f140-46a7-b002-58ba22ee6ff3",  
    "resource_name" : "testdcc",  
    "engine_name" : "gaussdb-mysql",  
    "architecture" : "ARM",  
    "status" : "NORMAL",  
    "capacity" : {  
      "ram" : 256,  
      "volume" : 10000000,  
      "vcpus" : 64  
    },  
    "availability_zone" : [ "az1xahz" ]  
  } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.14 Querying Dedicated Resources

Function

This API is used to query dedicated resources. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

```
GET /v3/{project_id}/dedicated-resource/{dedicated_resource_id}
```

Table 4-128 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
dedicated_resource_id	Yes	String	ID of the dedicated resource pool.

Request Parameters

Table 4-129 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-130 Response body parameters

Parameter	Type	Description
id	String	ID of the dedicated resource pool.
name	String	Name of the dedicated resource pool.
engine_name	String	Database name.

Parameter	Type	Description
availability_zone_ids	Array of strings	AZ.
architecture	String	CPU architecture.
status	String	Status of the dedicated resource pool.
dedicated_compute_info	DedicatedComputeInfo object	Compute resource information.
dedicated_storage_info	DedicatedStorageInfo object	Storage resource information.

Table 4-131 DedicatedComputeInfo

Parameter	Type	Description
vcpus_total	Integer	Total vCPUs in the dedicated resource pool.
vcpus_used	Integer	Used vCPUs in the dedicated resource pool.
ram_total	Integer	Total memory size of the dedicated resource pool, in GB.
ram_used	Integer	Used memory size of the dedicated resource pool, in GB.
spec_code	String	Compute resource specification code of the dedicated resource pool.
host_num	Integer	Number of compute hosts in the dedicated resource pool.

Table 4-132 DedicatedStorageInfo

Parameter	Type	Description
spec_code	String	Storage resource specification code of the dedicated resource pool.
host_num	Integer	Number of storage hosts in the dedicated resource pool.

Status code: 400

Table 4-133 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-134** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying dedicated resources

GET https://{endpoint}/v3/058497e1c100d3eb2f3cc01160616934/dedicated-resource/6e097c33-d6b9-4ca5-83cb-6cc79dcf4f06

Example Response

Status code: 200

Success.

```
{  
  "id" : "e097c33-d6b9-4ca5-83cb-6cc79dcf4f06",  
  "name" : "test_dcc",  
  "engine_name" : "taurus",  
  "availability_zone_ids" : [ "az1xahz", "az2xahz" ],  
  "architecture" : "ARM",  
  "status" : "normal",  
  "dedicated_compute_info" : {  
    "vcpus_total" : 128,  
    "vcpus_used" : 64,  
    "ram_total" : 512,  
    "ram_used" : 256,  
    "spec_code" : "gaussdb.mysql.c6.host",  
    "host_num" : 1  
  },  
  "dedicated_storage_info" : {  
    "spec_code" : "gaussdb.mysql.dfvpool.30tb.host",  
    "host_num" : 1  
  }  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.15 Configuring the Monitoring By Seconds Function

Function

This API is used to configure the Monitoring By Seconds function for instances. You can set the monitoring interval to 1 second or 5 seconds to view the metric values. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/monitor-policy

Table 4-135 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Request Parameters

Table 4-136 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	<p>Request language type. The default value is en-us.</p> <p>Value:</p> <ul style="list-style-type: none">• en-us• zh-cn

Table 4-137 Request body parameters

Parameter	Mandatory	Type	Description
monitor_switch	Yes	Boolean	<p>Whether to enable Monitoring by Seconds.</p> <ul style="list-style-type: none">• true: enabled• false: disabled
period	No	Integer	<p>Collection period.</p> <ul style="list-style-type: none">• This parameter is valid only when monitor_switch is set to true. The default value is 5s. <p>Value:</p> <ul style="list-style-type: none">- 1: The collection period is 1s.- 5: The collection period is 5s. <ul style="list-style-type: none">• This parameter is not specified when monitor_switch is set to false.

Response Parameters

Status code: 200

Table 4-138 Response body parameters

Parameter	Type	Description
job_id	String	Taskflow ID for modifying Monitoring by Seconds

Status code: 400

Table 4-139 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-140** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Enabling Monitoring by Seconds and changing its collection period to 1s

```
PUT https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
61a4ea66210545909d74a05c27a7179ein07/monitor-policy  
{  
    "monitor_switch" : true,  
    "period" : 1  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "6b7dd5d4-4590-4f14-b164-a8737ce071d5"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.16 Querying the Configuration of Monitoring by Seconds

Function

This API is used to query the configuration of Monitoring by Seconds. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/monitor-policy

Table 4-141 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Request Parameters

Table 4-142 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-143 Response body parameters

Parameter	Type	Description
monitor_switch	Boolean	Whether to enable Monitoring by Seconds. <ul style="list-style-type: none">• true: enabled• false: disabled
period	Integer	Collection period. This parameter is returned only when monitor_switch is set to true . <ul style="list-style-type: none">• 1: The collection period is 1s.• 5: The collection period is 5s.

Status code: 400**Table 4-144** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-145** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying the status of Monitoring by Seconds for a DB instance

GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/61a4ea66210545909d74a05c27a7179ein07/monitor-policy

Example Response

Status code: 200

Success.

{
 "monitor_switch" : true,
 "period" : "1"
}

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.17 Rebooting a Node

Function

This API is used to reboot a node. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/nodes/{node_id}/restart

Table 4-146 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.
node_id	Yes	String	Node ID.

Request Parameters

Table 4-147 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-148 Request body parameters

Parameter	Mandatory	Type	Description
delay	No	Boolean	Whether the node is rebooted immediately or in the specified maintenance window. <ul style="list-style-type: none">• true: The node is rebooted in the specified maintenance window.• false (default value): The node is rebooted immediately. It is a default value.

Response Parameters

Status code: 200

Table 4-149 Response body parameter

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-150 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-151 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Rebooting a node of a DB instance

```
POST https://[endpoint]/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
af315b8e6aaa41799bd9a31f2de15abcin07/nodes/f0d5f01f04964f36a545ad85e4e9cf  
e9no07/restart  
{  
  "delay": false  
}
```

Example Response

Success.

```
{  
  "job_id" : "6b7dd5d4-4590-4f14-b164-a8737ce071d5"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.18 Upgrading the Kernel Version of a DB Instance

Function

This API is used to upgrade the kernel version of a DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/db-upgrade

Table 4-152 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID of a tenant in a project.

Request Parameters

Table 4-153 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-154 Request body parameter

Parameter	Mandatory	Type	Description
delay	No	Boolean	Whether the instance will be upgraded with a delay. <ul style="list-style-type: none">• true: The instance will be upgraded during the specified maintenance window.• false: The instance will be upgraded immediately.

Response Parameters

Status code: 200

Table 4-155 Response body parameter

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-156 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-157 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Upgrading the minor version of a DB instance immediately

```
POST https://{endpoint}/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/db-upgrade  
{  
    "delay" : false  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "e0fbff8-1ac4-4721-b9e9-7dd685c5bdd7"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.19 Enabling or Disabling SSL

Function

This API is used to enable or disable SSL. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/ssl-option

Table 4-158 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-159 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-160 Request body parameter

Parameter	Mandatory	Type	Description
ssl_option	Yes	Boolean	Whether to enable SSL. <ul style="list-style-type: none">• true: SSL is enabled.• false: SSL is disabled.

Response Parameters

Status code: 200

Table 4-161 Response body parameter

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-162 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-163 Response body parameter

Parameter	Type	Description
error_code	String	Error code.

Parameter	Type	Description
error_msg	String	Error message.

Example Request

Enabling SSL for a DB instance

```
PUT https://{endpoint}/v3/056538411200d4cd2f79c003c7606412/instances/096c0fc43e804757b59946b80dc27f8bin07/ssl-option
{
  "ssl_option" : true
}
```

Example Response

Status code: 200

Success.

```
{
  "job_id" : "e0fbfffc8-1ac4-4721-b9e9-7dd685c5bdd7"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.20 Binding an EIP

Function

This API is used to bind an EIP to a DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

```
PUT /v3/{project_id}/instances/{instance_id}/public-ips/bind
```

Table 4-164 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-165 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-166 Request body parameters

Parameter	Mandatory	Type	Description
public_ip	Yes	String	EIP to be bound.
public_ip_id	Yes	String	EIP ID.

Response Parameters

Status code: 200

Table 4-167 Response body parameter

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-168 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-169 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Binding an EIP to a DB instance

```
PUT https://{{endpoint}}/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/public-ips/bind  
{  
    "public_ip" : "10.145.51.214",  
    "public_ip_id" : "8403e9cd-a7fa-4288-8b15-c7ceac1etest"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "e0fbfffc8-1ac4-4721-b9e9-7dd685c5bdd7"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.21 Unbinding an EIP

Function

This API is used to unbind an EIP from a DB Instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/public-ips/unbind

Table 4-170 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-171 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-172 Response body parameter

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-173 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-174 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Unbinding an EIP from a DB instance

```
PUT https://{endpoint}/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/public-ips/unbind
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "e0fbff8-1ac4-4721-b9e9-7dd685c5bdd7"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.22 Promoting a Read Replica to Primary

Function

This API is used to promote a read replica to the primary node. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/switchover

Table 4-175 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-176 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-177 Request body parameters

Parameter	Mandatory	Type	Description
node_id	Yes	String	ID of the read replica that will be promoted to the primary.

Response Parameters

Status code: 200

Table 4-178 Response body parameter

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-179 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-180 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Promoting a read replica to primary

```
PUT https://[endpoint]/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/switchover  
{  
    "node_id" : "1801a615b52b4a5697fce385f6affbf4no07"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "e0fbff8-1ac4-4721-b9e9-7dd685c5bdd7"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.23 Changing a Maintenance Window

Function

This API is used to change a maintenance window. To prevent service interruption, set the maintenance window to off-peak hours. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/ops-window

Table 4-181 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-182 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-183 Request body parameters

Parameter	Mandatory	Type	Description
start_time	Yes	String	Start time for a maintenance window (UTC time).
end_time	Yes	String	End time for a maintenance window (UTC time). NOTE The start time and end time of a maintenance window must be on the hour, and the interval between them must be four hours.

Response Parameters

Status code: 400

Table 4-184 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-185 Response body parameter

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the maintenance window of a DB instance to 22:00-02:00

```
PUT https://[endpoint]/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/ops-window  
{  
    "start_time" : "22:00",  
    "end_time" : "02:00"  
}
```

Example Response

Status code: 200

Success.

```
{ }
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.24 Modifying a Security Group

Function

This API is used to modify the security group of a specified DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

```
PUT /v3/{project_id}/instances/{instance_id}/security-group
```

Table 4-186 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-187 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-188 Request body parameter

Parameter	Mandatory	Type	Description
security_group_id	Yes	String	Security group ID.

Response Parameters

Status code: 200

Table 4-189 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400**Table 4-190** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-191** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the security group of a DB instance

```
PUT https://{endpoint}/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/security-group  
{  
    "security_group_id" : "054f55b5-946e-4761-a1e3-3be6892827c1"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "e0fbff8c-1ac4-4721-b9e9-7dd685c5bdd7"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.25 Changing a Private IP Address

Function

This API is used to change the private IP address of a DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/internal-ip

Table 4-192 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-193 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-194 Request body parameters

Parameter	Mandatory	Type	Description
internal_ip	Yes	String	Private IP address.

Response Parameters

Status code: 200

Table 4-195 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-196 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-197 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the private IP address of a DB instance

```
PUT https://[endpoint]/v3/056538411200d4cd2f79c003c7606412/instances/096c0fc43e804757b59946b80dc27f8bin07/internal-ip
{
  "internal_ip" : "192.168.0.213"
}
```

Example Response

Status code: 200

Success.

```
{
  "job_id" : "e0fbfffc8-1ac4-4721-b9e9-7dd685c5bdd7"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.26 Changing a Database Port

Function

This API is used to change the database port of a DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/port

Table 4-198 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-199 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-200 Request body parameter

Parameter	Mandatory	Type	Description
port	Yes	Integer	Port number. Value range: 1024 to 65535, excluding 5342 to 5345, 12017, 20000, 20201, 20202, 33062, and 33071.

Response Parameters

Status code: 200

Table 4-201 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-202 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-203** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the database port to 8836

```
PUT https://{endpoint}/v3/056538411200d4cd2f79c003c7606412/instances/096c0fc43e804757b59946b80dc27f8bin07/port
{
    "port" : 8836
}
```

Example Response

Status code: 200

Success.

```
{
    "job_id" : "e0fbfffc8-1ac4-4721-b9e9-7dd685c5bdd7"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.27 Changing a DB Instance Description

Function

This API is used to change a DB instance description. Before calling this API:

- Learn how to [authorize and authenticate](#) it.

- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/alias

Table 4-204 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-205 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">en-uszh-cn

Table 4-206 Request body parameter

Parameter	Mandatory	Type	Description
alias	Yes	String	Instance description. The value can contain 0 to 64 characters, including letters, digits, periods (.), underscores (_), and hyphens (-).

Response Parameters

Status code: 400

Table 4-207 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-208 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the description of a DB instance to **Test_alias**

```
PUT https://[endpoint]/v3/056538411200d4cd2f79c003c7606412/instances/096c0fc43e804757b59946b80dc27f8bin07/alias
{
    "alias" : "Test_alias"
}
```

Example Response

Status code: 200

Success.

```
{}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.28 Applying for a Private Domain Name

Function

This API is used to apply for a private domain name. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is in the open beta test (OBT) phase. To use this API, submit a service ticket.

URI

POST /v3/{project_id}/instances/{instance_id}/dns

Table 4-209 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-210 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-211 Request body parameter

Parameter	Mandatory	Type	Description
dns_type	Yes	String	Domain name type. Currently, only private is supported.

Response Parameters

Status code: 200

Table 4-212 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-213 Response body parameters

Parameter	Type	Description
error_code	String	Error code.

Parameter	Type	Description
error_msg	String	Error message.

Status code: 500

Table 4-214 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Applying for a private domain name

```
PUT https://[endpoint]/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
af315b8e6aaa41799bd9a31f2de15abcin07/dns  
{  
    "dns_type" : "private"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "d5169969-e391-482a-9755-042b2d83ed17"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.29 Changing a Private Domain Name

Function

This API is used to change a private domain name. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/dns

Table 4-215 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-216 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-217 Request body parameter

Parameter	Mandatory	Type	Description
dns_name	Yes	String	Prefix of the new domain name. Value: The name can contain 8 to 63 characters. Only uppercase letters, lowercase letters, and digits are allowed.

Response Parameters

Status code: 200

Table 4-218 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-219 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-220 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing a private domain name

```
POST https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
af315b8e6aaa41799bd9a31f2de15abcin07/dns
```

```
{  
  "dns_name" : "testmodifydnsname"  
}
```

Example Response

Status code: 200

Success.

```
{  
  "job_id" : "d5169969-e391-482a-9755-042b2d83ed17"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.3.30 Querying the Kernel Version

Function

This API is used to query the kernel version of a DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/database-version

Table 4-221 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-222 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-223 Response body parameters

Parameter	Type	Description
datastore	InstanceData baseVersionInfo object	DB version information.
upgrade_flag	Boolean	Whether the version can be upgraded. <ul style="list-style-type: none">• true: The version can be upgraded.• false: The instance cannot be upgraded.

Table 4-224 InstanceDatabaseVersionInfo

Parameter	Type	Description
current_version	String	Current database version.
current_kernel_version	String	Current database kernel version.

Parameter	Type	Description
latest_version	String	Latest database version.
latest_kernel_version	String	Latest kernel version.

Status code: 400**Table 4-225** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-226** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying the kernel version of a DB instance

```
GET https://{endpoint}/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
61a4ea66210545909d74a05c27a7179ein07/database-version
```

Example Response

Status code: 200

Success.

```
{  
  "datastore": {  
    "current_version": "8.0.22",  
    "current_kernel_version": "2.0.28.15",  
    "latest_version": "8.0.22",  
    "latest_kernel_version": "2.0.42.230600"  
  },  
  "upgrade_flag": true  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.3.31 Modifying Auto Scaling Policies

Function

This API is used to modify auto scaling policy. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is in the open beta test (OBT) phase. To use this API, submit a service ticket.

URI

PUT /v3/{project_id}/instances/{instance_id}/auto-scaling/policy

Table 4-227 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-228 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. To obtain the value, call the API for obtaining a user token . After the request is processed, the value of X-Subject-Token in the message header is the token value.
Content-Type	Yes	String	Content type. Value: application/json
X-Language	No	String	Request language type. The default value is en-us . Value range: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-229 Request body parameters

Parameter	Mandatory	Type	Description
status	Yes	String	Whether auto scaling is enabled. Value: <ul style="list-style-type: none">• ON: enabled• OFF: disabled
scaling_strategy	Yes	ScalingStrategyReqInfo object	Auto scaling policy.
monitor_cycle	No	Integer	Observation period, in seconds. During the entire observation period, if the average CPU usage is greater than or equal to the preset value, a scale-up is triggered. Value: 300, 600, 900, or 1800 . This parameter is mandatory when status is set to ON .

Parameter	Mandatory	Type	Description
silence_cycle	No	Integer	Silent period, in seconds. It indicates the minimum interval between two auto scale-up operations or two scale-down operations. Value: 300, 600, 1800, 3600, 7200, 10800, 86400, or 604800 . This parameter is mandatory when status is set to ON .
enlarge_threshold	No	Integer	Average CPU usage (%). Value range: 50 to 100 . This parameter is mandatory when status is set to ON .
max_flavor	No	String	Maximum specifications. This parameter is mandatory when the instance specifications are automatically scaled up or down.
reduce_enabled	No	Boolean	Whether auto-down is enabled. This parameter is mandatory when auto scaling is enabled. • true : enabled • false : disabled
max_read_only_count	No	Integer	Maximum number of read replicas. This parameter is mandatory when read replicas are automatically added or deleted.
read_only_weight	No	Integer	Read weights of read replicas. This parameter is mandatory when read replicas are automatically added or deleted.

Table 4-230 ScalingStrategyReqInfo

Parameter	Mandatory	Type	Description
flavor_switch	Yes	String	Whether instance specifications can be automatically scaled up or down. <ul style="list-style-type: none">• ON: Yes• OFF: No
read_only_switch	Yes	String	Whether read replicas can be automatically added or deleted. To use this function, ensure that there is only one proxy instance. For details about how to create a proxy instance, see Creating a Proxy Instance . <ul style="list-style-type: none">• ON: Yes• OFF: No

Response Parameters

Status code: 200

Table 4-231 Response body parameters

Parameter	Type	Description
instance_id	String	Instance ID.
instance_name	String	Instance name.
switch_status	AutoScalingSwitchStatus object	Switch status.

Table 4-232 AutoScalingSwitchStatus

Parameter	Type	Description
scaling_switch	String	Whether auto scaling is enabled. Value: <ul style="list-style-type: none">• ON: enabled• OFF: disabled

Parameter	Type	Description
flavor_switch	String	Whether instance specifications can be automatically scaled up or down. Value: <ul style="list-style-type: none">• ON: Yes• OFF: No
read_only_switch	String	Whether read replicas can be automatically added or deleted. Value: <ul style="list-style-type: none">• ON: Yes• OFF: No

Status code: 400**Table 4-233** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-234** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Modifying auto scaling policies

```
PUT https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
61a4ea66210545909d74a05c27a7179ein07/auto-scaling/policy
```

```
{  
    "enlarge_threshold": 50,  
    "max_flavor": "gaussdb.mysql.large.x86.4",  
    "max_read_only_count": 2,  
    "monitor_cycle": 300,  
    "read_only_weight": 10,  
    "reduce_enabled": false,  
    "scaling_strategy": {  
        "flavor_switch": "ON",
```

```
        "read_only_switch" : "ON"
    },
    "silence_cycle" : 300,
    "status" : "ON"
}
```

Example Response

Status code: 200

Success.

```
{
    "instance_id" : "61a4ea66210545909d74a05c27a7179ein07",
    "instance_name" : "gauss-test-1",
    "switch_status" : {
        "scaling_switch" : "ON",
        "flavor_switch" : "ON",
        "read_only_switch" : "ON"
    }
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.3.32 Querying Auto Scaling Policies

Function

This API is used to query auto scaling policies. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/auto-scaling/policy

Table 4-235 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-236 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. To obtain the value, call the API for obtaining a user token . After the request is processed, the value of X-Subject-Token in the message header is the token value.
Content-Type	Yes	String	Content type. Value: application/json
X-Language	No	String	Request language type. The default value is en-us . Value range: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-237 Response body parameters

Parameter	Type	Description
id	String	ID of querying auto scaling policies.
instance_id	String	Instance ID.

Parameter	Type	Description
instance_name	String	Instance name.
status	String	Whether auto scaling is enabled. Value: <ul style="list-style-type: none">• ON: enabled• OFF: disabled
monitor_cycle	Integer	Observation period, in seconds. During the entire observation period, if the average CPU usage is greater than or equal to the preset value, a scale-up is triggered.
silence_cycle	Integer	Silent period, in seconds. It indicates the minimum interval between two auto scale-up operations or two scale-down operations.
enlarge_threshold	Integer	Average CPU usage.
max_flavor	String	Maximum specifications.
reduce_enabled	Boolean	Whether auto scale-down is enabled. Value: <ul style="list-style-type: none">• true: enabled• false: disabled
min_flavor	String	Minimum instance specifications.
silence_start_at	String	Start time of the silent period (end time of the last change). The format is yyyy-mm-ddThh:mm:ssZ. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
scaling_strategy	ScalingStrategyInfo object	Auto scaling policy.
max_read_only_count	Integer	Maximum number of read replicas.
min_read_only_count	Integer	Minimum number of read replicas.
read_only_weight	Integer	Read weights of read replicas.

Table 4-238 ScalingStrategyInfo

Parameter	Type	Description
flavor_switch	String	Whether instance specifications can be automatically scaled up or down. <ul style="list-style-type: none">• ON: Yes• OFF: No
read_only_switch	String	Whether read replicas can be automatically added or deleted. <ul style="list-style-type: none">• ON: Yes• OFF: No

Status code: 400**Table 4-239** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-240** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying auto scaling policies

GET https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/instances/61a4ea66210545909d74a05c27a7179ein07/auto-scaling/policy

Example Response

Status code: 200

Success.

- Performing a query after auto scaling is enabled

{
 "id" : "26d8e193-1ea0-4adb-89d0-d1343399d0e7",

```
"instance_id" : "41ff7519e22d44eea6066615fa5b17c7in07",
"instance_name" : "gauss-test-1",
"status" : "ON",
"monitor_cycle" : 300,
"silence_cycle" : 300,
"enlarge_threshold" : 50,
"max_flavor" : "gaussdb.mysql.large.x86.4",
"reduce_enabled" : false,
"min_flavor" : "gaussdb.mysql.medium.x86.4",
"silence_start_at" : "2023-08-31T08:59:09+0000",
"scaling_strategy" : {
    "flavor_switch" : "ON",
    "read_only_switch" : "ON"
},
"max_read_only_count" : 2,
"min_read_only_count" : 1,
"read_only_weight" : 10
}
```

- Performing a query after auto scaling is disabled

```
{
    "id" : null,
    "instance_id" : "41ff7519e22d44eea6066615fa5b17c7in07",
    "instance_name" : "gauss-test-1",
    "status" : "OFF",
    "monitor_cycle" : null,
    "silence_cycle" : null,
    "enlarge_threshold" : null,
    "max_flavor" : null,
    "reduce_enabled" : null,
    "min_flavor" : null,
    "silence_start_at" : "",
    "scaling_strategy" : {
        "flavor_switch" : "",
        "read_only_switch" : ""
    },
    "max_read_only_count" : null,
    "min_read_only_count" : null,
    "read_only_weight" : null
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.3.33 Pre-Checking Resources

Function

This API is used to pre-check resources. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/resource-check

Table 4-241 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-242 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. To obtain the value, call the API for obtaining a user token . After the request is processed, the value of X-Subject-Token in the message header is the token value.
Content-Type	Yes	String	Content type. Value: application/json
X-Language	No	String	Request language type. The default value is en-us . Value range: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-243 Request body parameters

Parameter	Mandatory	Type	Description
action	Yes	String	Verification type. <ul style="list-style-type: none">● createInstance: pre-checking resources during instance creation● createReadOnlyNode: pre-checking resources during read replica creation● resizeFlavor: pre-checking resources during instance specification change
resource	Yes	CheckResourceInfo object	Resource information.

Table 4-244 CheckResourceInfo

Parameter	Mandatory	Type	Description
enterprise_project_id	No	String	Enterprise project ID. This parameter is mandatory when action is set to createInstance .
instance_num	No	Integer	Number of instances. This parameter is mandatory when action is set to createInstance .
mode	No	String	Instance type. Its value is Cluster . This parameter is mandatory when action is set to createInstance .
availability_zone_mode	No	String	AZ type. The value can be single or multi . This parameter is mandatory when action is set to createInstance .
node_num	No	Integer	Number of nodes. This parameter is mandatory when action is set to createInstance or createReadOnlyNode .

Parameter	Mandatory	Type	Description
flavor_ref	No	String	Specification code. This parameter is mandatory when action is set to createInstance or resizeFlavor .
availability_zone	No	String	AZ code.
subnet_id	No	String	Subnet ID. This parameter is mandatory when action is set to createInstance .
instance_id	No	String	Instance ID. This parameter is mandatory when action is set to createReadOnlyNode or resizeFlavor .

Response Parameters

Status code: 200

Table 4-245 Response body parameters

Parameter	Type	Description
result	Boolean	Returned result. <ul style="list-style-type: none">• true: The check is passed.• false: The check fails.

Status code: 400

Table 4-246 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-247 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- Pre-checking resources during instance creation

POST [https://\[endpoint\]/v3/97b026aa9cc4417888c14c84a1ad9860/resource-check](https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/resource-check)

```
{  
    "action" : "createInstance",  
    "resource" : {  
        "enterprise_project_id" : 0,  
        "instance_num" : 1,  
        "mode" : "Cluster",  
        "availability_zone_mode" : "single",  
        "node_num" : 2,  
        "flavor_ref" : "gaussdb.mysql.xlarge.x86.4",  
        "availability_zone" : "cn-southwest-244b",  
        "subnet_id" : "1e9f71dd-9192-4c0d-9739-161d8dcca68c"  
    }  
}
```

- Pre-checking resources during read replica creation

POST [https://\[endpoint\]/v3/97b026aa9cc4417888c14c84a1ad9860/resource-check](https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/resource-check)

```
{  
    "action" : "createReadonlyNode",  
    "resource" : {  
        "instance_id" : "376e0847a2224e95afcd3e607eccd544in07",  
        "node_num" : 1  
    }  
}
```

- Pre-checking resources during instance specification change

POST [https://\[endpoint\]/v3/97b026aa9cc4417888c14c84a1ad9860/resource-check](https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/resource-check)

```
{  
    "action" : "resizeFlavor",  
    "resource" : {  
        "instance_id" : "376e0847a2224e95afcd3e607eccd544in07",  
        "flavor_ref" : "gaussdb.mysql.xlarge.x86.4"  
    }  
}
```

Example Response

Status code: 200

Success.

```
{  
    "result" : true  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.4 Backup Management

4.4.1 Configuring a Same-Region Backup Policy

Function

This API is used to configure a same-region backup policy. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/backups/policy/update

Table 4-248 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-249 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-250 Request body parameters

Parameter	Mandatory	Type	Description
backup_policy	Yes	MysqlBackup Policy object	Database backup policy.

Table 4-251 MysqlBackupPolicy

Parameter	Mandatory	Type	Description
start_time	Yes	String	<p>Backup time window. Automated backups will be triggered during the backup time window.</p> <p>The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format.</p> <ul style="list-style-type: none">• The HH value must be 1 greater than the hh value.• The values of mm and MM must be the same and must be set to 00. <p>Example value: 21:00-22:00</p>
keep_days	Yes	Integer	<p>Backup retention days.</p> <p>Value: 1 to 732</p>
period	Yes	String	<p>Backup cycle configuration. Data will be automatically backed up on the selected days every week.</p> <p>Value range: The value is a number separated by commas (,), indicating the days of the week.</p> <p>For example, the value 1,2,3,4 indicates that the backup period is Monday, Tuesday, Wednesday, and Thursday.</p>

Parameter	Mandatory	Type	Description
retention_number_backup_level1	No	Integer	<p>Number of retained level-1 backups. The default value is 0.</p> <ul style="list-style-type: none"> • This parameter is mandatory when the level-1 backup function is enabled. <p>Value:</p> <ul style="list-style-type: none"> - 0 - 1 <ul style="list-style-type: none"> • This parameter is unavailable when the level-1 backup function is disabled.

Response Parameters

Status code: 200

Table 4-252 Response body parameters

Parameter	Type	Description
status	String	<p>Status.</p> <p>Value:</p> <ul style="list-style-type: none"> • BUILDING: Modification in progress • COMPLETED: Modification completed • FAILED: Modification failed
instance_id	String	Instance ID.
instance_name	String	Instance name.

Status code: 400

Table 4-253 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-254 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Modifying the automated backup policy of the DB instance (Data is backed up from 19:00 to 20:00 every Monday to Friday. Backup files are stored for seven days.)

```
PUT https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
ba62a0b83a1b42bfab275829d86ac0fdin07/backups/policy/update  
{  
    "backup_policy" : {  
        "keep_days" : 7,  
        "start_time" : "19:00-20:00",  
        "period" : "1,2,3,4,5"  
    }  
}
```

Example Response

Status code: 200

Success.

```
{  
    "status" : "COMPLETED",  
    "instance_id" : "ba62a0b83a1b42bfab275829d86ac0fdin07",  
    "instance_name" : "gauss-mysql"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.2 Creating a Manual Backup

Function

This API is used to create a manual backup. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/backups/create

Table 4-255 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-256 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-257 Request body parameters

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Parameter	Mandatory	Type	Description
name	Yes	String	Backup name. Value: The name must start with a letter and consist of 4 to 64 characters. Only letters (case-sensitive), digits, hyphens (-), and underscores (_) are allowed.
description	No	String	Backup description. Value: It contains a maximum of 256 characters and cannot contain the special characters (>!<"&'=).

Response Parameters

Status code: 201

Table 4-258 Response body parameters

Parameter	Type	Description
backup	backup object	Backup information.
job_id	String	Task ID.

Table 4-259 backup

Parameter	Type	Description
id	String	Backup ID.
name	String	Backup name.
description	String	Backup description.
begin_time	String	Backup start time in the "yyyy-mm-ddThh:mm:ssZ" format, where "T" indicates the start time of the time field, and "Z" indicates the time zone offset.
status	String	Backup status. Value: BUILDING: Backup in progress

Parameter	Type	Description
type	String	Backup type. Value: manual : manual full backup
instance_id	String	Instance ID.

Status code: 400**Table 4-260** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-261** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Creating a manual backup

```
POST https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/backups/create
{
  "instance_id" : "07033b125fd94a8a96896f8bcfee6ddain07",
  "name" : "backup-1",
  "description": "Manual backup"
}
```

Example Response

Status code: 201

Success.

```
{
  "backup" : {
    "id" : "2f4ddb93-b901-4b08-93d8-1d2e472f30fe",
    "name" : "backup-1",
    "description": "Manual backup"
    "begin_time" : "2020-07-07T01:17:05+0800",
    "status" : "BUILDING",
```

```
        "type" : "manual",
        "instance_id" : "07033b125fd94a8a96896f8bcfee6ddain07"
    },
    "job_id" : "e0fbbfc8-1ac4-4721-b9e9-7dd685c5bdd7"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.3 Querying Full Backups

Function

This API is used to query backups according to search criteria. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/backups

Table 4-262 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-263 Query parameters

Parameter	Mandatory	Type	Description
instance_id	No	String	Instance ID.
backup_id	No	String	Backup ID. To obtain the value, see the response parameter backup returned in Creating a Manual Backup .

Parameter	Mandatory	Type	Description
backup_type	No	String	Backup type. Value: <ul style="list-style-type: none">• auto: automated full backup• manual: manual full backup
offset	No	String	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	String	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
begin_time	No	String	Query start time. The format is "yyyy-mm-ddThh:mm:ssZ". T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
end_time	No	String	Query end time. The format is "yyyy-mm-ddThh:mm:ssZ" and the end time must be later than the start time. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
name	No	String	Backup name.
instance_name	No	String	Instance name.

Request Parameters

Table 4-264 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-265 Response body parameters

Parameter	Type	Description
backups	Array of backups objects	Backup information.
total_count	Long	Total number of backup files.

Table 4-266 backups

Parameter	Type	Description
id	String	Backup ID.
name	String	Backup name.

Parameter	Type	Description
begin_time	String	Backup start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
end_time	String	Backup end time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
status	String	Backup status. Value: <ul style="list-style-type: none">• BUILDING: Backup in progress• COMPLETED: Backup completed• FAILED: Backup failed• AVAILABLE: Backup available
take_up_time	Integer	Backup duration in minutes.
type	String	Backup type. Value: <ul style="list-style-type: none">• auto: automated full backup• manual: manual full backup
size	Long	Backup size in MB.
datastore	MysqlDataset object	Database information.
instance_id	String	Instance ID.
instance_name	String	Instance name.
backup_level	String	Backup level. This parameter is returned when the level-1 backup function is enabled. Value: <ul style="list-style-type: none">• 0: Backup being created or creation failed• 1: level-1 backup• 2: level-2 backup
description	String	Description of the backup file.

Table 4-267 MysqlDatastore

Parameter	Type	Description
type	String	DB engine.
version	String	DB version. For details about supported DB versions, see Querying Version Information About a DB Engine .

Status code: 400**Table 4-268** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-269** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying automated backups generated from July 6, 2020 to July 16, 2020

```
GET https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/backups?  
instance_id=43e4feaab48f11e89039fa163eba7e4br01&backup_id=c0cf155c7b7423a9d30f0175998b63bb0  
1&backup_type=auto&offset=0&limit=10&begin_time=2020-07-06T10:41:14+0800&end_time=2020-07-16T1  
0:41:14+0800
```

Example Response

Status code: 200

Success.

```
{  
  "backups": [ {  
    "id": "1fe4feaab48f11e6654hfa163eba87e4b66u",  
    "name": "GaussDBforMySQL-gauss-e747-20200705185048266",  
    "begin_time": "2018-08-06T12:41:14+0800",  
    "end_time": "2018-08-06T12:45:14+0800",  
  } ]  
}
```

```
"take_up_time" : 2,  
"status" : "COMPLETED",  
"type" : "auto",  
"size" : 2803,  
"datastore" : {  
    "type" : "GaussDB(for MySQL)",  
    "version" : "8.0"  
},  
"instance_id" : "43e4feaab48f11e89039fa163ebaa7e4br01",  
"instance_name" : "GaussDBforMySQL-gauss-e747",  
"backup_level" : "2"  
} ],  
"total_count" : 1  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.4 Querying an Automated Backup Policy

Function

This API is used to query an automated backup policy. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/backups/policy

Table 4-270 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-271 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-272 Response body parameters

Parameter	Type	Description
backup_policy	BackupPolicy object	Backup policy information.

Table 4-273 BackupPolicy

Parameter	Type	Description
keep_days	Integer	Backup retention days. Value: 1 to 732
start_time	String	Backup time window. Automated backups will be triggered during the backup time window. The value must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format.

Parameter	Type	Description
period	String	Backup cycle configuration. Data will be automatically backed up on the selected days every week. The value is a number separated by commas (,), indicating the days of the week.
retention_num_backup_level1	Integer	Number of retained level-1 backups. This parameter is returned when level-1 backup is enabled.

Status code: 400**Table 4-274** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-275** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying the automated backup policy of a DB instance

```
GET https://[endpoint]/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/61a4ea66210545909d74a05c27a7179ein07/backups/policy
```

Example Response

Status code: 200

Success.

```
{  
  "backup_policy": {  
    "keep_days": "7",  
    "start_time": "19:00-20:00",  
    "period": "1,2",  
    "retention_num_backup_level1": 1  
}
```

{}

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.5 Deleting a Manual Backup

Function

This API is used to delete a manual backup. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/backups/{backup_id}

Table 4-276 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
backup_id	Yes	String	Backup file ID. To obtain this value, see Querying Full Backups .

Request Parameters

Table 4-277 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200**Table 4-278** Response body parameters

Parameter	Type	Description
backup_id	String	Backup ID.
backup_name	String	Backup name.

Status code: 400**Table 4-279** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-280 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting a manual backup

```
DELETE https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/backups/  
1fe4feaab48f11e6654hfa163eba87e4b66
```

Example Response

Status code: 200

Success.

```
{  
    "backup_id" : "b1182ccdda034f2b9535f3dca5c47e71br07",  
    "backup_name" : "backup-f3c1"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.6 Restoring Data to the Original Instance or an Existing Instance

Function

This API is used to restore data to the original instance or an existing instance.
Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

DB instances will not be displayed unless they have the same DB engine type, version, and table name case sensitivity as the original DB instance.

URI

POST /v3/{project_id}/instances/restore

Table 4-281 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-282 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-283 Request body parameters

Parameter	Mandatory	Type	Description
target_instance_id	Yes	String	Target instance ID.
source_instance_id	Yes	String	Source instance ID.

Parameter	Mandatory	Type	Description
type	Yes	String	Restoration type. Value: <ul style="list-style-type: none">• backup: indicates restoration from backup files. backup_id is mandatory when type is not mandatory.• timestamp: indicates point-in-time restoration. In this mode, restore_time is mandatory when type is mandatory.
backup_id	No	String	ID of the backup to be restored. This parameter must be specified when the backup file is used for restoration. To obtain this value, see Querying Full Backups .
restore_time	No	Long	Time point of data restoration in the UNIX timestamp format. The unit is millisecond and the time zone is UTC.

Response Parameters

Status code: 200

Table 4-284 Response body parameters

Parameter	Type	Description
job_id	String	Workflow ID.

Status code: 400

Table 4-285 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-286 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- Restoring data to the original instance using a backup file
POST `https://{{endpoint}}/v3/054e292c9880d4992f02c0196d3ea468/instances/restore`

```
{  
    "target_instance_id": "7033e7c3cf93438797d44ad7ae0a7d95in07",  
    "source_instance_id": "690e08a7c3854c218df0e59de3b0c6cein07",  
    "backup_id": "7ffbf305376b4cbea0ae491257b6aaf9br07",  
    "type": "backup"  
}
```
- Restoring data to the original instance through PITR
POST `https://{{endpoint}}/v3/054e292c9880d4992f02c0196d3ea468/instances/restore`

```
{  
    "target_instance_id": "7033e7c3cf93438797d44ad7ae0a7d95in07",  
    "source_instance_id": "690e08a7c3854c218df0e59de3b0c6cein07",  
    "restore_time": 1673852043000,  
    "type": "timestamp"  
}
```
- Restoring data to an existing instance using a backup file
POST `https://{{endpoint}}/v3/054e292c9880d4992f02c0196d3ea468/instances/restore`

```
{  
    "target_instance_id": "7033e7c3cf93438797d44ad7ae0a7d95in07",  
    "source_instance_id": "690e08a7c3854c218df0e59de3b0c6cein07",  
    "backup_id": "be4ddfd7e2b94640b5e2cb44efb30b22br07",  
    "type": "backup"  
}
```
- Restoring data to an existing instance through PITR
POST `https://{{endpoint}}/v3/054e292c9880d4992f02c0196d3ea468/instances/restore`

```
{  
    "target_instance_id": "7033e7c3cf93438797d44ad7ae0a7d95in07",  
    "source_instance_id": "690e08a7c3854c218df0e59de3b0c6cein07",  
    "restore_time": 1673852043000,  
    "type": "timestamp"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id": "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.7 Querying the Restoration Time Range

Function

This API is used to query the restoration time range of an instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/restore-time

Table 4-287 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID of a tenant in a project.

Table 4-288 Query parameters

Parameter	Mandatory	Type	Description
date	No	String	Date to be queried. The value is in the "yyyy-mm-dd" format, and the time zone is UTC.

Request Parameters

Table 4-289 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-290 Response body parameters

Parameter	Type	Description
restore_times	Array of RestoreTimeInfo objects	Restoration time ranges.

Table 4-291 RestoreTimeInfo

Parameter	Type	Description
start_time	Integer	Start time of the restoration time range in the UNIX timestamp format. The unit is millisecond and the time zone is UTC.
end_time	Integer	End time of the restoration time range in the UNIX timestamp format. The unit is millisecond and the time zone is UTC.

Status code: 400

Table 4-292 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-293** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying the restoration time range of the DB instance on January 31, 2023

```
GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
096c0fc43e804757b59946b80dc27f8bin07/restore-time?date=2023-01-31
```

Example Response

Status code: 200

Success.

```
{  
  "restore_times" : [ {  
    "start_time" : 1675149246000,  
    "end_time" : 1675094400000  
  } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.8 Enabling or Disabling Encrypted Backup

Function

This API is used to enable or disable encrypted backup. Before calling this API:

- Learn how to [authorize and authenticate](#) it.

- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/backups/encryption

Table 4-294 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-295 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">en-uszh-cn

Table 4-296 Request body parameters

Parameter	Mandatory	Type	Description
encryption_status	Yes	String	Whether to enable or disable encrypted backup. Value (case insensitive): <ul style="list-style-type: none">• on: Enabling encrypted backup• off: Disabling encrypted backup
type	No	String	Encryption type. Currently, only kms (case-insensitive) is supported. This parameter is mandatory when encrypted backup is enabled and is not required when encrypted backup is disabled.
kms_key_id	No	String	KMS ID. This parameter is mandatory when encrypted backup is enabled and is not required when encrypted backup is disabled. To obtain the value, see the response parameter key_id in the API for creating a key .

Response Parameters

Status code: 200

Table 4-297 Response body parameters

Parameter	Type	Description
encryption_status	String	Whether encrypted backup is enabled or disabled. Value: <ul style="list-style-type: none">• on: Encrypted backup is enabled• off: Encrypted backup is disabled.

Status code: 400

Table 4-298 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-299** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- Enabling encrypted backup
POST https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/7033e7c3cf93438797d44ad7ae0a7d95in07/backups/encryption{
 "type" : "kms",
 "kms_key_id" : "b82fa43f-f6e8-4ec4-9c31-231bc547c526",
 "encryption_status" : "on"
}
- Disabling encrypted backup
POST https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/7033e7c3cf93438797d44ad7ae0a7d95in07/backups/encryption{
 "encryption_status" : "off"
}

Example Response

Status code: 200

Success.

{
 "encryption_status" : "on"
}

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.9 Checking Whether Encrypted Backup Is Enabled

Function

This API is used to check whether encrypted backup is enabled. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/backups/encryption

Table 4-300 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-301 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-302 Response body parameters

Parameter	Type	Description
encryption_status	String	Whether encrypted backup is enabled or disabled. Value: <ul style="list-style-type: none">• on: Encrypted backup is enabled.• off: Encrypted backup is disabled.

Status code: 400

Table 4-303 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-304 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Checking whether encrypted backup is enabled

```
GET https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
7033e7c3cf93438797d44ad7ae0a7d95in07/backups/encryption
```

Example Response

Status code: 200

Success.

```
{  
    "encryption_status" : "on"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.10 Querying Incremental Backups

Function

This API is used to query incremental backups. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/incremental-backups

Table 4-305 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-306 Query parameters

Parameter	Mandatory	Type	Description
offset	No	String	Index offset. If offset is set to <i>N</i> , the resource query starts from the <i>N+1</i> piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.

Parameter	Mandatory	Type	Description
limit	No	String	Number of records to be queried. Value: 10 (default value), 20 , or 50 .
begin_time	No	String	Query start time. The format is "yyyy-mm-ddThh:mm:ssZ". T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 . When begin_time is not empty, end_time is mandatory.
end_time	No	String	Query end time. The format is "yyyy-mm-ddThh:mm:ssZ" and the end time must be later than the start time. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 . When end_time is not empty, begin_time is mandatory.

Request Parameters

Table 4-307 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-308 Response body parameters

Parameter	Type	Description
backups	Array of IncrementalBackups objects	Backup information.
total_count	Long	Total number of backup files.

Table 4-309 IncrementalBackups

Parameter	Type	Description
id	String	Backup ID.
name	String	Backup name.
begin_time	String	Backup start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
end_time	String	Backup end time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
size	Number	Backup size, in KB.
instance_id	String	Instance ID.

Status code: 400**Table 4-310** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-311** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying incremental backups generated from July 6, 2022 to July 16, 2022

```
GET https://{endpoint}/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
61a4ea66210545909d74a05c27a7179ein07/incremental-backups?  
offset=0&limit=10&begin_time=2022-07-06T10:41:14+0800&end_time=2022-07-16T10:41:14+0800
```

Example Response

Status code: 200

Success.

```
{  
  "backups" : [ {  
    "id" : "f0d2aea28d26t4848b8c84ed3fea1822fbr07",  
    "name" : "GaussDBforMySQL-20230728181555006",  
    "begin_time" : "2022-07-07T12:41:14+0800",  
    "end_time" : "2022-07-08T12:45:14+0800",  
    "size" : 0.109375,  
    "instance_id" : "61a4ea66210545909d74a05c27a7179ein07"  
  } ],  
  "total_count" : 1  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.11 Configuring a Cross-Region Backup Policy

Function

This API is used to configure a cross-region backup policy. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/backups/offsite-policy

Table 4-312 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-313 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-314 Request body parameter

Parameter	Mandatory	Type	Description
backup_policy	Yes	UpdateBackupOffsitePolicyInfo object	Backup policy information.

Table 4-315 UpdateBackupOffsitePolicyInfo

Parameter	Mandatory	Type	Description
open_auto_backup	Yes	Boolean	<p>Whether to enable cross-region full backup.</p> <ul style="list-style-type: none">• true: Enable cross-region full backup.• false: Disable cross-region full backup.
open_incremental_backup	Yes	Boolean	<p>Whether to enable cross-region incremental backup.</p> <ul style="list-style-type: none">• true: Enable cross-region incremental backup. This function can be enabled only when open_auto_backup is enabled.• false: Disable cross-region incremental backup.
destination_project_id	Yes	String	<p>Target project ID for the cross-region backup policy.</p> <p>Project ID of a tenant in a region.</p> <p>To obtain this value, see Obtaining a Project ID.</p>
destination_region	Yes	String	Target region for the cross-region backup policy.
keep_days	Yes	Integer	Backup retention days. Value: 1 to 1825

Response Parameters

Status code: 200

Table 4-316 Response body parameters

Parameter	Type	Description
result	String	Returned result.

Status code: 400**Table 4-317** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-318** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Configuring a cross-region backup policy

```
PUT https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
61a4ea66210545909d74a05c27a7179ein07/backups/offsite-policy  
  
{  
    "backup_policy" : {  
        "open_auto_backup" : true,  
        "open_incremental_backup" : false,  
        "destination_project_id" : "fd710c89089a448aa2e666ab15817090",  
        "destination_region" : "cn-north-7",  
        "keep_days" : 1  
    }  
}
```

Example Response

Status code: 200

Success.

```
{  
    "result" : "success"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.12 Restoring Tables to a Specified Point in Time

Function

This API is used to restore tables to a specified point in time. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/backups/restore/tables

Table 4-319 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-320 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-321 Request body parameter

Parameter	Mandatory	Type	Description
restore_time	Yes	String	Backup time, in timestamp format.
restore_tables	Yes	Array of CreateRestoreDatabaseTableInfo objects	Database information.
last_table_info	No	String	Whether the data is restored to the most recent table. The default value is false . <ul style="list-style-type: none">• true: most recent table.• false (default value): time-specific table

Table 4-322 CreateRestoreDatabaseTableInfo

Parameter	Mandatory	Type	Description
database	Yes	String	Database name.
tables	Yes	Array of CreateRestoreTableInfo objects	Table information.

Table 4-323 CreateRestoreTableInfo

Parameter	Mandatory	Type	Description
old_name	Yes	String	Original table name before the restoration.

Parameter	Mandatory	Type	Description
new_name	Yes	String	Table name after the restoration.

Response Parameters

Status code: 200

Table 4-324 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-325 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-326 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Restoring tables to a point in time

```
POST https://{endpoint}/v3/97b026aa9cc4417888c14c84a1ad9860/instances/61a4ea66210545909d74a05c27a7179ein07/backups/restore/tables
{
  "restore_time" : 1690890940000,
  "last_table_info" : true,
  "restore_tables" : [ {
    "database" : "test_db_1",
    "tables" : [ {
      "new_name" : "t3_1690899914000",
```

```
        "old_name" : "t3"
    }]
}
}
```

Example Response

Status code: 200

Success.

```
{
  "job_id" : "9c77973c-9332-4fbe-bb4d-b76760dbc9b2"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.4.13 Querying Tables for Table-level Point-in-Time Recovery

Function

This API is used to query available tables for table-level point-in-time recovery (PITR). Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/backups/restore/tables

Table 4-327 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-328 Query parameters

Parameter	Mandatory	Type	Description
restore_time	Yes	String	Backup time, in timestamp format. To obtain this value, see Querying the Restoration Time Range .
last_table_info	Yes	String	Whether data is restored to the most recent table. <ul style="list-style-type: none">• true: most recent table• false: time-specific table
database_name	No	String	Database name, which is used for fuzzy match.
table_name	No	String	Table name, which is used for fuzzy match.

Request Parameters

Table 4-329 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-330 Response body parameters

Parameter	Type	Description
total_databases	Integer	Total number of databases.
databases	Array of RestoreDatabaseInfos objects	Database information.

Table 4-331 RestoreDatabaseInfos

Parameter	Type	Description
name	String	Database name.
total_tables	Integer	Total number of tables.
tables	Array of RestoreDatabaseTableInfo objects	Table information.

Table 4-332 RestoreDatabaseTableInfo

Parameter	Type	Description
name	String	Table name.

Status code: 400**Table 4-333** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-334 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying tables for table-level point-in-time recovery

```
GET https://{endpoint}/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
61a4ea66210545909d74a05c27a7179ein07/backups/restore/tables?  
database_name=test&last_table_info=true&restore_time=1690890940000&table_name=t
```

Example Response

Status code: 200

Success.

```
{  
    "total_databases": 1,  
    "databases": [ {  
        "name": "test_db_1",  
        "total_tables": 1,  
        "tables": [ {  
            "name": "t3"  
        } ]  
    } ]  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.5 Parameter Template Management

4.5.1 Querying Parameter Templates

Function

This API is used to query parameter templates, including all databases' default and custom parameter templates. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/configurations

Table 4-335 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-336 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-337 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-338 Response body parameters

Parameter	Type	Description
configurations	Array of ConfigurationSummary objects	Parameter template information.
total_count	Integer	Total number of parameter templates.

Table 4-339 ConfigurationSummary

Parameter	Type	Description
id	String	Parameter template ID.
name	String	Parameter template name.
description	String	Parameter template description.
datastore_version_name	String	DB version.

Parameter	Type	Description
datastore_name	String	Database name.
created	String	Creation time in the "yyyy-MM-ddTHH:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
updated	String	Update time in the "yyyy-MM-ddTHH:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
user_defined	Boolean	Whether the parameter template is a custom template. Value: <ul style="list-style-type: none">• false: The parameter template is a default template.• true: The parameter template is a custom template.

Status code: 400**Table 4-340** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-341** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying parameter templates

GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/configurations

Example Response

Status code: 200

Success.

```
{  
    "total_count": 1,  
    "configurations": [  
        {  
            "id": "887ea0d1bb0843c49e8d8e5a09a95652pr07",  
            "name": "configuration_test",  
            "description": "configuration_test",  
            "datastore_version_name": "8.0",  
            "datastore_name": "GaussDB(for MySQL)",  
            "created": "2019-05-15T11:53:34+0000",  
            "updated": "2019-05-15T11:53:34+0000",  
            "user_defined": true  
        }, {  
            "id": "3bc1e9cc0d34404b9225ed7a58fb284ep07",  
            "name": "Default-GaussDBforMySQL",  
            "description": "Default parameter template for GaussDBforMySQL",  
            "datastore_version_name": "8.0",  
            "datastore_name": "GaussDB(for MySQL)",  
            "created": "2019-05-27T03:38:51+0000",  
            "updated": "2019-05-27T03:38:51+0000",  
            "user_defined": false  
        } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.2 Creating a Parameter Template

Function

This API is used to create a parameter template. The following information needs to be configured: template name, description, DB engine version, and parameter values. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

- This API is available only for GaussDB(for MySQL) primary/standby instances (dedicated edition).
- The name of the custom parameter template is case-sensitive and must be different from the name of an existing or a default parameter template.

- The value of **parameter_values** in the custom parameter template must be within the default value range of the specified database version.

URI

POST /v3/{project_id}/configurations

Table 4-342 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-343 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-344 Request body parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Parameter template name. Value: The template name can contain 1 to 64 characters. Only letters (case-sensitive), digits, hyphens (-), underscores (_), and periods (.) are allowed.
description	No	String	Parameter template description. The value is left blank by default. Value: The description can consist of up to 256 characters, and cannot contain the carriage return characters or special characters (!<='>&).
parameter_values	No	Map<String, String>	Mapping between parameter names and parameter values. You can specify parameter values based on a default parameter template.
datastore	No	DatastoreResult object	Database object.

Table 4-345 DatastoreResult

Parameter	Mandatory	Type	Description
type	Yes	String	DB engine. Currently, only gaussdb-mysql is supported.
version	Yes	String	DB version. For details about supported DB versions, see Querying Version Information About a DB Engine .

Response Parameters

Status code: 200

Table 4-346 Response body parameters

Parameter	Type	Description
configurations	ConfigurationSummary2 object	Parameter template information.

Table 4-347 ConfigurationSummary2

Parameter	Type	Description
id	String	Parameter template ID.
name	String	Parameter template name.
description	String	Parameter template description.
datastore	DatastoreResult object	Database object.
created	String	Creation time in the "yyyy-MM-ddTHH:mm:ssZ" format. T is the separator between calendar and hourly notation of time. Z indicates the time zone offset.
updated	String	Update time in the "yyyy-MM-ddTHH:mm:ssZ" format. T is the separator between calendar and hourly notation of time. Z indicates the time zone offset.

Table 4-348 DatastoreResult

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.
version	String	DB version. For details about supported DB versions, see Querying Version Information About a DB Engine .

Status code: 400

Table 4-349 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-350** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Creating a parameter template (There are up to 10 concurrent connections for the account.)

```
POST https://{endpoint}/v3/056538411200d4cd2f79c003c7606412/configurations
{
    "name" : "myparameter",
    "description" : "parameter1",
    "datastore" : {
        "type" : "gaussdb-mysql",
        "version" : "8.0"
    },
    "parameter_values" : {
        "max_user_connections" : "10"
    }
}
```

Example Response

Status code: 200

Success.

```
{
    "configurations" : {
        "id" : "887ea0d1bb0843c49e8d8e5a09a95652pr07",
        "name" : "myparameter",
        "description" : "parameter1",
        "datastore" : {
            "type" : "gaussdb-mysql",
            "version" : "8.0"
        },
        "created" : "2022-05-15T11:53:34+0000",
        "updated" : "2022-05-15T11:53:34+0000"
    }
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.3 Deleting a Parameter Template

Function

This API is used to delete a specified parameter template. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

- This API is suitable only for GaussDB(for MySQL) instances.
- Default parameter templates cannot be deleted.

URI

DELETE /v3/{project_id}/configurations/{configuration_id}

Table 4-351 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
configuration_id	Yes	String	Parameter template ID.

Request Parameters

Table 4-352 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-353 Response body parameters

Parameter	Type	Description
configuration_id	String	Parameter template ID.
configuration_name	String	Parameter template name.

Status code: 400

Table 4-354 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-355 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting a parameter template

```
DELETE https://[endpoint]/v3/056538411200d4cd2f79c003c7606412/configurations/  
43570e0de32e40c5a15f831aa5ce4176pr07
```

Example Response

Status code: 200

Success.

```
{  
  "configuration_id" : "887ea0d1bb0843c49e8d8e5a09a95652pr07",  
  "configuration_name" : "myparameter"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.4 Obtaining Details About a Parameter Template

Function

This API is used to obtain parameter details of a specified parameter template.
Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is available only for GaussDB(for MySQL) primary/standby instances (dedicated edition).

URI

GET /v3/{project_id}/configurations/{configuration_id}

Table 4-356 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
configuration_id	Yes	String	Parameter template ID.

Request Parameters

Table 4-357 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-358 Response body parameters

Parameter	Type	Description
configurations	ConfigurationSummary2 object	Parameter template information.

Parameter	Type	Description
parameter_values	Map<String, String>	Mapping between parameter names and parameter values. You can specify parameter values based on a default parameter template.

Table 4-359 ConfigurationSummary2

Parameter	Type	Description
id	String	Parameter template ID.
name	String	Parameter template name.
description	String	Parameter template description.
datastore	DatastoreResult object	Database object.
created	String	Creation time in the "yyyy-MM-ddTHH:mm:ssZ" format. T is the separator between calendar and hourly notation of time. Z indicates the time zone offset.
updated	String	Update time in the "yyyy-MM-ddTHH:mm:ssZ" format. T is the separator between calendar and hourly notation of time. Z indicates the time zone offset.

Table 4-360 DatastoreResult

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.
version	String	DB version. To obtain details about supported DB engine versions, call the API for querying the DB engine versions .

Status code: 400**Table 4-361 Response body parameters**

Parameter	Type	Description
error_code	String	Error code.

Parameter	Type	Description
error_msg	String	Error message.

Status code: 500**Table 4-362** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Obtaining details about a parameter template

```
GET https://{endpoint}/v3/0549b4a43100d4f32f51c01c2fe4acdb/configurations/  
7a8d539ba30f43adaf1b16d08b1df4bdpr07
```

Example Response

Status code: 200

Success.

```
{  
  "configurations" : {  
    "id" : "887ea0d1bb0843c49e8d8e5a09a95652pr07",  
    "name" : "myparameter",  
    "description" : "parameter1",  
    "datastore" : {  
      "type" : "gaussdb-mysql",  
      "version" : "8.0"  
    },  
    "created" : "2022-05-15T11:53:34+0000",  
    "updated" : "2022-05-15T11:53:34+0000"  
  },  
  "parameter_values" : {  
    "binlog_rows_query_log_events" : "OFF",  
    "mount_vip_when_failover" : "ON",  
    "log-bin" : "ON",  
    "gtid_mode" : "ON",  
    "enforce_gtid_consistency" : "ON",  
    "innodb_online_alter_log_max_size" : "134217728",  
    "binlog_gtid_simple_recovery" : "ON",  
    "max_user_connections" : "10"  
  }  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.5 Modifying Parameters in a Parameter Template

Function

This API is used to modify parameters in a specified parameter template, including parameter names, descriptions, and values. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

- This API is available only for GaussDB(for MySQL) primary/standby instances (dedicated edition).
- Default parameter templates cannot be modified.
- The name of the modified parameter template must be different from that of a default parameter template.
- The parameter values to be modified must be within the default value range of the specified database version.

URI

PUT /v3/{project_id}/configurations/{configuration_id}

Table 4-363 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
configuration_id	Yes	String	Parameter template ID.

Request Parameters

Table 4-364 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-365 Request body parameters

Parameter	Mandatory	Type	Description
name	No	String	Parameter template name. Value: The template name can contain 1 to 64 characters. Only letters (case-sensitive), digits, hyphens (-), underscores (_), and periods (.) are allowed. The parameter template description, parameter name, and parameter value mapping cannot be empty at the same time.

Parameter	Mandatory	Type	Description
description	No	String	Parameter template description. The value is left blank by default. Value: The description can consist of up to 256 characters, and cannot contain the carriage return characters or special characters (!<='>&).
parameter_values	No	Map<String, String>	Mapping between parameter names and parameter values. You can specify parameter values based on a default parameter template. If this parameter is not specified, the original parameter information is retained.

Response Parameters

Status code: 200

Table 4-366 Response body parameters

Parameter	Type	Description
job_id	String	Task ID for modifying the parameter template.

Status code: 400

Table 4-367 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-368 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Modifying parameters in a parameter template

```
PUT https://'{endpoint}'/v3/0549b4a43100d4f32f51c01c2fe4acdb/configurations/  
7a8d539ba30f43adaf1b16d08b1df4bdpr07  
{  
    "parameter_values" : {  
        "max_user_connections" : "4"  
    }  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "f6cb21fe-186a-4931-b20d-764ced1f1f6b"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.6 Applying a Parameter Template

Function

This API is used to apply a parameter template to a specified DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

```
PUT /v3/{project_id}/configurations/{configuration_id}/apply
```

Table 4-369 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
configuration_id	Yes	String	Parameter template ID.

Request Parameters

Table 4-370 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-371 Request body parameter

Parameter	Mandatory	Type	Description
instance_ids	Yes	Array of strings	Instance IDs. Up to 10 instance IDs can be returned.

Response Parameters

Status code: 200

Table 4-372 Response body parameters

Parameter	Type	Description
job_id	String	Task ID for applying a parameter template.

Status code: 400**Table 4-373** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-374** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Applying a parameter template

```
PUT https://{endpoint}/v3/0549b4a43100d4f32f51c01c2fe4acdb/configurations/  
7a8d539ba30f43adaf1b16d08b1df4bdpr07/apply  
{  
    "instance_ids" : "1c3f12d626824d4ca357104def25a455in07"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "bf26cf3c-d046-4080-bb45-f114be7afa5f"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.7 Replicating a Parameter Template

Function

This API is used to replicate a parameter template. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/configurations/{configuration_id}/copy

Table 4-375 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
configuration_id	Yes	String	Parameter template ID. To obtain this value, see Querying Parameter Templates . After the request is processed, the value of id in the response body is the value of configuration_id .

Request Parameters

Table 4-376 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-377 Request body parameter

Parameter	Mandatory	Type	Description
name	Yes	String	Name of the replicated parameter template. The template name can contain 1 to 64 characters. Only letters (case-sensitive), digits, hyphens (-), underscores (_), and periods (.) are allowed.
description	No	String	Description of the replicated parameter template. The value is left blank by default. The description must consist of a maximum of 256 characters and cannot contain the carriage return characters or the following special characters (>!<"&=).

Response Parameters

Status code: 200

Table 4-378 Response body parameters

Parameter	Type	Description
configuration_id	String	Parameter template ID.

Status code: 400**Table 4-379** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-380** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Replicating a parameter template

```
POST https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/configurations/  
a2069d40256f40078c52d90d6a91ee63pr07/copy  
  
{  
    "name" : "paramTemplate-new",  
    "description" : "new-parameter-group"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "configuration_id" : "7b4e07852bd54016906e89461b3182cdpr02"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.8 Comparing Parameter Templates

Function

This API is used to compare two parameter templates. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/configurations/comparison

Table 4-381 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-382 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-383 Request body parameter

Parameter	Mandatory	Type	Description
source_configuration_id	Yes	String	ID of the source parameter template to be compared. To obtain this value, see Querying Parameter Templates . After the request is processed, the value of id in the response body is the value of source_configuration_id .
target_configuration_id	Yes	String	ID of the destination parameter template for comparison To obtain this value, see Querying Parameter Templates . After the request is processed, the value of id in the response body is the value of target_configuration_id .

Response Parameters

Status code: 200

Table 4-384 Response body parameters

Parameter	Type	Description
differences	Array of ParamGroupParameterDifferences objects	Differences between parameters.

Table 4-385 ParamGroupParameterDifferences

Parameter	Type	Description
parameter_name	String	Parameter name.
source_value	String	Parameter value in the source parameter template.

Parameter	Type	Description
target_value	String	Parameter value in the destination parameter template.

Status code: 400

Table 4-386 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-387 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Compare parameter templates

```
POST https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/configurations/comparison
{
  "source_configuration_id" : "a2069d40256f40078c52d90d6a91ee63pr07",
  "target_configuration_id" : "0cd8ef851dc4422f98e7717205ed13e6pr07"
}
```

Example Response

Status code: 200

Success.

```
{
  "differences" : [ {
    "parameter_name" : "innodb_purge_threads",
    "source_value" : 1,
    "target_value" : 4
  }, {
    "parameter_name" : "connect_timeout",
    "source_value" : 10,
    "target_value" : 20
  } ]
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.9 Querying Instances That a Parameter Template Can Be Applied To

Function

This API is used to query DB instances that a parameter template can be applied to. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/configurations/{configuration_id}/applicable-instances

Table 4-388 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
configuration_id	Yes	String	Parameter template ID. To obtain this value, see Querying Parameter Templates . After the request is processed, the value of id in the response body is the value of configuration_id .

Table 4-389 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the $N+1$ piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-390 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-391 Response body parameters

Parameter	Type	Description
instances	Array of ApplicableInstances objects	List of instances that the parameter template can be applied to.
total_count	Integer	Number of instances that the parameter template can be applied to.

Table 4-392 ApplicableInstances

Parameter	Type	Description
instance_id	String	Instance ID.
instance_name	String	Instance name.

Status code: 400**Table 4-393** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-394** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying instances that a template parameter template can be applied to

```
GET https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/configurations/  
0c82974e2354466098d7b4b72e55129dpr07/applicable-instances
```

Example Response

Status code: 200

Success.

```
{  
    "total_count": 10,  
    "instances": [ {  
        "instance_id": "75e1935142974ca685357dc784626f22in07",  
        "instance_name": "gauss-ff14-hll"  
    }, {  
        "instance_id": "cf72c31a689c40b7883c355a0bb5cc1din07",  
        "instance_name": "tst-bbbnew"  
    }, {  
        "instance_id": "4a99fbae95df43648281cdd9e269c1c7in07",  
        "instance_name": "gauss-62d8"  
    }, {  
        "instance_id": "fb6244dc9b1443b7ad0aae81283d5d28in07",  
        "instance_name": "gauss-test-1"  
    }, {  
        "instance_id": "2260da7e105e485ebc9c060c1663d89ain07",  
        "instance_name": "gauss-f4c6-cx"  
    }, {  
        "instance_id": "1cf7357f931448f89229de664c114d05in07",  
        "instance_name": "gauss-wry-0710-3"  
    }, {  
        "instance_id": "5280b1a667d142378fe28816afb2e4b8in07",  
        "instance_name": "taurus_WAkJSzVy"  
    }, {  
        "instance_id": "56c6924923804259a1b15b846c6b4bf1in07",  
        "instance_name": "tck-update3"  
    }, {  
        "instance_id": "72a8f4287e04427985087795825fcddain07",  
        "instance_name": "critBack"  
    }, {  
        "instance_id": "c5df1dec75ed48ab85fe52c72ba784bbin07",  
        "instance_name": "gauss-f873-cx"  
    } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.10 Viewing Parameter Change History

Function

This API is used to view the parameter change history. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/configurations/{configuration_id}/modify-history

Table 4-395 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
configuration_id	Yes	String	Parameter template ID. To obtain this value, see Querying Details of a DB Instance . After the request is processed, the value of configuration_id in the response body is the value of configuration_id .

Table 4-396 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-397 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-398 Response body parameters

Parameter	Type	Description
total_count	Integer	Total number of records.
histories	Array of ParamGroupHistoryResponse objects	Change history of the parameter template.

Table 4-399 ParamGroupHistoryResponse

Parameter	Type	Description
parameter_name	String	Parameter name.
old_value	String	Old parameter value.
new_value	String	New parameter value.
update_result	String	Update result.

Parameter	Type	Description
is_applied	Boolean	Whether the changed template is applied. <ul style="list-style-type: none">• true: applied.• false: not applied
updated	String	Time when the template was modified. The format is yyyy-mm-ddThh:mm:ssZ. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
applied	String	Time when the template was applied. The format is yyyy-mm-ddThh:mm:ssZ. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .

Status code: 400**Table 4-400** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-401** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying change history of a parameter template

GET https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/configurations/7625c6a12d884be1891c61d921e0e114pr07/modify-history

Example Response

Status code: 200

Success.

```
{  
    "total_count": 2,  
    "histories": [ {  
        "parameter_name": "binlog_rows_query_log_events",  
        "old_value": false,  
        "new_value": true,  
        "update_result": "SUCCESS",  
        "is_applied": true,  
        "updated": "2023-07-10T02:14:28+0000",  
        "applied": "2023-07-10T02:14:28+0000"  
    }, {  
        "parameter_name": "block_encryption_mode",  
        "old_value": "aes-256-cbc",  
        "new_value": "aes-128-cfb1",  
        "update_result": "SUCCESS",  
        "is_applied": true,  
        "updated": "2023-07-10T02:14:28+0000",  
        "applied": "2023-07-10T02:14:28+0000"  
    } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.11 Obtaining Parameter Information of a Specified DB Instance

Function

This API is used to obtain parameter information of a specified DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/configurations

Table 4-402 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-403 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-404 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-405 Response body parameters

Parameter	Type	Description
configurations	ParameterConfigurationInfo object	Parameter information.
total_count	Long	Total number of parameters.
parameter_values	Array of ParameterValuesInfo objects	Parameter object.

Table 4-406 ParameterConfigurationInfo

Parameter	Type	Description
datastore_version_name	String	DB version name.
datastore_name	String	Database name.
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .

Parameter	Type	Description
updated	String	Update time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .

Table 4-407 ParameterValuesInfo

Parameter	Type	Description
name	String	Parameter name.
value	String	Parameter value.
restart_required	Boolean	Whether the instance needs to be rebooted. <ul style="list-style-type: none">• false: The instance does not need to be rebooted.• true: The instance needs to be rebooted.
readonly	Boolean	Whether the instance is read-only <ul style="list-style-type: none">• false: The instance is read-only.• true: The instance is not read-only.
value_range	String	Parameter value range. If the parameter type is integer , the value is 0 or 1 . If the parameter type is boolean , the value is true or false .
type	String	Parameter type. <ul style="list-style-type: none">• string• integer• boolean• list• float
description	String	Parameter description.

Status code: 400**Table 4-408** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-409** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Obtaining parameter information of a specified DB instance

```
GET https://[endpoint]/v3/0483b6b16e954cb88930a360d2c4e663/instances/  
61a4ea66210545909d74a05c27a7179ein07/configurations
```

Example Response

Status code: 200

Success.

```
{  
    "configurations": {  
        "datastore_version_name": 2.0,  
        "datastore_name": "taurus",  
        "created": "2022-10-29T09:38:36+0000",  
        "updated": "2022-10-29T09:38:36+0000"  
    },  
    "total_count": 125,  
    "parameter_values": [ {  
        "name": "auto_increment_increment",  
        "value": 1,  
        "restart_required": false,  
        "readonly": false,  
        "value_range": "1-65535",  
        "type": "integer",  
        ...."description": auto_increment_increment and auto_increment_offset are used for master-to-master  
replication and to control the operations of the AUTO_INCREMENT column.  
    }, {  
        "name": "auto_increment_offset",  
        "value": 1,  
        "restart_required": false,  
        "readonly": false,  
        "value_range": "1-65535",  
        "type": "integer",  
        ...."description": auto_increment_increment and auto_increment_offset are used for master-to-master  
replication and to control the operations of the AUTO_INCREMENT column.  
    } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.5.12 Modifying Parameters of a Specified DB Instance

Function

This API is used to modify parameters of a specified DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/configurations

Table 4-410 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-411 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. To obtain the value, call the API for obtaining a user token . After the request is processed, the value of X-Subject-Token in the message header is the token value.
Content-Type	Yes	String	Content type. Value: application/json

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value range: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-412 Request body parameters

Parameter	Mandatory	Type	Description
parameter_values	Yes	Map<String, String>	Mapping between parameter names and parameter values. You can specify parameter values based on a default parameter template. If this parameter is not specified, the original parameter information is retained.

Response Parameters

Status code: 200

Table 4-413 Response body parameters

Parameter	Type	Description
job_id	String	Task ID for modifying the parameters of a specified DB instance.
restart_required	Boolean	Whether the instance needs to be rebooted. <ul style="list-style-type: none">• true: The instance needs to be rebooted.• false: The instance does not need to be rebooted.

Status code: 400

Table 4-414 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-415** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Modifying parameters of a specified DB instance

```
PUT https://{endpoint}/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
3ef58db3986540d19f95151309368d34in07/configurations  
  
{  
    "parameter_values" : {  
        "max_user_connections" : "100"  
    }  
}
```

Example Response**Status code: 200**

Success.

```
{  
    "job_id" : "e5d698a9-d8db-47d2-bf75-3c9018f72b6f",  
    "restart_required" : false  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error CodeFor details, see [Error Codes](#).

4.5.13 Replicating the Parameter Template of a DB Instance

Function

This API is used to replicate the parameter template of a DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/configurations/{configuration_id}/copy

Table 4-416 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
configuration_id	Yes	String	Parameter template ID. To obtain the value, call the API for querying details of a DB instance . After the request is processed, this parameter value is the value of configuration_id in the response body

Request Parameters

Table 4-417 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. To obtain the value, call the API for obtaining a user token . After the request is processed, the value of X-Subject-Token in the message header is the token value.
Content-Type	Yes	String	Content type. Value: application/json

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value range: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-418 Request body parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Name of the replicated parameter template. The template name can contain 1 to 64 characters. Only letters (case-sensitive), digits, hyphens (-), underscores (_), and periods (.) are allowed.
description	No	String	Description of the replicated parameter template. The value is left blank by default. The description can consist of up to 256 characters, and cannot contain the carriage return characters or special characters (!<='>&).

Response Parameters

Status code: 200

Table 4-419 Response body parameters

Parameter	Type	Description
configuration_id	String	Parameter template ID.

Status code: 400

Table 4-420 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-421** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Replicating the parameter template of a DB instance

```
POST https://{endpoint}/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
61a4ea66210545909d74a05c27a7179ein07/configurations/b26ab68e7a77495c8d84b92e4eaa33d3pr07/copy  
{  
    "name" : "paramTemplate-test-1",  
    "description" : "test"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "configuration_id" : "c82d8c54c4c7416a946f58d9ee89ed8epr07"  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.6 Quota Management

4.6.1 Querying the Instance Quotas of a Tenant

Function

This API is used to query the resource quotas of a specified tenant. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/project-quotas

Table 4-422 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-423 Query parameters

Parameter	Mandatory	Type	Description
type	No	String	Quota of a specified type. Value: instance

Request Parameters

Table 4-424 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-425 Response body parameters

Parameter	Type	Description
quotas	project-quotas object	Tenant instance quota information.

Table 4-426 project-quotas

Parameter	Type	Description
resources	Array of resource objects	Resource list objects.

Table 4-427 resource

Parameter	Type	Description
type	String	Quota of a specified type. Its value is instance .
used	Integer	Number of created resources.
quota	Integer	Maximum resource quota.

Status code: 400**Table 4-428** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-429** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying the instance quotas of a tenant

GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/project-quotas?type=instance

Example Response

Status code: 200

Success.

{
 "quotas" : {
 "resources" : [{
 "type" : "instance,",
 "used" : "4,",
 "quota" : 50
 }]
 }
}

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.6.2 Querying the Resource Quotas of a Specified Enterprise Project

Function

This API is used to query the resource quotas of a specified enterprise project.
Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is in the open beta test (OBT) phase. To use this API, submit a service ticket.

URI

GET /v3/{project_id}/quotas

Table 4-430 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-431 Query parameters

Parameter	Mandatory	Type	Description
offset	No	String	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number. Value: 0 to 10000

Parameter	Mandatory	Type	Description
limit	No	String	Number of records to be queried. The default value is 10 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
enterprise_project_name	No	String	Enterprise project name.

Request Parameters

Table 4-432 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-433 Response body parameters

Parameter	Type	Description
quota_list	Array of quota objects	Resource list objects.
total_count	Integer	Number of quota records.

Table 4-434 quota

Parameter	Type	Description
enterprise_project_id	String	Enterprise project ID.
enterprise_project_name	String	Enterprise project name.
instance_quota	Integer	Quota of the DB instance quantity.
vcpus_quota	Integer	Quota of vCPUs.
ram_quota	Integer	Memory quota in GB.
availability_instance_quota	Integer	Remaining quota of DB instances.
availability_vcpus_quota	Integer	Remaining quota of vCPUs.
availability_ram_quota	Integer	Remaining memory quota.

Status code: 400**Table 4-435 Response body parameters**

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-436 Response body parameters**

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying resource quotas

GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/quotas

Example Response

Status code: 200

Success.

```
{  
    "quota_list": [ {  
        "enterprise_project_id": "0",  
        "enterprise_project_name": "default",  
        "instance_quota": 20,  
        "vcpus_quota": 20,  
        "ram_quota": 40,  
        "availability_instance_quota": 1,  
        "availability_vcpus_quota": 4,  
        "availability_ram_quota": 8  
    } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.6.3 Configuring Resource Quotas for a Specified Enterprise Project

Function

This API is used to configure resource quotas for a specified enterprise project. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is in the open beta test (OBT) phase. To use this API, submit a service ticket.

URI

POST /v3/{project_id}/quotas

Table 4-437 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-438 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-439 Request body parameters

Parameter	Mandatory	Type	Description
quota_list	Yes	Array of setQuota objects	Quota details. Up to 10 quota records can be configured at a time.

Table 4-440 setQuota

Parameter	Mandatory	Type	Description
enterprise_project_id	Yes	String	Enterprise project ID.
instance_quota	No	Integer	Instance quantity quota. Value: 0 to 100000 . NOTE (If there are already instances created, this parameter value must be greater than the number of existing instances.)

Parameter	Mandatory	Type	Description
vcpus_quota	No	Integer	vCPU quota. Value: 0 to 2147483646 . NOTE (If there are already instances created, this parameter value must be greater than the number of used vCPUs.)
ram_quota	No	Integer	Memory quota in GB. Value: 0 to 2147483646 . NOTE (If there are already instances created, this parameter value must be greater than the used memory size.)

Response Parameters

Status code: 200

Table 4-441 Response body parameters

Parameter	Type	Description
quota_list	Array of setQuota objects	Configured quota information.

Table 4-442 setQuota

Parameter	Type	Description
enterprise_project_id	String	Enterprise project ID.
instance_quota	Integer	Instance quantity quota.
vcpus_quota	Integer	vCPU quota.
ram_quota	Integer	Memory quota in GB.

Example Request

Configuring resource quotas

```
POST https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/quotas
{
```

```
"quota_list" : [ {  
    "enterprise_project_id" : "0",  
    "instance_quota" : 20,  
    "vcpus_quota" : 20,  
    "ram_quota" : 40  
} ]  
}
```

Example Response

Status code: 200

Success.

```
{  
    "quota_list" : [ {  
        "enterprise_project_id" : "0",  
        "instance_quota" : 20,  
        "vcpus_quota" : 20,  
        "ram_quota" : 40  
    } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.6.4 Modifying the Resource Quotas of a Specified Enterprise Project

Function

This API is used to modify the resource quotas of a specified enterprise project.
Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is in the open beta test (OBT) phase. To use this API, submit a service ticket.

URI

PUT /v3/{project_id}/quotas

Table 4-443 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-444 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-445 Request body parameters

Parameter	Mandatory	Type	Description
quota_list	Yes	Array of setQuota objects	Enterprise project resource quotas to be updated. A maximum of 10 quotas can be updated at a time.

Table 4-446 setQuota

Parameter	Mandatory	Type	Description
enterprise_project_id	Yes	String	Enterprise project ID.

Parameter	Mandatory	Type	Description
instance_quota	No	Integer	Instance quantity quota. Value: 0 to 100000 . NOTE (If there are already instances created, this parameter value must be greater than the number of existing instances.)
vcpus_quota	No	Integer	vCPU quota. Value: 0 to 2147483646 . NOTE (If there are already instances created, this parameter value must be greater than the number of used vCPUs.)
ram_quota	No	Integer	Memory quota in GB. Value: 0 to 2147483646 . NOTE (If there are already instances created, this parameter value must be greater than the used memory size.)

Response Parameters

Status code: 200

Table 4-447 Response body parameters

Parameter	Type	Description
quota_list	Array of setQuota objects	Configured quota information.

Table 4-448 setQuota

Parameter	Type	Description
enterprise_project_id	String	Enterprise project ID.
instance_quota	Integer	Quota of the DB instance quantity.
vcpus_quota	Integer	Quota of vCPUs.
ram_quota	Integer	Memory quota in GB.

Status code: 400**Table 4-449** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-450** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Modifying the resource quotas of a specified enterprise project

```
PUT https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/quotas
{
    "quota_list" : [ {
        "enterprise_project_id" : "0",
        "instance_quota" : 20,
        "vcpus_quota" : 20,
        "ram_quota" : 40
    } ]
}
```

Example Response

Status code: 200

Success.

```
{
    "quota_list" : [ {
        "enterprise_project_id" : "0",
        "instance_quota" : 20,
        "vcpus_quota" : 20,
        "ram_quota" : 40
    } ]
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.6.5 Querying Enterprise Projects

Function

This API is used to query enterprise projects. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/enterprise-projects

Table 4-451 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-452 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-453 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-454 Response body parameters

Parameter	Type	Description
enterprise_projects	Array of EnterpriseProjectItem objects	Enterprise project information.
total_count	Integer	Total number of enterprise projects.

Table 4-455 EnterpriseProjectItem

Parameter	Type	Description
id	String	Enterprise project ID.
name	String	Enterprise project name.
description	String	Description.

Parameter	Type	Description
status	String	Status. <ul style="list-style-type: none">• 1: normal• 0: abnormal
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
updated	String	Update time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .

Status code: 400**Table 4-456** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-457** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying Enterprise Projects

GET https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/enterprise-projects

Example Response

Status code: 200

Success.

```
{  
    "total_count": 4,  
    "enterprise_projects": [ {  
        "id": 0,  
        "name": "default",  
        "description": null,  
        "status": 1,  
        "created": null,  
        "updated": null  
    }, {  
        "id": "5c7d11e0-3201-4558-bcce-1172137cf7e2",  
        "name": "sjw-eps",  
        "description": null,  
        "status": 1,  
        "created": "2023-06-12T02:14:28+0000",  
        "updated": "2023-06-12T02:14:28+0000"  
    }, {  
        "id": "12093327-28dc-46c5-8ba6-d42c9236f9d6",  
        "name": "adf",  
        "description": null,  
        "status": 1,  
        "created": "2023-05-06T08:33:03+0000",  
        "updated": "2023-05-06T08:33:03+0000"  
    }, {  
        "id": "07d90b3f-422b-40c9-b9b3-6d00d1d7a60b",  
        "name": "eps-test",  
        "description": null,  
        "status": 1,  
        "created": "2023-03-16T01:38:13+0000",  
        "updated": "2023-03-16T01:38:13+0000"  
    } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7 Database Proxy

4.7.1 Creating a Proxy Instance

Function

This API is used to create a proxy instance in ELB mode. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/proxy

Table 4-458 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-459 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-460 Request body parameters

Parameter	Mandatory	Type	Description
flavor_ref	Yes	String	Proxy specification code.
node_num	Yes	Integer	Proxy instance nodes. Value range: 2 to 32 .

Parameter	Mandatory	Type	Description
proxy_name	No	String	Proxy instance name. Instances of the same type can have same names under the same tenant. The name consists of 4 to 64 characters and starts with a letter. It is case-sensitive and can contain only letters, digits, hyphens (-), and underscores (_).
proxy_mode	No	String	Proxy instance type. The default type is readwrite . <ul style="list-style-type: none">• readwrite: read and write• readonly: read-only
route_mode	No	Integer	Routing policy of the proxy instance. Value: <ul style="list-style-type: none">• 0 (default value): weighted• 1: load balancing (The primary node does not process read requests.)• 2: load balancing (The primary node processes read requests.)
nodes_read_weight	No	Array of NodesWeight objects	Read weight of the node.
subnet_id	No	String	Subnet ID in the VPC of the database.
new_node_auto_add_status	No	String	Whether new nodes are automatically associate with proxy instances. To configure this parameter, contact customer service. Value: <ul style="list-style-type: none">• ON: New nodes are automatically associate with proxy instances.• OFF: New nodes are not automatically associate with proxy instances.

Parameter	Mandatory	Type	Description
new_node_weight	No	Integer	<p>Read weight of the new node.</p> <ul style="list-style-type: none">• If route_mode is 0 and new_node_auto_add_status is ON, the value of this parameter ranges from 0 to 1000.• If route_mode is not 0 and new_node_auto_add_status is OFF, this parameter is unavailable.

Table 4-461 NodesWeight

Parameter	Mandatory	Type	Description
id	No	String	Node ID.
weight	No	Integer	<p>Weight assigned to the node.</p> <ul style="list-style-type: none">• If route_mode is 0, the value is 0 to 1000.• If route_mode is 1, the value for the primary node is 0 and the value for read replicas is 0 or 1.• If route_mode is 2, the value for the primary node is 1 and the value for read replicas is 0 or 1.

Response Parameters

Status code: 201

Table 4-462 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-463 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-464** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Creating a proxy instance (The proxy instance specifications are 2 vCPUs and 8 GB memory, and the proxy mode is read-only)

```
POST https://[endpoint]/v3/0483b6b16e954cb88930a360d2c4e663/instances/  
43e4feaab48f11e89039fa163ebaa7e4br01/proxy  
{  
    "flavor_ref": "gaussdb.proxy.large.x86.2",  
    "node_num": 2,  
    "proxy_name": "gaussdb-proxy",  
    "proxy_mode": "readonly",  
    "route_mode": 0,  
    "nodes_read_weight": [ {  
        "id": "45021bf73a244312a3f2af95092feecno07",  
        "weight": 50  
    }, {  
        "id": "d78a65690cea4af5ad14585e110ff89bno07",  
        "weight": 400  
    } ],  
    "subnet_id": "6991d82d-9166-4aff-a1fa-d2a8748b7084"  
}
```

Example Response

Status code: 201

Success.

```
{  
    "job_id": "04efe8e2-9255-44ae-a98b-d87cae411890"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.2 Deleting a Proxy Instance

Function

This API is used to delete a proxy instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/instances/{instance_id}/proxy

Table 4-465 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-466 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	<p>Request language type. The default value is en-us.</p> <p>Value:</p> <ul style="list-style-type: none">• en-us• zh-cn

Table 4-467 Request body parameters

Parameter	Mandatory	Type	Description
proxy_ids	No	Array of strings	<p>Proxy instance IDs.</p> <ul style="list-style-type: none">• If there is only one proxy instance, this parameter is optional.• If there are multiple proxy instances, this parameter is mandatory. You must specify the ID of the proxy instance to be disabled.

Response Parameters

Status code: 200

Table 4-468 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-469 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-470 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting a specified proxy instance

```
DELETE https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
096c0fc43e804757b59946b80dc27f8bin07/proxy  
{  
    "proxy_ids" : [ "151c14381ac14ecfb9703a745b992677po01" ]  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "04efe8e2-9255-44ae-a98b-d87cae411890"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.3 Querying Proxy Instances

Function

This API is used to query proxy instances. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/proxies

Table 4-471 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-472 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 10 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-473 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-474 Response body parameters

Parameter	Type	Description
proxy_list	Array of MysqlShowProxyResponseV3 objects	Proxy instances.

Table 4-475 MysqlShowProxyResponseV3

Parameter	Type	Description
proxy	MysqlProxyV3 object	Proxy instance information.
master_node	MysqlProxyNodeV3 object	Primary node information.
readonly_nodes	Array of MysqlProxyNodeV3 objects	Read replica information.

Table 4-476 MysqlProxyV3

Parameter	Type	Description
pool_id	String	Proxy instance ID.

Parameter	Type	Description
status	String	<p>Operating status of the proxy instance.</p> <p>Value:</p> <ul style="list-style-type: none">• ACTIVE: The proxy instance is normal.• FAILED: The proxy instance fails to be created.• DELETED: The proxy instance is deleted.• ABNORMAL: The proxy instance is abnormal.• ENABLING PROXY: The proxy instance is being created.• DISABLING PROXY: The proxy instance is being deleted.• ADDING PROXY NODE: Nodes are being added to the proxy instance.• DELETING READ REPLICAS FROM PROXY: Read replicas are being removed from the proxy instance.• ADDING READ REPLICAS TO PROXY: Read replicas are being added to the proxy instance.• CHANGING WEIGHTS: The weights of read replicas for the proxy instance are being changed.
address	String	Read/write splitting address.
port	Integer	Read/write splitting port.
pool_status	String	<p>Proxy instance status.</p> <p>Value:</p> <ul style="list-style-type: none">• ACTIVE: The proxy instance is normal.• ABNORMAL: The proxy instance is abnormal.• FAILED: The proxy instance failed.• DELETED: The proxy instance has been deleted.
delay_threshold_in_seconds	Integer	Delay threshold in seconds.
elb_vip	String	Virtual IP address in ELB mode.
eip	String	EIP information.
vcpus	String	Number of vCPUs of the proxy instance.
ram	String	Memory size of the proxy instance.

Parameter	Type	Description
node_num	Integer	Proxy instance nodes.
mode	String	Primary/standby proxy. The value is Cluster .
nodes	Array of MysqlProxyNodes objects	Proxy node information.
flavor_ref	String	Proxy instance specifications.
name	String	Proxy instance name.
transaction_split	String	Whether the proxy transaction splitting is enabled. Value: <ul style="list-style-type: none">• ON: Transaction splitting is enabled.• OFF: Transaction splitting is disabled.
connection_pool_type	String	Connection pool type. Value: <ul style="list-style-type: none">• CLOSED: The connection pool is not used.• SESSION: The session-level connection pool is used.
switch_connection_pool_type_enabled	Boolean	Whether the proxy version supports session-level connection pool. Value: <ul style="list-style-type: none">• true: supported• false: not supported
route_mode	Integer	Routing policy of the proxy instance. Value: <ul style="list-style-type: none">• 0 (default value): weighted• 1: load balancing (The primary node does not process read requests.)• 2: load balancing (The primary node processes read requests.)
balance_route_mode_enabled	Boolean	Whether the database proxy version supports load balancing. Value: <ul style="list-style-type: none">• true: supported• false: not supported

Parameter	Type	Description
consistence_mode	String	Consistency mode. The default value is empty. In this case, the value of session_consistency is used. Value: <ul style="list-style-type: none">• session: session consistency• global: global consistency• eventual: eventual consistency
subnet_id	String	ID of the subnet to which the proxy instance belongs.
ssl_option	String	Whether to enable SSL. Value: <ul style="list-style-type: none">• true: SSL is enabled.• false: SSL is disabled.
new_node_auto_add_status	String	Whether new nodes are automatically associate with proxy instances. Value: <ul style="list-style-type: none">• ON: New nodes are automatically associate with proxy instances.• OFF: New nodes are not automatically associate with proxy instances.
new_node_weight	Integer	Read weight of the new node.

Table 4-477 MysqlProxyNodes

Parameter	Type	Description
id	String	Proxy node ID.
status	String	Proxy node status. Value: <ul style="list-style-type: none">• ACTIVE: The node is available.• ABNORMAL: The node is abnormal.• FAILED: The node fails.• DELETED: The node has been deleted.
name	String	Proxy node name.

Parameter	Type	Description
role	String	Proxy node name. Value: <ul style="list-style-type: none">● master: primary node● slave: read replica
az_code	String	AZ.
frozen_flag	Integer	Whether the proxy node is frozen. Value: <ul style="list-style-type: none">● 0: unfrozen● 1: frozen● 2: deleted after being frozen

Table 4-478 MysqlProxyNodeV3

Parameter	Type	Description
id	String	Node ID.
instance_id	String	Instance ID.
status	String	Node status.
name	String	Node name.
weight	Integer	Read weight of the node.
availability_zone	Array of MysqlProxyAvailable objects	AZ information.

Table 4-479 MysqlProxyAvailable

Parameter	Type	Description
code	String	AZ code.
description	String	AZ description.

Status code: 400

Table 4-480 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-481** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying proxy instances

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
096c0fc43e804757b59946b80dc27f8bin07/proxies?offset=0&limit=10
```

Example Response

Status code: 200

Success.

```
{  
  "proxy_list" : [ {  
    "proxy" : {  
      "pool_id" : "2e7cf21d14794bafab623a334efd9ad8po01",  
      "status" : "ACTIVE",  
      "address" : "192.168.125.69",  
      "port" : 3306,  
      "pool_status" : "ACTIVE",  
      "delay_threshold_in_seconds" : 30,  
      "elb_vip" : "192.168.125.60",  
      "eip" : "192.168.125.50",  
      "vcpus" : 4,  
      "ram" : 8,  
      "node_num" : 2,  
      "mode" : "Cluster",  
      "nodes" : [ {  
        "id" : "db53a238a02240c49365e72e284a4890pn01",  
        "name" : "PROXY-2e7cf21d14794bafab623a334efd9ad8po01_0",  
        "role" : "master",  
        "az_code" : "az1xahz",  
        "status" : "ACTIVE",  
        "frozen_flag" : 0  
      } ],  
      "name" : "proxy-name",  
  
      "connection_pool_type" : "SESSION",  
      "switch_connection_pool_type_enabled" : true ,  
      "subnet_id" : "6991d82d-9166-4aff-a1fa-d2a8748b7084"  
    } ]  
}
```

```
        },
        "master_node" : {
            "id" : "c01a5645eb2c4fb6a9373542f5366e50no07",
            "instance_id" : "7a871d6d494e4327ad2e326afb591108in07",
            "status" : "ACTIVE",
            "name" : "taurus_mysql80_x86-ondemand-2-1U4G_1_202103070251274842281_node01",
            "weight" : 0,
            "availability_zone" : [{
                "code" : "az1",
                "description": "AZ1"
            }]
        },
        "readonly_nodes" : {
            "id" : "d23535333138462880bfa1838fdfced2no07",
            "instance_id" : "7a871d6d494e4327ad2e326afb591108in07",
            "status" : "ACTIVE",
            "name" : "taurus_mysql80_x86-ondemand-2-1U4G_1_202103070251274842281_node02",
            "weight" : 100,
            "availability_zone" : [{
                "code" : "az1",
                "description": "AZ1"
            }]
        }
    ]
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.4 Querying Proxy Instance Specifications

Function

This API is used to query proxy instance specifications. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/proxy/flavors

Table 4-482 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-483 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-484 Response body parameters

Parameter	Type	Description
proxy_flavor_groups	Array of MysqlProxyFlavorGroups objects	Specification group information.

Table 4-485 MysqlProxyFlavorGroups

Parameter	Type	Description
group_type	String	Specification group type. It can be x86 or arm . <ul style="list-style-type: none">● arm: exclusive Arm● x86: exclusive x86
proxy_flavors	Array of MysqlProxyComputeFlavor objects	Proxy specifications.

Table 4-486 MysqlProxyComputeFlavor

Parameter	Type	Description
vcpus	String	Number of vCPUs. For example, the value 1 indicates 1 vCPU.
ram	String	Memory size in GB.
db_type	String	Database type.
id	String	Proxy specification ID.
spec_code	String	Proxy specification code.
az_status	Object	key indicates the AZ ID, and value indicates the specification status in the AZ. Value: <ul style="list-style-type: none">● normal● unsupported: indicates that the specifications are not supported.

Status code: 400**Table 4-487** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-488 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying proxy instance specifications

```
GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
096c0fc43e804757b59946b80dc27f8bin07/proxy/flavors
```

Example Response

Status code: 200

Success.

```
{  
  "proxy_flavor_groups" : {  
    "group_type" : "X86",  
    "proxy_flavors" : {  
      "id" : "19be4c5d-d363-3342-bdbc-0dd9dbf7faf",  
      "spec_code" : "gaussdb.proxy.large.x86.2",  
      "vcpus" : 2,  
      "ram" : 4,  
      "db_type" : "Proxy",  
      "az_status" : {  
        "az1" : "normal"  
      }  
    }  
  }  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.5 Adding Proxy Nodes

Function

This API is used to add proxy nodes. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/proxy/enlarge

Table 4-489 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-490 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-491 Request body parameters

Parameter	Mandatory	Type	Description
node_num	Yes	Integer	The number of proxy nodes to be added. The value is an integer from 1 to 30. Restrictions: The total number of proxy nodes for an instance is no more than 32.
proxy_id	No	String	Proxy instance ID. <ul style="list-style-type: none">If there is only one proxy instance, this parameter is optional.If there are multiple proxy instances, this parameter is mandatory. You must specify the ID of the proxy instance that you want to add nodes for.

Response Parameters

Status code: 201

Table 4-492 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-493 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-494 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Adding proxy nodes

```
POST https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
61a4ea66210545909d74a05c27a7179ein07/proxy/enlarge  
{  
    "node_num": 2,  
    "proxy_id": "151c14381ac14ecfb9703a745b992677po01"  
}
```

Example Response

Status code: 201

Success.

```
{  
    "job_id": "04efe8e2-9255-44ae-a98b-d87cae411890"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.6 Deleting Proxy Nodes

Function

This API is used to delete proxy nodes. Before calling this API: Database proxy is unavailable for DB instances in a DeC.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/reduce

Table 4-495 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-496 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-497 Request body parameter

Parameter	Mandatory	Type	Description
node_num	Yes	Integer	Number of proxy nodes to be deleted. The value is an integer from 1 to 30. Restrictions: The total number of proxy nodes of the instance ranges from 2 to 32.

Response Parameters

Status code: 201

Table 4-498 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-499 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-500 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting proxy nodes

```
PUT https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
61a4ea66210545909d74a05c27a7179ein07/proxy/151c14381ac14ecfb9703a745b992677po01/reduce
```

```
{  
    "node_num": 1  
}
```

Example Response

Status code: 201

Success.

```
{  
    "job_id": "04efe8e2-9255-44ae-a98b-d87cae411890"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.7 Changing Specifications of a Proxy Instance

Function

This API is used to change specifications of a proxy instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/flavor

Table 4-501 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-502 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-503 Request body parameters

Parameter	Mandatory	Type	Description
flavor_ref	Yes	String	ID of the new flavor.

Response Parameters

Status code: 200

Table 4-504 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-505 Response body parameters

Parameter	Type	Description
error_code	String	Error code.

Parameter	Type	Description
error_msg	String	Error message.

Status code: 500

Table 4-506 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the specifications of a proxy instance to 4 vCPUs and 8 GB memory

```
PUT https://[endpoint]/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
61a4ea66210545909d74a05c27a7179ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/flavor  
{  
    "flavor_ref" : "gaussdb.proxy.xlarge.arm.2"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "04efe8e2-9255-44ae-a98b-d87cae411890"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.8 Assigning Read Weights

Function

This API is used to assign read weights for nodes. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/weight

Table 4-507 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-508 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-509 Request body parameters

Parameter	Mandatory	Type	Description
master_weight	No	Integer	Weight of the primary node.
readonly_nodes	No	Array of TaurusModifyProxyWeightReadOnlyNode objects	Weight information of the read replicas.

Table 4-510 TaurusModifyProxyWeightReadOnlyNode

Parameter	Mandatory	Type	Description
id	No	String	Read replica ID.
weight	No	Integer	Weight of the read replica.

Response Parameters

Status code: 200

Table 4-511 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-512 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-513 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Assigning the weight of the primary node to 100

```
PUT https://[endpoint]/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/e73893ef73754465a8bd2e0857bbf13ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/weight
{
    "master_weight" : 100
}
```

Example Response

Status code: 200

Success.

```
{
    "job_id" : "04efe8e2-9255-44ae-a98b-d87c11411890"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.9 Changing the Routing Policy of a Proxy Instance

Function

This API is used to change the routing policy of a proxy instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is in the open beta test (OBT) phase. To use this API, submit a service ticket.

URI

```
PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/route-mode
```

Table 4-514 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-515 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-516 Request body parameters

Parameter	Mandatory	Type	Description
route_mode	Yes	Integer	<p>Routing policy of the proxy instance.</p> <p>Value:</p> <ul style="list-style-type: none">• 0: weighted• 1: load balancing (The primary node does not process read requests.)• 2: load balancing (The primary node processes read requests.)
master_weight	No	Integer	<p>Weight of the primary node.</p> <ul style="list-style-type: none">• If the routing policy is 0, the value is 0 to 1000.• If the routing policy is 1, the value is 0.• If the routing policy is 2, the value is 1.
readonly_nodes	No	Array of ModifyProxyRouteModeWeightReadonlyNode objects	Weight information of the read replicas.
new_node_auto_add_status	No	String	<p>Whether new nodes are automatically associate with proxy instances. To configure this parameter, contact customer service.</p> <p>Value:</p> <ul style="list-style-type: none">• ON: New nodes are automatically associate with proxy instances.• OFF: New nodes are not automatically associate with proxy instances.

Parameter	Mandatory	Type	Description
new_node_weight	No	Integer	<p>Read weight of the new node.</p> <ul style="list-style-type: none">• If route_mode is 0 and new_node_auto_add_status is ON, the value of this parameter ranges from 0 to 1000.• If route_mode is not 0 and new_node_auto_add_status is OFF, this parameter is unavailable.

Table 4-517 ModifyProxyRouteModeWeightReadonlyNode

Parameter	Mandatory	Type	Description
id	Yes	String	Read replica ID.
weight	Yes	Integer	<p>Weight of the read replica.</p> <ul style="list-style-type: none">• If the routing policy is 0, the value is 0 to 1000.• If the routing policy is 1 or 2, the value is 0 or 1.

Response Parameters

Status code: 200

Table 4-518 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-519 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-520 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- **Changing the routing policy of a proxy instance to 0**
PUT https://[endpoint]/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/e73893ef73754465a8bd2e0857bbf13ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/route-mode
{
 "route_mode" : 0,
 "master_weight" : 100,
 "readonly_nodes" : {
 "id" : "d23535333138462880bfa1838fdfced2no07",
 "weight" : 200
 }
}
- **Changing the routing policy of a proxy instance to 1**
PUT https://[endpoint]/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/e73893ef73754465a8bd2e0857bbf13ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/route-mode
{
 "route_mode" : 1,
 "master_weight" : 0,
 "readonly_nodes" : {
 "id" : "d23535333138462880bfa1838fdfced2no07",
 "weight" : 1
 }
}
- **Changing the routing policy of a proxy instance to 2**
PUT https://[endpoint]/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/e73893ef73754465a8bd2e0857bbf13ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/route-mode
{
 "route_mode" : 2,
 "master_weight" : 1,
 "readonly_nodes" : {
 "id" : "d23535333138462880bfa1838fdfced2no07",
 "weight" : 0
 }
}

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "04efe8e2-9255-44ae-a98b-d87c11411890"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.10 Enabling or Disabling Transaction Splitting of a Proxy Instance

Function

This API is used to enable or disable transaction splitting of a proxy instance.
Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/proxy/transaction-split

Table 4-521 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-522 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-523 Request body parameters

Parameter	Mandatory	Type	Description
transaction_sp lit	Yes	String	Whether transaction splitting is enabled. Value: <ul style="list-style-type: none">• ON: Transaction splitting is enabled.• OFF: Transaction splitting is disabled.
proxy_id_list	Yes	Array of strings	Proxy instances.

Response Parameters

Status code: 200

Table 4-524 Response body parameters

Parameter	Type	Description
job_id	String	Workflow ID

Status code: 400

Table 4-525 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-526 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Disabling transaction splitting of a proxy instance

```
POST https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
6b030d160ac24eda9a5320fb38dc2d0ain07/proxy/transaction-split  
{  
    "transaction_split" : "OFF",  
    "proxy_id_list" : [ "2a2060f2486e4a47934182d91a3b53d2po01" ]  
}
```

Example Response

Status code: 200

success

```
{  
    "job_id" : "11921bf5-f286-45ee-ab35-12a3d4084c57"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.11 Enabling or Disabling Association of New Nodes with Proxy Instances

Function

This API is used to enable or disable association of new nodes with proxy instances. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is in the open beta test (OBT) phase. To use this API, submit a service ticket.

URI

POST /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/new-node-auto-add

Table 4-527 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-528 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-529 Request body parameters

Parameter	Mandatory	Type	Description
switch_status	Yes	String	Whether new nodes are automatically associate with proxy instances. Value: <ul style="list-style-type: none">• ON: New nodes are automatically associate with proxy instances.• OFF: New nodes are not automatically associate with proxy instances.
weight	No	Integer	Read weight of the new node. <ul style="list-style-type: none">• If switch_status is ON, the value ranges from 0 to 1000.• If switch_status is OFF, this parameter is unavailable.

Response Parameters

Status code: 200

Table 4-530 Response body parameters

Parameter	Type	Description
result	String	Result of enabling or disabling association of new nodes with proxy instances.

Status code: 400

Table 4-531 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-532 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Automatically associating new nodes with proxy instances

```
POST https://{{endpoint}}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
e73893ef73754465a8bd2e0857bbf13ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/new-node-  
auto-add  
{  
    "switch_status" : "ON",  
    "weight" : 100  
}
```

Example Response

Status code: 200

Success.

```
{  
    "result" : "success"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.12 Changing Session Consistency of a Proxy Instance

Function

This API is used to change the session consistency of a proxy instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/session-consistence

Table 4-533 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-534 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-535 Request body parameter

Parameter	Mandatory	Type	Description
session_consistency	Yes	String	Whether session consistency is enabled. Value: <ul style="list-style-type: none">• true: Session consistency is enabled.• false: Session consistency is disabled.
consistency_mode	No	String	Consistency mode. The default value is empty. In this case, the value of session_consistency is used. Value: <ul style="list-style-type: none">• session: session consistency• global: global consistency• eventual: eventual consistency

Response Parameters

Status code: 200

Table 4-536 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-537 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-538 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Enabling session consistency for a proxy instance

```
PUT https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/  
d512257ecc04d96a0f3a9021018a385in07/proxy/7bf4a8bbb4f4fb58233a242ee13603bpo01/session-  
consistence  
{  
    "session_consistence" : "true"  
}
```

Example Response

Status code: 200

Success

```
{  
    "job_id" : "e0fbbfc8-1ac4-4721-b9e9-7dd685c5bdd7"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.13 Changing the Connection Pool Type of a Proxy Instance

Function

This API is used to change the connection pool type of a proxy instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

This API is in the open beta test (OBT) phase. To use this API, submit a service ticket.

URI

PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/connection-pool-type

Table 4-539 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-540 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-541 Request body parameters

Parameter	Mandatory	Type	Description
connection_pool_type	Yes	String	Connection pool type. Value: <ul style="list-style-type: none">• CLOSED: The connection pool is closed.• SESSION: The session-level connection pool is enabled.

Response Parameters

Status code: 200

Table 4-542 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-543 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-544 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Enabling the session connection pool for a proxy instance

```
PUT https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instance/  
af315b8e6aaa41799bd9a31f2de15abcin07/proxy/5881e1ca66af4aefbc64dc2874e55b3fpo01/connection-
```

```
pool-type
{
  "connection_pool_type" : "SESSION"
}
```

Example Response

Status code: 200

Success.

```
{
  "job_id" : "a4217ac4-12cd-4fb3-acfc-db4a4a1896ea"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.14 Changing the Port of a Proxy Instance

Function

This API is used to change the port of a proxy instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/port

Table 4-545 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-546 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-547 Request body parameters

Parameter	Mandatory	Type	Description
port	Yes	Integer	New port of the proxy instance. Value range: 1025 to 65534, excluding 1033, 5342 to 5345, 12017, 20000, 20201, 20202, 33062, and 33071.

Response Parameters

Status code: 200

Table 4-548 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for changing the port of the proxy instance.

Status code: 400

Table 4-549 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-550** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing the port of a proxy instance

```
PUT https://{endpoint}/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/proxy/fbece38953e24a2b891488ed2fdf81abpo01/port  
{  
    "port" : 3308  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "*****"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.15 Modifying Parameters of a Proxy Instance

Function

This API is to modify parameters of a proxy instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.

- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/configurations

Table 4-551 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-552 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">en-uszh-cn

Table 4-553 Request body parameter

Parameter	Mandatory	Type	Description
configurations	Yes	Array of UpdateProxyConfigurationItem objects	Configurations to be modified.

Table 4-554 UpdateProxyConfigurationItem

Parameter	Mandatory	Type	Description
name	Yes	String	Parameter name.
value	Yes	String	Parameter value.
elem_type	Yes	String	Parent tag type.

Response Parameters

Status code: 200

Table 4-555 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-556 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-557 Response body parameters

Parameter	Type	Description
error_code	String	Error code.

Parameter	Type	Description
error_msg	String	Error message.

Example Request

Modifying parameters of a proxy instance

```
PUT https://[endpoint]/v3/0483b6b16e954cb88930a360d2c4e663/instances/  
61a4ea66210545909d74a05c27a7179ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/configurations  
{  
  "configurations" : [ {  
    "name" : "multiStatementType",  
    "value" : "Loose",  
    "elem_type" : "system"  
  } ]  
}
```

Example Response

Status code: 200

Success.

```
{  
  "job_id" : "994cb0aa-9547-4271-bfc2-08f968276744"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.16 Enabling or Disabling Access Control

Function

This API is used to enable or disable access control. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/access-control-switch

Table 4-558 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-559 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-560 Request body parameter

Parameter	Mandatory	Type	Description
open_access_control	Yes	Boolean	Whether to enable access control. Value: <ul style="list-style-type: none">• true: Access control is enabled.• false: Access control is disabled.

Response Parameters

Status code: 200

Table 4-561 Response body parameters

Parameter	Type	Description
open_access_control	Boolean	Whether access control is enabled. Value: <ul style="list-style-type: none">• true: enabled• false: disabled

Status code: 400

Table 4-562 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-563 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- Enabling access control

```
POST https://[endpoint]/v3/0483b6b16e954cb88930a360d2c4e663/instances/61a4ea66210545909d74a05c27a7179ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/access-control-switch
```

```
{  
    "open_access_control" : true  
}
```

- Disabling access control

```
POST https://[endpoint]/v3/0483b6b16e954cb88930a360d2c4e663/instances/61a4ea66210545909d74a05c27a7179ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/access-control-switch
```

```
{  
    "open_access_control" : false  
}
```

Example Response

Status code: 200

Success.

- Enabling access control

```
{  
    "open_access_control" : true  
}
```

- Disabling access control

```
{  
    "open_access_control" : false  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.17 Configuring Access Control Rules

Function

This API is used to configure access control rules. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

```
POST /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/access-control
```

Table 4-564 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
proxy_id	Yes	String	Proxy instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-565 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-566 Request body parameter

Parameter	Mandatory	Type	Description
type	Yes	String	Access control mode. Value: <ul style="list-style-type: none">• white: indicates the whitelist.• black: indicates the blacklist.

Parameter	Mandatory	Type	Description
ip_list	Yes	Array of AccessControlRule objects	Array of IP addresses that control access. A maximum of 300 IP addresses or CIDR blocks can be added.

Table 4-567 AccessControlRule

Parameter	Mandatory	Type	Description
ip	Yes	String	IP address or CIDR block.
description	No	String	Remarks. Character length: 0-50. Angle brackets (<>) are not allowed.

Response Parameters

Status code: 200

Table 4-568 Response body parameters

Parameter	Type	Description
open_access_control	Boolean	Whether access control is enabled. Value: • true : enabled • false : disabled

Status code: 400

Table 4-569 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-570 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Configuring access control rules

```
POST https://[endpoint]/v3/0483b6b16e954cb88930a360d2c4e663/instances/  
61a4ea66210545909d74a05c27a7179ein07/proxy/e87088f0b6a345e79db19d57c41fde15po01/access-control  
{  
    "type" : "black",  
    "ip_list" : [ {  
        "ip" : "192.107.0.1",  
        "description" : "black01"  
    } ]  
}
```

Example Response

Status code: 200

Success.

```
{  
    "open_access_control" : false  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.7.18 Enabling or Disabling SSL for a Proxy Instance

Function

This API is used to enable or disable SSL for a proxy instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/proxy/{proxy_id}/ssl

Table 4-571 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID of a tenant in a project.
proxy_id	Yes	String	Proxy instance ID.

Request Parameters

Table 4-572 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-573 Request body parameters

Parameter	Mandatory	Type	Description
ssl_option	Yes	Boolean	Whether to enable SSL. Value: <ul style="list-style-type: none">• true: SSL is enabled.• false: SSL is disabled.

Response Parameters

Status code: 200

Table 4-574 Response body parameters

Parameter	Type	Description
job_id	String	Task ID.

Status code: 400

Table 4-575 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-576 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Enabling SSL

```
PUT https://[endpoint]/v3/056538411200d4cd2f79c003c7606412/instances/  
096c0fc43e804757b59946b80dc27f8bin07/proxyId/2ec617ba62da4eafb921b69438beed3cpo01/ssl  
{  
    "ssl_option" : true  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "e0fbfffc8-1ac4-4721-b9e9-7dd685c5bdd7"  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.8 Log Management

4.8.1 Enabling or Disabling SQL Explorer

Function

This API is used to enable or disable SQL Explorer. Before calling this API: If SQL Explorer is disabled, SQL Explorer may become unavailable for DAS and DBSS.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instance/{instance_id}/audit-log/switch

Table 4-577 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-578 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-579 Request body parameter

Parameter	Mandatory	Type	Description
switch_status	Yes	String	Whether SQL Explorer is enabled. Value: <ul style="list-style-type: none">• ON: SQL Explorer is enabled.• OFF: SQL Explorer is disabled.

Response Parameters

Status code: 200

Table 4-580 Response body parameters

Parameter	Type	Description
result	String	Result for enabling or disabling SQL Explorer.

Status code: 400

Table 4-581 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-582** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Enabling SQL Explorer

```
POST https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instance/  
61a4ea66210545909d74a05c27a7179ein07/audit-log/status  
{  
    "switch_status" : "ON"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "result" : "success"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.8.2 Querying Whether SQL Explorer Is Enabled

Function

This API is used to query whether SQL Explorer is enabled. Before calling this API:

- Learn how to [authorize and authenticate](#) it.

- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instance/{instance_id}/audit-log/switch-status

Table 4-583 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-584 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">en-uszh-cn

Response Parameters

Status code: 200

Table 4-585 Response body parameters

Parameter	Type	Description
switch_status	String	Whether SQL Explorer is enabled. Value: <ul style="list-style-type: none">• ON: SQL Explorer is enabled.• OFF: SQL Explorer is disabled.

Status code: 400**Table 4-586** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-587** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying whether SQL Explorer is enabled

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instance/  
61a4ea66210545909d74a05c27a7179ein07/audit-log/switch-status
```

Example Response

Status code: 200

Success.

```
{  
    "switch_status" : "ON"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.8.3 Querying Slow Query Logs

Function

This API is used to query the slow query logs of a specified DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3.1/{project_id}/instances/{instance_id}/slow-logs

Table 4-588 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-589 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	<p>Request language type. The default value is en-us.</p> <p>Value:</p> <ul style="list-style-type: none">• en-us• zh-cn

Table 4-590 Request body parameters

Parameter	Mandatory	Type	Description
node_id	Yes	String	Node ID.
start_time	Yes	String	<p>Start time in the "yyyy-mm-ddThh:mm:ssZ" format.</p> <p>T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100.</p>
end_time	Yes	String	<p>End time in the "yyyy-mm-ddThh:mm:ssZ" format.</p> <p>T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100.</p>
limit	Yes	Integer	Number of records to be queried.
line_num	No	String	Sequence number of a log event. This parameter is not required for the first query, but is required for subsequent pagination queries. The value can be obtained from the response of the last query.

Parameter	Mandatory	Type	Description
operate_type	No	String	Statement type. If it is left blank, all statement types are queried. Value: <ul style="list-style-type: none">• INSERT• UPDATE• SELECT• DELETE• ALTER• DROP• CREATE
database	No	String	Database which slow logs belong to.

Response Parameters

Status code: 200

Table 4-591 Response body parameters

Parameter	Type	Description
slow_log_list	Array of LtsLogSlowDetail objects	Slow query logs.

Table 4-592 LtsLogSlowDetail

Parameter	Type	Description
node_id	String	Node ID.
count	String	Number of executions.
time	String	Execution time.
lock_time	String	Lock wait time.
rows_sent	String	Number of sent rows.
rows_examined	String	Number of scanned rows.
database	String	Database which slow logs belong to.
users	String	Account.
query_sample	String	Execution syntax.

Parameter	Type	Description
type	String	Statement type.
start_time	String	Start time in the UTC format.
client_ip	String	IP address.
line_num	String	Sequence number of a log event.

Status code: 400**Table 4-593** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-594** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying slow query logs

```
POST https://{endpoint}/v3.1/056538411200d4cd2f79c003c7606412/instances/096c0fc43e804757b59946b80dc27f8bin07/slow-logs
{
  "start_time" : "2022-11-20T00:00:00+0800",
  "end_time" : "2022-11-29T00:00:00+0800",
  "node_id" : "cc07c60e94ec4575989840e648fb4f66no07",
  "limit" : 10,
  "line_num" : 1669344916000
}
```

Example Response

Status code: 200

Success.

```
{
  "slow_log_list" : [ {
    "node_id" : "cc07c60e94ec4575989840e648fb4f66no07",
```

```
"count" : 1,
"time" : "1.04899 s",
"lock_time" : "0.00003 s",
"rows_sent" : 0,
"rows_examined" : 0,
"database" : "gaussdb-mysql",
"users" : "root",
"query_sample" : "INSERT INTO time_zone_name (Name, Time_zone_id) VALUES (N @time_zone_id);",
"type" : "INSERT",
"start_time" : "2022-11-25T10:55:16.000",
"client_ip" : "192.*.*.1",
"line_num" : 1669344916000
} ]
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.8.4 Querying Error Logs

Function

This API is used to query the error logs of a specified DB instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3.1/{project_id}/instances/{instance_id}/error-logs

Table 4-595 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-596 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-597 Request body parameters

Parameter	Mandatory	Type	Description
node_id	Yes	String	Node ID.
start_time	Yes	String	Start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
end_time	Yes	String	End time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
limit	Yes	Integer	Number of records to be queried.

Parameter	Mandatory	Type	Description
line_num	No	String	Sequence number of a log event. This parameter is not required for the first query, but is required for subsequent pagination queries. The value can be obtained from the response of the last query.
level	No	String	Log level. The default value is ALL . Value: <ul style="list-style-type: none">• ALL• INFO• LOG• WARNING• ERROR• FATAL• PANIC• NOTE

Response Parameters

Status code: 200

Table 4-598 Response body parameters

Parameter	Type	Description
error_log_list	Array of LtsLogErrorDetail objects	Error logs.

Table 4-599 LtsLogErrorDetail

Parameter	Type	Description
node_id	String	Node ID.
time	String	Execution time.
level	String	Log level.
content	String	Error log content.
line_num	String	Sequence number of a log event.

Status code: 400**Table 4-600** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-601** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying error logs

```
POST https://{endpoint}/v3.1/056538411200d4cd2f79c003c7606412/instances/096c0fc43e804757b59946b80dc27f8bin07/error-logs
{
    "start_time" : "2022-11-20T00:00:00+0800",
    "end_time" : "2022-11-29T00:00:00+0800",
    "node_id" : "cc07c60e94ec4575989840e648fb4f66no07",
    "limit" : 10,
    "line_num" : 1669344916000
}
```

Example Response

Status code: 200

Success.

```
{
    "error_log_list" : [ {
        "node_id" : "cc07c60e94ec4575989840e648fb4f66no07",
        "time" : "2022-11-25T10:55:16.000",
        "level" : "ERROR",
        "content" : "[MY013508] [Repl] do failed: 1",
        "line_num" : 1669344916000
    } ]
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.8.5 Obtaining the Temporary Link for Downloading Full SQL

Function

This API is used to obtain the temporary link for downloading full SQL. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instance/{instance_id}/auditlog/download-link

Table 4-602 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-603 Query parameters

Parameter	Mandatory	Type	Description
start_time	Yes	String	Start time, which cannot be earlier than the instance creation time. The format is yyyy-mm-ddThh:mm:ssZ. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .

Parameter	Mandatory	Type	Description
end_time	Yes	String	<p>End time, which cannot be later than the current time. The format is yyyy-mm-ddThh:mm:ssZ.</p> <p>T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100.</p>
node_id	No	String	<p>Node ID.</p> <ul style="list-style-type: none">If this parameter is specified, the link is used for only downloading full SQL of the node.If this parameter is not specified, the link is used for downloading full SQL of all nodes of the instance.
last_file_name	No	String	<p>Name of the last file queried last time.</p> <ul style="list-style-type: none">If this parameter is specified, the query starts from the file name in alphabetical order.If this parameter is not specified, the query starts from the first file.
limit	No	Integer	<p>Number of files returned in one query.</p> <p>Default value: 10. Value: an integer ranging from 1 to 50</p>

Request Parameters

Table 4-604 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-605 Response body parameters

Parameter	Type	Description
files	Array of FileInfo objects	Obtained full SQL file information.

Table 4-606 FileInfo

Parameter	Type	Description
name	String	File name.
size	Long	File size, in KB.
updated_time	String	Last modification time of the SQL file. The format is yyyy-mm-ddThh:mm:ssZ. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .

Parameter	Type	Description
download_link	String	Link for downloading the file.
link_expired_time	String	Link expiration time. The format is yyyy-mm-ddThh:mm:ssZ. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .

Status code: 400**Table 4-607** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-608** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Obtaining the temporary link for downloading full SQL

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instance/  
669a94abef9f4979b2dfba92f48f4042in07/auditlog/download-link?  
node_id=2e723b45786148fc94c8737f5980786cno07&last_file_name=20230724160316_99b1d48896bb44178  
b715d64b68603f9in07_6a21d5df9bb24f5db83121c5fec0b1d2n07_SQLAudit_8b4b53d2-29f8-11ee-92aa-  
fa163ef00f0d&limit=10&start_time=2023-07-24T09:27:00+0800&end_time=2023-07-25T15:00:14+0800
```

Example Response

Status code: 200

Success.

```
{  
  "files" : [ {  
    "name" :
```

```
"20230706023359_669a94abef9f4979b2dfba92f48f4042in07_b051c8f7b98f4deef88ba97c8daba9dno07_SQLAudit_903bdbb6-1ba5-11ee-8b97-fa163ef0f8c2",
  "size" : 928,
  "updated_time" : "2023-07-06T02:43:57+0800",
  "download_link" : "https://obs.obs.domainname.com/bucketname/userid_instanceid/20230706/SQLAudit/xxxxxx",
  "link_expired_time" : "2023-07-13T012:30:36+0800"
} ]
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.9 Tag Management

4.9.1 Querying Resource Tags

Function

This API is used to query tags of a specified instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/tags

Table 4-609 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-610 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to <i>N</i> , the resource query starts from the <i>N+1</i> piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-611 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-612 Response body parameters

Parameter	Type	Description
total_count	Integer	Total number of records.
tags	Array of ResourceTagItem objects	Tag list.

Table 4-613 ResourceTagItem

Parameter	Type	Description
key	String	Tag key.
value	String	Tag value.

Status code: 400

Table 4-614 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-615 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying resource tags

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
61a4ea66210545909d74a05c27a7179ein07/tags?offset=0&limit=2
```

Example Response

Status code: 200

Success.

```
{  
    "total_count": 2,  
    "tags": [  
        {  
            "key": "key1",  
            "value": "value1"  
        }, {  
            "key": "key2",  
            "value": "value2"  
        }]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.9.2 Querying Project Tags

Function

This API is used to query all tags of instances in a specified project. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/tags

Table 4-616 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-617 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the $N+1$ piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-618 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-619 Response body parameters

Parameter	Type	Description
total_count	Integer	Total number of records.
tags	Array of ProjectTagItem objects	Tag list.

Table 4-620 ProjectTagItem

Parameter	Type	Description
key	String	Tag key.
values	Array of strings	Tag value.

Status code: 400**Table 4-621** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-622** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying project tags

GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/tags?offset=0&limit=2

Example Response

Status code: 200

Success.

```
{
  "total_count": 2,
  "tags": [
    {
      "key": "key1",
      "values": [ "value1", "value2" ]
    },
    {
      "key": "key2",
      "values": [ "value3", "value4" ]
    }
  ]
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.9.3 Adding or Deleting Tags in Batches

Function

This API is used to add tags to or delete tags from a specified DB instance in batches. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/tags/action

Table 4-623 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-624 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-625 Request body parameters

Parameter	Mandatory	Type	Description
action	Yes	String	Operation identifier. Value: <ul style="list-style-type: none">• create: adding tags• delete: deleting tags
tags	Yes	Array of TagItem objects	Tag list.

Table 4-626 TagItem

Parameter	Mandatory	Type	Description
key	Yes	String	Tag key. It contains a maximum of 36 Unicode characters and cannot be null, an empty string, or a space. Only digits, uppercase letters, lowercase letters, underscores (_), and hyphens (-) are allowed.

Parameter	Mandatory	Type	Description
value	No	String	<p>Tag value. It contains a maximum of 43 Unicode characters. It can be an empty string but cannot be a space. Only digits, uppercase letters, lowercase letters, underscores (_), periods (.), and hyphens (-) are allowed.</p> <ul style="list-style-type: none">• If action is set to create, this parameter is mandatory.• If action is set to delete and value is specified, tags are deleted by key and value. If value is not specified, tags are deleted by key.

Response Parameters

Status code: 400

Table 4-627 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-628 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- Adding tags in batches

```
POST https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
61a4ea66210545909d74a05c27a7179ein07/tags/action  
{  
    "action" : "create",
```

```
"tags" : [ {  
    "key" : "key1",  
    "value" : "value1"  
}, {  
    "key" : "key2",  
    "value" : "value2"  
} ]  
}
```

- Deleting tags in batches

```
POST https://{{endpoint}}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
61a4ea66210545909d74a05c27a7179ein07/tags/action  
{  
    "action" : "delete",  
    "tags" : [ {  
        "key" : "key1"  
    }, {  
        "key" : "key2",  
        "value" : "value2"  
    } ]  
}
```

Example Response

None

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.10 Database User Management

4.10.1 Creating a Database Account

Function

This API is used to create a database account for a GaussDB(for MySQL) instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

```
POST /v3/{project_id}/instances/{instance_id}/db-users
```

Table 4-629 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-630 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-631 Request body parameter

Parameter	Mandatory	Type	Description
users	Yes	Array of CreateDatabaseUserList objects	List of database users. The list contains up to 50 database users.

Table 4-632 CreateDatabaseUserList

Parameter	Mandatory	Type	Description
name	Yes	String	Database username. The value can contain 1 to 32 characters, including letters, digits, and underscores (_).
password	Yes	String	<p>Password of the database user. It cannot be the same as the user name. The value cannot be empty and must consist of 8 to 32 characters and contain at least three types of the following: uppercase letters, lowercase letters, digits, and special characters (~!@#\$%^*-_=+?,()&).</p> <p>You are advised to enter a strong password to improve security and prevent security risks such as brute force cracking.</p>
comment	No	String	<p>Database remarks. The value can consist of up to 512 characters, and cannot contain the carriage return characters or special characters (!<"='>&). This field is only suitable for instances 2.0.13.0 or later. To upgrade an instance to the latest version, see Upgrading the Kernel Version of a DB Instance.</p>
hosts	No	Array of strings	Host IP address. The default value is %, indicating that all IP addresses are allowed to access your GaussDB(for MySQL) instance. If its value is 10.10.10. %, all 10.10.10.XIP addresses can access your GaussDB(for MySQL) instance. You can add up to 50 IP addresses and separate them with commas (,), for example, 192.168.0.1,172.16.213.9 (no spaces before and after the comma).

Parameter	Mandatory	Type	Description
databases	No	Array of CreateDatabaseList objects	List of the databases. The list contains up to 50 databases. When you create a database user, you can authorize the permissions of databases in the list to the user. If there is no database in the list, you can invoke an API to authorize database permissions to the database user.

Table 4-633 CreateDatabaseList

Parameter	Mandatory	Type	Description
name	Yes	String	Database name.
readonly	Yes	Boolean	Whether the permission is read-only. Value: <ul style="list-style-type: none">• true: read-only• false: read/write

Response Parameters

Status code: 201

Table 4-634 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for creating a database account.

Status code: 400

Table 4-635 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-636 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Creating a database user with the read/write permission (The host IP address is 127.0.0.1.)

```
POST https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
a23fb62bd61e4e9e9636fd2225f395bein07/db-users  
{  
    "users": [ {  
        "name": "gaussdb_mysql_user1",  
        "password": "Rds_1234",  
        "hosts": [ "127.0.0.1" ],  
        "comment": "database_user_comment",  
        "databases": [ {  
            "name": "test",  
            "readonly": false  
        } ]  
    } ]  
}
```

Example Response

Status code: 201

Success.

```
{  
    "job_id": "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.10.2 Querying Database Users

Function

This API is used to query database users of a GaussDB(for MySQL) instance.
Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/db-users

Table 4-637 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-638 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-639 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-640 Response body parameters

Parameter	Type	Description
users	Array of ListGaussMySqlDatabaseUser objects	List of database users.
total_count	Integer	Total number of database users of a DB instance.

Table 4-641 ListGaussMySqlDatabaseUser

Parameter	Type	Description
name	String	Database username.
host	String	Host IP address.
comment	String	Remarks of the database account.

Parameter	Type	Description
databases	Array of ListGaussMySqlDatabase objects	List of databases.

Table 4-642 ListGaussMySqlDatabase

Parameter	Type	Description
name	String	Database name.
readonly	Boolean	Whether the permission is read-only. Value: <ul style="list-style-type: none">• true: read-only• false: read/write

Status code: 400**Table 4-643** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-644** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying database users

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
a23fb62bd61e4e9e9636fd2225f395bein07/db-users?offset=0&limit=100
```

Example Response

Status code: 200

Success.

```
{  
  "users": [ {  
    "name": "gaussdb_mysql_user1",  
    "host": "127.0.0.1",  
    "comment": "database_user_comment",  
    "databases": [ {  
      "name": "test",  
      "readonly": false  
    } ]  
  },  
  "total_count": 1  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.10.3 Deleting a Database User

Function

This API is used to delete a database user. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/instances/{instance_id}/db-users

Table 4-645 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-646 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-647 Request body parameter

Parameter	Mandatory	Type	Description
users	Yes	Array of ListDeleteDatabaseUserRequest objects	List of database users to be deleted. The list contains up to 50 database users.

Table 4-648 ListDeleteDatabaseUserRequest

Parameter	Mandatory	Type	Description
name	Yes	String	Database username.
host	Yes	String	Host IP address.

Response Parameters

Status code: 202

Table 4-649 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for deleting database users.

Status code: 400**Table 4-650** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-651** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting the database user whose host IP address is 127.0.0.1

```
DELETE https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/
a23fb62bd61e4e9e9636fd2225f395bein07/db-users
{
  "users" : [ {
    "name" : "gaussdb_mysql_user1",
    "host" : "127.0.0.1"
  }]
}
```

Example Response

Status code: 202

Success.

```
{
  "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.10.4 Modifying Remarks of a Database User

Function

This API is used to modify the remarks of a database user. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/db-users/comment

Table 4-652 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-653 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-654 Request body parameters

Parameter	Mandatory	Type	Description
users	Yes	Array of UpdateDatabaseUserComment objects	List of database users that you want to change the remarks for. The list contains up to 50 database users.

Table 4-655 UpdateDatabaseUserComment

Parameter	Mandatory	Type	Description
name	Yes	String	Database username.
host	Yes	String	Host IP address.
comment	Yes	String	Database user remarks. The value can consist of up to 512 characters, and cannot contain the carriage return characters or special characters (!<"=>&). This field is only suitable for instances 2.0.13.0 or later. To upgrade an instance to the latest version, see Upgrading the Kernel Version of a DB Instance .

Response Parameters

Status code: 202

Table 4-656 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for changing the remarks of the database user.

Status code: 400

Table 4-657 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-658 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Modifying remarks of a database user

```
PUT https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/a23fb62bd61e4e9e9636fd2225f395bein07/db-users/comment

{
  "users" : [ {
    "name" : "gaussdb_mysql_user1",
    "host" : "127.0.0.1",
    "comment" : "first_database_user"
  } ]
}
```

Example Response

Status code: 202

Success.

```
{
  "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.10.5 Changing Password of a Database User

Function

This API is used to change password of a database user. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/db-users/password

Table 4-659 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-660 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-661 Request body parameter

Parameter	Mandatory	Type	Description
users	Yes	Array of ResetDatabasePassword objects	List of database users that you want to change the passwords for. The list contains up to 50 database users.

Table 4-662 ResetDatabasePassword

Parameter	Mandatory	Type	Description
name	Yes	String	Database username.
host	Yes	String	Host IP address.
password	Yes	String	<p>Password of the database user. The value can consist of 8 to 32 characters and contain at least three types of the following characters: uppercase letters, lowercase letters, digits, and special characters (~!@#\$%^*-_=+?, ()&).</p> <p>You are advised to enter a strong password to improve security and prevent security risks such as brute force cracking.</p>

Response Parameters

Status code: 202

Table 4-663 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for changing the passwords of database users.

Status code: 400

Table 4-664 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-665** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Changing password of database user **gaussdb_mysql_user1**

```
PUT https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/a23fb62bd61e4e9e9636fd2225f395bein07/db-users/password
{
  "users" : [ {
    "name" : "gaussdb_mysql_user1",
    "host" : "127.0.0.1",
    "password" : "Rds_1234"
  }]
}
```

Example Response

Status code: 202

Success.

```
{
  "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.10.6 Granting Permissions to a Database User

Function

This API is used to grant permissions to a database user. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/db-users/privilege

Table 4-666 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-667 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-668 Request body parameter

Parameter	Mandatory	Type	Description
users	Yes	Array of GrantDatabasePermission objects	List of database users. The list contains up to 50 database users.

Table 4-669 GrantDatabasePermission

Parameter	Mandatory	Type	Description
name	Yes	String	Database username.
host	Yes	String	Host IP address.
databases	Yes	Array of DatabasePermission objects	List of databases. The list contains up to 50 databases.

Table 4-670 DatabasePermission

Parameter	Mandatory	Type	Description
name	Yes	String	Database name.
readonly	Yes	Boolean	Whether the permission is read-only. Value: <ul style="list-style-type: none">• true: read-only• false: read/write

Response Parameters

Status code: 201

Table 4-671 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for authorizing the database permissions to a user.

Status code: 400

Table 4-672 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-673** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Granting the read/write permission to a database user

```
POST https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
a23fb62bd61e4e9e9636fd2225f395bein07/db-users/privilege  
{  
    "users" : [ {  
        "name" : "gaussdb_mysql_user1",  
        "host" : "127.0.0.1",  
        "databases" : [ {  
            "name" : "test",  
            "readonly" : false  
        } ]  
    } ]  
}
```

Example Response

Status code: 201

Success.

```
{  
    "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.10.7 Deleting Permissions of a Database User

Function

This API is used to delete permissions of a database user. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/instances/{instance_id}/db-users/privilege

Table 4-674 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-675 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-676 Request body parameter

Parameter	Mandatory	Type	Description
users	Yes	Array of DeleteDatabasePermission objects	List of database users. The list contains up to 50 database users.

Table 4-677 DeleteDatabasePermission

Parameter	Mandatory	Type	Description
name	Yes	String	Database username.
host	Yes	String	Host IP address.
databases	Yes	Array of strings	List of databases.

Response Parameters

Status code: 202

Table 4-678 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for deleting database permissions of database users.

Status code: 400

Table 4-679 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-680 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting permissions of database user **gaussdb_mysql_user1**

```
DELETE https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
a23fb62bd61e4e9e9636fd2225f395bein07/db-users/privilege  
{  
    "users" : [ {  
        "name" : "gaussdb_mysql_user1",  
        "host" : "127.0.0.1",  
        "databases" : [ "test" ]  
    } ]  
}
```

Example Response

Status code: 202

Success.

```
{  
    "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.11 Database Management

4.11.1 Querying Available Database Character Sets

Function

This API is used to query available database character sets of a GaussDB(for MySQL) instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/databases/charsets

Table 4-681 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-682 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-683 Response body parameters

Parameter	Type	Description
charsets	Array of strings	List of database character sets.

Status code: 400**Table 4-684** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-685** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying available database character sets

GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/a23fb62bd61e4e9e9636fd2225f395bein07/databases/charsets

Example Response

Status code: 200

Success.

{
 "charsets" : ["utf8mb4", "gbk"]
}

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.11.2 Creating a Database

Function

This API is used to create a database for a GaussDB(for MySQL) instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/databases

Table 4-686 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-687 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-688 Request body parameter

Parameter	Mandatory	Type	Description
databases	Yes	Array of CreateGauss MySqlDatabase objects	Database information list. The list contains up to 50 databases.

Table 4-689 CreateGaussMySqlDatabase

Parameter	Mandatory	Type	Description
name	Yes	String	Database name. The name can contain 1 to 64 characters. Only letters, digits, hyphens (-), and underscores (_) are allowed. The total number of hyphens (-) cannot exceed 10.
comment	No	String	Database remarks. The value can consist of up to 512 characters, and cannot contain the carriage return characters or special characters (!<"=!'>&).
character_set	Yes	String	Database character set, for example, utf8mb4 or gbk .
users	No	Array of GaussMySql DatabaseUser objects	List of database users. The list contains up to 50 database users. When you create a database, you can authorize the database permissions to the users in the list. If there is no database user in the list, you cannot authorize the database permissions to database users when creating a database. If you need to authorize the database permissions to a database user later, call the API (Granting Permissions to a Database User).

Table 4-690 GaussMySqlDatabaseUser

Parameter	Mandatory	Type	Description
name	Yes	String	Database username.
host	Yes	String	Host IP address.
readonly	Yes	Boolean	Whether the permission is read-only. Value: <ul style="list-style-type: none">• true: read-only• false: read/write

Response Parameters

Status code: 201

Table 4-691 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for creating a database.

Status code: 400

Table 4-692 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-693 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Creating a database (with utf8mb4 as character set and read/write permission)

```
POST https://{{endpoint}}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
a23fb62bd61e4e9e9636fd2225f395bein07/databases  
{  
    "databases" : [ {  
        "name" : "test",  
        "comment" : "database_comment",  
        "character_set" : "utf8mb4",  
        "users" : [ {  
            "name" : "gaussdb_mysql_user1",  
            "host" : "127.0.0.1",  
            "readonly" : false  
        } ]  
    } ]  
}
```

Example Response

Status code: 201

Success.

```
{  
    "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.11.3 Modifying Database Remarks

Function

This API is used to modify database remarks of a GaussDB(for MySQL) instance.
Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/databases/comment

Table 4-694 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Parameter	Mandatory	Type	Description
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-695 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-696 Request body parameters

Parameter	Mandatory	Type	Description
databases	Yes	Array of Table 4-697 objects	List of databases that you want to change the remarks for. The list contains up to 50 databases.

Table 4-697 UpdateDatabaseComment

Parameter	Mandatory	Type	Description
name	Yes	String	Database name.

Parameter	Mandatory	Type	Description
comment	Yes	String	Database remarks. Value: The value can consist of up to 512 characters, and cannot contain the carriage return characters or special characters (!<='>&).

Response Parameters

Status code: 202

Table 4-698 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for changing database remarks.

Status code: 400

Table 4-699 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-700 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Modifying database remarks

```
PUT https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
a23fb62bd61e4e9e9636fd2225f395bein07/databases/comment
```

```
{  
  "databases" : [ {  
    "name" : "gaussdb_mysql_user1",  
    "comment" : "first_database"  
  } ]  
}
```

Example Response

Status code: 202

Success.

```
{  
  "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.11.4 Querying Databases

Function

This API is used to query databases of a GaussDB(for MySQL) instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/databases

Table 4-701 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-702 Query parameters

Parameter	Mandatory	Type	Description
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
name	No	String	Database name.
charset	No	String	Database character set, for example, utf8mb4 or gbk .

Request Parameters

Table 4-703 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-704 Response body parameters

Parameter	Type	Description
databases	Array of ListGaussMysqldatabaseInfo objects	Database information list.
total_count	Integer	Total number of databases.

Table 4-705 ListGaussMysqlDatabaseInfo

Parameter	Type	Description
name	String	Database name.
charset	String	Database character set, for example, utf8mb4 or gbk .
comment	String	Database remarks.
users	Array of GaussMySqlDatabaseInfo objects	List of authorized database users.

Table 4-706 GaussMySqlDatabaseInfo

Parameter	Type	Description
name	String	Database username.
host	String	Host IP address.
readonly	Boolean	Whether the permission is read-only. Value: <ul style="list-style-type: none">• true: read-only• false: read/write

Status code: 400**Table 4-707** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-708** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying databases

```
GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/a23fb62bd61e4e9e9636fd2225f395bein07/databases?offset=0&limit=100&charset=utf8mb4&name=test
```

Example Response

Status code: 200

Success.

```
{  
  "databases": [ {  
    "name": "test",  
    "charset": "utf8mb4",  
    "comment": "database_comment",  
    "users": [ {  
      "name": "gaussdb-mysql-instance1",  
      "host": "127.0.0.1",  
      "readonly": false  
    } ]  
  },  
  "total_count": 1  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.11.5 Deleting a Database

Function

This API is used to delete a database from a GaussDB(for MySQL) instance. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/instances/{instance_id}/databases

Table 4-709 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-710 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-711 Request body parameter

Parameter	Mandatory	Type	Description
databases	Yes	Array of strings	List of databases to be deleted. The list contains up to 50 databases.

Response Parameters

Status code: 202

Table 4-712 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for deleting databases.

Status code: 400

Table 4-713 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-714 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting databases

```
DELETE https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
a23fb62bd61e4e9e9636fd2225f395bein07/databases  
{  
    "databases" : [ "test" ]  
}
```

Example Response

Status code: 202

Success.

```
{  
    "job_id" : "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.12 SQL Statement Concurrency Control

4.12.1 Enabling or Disabling SQL Statement Concurrency Control

Function

This API is used to enable or disable SQL Statement Concurrency Control. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

POST /v3/{project_id}/instances/{instance_id}/sql-filter/switch

Table 4-715 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-716 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-717 Request body parameter

Parameter	Mandatory	Type	Description
switch_status	Yes	String	Whether SQL Statement Concurrency Control is enabled. Value: <ul style="list-style-type: none">• ON: SQL Statement Concurrency Control is enabled.• OFF: SQL Statement Concurrency Control is disabled.

Response Parameters

Status code: 200

Table 4-718 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for enabling or disabling SQL Statement Concurrency Control.

Status code: 400**Table 4-719** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-720** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

- Enabling SQL Statement Concurrency Control

```
POST https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instance/  
af315b8e6aaa41799bd9a31f2de15abcin07/sql-filter/switch  
{  
    "switch_status" : "ON"  
}
```

- Disabling SQL Statement Concurrency Control

```
POST https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instance/  
af315b8e6aaa41799bd9a31f2de15abcin07/sql-filter/switch  
{  
    "switch_status" : "OFF"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "job_id" : "aef6a470-fb63-4d5b-b644-12ead7e019b3"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.12.2 Querying Whether SQL Statement Concurrency Control Is Enabled

Function

This API is used to query whether SQL Statement Concurrency Control is enabled. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/sql-filter/switch

Table 4-721 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-722 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-723 Response body parameters

Parameter	Type	Description
switch_status	String	Whether SQL Statement Concurrency Control is enabled. Value: <ul style="list-style-type: none">• ON: enabled• OFF: disabled

Status code: 400

Table 4-724 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-725 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying whether SQL Statement Concurrency Control is enabled

GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instance/
af315b8e6aaa41799bd9a31f2de15abcin07/sql-filter/switch

Example Response

Status code: 200

Success.

```
{  
  "switch_status" : "ON"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.12.3 Configuring Concurrency Control Rules of SQL Statements

Function

This API is used to configure concurrency control rules of SQL statements. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

PUT /v3/{project_id}/instances/{instance_id}/sql-filter/rules

Table 4-726 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-727 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-728 Request body parameter

Parameter	Mandatory	Type	Description
sql_filter_rules	Yes	Array of NodeSqlFilterRuleInfo objects	Concurrency control rules of SQL statements for nodes.

Table 4-729 NodeSqlFilterRuleInfo

Parameter	Mandatory	Type	Description
node_id	Yes	String	Node ID.
rules	Yes	Array of NodeSqlFilterRule objects	Concurrency control rules of SQL statements. The sql_type value must be unique.

Table 4-730 NodeSqlFilterRule

Parameter	Mandatory	Type	Description
sql_type	Yes	String	SQL statement type. Valid value: <ul style="list-style-type: none">• SELECT• UPDATE• DELETE
patterns	Yes	Array of NodeSqlFilterRulePattern objects	Concurrency control rules of SQL statements.

Table 4-731 NodeSqlFilterRulePattern

Parameter	Mandatory	Type	Description
pattern	Yes	String	A concurrency control rule of SQL statements. A rule can consist of up to 128 keywords. The keywords are separated by tildes (~), for example, select~from~t1 . The rule cannot contain backslashes (\), commas (,), or double tildes (~~). It cannot end with tildes (~).
max_concurrency	Yes	Integer	Maximum number of concurrent SQL statements. Value: a non-negative integer.

Response Parameters

Status code: 200

Table 4-732 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for configuring concurrency control rules of SQL statements.

Status code: 400

Table 4-733 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-734** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Configuring concurrency control rules of SQL statements (SQL statement types include SELECT, UPDATE, and DELETE.)

```
PUT https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instance/  
af315b8e6aaa41799bd9a31f2de15abcin07/sql-filter/rules  
{  
    "sql_filter_rules": [ {  
        "node_id": "c01a5645eb2c4fb6a9373542f5366e50no07",  
        "rules": [ {  
            "sql_type": "SELECT",  
            "patterns": [ {  
                "pattern": "select~from~t1",  
                "max_concurrency": 0  
            }, {  
                "pattern": "select~from~t3~where~id",  
                "max_concurrency": 10  
            } ]  
        }, {  
            "sql_type": "UPDATE",  
            "patterns": [ {  
                "pattern": "update~t3~where~id",  
                "max_concurrency": 10  
            } ]  
        }, {  
            "node_id": "b234a5645eb2c4ji3b9372342f5362397no07",  
            "rules": [ {  
                "sql_type": "SELECT",  
                "patterns": [ {  
                    "pattern": "select~from~t3~where~id",  
                    "max_concurrency": 10  
                } ]  
            }, {  
                "sql_type": "DELETE",  
                "patterns": [ {  
                    "pattern": "delete~t3~where~id",  
                    "max_concurrency": 10  
                } ]  
            } ]  
        } ]  
    } ]
```

```
    } ]  
}
```

Example Response

Status code: 200

Success.

```
{  
  "job_id" : "aef6a470-fb63-4d5b-b644-12ead7e019b3"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.12.4 Querying Concurrency Control Rules of SQL Statements

Function

This API is used to query concurrency control rules of SQL statements. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/sql-filter/rules

Table 4-735 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Table 4-736 Query parameters

Parameter	Mandatory	Type	Description
node_id	Yes	String	Node ID.

Parameter	Mandatory	Type	Description
sql_type	No	String	<p>SQL statement type. The value is case-insensitive. If this parameter is not specified, concurrency control rules of all types of statements are queried.</p> <p>Value:</p> <ul style="list-style-type: none">• SELECT• UPDATE• DELETE

Request Parameters

Table 4-737 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	<p>User token.</p> <p>If the following response body is returned for calling the API used to obtain a user token, the request is successful.</p> <p>After the request is processed, the value of X-Subject-Token in the message header is the token value.</p>
X-Language	No	String	<p>Request language type. The default value is en-us.</p> <p>Value:</p> <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-738 Response body parameters

Parameter	Type	Description
node_id	String	Node ID.

Parameter	Type	Description
sql_filter_rules	Array of SqlFilterRule objects	Concurrency control rules of SQL statements.

Table 4-739 SqlFilterRule

Parameter	Type	Description
sql_type	String	SQL statement type. Value: <ul style="list-style-type: none">• SELECT• UPDATE• DELETE
patterns	Array of SqlFilterRule Pattern objects	Concurrency control rules of SQL statements.

Table 4-740 SqlFilterRulePattern

Parameter	Type	Description
pattern	String	A concurrency control rule of SQL statements.
max_concurrency	Integer	Maximum number of concurrent SQL statements.

Status code: 400**Table 4-741** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-742 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying concurrency control rules of SQL statements

```
GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instance/  
af315b8e6aaa41799bd9a31f2de15abcin07/sql-filter/rules?  
node_id=c01a5645eb2c4fb6a9373542f5366e50no07
```

Example Response

Status code: 200

Success.

```
{  
    "node_id" : "c01a5645eb2c4fb6a9373542f5366e50no07",  
    "sql_filter_rules" : [ {  
        "sql_type" : "SELECT",  
        "patterns" : [ {  
            "pattern" : "select~from~t1",  
            "max_concurrency" : 0  
        }, {  
            "pattern" : "select~from~t2~where~id",  
            "max_concurrency" : 10  
        } ]  
    }, {  
        "sql_type" : "UPDATE",  
        "patterns" : [ {  
            "pattern" : "update~t1",  
            "max_concurrency" : 0  
        }, {  
            "pattern" : "update~t2~where~id",  
            "max_concurrency" : 10  
        } ]  
    }, {  
        "sql_type" : "DELETE",  
        "patterns" : [ {  
            "pattern" : "delete~from",  
            "max_concurrency" : 0  
        } ]  
    } ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.12.5 Deleting Concurrency Control Rules of SQL Statements

Function

This API is used to delete concurrency control rules of SQL statements. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/instances/{instance_id}/sql-filter/rules

Table 4-743 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-744 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-745 Request body parameter

Parameter	Mandatory	Type	Description
sql_filter_rules	Yes	Array of DeleteNodeS qlFilterRuleI nfo objects	Concurrency control rules of SQL statements for nodes.

Table 4-746 DeleteNodeSqlFilterRuleInfo

Parameter	Mandatory	Type	Description
node_id	Yes	String	Node ID.
rules	Yes	Array of DeleteNodeS qlFilterRule objects	Concurrency control rules of SQL statements.

Table 4-747 DeleteNodeSqlFilterRule

Parameter	Mandatory	Type	Description
sql_type	Yes	String	SQL statement type. Value: <ul style="list-style-type: none">• SELECT• UPDATE• DELETE
patterns	Yes	Array of strings	Concurrency control rules of SQL statements.

Response Parameters

Status code: 200

Table 4-748 Response body parameters

Parameter	Type	Description
job_id	String	ID of the task for deleting concurrency control rules of SQL statements.

Status code: 400

Table 4-749 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-750** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting concurrency control rules of SQL statements (SQL statement types include SELECT, UPDATE, and DELETE.)

```
DELETE https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instance/af315b8e6aaa41799bd9a31f2de15abcin07/sql-filter/rules
{
  "sql_filter_rules": [ {
    "node_id": "c01a5645eb2c4fb6a9373542f5366e50no07",
    "rules": [ {
      "sql_type": "SELECT",
      "patterns": [ "select~from~t1", "select~from~t2" ]
    }, {
      "sql_type": "UPDATE",
      "patterns": [ "udpate~t3~where~id" ]
    } ]
  }, {
    "node_id": "b234a5645eb2c4ji3b9372342f5362397no07",
    "rules": [ {
      "sql_type": "SELECT",
      "patterns": [ "select~from~t1", "select~from~t2" ]
    }, {
      "sql_type": "DELETE",
      "patterns": [ "delete~t3~where~id" ]
    } ]
  }
}
```

Example Response

Status code: 200

Success.

```
{
  "job_id": "aef6a470-fb63-4d5b-b644-12ead7e019b3"
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.13 Task Center

4.13.1 Obtaining Information About a Task with a Specified ID

Function

This API is used to obtain task information from the task center. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

Constraints

- This API is used to query asynchronous tasks of the last one month in the task center.
- After a job is generated, it takes several seconds to query the job ID.

URI

GET /v3/{project_id}/jobs

Table 4-751 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-752 Query parameters

Parameter	Mandatory	Type	Description
id	Yes	String	Task ID.

Request Parameters

Table 4-753 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-754 Response body parameters

Parameter	Type	Description
job	GetJobInfoDetail object	Task information.

Table 4-755 GetJobInfoDetail

Parameter	Type	Description
id	String	Task ID.
name	String	Task name.
status	String	Task execution status. Value: <ul style="list-style-type: none">• Running: The task is being executed.• Completed: The task is successfully executed.• Failed: The task failed to be executed.

Parameter	Type	Description
created	String	<p>Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
ended	String	<p>End time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
process	String	Task execution progress. The execution progress (such as 60%) is displayed only when the task is being executed. Otherwise, "" is returned.
instance	GetJobInstanceInfoDetail object	Instance information of the task with the specified ID.
entities	Object	Displayed information varies depending on tasks.
fail_reason	String	Task failure information.

Table 4-756 GetJobInstanceInfoDetail

Parameter	Type	Description
id	String	Instance ID.
name	String	Instance name.

Status code: 400

Table 4-757 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-758** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Obtaining information about a task with a specified ID

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/jobs?id=a9767ede-fe0f-4888-9003-e843a4c90514
```

Example Response

Status code: 200

In the response example, some tasks in the task center are used as examples.

Success.

```
{
  "job": {
    "id": "31b8ae23-c687-4d80-b7b4-42a66c9bb886",
    "name": "CreateGaussDBforMySQLInstance",
    "status": "Completed",
    "created": "2018-08-06T10:41:14+0800",
    "ended": "2018-08-06T16:41:14+0000",
    "process": "",
    "instance": {
      "id": "a48e43ff268f4c0e879652d65e63d0fb07",
      "name": "DO-NOT-TOUCH-mgr2-mysql-single"
    },
    "entities": {
      "instance": {
        "endpoint": "192.168.1.203:3306",
        "type": "Cluster",
        "datastore": {
          "type": "gaussdb-mysql",
          "version": "8.0"
        }
      },
      "resource_ids": [ "a48e43ff268f4c0e879652d65e63d0fb07.vm",
        "a48e43ff268f4c0e879652d65e63d0fb07.volume" ]
    }
  }
}
```

```
    }  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.13.2 Obtaining Instant Tasks

Function

This API is used to obtain the instant tasks. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/immediate-jobs

Table 4-759 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-760 Query parameters

Parameter	Mandatory	Type	Description
status	No	String	Task execution status. Value: <ul style="list-style-type: none">• Running: The task is being executed.• Completed: The task is successfully executed.• Failed: The task failed to be executed.• Pending: The task is not executed.

Parameter	Mandatory	Type	Description
job_name	No	String	<p>Task name. Value: Value:</p> <ul style="list-style-type: none">• CreateGaussDBforMySQLInstance: Creating a DB instance• RestoreGaussDBforMySQLNewInstance: Restoring data to a new DB instance• AddGaussDBforMySQLNodes: Adding a node• DeleteGaussDBforMySQLNode: Deleting a node• RebootGaussDBforMySQLInstance: Rebooting a DB instance• ModifyGaussDBforMySQLPort: Changing a database port• ModifyGaussDBforMySQLSecurityGroup: Changing a security group• ResizeGaussDBforMySQLFlavor: Changing instance specifications• SwitchoverGaussDBforMySQLMasterNode: Promoting a read replica to the primary node• GaussDBforMySQLBindEIP: Binding an EIP• GaussDBforMySQLUnbindEIP: Unbinding an EIP• RenameGaussDBforMySQLInstance: Changing a DB instance name• DeleteGaussDBforMySQLInstance: Deleting a DB instance• UpgradeGaussDBforMySQLDatabaseVersion: Upgrading version• EnlargeGaussDBforMySQLProxy: Adding nodes for a proxy instance

Parameter	Mandatory	Type	Description
			<ul style="list-style-type: none">● OpenGaussDBforMySQL-Proxy: Creating a proxy instance● CloseGaussDBforMySQL-Proxy: Deleting a proxy instance● GaussdbforMySQLModify-ProxyIp: Changing the IP address of a proxy instance● ScaleGaussDBforMySQL-Proxy: Changing the node specifications of a proxy instance● GaussDBforMySQLModifyInstanceMetricExtend: Enabling or disabling Monitoring by Seconds● GaussDBforMySQLModifyInstanceDataVip: Changing the private IP address● GaussDBforMySQLSwitchSSL: Enabling or disabling SSL● GaussDBforMySQLModify-ProxyConsist: Changing the proxy consistency● GaussDBforMySQLModify-ProxyWeight: Changing the read weights of nodes
job_id	No	String	Task ID.
offset	No	String	Index offset. The query starts from the first piece of data. The default value is 1 . The value must be a number and cannot be a negative number.
limit	No	String	Number of records to be queried. Value: 10 (default value), 20 , or 50 .

Parameter	Mandatory	Type	Description
start_time	No	String	Start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
end_time	No	String	End time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .

Request Parameters

Table 4-761 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-762 Response body parameters

Parameter	Type	Description
jobs	Array of TaskDetailInfo objects	Task details.
total_count	Integer	Total number of tasks.

Table 4-763 TaskDetailInfo

Parameter	Type	Description
instance_id	String	Instance ID.
instance_name	String	Instance name.
instance_status	String	Instance status. Value: <ul style="list-style-type: none">• createfail: The DB instance fails to be created.• creating: The DB instance is being created.• normal: The DB instance is normal.• abnormal: The DB instance is abnormal.• deleted: The DB instance has been deleted.
job_id	String	Task ID.
order_id	String	Order ID.

Parameter	Type	Description
job_name	String	<p>Task name.</p> <p>Value:</p> <ul style="list-style-type: none">• CreateGaussDBforMySQLInstance: Creating a DB instance• RestoreGaussDBforMySQLNewInstance: Restoring data to a new DB instance• AddGaussDBforMySQLNodes: Adding a node• DeleteGaussDBforMySQLNode: Deleting a node• RebootGaussDBforMySQLInstance: Rebooting a DB instance• ModifyGaussDBforMySQLPort: Changing a database port• ModifyGaussDBforMySQLSecurityGroup: Changing a security group• ResizeGaussDBforMySQLFlavor: Changing instance specifications• SwitchoverGaussDBforMySQLMaster-Node: Promoting a read replica to the primary node• GaussDBforMySQLBindEIP: Binding an EIP• GaussDBforMySQLUnbindEIP: Unbinding an EIP• RenameGaussDBforMySQLInstance: Changing a DB instance name• DeleteGaussDBforMySQLInstance: Deleting a DB instance• UpgradeGaussDBforMySQLDatabaseVer-sion: Upgrading version• EnlargeGaussDBforMySQLProxy: Adding nodes for a proxy instance• OpenGaussDBforMySQLProxy: Creating a proxy instance• CloseGaussDBforMySQLProxy: Deleting a proxy instance• GaussdbforMySQLModifyProxylp: Changing the IP address of a proxy instance• ScaleGaussDBforMySQLProxy: Changing the node specifications of a proxy instance• GaussDBforMySQLModifyInstanceMetri-cExtend: Enabling or disabling Monitoring by Seconds

Parameter	Type	Description
		<ul style="list-style-type: none">• GaussDBforMySQLModifyInstanceData-Vip: Changing the private IP address• GaussDBforMySQLSwitchSSL: Enabling or disabling SSL• GaussDBforMySQLModifyProxyConsist: Changing the proxy consistency• GaussDBforMySQLModifyProxyWeight: Changing the read weights of nodes
status	String	Task execution status. Value: <ul style="list-style-type: none">• Running: The task is being executed.• Completed: The task is successfully executed.• Failed: The task failed to be executed.• Pending: The task is delayed and is not executed.
process	String	Task progress.
created_time	String	Task creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
ended_time	String	Task end time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 .
fail_reason	String	Task failure cause.

Status code: 400**Table 4-764** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-765 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Obtaining the instant tasks

```
GET https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/immediate-jobs
```

Example Response

Status code: 200

Success.

```
{
  "jobs" : [ {
    "instance_id" : "ede953923f06448d9be8686ef0c1378ein07",
    "instance_name" : "gauss-1234",
    "instance_status" : "deleted",
    "job_id" : "7155730b-a60b-4dc0-9f89-3f55897f29d6",
    "order_id" : "",
    "job_name" : "CloseGaussDBforMySQLProxy",
    "status" : "Completed",
    "process" : "",
    "created_time" : "2018-08-06T10:41:14+0000",
    "ended_time" : "2018-08-06T12:41:14+0000",
    "fail_reason" : "Single task exception."
  }],
  "total_count" : 1
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.13.3 Obtaining Scheduled Tasks

Function

This API is used to obtain the scheduled tasks. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

```
GET /v3/{project_id}/scheduled-jobs
```

Table 4-766 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-767 Query parameters

Parameter	Mandatory	Type	Description
offset	No	String	Index offset. The query starts from the first piece of data. The default value is 0 . The value must be a number and cannot be a negative number.
limit	No	String	Number of records to be queried. The default value is 10 .
status	No	String	Task execution status. Value: <ul style="list-style-type: none">• Running: The task is being executed.• Completed: The task is successfully executed.• Failed: The task failed to be executed.• Pending: The task is not executed.
start_time	No	String	Start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100 . NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.

Parameter	Mandatory	Type	Description
end_time	No	String	<p>End time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
job_id	No	String	Task ID.
job_name	No	String	Task scheduling type.

Request Parameters

Table 4-768 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	<p>User token.</p> <p>If the following response body is returned for calling the API used to obtain a user token, the request is successful.</p> <p>After the request is processed, the value of X-Subject-Token in the message header is the token value.</p>
X-Language	No	String	<p>Request language type. The default value is en-us.</p> <p>Value:</p> <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-769 Response body parameters

Parameter	Type	Description
schedules	Array of ScheduleTask objects	Task details.
total_count	Integer	Total number of records.

Table 4-770 ScheduleTask

Parameter	Type	Description
job_id	String	Task ID.
instance_id	String	Instance ID.
instance_name	String	Instance name.
instance_status	String	Instance status. Value: <ul style="list-style-type: none">• createfail: The DB instance fails to be created.• creating: The DB instance is being created.• normal: The DB instance is normal.• abnormal: The DB instance is abnormal.• deleted: The DB instance has been deleted.
project_id	String	Project ID of a tenant in a region.

Parameter	Type	Description
job_name	String	<p>Task name.</p> <p>Value:</p> <ul style="list-style-type: none">• CreateGaussDBforMySQLInstance: Creating a DB instance• RestoreGaussDBforMySQLNewInstance: Restoring data to a new DB instance• AddGaussDBforMySQLNodes: Adding a node• DeleteGaussDBforMySQLNode: Deleting a node• RebootGaussDBforMySQLInstance: Rebooting a DB instance• ModifyGaussDBforMySQLPort: Changing a database port• ModifyGaussDBforMySQLSecurityGroup: Changing a security group• ResizeGaussDBforMySQLFlavor: Changing instance specifications• SwitchoverGaussDBforMySQLMaster-Node: Promoting a read replica to the primary node• GaussDBforMySQLBindEIP: Binding an EIP• GaussDBforMySQLUnbindEIP: Unbinding an EIP• RenameGaussDBforMySQLInstance: Changing a DB instance name• DeleteGaussDBforMySQLInstance: Deleting a DB instance• UpgradeGaussDBforMySQLDatabaseVer-sion: Upgrading version• EnlargeGaussDBforMySQLProxy: Adding nodes for a proxy instance• OpenGaussDBforMySQLProxy: Creating a proxy instance• CloseGaussDBforMySQLProxy: Deleting a proxy instance• GaussdbforMySQLModifyProxylp: Changing the IP address of a proxy instance• ScaleGaussDBforMySQLProxy: Changing the node specifications of a proxy instance• GaussDBforMySQLModifyInstanceMetri-cExtend: Enabling or disabling Monitoring by Seconds

Parameter	Type	Description
		<ul style="list-style-type: none">• GaussDBforMySQLModifyInstanceData-Vip: Changing the private IP address• GaussDBforMySQLSwitchSSL: Enabling or disabling SSL• GaussDBforMySQLModifyProxyConsist: Changing the proxy consistency• GaussDBforMySQLModifyProxyWeight: Changing the read weights of nodes
create_time	String	<p>Task creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
start_time	String	<p>Task start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
end_time	String	<p>Task end time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, if the time zone offset is one hour, the value of Z is +0100.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
job_status	String	<p>Task execution status.</p> <p>Value:</p> <ul style="list-style-type: none">• Pending: The task is delayed and is not executed.• Running: The task is being executed.• Completed: The task is successfully executed.• Failed: The task failed to be executed.

Parameter	Type	Description
datastore_type	String	Database type.
target_config	Object	Instance configuration information, such as specifications.

Status code: 400**Table 4-771** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-772** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Obtaining scheduled tasks

```
GET https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/scheduled-jobs?offset=1&limit=10
```

Example Response

Status code: 200

Success.

```
{  
    "schedules": [ {  
        "job_id": "56d3c1138dcf4f1da73b0170700c78d0",  
        "instance_id": "79bc540dd4d6432784894a981fdfacfcin07",  
        "instance_name": "gauss-f821",  
        "instance_status": "BUILD",  
        "project_id": "053f533ead80d5102f0cc012e8d468a4",  
        "job_name": "UpgradeGaussDBforMySQLDatabaseVersion",  
        "create_time": "2018-08-06T10:41:14+0000",  
        "start_time": "2018-08-06T10:41:14+0000",  
        "end_time": "2018-08-06T10:41:14+0000",  
        "job_status": "Completed",  
        "datastore_type": "gaussdb-mysql",  
    } ]}
```

```
"target_config" : {  
    "flavor" : "gaussdb.mysql.xlarge.arm.4",  
    "mem" : "16",  
    "cpu" : "4"  
}  
},  
}],  
"total_count" : 1  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.13.4 Canceling a Scheduled Task

Function

This API is used to cancel a scheduled task. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/scheduled-jobs

Table 4-773 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-774 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-775 Request body parameter

Parameter	Mandatory	Type	Description
job_ids	Yes	Array of strings	Task ID.

Response Parameters

Status code: 200

Table 4-776 Response body parameters

Parameter	Type	Description
job_ids	Array of strings	Task ID for canceling a scheduled task.

Status code: 400

Table 4-777 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-778** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Canceling a scheduled task

```
DELETE https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/scheduled-jobs
{
    "job_ids" : [ "56d3c1138dcf4f1da73b0170700c78d0" ]
}
```

Example Response

Status code: 200

Success.

```
{
    "job_ids" : [ "56d3c1138dcf4f1da73b0170700c78d0" ]
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.13.5 Deleting a Task Record

Function

This API is used to delete the record of a specific task. Before calling this API:

- Learn how to [authorize and authenticate](#) it.

- Obtain the required [region and endpoint](#).

URI

DELETE /v3/{project_id}/jobs/{job_id}

Table 4-779 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
job_id	Yes	String	Task ID.

Request Parameters

Table 4-780 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">en-uszh-cn

Response Parameters

Status code: 400

Table 4-781 Response body parameters

Parameter	Type	Description
error_code	String	Error code.

Parameter	Type	Description
error_msg	String	Error message.

Status code: 500**Table 4-782** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting a specified task record

```
DELETE https://{endpoint}/v3/619d3e78f61b4be68bc5aa0b59edcf7b/jobs/6b00c41d-d54f-4bcb-80da-566ccedc2b5d
```

Example Response

Status code: 200

Success.

```
{}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.13.6 Deleting a Scheduled Task Record

Function

This API is used to delete a scheduled task record. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

```
DELETE /v3/{project_id}/instance/{instance_id}/scheduled-jobs
```

Table 4-783 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request Parameters

Table 4-784 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Table 4-785 Request body parameter

Parameter	Mandatory	Type	Description
job_id	Yes	String	Task ID.

Response Parameters

Status code: 200

Table 4-786 Response body parameters

Parameter	Type	Description
result	Boolean	Returned result.

Status code: 400**Table 4-787** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-788** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Deleting a scheduled task record

```
DELETE https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/instance/  
34cbc6c13e074761a0f893e9f30e6edfin07/scheduled-jobs  
{  
    "job_id" : "54c219a29a5f477ba69e36d0116d05d7"  
}
```

Example Response

Status code: 200

Success.

```
{  
    "result" : true  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

4.14 Intelligent Diagnosis

4.14.1 Querying Abnormal Instances by Each Metric

Function

This API is used to query abnormal instances by each metric. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/diagnosis-instance-count

Table 4-789 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request Parameters

Table 4-790 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. To obtain the value, call the API for obtaining a user token . After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value range: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-791 Response body parameters

Parameter	Type	Description
diagnosis_info	Array of DiagnosisInfo objects	Diagnosis information list.

Table 4-792 DiagnosisInfo

Parameter	Type	Description
metric_name	String	Metric name.
count	Integer	Number of instances.

Status code: 400

Table 4-793 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 4-794 Response body parameters

Parameter	Type	Description
error_code	String	Error code.

Parameter	Type	Description
error_msg	String	Error message.

Example Request

Querying the number of abnormal instances by each metric based on project_id

```
GET https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/instances/diagnosis-instance-count
```

Example Response

Status code: 200

Success.

```
{  
  "diagnosis_info" : [ {  
    "metric_name" : "high_pressure",  
    "count" : 8  
  }, {  
    "metric_name" : "insufficient_capacity",  
    "count" : 0  
  }, {  
    "metric_name" : "slow_sql_frequency",  
    "count" : 0  
  }, {  
    "metric_name" : "mem_overrun",  
    "count" : 0  
  }, {  
    "metric_name" : "connections_exceed",  
    "count" : 0  
  } ]  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

4.14.2 Querying Abnormal Instance Information by a Specific Metric

Function

This API is used to abnormal instance information by a specific metric. Before calling this API:

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/diagnosis-instance-infos

Table 4-795 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 4-796 Query parameters

Parameter	Mandatory	Type	Description
metric_name	Yes	String	Metric name.
offset	Yes	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	Yes	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request Parameters

Table 4-797 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. To obtain the value, call the API for obtaining a user token . After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value range: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 4-798 Response body parameters

Parameter	Type	Description
total_count	Integer	Number of abnormal instances queried by the current metric.
instance_infos	Array of InstanceInfoForDiagnosis objects	Information about the abnormal instances.

Table 4-799 InstanceInfoForDiagnosis

Parameter	Type	Description
instance_id	String	Instance ID.
master_node_id	String	Primary node ID.

Status code: 400

Table 4-800 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 4-801** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying abnormal instance information based on project_id and a metric name
(The information is displayed on multiple pages)

```
GET https://{endpoint}/v3/0483b6b16e954cb88930a360d2c4e663/instances/diagnosis-instance-infos?  
metric_name=high_pressure&offset=0&limit=10
```

Example Response

Status code: 200

Success.

```
{  
    "total_count" : 6,  
    "instance_infos" : [ {  
        "instance_id" : "6206d5be05914703938ff9dfe5c07d34in07",  
        "master_node_id" : "7fe925aa8bab4cc9bac3990a94386c29no07"  
    }, {  
        "instance_id" : "cbdb32e08f0440158c4f2998dbf69b14in07",  
        "master_node_id" : "3e90e7b99b964dca9704b3af903fcba1no07"  
    }, {  
        "instance_id" : "325af119c2ca4e77b1deb4810a9b921bin07",  
        "master_node_id" : "f4dfb362039a45818e59416abc9a5ca6no07"  
    }, {  
        "instance_id" : "9e8b52a5b6e84f4a9e4db01235b1c770in07",  
        "master_node_id" : "408666cd6f104133ad0685b722f88cffno07"  
    }, {  
        "instance_id" : "5814254f12f74d16bd0a93885b00867fin07",  
        "master_node_id" : "637d96ffbf6745ff835445fe87d08fc5no07"  
    }, {  
        "instance_id" : "d0da4882ebdf44bd9d3f1edf9b0bd4a2in07",  
        "master_node_id" : "7a670f4ecdf14db5a4b5df737b0911a5no07"  
    } ]  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

5 APIs (Unavailable Soon)

5.1 DB Engine Version Queries

5.1.1 Querying Version Information About a DB Engine

Function

This API is used to query the version information of a specified DB engine. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Version Information About a DB Engine](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
GET https://`{endpoint}`/mysql/v3/`{project_id}`/datastores/`{database_name}`
- Example
GET https://`{endpoint}`/mysql/v3/619d3e78f61b4be68bc5aa0b59edcf7b/datastores/gaussdb-mysql
- Parameter description

Table 5-1 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
database_name	Yes	DB engine. The following DB engine is supported (case-insensitive): gaussdb-mysql

Request

None.

Response

- Normal response

Table 5-2 Parameter description

Name	Type	Description
datastores	Array of objects	DB versions. For details, see Table 5-3 .

Table 5-3 datastores field data structure description

Name	Type	Description
id	String	DB version ID. Its value is unique.
name	String	DB version number. Only the major version number with two digits is returned.

- Example normal response

```
{  
    "datastores": [  
        {"  
            "id": "87620726-6802-46c0-9028-a8785e1f1921",  
            "name": "8.0"  
        }  
    ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.2 Database Specification Queries

5.2.1 Querying Database Specifications

Function

This API is used to query the database specifications of a specified DB engine version. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Database Specifications](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
`GET https://{{endpoint}}/mysql/v3/{{project_id}}/flavors/{{database_name}}?version_name={{version_name}}&spec_code={{spec_code}}&availability_zone_mode={{availability_zone_mode}}`
- Example
`GET https://{{endpoint}}/mysql/v3/0483b6b16e954cb88930a360d2c4e663/flavors/gaussdb-mysql?version_name=8.0&spec_code=gaussdb.mysql.xlarge.x86.4&availability_zone_mode=single`
- Parameter description

Table 5-4 Parameter description

Name	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
database_name	Yes	String	DB engine. Its value is case-insensitive and can be: gaussdb-mysql

Name	Mandatory	Type	Description
version_name	No	String	DB version number. To obtain this value, see Querying Version Information About a DB Engine . Currently, only MySQL 8.0 is supported.
availability_zone_mode	Yes	String	AZ mode. Its value can be single or multi and is case-insensitive.
spec_code	No	String	Specification code.

Request

None.

Response

- Normal response

Table 5-5 Parameter description

Name	Type	Description
flavors	Array of objects	DB instance specification list. For details, see Table 5-6 .

Table 5-6 flavors field data structure description

Name	Type	Description
vcpus	String	Number of vCPUs. For example, the value 1 indicates 1 vCPU.
ram	String	Memory size in GB.
type	String	Specification type. The value can be arm .
id	String	Specification ID. The value must be unique.
spec_code	String	Resource specification code. Its value is same as the value of flavor_ref .
version_name	String	DB version number.
instance_mode	String	DB instance type. Currently, only the cluster type is supported.

Name	Type	Description
az_status	Map<String, String>	Status of the AZ where the specification belongs. Its value can be any of the following: <ul style="list-style-type: none">● normal: on sale.● unsupported: not supported● sellout: sold out

- Example normal response

```
{  
    "flavors": [  
        {  
            "vcpus": "1",  
            "ram": "4",  
            "type": "x86",  
            "id": "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",  
            "spec_code": "gaussdb.xlarge.x86.4",  
            "instance_mode": "Cluster",  
            "version_name": "8.0",  
            "az_status": {  
                "az1": "normal",  
                "az2": "normal"  
            }  
        },  
        {  
            "vcpus": "2",  
            "ram": "4",  
            "type": "arm",  
            "id": "cefb8fab-c9f7-482f-a97c-e8a0c8abe35b",  
            "spec_code": "gaussdb.mysql.xlarge.x86.2",  
            "instance_mode": "Cluster",  
            "version_name": "8.0",  
            "az_status": {  
                "az1": "normal",  
                "az2": "normal"  
            }  
        }  
    ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3 Instance Management

5.3.1 Creating a DB Instance

Function

This API is used to create a GaussDB(for MySQL) instance. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Creating a DB Instance](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
POST https://[{endpoint}](#)/mysql/v3/{project_id}/instances
- Example
POST https://[{endpoint}](#)/mysql/v3/0483b6b16e954cb88930a360d2c4e663/instances
- Parameter description

Table 5-7 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request

Table 5-8 Parameter description

Name	Mandatory	Type	Description
charge_info	No	Object	Billing mode, which is yearly/monthly or pay-per-use (default setting). For details, see Table 5-9 . Note: You cannot create yearly/monthly instances in a DeC.

Name	Mandatory	Type	Description
name	Yes	String	DB instance name. Instances of the same type can have same names under the same tenant. The value consists of 4 to 64 characters and starts with a letter. It is case-sensitive and contains only letters, digits, hyphens (-), and underscores (_).
datastore	Yes	Object	Database information. For details, see Table 5-10 .
mode	Yes	String	DB instance type, which is case-insensitive. Currently, only the cluster type is supported.
flavor_ref	Yes	String	Specification code. For details, see Table 5-6 .
vpc_id	Yes	String	VPC ID. To obtain this value, use either of the following methods: <ul style="list-style-type: none">Method 1: Log in to the VPC console and view the VPC ID on the VPC details page.Method 2: See "Querying VPCs" in the <i>Virtual Private Cloud API Reference</i>.
subnet_id	Yes	String	Network ID. To obtain this value, use either of the following methods: <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the network ID on the displayed page.Method 2: See "Querying Subnets" in the <i>Virtual Private Cloud API Reference</i>.

Name	Mandatory	Type	Description
security_group_id	No	String	<p>Security group ID.</p> <p>If network ACL is enabled, this parameter cannot be specified. If network ACL is disabled, this parameter is mandatory.</p> <ul style="list-style-type: none">Method 1: Log in to VPC console. Choose Access Control > Security Groups in the navigation pane on the left. On the displayed page, click the target security group. You can view the security group ID on the displayed page.Method 2: See "Querying Security Groups" in the <i>Virtual Private Cloud API Reference</i>.
configuration_id	No	String	Parameter template ID.
password	Yes	String	<p>Database password.</p> <p>Valid value:</p> <p>The password consists of 8 to 32 characters and contains at least three types of the following: uppercase letters, lowercase letters, digits, and special characters (~!@#%^*-_=+?).</p> <p>You are advised to enter a strong password to improve security and prevent security risks such as brute force cracking. If you enter a weak password, the system automatically determines that the password is invalid.</p>
backup_strategy	No	Object	Automated backup policy. For details, see Table 5-11 .
time_zone	No	String	<p>UTC time zone.</p> <ul style="list-style-type: none">If this parameter is not specified, UTC is used by default.If this parameter is specified, the value ranges from UTC-12:00 to UTC+12:00 at the full hour. For example, the parameter can be UTC+08:00 rather than UTC+08:30.
availability_zone_mode	Yes	String	AZ type. It can be single or multi .

Name	Mandatory	Type	Description
master_availability_zone	If availability_zone_mode is set to multi , this parameter is mandatory. If availability_zone_mode is set to single , this parameter cannot be specified.	String	Primary AZ.
slave_count	Yes	Integer	Number of read replicas. The value is from 1 to 9. An instance contains up to 15 read replicas.
region	Yes	String	Region ID. The value cannot be empty. To obtain this value, see Regions and Endpoints .
volume	No	Object	Volume information. This parameter is optional during the creation of yearly/monthly instances. For details, see Table 5-12 .
enterprise_project_id	No	String	Enterprise project ID. This parameter is mandatory when the enterprise project is enabled, and cannot be specified when the enterprise project is disabled.

Name	Mandatory	Type	Description
lower_case_table_names	No	Integer	Whether a kernel table name is case-sensitive. If the value is 1 (by default), the table name is case-insensitive. If the value is 0 , the table name is case-sensitive.
tags	No	Array of objects	<p>Tag list. Instances are created based on tag keys and values.</p> <ul style="list-style-type: none">• <i>{key}</i> indicates the tag key. It must be unique and cannot be empty.• <i>{value}</i> indicates the tag value, which can be empty. <p>To create instances with multiple tag keys and values, separate key-value pairs with commas (,). Up to 20 key-value pairs can be added.</p> <p>For details, see Table 5-13.</p>

Table 5-9 charge_info field data structure description

Name	Mandatory	Type	Description
charge_mode	Yes	String	<p>Billing mode.</p> <p>Valid value:</p> <ul style="list-style-type: none">• prePaid: indicates the yearly/monthly billing mode.• postPaid: indicates the pay-per-use billing mode.
period_type	No	String	<p>Subscription period.</p> <p>Valid value:</p> <ul style="list-style-type: none">• month: The service is subscribed by month.• year: The service is subscribed by year. <p>NOTE This parameter is valid and mandatory if charge_mode is set to prePaid.</p>

Name	Mandatory	Type	Description
period_num	No	Integer	<p>Subscription duration. This parameter is valid and mandatory if charge_mode is set to prePaid.</p> <p>Valid value:</p> <ul style="list-style-type: none">• When period_type is set to month, the parameter value ranges from 1 to 9.• When period_type is set to year, the parameter value ranges from 1 to 3.

Table 5-10 datastore field data structure description

Name	Mandatory	Type	Description
type	Yes	String	DB engine. Currently, only gaussdb-mysql is supported.
version	Yes	String	DB version. For details about supported DB versions, see Querying Version Information About a DB Engine .

Table 5-11 backup_strategy field data structure description

Name	Mandatory	Type	Description
start_time	Yes	String	<p>Automated backup start time. The automated backup will be triggered within one hour after the time specified by this parameter.</p> <p>The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format.</p> <ul style="list-style-type: none">• The HH value must be 1 greater than the hh value.• The values of mm and MM must be the same and must be set to 00. <p>Example value:</p> <ul style="list-style-type: none">• 21:00-22:00

Table 5-12 volume field data structure description

Name	Mandatory	Type	Description
size	Yes	Integer	<p>Disk size. The default value is 40 GB.</p> <p>The value ranges from 40 GB to 128,000 GB and must be a multiple of 10.</p>

Table 5-13 tags field data structure description

Name	Mandatory	Type	Description
key	Yes	String	Tag key. It contains a maximum of 36 Unicode characters. The value cannot be an empty string, a space, or left blank. Only uppercase letters, lowercase letters, digits, hyphens (-), and underscores (_) are allowed.
value	Yes	String	Tag value. It contains a maximum of 43 Unicode characters. It can be an empty string. Only uppercase letters, lowercase letters, digits, periods (.), hyphens (-), and underscores (_) are allowed.

 **NOTE**

The value of **region** in the following is used as an example.

- Request example

```
{  
    "charge_info":{  
        "charge_mode":"postPaid"  
    },  
    "region":"xxx",  
    "name":"gaussdb-2d34",  
    "datastore":{  
        "type":"gaussdb-mysql",  
        "version":"8.0"  
    },  
    "mode":"Cluster",  
    "flavor_ref":"gaussdb.mysql.large.x86_4",  
    "vpc_id":"f7ee62e2-9705-4523-ba49-a85ea1a1fa87",  
    "subnet_id":"140af7bf-a9da-4dcf-8837-34199fd6d186",  
    "security_group_id":"c7f69884-fe2b-4630-8114-70a11499d902",  
    "configuration_id":"43570e0de32e40c5a15f831aa5ce4176pr07",  
    "password":"xxxx",  
    "backup_strategy":{  
        "start_time":"17:00-18:00"  
    },  
    "time_zone":"UTC+08:00",  
    "availability_zone_mode":"multi",  
    "master_availability_zone":"az1pod1",  
    "slave_count":1,  
    "enterprise_project_id":"0",  
    "lower_case_table_names":1  
}
```

Response

- Normal response

Table 5-14 Parameter description

Name	Type	Description
instance	Object	Instance information. For details, see Table 5-15 .
job_id	String	DB instance creation task ID. This parameter is returned only when pay-per-use DB instances are created.
order_id	String	Order ID. This parameter is returned only when yearly/monthly instances are created.

Table 5-15 instance field data structure description

Name	Type	Description
id	String	DB instance ID.
name	String	DB instance name. Instances of the same type can have same names under the same tenant. The value consists of 4 to 64 characters and starts with a letter. It is case-insensitive and contains only letters, digits, hyphens (-), and underscores (_).
status	String	DB instance status. This parameter is returned only when pay-per-use DB instances are created.
datastore	Object	Database information. For details, see Table 5-16 .
mode	String	DB instance type. Currently, only the cluster type is supported.
configuration_id	String	Parameter template ID.
port	String	Database port, which is the same as the request parameter.
backup_strategy	Object	Automated backup policy. For details, see Table 5-17 .

Name	Type	Description
enterprise_project_id	String	Enterprise project ID, which is the same as the request parameter.
region	String	Region ID, which is the same as the request parameter.
availability_zone_mode	String	AZ type, which is the same as the request parameter.
master_availability_zone	String	Primary AZ ID.
vpc_id	String	VPC ID, which is the same as the request parameter.
security_group_id	String	Security group ID, which is the same as the request parameter.
subnet_id	String	Subnet ID, which is the same as the request parameter.
flavor_ref	String	Specification code, which is the same as the request parameter. For details, see Table 5-6 .
charge_info	Object	Billing mode, which is yearly/monthly or pay-per-use. For details, see Table 5-18 .

Table 5-16 datastore field data structure description

Name	Type	Description
type	String	DB Engine
version	String	DB version.

Table 5-17 backup_strategy field data structure description

Name	Type	Description
start_time	String	Backup time window. Automated backups will be triggered during the backup time window.
keep_days	Integer	Backup retention days.

Table 5-18 charge_info field data structure description

Name	Type	Description
charge_mode	String	Billing mode, which is yearly/monthly or pay-per-use.
period_num	Integer	Subscription duration, which is calculated by month. This parameter is valid when charge_mode is set to prePaid (this parameter is valid only for yearly/monthly instances).

 NOTE

The values of **region** and **master_availability_zone** are used as examples.

- Example normal response

```
{  
    "instance":{  
        "id":"5eebbb4c0f9f4a99b42ed1b6334569aain07",  
        "name":"gaussdb-2d34",  
        "status":"BUILD",  
        "datastore":{  
            "type":"gaussdb-mysql",  
            "version":"8.0"  
        },  
        "mode":"Cluster",  
        "configuration_id": "",  
        "port":null,  
        "backup_strategy":{  
            "start_time":null,  
            "keep_days":"7"  
        },  
        "enterprise_project_id": "0",  
        "region":"aaa",  
        "availability_zone_mode":"multi",  
        "master_availability_zone":"aaa",  
        "vpc_id":"f7ee62e2-9705-4523-ba49-a85ea1a1fa87",  
        "security_group_id":"c7f69884-fe2b-4630-8114-70a11499d902",  
        "subnet_id":"140af7bf-a9da-4dcf-8837-34199fd6d186"  
        "charge_info":{  
            "charge_mode":"postPaid"  
        },  
        "flavor_ref":"gaussdb.mysql.large.x86.4"  
    },  
    "job_id":"43672fe5-56bd-47f1-8fd1-595cded08a7c"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.2 Querying DB Instances

Function

This API is used to query instances according to search criteria. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying DB instances](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format

```
GET https://{{endpoint}}/mysql/v3/{{project_id}}/instances?  
id={{id}}&name={{name}}&type={{type}}&datastore_type={{datastore_type}}&vpc_id  
={{vpc_id}}&subnet_id={{subnet_id}}&offset={{offset}}&limit={{limit}}
```

- Example

```
GET https://{{endpoint}}/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/  
instances?  
id=ed7cc6166ec24360a5ed5c5c9c2ed726in01&name=hy&type=Cluster&datast  
ore_type=gaussdb-mysql&vpc_id=19e5d45d-70fd-4a91-87e9-  
b27e71c9891f&subnet_id=bd51fb45-2dcb-4296-8783-8623bfe89bb7&offset=0  
&limit=10
```

- Parameter description

Table 5-19 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
id	String	No	DB instance ID. The asterisk (*) is reserved for the system. If the instance ID starts with an asterisk (*), the value following asterisk (*) is used for fuzzy matching. Otherwise, the instance ID is used for exact matching.

Name	Type	Mandatory	Description
name	String	No	DB instance name. The asterisk (*) is reserved for the system. If the instance name starts with an asterisk (*), the value following asterisk (*) is used for fuzzy matching. Otherwise, the instance name is used for exact matching.
type	String	No	DB instance type to be queried. Currently, only the cluster type is supported.
datastore_type	String	No	DB type. Currently, only gaussdb-mysql is supported.
vpc_id	String	No	VPC ID. <ul style="list-style-type: none">• Method 1: Log in to the VPC console and view the VPC ID on the VPC details page.• Method 2: See "Querying VPCs" in the <i>Virtual Private Cloud API Reference</i>.
subnet_id	String	No	Network ID of the subnet. <ul style="list-style-type: none">• Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the network ID on the displayed page.• Method 2: See "Querying Subnets" in the <i>Virtual Private Cloud API Reference</i>.
offset	Integer	No	Index offset. If offset is set to <i>N</i> , the resource query starts from the <i>N+1</i> piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	Integer	No	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Request

None.

Response

- Normal response

Table 5-20 Parameter description

Name	Type	Description
instances	Array of objects	Instance information. For details, see Table 5-21 .
total_count	Integer	Total number of records.

Table 5-21 instances field data structure description

Name	Type	Description
id	String	DB instance ID.
name	String	DB instance name.
status	String	DB instance status.
private_ips	List<String>	Private IP address for write. It is a blank string until an ECS is created.
public_ips	List<String>	Public IP addresses.
port	String	Database port.
type	String	DB instance type. The value is Cluster .
region	String	Region where the DB instance is deployed.
datastore	Object	Database information. For details, see Table 5-22 .
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 . The value is empty unless the instance creation is complete.
updated	String	Update time. The format is the same as that of the created field. The value is empty unless the instance creation is complete.
db_user_name	String	Default username.

Name	Type	Description
vpc_id	String	VPC ID.
subnet_id	String	Network ID of the subnet.
security_group_id	String	Security group ID.
flavor_ref	String	Specification code. For details, see Table 5-6 .
flavor_info	Object	Specification description.
volume	Object	Volume information. For details, see Table 5-23 .
backup_strategy	Object	Backup policy. For details, see Table 5-25 .
enterprise_project_id	String	Enterprise project ID.
time_zone	String	Time zone.
charge_info	Object	Billing mode, which is yearly/monthly or pay-per-use. By default, pay-per-use is used. For details, see Table 5-26 .

Table 5-22 datastore field data structure description

Name	Type	Description
type	String	DB engine.
version	String	DB version.

Table 5-23 volume field data structure description

Name	Type	Description
type	String	Disk type.
size	String	Used disk size in GB.

Table 5-24 flavor_ref field data structure description

Name	Type	Description
vcpus	String	Number of vCPUs.
ram	String	Memory size in GB.

Table 5-25 backup_strategy field data structure description

Name	Type	Description
start_time	String	Backup time window. Automated backups will be triggered during the backup time window.
keep_days	String	Backup retention days.

Table 5-26 charge_info field data structure description

Name	Type	Description
charge_mode	String	Billing mode. Valid value: <ul style="list-style-type: none">• prePaid: indicates the yearly/monthly billing mode.• postPaid: indicates the pay-per-use billing mode.

NOTE

The value of **region** is used as an example in the following response.

- Example normal response

```
{  
    "total_count":6,  
    "instances": [  
        {  
            "id":"d738399de028480fabb2b8120d4e01a4in07",  
            "status":"ACTIVE",  
            "name":"oMos_001",  
            "port":3306,  
            "type":"Cluster",  
            "private_ips": ["192.168.0.142"],  
            "public_ips": ["10.154.219.187"],  
            "db_user_name": "root",  
            "region": "aaa",  
            "datastore": {"type": "gaussdb-mysql", "version":"8.0"},  
            "created": "2018-08-20T02:33:49+0800",  
            "updated": "2018-08-20T02:33:50+0800",  
            "volume": {  
                "type": "POOL",  
            }  
        }  
    ]  
}
```

```
        "used_size": 100
    },
    "vpc_id": "f7ee62e2-9705-4523-ba49-a85ea1a1fa87",
    "subnet_id": "140af7bf-a9da-4dcf-8837-34199fd6d186",
    "security_group_id": "c7f69884-fe2b-4630-8114-70a11499d902",
    "flavor_ref": "gaussdb.mysql.c3.small.4",
    "backup_strategy": {"start_time": "19:00-20:00", "keep_days": 7},
    "charge_info": {
        "charge_mode": "postPaid"
    },
    "enterprise_project_id": "0",
    "time_zone": ""
}
]
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.3 Querying DB Instances

Function

This API is used to query DB instances according to search criteria. Before calling this API:

NOTICE

This API will be unavailable on December 31, 2025. You are advised to switch workloads to the new API ([Querying DB instances](#)) before then.

URI

GET /v3/{project_id}/instances

Table 5-27 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 5-28 Query parameters

Parameter	Mandatory	Type	Description
id	No	String	Instance ID. The asterisk (*) is reserved for the system. If the instance ID starts with *, it indicates that fuzzy match is performed based on the value following *. Otherwise, the exact match is performed based on the instance ID. The value cannot contain only asterisks (*).
name	No	String	Instance name. The asterisk (*) is reserved for the system. If the instance name starts with *, it indicates that fuzzy match is performed based on the value following *. Otherwise, the exact match is performed based on the instance name. The value cannot contain only asterisks (*).
type	No	String	Instance type to be queried. Currently, only the cluster type is supported.
datastore_type	No	String	DB type. Currently, only gaussdb-mysql is supported.
vpc_id	No	String	VPC ID.
subnet_id	No	String	Network ID of the subnet.
private_ip	No	String	Private IP address.
readonly_private_ip	No	String	Private IP address for read.
proxy_ip	No	String	Read/write splitting address.
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.

Parameter	Mandatory	Type	Description
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
tags	No	String	<p>Query based on the instance tag key and value.</p> <ul style="list-style-type: none">• <i>{key}</i> indicates the tag key.• <i>{value}</i> indicates the tag value. <p>To query instances with multiple tag keys and values, separate key-value pairs with commas (,). The key must be unique. Multiple keys are in AND relationship.</p>

Request Parameters

Table 5-29 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	<p>User token.</p> <p>If the following response body is returned for calling the API used to obtain a user token, the request is successful.</p> <p>After the request is processed, the value of X-Subject-Token in the message header is the token value.</p>
X-Language	No	String	<p>Request language type. The default value is en-us.</p> <p>Value:</p> <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 5-30 Response body parameters

Parameter	Type	Description
instances	Array of MysqlInstanceListInfo objects	Instance list information.
total_count	Integer	Total number of records.

Table 5-31 MysqlInstanceListInfo

Parameter	Type	Description
id	String	Instance ID.
name	String	Instance name.
status	String	Instance status.
private_ips	Array of strings	Private IP address for write. It is left blank until an ECS is created.
readonly_private_ips	Array of strings	Private IP addresses for read. It is left blank until an ECS is created.
proxy_ips	Array of strings	Read/write splitting IP addresses. It is left blank until proxy instances are created for an instance.
public_ips	Array of strings	Public IP addresses.
port	String	Database port.
type	String	DB instance type. The value is Cluster .
region	String	Region where the DB instance is deployed.
datastore	MysqlDatastore object	Database information.
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 . NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.

Parameter	Type	Description
updated	String	Update time. The format is the same as that of the created field. NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.
db_user_name	String	Default username.
vpc_id	String	VPC ID.
subnet_id	String	Network ID of the subnet.
security_group_id	String	Security group ID.
flavor_ref	String	Specification code.
flavor_info	MysqlFlavorInfo object	Flavor information.
volume	MysqlVolumeInfo object	Storage disk information.
backup_strategy	MysqlBackupStrategy object	Automated backup policy.
enterprise_project_id	String	Enterprise project ID.
time_zone	String	Time zone.
charge_info	MysqlChargeInfo object	Billing mode, which is yearly/monthly or pay-per-use (default setting).
dedicated_resource_id	String	Dedicated resource pool ID. This parameter is returned only when the instance belongs to a dedicated resource pool.
tags	Array of InstanceTagItem objects	Tag list.

Table 5-32 MysqlDatastoreWithKernelVersion

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.

Parameter	Type	Description
version	String	DB version. To obtain details about supported DB engine versions, call the API for querying the DB engine versions .
kernel_version	String	Database kernel version.

Table 5-33 MysqlFlavorInfo

Parameter	Type	Description
vcpus	String	Number of vCPUs.
ram	String	Memory size in GB.

Table 5-34 MysqlVolumeInfo

Parameter	Type	Description
type	String	Disk type.
size	String	Used disk size in GB.

Table 5-35 MysqlBackupStrategy

Parameter	Type	Description
start_time	String	Automated backup start time. The automated backup will be triggered within one hour after the time specified by this parameter. The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format. 1. The HH value must be 1 greater than the hh value. 2. The values of mm and MM must be the same and must be set to 00 .
keep_days	String	Automated backup retention days. Value: 1-732 .

Table 5-36 MysqlChargeInfo

Parameter	Type	Description
charge_mode	String	<p>Billing mode.</p> <p>Valid value:</p> <ul style="list-style-type: none">• prePaid: indicates the yearly/monthly billing mode.• postPaid: indicates the pay-per-use billing mode.
period_type	String	<p>Subscription period. This parameter is available and mandatory only when charge_mode is set to prePaid.</p> <p>Valid value:</p> <ul style="list-style-type: none">• month: The service is subscribed by month.• year: The service is subscribed by year.
period_num	Integer	<p>This parameter is valid and mandatory only when charge_mode is set to prePaid.</p> <p>Valid value:</p> <ul style="list-style-type: none">• When period_type is set to month, the parameter value ranges from 1 to 9.• When period_type is set to year, the parameter value ranges from 1 to 3.
is_auto_renew	String	<p>Whether automatic renewal is enabled for yearly/monthly DB instances. The renewal period is the same as the original period and the order will be automatically paid during the subscription renewal.</p> <ul style="list-style-type: none">• true: indicates that automatic renewal is enabled.• false: indicates that automatic renewal is disabled. The default value is false.
is_auto_pay	String	<p>Whether the order will be automatically paid after yearly/monthly instances are created. This parameter does not affect the payment method of automatic renewal.</p> <ul style="list-style-type: none">• true: indicates the order will be automatically paid from your account. The default value is true.• false: indicates the order will be manually paid.

Table 5-37 InstanceTagItem

Parameter	Type	Description
key	String	Tag key.
value	String	Tag value.

Status code: 400**Table 5-38** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 5-39** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying GaussDB(for MySQL) instances whose private IP addresses are 192.168.0.142

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances?  
id=61a4ea66210545909d74a05c27a7179ein07&name=hyAbc&type=Cluster&datastore_type=gaussdb-  
mysql&vpc_id=19e5d45d-70fd-4a91-87e9-  
b27e71c9891f&subnet_id=bd51fb45-2dcb-4296-8783-8623bfe89bb7&private_ip=192.168.0.142&offset=0&li-  
mit=10&tags=taurusKey1=value1
```

Example Response

Status code: 200

The value of **region** is used as an example in the following response.

Success.

```
{  
  "total_count": 1,  
  "instances": [  
    {  
      "id": "d738399de028480fabb2b8120d4e01a4in07",  
      "region": "RegionA",  
      "private_ip": "192.168.0.142",  
      "status": "Normal",  
      "type": "Cluster",  
      "datastore_type": "gaussdb-mysql",  
      "vpc_id": "19e5d45d-70fd-4a91-87e9-b27e71c9891f",  
      "subnet_id": "bd51fb45-2dcb-4296-8783-8623bfe89bb7",  
      "create_time": "2024-02-20T10:00:00Z",  
      "update_time": "2024-02-20T10:00:00Z",  
      "tags": [{"tag": "taurusKey1", "value": "value1"}]  
    }  
  ]  
}
```

```
"name" : "gaussdb-mysql-instance01",
"status" : "ACTIVE",
"port" : 3306,
"type" : "Cluster",
"private_ips" : [ "192.168.0.142" ],
"db_user_name" : "root",
"region" : "aaa",
"datastore" : [
    {
        "type" : "gaussdb-mysql",
        "version" : "8.0",
        "kernel_version" : "2.0.29.1"
    }
],
"created" : "2018-08-20T02:33:49_0800",
"updated" : "2018-08-20T02:33:49_0800",
"volume" : [
    {
        "type" : "POOL",
        "size" : 100
    }
],
"vpc_id" : "3cedfc54-b105-4652-a4e0-847b11576b58",
"subnet_id" : "c1cfa53c-65d3-431e-8552-326bf310c7ad",
"security_group_id" : "fc577a1a-f202-424a-977f-24faec3fdd55",
"flavor_ref" : "gaussdb.mysql.xlarge.x86_4",
"flavor_info" : [
    {
        "vcpus" : 4,
        "ram" : 16
    }
],
"backup_strategy" : [
    {
        "start_time" : "19:00-20:00",
        "keep_days" : 7
    }
],
"charge_info" : [
    {
        "charge_mode" : "postPaid"
    }
],
"enterprise_project_id" : 0,
"time_zone" : "UTC",
"tags" : []
} ]
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.4 Deleting a DB Instance

Function

This API is used to delete a DB instance.

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Deleting or Unsubscribing from a DB Instance](#)) before then.

- Learn how to [authorize and authenticate](#) it.

- Obtain the required [region and endpoint](#).

URI

- URI format
DELETE https://{endpoint}/mysql/v3/{project_id}/instances/{instance_id}
- Example
DELETE https://{endpoint}/mysql/v3/0483b6b16e954cb88930a360d2c4e663/instances/dsfae23fsfdsae3435in01
- Parameter description

Table 5-40 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	Instance ID, which is compliant with the UUID format.

Request

None

Response

- Normal response

Table 5-41 Parameter description

Name	Type	Description
job_id	String	ID of the task for deleting a DB instance.

- Example normal response

```
{  
    "job_id": "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.5 Querying Details of a DB Instance

Function

This API is used to query the details of a specified DB instance. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025.

URI

GET /v3/{project_id}/instances/{instance_id}

Table 5-42 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Request Parameters

Table 5-43 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.

Parameter	Mandatory	Type	Description
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 5-44 Response body parameters

Parameter	Type	Description
instance	MysqlInstanceInfoDetail object	Instance information.

Table 5-45 MysqlInstanceInfoDetail

Parameter	Type	Description
id	String	Instance ID.
name	String	DB instance name.
project_id	String	Project ID of a tenant in a region.

Parameter	Type	Description
status	String	<p>DB instance status.</p> <p>Value:</p> <ul style="list-style-type: none">• BUILD: The DB instance is being created.• ACTIVE: The DB instance is normal.• FAILED: The DB instance is abnormal.• FROZEN: The DB instance is frozen.• MODIFYING: The DB instance is being scaled up.• REBOOTING: The DB instance is being rebooted.• RESTORING: The DB instance is being restored.• MODIFYING INSTANCE TYPE: The DB instance is changing from primary to standby.• SWITCHOVER: A primary/standby switchover is being performed.• MIGRATING: The DB instance is being migrated.• BACKING UP: The DB instance is being backed up.• MODIFYING DATABASE PORT: The database port is being changed.• STORAGE FULL: The DB instance storage space is full.
port	String	Database port.
alias	String	Instance remarks.
type	String	Instance type. The value is Cluster .
charge_info	MysqlInstanceChargeInfo object	Billing mode, which is yearly/monthly or pay-per-use (default setting).
node_count	Integer	Number of nodes.
datastore	MysqlDatastore object	Database information.
backup_used_space	Double	Used backup space in GB.

Parameter	Type	Description
created	String	<p>Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
updated	String	<p>Update time. The format is the same as that of the created field.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
private_write_ips	Array of strings	Private IP address for write.
private_dns_names	Array of strings	Private domain names of the instance. After a DB instance is created, you need to manually apply for a private domain name, or the private domain name is left blank.
public_ips	String	Public IP address of the instance.
db_user_name	String	Default username.
vpc_id	String	VPC ID.
subnet_id	String	Network ID of the subnet.
security_group_id	String	Security group ID.
configuration_id	String	ID of the parameter template used for creating an instance or ID of the latest parameter template that is applied to an instance.
backup_strategy	MysqlBackupStrategy object	Automated backup policy.
nodes	Array of MysqlInstanceNodeInfo objects	Node information.
enterprise_project_id	String	Enterprise project ID.
time_zone	String	Time zone.

Parameter	Type	Description
az_mode	String	AZ type. Value: <ul style="list-style-type: none">• single: single AZ• multi: multiple AZs
master_az_code	String	Primary AZ.
maintenance_window	String	Maintenance window in the UTC format.
tags	Array of MysqlTags objects	Tags for managing instances.
dedicated_resource_id	String	Dedicated resource pool ID. This parameter is returned only when the instance belongs to a dedicated resource pool.
proxies	Array of MysqlProxyInfo objects	Proxy instance information.

Table 5-46 MysqlInstanceChargeInfo

Parameter	Type	Description
charge_mode	String	Billing mode.
order_id	String	Order ID.

Table 5-47 MySqlDatastoreWithKernelVersion

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.
version	String	DB version. For details about supported DB versions, see Querying Version Information About a DB Engine .
kernel_version	String	Database kernel version.

Table 5-48 MysqlBackupStrategy

Parameter	Type	Description
start_time	String	Automated backup start time. The automated backup will be triggered within one hour after the time specified by this parameter. The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format. 1. The HH value must be 1 greater than the hh value. 2. The values of mm and MM must be the same and must be set to 00 .
keep_days	String	Automated backup retention days. Value: 1-732 .

Table 5-49 MysqlInstanceNodeInfo

Parameter	Type	Description
id	String	Instance ID.
name	String	Node name.
type	String	Node type. Value: <ul style="list-style-type: none">• master: primary node• slave: read replica
status	String	Node status.
port	Integer	Database port.
private_read_ips	Array of strings	Private IP address for read of the node.
volume	MysqlInstanceNodeVolumeInfo object	Storage disk information.
az_code	String	AZ.
region_code	String	Region where the instance is located.

Parameter	Type	Description
created	String	<p>Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
updated	String	<p>Update time. The format is the same as that of the created field.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
flavor_id	String	Specification ID.
flavor_ref	String	Specification code.
max_connections	String	Maximum number of connections.
vcpus	String	Number of vCPUs.
ram	String	Memory size in GB.
need_restart	Boolean	Whether to reboot the instance for the parameter modifications to take effect.
priority	Integer	Failover priority.

Table 5-50 MysqlInstanceNodeVolumeInfo

Parameter	Type	Description
type	String	Disk type.
used	String	Used disk size in GB.
size	Long	Disk size of the yearly/monthly instance in GB

Table 5-51 MysqlTags

Parameter	Type	Description
key	String	Tag key. The value can contain a maximum of 36 Unicode characters. The value cannot be an empty string, a space, or left blank. Only uppercase letters, lowercase letters, digits, hyphens (-), and underscores (_) are allowed.
value	String	Tag value. It contains a maximum of 43 Unicode characters. The value can be an empty string. Only uppercase letters, lowercase letters, digits, periods (.), hyphens (-), and underscores (_) are allowed.

Table 5-52 MysqlProxyInfo

Parameter	Type	Description
pool_id	String	Proxy instance ID.
name	String	Proxy instance name.
address	String	Read/Write splitting address of a proxy instance

Status code: 400**Table 5-53** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 5-54** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying details of a specified DB instance

```
GET https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
436aaaf689c4250a9a5bb33cb271e8cin07
```

Example Response

Status code: 201



The values of **region_code** and **az_code** are used as examples.

Success.

```
{  
    "instance": {  
        "id": "d738399de028480fabb2b8120d4e01a4in07",  
        "name": "gaussdb-mysql-instance01",  
        "alias": "",  
        "status": "ACTIVE",  
        "project_id": "3cedfc54-b105-4652-a4e0-847b11576628",  
        "enterprise_project_id": 0,  
        "type": "Cluster",  
        "charge_info": {  
            "charge_mode": "postPaid",  
            "order_id": ""  
        },  
        "node_count": 2,  
        "datastore": {  
            "type": "gaussdb-mysql",  
            "version": "8.0",  
            "kernel_version": "2.0.29.1"  
        },  
        "created": "2022-07-14T16:26:58+0800",  
        "updated": "2022-07-18T14:20:33+0800",  
        "public_ips": [ "10.154.219.187" ],  
        "private_write_ips": [ "192.168.0.142" ],  
        "private_dns_names": [ "d738399de028480fabb2b8120d4e01a4in07.internal.cn-xianhz-1.gaussdbformysql.myhuaweicloud.com" ],  
        "db_user_name": "root",  
        "port": 3306,  
        "vpc_id": "3cedfc54-b105-4652-a4e0-847b11576b58",  
        "subnet_id": "c1cfa53c-65d3-431e-8552-326bf310c7ad",  
        "security_group_id": "fc577a1a-f202-424a-977f-24faec3fdd55",  
        "backup_strategy": {  
            "start_time": "19:00-20:00",  
            "keep_days": 7  
        },  
        "nodes": [ {  
            "id": "799a0f2fa49a4151bf9f7063c1fbba36no07",  
            "name": "gauss-d616-lb07_node01",  
            "type": "master",  
            "status": "ACTIVE",  
            "port": 3306,  
            "private_read_ips": [ "192.168.0.163" ],  
            "volume": {  
                "type": "POOL",  
                "used": 0.07  
            },  
            "az_code": "az1xahz",  
            "region_code": "cn-xianhz-1",  
            "flavor_id": "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",  
            "flavor_ref": "gaussdb.mysql.xlarge.x86.4",  
            "max_connections": 1500,  
            "max_connections": 1500  
        } ]  
    }  
}
```

```
"vcpus" : 4,
"ram" : 16,
"need_restart" : false,
"priority" : 1,
"created" : "2022-07-14T16:26:58+0800",
"updated" : "2022-07-18T09:24:18+0800"
}, {
"id" : "799a0f2fa49a4151bf9f7063c1fbba35no07",
"name" : "gauss-d616-lb07_node02",
"type" : "slave",
"status" : "ACTIVE",
"port" : 3306,
"private_read_ips" : [ "192.168.0.162" ],
"volume" : {
  "type" : "POOL",
  "used" : 0.07
},
"az_code" : "az1xahz",
"region_code" : "cn-xianhz-1",
"flavor_id" : "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
"flavor_ref" : "gaussdb.mysqlxlarge.arm.2.ha",
"max_connections" : 1500,
"vcpus" : 1,
"ram" : 4,
"need_restart" : false,
"priority" : 1,
"created" : "2022-07-14T16:26:58+0800",
"updated" : "2022-07-18T09:36:18+0800"
} ],
"time_zone" : "UTC+08:00",
"backup_used_space" : 0.24,
"az_mode" : "single",
"master_az_code" : "az1",
"maintenance_window" : "18:00-22:00",
"tags" : [ ],
"configuration_id" : "53570e0de54e40c5a15f331aa5sd2176pr07",
"dedicated_resource_id" : "",
"proxies" : [ {
  "pool_id" : "dab1fcf5150c4d1ca0e8c6596bfc0d8cp01",
  "address" : "192.168.10.76",
  "name" : "proxy-name"
}
]
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.6 Querying Details of DB Instances in Batches

Function

This API is used to query details of DB instances in batches. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025.

URI

GET /v3/{project_id}/instances/details

Table 5-55 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Table 5-56 Query parameters

Parameter	Mandatory	Type	Description
instance_ids	Yes	String	Instance ID. A maximum of 20 instance IDs can be entered at a time. Separate them with commas (,).

Request Parameters

Table 5-57 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	User token. If the following response body is returned for calling the API used to obtain a user token , the request is successful. After the request is processed, the value of X-Subject-Token in the message header is the token value.
X-Language	No	String	Request language type. The default value is en-us . Value: <ul style="list-style-type: none">• en-us• zh-cn

Response Parameters

Status code: 200

Table 5-58 Response body parameters

Parameter	Type	Description
instances	Array of MysqlInstanceInfoDetail objects	Instance details.

Table 5-59 MysqlInstanceInfoDetail

Parameter	Type	Description
id	String	Instance ID.
name	String	Instance name.
project_id	String	Project ID of a tenant in a region.
status	String	Instance status. Value: <ul style="list-style-type: none">• BUILD: The DB instance is being created.• ACTIVE: The DB instance is normal.• FAILED: The instance fails to be created.• FROZEN: The DB instance is frozen.• MODIFYING: The DB instance is being scaled up.• REBOOTING: The DB instance is being rebooted.• RESTORING: The DB instance is being restored.• SWITCHOVER: A primary/standby switchover is being performed.• MIGRATING: The DB instance is being migrated.• BACKING UP: The DB instance is being backed up.• MODIFYING DATABASE PORT: The database port is being changed.• STORAGE FULL: The DB instance storage space is full.
port	String	Database port.
alias	String	Instance remarks.

Parameter	Type	Description
type	String	Instance type. The value is Cluster .
charge_info	MysqlInstanceChargeInfo object	Billing mode, which is yearly/monthly or pay-per-use (default setting).
node_count	Integer	Number of nodes.
datastore	MysqlDatastoreWithKernelVersion object	Database information.
backup_used_space	Double	Used backup space in GB.
created	String	<p>Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
updated	String	<p>Update time. The format is the same as that of the created field.</p> <p>NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.</p>
private_write_ips	Array of strings	Private IP address for write.
private_dns_names	Array of strings	Private domain names of the instance. After a DB instance is created, you need to manually apply for a private domain name, or the private domain name is left blank.
public_ips	String	Public IP address of the instance.
db_user_name	String	Default username.
vpc_id	String	VPC ID.
subnet_id	String	Network ID of the subnet.
security_group_id	String	Security group ID.

Parameter	Type	Description
configuration_id	String	ID of the parameter template used for creating an instance or ID of the latest parameter template that is applied to an instance.
backup_strategy	MysqlBackupStrategy object	Automated backup policy.
nodes	Array of MysqlInstanceNodeInfo objects	Node information.
enterprise_project_id	String	Enterprise project ID.
time_zone	String	Time zone.
az_mode	String	AZ type. Value: <ul style="list-style-type: none">• single: single AZ• multi: multiple AZs
master_az_code	String	Primary AZ.
maintenance_window	String	Maintenance window in the UTC format.
tags	Array of MysqlTags objects	Tags for managing instances.
dedicated_resource_id	String	Dedicated resource pool ID. This parameter is returned only when the instance belongs to a dedicated resource pool.
proxies	Array of MysqlProxyInfo objects	Proxy instance information.

Table 5-60 MysqlInstanceChargeInfo

Parameter	Type	Description
charge_mode	String	Billing mode.
order_id	String	Order ID.

Table 5-61 MysqlDatastoreWithKernelVersion

Parameter	Type	Description
type	String	DB engine. Currently, only gaussdb-mysql is supported.
version	String	DB version. For details about supported DB versions, see Querying Version Information About a DB Engine .
kernel_version	String	Database kernel version.

Table 5-62 MysqlBackupStrategy

Parameter	Type	Description
start_time	String	Automated backup start time. The automated backup will be triggered within one hour after the time specified by this parameter. The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format. 1. The HH value must be 1 greater than the hh value. 2. The values of mm and MM must be the same and must be set to 00 .
keep_days	String	Automated backup retention days. Value: 1-732 .

Table 5-63 MysqlInstanceNodeInfo

Parameter	Type	Description
id	String	Instance ID.
name	String	Node name.
type	String	Node type. Value: <ul style="list-style-type: none">• master: primary node• slave: read replica
status	String	Node status.

Parameter	Type	Description
port	Integer	Database port.
private_read_ips	Array of strings	Private IP address for read of the node.
volume	MysqlInstanceNodeVolumeInfo object	Storage disk information.
az_code	String	AZ.
region_code	String	Region where the instance is located.
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 . NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.
updated	String	Update time. The format is the same as that of the created field. NOTE The value is empty when the DB instance is being created. After the DB instance is created, the value is not empty.
flavor_id	String	Specification ID.
flavor_ref	String	Specification code.
max_connections	String	Maximum number of connections.
vcpus	String	Number of vCPUs.
ram	String	Memory size in GB.
need_restart	Boolean	Whether to reboot the instance for the parameter modifications to take effect.
priority	Integer	Failover priority.

Table 5-64 MysqlInstanceNodeVolumeInfo

Parameter	Type	Description
type	String	Disk type.
used	String	Used disk size in GB.
size	Long	Disk size of the yearly/monthly instance in GB

Table 5-65 MySqlTags

Parameter	Type	Description
key	String	Tag key. The value can contain a maximum of 36 Unicode characters. The value cannot be an empty string, a space, or left blank. Only uppercase letters, lowercase letters, digits, hyphens (-), and underscores (_) are allowed.
value	String	Tag value. It contains a maximum of 43 Unicode characters. The value can be an empty string. Only uppercase letters, lowercase letters, digits, periods (.), hyphens (-), and underscores (_) are allowed.

Table 5-66 MySqlProxyInfo

Parameter	Type	Description
pool_id	String	Proxy instance ID.
name	String	Proxy instance name.
address	String	Read/Write splitting address of a proxy instance

Status code: 400**Table 5-67** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 5-68 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

Querying details of DB instances in batches

```
GET https://[endpoint]/v3/97b026aa9cc4417888c14c84a1ad9860/instances/details?  
instance_ids=436aaafb689c4250a9a5bb33cb271e8cin07,d738399de028480fabb2b8120d4e01a4in07
```

Example Response

Status code: 200

Success.

```
{  
    "instances": [ {  
        "id": "d738399de028480fabb2b8120d4e01a4in07",  
        "name": "gaussdb-mysql-instance01",  
        "alias": "",  
        "status": "ACTIVE",  
        "project_id": "3cedfc54-b105-4652-a4e0-847b11576628",  
        "enterprise_project_id": 0,  
        "type": "Cluster",  
        "charge_info": {  
            "charge_mode": "postPaid",  
            "order_id": ""  
        },  
        "node_count": 2,  
        "datastore": {  
            "type": "gaussdb-mysql",  
            "version": "8.0",  
            "kernel_version": "2.0.29.1"  
        },  
        "created": "2022-07-14T16:26:58+0800",  
        "updated": "2022-07-18T14:20:33+0800",  
        "public_ips": [ "10.154.219.187" ],  
        "private_write_ips": [ "192.168.0.142" ],  
        "private_dns_names": [ "11684a0e59e94bceba7880d58cfb07b5in07.internal.cn-xianhz-1.gaussdbformysql.myhuaweicloud.com" ],  
        "db_user_name": "root",  
        "port": 3306,  
        "vpc_id": "3cedfc54-b105-4652-a4e0-847b11576b58",  
        "subnet_id": "c1cfa53c-65d3-431e-8552-326bf310c7ad",  
        "security_group_id": "fc577a1a-f202-424a-977f-24faec3fdd55",  
        "backup_strategy": {  
            "start_time": "19:00-20:00",  
            "keep_days": 7  
        },  
        "nodes": [ {  
            "id": "799a0f2fa49a4151bf9f7063c1fbba36no07",  
            "name": "gauss-d616-lb07_node01",  
            "type": "master",  
            "status": "ACTIVE",  
            "port": 3306,  
            "private_read_ips": [ "192.168.0.163" ],  
            "volume": {  
                "type": "POOL",  
                "size": 100  
            }  
        } ]  
    } ]  
}
```

```
        "used" : 0.07
    },
    "az_code" : "az1xahz",
    "region_code" : "cn-xianhz-1",
    "flavor_id" : "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
    "flavor_ref" : "gaussdb.mysql.xlarge.x86.4",
    "max_connections" : 1500,
    "vcpus" : 4,
    "ram" : 16,
    "need_restart" : false,
    "priority" : 1,
    "created" : "2022-07-14T16:26:58+0800",
    "updated" : "2022-07-18T09:24:18+0800"
}, {
    "id" : "799a0f2fa49a4151bf9f7063c1fbba35no07",
    "name" : "gauss-d616-lb07_node02",
    "type" : "slave",
    "status" : "ACTIVE",
    "port" : 3306,
    "private_read_ips" : [ "192.168.0.162" ],
    "volume" : {
        "type" : "POOL",
        "used" : 0.07
    },
    "az_code" : "az1xahz",
    "region_code" : "cn-xianhz-1",
    "flavor_id" : "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
    "flavor_ref" : "gaussdb.mysql.xlarge.x86.4",
    "max_connections" : 1500,
    "vcpus" : 4,
    "ram" : 16,
    "need_restart" : false,
    "priority" : 1,
    "created" : "2022-07-14T16:26:58+0800",
    "updated" : "2022-07-18T09:36:18+0800"
} ],
    "time_zone" : "UTC+08:00",
    "backup_used_space" : 0.24,
    "az_mode" : "single",
    "master_az_code" : "az1",
    "maintenance_window" : "18:00-22:00",
    "tags" : [ ],
    "configuration_id" : "53570e0de54e40c5a15f331aa5sd2176pr07",
    "dedicated_resource_id" : "",
    "proxies" : [ {
        "pool_id" : "dab1cf5150c4d1ca0e8c6596bfc0d8cp01",
        "address" : "192.168.10.76",
        "name" : "proxy-name"
    } ]
}
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.7 Querying Details of a DB Instance

Function

This API is used to query the details of a specified DB instance. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Details of a DB Instance](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
GET https://[{endpoint}](#)/mysql/v3/{project_id}/instances/{instance_id}
- Example
GET https://[{endpoint}](#)/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/436aaafb689c4250a9a5bb33cb271e8cin07
- Parameter description

Table 5-69 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	Yes	DB instance ID.

Request

None.

Response

- Normal response

Table 5-70 Parameter description

Name	Type	Description
instance	Object	Instance information. For details, see Table 5-71 .

Table 5-71 instance field data structure description

Name	Type	Description
id	String	DB instance ID.
name	String	DB instance name.
project_id	String	Project ID of a tenant in a region.

Name	Type	Description
status	String	<p>DB instance status.</p> <p>Valid value:</p> <p>If the value is BUILD, the DB instance is being created.</p> <p>If the value is ACTIVE, the DB instance is normal.</p> <p>If the value is FAILED, the DB instance is abnormal.</p> <p>If the value is FROZEN, the DB instance is frozen.</p> <p>If the value is MODIFYING, the DB instance is being scaled up.</p> <p>If the value is REBOOTING, the DB instance is being rebooted.</p> <p>If the value is RESTORING, the DB instance is being restored.</p> <p>If the value is MODIFYING INSTANCE TYPE, the DB instance is changing from primary to standby.</p> <p>If the value is SWITCHOVER, the primary/standby switchover is being performed.</p> <p>If the value is MIGRATING, the DB instance is being migrated.</p> <p>If the value is BACKING UP, the DB instance is being backed up.</p> <p>If the value is MODIFYING DATABASE PORT, the database port is being changed.</p> <p>If the value is STORAGE FULL, the instance storage space is full.</p>
enterprise_project_id	String	Enterprise project ID.
type	String	DB instance type. Currently, only the cluster type is supported.
node_count	Integer	Number of nodes.
datastore	Object	Database information. For details, see Table 5-72 .
backup_used_space	Double	Used backup space in GB.

Name	Type	Description
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 . The value is empty unless the instance creation is complete.
updated	String	Update time. The format is the same as that of the created field. The value is empty unless the instance creation is complete.
public_ips	String	Public IP address of the instance.
private_write_ip_s	Array of List	Private IP address for write.
db_user_name	String	Default username.
port	String	Database port.
vpc_id	String	VPC ID.
subnet_id	String	Network ID of the subnet.
security_group_id	String	Security group ID.
volume	Object	Disk information. For details, see Table 5-75 .
backup_strategy	Object	Backup policy. For details, see Table 5-73 .
nodes	Arrays of object	Node information. For details, see Table 5-74 .
time_zone	String	Time zone.
az_mode	String	AZ type. It can be single or multi .
master_az_code	String	Primary AZ.
maintenance_window	String	Maintenance window in the UTC format.
configuration_id	String	ID of the parameter template used for creating an instance or ID of the latest parameter template that is applied to an instance.
tags	Arrays of object	Tags for managing instances. For details, see Table 5-76 .

Table 5-72 datastore field data structure description

Name	Type	Description
type	String	DB engine.
version	String	DB version.

Table 5-73 backup_strategy field data structure description

Name	Type	Description
start_time	String	Backup time window. Automated backups will be triggered during the backup time window.
keep_days	Integer	Backup retention days.

Table 5-74 nodes field data structure description

Name	Type	Description
id	String	Node ID.
name	Array of object	Node name.
type	String	Node type, which can be master or slave .
status	String	Node status.
port	Integer	Database port.
private_read_ips	Array of String	Private IP address for read.
volume	Object	Disk information.
az_code	String	AZ.
region_code	String	Region where the DB instance is deployed.
created	String	DB instance creation time.
updated	String	Update time.
flavor_ref	String	Specification code. For details, see Table 5-6 .
max_connections	String	Maximum number of connections.

Name	Type	Description
vcpus	String	Number of vCPUs.
ram	String	Memory size in GB.
need_restart	Boolean	Whether to reboot the DB instance for the modifications to take effect.
priority	String	Failover priority.

Table 5-75 volume field data structure description

Name	Type	Description
type	String	Storage type. Currently, only POOL is supported.
used	String	Used storage size in GB.

Table 5-76 tags field data structure description

Name	Type	Description
type	String	Tag key. The value can contain a maximum of 36 Unicode characters. The value cannot be an empty string, a space, or left blank. Only uppercase letters, lowercase letters, digits, hyphens (-), and underscores (_) are allowed.
used	String	Tag value. The value contains a maximum of 43 Unicode characters and can also be an empty string. Only uppercase letters, lowercase letters, digits, periods (.), hyphens (-), and underscores (_) are allowed.

 NOTE

The values of **region_code** and **az_code** are used as examples.

- Example normal response

```
{  
  "instance": {  
    "id": "d2cda7b97a39488e8b30e3cea4066204in07",  
    "name": "gauss-d616-lb07",  
    "status": "FAILED",  
    "project_id": "053f533ead80d5102f0cc012e8d468a4",  
    "enterprise_project_id": "0",  
    "type": "Cluster",  
    "charge_info": {
```

```
"charge_mode": "postPaid",
"order_id": ""
},
"node_count": 2,
"datastore": {
  "type": "GaussDB(for MySQL)",
  "version": "8.0"
},
"created": "2020-07-21T09:13:56+0800",
"updated": "2020-07-21T09:27:54+0800",
"public_ips": "",
"private_write_ips": [
  "192.168.0.235"
],
"db_user_name": "root",
"port": "3306",
"vpc_id": "f7ee62e2-9705-4523-ba49-a85ea1a1fa87",
"subnet_id": "140af7bf-a9da-4dcf-8837-34199fd6d186",
"security_group_id": "c7f69884-fe2b-4630-8114-70a11499d902",
"backup_strategy": {
  "start_time": "00:00-00:00",
  "keep_days": "0"
},
"nodes": [
{
  "id": "799a0f2fa49a4151bf9f7063c1fbba36no07",
  "name": "gauss-d616-lb07_node01",
  "type": "master",
  "status": "FAILED",
  "port": 3306,
  "private_read_ips": [
    "192.168.0.163"
  ],
  "volume": {
    "type": "POOL",
    "used": "0.0"
  },
  "az_code": "az1xahz",
  "region_code": "cn-xianhz-1",
  "flavor_id": "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
  "flavor_ref": "gaussdb.large.4",
  "max_connections": null,
  "vcpus": "1",
  "ram": "4",
  "need_restart": false,
  "priority": 1
},
{
  "id": "816459d771c444db9fa4c1d5c173cb1cno07",
  "name": "gauss-d616-lb07_node02",
  "type": "slave",
  "status": "FAILED",
  "port": 3306,
  "private_read_ips": [
    "192.168.0.160"
  ],
  "volume": {
    "type": "POOL",
    "used": "0.0"
  },
  "az_code": "az1xahz",
  "region_code": "cn-xianhz-1",
}
```

```
"flavor_id": "3169caaf-6c2f-41d5-aadd-c8fc3d83597e",
"flavor_ref": "gaussdb.large.4",
"max_connections": null,
"vcpus": "1",
"ram": "4",
"need_restart": false,
"priority": 1
},
],
"time_zone": "UTC+08:00",
"backup_used_space": 0,
"az_mode": "single",
"master_az_code": "az1xahz",
"maintenance_window": "18:00-22:00"
}
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.8 Creating a Read Replica

Function

This API is used to create a read replica. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Creating a Read Replica](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
POST https://[endpoint]/mysql/v3/{project_id}/instances/{instance_id}/nodes/enlarge
- Example
POST https://[endpoint]/mysql/v3/0483b6b16e954cb88930a360d2c4e663/instances/dsfae23fsfdsae3435in01/nodes/enlarge
- Parameter description

Table 5-77 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	Instance ID, which is compliant with the UUID format.

Request

Table 5-78 Parameter description

Name	Mandatory	Type	Description
priorities	Yes	List<Integer>	Failover priority of a read replica. Failover priority ranges from 1 for the first priority to 16 for the last priority. This priority determines the order in which read replicas are promoted when recovering from a primary node failure. Read replicas with the same priority have a same probability of being promoted to the new primary node.
is_auto_pay	No	String	Whether the order will be automatically paid after yearly/monthly instances are created. <ul style="list-style-type: none">• true: indicates the order will be automatically paid from your account. The default value is true.• false: indicates the order will be manually paid.

- Request example

```
{  
    "priorities": [1],  
}
```

Response

- Normal response

Table 5-79 Parameter description

Name	Type	Description
instance_id	String	DB instance ID.
node_names	List<String>	Node name.
job_id	String	ID of the task for creating a read replica.
order_id	String	Order ID. This parameter is returned only when yearly/monthly instances are created.

- Example normal response

```
{  
    "instance_id": "f381d0b539e644df8f5b0d3a62129515in07",  
    "node_names": ["gauss-ccf5_node03"],  
    "job_id": "0f6b6a9e-bd39-4e95-9374-e4d134e5a3d1"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.9 Deleting a Read Replica

Function

This API is used to delete a read replica. For multi-AZ deployment, the primary node and remaining read replicas must be located in different AZs after read replicas are deleted. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Deleting or Unsubscribing from a Read Replica](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format

DELETE https://[endpoint]/mysql/v3/{project_id}/instances/{instance_id}/nodes/{node_id}

- Example

DELETE https://[endpoint]/mysql/v3/0483b6b16e954cb88930a360d2c4e663/instances/dsfae23fsfdsae3435in01/nodes/d11ae66fsfdsaer3w3ino9

- Parameter description

Table 5-80 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	Instance ID, which is compliant with the UUID format.
node_id	Yes	Read-only node ID, which is compliant with the UUID format.

Request

None

Response

- Normal response

Table 5-81 Parameter description

Name	Type	Description
job_id	String	ID of the task for deleting a read replica.

- Example normal response

```
{  
    "job_id": "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.10 Scaling up Storage of a Yearly/Monthly DB Instance

Function

This API is used to scale up storage space of a yearly/monthly DB instance. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Scaling up Storage of a Yearly/Monthly DB Instance](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
POST https://[endpoint]/mysql/v3/{project_id}/instances/{instance_id}/volume/extend
- Example
POST https://[endpoint]/mysql/v3/0483b6b16e954cb88930a360d2c4e663/instances/dsfae23fsfdsae3435in01/volume/extend
- Parameter description

Table 5-82 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	Instance ID, which is compliant with the UUID format.

Request

Table 5-83 Parameter description

Name	Mandatory	Type	Description
size	Yes	Integer	Storage space after expansion. The value ranges from 40 GB to 128,000 GB. The minimum increment for each scaling is 10 GB.
is_auto_pay	No	String	Whether the order will be automatically paid. <ul style="list-style-type: none">• true: indicates the order will be automatically paid from your account. The default value is true.• false: indicates the order will be manually paid.

- Request example

```
{  
  "size":50,  
  "is_auto_pay":"true"  
}
```

Response

- Normal response

Table 5-84 Parameter description

Name	Type	Description
size	Integer	Storage space after expansion.
order_id	String	Order ID.

- Example normal response

```
{  
  "size":50,  
  "order_id": "CS2006231950I8NQA"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.11 Changing a DB Instance Name

Function

This API is used to change a DB instance name. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Changing a DB Instance Name](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
PUT https://[{endpoint}](#)/mysql/v3/[{project_id}](#)/instances/[{instance_id}](#)/name
- Example
PUT https://[{endpoint}](#)/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/c3ec2c6148ad4d71b1a8411a62df0d3cin07/name
- Parameter description

Table 5-85 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	Yes	DB instance ID.

Request

Table 5-86 Parameter description

Name	Type	Mandatory	Description
name	String	Yes	DB instance name. Instances of the same type can have same names under the same tenant. The value consists of 4 to 64 characters and starts with a letter. It is case-sensitive and contains only letters, digits, hyphens (-), and underscores (_).

- Request example

```
{  
    "name": "gaussdb-name"  
}
```

Response

- Normal response

Table 5-87 Parameter description

Name	Type	Description
job_id	String	Task ID for changing an instance name.

- Example normal response

```
{  
    "job_id": "0f6b6a9e-bd39-4e95-9374-e4d134e5a3d1"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.12 Resetting a Database Password

Function

This API is used to reset a database password. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Resetting a Database Password](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
POST https://[{endpoint}](#)/mysql/v3/{project_id}/instances/{instance_id}/password
- Example
POST https://[{endpoint}](#)/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/c3ec2c6148ad4d71b1a8411a62df0d3cin07/password
- Parameter description

Table 5-88 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	No	DB instance ID.

Request

Table 5-89 Parameter description

Name	Type	Mandatory	Description
password	String	Yes	<p>Database password.</p> <p>Valid value:</p> <p>The password consists of 8 to 32 characters and contains at least three types of the following: uppercase letters, lowercase letters, digits, and special characters (~!@#\$%^*-_=+?,()&).</p> <p>You are advised to enter a strong password to improve security and prevent security risks such as brute force cracking. If you enter a weak password, the system automatically determines that the password is invalid.</p>

- Request example

```
{ "password": "Test_345612" }
```

Response

- Normal response
None
- Example normal response

```
{}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.3.13 Modifying DB Instance Specifications

Function

This API is used to change DB instance specifications. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Changing DB Instance Specifications](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
POST https://[{endpoint}](#)/mysql/v3/{project_id}/instances/{instance_id}/action
- Example
POST https://[{endpoint}](#)/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/c3ec2c6148ad4d71b1a8411a62df0d3cin07/action
- Parameter description

Table 5-90 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	No	DB instance ID.

Request

Table 5-91 Parameter description

Name	Type	Mandatory	Description
resize_flavor	Object	Yes	For details, see Table 5-92 .

Name	Type	Mandatory	Description
is_auto_pay	String	No	<p>Whether the order will be automatically paid when the specifications of yearly/monthly instances are changed.</p> <ul style="list-style-type: none">• true: indicates the order will be automatically paid from your account. The default value is true.• false: indicates the order will be manually paid.

Table 5-92 resize_flavor field data structure description

Name	Type	Mandatory	Description
spec_code	String	Yes	Specification code.

- Request example

```
{  
  "resize_flavor": {  
    "spec_code":"gaussdb.large.4"  
  }  
}
```

Response

- Normal response

Table 5-93 Parameter description

Name	Type	Description
job_id	String	Job ID for changing DB instance specifications. This parameter is returned only when you change the specifications of a pay-per-use DB instance.

Name	Type	Description
order_id	String	Order ID for changing DB instance specifications. This parameter is returned only when you change the specification of a yearly/monthly DB instance.

- Example normal response

```
{  
  "job_id": "0f6b6a9e-bd39-4e95-9374-e4d134e5a3d1"  
}
```

Example Request

Changing instance specifications

```
POST https://{endpoint}/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/  
ba62a0b83a1b42bfab275829d86ac0fdin07/action  
{  
  "resize_flavor": {  
    "spec_code": "taurus.large.4"  
  }  
}
```

Example Response

None

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.4 Backup Management

5.4.1 Modifying the Automated Backup Policy

Function

This API is used to modify the automated backup policy. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Configuring a Same-Region Backup Policy](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
PUT https://{{endpoint}}/mysql/v3/{{project_id}}/instances/{{instance_id}}/backups/policy/update
- Example
PUT https://{{endpoint}}/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/c3ec2c6148ad4d71b1a8411a62df0d3cin07/backups/policy/update
- Parameter description

Table 5-94 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	No	DB instance ID.

Request

Table 5-95 Parameter description

Name	Type	Mandatory	Description
backup_policy	object	Yes	Backup policy information. For details, see Table 5-96 .

Table 5-96 backup_policy field data structure description

Name	Type	Mandatory	Description
keep_days	Integer	Yes	Backup retention days. The value ranges from 1 to 732.

Name	Type	Mandatory	Description
start_time	String	Yes	<p>Backup time window. Automated backups will be triggered during the backup time window.</p> <p>The value cannot be empty. It must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format.</p> <ul style="list-style-type: none">• The HH value must be 1 greater than the hh value.• The values of mm and MM must be the same and must be set to 00. <p>Example value:</p> <ul style="list-style-type: none">• 21:00-22:00
period	String	Yes	<p>Backup cycle configuration. Data will be automatically backed up on the selected days every week.</p> <p>Value range: The value is a number separated by commas (,), indicating the days of the week.</p> <p>For example, the value 1,2,3,4 indicates that the backup period is Monday, Tuesday, Wednesday, and Thursday.</p>
retention_num_backup_level1	Integer	No	<p>Number of retained level-1 backups. The default value is 0. This parameter is mandatory when the level-1 backup function is enabled. This parameter is unavailable when the level-1 backup function is disabled. Value:</p> <ul style="list-style-type: none">• 0• 1

- Request example

```
{  
    "backup_policy": {  
        "keep_days": 7,  
        "start_time": "19:00-20:00",  
        "period": "1,2,3,4,5"  
    }  
}
```

Response

- Normal response

Table 5-97 Parameter description

Name	Type	Description
status	String	Backup status. Value: <ul style="list-style-type: none">BUILDING: Modification in progressCOMPLETED: Modification completedFAILED: Modification failed
instance_id	String	DB instance ID.
instance_name	String	DB instance name.

- Example normal response

```
{  
  "status": "COMPLETED",  
  "instance_id": "ef25188419f941309882d2986b2210b9in07",  
  "instance_name": "gauss-fhc"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.4.2 Creating a Manual Backup

Function

This API is used to create a manual backup. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Creating a Manual Backup](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
POST https://[endpoint]/mysql/v3/{project_id}/backups/create
- Example
POST https://[endpoint]/mysql/v3/0483b6b16e954cb88930a360d2c4e663/backups/create
- Parameter description

Table 5-98 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request

Table 5-99 Parameter description

Name	Mandatory	Type	Description
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.
name	Yes	String	Backup name. The value consists of 4 to 64 characters and starts with a letter. It is case-sensitive and contains only letters, digits, hyphens (-), and underscores (_).
description	No	String	Backup description. It contains a maximum of 256 characters and cannot contain the special characters (>!<"&=)

- Request example

```
{  
    "instance_id": "d8e6ca5a624745bcb546a227aa3ae1cf1n01",  
    "name": "backup-1",  
    "description": "manual backup"  
}
```

Response

- Normal response

Table 5-100 Parameter description

Name	Type	Description
backup	Object	Backup information. For details, see Table 5-101 .

Table 5-101 backup field data structure description

Name	Type	Description
id	String	Backup ID.
name	String	Backup name.
description	String	Backup description.
begin_time	String	Backup start time in the "yyyy-mm-ddThh:mm:ssZ" format, where "T" indicates the start time of the time field, and "Z" indicates the time zone offset.
status	String	Backup status. Value: <ul style="list-style-type: none">• BUILDING: Backup in progress• COMPLETED: Backup completed• FAILED: Backup failed• AVAILABLE: Backup available
type	String	Backup type. Value: <ul style="list-style-type: none">• manual: manual full backup
instance_id	String	DB instance ID.

- Example normal response

```
{  
"backup": {  
"id": "2f4ddb93-b901-4b08-93d8-1d2e472f30fe",  
"name": "backup-1",  
"begin_time": "2020-07-07T01:17:05+0800",  
"status": "BUILDING",  
"type": "manual",  
"instance_id": "d8e6ca5a624745bcb546a227aa3ae1cf01",  
"description": "desc"  
}  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.4.3 Querying Backups

Function

This API is used to query backups according to search criteria. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Full Backups](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format

```
GET https://{{endpoint}}/mysql/v3/{{project_id}}/backups?  
instance_id={{instance_id}}&backup_id={{backup_id}}&backup_type={{backup_type}}&offset={{offset}}&limit={{limit}}&begin_time={{begin_time}}&end_time={{end_time}}
```

- Example

```
GET https://{{endpoint}}/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/backups?  
instance_id=c3ec2c6148ad4d71b1a8411a62df0d3cin07&backup_id=43e4feaab  
48f11e89039fa163ebaa7e4br01&backup_type=auto&offset=0&limit=10&begin_time=2020-07-06T10:41:14+0800&end_time=2020-07-16T10:41:14+0800
```

- Parameter description

Table 5-102 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	No	DB instance ID.
backup_id	String	No	Backup ID.

Name	Type	Mandatory	Description
backup_type	String	No	Backup type. Value: <ul style="list-style-type: none">• auto: automated full backup• manual: manual full backup
offset	String	No	Index offset. If offset is set to <i>N</i> , the resource query starts from the <i>N</i> +1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	String	No	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
begin_time	String	No	Query start time. The format is "yyyy-mm-ddThh:mm:ssZ". T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
end_time	String	No	Query end time. The format is "yyyy-mm-ddThh:mm:ssZ" and the end time must be later than the start time. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .

Request

None

Response

- Normal response

Table 5-103 Parameter description

Name	Type	Description
backups	Array of objects	Backup information. For details, see Table 5-104 .

Name	Type	Description
total_count	Integer	Total number of records.

Table 5-104 backups field data structure description

Name	Type	Description
id	String	Backup ID.
name	String	Backup name.
begin_time	String	Backup start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
end_time	String	Backup end time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
status	String	Backup status. Value: <ul style="list-style-type: none">● BUILDING: Backup in progress● COMPLETED: Backup completed● FAILED: Backup failed● AVAILABLE: Backup available
take_up_time	Integer	Backup duration in minutes.
type	String	Backup type. Value: <ul style="list-style-type: none">● auto: automated full backup● manual: manual full backup
size	Double	Backup size in MB.
datastore	Object	Database information. For details, see Table 5-105 .
instance_id	String	DB instance ID.

Name	Type	Description
backup_level	String	Backup level. This parameter is returned when the level-1 backup function is enabled. Value: <ul style="list-style-type: none">• 1: level-1 backup• 2: level-2 backup• 0: Backup being created or creation failed

Table 5-105 datastore field data structure description

Name	Type	Description
type	String	DB engine.
version	String	DB version.

- Example normal response

```
{  
  "backups": [  
    {  
      "id": "43e4feaab48f11e89039fa163ebaa7e4br01",  
      "name": "GaussDBforMySQL-gauss-e747-20200705185048266",  
      "begin_time": "2018-08-06T12:41:14+0800",  
      "end_time": "2018-08-06T12:45:14+0800",  
      "take_up_time": 2,  
      "status": "COMPLETED",  
      "type": "auto",  
      "size": 2803,  
      "datastore": {  
        "type": "gaussdb-mysql",  
        "version": "8.0"  
      },  
      "instance_id": "c3ec2c6148ad4d71b1a8411a62df0d3cin07",  
      "backup_level": "2"  
    }],  
    "total_count": 1  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.4.4 Querying an Automated Backup Policy

Function

This API is used to query an automated backup policy. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying an Automated Backup Policy](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
GET https://{{endpoint}}/mysql/v3/{{project_id}}/instances/{{instance_id}}/backups/policy
- Example
GET https://{{endpoint}}/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/c3ec2c6148ad4d71b1a8411a62df0d3cin07/backups/policy
- Parameter description

Table 5-106 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	Yes	DB instance ID.

Request

None

Response

- Normal response

Table 5-107 Parameter description

Name	Type	Description
backup_policy	object	Backup policy information. For details, see Table 5-108 .

Table 5-108 backup_policy field data structure description

Name	Type	Description
keep_days	Integer	Backup retention days. Value: 1 to 732 Minimum value: 1 . Maximum value: 732
start_time	String	Backup time window. Automated backups will be triggered during the backup time window. The value must be a valid value in the "hh:mm-HH:MM" format. The current time is in the UTC format.
period	String	Backup cycle configuration. Data will be automatically backed up on the selected days every week. Value range: The value is a number separated by commas (,), indicating the days of the week.
retention_num_backup_level1	Integer	Number of retained level-1 backups. This parameter is returned when level-1 backup is enabled.

- Example normal response

```
{  
  "backup_policy": {  
    "keep_days": 7,  
    "start_time": "19:00-20:00",  
    "period": "1,2",  
    "retention_num_backup_level1": 1  
  }  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.5 Parameter Template Management

5.5.1 Querying Parameter Templates

Function

This API is used to query parameter templates, including all databases' default and custom parameter templates. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Parameter Templates](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
GET `https://{{endpoint}}/mysql/v3/{{project_id}}/configurations`
- Example
GET `https://{{endpoint}}/mysql/v3/0483b6b16e954cb88930a360d2c4e663/configurations`
- Parameter description

Table 5-109 Parameter description

Name	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .

Request

None

Response

- Normal response

Table 5-110 Parameter description

Name	Type	Description
configurations	Array of objects	Parameter template list. For details, see Table 5-111 .

Name	Type	Description
total_count	Integer	Total number of parameter templates.

Table 5-111 configurations field data structure description

Name	Type	Description
id	String	Parameter template ID.
name	String	Parameter template name.
description	String	Parameter template description.
datastore_version_name	String	DB version name.
datastore_name	String	DB name.
created	String	Creation time in the "yyyy-MM-ddTHH:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
updated	String	Update time in the "yyyy-MM-ddTHH:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
user_defined	Boolean	Whether the parameter template is a custom template. <ul style="list-style-type: none">• false: The parameter template is a default template.• true: The parameter template is a custom template.

- Example normal response

```
{  
  "configurations": [  
    {  
      "id": "1ad028f5f6b8482483948860feb33339pr07",  
      "name": "DBS_GaussDB_ParameterTemple_Apply_001",  
      "description": "GaussDB-Test",  
      "datastore_version_name": "8.0",  
      "datastore_name": "gaussdb-mysql",  
      "created": "2020-04-08 07:12:17",  
      "updated": "2020-04-08 07:12:17",  
    }  
  ]  
}
```

```
        "user_defined":true,  
    }  
]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.6 Quota Management

5.6.1 Querying the Instance Quotas of a Tenant

Function

This API is used to modify the resource quotas of a specified enterprise project. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying the Instance Quotas of a Tenant](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /mysql/v3/{project_id}/project-quotas

Table 5-112 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. To obtain this value, see Obtaining a Project ID .

Table 5-113 Query parameters

Parameter	Mandatory	Type	Description
type	No	String	Resource type used to filter quotas. Its value can be instance .

Request Parameters

Table 5-114 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	No	String	User token.
X-Language	No	String	Language.

Response Parameters

Status code: 200

Table 5-115 Response body parameters

Parameter	Type	Description
quotas	Object	Tenant instance quota information.

Table 5-116 project-quotas

Parameter	Type	Description
resources	Array of objects	Resource list objects.

Table 5-117 resource

Parameter	Type	Description
type	String	Quota of the specified type. The value is instance , which indicates the instance quota.
used	Integer	Number of created resources.
quota	Integer	Maximum resource quota.

Status code: 400**Table 5-118** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 5-119** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

GET https://{endpoint}/mysql/v3/054e292c9880d4992f02c0196d3ea468/quotas?type=instance

Example Response

Status code: 200

Success.

```
{  
  "quotas": {  
    "resources": [ {  
      "type": "instance",  
      "used": 4,  
      "quota": 50  
    } ]  
  }  
}
```

Status Code

Status Code	Description
200	Success.
400	Client error.
500	Server error.

Error Code

For details, see [Error Codes](#).

5.6.2 Querying Resource Quotas

Function

This API is used to obtain the resource quotas of a specified enterprise project. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying the Resource Quotas of a Specified Enterprise Project](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
GET https://`{endpoint}`/mysql/v3/`{project_id}`/quotas
- Example
GET https://`{endpoint}`/mysql/v3/619d3e78f61b4be68bc5aa0b59edcf7b/quotas
- Parameter description

Table 5-120 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
offset	No	Index offset. If offset is set to <i>N</i> , the resource query starts from the <i>N+1</i> piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Number of records to be queried. The default value is 10 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .

Name	Mandatory	Description
enterprise_project_name	No	Enterprise project name.

Request

None

Response

- Parameter description

Table 5-121 Parameter description

Name	Type	Description
quota_list	Array of objects	Quota information list. For details, see Table 5-122 .
total_count	Integer	Number of quota records.

Table 5-122 quota_list field data structure description

Name	Type	Description
enterprise_project_id	String	Enterprise project ID.
enterprise_project_name	String	Enterprise project name.
instance_quota	Integer	Quota of the DB instance quantity.
vcpus_quota	Integer	Quota of vCPUs.
ram_quota	Integer	Memory quota in GB.
availability_instance_quota	Integer	Remaining quota of DB instances.
availability_vcpus_quota	Integer	Remaining quota of vCPUs.
availability_ram_quota	Integer	Remaining memory quota.

- Example response

```
"quota_list": [  
  {  
    "enterprise_project_id": "0",
```

```
        "enterprise_project_name": "default",
        "instance_quota": 20,
        "vcpus_quota": 20,
        "ram_quota": 40,
        "availability_instance_quota": 1,
        "availability_vcpus_quota": 4,
        "availability_ram_quota": 8
    },
    {
        "enterprise_project_id": "d72ebb42-9110-464c-a8e2-f9b9f349f80f",
        "enterprise_project_name": "eps_auto_test",
        "instance_quota": 0,
        "vcpus_quota": 0,
        "ram_quota": 0,
        "availability_instance_quota": 1,
        "availability_vcpus_quota": 4,
        "availability_ram_quota": 8
    }
],
"total_count": 2
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.6.3 Configuring Resource Quotas

Function

This API is used to configure resource quotas for a specified enterprise project.
Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Configuring Resource Quotas for a Specified Enterprise Project](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
POST https://[{endpoint}](#)/mysql/v3/[{project_id}](#)/quotas
- Example
POST https://[{endpoint}](#)/mysql/v3/0483b6b16e954cb88930a360d2c4e663/quotas

- Parameter description

Table 5-123 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
quota_list	Yes	Quota details. Up to 10 quota records can be configured at a time. For details, see Table 5-124 .

Request

- Parameter description

Table 5-124 quota_list field data structure description

Name	Type	Description
enterprise_project_id	String	Enterprise project ID.
instance_quota	Integer	Quota of the DB instance quantity. The value ranges from 0 to 1000 . (If there are already instances created, this parameter value must be greater than the number of existing instances.)
vcpus_quota	Integer	Quota of vCPUs. Value: 0 to 3600000 . (If there are already instances created, this parameter value must be greater than the number of used vCPUs.)
ram_quota	Integer	Memory quota in GB. Value: 0 to 19200000 . (If there are already instances created, this parameter value must be greater than the used memory size.)

- Request example

```
{  
    "quota_list": [  
        {  
            "enterprise_project_id": "0",  
            "instance_quota": 1,  
            "vcpus_quota": 4,  
            "ram_quota": 8  
        }  
    ]  
}
```

Response

- Parameter description

Table 5-125 Parameter description

Name	Type	Description
quota_list	Array of objects	Configured quota information. For details, see Table 5-126 .

Table 5-126 quota_list field data structure description

Name	Type	Description
enterprise_project_id	String	Enterprise project ID.
instance_quota	Integer	Quota of the DB instance quantity.
vcpus_quota	Integer	Quota of vCPUs.
ram_quota	Integer	Memory quota in GB.

- Example response

```
{  
    "quota_list": [  
        {  
            "enterprise_project_id": "0",  
            "instance_quota": 1,  
            "vcpus_quota": 4,  
            "ram_quota": 8  
        }  
    ]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.6.4 Modifying Resource Quotas

Function

This API is used to modify the resource quotas of a specified enterprise project.
Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Modifying the Resource Quotas of a Specified Enterprise Project](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
PUT https://[{endpoint}/mysql/v3/{project_id}/quotas](#)
- Example
PUT https://[{endpoint}/mysql/v3/0483b6b16e954cb88930a360d2c4e663/quotas](#)
- Parameter description

Table 5-127 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
quota_list	Yes	Enterprise project resource quotas to be updated. A maximum of 10 quotas can be updated at a time. For details, see Table 5-128 .

Request

- Parameter description

Table 5-128 quota_list field data structure description

Name	Type	Description
enterprise_project_id	String	Enterprise project ID.
instance_quota	Integer	Quota of the DB instance quantity. The value ranges from 0 to 1000 . (If there are already DB instances created, this parameter value must be at least the number of existing DB instances.)

Name	Type	Description
vcpus_quota	Integer	Quota of vCPUs. Value: 0 to 3600000 . (If there are already DB instances created, this parameter value must be at least the number of used vCPUs.)
ram_quota	Integer	Memory quota in GB. Memory quota in GB. Value: 0 to 19200000 . (If there are already DB instances created, this parameter value must be at least the used memory size.)

- Request example

```
{  
  "quota_list": [  
    {  
      "enterprise_project_id": "0",  
      "instance_quota": 1,  
      "vcpus_quota": 4,  
      "ram_quota": 8  
    }  
  ]  
}
```

Response

- Parameter description

Table 5-129 Parameter description

Name	Type	Description
quota_list	Array of objects	Configured quota information. For details, see Table 5-130 .

Table 5-130 quota_list field data structure description

Name	Type	Description
enterprise_project_id	String	Enterprise project ID.
instance_quota	Integer	Quota of the DB instance quantity.
vcpus_quota	Integer	Quota of vCPUs.
ram_quota	Integer	Memory quota in GB.

- Example response

```
{  
  "quota_list": [  
    {  
      "enterprise_project_id": "0",  
      "instance_quota": 1,  
      "vcpus_quota": 4,  
      "ram_quota": 8  
    }  
  ]  
}
```

```
        "enterprise_project_id": "0",
        "instance_quota": 1,
        "vcpus_quota": 4,
        "ram_quota": 8
    }
]
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.7 Database Proxy

5.7.1 Creating Proxy Instance

Function

This API is used to create a proxy instance in ELB mode. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Creating a Proxy Instance](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).
- Database proxy is unavailable for DB instances in a DeC.

URI

- URI format
POST https://[endpoint]/mysql/v3/{project_id}/instances/{instance_id}/proxy
- Example
POST https://[endpoint]/mysql/v3/0483b6b16e954cb88930a360d2c4e663/instances/c3ec2c6148ad4d71b1a8411a62df0d3cin07/proxy
- Parameter description

Table 5-131 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
<i>instance_id</i>	Yes	DB instance ID.

Request

Table 5-132 Parameter description

Name	Mandatory	Type	Description
flavor_ref	Yes	String	Proxy specification code.
node_num	Yes	Integer	Number of proxy instance nodes. It is an integer from 2 to 32.

- Request example

```
{  
    "flavor_ref ":"gaussdb.mysql.large.x86.4",  
    "node_num ":2  
}
```

Response

- Normal response

Table 5-133 Parameter description

Name	Type	Description
job_id	String	Job ID for creating a proxy instance.

- Example normal response

```
{  
    "job_id ":"3a4ea53b-3c6c-4f88-9dd0-e21ed77b7e6a"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.7.2 Deleting a Proxy Instance

Function

This API is used to delete a proxy instance. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Deleting a Proxy Instance](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).
- Database proxy is unavailable for DB instances in a DeC.

URI

- URI format
DELETE https://[{endpoint}](#)/mysql/v3/[{project_id}](#)/instances/[{instance_id}](#)/proxy
- Example
DELETE https://[{endpoint}](#)/mysql/v3/0483b6b16e954cb88930a360d2c4e663/instances/dsfae23fsfdsae3435in01/proxy
- Parameter description

Table 5-134 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	Instance ID, which is compliant with the UUID format.

Request

None

Response

- Normal response

Table 5-135 Parameter description

Name	Type	Description
job_id	String	Job ID for deleting a proxy instance.

- Example normal response

```
{  
    "job_id": "dff1d289-4d03-4942-8b9f-463ea07c000d"  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.7.3 Querying Information About a Proxy Instance

Function

This API is used to query information of a proxy instance. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Proxy Instances](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).
- Database proxy is unavailable for DB instances in a DeC.

URI

GET /v3/{project_id}/instances/{instance_id}/proxy

Table 5-136 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Request Parameters

Table 5-137 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	No	String	User token.
X-Language	No	String	Language.

Response Parameters

Status code: 200

Table 5-138 Response body parameters

Parameter	Type	Description
proxy	MysqlProxy object	Proxy instance information.
master_node	MysqlProxyN ode object	Primary node information.
readonly_nodes	Array of MysqlProxyN ode objects	Read replica information.

Table 5-139 MysqlProxy

Parameter	Type	Description
pool_id	String	Proxy instance ID.
status	String	Operating status of the proxy instance. Value: closed , open , frozen , opening , closing , enlarging , freezing , and unfreezing .

Parameter	Type	Description
address	String	Proxy read/write splitting address.
port	Integer	Proxy port information.
pool_status	String	Proxy instance status. Value: ACTIVE , BUILD , FAILED , or DELETED .
delay_threshold_in_seconds	Integer	Delay threshold in seconds.
elb_vip	String	Virtual IP address in ELB mode.
eip	String	EIP information.
vcpus	String	Number of vCPUs of the proxy instance.
ram	String	Memory size of the proxy instance.
node_num	Integer	Number of proxy nodes.
mode	String	Primary/standby proxy. The value is Cluster .
nodes	Array of MysqlProxyNodes objects	Proxy node information.
flavor_ref	String	Proxy specifications.
name	String	Proxy instance name.

Table 5-140 MysqlProxyNodes

Parameter	Type	Description
id	String	Proxy node ID.
status	String	Proxy node status. Value: normal , abnormal , creating , or deleted .
name	String	Proxy node name.
role	String	Role of the proxy node. It can be master or slave .
az_code	String	AZ.
frozen_flag	Integer	Whether the proxy node is frozen. It can be 0 (unfrozen), 1 (frozen), or 2 (deleted after being frozen).

Table 5-141 MysqlProxyNode

Parameter	Type	Description
id	String	Node ID.
instance_id	String	Instance ID.
status	String	Node status.
name	String	Node name.
weight	Integer	Read weight of the node.
available_zones	Array of MysqlProxyAvailable objects	AZ information.

Table 5-142 MysqlProxyAvailable

Parameter	Type	Description
code	String	AZ code.
description	String	AZ description.

Status code: 400**Table 5-143** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 5-144** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/  
096c0fc43e804757b59946b80dc27f8bin07/proxy
```

Example Response

Status code: 200

Success.

```
{  
  "proxy": {  
    "pool_id": "2e7cf21d14794bafab623a334efd9ad8po01",  
    "status": "open",  
    "address": "192.168.125.69",  
    "port": 3306,  
    "pool_status": "ACTIVE",  
    "delay_threshold_in_seconds": 30,  
    "elb_vip": "192.168.125.60",  
    "eip": "192.168.125.50",  
    "vcpus": 4,  
    "ram": 8,  
    "node_num": 2,  
    "mode": "Cluster",  
    "nodes": {  
      "id": "db53a238a02240c49365e72e284a4890pn01",  
      "name": "PROXY-2e7cf21d14794bafab623a334efd9ad8po01_0",  
      "role": "master",  
      "az_code": "az1xahz",  
      "status": "ACTIVE",  
      "frozen_flag": 0  
    },  
    "name": "proxy-name"  
  },  
  "master_node": {  
    "id": "5ee8010ab992460d8d9cffcc5edabb59no07",  
    "instance_id": "7a871d6d494e4327ad2e326afb591108in07",  
    "status": "ACTIVE",  
    "name": "taurus_mysql80_x86-ondemand-2-1U4G_1_202103070251274842281_node01",  
    "weight": 0,  
    "available_zones": {  
      "code": "az1xahz",  
      "description": "AZ1"  
    }  
  },  
  "readonly_nodes": {  
    "id": "d23535333138462880bfa1838fdfced2no07",  
    "instance_id": "7a871d6d494e4327ad2e326afb591108in07",  
    "status": "ACTIVE",  
    "name": "taurus_mysql80_x86-ondemand-2-1U4G_1_202103070251274842281_node02",  
    "weight": 100,  
    "available_zones": {  
      "code": "az1xahz",  
      "description": "AZ1"  
    }  
  }  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.7.4 Querying Proxy Instance Information

Function

This API is used to query information of a proxy instance. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Proxy Instances](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).
- Database proxy is unavailable for DB instances in a DeC.

URI

- URI format
GET https://[{endpoint}](#)/mysql/v3/{project_id}/instances/{instance_id}/proxy
- Example
GET https://[{endpoint}](#)/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/436aaafb689c4250a9a5bb33cb271e8cin07/proxy
- Parameter description

Table 5-145 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	Yes	DB instance ID.

Request

None

Response

- Normal response

Table 5-146 Parameter description

Name	Type	Description
proxy	Object	Proxy instance information. For details, see Table 5-147 .
master_node	Object	Primary node. For details, see Table 5-148 .
readonly_nodes	Array of Object	Read replica information. For details, see Table 5-149 .

Table 5-147 proxy field data structure description

Name	Type	Description
pool_id	String	Proxy instance ID.
status	String	Whether the proxy instance is enabled. It can be closed , open , frozen , opening , closing , enlarging , freezing , or unfreezing .
address	String	Proxy read/write splitting address.
port	Integer	Proxy port information.
pool_status	String	Proxy instance status. It can be abnormal , normal , creating , or deleted .
delay_threshold_in_seconds	Integer	Delay threshold in seconds.
elb_vip	String	Virtual IP address in ELB mode.
eip	String	EIP information.
vcpus	String	Number of vCPUs of the proxy instance.
ram	String	Memory size of the proxy instance.
node_num	Integer	Number of proxy nodes.
mode	String	Primary/standby proxy. It can be Cluster .

Name	Type	Description
nodes	Object	Proxy node information. For details, see Table 5-150 .
flavor_ref	String	Proxy specification code.

Table 5-148 master_node data structure description

Name	Type	Description
id	String	Primary node ID.
instance_id	String	DB instance ID.
status	String	Primary node status.
name	String	Primary node name.
weight	Integer	Read/write splitting weight of the primary node.
available_zones	Array of object	AZ information. For details, see Table 5-151 .

Table 5-149 readonly_nodes field data structure description

Name	Type	Description
id	String	Read replica ID.
instance_id	String	DB instance ID.
status	String	Read replica status.
name	String	Read replica name.
weight	Integer	Read weight of read replicas.
available_zones	Array of object	AZ information.

Table 5-150 nodes field data structure description

Name	Type	Description
id	String	Proxy node ID.
status	String	Proxy node status. It can be normal , abnormal , creating , or deleted .
name	String	Proxy node name.

Name	Type	Description
role	String	Role of the proxy node. It can be master or slave .
az_code	String	AZ.
frozen_flag	Integer	Whether the proxy node is frozen. It can be 0 (unfrozen), 1 (frozen), or 2 (deleted after being frozen).

Table 5-151 available_zones field data structure description

Name	Type	Description
code	String	AZ code.
description	String	AZ description.

- Example normal response

```
{  
  "proxy":{  
    "pool_id":null,  
    "status":"closed",  
    "address":null,  
    "port":null,  
    "pool_status":null,  
    "delay_threshold_in_seconds":null,  
    "elb_vip":null,  
    "eip":null,  
    "vcpus":null,  
    "ram":null,  
    "node_num":null,  
    "mode":null,  
    "nodes": [  
      ],  
    "flavor_ref": "gaussdb.proxy.xlarge.arm.2"  
  },  
  "master_node":{  
    "id": "294daeb0ec9e4c4eacf2c6dbd8246a9no07",  
    "instance_id": "71215aadf19c428db088e51b157583f2in07",  
    "status": "ACTIVE",  
    "name": "BUG-gauss-dw_node01",  
    "weight": null,  
  }  
}
```

```
"available_zones": [
  {
    "code": "az1xahz",
    "description": "az1xahz"
  }
],
},
"readonly_nodes": [
{
  "id": "b36d70cc3c3b4ef680e34c5b25b168dano07",
  "instance_id": "71215aadf19c428db088e51b157583f2in07",
  "status": "ACTIVE",
  "name": "BUG-gauss-dw_node02",
  "weight": null,
  "available_zones": [
    {
      "code": "az1xahz",
      "description": "az1xahz"
    }
  ]
}
]
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.7.5 Querying Proxy Instance Specifications

Function

This API is used to query proxy instance specifications. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Proxy Instance Specifications](#)) before then.

- Learn how to [authorize and authenticate](#) it.

- Obtain the required [region and endpoint](#).
- Database proxy is unavailable for DB instances in a DeC.

URI

- URI format
GET https://{{endpoint}}/mysql/v3/{{project_id}}/instances/{{instance_id}}/proxy/flavors
- Example
GET https://{{endpoint}}/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/436aaafb689c4250a9a5bb33cb271e8cin07/proxy/flavors
- Parameter description

Table 5-152 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	Yes	DB instance ID.

Request

None

Response

- Normal response

Table 5-153 Parameter description

Name	Type	Description
proxy_flavor_groups	Array of Object	Proxy specification groups. For details, see Table 5-154 .

Table 5-154 proxy_flavor_groups field data structure description

Name	Type	Description
group_type	String	Specification group type. It can be x86 or arm .

Name	Type	Description
proxy_flavors	Array of Object	Proxy specifications. For details, see Table 5-155 .

Table 5-155 proxy_flavors field data structure description

Name	Type	Description
id	String	Proxy specification ID.
spec_code	String	Proxy specification code.
vcpus	String	Number of vCPUs. For example, the value 1 indicates 1 vCPU.
ram	String	Memory size in GB.
db_type	String	Database type.
az_status	Map<String, String>	key indicates the AZ ID and value indicates the status of the AZ where the proxy specifications reside. It can be normal or unsupported .

- Example normal response

```
{  
  "proxy_flavor_groups": [  
    {  
      "group_type": "x86",  
      "proxy_flavors": [  
        {  
          "id": "19be4c5d-d363-3342-bdbc-0dd9dbf7fafe",  
          "spec_code": "gaussdb.proxy.large.x86.2",  
          "vcpus": "2",  
          "ram": "4",  
          "db_type": "Proxy",  
          "az_status": {  
            "az1xahz": "normal"  
          }  
        }  
      ]  
    },  
    {  
      "group_type": "arm",  
      "proxy_flavors": [  
        {  
          "id": "19be4c5d-d363-3342-bdbc-0dd9dbf7fafe",  
          "spec_code": "gaussdb.proxy.large.arm.2",  
          "vcpus": "2",  
          "ram": "4",  
          "db_type": "Proxy",  
          "az_status": {  
            "az1xahz": "normal"  
          }  
        }  
      ]  
    }  
  ]  
}
```

```
{  
    "id": "2ff9a704-f238-3e7a-9ed2-208c2542c8b9",  
  
    "spec_code": "gaussdb.proxy.large.arm.2",  
    "vcpus": "2",  
    "ram": "4",  
    "db_type": "Proxy",  
    "az_status": {  
        "az1xahz": "normal"  
    }  
}  
}  
]  
}  
]  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.7.6 Adding Proxy Nodes

Function

This API is used to add proxy nodes. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Adding Proxy Nodes](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).
- Database proxy is unavailable for DB instances in a DeC.

URI

- URI format
POST https://[endpoint]/mysql/v3/{project_id}/instances/{instance_id}/proxy/enlarge
- Example

post https://[endpoint]/mysql/v3/619d3e78f61b4be68bc5aa0b59edcf7b/instances/e73893ef73754465a8bd2e0857bbf13ein07/proxy/enlarge

- Parameter description

Table 5-156 Parameter description

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID, which is compliant with the UUID format.

Request

Table 5-157 Parameter description

Parameter	Mandatory	Type	Description
node_num	Yes	Integer	The number of proxy nodes to be added. The value is an integer from 1 to 30. Restrictions: The total number of proxy nodes for an instance is no more than 32.

- Request example

```
{  
    "node_num" : 2  
}
```

Response

- Normal response

Table 5-158 Parameter description

Parameter	Type	Description
job_id	String	Task ID.

- Example normal response

```
{  
    "job_id" : "04efe8e2-9255-44ae-a98b-d87cae411890"
```

}

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.8 Log Management

5.8.1 Querying Database Error Logs

Function

This API is used to query database error logs. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Error Logs](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
`GET https://{{endpoint}}/mysql/v3/{{project_id}}/instances/{{instance_id}}/errorlog?offset={{offset}}&limit={{limit}}&level={{level}}&start_date={{start_date}}&end_date={{end_date}}&node_id={{node_id}}`
- Example
`GET https://{{endpoint}}/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/instances/c3ec2c6148ad4d71b1a8411a62df0d3cin07/errorlog?offset=0&limit=100&level=ALL&start_date=2018-08-06T10:41:14+0800&end_date=2018-08-07T10:41:14+0800&node_id=cc07c60e94ec4575989840e648fb4f66no07`
- Parameter description

Table 5-159 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	Yes	DB instance ID.
node_id	String	Yes	Instance node ID.
start_date	String	Yes	Start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
end_date	String	Yes	End time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 . Only error logs generated within the last month can be queried.
offset	Integer	No	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The default value is 0 , indicating that the query starts from the first piece of data. The value must be a positive integer and the minimum value is 0 .
limit	Integer	No	Number of records to be queried. The default value is 10 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
level	String	No	Log level. The default value is ALL . Valid value: <ul style="list-style-type: none">• ALL• INFO• WARNING• ERROR• FATAL• NOTE

Request

None.

Response

- Normal response

Table 5-160 Parameter description

Name	Type	Description
error_log_list	Array of objects	Error log details. For details, see Table 3.
total_record	Integer	Total number of records.

Table 5-161 error_log_list parameter description

Name	Type	Description
node_id	String	Node ID.
time	String	Time in the UTC format.
level	String	Log level. <ul style="list-style-type: none">ALLINFOWARNINGERRORFATALNOTE
content	String	Error log content.

- Example normal response

```
{  
  "error_log_list": [  
    {  
      "node_id": "cc07c60e94ec4575989840e648fb4f66no07",  
      "time": "2021-03-06T12:07:05",  
      "level": "ERROR",  
      "content": "[MY013508] [Repl] do failed: 1"  
    }  
  ],
```

```
"total_record":15  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.8.2 Querying Database Error Logs

Function

This API is used to query database error logs. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Error Logs](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/errorlog

Table 5-162 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Table 5-163 Query parameters

Parameter	Mandatory	Type	Description
start_date	Yes	String	Start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
end_date	Yes	String	End time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 . Only error logs generated within the last month can be queried.
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
level	No	String	Log level. The default value is ALL . Valid value: <ul style="list-style-type: none">• ALL• INFO• WARNING• ERROR• FATAL• NOTE

Parameter	Mandatory	Type	Description
node_id	Yes	String	Node ID.

Request Parameters

Table 5-164 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	No	String	User token.
X-Language	No	String	Language.

Response Parameters

Status code: 200

Table 5-165 Response body parameters

Parameter	Type	Description
error_log_list	Array of MysqlErrorLogList objects	Error log details.
total_record	Integer	Total number of records.

Table 5-166 MysqlErrorLogList

Parameter	Type	Description
node_id	String	Node ID.
time	String	Time in the UTC format.
level	String	Log level. <ul style="list-style-type: none">• ALL• INFO• WARNING• ERROR• FATAL• NOTE
content	String	Error log content.

Status code: 400**Table 5-167** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500**Table 5-168** Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

```
GET https://{endpoint}/v3/054e292c9880d4992f02c0196d3ea468/instances/  
096c0fc43e804757b59946b80dc27f8bin07/errorlog?  
offset=0&limit=1&level=ALL&start_date=2022-07-10T00:00:00+0800&end_date=2022-07-19T00:00:00+0800&  
node_id=cc07c60e94ec4575989840e648fb4f66no07
```

Example Response**Status code: 200**

Success.

```
{  
  "error_log_list": [ {  
    "node_id": "cc07c60e94ec4575989840e648fb4f66no07",  
    "time": "2022-07-17T07:34:33",  
    "level": "ERROR",  
    "content": "[MY013508] [Repl] do failed: 1"  
  } ]  
}
```

Status CodeFor details, see [Status Codes](#).**Error Code**For details, see [Error Codes](#).

5.8.3 Querying Database Slow Logs

Function

This API is used to query database slow logs. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Slow Query Logs](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format

GET https://**{endpoint}**/mysql/v3/{project_id}/instances/{instance_id}/slowlog?
offset={offset}&limit={limit}&level={level}&start_date={start_date}&end_date
={end_date}&node_id={node_id}

- Example

GET https://**{endpoint}**/mysql/v3/97b026aa9cc4417888c14c84a1ad9860/
instances/c3ec2c6148ad4d71b1a8411a62df0d3cin07/slowlog?
offset=0&limit=100&level=ALL&start_date=2018-08-06T10:41:14+0800&end_d
ate=2018-08-07T10:41:14+0800&node_id=cc07c60e94ec4575989840e648fb4f6
6no07

- Parameter description

Table 5-169 Parameter description

Name	Type	Mandatory	Description
project_id	String	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	String	Yes	DB instance ID.
node_id	String	Yes	Instance node ID.
start_date	String	Yes	Start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .

Name	Type	Mandatory	Description
end_date	String	Yes	<p>End time in the "yyyy-mm-ddThh:mm:ssZ" format.</p> <p>T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800.</p> <p>Only error logs generated within the last month can be queried.</p>
offset	Integer	No	<p>Index offset. If offset is set to <i>N</i>, the resource query starts from the <i>N+1</i> piece of data. The default value is 0, indicating that the query starts from the first piece of data. The value must be a positive integer and the minimum value is 0.</p>
limit	Integer	No	<p>Number of records to be queried. The default value is 10. The value must be a positive integer. The minimum value is 1 and the maximum value is 100.</p>
type	String	No	<p>Statement type. The default value All. If this parameter is left empty, all statement types are queried. Valid value:</p> <ul style="list-style-type: none">• ALL• INSERT• UPDATE• SELECT• DELETE• CREATE• DROP• ALTER

Request

None.

Response

- Normal response

Table 5-170 Parameter description

Name	Type	Description
slow_log_list	Array of objects	Slow log information. For details, see Table 3.
long_query_time	String	Threshold of slow logs in seconds.
total_record	Integer	Total number of records.

Table 5-171 error_log_list parameter description

Name	Type	Description
node_id	String	Node ID.
time	String	Execution time.
count	String	Number of executions.
lock_time	String	Lock wait time.
rows_sent	String	Number of sent rows.
rows_examined	String	Number of scanned rows.
database	String	Database which slow logs belong to.
users	String	Account.
query_sample	String	Execution syntax.
type	String	Statement type.
start_time	String	Time in the UTC format.
client_ip	String	IP address.

- Example normal response

```
{  
  "slow_log_list": [  
    {  
      "node_id": "cc07c60e94ec4575989840e648fb4f66no07",  
      "count": "1",  
      "time": "1.04899 s",  
      "lock_time": "0.00003 s",  
      "database": "information_schema",  
      "users": "root",  
      "query_sample": "SELECT * FROM performance_schema.events_waits_current;  
      "type": "SELECT",  
      "start_time": "2024-02-20T10:00:00+00:00",  
      "client_ip": "127.0.0.1"  
    }  
  ]  
}
```

```
"rows_sent":"0",
"rows_examined":"0",
"database":"gaussdb-mysql",
"users":"root",
"query_sample":"INSERT INTO time_zone_name (Name, Time_zone_id)
VALUES (N, @time_zone_id);",
"type":"INSERT",
"start_time":"2021-03-25T10:55:16",
"client_ip ":"192.*.*.1"
}
],
"long_query_time":" 10",
"total_record":15
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.8.4 Querying Database Slow Logs

Function

This API is used to query database slow logs. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Querying Slow Query Logs](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

GET /v3/{project_id}/instances/{instance_id}/slowlog

Table 5-172 URI parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
instance_id	Yes	String	Instance ID.

Table 5-173 Query parameters

Parameter	Mandatory	Type	Description
start_date	Yes	String	Start time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
end_date	Yes	String	End time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 . Only error logs generated within the last month can be queried.
offset	No	Integer	Index offset. If offset is set to N , the resource query starts from the N+1 piece of data. The value is 0 by default, indicating that the query starts from the first piece of data. The value cannot be a negative number.

Parameter	Mandatory	Type	Description
limit	No	Integer	Number of records to be queried. The default value is 100 . The value must be a positive integer. The minimum value is 1 and the maximum value is 100 .
type	No	String	Statement type. The default value All . If this parameter is left empty, all statement types are queried. Valid value: <ul style="list-style-type: none">• ALL• INSERT• UPDATE• SELECT• DELETE• CREATE• DROP• ALTER
node_id	Yes	String	Node ID.

Request Parameters

Table 5-174 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	No	String	User token.
X-Language	No	String	Language.

Response Parameters

Status code: 200

Table 5-175 Response body parameters

Parameter	Type	Description
slow_log_list	Array of MysqlSlowLogList objects	Error log details.

Parameter	Type	Description
long_query_time	String	Slow query log threshold.
total_record	Integer	Total number of records.

Table 5-176 MysqlSlowLogList

Parameter	Type	Description
node_id	String	Node ID.
count	String	Number of executions.
time	String	Execution time.
lock_time	String	Lock wait time.
rows_sent	String	Number of sent rows.
rows_examined	String	Number of scanned rows.
database	String	Database which slow logs belong to.
users	String	Account.
query_sample	String	Execution syntax.
type	String	Statement type.
start_time	String	Start time in the UTC format.
client_ip	String	IP address.

Status code: 400**Table 5-177 Response body parameters**

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Status code: 500

Table 5-178 Response body parameters

Parameter	Type	Description
error_code	String	Error code.
error_msg	String	Error message.

Example Request

```
GET https://[endpoint]/v3/054e292c9880d4992f02c0196d3ea468/instances/096c0fc43e804757b59946b80dc27f8bin07/slowlog?offset=0&limit=1&start_date=2022-07-10T00:00:00+0800&end_date=2022-07-19T00:00:00+0800&node_id=cc07c60e94ec4575989840e648fb4f66no07&type=INSERT
```

Example Response

Status code: 200

Success.

```
{
  "slow_log_list": [ {
    "node_id": "cc07c60e94ec4575989840e648fb4f66no07",
    "count": 1,
    "time": "1.04899 s",
    "lock_time": "0.00003 s",
    "rows_sent": 0,
    "rows_examined": 0,
    "database": "gaussdb-mysql",
    "users": "root",
    "query_sample": "INSERT INTO time_zone_name (Name, Time_zone_id) VALUES (N @time_zone_id);",
    "type": "INSERT",
    "start_time": "2021-03-25T10:55:16.000Z",
    "client_ip": "192.*.*.1"
  }],
  "long_query_time": 10,
  "total_record": 15
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

5.9 Task Information Queries

5.9.1 Obtaining Information About a Task

Function

This API is used to obtain task information from the task center. Before calling this API:

NOTICE

This API will be unavailable on March 31, 2025. You are advised to switch workloads to the new API ([Obtaining Information About a Task with a Specified ID](#)) before then.

- Learn how to [authorize and authenticate](#) it.
- Obtain the required [region and endpoint](#).

URI

- URI format
GET `https://{{endpoint}}/mysql/v3/{{project_id}}/jobs?id={{id}}`
- Example
GET `https://{{endpoint}}/mysql/v3/0483b6b16e954cb88930a360d2c4e663/jobs?id=a9767ede-fe0f-4888-9003-e843a4c90514`
- Parameter description

Table 5-179 Parameter description

Name	Mandatory	Description
project_id	Yes	Project ID of a tenant in a region. To obtain this value, see Obtaining a Project ID .
id	Yes	Task ID.

Request

None

Response

- Normal response

Table 5-180 Parameter description

Name	Type	Description
job	Object	Task information. For details, see Table 5-181 .

Table 5-181 job field data structure description

Name	Type	Description
id	String	Task ID.
name	String	Task name.
status	String	Task execution status. Valid value: <ul style="list-style-type: none">• Running: The task is being executed.• Completed: The task is successfully executed.• Failed: The task fails to be executed.
created	String	Creation time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
ended	String	End time in the "yyyy-mm-ddThh:mm:ssZ" format. T is the separator between the calendar and the hourly notation of time. Z indicates the time zone offset. For example, in the Beijing time zone, the time zone offset is shown as +0800 .
process	String	Task execution progress.
instance	Object	DB instance on which the task is executed. For details, see Table 5-182 .
entities	Object	Displayed information varies depending on tasks. For details, see Table 5-183 .
fail_reason	String	Task failure information.

Table 5-182 instances field data structure description

Name	Type	Description
id	String	DB instance ID.
name	String	DB instance name.

Table 5-183 entities field data structure description

Name	Type	Description
instance	Object	DB instance queried in the task. For details, see Table 5-184 .
resource_ids	List<String>	Resource ID involved in a task.

Table 5-184 entities.instance field data structure description

Name	Type	Description
endpoint	String	DB instance connection address.
type	String	DB instance type.
datastore	Object	DB information. For details, see Table 5-185 .

Table 5-185 datastore field data structure description

Name	Type	Description
type	String	DB engine.
version	String	DB version.

Table 5-186 entities field data structure description (binding or unbinding an EIP)

Name	Type	Description
public_ip	String	EIP used in the task.

 **NOTE**

In the response example, some tasks in the task center are used as examples.

- Example normal response

```
{  
  "job": {  
    "id": "31b8ae23-c687-4d80-b7b4-42a66c9bb886",  
    "name": "RestartGaussDBInstance",  
    "status": "Completed",  
    "created": "2018-08-06T10:41:14+0000",  
    "ended": "2018-08-06T16:41:14+0000",  
    "process": "",  
    "instance": {  
      "id": "a48e43ff268f4c0e879652d65e63d0fb01",  
      "name": "DO-NOT-TOUCH-mgr2-gaussdb"  
    },  
    "entities": {}  
  }  
}
```

Status Code

For details, see [Status Codes](#).

Error Code

For details, see [Error Codes](#).

6 Permissions Policies and Supported Actions

6.1 Permissions Policies and Supported Actions

This chapter describes fine-grained permissions management for your GaussDB(for MySQL). If your account does not need individual IAM users, then you may skip over this chapter.

By default, new IAM users do not have permissions assigned. You need to add a user to one or more groups, and attach permissions policies or roles to these groups. Users inherit permissions from the groups to which they are added and can perform specified operations on cloud services based on the permissions.

You can grant users permissions by using **Roles** and **Policies**. Roles are a type of coarse-grained authorization mechanism that defines permissions related to user responsibilities. Policies define API-based permissions for operations on specific resources under certain conditions, allowing for more fine-grained, secure access control of cloud resources.

NOTE

Policy-based authorization is useful if you want to allow or deny the access to an API.

An account has all the permissions required to call all APIs, but IAM users must be assigned the required permissions. The permissions required for calling an API are determined by the actions supported by the API. Only users who have been granted permissions allowing the actions can call the API successfully. For example, if an IAM user queries GaussDB instances using an API, the user must have been granted permissions that allow the **gaussdb:instance:list** action.

Supported Actions

GaussDB(for MySQL) provides system-defined policies that can be directly used in IAM. You can also create custom policies and use them to supplement system-defined policies, implementing more refined access control. Operations supported by policies are specific to APIs. The following are common concepts related to policies:

- Permission: A statement in a policy that allows or denies certain operations.
- APIs: REST APIs that can be called in a custom policy.
- Actions: Added to a custom policy to control permissions for specific operations.
- Related actions: Actions on which a specific action depends to take effect. When assigning permissions for the action to a user, you also need to assign permissions for the dependent actions.
- IAM projects or enterprise projects: Type of projects in which policies can be used to grant permissions. A policy can be applied to IAM projects, enterprise projects, or both. Policies that contain actions supporting both IAM and enterprise projects can be assigned to user groups and take effect in both IAM and Enterprise Management. Policies that only contain actions supporting IAM projects can be assigned to user groups and only take effect for IAM. Such policies will not take effect if they are assigned to user groups in Enterprise Management. For details about the differences between IAM and enterprise projects, see [Differences Between IAM and Enterprise Management](#).

 NOTE

The check mark (✓) indicates that an action takes effect. The cross mark (✗) indicates that an action does not take effect.

6.2 GaussDB(for MySQL) Actions

Table 6-1 Actions

Permissions	APIs	Actions	IAM Project	Enterprise Project
Querying Resource Quotas	GET /mysql/v3/{project_id}/quotas	gaussdb:instance:list	✓	✓
Configuring Resource Quotas	POST /mysql/v3/{project_id}/quotas	gaussdb:quota:modify	✓	✓
Modifying Resource Quotas	PUT /mysql/v3/{project_id}/quotas	gaussdb:quota:modify	✓	✓
Querying Version Information About a DB Engine	GET /mysql/v3/{project_id}/datastores/{database_name}	gaussdb:instance:list	✓	✓

Permissions	APIs	Actions	IAM Project	Enterprise Project
Querying Database Specifications	GET /mysql/v3/{project_id}/flavors/{database}?version_name={version_name}&spec_code={spec_code}	gaussdb:instance:list	✓	✓
Creating a DB Instance	POST /mysql/v3/{projectId}/instances	gaussdb:instance:create	✓	✓
Querying DB Instances	GET /mysql/v3/{projectId}/instances	gaussdb:instance:list	✓	✓
Querying Details of a DB Instance	GET /mysql/v3/{project_id}/instances/{instance_id}	gaussdb:instance:list	✓	✓
Deleting a DB Instance	DELETE /mysql/v3/{project_id}/instances/{instance_id}	gaussdb:instance:delete	✓	✓
Querying Parameter Templates	GET /mysql/v3/{project_id}/configurations	gaussdb:param:list	✓	✓
Obtaining Task Information	GET /mysql/v3/{projectId}/jobs	gaussdb:instance:list	✓	✓
Creating a Read Replica	POST /mysql/v3/{project_id}/instances/{instance_id}/nodes/enlarge	gaussdb:instance:create	✓	✓

Permissions	APIs	Actions	IAM Project	Enterprise Project
Deleting a Read Replica	DELETE /mysql/v3/{project_id}/instances/{instance_id}/nodes/{node_id}	gaussdb:instance:delete	✓	✓
Scaling up Storage Space of a Yearly/Monthly Instance	POST /mysql/v3/{project_id}/instances/{instance_id}/volume/extend	gaussdb:instance:modifySpec	✓	✓
Changing a DB Instance Name	PUT /mysql/v3/{project_id}/instances/{instance_id}/name	gaussdb:instance:modify	✓	✓
Resetting a Database Password	POST /mysql/v3/{project_id}/instances/{instance_id}/password	gaussdb:instance:modify	✓	✓
Changing DB Instance Specifications	POST /mysql/v3/{project_id}/instances/{instance_id}/action	gaussdb:instance:modifySpec	✓	✓
Creating a Manual Backup	POST /mysql/v3/{project_id}/backups/create	gaussdb:backup:create	✓	✓
Querying a Backup List	GET /mysql/v3/{project_id}/backups	gaussdb:backup:list	✓	✓

Permissions	APIs	Actions	IAM Project	Enterprise Project
Querying an Automated Backup Policy	GET /mysql/v3/ {project_id}/ instances/ {instance_id}/ backups/policy	gaussdb:backu p:list	✓	✓
Modifying an Automated Backup Policy	PUT /mysql/v3/ {project_id}/ instances/ {instance_id}/ backups/policy/ update	gaussdb:instan ce:modifyBack upPolicy	✓	✓

A Appendix

A.1 Abnormal Request Results

- Abnormal response description

Table A-1 Abnormal response description

Name	Type	Description
error_code	String	Returned error code when a task submission exception occurs. For details, see Error Codes .
error_msg	String	Returned error description when a task submission exception occurs.

- Example response

```
{  
    "error_code": "DBS.280234",  
    "error_msg": "Invalid DB instance name."  
}
```

A.2 Status Codes

The following table describes status codes.

Table A-2 Status codes

Status Code	Message	Description
100	Continue	The client should continue with its request. This interim response is used to inform the client that the initial part of the request has been received and has not yet been rejected by the server.
101	Switching Protocols	The protocol should be switched. The protocol can only be switched to a more advanced protocol. For example, the current HTTP protocol is switched to a later version.
200	OK	Request succeeded.
201	Created	The request for creating a resource or task has been fulfilled.
202	Accepted	The request has been accepted, but the processing has not been completed.
203	Non-Authoritative Information	Unauthorized information. The request is successful.
204	NoContent	The server has successfully processed the request, but has not returned any content. The status code is returned in response to an HTTP OPTIONS request.
205	Reset Content	The server has fulfilled the request, but the requester is required to reset the content.
206	Partial Content	The server has processed certain GET requests.
300	Multiple Choices	There are multiple options for the location of the requested resource. The response contains a list of resource characteristics and addresses from which the user or user agent (such as a browser) can choose the most appropriate one.
301	Moved Permanently	The requested resource has been assigned a new permanent URI, and the new URI is contained in the response.
302	Found	The requested resource was temporarily moved.
303	See Other	The response to the request can be found under a different URI and should be retrieved using a GET or POST method.

Status Code	Message	Description
304	Not Modified	The requested resource has not been modified. In such a case, there is no need to retransmit the resource since the client still has a previously-downloaded copy.
305	Use Proxy	The requested resource must be accessed through a proxy.
306	Unused	The HTTP status code is no longer used.
400	BadRequest	Invalid request. The client should not repeat the request without modifications.
401	Unauthorized	The status code is returned after the client provides the authentication information, indicating that the authentication information is incorrect or invalid.
402	Payment Required	This status code is reserved for future use.
403	Forbidden	The server understood the request, but is refusing to fulfill it. The client should not repeat the request without modifications.
404	NotFound	The requested resource cannot be found. The client should not repeat the request without modifications.
405	MethodNotAllowed	The method specified in the request is not supported for the requested resource. The client should not repeat the request without modifications.
406	Not Acceptable	The server cannot fulfill the request according to the content characteristics of the request.
407	Proxy Authentication Required	This status code is similar to 401, but indicates that the client must first authenticate itself with the proxy.
408	Request Time-out	The server timed out waiting for the request. The client may repeat the request without modifications at any later time.

Status Code	Message	Description
409	Conflict	<p>The request could not be processed due to a conflict.</p> <p>This status code indicates that the resource that the client attempts to create already exists, or the request fails to be processed because of the update of the conflict request.</p>
410	Gone	<p>The requested resource is no longer available.</p> <p>The requested resource has been deleted permanently.</p>
411	Length Required	<p>The server refuses to process the request without a defined Content-Length.</p>
412	Precondition Failed	<p>The server does not meet one of the preconditions that the requester puts on the request.</p>
413	Request Entity Too Large	<p>The request is larger than that a server is able to process. The server may close the connection to prevent the client from continuing the request. If the server temporarily cannot process the request, the response will contain a Retry-After header field.</p>
414	Request-URI Too Large	<p>The URI provided was too long for the server to process.</p>
415	Unsupported Media Type	<p>The server is unable to process the media format in the request.</p>
416	Requested range not satisfied	<p>The requested range is invalid.</p>
417	Expectation Failed	<p>The server fails to meet the requirements of the Expect request-header field.</p>
422	UnprocessableEntity	<p>The request is well-formed but is unable to be processed due to semantic errors.</p>
429	TooManyRequests	<p>The client has sent more requests than its rate limit is allowed within a given amount of time, or the server has received more requests than it is able to process within a given amount of time. In this case, it is advisable for the client to re-initiate requests after the time specified in the Retry-After header of the response expires.</p>
500	InternalServerError	<p>The server is able to receive the request but it could not understand the request.</p>

Status Code	Message	Description
501	Not Implemented	The server does not support the requested function.
502	Bad Gateway	The server acting as a gateway or proxy receives an invalid response from a remote server.
503	ServiceUnavailable	The requested service is invalid. The client should not repeat the request without modifications.
504	ServerTimeout	The request cannot be fulfilled within a given time. The response will reach the client only if the request carries a timeout parameter.
505	HTTP Version not supported	The server does not support the HTTP protocol version used in the request.

A.3 Error Codes

If an error code starting with **APIGW** is returned after you call an API, rectify the fault by referring to the instructions provided in [Error Codes](#).

The following table describes error codes.

Table A-3 Error codes

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.200 001	Parameter error .	Parameter error.	Check whether the transferred parameters or URLs are correct.
400	DBS.200 004	Parameter error .	Parameter error.	Check whether the transferred parameters or URLs are correct.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.200 006	The request is null. Enter a request parameter.	The request is null. Enter a request parameter.	Check whether any mandatory request parameter is empty.
400	DBS.200 021	Invalid DB instance name.	Invalid DB instance name.	Check whether the instance name is correct.
400	DBS.200 023	Storage space is out of range.	The storage space is out of range.	Check whether the storage space exceeds the allowed range.
400	DBS.200 024	Invalid region.	Invalid region.	Check whether the region is correct and whether the region is available.
400	DBS.200 025	Invalid AZ.	Invalid AZ.	Check whether the AZ name is correct and whether the AZ is available.
400	DBS.200 026	Invalid storage type.	Invalid storage type.	Check whether the storage type is correct.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.200 027	Storage space must be a multiple of 10.	Storage space must be a multiple of 10.	Check whether the storage space is a multiple of 10.
400	DBS.200 040	The DB engine or version is not supported.	The DB engine or version is not supported.	Check whether the DB engine and version match and meet the requirements.
400	DBS.200 041	Invalid database version.	Invalid database version.	Check whether the database version is supported.
400	DBS.200 042	The DB engine does not exist.	The DB engine does not exist.	Check whether the DB engine is supported by GaussDB.
400	DBS.200 043	Invalid synchronize model.	Invalid synchronize model.	Check whether the HA synchronization model meets the requirements.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.200 048	Invalid VPC ID.	Invalid VPC ID.	Check whether the VPC ID and name are correct and meet the requirements.
400	DBS.200 049	Invalid subnet ID.	Invalid subnet ID.	Check whether the subnet ID and name are correct and meet the requirements.
400	DBS.200 051	Invalid HA mode.	Invalid HA mode.	Check whether the HA mode meets the requirements.
400	DBS.200 052	Invalid database root password.	Invalid database root password.	Check whether the username and password match and whether the password meets the requirements.
400	DBS.200 053	The selected specifications do not exist.	The selected specifications do not exist.	Check whether the specifications are correct and available in the current AZ.
400	DBS.200 054	Invalid specifications.	Invalid specifications.	Check whether the specifications are correct and available in the current AZ.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.200 056	The maximum number of nodes has been reached.	The maximum number of nodes has been reached.	Check whether the number of instance nodes reaches the upper limit.
400	DBS.200 063	Invalid cluster mode.	Invalid cluster mode.	Check whether the cluster mode is valid.
400	DBS.200 086	This operation is not allowed by the DB instance status.	This operation is not allowed by the DB instance status.	Check whether the instance status or the ongoing operation on the instance conflicts with the request.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.200 087	The number of tags added for the DB instance has reached the quota.	The number of tags added for the DB instance has reached the quota.	Check whether the number of tags for the DB instance exceeds the upper limit.
400	DBS.200 098	The tag already exists.	The tag already exists.	Check whether the tag exists.
400	DBS.200 302	Storage space must be a multiple of 10.	Storage space must be a multiple of 10.	Check whether the storage space is a multiple of 10.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.200 306	The new storage space must be greater than or equal to the original storage space.	The new storage space must be at least the original storage space.	Check whether the storage space exceeds the upper limit.
400	DBS.200 461	The parameter value is out of range.	The parameter value is out of range.	Check whether the port is valid.
400	DBS.200 504	Invalid database version.	Invalid database version.	Check whether the database version is valid.
400	DBS.200 543	The job does not exist.	The task does not exist.	Check whether the task ID is valid.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.200823	The database does not exist.	The database does not exist.	Check whether the input database does not exist.
400	DBS.200824	The database account does not exist.	The database account does not exist.	Check whether the database account exists.
400	DBS.201014	This operation is not allowed by the DB instance status.	This operation is not allowed by the DB instance status.	Check whether the instance status or the ongoing operation on the instance conflicts with the request.
400	DBS.201101	Invalid backup cycle.	Invalid backup cycle.	Check whether the backup cycle meets the requirements.
400	DBS.201103	Invalid backup start time.	Invalid backup start time.	Check whether the start time meets the requirement.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.201 106	Invalid retention days.	Invalid retention days.	Check whether the backup retention period meets the requirements.
400	DBS.201 203	The backup file does not exist.	The backup file does not exist.	Check whether the backup exists and matches the instance.
400	DBS.201 207	The DB engine or version is not supported.	The DB engine or version is not supported.	Check whether the DB engine is supported by GaussDB.
400	DBS.201 208	The operation is not allowed by the backup status.	The operation is not allowed by the backup status.	Check whether the status of the backup is Completed .

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.212002	Incorrect parameter template quota.	Incorrect parameter template quota.	The parameter template quota exceeds the upper limit. Delete unnecessary parameter templates and create a new one.
400	DBS.212003	Operation not allowed.	The operation is not allowed.	Default parameter templates cannot be reset or deleted.
400	DBS.212004	Parameter group update error.	The parameter template fails to be updated.	Check whether the parameter values to be changed are valid.
400	DBS.212005	The node does not belong to the group.	The node does not belong to the group.	Check whether the instance ID or node ID is correct.
400	DBS.212007	The DB engine does not exist.	The DB engine does not exist.	Check whether the DB engine exists.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.212008	The DB engine is not supported.	The DB engine is not supported.	Check whether the DB engine is supported by GaussDB.
400	DBS.212009	Task processing failed.	The task fails to be processed.	Contact customer service.
400	DBS.212010	The parameter group is being applied.	The parameter template is being applied.	Perform the operation after the application is complete.
400	DBS.212011	Application failed.	Failed to apply the parameter template.	Contact customer service.
400	DBS.212012	The parameter does not exist.	The parameter does not exist.	Check whether the parameter to be modified is correct.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.212014	The node does not have a default parameter template.	The node does not have a default parameter template.	Check whether the node ID or parameter template ID is correct.
400	DBS.212015	Partial success.	Partial success.	Check whether the parameters to be modified are correct.
400	DBS.212016	Parameter update failed.	Parameter update failed.	Contact customer service.
400	DBS.212017	Invalid parameter.	Parameter error.	Check whether the parameter name is valid.
400	DBS.212025	Update failed.	Update failed.	Contact customer service.
400	DBS.212030	Parameter error.	Parameter error.	The parameter template name already exists.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.212032	The parameter template has been applied.	The parameter template has been applied and cannot be deleted.	
400	DBS.212037	Parameters are incorrectly configured.	Check whether the parameter values are valid or within the valid range.	
400	DBS.270024	Proxy instance does not exist.	Check whether the tenant has the proxy instance, whether the input proxy instance ID is correct, and whether the proxy instance exists.	
400	DBS.270025	Invalid weight.	Check whether the weight format and range are correct.	
400	DBS.270026	The proxy type is invalid.	Check whether the database proxy type is correct.	
400	DBS.270027	Select a proxy instance.	No proxy instance is specified.	Check whether the proxy instance ID is null.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.280001	Parameter error.	Parameter error.	Check whether the transferred parameters or URLs are correct and meet the requirements.
400	DBS.280127	Invalid backup description.	Invalid backup description.	Check whether the backup description is correct and meets the requirements.
400	DBS.280128	The database name does not exist.	The database name does not exist.	Check whether the tenant has the DB instance, whether the DB instance name or ID is correct, and whether the DB instance exists.
400	DBS.280203	This is a weak password. Please enter a strong password.	This is a weak password. Enter a strong password.	Password is too easy to guess. Change it to a strong password.
400	DBS.280204	Invalid parameter.	Invalid parameter.	Check whether the parameter values are valid or within the valid range.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.280214	The backup does not exist.	The backup does not exist.	Check whether the backup retention period is correct.
400	DBS.280216	Invalid backup start time.	Invalid backup start time.	Check whether the backup start time meets the requirements and whether the requirements between the backup start time and end time are correct.
400	DBS.280235	Invalid database type.	Invalid database type.	Check whether the DB engine is correct.
400	DBS.280237	Data store not specified.	Datastore is not specified.	Check whether the DB engine is supported by GaussDB.
400	DBS.280238	The DB engine or version is not supported.	The DB engine or version is not supported.	Check whether the DB engine and version match and meet the requirements.
400	DBS.280239	Invalid specifications.	Invalid specifications.	Check whether the specification code is correct, whether the specifications exist in the current AZ, and whether the specifications are supported.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.280241	Invalid storage type.	Invalid storage type.	Check whether the storage type is correct and meets the requirements.
400	DBS.280242	Storage space is out of range.	The storage space is out of range.	Check whether the specified storage space is correct.
400	DBS.280246	Invalid database root password.	Invalid database root password.	Check whether the username and password match and whether the password meets the requirements.
400	DBS.280250	Invalid backup retention days.	Invalid backup retention days.	Check whether the backup data retention period is valid or within the valid range.
400	DBS.280251	Invalid backup cycle.	Invalid backup cycle.	Check whether the backup cycle is valid or within the valid range.
400	DBS.280253	Invalid backup start time.	Invalid backup start time.	Check whether the backup start time meets the requirements and whether the requirements between the backup start time and end time are correct.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.280260	Invalid AZ mode.	Invalid AZ mode.	Check whether the AZ mode is valid.
400	DBS.280270	The parameter does not exist.	The parameter does not exist.	Check whether the parameters to be modified are correct.
400	DBS.280271	The parameter value is out of range.	The parameter value is out of range.	Check whether the parameter value is within the valid range.
400	DBS.280272	The tag key must be unique.	The tag key must be unique.	Check whether the new tag exists.
400	DBS.280277	Invalid object name.	Invalid backup name.	Check whether the backup name is correct and meets the requirements.
400	DBS.280285	Invalid AZ.	Invalid AZ.	Check whether the AZ name is correct and whether the AZ is available.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.280288	Invalid FlavorRef.	Invalid flavor.	Check whether the flavor ID is null or a null string.
400	DBS.280311	Invalid storage space size.	Invalid storage space.	Check whether the specified storage space is correct and meets the requirements.
400	DBS.280325	Invalid storage information.	Invalid storage information.	Check whether the storage space or type is valid.
400	DBS.280342	Invalid cluster mode.	Invalid cluster mode.	Check whether the instance mode is correct and whether the instance mode matches the instance ID.
400	DBS.280364	Invalid database port.	Invalid database port.	Check whether the database port is available.
400	DBS.280402	Invalid HA mode.	Invalid HA mode.	Check whether the HA mode meets the requirements.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.280404	Invalid DB instance ID or node ID format.	Invalid DB instance ID.	Check whether the instance ID is valid.
400	DBS.280434	Invalid specification code.	Invalid specification code.	Check whether the specification code complies with the rules, whether the specification exists, and whether the specification is available.
400	DBS.280439	Invalid records. Enter a positive integer less than 100.	Invalid value. Enter a positive integer of no more than 100.	Check whether the number of queried records is within the valid range.
400	DBS.280448	The storage type is sold out.	The storage type is sold out.	Check whether the current storage type is available.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.280449	Operation not allowed on frozen objects.	Operation not allowed on frozen objects.	Check whether the instance is frozen and whether the current operation can be performed when the instance is frozen.
400	DBS.280450	The DB instance specifications are sold out.	The DB instance specifications are sold out.	Change the AZ or contact customer service.
400	DBS.280500	ELB must be enabled.	ELB must be enabled.	Enable ELB.
400	DBS.280505	CBC error : There are unprocessed orders.	CBC error: There are unprocessed orders.	Check whether the current order has been processed.
400	DBS.290000	Parameter error .	Parameter error.	Check whether the transferred parameters or URLs are correct and meet the requirements.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	DBS.290001	Invalid parameter letter case.	Invalid parameter letter case.	Check whether the parameter letter case is correct and meets the requirements.
403	DBS.200010	The DB instance ID or user ID may be null, or the operation is not authorized.	The DB instance ID or user ID may be null, or the operation is not authorized.	Check whether the input parameters are correct, whether the instance exists, and whether the tenant has unauthorized operations.
403	DBS.200044	Resource not found or permission denied.	Resource not found or permission denied.	Check whether the parameters are correctly configured, whether the access resources exist, and whether the tenant has the access permission.

Status Code	Error Code	Error Message	Description	Troubleshooting
403	DBS.200 604	The DB instance ID or user ID may be null, or the operation is not authorized.	The DB instance ID or user ID may be null, or the operation is not authorized.	Check whether the input parameters are correct, whether the instance exists, and whether the tenant has unauthorized operations.
403	DBS.200 810	You are not allowed to create databases on read replicas.	You are not allowed to create databases on read replicas.	Create databases on the primary node.

Status Code	Error Code	Error Message	Description	Troubleshooting
403	DBS.200819	You are not allowed to delete database users on read replicas.	You are not allowed to delete database users on read replicas.	Database users cannot be deleted from read replicas.
403	DBS.201003	Resource not found or permission denied.	Resource not found or permission denied.	Check whether the parameters are correctly configured, whether the access resources exist, and whether the tenant has the access permission.
403	DBS.280015	Resource not found or permission denied.	Resource not found or permission denied.	Check whether the parameters are correctly configured, whether the access resources exist, and whether the tenant has the access permission.
403	DBS.280056	Invalid token.	Invalid token.	Check whether the instance belongs to the tenant and whether the token has been obtained again.

Status Code	Error Code	Error Message	Description	Troubleshooting
404	DBS.200 002	The DB instance does not exist.	The DB instance does not exist.	Check whether the instance and its ID are correct and whether the instance exists.
404	DBS.200 008	The ECS information of the DB instance cannot be found.	The ECS information of the DB instance cannot be found.	Check whether the parameters are correctly configured and whether the instance status is normal.
404	DBS.200 013	The original DB instance does not exist.	The original DB instance does not exist.	Check whether the instance and its ID are correct and whether the instance exists.
404	DBS.200 045	The DB instance does not exist.	The DB instance does not exist.	Check whether the instance and its ID are correct and whether the instance exists.

Status Code	Error Code	Error Message	Description	Troubleshooting
404	DBS.200 050	The security group does not exist or does not belong to the VPC.	The security group does not exist or does not belong to the VPC.	Check whether the security group ID is valid, whether the security group exists, and whether the private IP address for read of the node belongs to the security group.
404	DBS.200 408	The DB instance does not exist.	The instance does not exist or has been deleted.	Check whether the instance and its ID are correct and whether the instance exists.
404	DBS.200 470	The region or AZ does not exist.	The region or AZ does not exist.	Check whether the AZ is correct.
404	DBS.200 501	The subnet does not exist or does not belong to the VPC.	The subnet does not exist or does not belong to the VPC.	Check whether the subnet ID and name exist and whether the subnet belongs to the VPC.

Status Code	Error Code	Error Message	Description	Troubleshooting
404	DBS.200 503	The VPC does not exist or does not belong to the user.	The VPC does not exist or does not belong to the user.	Check whether the tenant has the VPC.
404	DBS.200 602	The DB instance does not exist.	The DB instance does not exist.	Check whether the instance and its ID are correct and whether the instance exists.
404	DBS.201 010	The backup information does not exist.	The backup information does not exist.	Check whether the backup exists and matches the instance.
404	DBS.201 028	The DB instance does not exist.	The instance does not exist or has been deleted.	Check whether the instance and its ID are correct and whether the instance exists.
404	DBS.212 001	The parameter group does not exist.	The parameter template does not exist.	Check whether the parameter template exists.

Status Code	Error Code	Error Message	Description	Troubleshooting
404	DBS.290002	The selected specifications do not exist.	The selected specifications do not exist.	Check whether the specifications are correct and available in the current AZ.
404	DBS.290005	The DB instance does not exist.	The DB instance does not exist.	Check whether the instance and its ID are correct and whether the instance exists.
404	DBS.290011	The DB instance does not exist.	The DB instance does not exist.	Check whether the instance and its ID are correct and whether the instance exists.
404	DBS.290013	Resource not found.	Resource not found.	Check whether the transferred parameters are correct and whether the DB instance exists.

Status Code	Error Code	Error Message	Description	Troubleshooting
409	DBS.200 011	An other operation is being performed on the DB instance or the DB instance is faulty.	Another operation is being performed on the DB instance or the DB instance is faulty.	Check whether the instance status or the ongoing operation on the instance conflicts with the request.
409	DBS.200 019	An other operation is being performed on the DB instance or the DB instance is faulty.	Another operation is being performed on the DB instance or the DB instance is faulty.	Check whether the instance status or the ongoing operation on the instance conflicts with the request.

Status Code	Error Code	Error Message	Description	Troubleshooting
409	DBS.200 022	The DB instance name already exists.	The DB instance name already exists.	Check whether the instance name exists.
409	DBS.200 047	An other operation is being performed on the DB instance or the DB instance is faulty.	Another operation is being performed on the DB instance or the DB instance is faulty.	Check whether the instance status or the ongoing operation on the instance conflicts with the request.

Status Code	Error Code	Error Message	Description	Troubleshooting
409	DBS.200 316	This operation cannot be performed because the DB instance status is Storage full .	This operation cannot be performed because the DB instance status is Storage full .	Adjust the storage space.
409	DBS.200 826	The database name already exists.	The database name already exists.	Check whether the database name is valid.
409	DBS.200 827	The database user already exists.	The database user already exists.	Check whether the database user is valid.

Status Code	Error Code	Error Message	Description	Troubleshooting
409	DBS.200 828	You are not allowed to create a database built-in account.	You are not allowed to create a database built-in account.	Check whether the database user is valid.
409	DBS.201 202	An other operation is being performed on the DB instance or the DB instance is faulty.	Another operation is being performed on the DB instance or the DB instance is faulty.	Check whether the instance status or the ongoing operation on the instance conflicts with the request.
409	DBS.201 205	Backup is in progress, please wait.	Backup is in progress.	Try again after the backup is complete.

Status Code	Error Code	Error Message	Description	Troubleshooting
409	DBS.212006	An other operation is being performed on the DB instance or the DB instance is faulty.	Another operation is being performed on the DB instance or the DB instance is faulty.	Check whether the instance status or the ongoing operation on the instance conflicts with the request.
409	DBS.280406	Operation not allowed by the DB instance type or status.	Operation not allowed by the DB instance type or status.	Check whether the instance type and instance status meet requirements.

Status Code	Error Code	Error Message	Description	Troubleshooting
413	DBS.200 046	The number of DB instances has reached the quota.	The number of DB instances has reached the quota.	Contact the database administrator to adjust the quota.
413	DBS.290 003	The number of DB instances has reached the quota.	The number of DB instances has reached the quota.	Contact the database administrator to adjust the quota.
422	DBS.212 019	The parameter cannot be processed.	The parameter cannot be processed.	Check whether the parameter is valid.
500	DBS.108 000	Server failure.	Server failure.	Contact customer service.
500	DBS.108 002	Server failure.	Server failure.	Contact customer service.

Status Code	Error Code	Error Message	Description	Troubleshooting
500	DBS.108005	Server failure.	Server failure.	Contact customer service.
500	DBS.200005	Server failure.	Server failure.	Contact customer service.
500	DBS.200208	Server failure.	Server failure.	Contact customer service.
500	DBS.200811	Failed to create the database.	Failed to create the database.	Check whether resources are insufficient and then contact customer service.
500	DBS.200821	Failed to modify database user permissions.	Failed to modify database user permissions.	This operation is not allowed in the current instance status. Try again later.
500	DBS.213002	Failed to process the request.	Failed to process the request.	Internal service error. Contact customer service.
500	DBS.213004	Failed to process the request.	Failed to process the request.	Internal service error. Contact customer service.

Status Code	Error Code	Error Message	Description	Troubleshooting
500	DBS.290006	Failed to process the request.	Failed to process the request.	Internal service error. Contact customer service.
500	DBS.290015	Failed to process the request.	Failed to process the request.	Internal service error. Contact customer service.

A.4 Obtaining a Project ID

Scenarios

When calling APIs, you need to specify the project ID in some URLs. To do so, you need to obtain the project ID first. Two methods are available:

- [Obtaining the Project ID by Calling an API](#)
- [Obtain a Project ID from the Console](#)

Obtaining the Project ID by Calling an API

You can obtain the project ID by calling the API used to [query project information based on the specified criteria](#).

The API used to obtain a project ID is [GET https://{{Endpoint}}/v3/projects](https://{{Endpoint}}/v3/projects). {{Endpoint}} is the IAM endpoint and can be obtained from [Regions and Endpoints](#). For details about API authentication, see [Authentication](#).

The following is an example response. The value of **id** is the project ID.

```
{  
  "projects": [  
    {  
      "domain_id": "65382450e8f64ac0870cd180d14e684b",  
      "is_domain": false,  
      "parent_id": "65382450e8f64ac0870cd180d14e684b",  
      "name": "project_name",  
      "description": "",  
      "links": {  
        "next": null,  
        "previous": null,  
        "self": "https://www.example.com/v3/projects/a4a5d4098fb4474fa22cd05f897d6b99"  
      },  
    },  
  ],  
}
```

```
        "id": "a4a5d4098fb4474fa22cd05f897d6b99",
        "enabled": true
    },
],
"links": {
    "next": null,
    "previous": null,
    "self": "https://www.example.com/v3/projects"
}
```

Obtain a Project ID from the Console

Step 1 Register yourself on the management console and log in to it.

Step 2 Hover the mouse over the username in the upper right corner and select **My Credentials** from the drop-down list.

On the **API Credentials** page, view the project ID in the project list.

Figure A-1 Viewing project IDs

The screenshot shows the 'API Credentials' page with the 'API Credentials' tab selected. It displays a table of projects with columns for Project ID, Project Name, and Region. The table contains 12 rows of data. A search bar at the top right is empty. At the bottom left, there is a dropdown menu set to '10' and a navigation bar with page numbers 1, 2, and >.

Project ID	Project Name	Region
0503dda897000fed2f78c00909158a4d	cn-north-1	CN North-Beijing1
05041fffa40025702f6dc009c6fbf33	cn-north-4	CN North-Beijing4
050420295f0026c12f8ac009ae3dfe89	cn-southwest-2	CN Southwest-Guiyang1
05e1aef9040010e22fccc009adecb056	cn-east-3	CN East-Shanghai1
05041fdbx98026c42f2bc0095a3bf05d	ap-southeast-3	AP-Singapore
05041fb08800256e2f94c0094395f73	af-south-1	AF-Johannesburg
0503ddabaa8010f2f2f3c009272536d2	cn-north-5	CN North-Ulanqab201
0503ddab5fb010df2f92c00977d3e282	cn-north-6	CN North-Ulanqab202
05041fea8a8025662f4ac00927982f3e	cn-east-2	CN East-Shanghai2
0504201bb680256b2f08c0099fc8f64	cn-south-1	CN South-Guangzhou

----End

A.5 GaussDB(for MySQL) Monitoring Metrics

Function Description

This section describes namespaces, descriptions, and dimensions of monitoring metrics to be reported to Cloud Eye. You can use APIs provided by Cloud Eye to retrieve monitoring metrics and alarm information generated for GaussDB(for MySQL).

Namespace

SYS.GAUSSDB

Monitoring Metrics

Table A-4 Monitoring metrics

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql001_cpu_util	CPU Usage	CPU usage of the monitored object	0–100%	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql002_mem_utl	Memory Usage	Memory usage of the monitored object	0–100%	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql004_bytes_in	Network Input Throughput	Incoming traffic in bytes per second	≥0 Bytes/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql005_bytes_out	Network Output Throughput	Outgoing traffic in bytes per second	≥0 Bytes/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql006_conn_count	Total Connections	Total number of connections that connect to the MySQL server	≥0 Connections	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql007_conn_active_count	Current Active Connections	Number of active connections	≥0 Connections	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql008_qps	QPS	Query times of SQL statements (including DDL, DML, SHOW, SET statements and storage procedures) per second	≥0 Times/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql009_tps	TPS	Execution times of submitted and rollback transactions per second	≥0 Times/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql010_innodb_buffer_usage	Buffer Pool Usage	Ratio of used pages to total pages in the InnoDB buffer	0-100%	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql011_innodb_buffer_hit	Buffer Pool Hit Ratio	Ratio of read hits to read requests in the InnoDB buffer	0-100%	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql012_innodb_buffer_dirty	Buffer Pool Dirty Block Ratio	Ratio of dirty data to all data in the InnoDB buffer	0-100%	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql013_innodb_reads	InnoDB Read Throughput	Number of read bytes per second in the InnoDB buffer	≥ 0 Bytes/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql014_innodb_writes	InnoDB Write Throughput	Number of write bytes per second in the InnoDB buffer	≥ 0 Bytes/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql017_innodb_log_write_req_count	InnoDB Log Write Requests per Second	Number of InnoDB log write requests per second	≥ 0 Requests/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql020_temp_tbl_count	Temporary Tables	Number of temporary tables automatically created on hard disks when MySQL statements are executed	≥ 0 Tables	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql028_comdml_del_count	DELETE Statements per Second	Number of DELETE statements executed per second	≥ 0 Statements/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql029_comdml_ins_count	INSERT Statements per Second	Number of INSERT statements executed per second	≥ 0 Statements/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql030_comdml_ins_sel_count	INSERT_SELECT Statements per Second	Number of INSERT_SELECT statements executed per second	≥0 Statements/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql031_comdml_rep_count	REPLACE Statements per Second	Number of REPLACE statements executed per second	≥0 Statements/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql032_comdml_rep_sel_count	REPLACE_SELECTION Statements per Second	Number of REPLACE_SELECTION statements executed per second	≥0 Statements/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql033_comdml_sel_count	SELECT Statements per Second	Number of SELECT statements executed per second	≥0 Statements/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql034_comdml_upd_count	UPDATE Statements per Second	Number of UPDATE statements executed per second	≥0 Statements/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql035_innodb_del_row_count	Row Delete Frequency	Number of rows deleted from the InnoDB table per second	≥0 Rows/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql036_innodb_ins_row_count	Row Insert Frequency	Number of rows inserted into the InnoDB table per second	≥0 Rows/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql037_innodb_read_row_count	Row Read Frequency	Number of rows read from the InnoDB table per second	≥0 Rows/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql038_innodb_upd_row_count	Row Update Frequency	Number of rows updated into the InnoDB table per second	≥0 Rows/s	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql048_disk_use_d_size	Used Storage Space	Used storage space of the monitored object	0 GB-128 TB	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql072_conn_usage	Connection Usage	Percent of used MySQL connections to the total number of connections	0-100%	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql074_slow_queries	Slow Query Logs	Number of MySQL slow query logs generated per minute	≥0 Queries/min	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql077_replication_delay	Replication Delay	Data replication delay between the primary node and read replicas	$\geq 0\text{s}$	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql104_dfv_write_delay	Storage Write Latency	Average latency of writing data to the storage layer in a specified period	$\geq 0\text{ ms}$	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql105_dfv_read_delay	Storage Read Latency	Average latency of reading data from the storage layer in a specified period	$\geq 0\text{ ms}$	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql106_innodb_row_lock_current_waits	InnoDB Row Locks	Number of row locks being waited by operations on the InnoDB table	$\geq 0\text{ Locks}$	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql107_comdml_ins_and_ins_sel_count	INSERT and INSERT_SELECT Statements per Second	Number of INSERT and INSERT_SELECT statements executed per second	$\geq 0\text{ Statements/s}$	Monitored object: ECS Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql108_com_commit_count	COMMIT Statements per Second	Number of COMMIT statements executed per second	$\geq 0\text{ Statements/s}$	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql109_com_rollback_count	ROLLBACK Statement s per Second	Number of ROLLBACK statements executed per second	≥0 Statements/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql110_innodb_bufpool_reads	InnoDB Storage Layer Read Requests per Second	Number of times that InnoDB reads data from the storage layer per second	≥0 Times/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql111_innodb_bufpool_read_requests	InnoDB Read Requests per Second	Number of InnoDB read requests per second	≥0 Requests/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql114_innodb_bufpool_read_ahead	InnoDB Bufpool Read Ahead	Number of pages read into the InnoDB buffer pool by the read-ahead background thread	≥0 Pages	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql115_innodb_bufpool_read_ahead_evicted	InnoDB Bufpool Read Ahead Evicted	Number of pages read into the InnoDB buffer pool by the read-ahead background thread that were subsequently evicted without having been accessed by queries	≥0 Pages	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql116_innodb_bufpool_read_ahead_rnd	InnoDB Bufpool Read Ahead Rnd	Number of random read-aheads initiated by InnoDB	≥ 0 Read-aheads	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql117_innodb_pages_read	InnoDB Pages Read	Number of pages read from the InnoDB buffer pool by operations on InnoDB tables	≥ 0 Pages	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql118_innodb_pages_written	InnoDB Pages Written	Number of pages written by operations on InnoDB tables	≥ 0 Pages	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql019_innodb_log_writes	InnoDB Log Writes	Number of physical writes to the InnoDB redo log file	≥ 0 Writes	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql342_iostat_iops_write	I/O Write IOPS	Number of disk writes per second	≥ 0 Operations/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql344_iostat_iops_read	I/O Read IOPS	Number of disk reads per second	≥ 0 Operations/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance

Metric	Name	Description	Value Range	Remarks
gaussdb_mysql346_iostat_th_roughput_write	I/O Write Bandwidth	Disk write bandwidth per second	≥ 0 Bytes/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql348_iostat_th_roughput_read	I/O Read Bandwidth	Disk read bandwidth per second	≥ 0 Bytes/s	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance
gaussdb_mysql119_disk_usage_d_ratio	Disk Usage	Disk usage of the monitored object	0-100%	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance 1 minute
gaussdb_mysql371_taurus_binlog_total_file_counts	Binlog Files	Number of GaussDB(for MySQL) binlog files	≥ 0	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance 5 minutes
gaussdb_mysql378_create_temp_tbl_per_min	Temporary Tables Created per Minute	Number of temporary tables automatically created on disks per minute when GaussDB(for MySQL) statements are executed	≥ 0 Tables/min	Monitored object: database Monitored instance type: GaussDB(for MySQL) instance 1 minute

Dimension

Key	Value
gaussdb_mysql_instance_id	GaussDB(for MySQL) instance ID.
gaussdb_mysql_node_id	Node ID of the GaussDB(for MySQL) instance.

B Change History

Released On	Description
2024-02-20	<p>This issue is the nineteenth official release.</p> <ul style="list-style-type: none">Added the <code>tde_info</code> parameter in Creating a DB Instance, Querying Details of a DB Instance, and Querying Details of DB Instances in Batches.Added the <code>availability_zone</code> parameter in Creating a Read Replica.Added the <code>new_node_auto_add_status</code> and <code>new_node_weight</code> parameters in Creating a Proxy Instance, Querying Proxy Instances, and Changing the Routing Policy of a Proxy Instance.Added Enabling or Disabling Association of New Nodes with Proxy Instances.
2023-12-08	<p>This issue is the eighteenth official release.</p> <ul style="list-style-type: none">Added Querying DB instances.Added Querying Details of a DB Instance.Added Querying Details of DB Instances in Batches.Added Enabling or Disabling SSL for a Proxy Instance.
2023-11-24	<p>This issue is the seventeenth official release.</p> <p>Added Querying Tables for Table-level Point-in-Time Recovery.</p>

Released On	Description
2023-11-03	<p>This issue is the sixteenth official release.</p> <ul style="list-style-type: none">Added Deleting Proxy Nodes.Added the request parameter <code>subnet_id</code> in Creating a Proxy Instance.Added the response parameter <code>subnet_id</code> in Querying Proxy Instances.Added Querying the Kernel Version.Added Modifying Auto Scaling Policies.Added Querying Auto Scaling Policies.Added Pre-Checking Resources.Added Modifying Parameters of a Specified DB Instance.Added Replicating the Parameter Template of a DB Instance.Added Querying Abnormal Instances by Each Metric.Added Querying Abnormal Instance Information by a Specific Metric.
2023-10-20	<p>This issue is the fifteenth official release.</p> <ul style="list-style-type: none">Added Querying Incremental Backups.Added Configuring a Cross-Region Backup Policy.Added Restoring Tables to a Specified Point in Time.Added Replicating a Parameter Template.Added Comparing Parameter Templates.Added Querying Instances That a Parameter Template Can Be Applied To.Added Viewing Parameter Change History.Added Obtaining Parameter Information of a Specified DB Instance.Added Querying Enterprise Projects.Added Modifying Parameters of a Proxy Instance.Added Enabling or Disabling Access Control.Added Configuring Access Control Rules.Added Deleting a Scheduled Task Record.Modified Querying Databases. The <code>name</code> and <code>charset</code> parameters are supported.

Released On	Description
2023-09-15	<p>This is the fourteenth official release.</p> <ul style="list-style-type: none">Added Obtaining the Temporary Link for Downloading Full SQL.Added the volume parameter in Creating a DB Instance.
2023-08-04	<p>This is the thirteenth official release.</p> <ul style="list-style-type: none">Added Changing the Routing Policy of a Proxy Instance.Added the parameters version and kernel_version in Querying Version Information About a DB Engine.Added the kernel_version parameter in Creating a DB Instance.Added the route_mode parameter in Creating a Proxy Instance.Added the balance_route_mode_enabled parameter in Querying Proxy Instances.
2023-06-19	<p>This issue is the twelfth official release.</p> <ul style="list-style-type: none">Modified Deleting or Unsubscribing from a DB Instance to support unsubscription from yearly/monthly DB instances.Modified Deleting or Unsubscribing from a Read Replica to support unsubscription from read replicas of yearly/monthly DB instances.

Released On	Description
2023-05-25	<p>This issue is the eleventh official release.</p> <ul style="list-style-type: none">Added Changing the Connection Pool Type of a Proxy Instance.Added Restoring Data to the Original Instance or an Existing Instance.Added Querying the Restoration Time Range.Added Modifying Remarks of a Database User.Added Modifying Database Remarks.Added Querying Slow Query Logs.Added Querying Error Logs.Added general-purpose specifications in Querying Database Specifications.Added the <code>restore_point</code> parameter in Creating a DB Instance.Added the parameters <code>readonly_private_ip</code> and <code>proxy_ip</code> in Querying DB Instances.Added the parameters <code>connection_pool_type</code> and <code>switch_connection_pool_type_enabled</code> in Querying Proxy Instances.Added the <code>comment</code> parameter in Creating a Database Account.Added the <code>comment</code> parameter in Querying Database Users.Added the <code>comment</code> parameter in Creating a Database.Added the <code>comment</code> parameter in Querying Databases.
2023-03-31	<p>This issue is the tenth official release.</p> <p>Added the unavailable time of some APIs and new APIs that replace the unavailable APIs.</p>
2023-03-08	<p>This is the ninth official release.</p> <p>Optimized Creating a Database. Hyphens (-) are allowed in database names.</p>

Released On	Description
2023-02-24	<p>This is the eighth official release.</p> <p>Optimized examples in the following sections:</p> <ul style="list-style-type: none">• Creating a Database Account• Querying Database Users• Deleting a Database User• Changing Password of a Database User• Granting Permissions to a Database User• Deleting Permissions of a Database User• Creating a Database• Obtaining Scheduled Tasks
2022-12-12	<p>This is the seventh official release.</p> <ul style="list-style-type: none">• Added Rebooting a Node.• Added Upgrading the Kernel Version of a DB Instance.• Added Enabling or Disabling SSL.• Added Binding an EIP.• Added Unbinding an EIP.• Added Promoting a Read Replica to Primary.• Added Changing a Maintenance Window.• Added Modifying a Security Group.• Added Changing a Private IP Address.• Added Changing a Database Port.• Added Changing a DB Instance Description.• Added Deleting a Manual Backup.• Added Changing Session Consistency of a Proxy Instance.• Added Creating a Parameter Template.• Added Deleting a Parameter Template.• Added Obtaining Details About a Parameter Template.• Added Modifying Parameters in a Parameter Template.• Added Applying a Parameter Template.• Added Obtaining Instant Tasks.• Added Obtaining Scheduled Tasks.• Added Canceling a Scheduled Task.• Added Deleting a Task Record.

Released On	Description
2022-11-07	This issue is the sixth official release, which incorporates the following changes: <ul style="list-style-type: none">Added Enabling or Disabling Transaction Splitting of a Proxy Instance.Added the <code>lower_case_table_names</code> request parameter in Creating a DB Instance.Moved the API for querying proxy instance information to "API (Unavailable Soon)".
2022-08-30	This issue is the fifth official release, which incorporates the following changes: <ul style="list-style-type: none">Added Querying Details of DB Instances in Batches.Modified the example in Querying Proxy Instances.
2021-07-15	This issue is the fourth official release, which incorporates the following changes: <ul style="list-style-type: none">Added Adding Proxy Nodes.Optimized parameter descriptions in the following sections:<ul style="list-style-type: none">Creating a DB InstanceQuerying DB InstancesQuerying Details of a DB InstanceCreating a Read ReplicaResetting a Database PasswordQuerying Full BackupsQuerying an Automated Backup PolicyGaussDB(for MySQL) Monitoring Metrics
2021-04-06	This issue is the third official release, which added the following sections: <ul style="list-style-type: none">Querying Proxy Instance SpecificationsCreating a Proxy InstanceDeleting a Proxy Instance
2021-03-22	This issue is the second official release, which incorporates the following changes: <ul style="list-style-type: none">Added tag parameters in Creating a DB Instance.Optimized parameter descriptions in Querying DB Instances.
2020-10-27	This issue is the first official release.