

**MapReduce Service**

# **Component Operation Guide ( LTS )**

**Date**      2022-11-30

---

# Contents

---

<b>1 Using CarbonData.....</b>	<b>1</b>
1.1 Overview.....	1
1.1.1 CarbonData Overview.....	1
1.1.2 Main Specifications of CarbonData.....	4
1.2 Configuration Reference.....	5
1.3 CarbonData Operation Guide.....	18
1.3.1 CarbonData Quick Start.....	18
1.3.2 CarbonData Table Management.....	20
1.3.2.1 About CarbonData Table.....	21
1.3.2.2 Creating a CarbonData Table.....	22
1.3.2.3 Deleting a CarbonData Table.....	24
1.3.2.4 Modify the CarbonData Table.....	25
1.3.3 CarbonData Table Data Management.....	25
1.3.3.1 Loading Data.....	26
1.3.3.2 Deleting Segments.....	26
1.3.3.3 Combining Segments.....	28
1.3.4 CarbonData Data Migration.....	31
1.3.5 Migrating Data on CarbonData from Spark1.5 to Spark2x.....	32
1.4 CarbonData Performance Tuning.....	34
1.4.1 Tuning Guidelines.....	34
1.4.2 Suggestions for Creating CarbonData Tables.....	36
1.4.3 Configurations for Performance Tuning.....	39
1.5 CarbonData Access Control.....	42
1.6 CarbonData Syntax Reference.....	43
1.6.1 DDL.....	44
1.6.1.1 CREATE TABLE.....	44
1.6.1.2 CREATE TABLE As SELECT.....	46
1.6.1.3 DROP TABLE.....	47
1.6.1.4 SHOW TABLES.....	48
1.6.1.5 ALTER TABLE COMPACTION.....	49
1.6.1.6 TABLE RENAME.....	50
1.6.1.7 ADD COLUMNS.....	51
1.6.1.8 DROP COLUMNS.....	52

1.6.1.9 CHANGE DATA TYPE.....	53
1.6.1.10 REFRESH TABLE.....	54
1.6.1.11 REGISTER INDEX TABLE.....	55
1.6.1.12 REFRESH INDEX.....	56
1.6.2 DML.....	57
1.6.2.1 LOAD DATA.....	57
1.6.2.2 UPDATE CARBON TABLE.....	62
1.6.2.3 DELETE RECORDS from CARBON TABLE.....	63
1.6.2.4 INSERT INTO CARBON TABLE.....	65
1.6.2.5 DELETE SEGMENT by ID.....	66
1.6.2.6 DELETE SEGMENT by DATE.....	66
1.6.2.7 SHOW SEGMENTS.....	67
1.6.2.8 CREATE SECONDARY INDEX.....	68
1.6.2.9 SHOW SECONDARY INDEXES.....	69
1.6.2.10 DROP SECONDARY INDEX.....	70
1.6.2.11 CLEAN FILES.....	70
1.6.2.12 SET/RESET.....	71
1.6.3 Operation Concurrent Execution.....	74
1.6.4 API.....	78
1.6.5 Spatial Indexes.....	80
1.7 CarbonData Troubleshooting.....	94
1.7.1 Filter Result Is not Consistent with Hive when a Big Double Type Value Is Used in Filter.....	94
1.7.2 Query Performance Deterioration.....	94
1.8 CarbonData FAQ.....	95
1.8.1 Why Is Incorrect Output Displayed When I Perform Query with Filter on Decimal Data Type Values?.....	95
1.8.2 How to Avoid Minor Compaction for Historical Data?.....	96
1.8.3 How to Change the Default Group Name for CarbonData Data Loading?.....	96
1.8.4 Why Does INSERT INTO CARBON TABLE Command Fail?.....	97
1.8.5 Why Is the Data Logged in Bad Records Different from the Original Input Data with Escape Characters?.....	97
1.8.6 Why Data Load Performance Decreases due to Bad Records?.....	98
1.8.7 Why INSERT INTO/LOAD DATA Task Distribution Is Incorrect and the Opened Tasks Are Less Than the Available Executors when the Number of Initial Executors Is Zero?.....	98
1.8.8 Why Does CarbonData Require Additional Executors Even Though the Parallelism Is Greater Than the Number of Blocks to Be Processed?.....	99
1.8.9 Why Data loading Fails During off heap?.....	99
1.8.10 Why Do I Fail to Create a Hive Table?.....	100
1.8.11 Why CarbonData tables created in V100R002C50RC1 not reflecting the privileges provided in Hive Privileges for non-owner?.....	100
1.8.12 How Do I Logically Split Data Across Different Namespaces?.....	101
1.8.13 Why Missing Privileges Exception is Reported When I Perform Drop Operation on Databases?....	102
1.8.14 Why the UPDATE Command Cannot Be Executed in Spark Shell?.....	102
1.8.15 How Do I Configure Unsafe Memory in CarbonData?.....	103

1.8.16 Why Exception Occurs in CarbonData When Disk Space Quota is Set for Storage Directory in HDFS?.....	103
1.8.17 Why Does Data Query or Loading Fail and "org.apache.carbondata.core.memory.MemoryException: Not enough memory" Is Displayed?.....	104
<b>2 Using ClickHouse.....</b>	<b>105</b>
2.1 Using ClickHouse from Scratch.....	105
2.2 Common ClickHouse SQL Syntax.....	108
2.2.1 CREATE DATABASE: Creating a Database.....	108
2.2.2 CREATE TABLE: Creating a Table.....	108
2.2.3 INSERT INTO: Inserting Data into a Table.....	109
2.2.4 SELECT: Querying Table Data.....	110
2.2.5 ALTER TABLE: Modifying a Table Structure.....	111
2.2.6 DESC: Querying a Table Structure.....	112
2.2.7 DROP: Deleting a Table.....	112
2.2.8 SHOW: Displaying Information About Databases and Tables.....	112
2.2.9 Importing and Exporting File Data.....	113
2.3 User Management and Authentication.....	114
2.3.1 ClickHouse User and Permission Management.....	114
2.3.2 Setting the ClickHouse Username and Password.....	118
2.4 ClickHouse Table Engine Overview.....	119
2.5 Creating a ClickHouse Table.....	126
2.6 Using the ClickHouse Data Migration Tool.....	131
2.7 Monitoring of Slow ClickHouse Query Statements and Replication Table Data Synchronization.....	134
2.7.1 Slow Query Statement Monitoring.....	134
2.7.2 Replication Table Data Synchronization Monitoring.....	136
2.8 Adaptive MV Usage in ClickHouse.....	136
2.9 ClickHouse Log Overview.....	141
<b>3 Using DBService.....</b>	<b>145</b>
3.1 Configuring SSL for the HA Module.....	145
3.2 Restoring SSL for the HA Module.....	146
3.3 Configuring the Timeout Interval of DBService Backup Tasks.....	148
3.4 DBService Log Overview.....	148
<b>4 Using Flink.....</b>	<b>152</b>
4.1 Using Flink from Scratch.....	152
4.2 Viewing Flink Job Information.....	155
4.3 Flink Configuration Management.....	156
4.3.1 Configuring Parameter Paths.....	156
4.3.2 JobManager & TaskManager.....	156
4.3.3 Blob.....	166
4.3.4 Distributed Coordination (via Akka).....	167
4.3.5 SSL.....	173
4.3.6 Network communication (via Netty).....	174

4.3.7 JobManager Web Frontend.....	175
4.3.8 File Systems.....	180
4.3.9 State Backend.....	181
4.3.10 Kerberos-based Security.....	183
4.3.11 HA.....	185
4.3.12 Environment.....	188
4.3.13 Yarn.....	189
4.3.14 Pipeline.....	190
4.4 Security Configuration.....	191
4.4.1 Security Features.....	191
4.4.2 Configuring Kafka.....	192
4.4.3 Configuring Pipeline.....	193
4.5 Security Hardening.....	194
4.5.1 Authentication and Encryption.....	194
4.5.2 ACL Control.....	200
4.5.3 Web Security.....	200
4.6 Security Statement.....	202
4.7 Using the Flink Web UI.....	203
4.7.1 Overview.....	203
4.7.1.1 Introduction to Flink Web UI.....	203
4.7.1.2 Flink Web UI Application Process.....	204
4.7.2 FlinkServer Permissions Management.....	206
4.7.2.1 Overview.....	206
4.7.2.2 Authentication Based on Users and Roles.....	206
4.7.3 Accessing the Flink Web UI.....	207
4.7.4 Creating an Application on the Flink Web UI.....	208
4.7.5 Creating a Cluster Connection on the Flink Web UI.....	209
4.7.6 Creating a Data Connection on the Flink Web UI.....	211
4.7.7 Managing Tables on the Flink Web UI.....	213
4.7.8 Managing Jobs on the Flink Web UI.....	216
4.7.9 Managing UDFs on the Flink Web UI.....	220
4.7.9.1 Managing UDFs on the Flink Web UI.....	220
4.7.9.2 UDF Java and SQL Examples.....	222
4.7.9.3 UDAF Java and SQL Examples.....	222
4.7.9.4 UDTF Java and SQL Examples.....	223
4.7.10 Interconnecting FlinkServer with External Components.....	223
4.7.10.1 Interconnecting FlinkServer with ClickHouse.....	224
4.7.10.2 Interconnecting FlinkServer with HBase.....	229
4.7.10.3 Interconnecting FlinkServer with HDFS.....	232
4.7.10.4 Interconnecting FlinkServer with Hive.....	237
4.7.10.5 Interconnecting FlinkServer with Hudi.....	241
4.7.10.6 Interconnecting FlinkServer with Kafka.....	244

4.8 Deleting Residual Information About Flink Tasks.....	247
4.9 Flink Log Overview.....	248
4.10 Flink Performance Tuning.....	251
4.10.1 Optimization DataStream.....	251
4.10.1.1 Memory Configuration Optimization.....	251
4.10.1.2 Configuring DOP.....	252
4.10.1.3 Configuring Process Parameters.....	253
4.10.1.4 Optimizing the Design of Partitioning Method.....	254
4.10.1.5 Configuring the Netty Network Communication.....	255
4.10.1.6 Summarization.....	256
4.11 Common Flink Shell Commands.....	256
<b>5 Using Flume.....</b>	<b>262</b>
5.1 Using Flume from Scratch.....	262
5.2 Overview.....	265
5.3 Installing the Flume Client on Clusters.....	268
5.4 Viewing Flume Client Logs.....	271
5.5 Stopping or Uninstalling the Flume Client.....	272
5.6 Using the Encryption Tool of the Flume Client.....	273
5.7 Flume Service Configuration Guide.....	274
5.8 Flume Configuration Parameter Description.....	307
5.9 Using Environment Variables in the <b>properties.properties</b> File.....	322
5.10 Non-Encrypted Transmission.....	324
5.10.1 Configuring Non-encrypted Transmission.....	324
5.10.2 Typical Scenario: Collecting Local Static Logs and Uploading Them to Kafka.....	327
5.10.3 Typical Scenario: Collecting Local Static Logs and Uploading Them to HDFS.....	330
5.10.4 Typical Scenario: Collecting Local Dynamic Logs and Uploading Them to HDFS.....	333
5.10.5 Typical Scenario: Collecting Logs from Kafka and Uploading Them to HDFS.....	336
5.10.6 Typical Scenario: Collecting Logs from Kafka and Uploading Them to HDFS Through the Flume Client.....	339
5.10.7 Typical Scenario: Collecting Local Static Logs and Uploading Them to HBase.....	344
5.11 Encrypted Transmission.....	352
5.11.1 Configuring the Encrypted Transmission.....	352
5.11.2 Typical Scenario: Collecting Local Static Logs and Uploading Them to HDFS.....	362
5.12 Viewing Flume Client Monitoring Information.....	378
5.13 Connecting Flume to Kafka in Security Mode.....	378
5.14 Connecting Flume with Hive in Security Mode.....	379
5.15 Configuring the Flume Service Model.....	382
5.15.1 Overview.....	382
5.15.2 Service Model Configuration Guide.....	382
5.16 Introduction to Flume Logs.....	388
5.17 Flume Client Cgroup Usage Guide.....	391
5.18 Secondary Development Guide for Flume Third-Party Plug-ins.....	392

5.19 Common Issues About Flume.....	393
<b>6 Using HBase.....</b>	<b>395</b>
6.1 Using HBase from Scratch.....	395
6.2 Creating HBase Roles.....	397
6.3 Using an HBase Client.....	400
6.4 Configuring HBase Replication.....	401
6.5 Enabling Cross-Cluster Copy.....	410
6.6 Supporting Full-Text Index.....	411
6.7 Using the ReplicationSyncUp Tool.....	413
6.8 Using HIndex.....	415
6.8.1 Introduction to HIndex.....	415
6.8.2 Loading Index Data in Batches.....	424
6.8.3 Using an Index Generation Tool.....	427
6.9 Configuring HBase DR.....	429
6.10 Performing an HBase DR Service Switchover.....	439
6.11 Configuring HBase Data Compression and Encoding.....	441
6.12 Performing an HBase DR Active/Standby Cluster Switchover.....	443
6.13 Community BulkLoad Tool.....	445
6.14 Configuring the MOB.....	445
6.15 Configuring Secure HBase Replication.....	446
6.16 Configuring Region In Transition Recovery Chore Service.....	448
6.17 Using a Secondary Index.....	448
6.18 HBase Log Overview.....	450
6.19 HBase Performance Tuning.....	453
6.19.1 Improving the BulkLoad Efficiency.....	453
6.19.2 Improving Put Performance.....	454
6.19.3 Optimizing Put and Scan Performance.....	455
6.19.4 Improving Real-time Data Write Performance.....	459
6.19.5 Improving Real-time Data Read Performance.....	467
6.19.6 Optimizing JVM Parameters.....	471
6.20 Common Issues About HBase.....	472
6.20.1 Why Does a Client Keep Failing to Connect to a Server for a Long Time?.....	472
6.20.2 Operation Failures Occur in Stopping BulkLoad On the Client.....	474
6.20.3 Why May a Table Creation Exception Occur When HBase Deletes or Creates the Same Table Consecutively?.....	474
6.20.4 Why Other Services Become Unstable If HBase Sets up A Large Number of Connections over the Network Port?.....	475
6.20.5 Why Does the HBase BulkLoad Task (One Table Has 26 TB Data) Consisting of 210,000 Map Tasks and 10,000 Reduce Tasks Fail?.....	476
6.20.6 How Do I Restore a Region in the RIT State for a Long Time?.....	477
6.20.7 Why Does HMaster Exits Due to Timeout When Waiting for the Namespace Table to Go Online? .....	477
6.20.8 Why Does SocketTimeoutException Occur When a Client Queries HBase?.....	478

6.20.9 Why Modified and Deleted Data Can Still Be Queried by Using the Scan Command?.....	479
6.20.10 Why "java.lang.UnsatisfiedLinkError: Permission denied" exception thrown while starting HBase shell?.....	480
6.20.11 When does the RegionServers listed under "Dead Region Servers" on HMaster WebUI gets cleared?.....	481
6.20.12 Why Are Different Query Results Returned After I Use Same Query Criteria to Query Data Successfully Imported by HBase bulkload?.....	481
6.20.13 What Should I Do If I Fail to Create Tables Due to the FAILED_OPEN State of Regions?.....	482
6.20.14 How Do I Delete Residual Table Names in the /hbase/table-lock Directory of ZooKeeper?.....	482
6.20.15 Why Does HBase Become Faulty When I Set a Quota for the Directory Used by HBase in HDFS? .....	483
6.20.16 Why HMaster Times Out While Waiting for Namespace Table to be Assigned After Rebuilding Meta Using OfflineMetaRepair Tool and Startups Failed.....	484
6.20.17 Why Messages Containing FileNotFoundException and no lease Are Frequently Displayed in the HMaster Logs During the WAL Splitting Process?.....	485
6.20.18 Why Does the ImportTsv Tool Display "Permission denied" When the Same Linux User as and a Different Kerberos User from the Region Server Are Used?.....	486
6.20.19 Insufficient Rights When a Tenant Accesses Phoenix.....	487
6.20.20 What Can I Do When HBase Fails to Recover a Task and a Message Is Displayed Stating "Rollback recovery failed"?.....	488
6.20.21 How Do I Fix Region Overlapping?.....	488
6.20.22 Why Does RegionServer Fail to Be Started When GC Parameters Xms and Xmx of HBase RegionServer Are Set to 31 GB?.....	489
6.20.23 Why Does the LoadIncrementalHFiles Tool Fail to Be Executed and "Permission denied" Is Displayed When Nodes in a Cluster Are Used to Import Data in Batches?.....	490
6.20.24 Why Is the Error Message "import argparse" Displayed When the Phoenix sqlline Script Is Used? .....	491
6.20.25 How Do I Deal with the Restrictions of the Phoenix BulkLoad Tool?.....	491
6.20.26 Why a Message Is Displayed Indicating that the Permission is Insufficient When CTBase Connects to the Ranger Plug-ins?.....	492
<b>7 Using HDFS.....</b>	<b>494</b>
7.1 Configuring Memory Management.....	494
7.2 Creating an HDFS Role.....	496
7.3 Using the HDFS Client.....	498
7.4 Running the DistCp Command.....	500
7.5 Overview of HDFS File System Directories.....	504
7.6 Changing the DataNode Storage Directory.....	508
7.7 Configuring HDFS Directory Permission.....	512
7.8 Configuring NFS.....	512
7.9 Planning HDFS Capacity.....	513
7.10 Configuring ulimit for HBase and HDFS.....	517
7.11 Balancing DataNode Capacity.....	518
7.12 Configuring Replica Replacement Policy for Heterogeneous Capacity Among DataNodes.....	523
7.13 Configuring the Number of Files in a Single HDFS Directory .....	524
7.14 Configuring the Recycle Bin Mechanism.....	525

7.15 Setting Permissions on Files and Directories.....	526
7.16 Setting the Maximum Lifetime and Renewal Interval of a Token.....	527
7.17 Configuring the Damaged Disk Volume.....	528
7.18 Configuring Encrypted Channels.....	528
7.19 Reducing the Probability of Abnormal Client Application Operation When the Network Is Not Stable .....	530
7.20 Configuring the NameNode Blacklist.....	530
7.21 Optimizing HDFS NameNode RPC QoS.....	533
7.22 Optimizing HDFS DataNode RPC QoS.....	536
7.23 Configuring Reserved Percentage of Disk Usage on DataNodes.....	536
7.24 Configuring HDFS NodeLabel.....	537
7.25 Configuring HDFS DiskBalancer.....	543
7.26 Performing Concurrent Operations on HDFS Files.....	546
7.27 Introduction to HDFS Logs.....	548
7.28 HDFS Performance Tuning.....	553
7.28.1 Improving Write Performance.....	553
7.28.2 Improving Read Performance Using Client Metadata Cache.....	554
7.28.3 Improving the Connection Between the Client and NameNode Using Current Active Cache.....	556
7.29 FAQ.....	557
7.29.1 NameNode Startup Is Slow.....	557
7.29.2 Why MapReduce Tasks Fails in the Environment with Multiple NameServices?.....	558
7.29.3 DataNode Is Normal but Cannot Report Data Blocks.....	559
7.29.4 HDFS WebUI Cannot Properly Update Information About Damaged Data.....	560
7.29.5 Why Does the Distcp Command Fail in the Secure Cluster, Causing an Exception?.....	560
7.29.6 Why Does DataNode Fail to Start When the Number of Disks Specified by dfs.datanode.data.dir Equals dfs.datanode.failed.volumes.tolerated?.....	561
7.29.7 Why Does an Error Occur During DataNode Capacity Calculation When Multiple data.dir Are Configured in a Partition?.....	561
7.29.8 Standby NameNode Fails to Be Restarted When the System Is Powered off During Metadata (Namespace) Storage.....	562
7.29.9 Why Data in the Buffer Is Lost If a Power Outage Occurs During Storage of Small Files.....	563
7.29.10 Why Does Array Border-crossing Occur During FileInputFormat Split?.....	564
7.29.11 Why Is the Storage Type of File Copies DISK When the Tiered Storage Policy Is LAZY_PERSIST?.....	564
7.29.12 The HDFS Client Is Unresponsive When the NameNode Is Overloaded for a Long Time.....	565
7.29.13 Can I Delete or Modify the Data Storage Directory in DataNode?.....	566
7.29.14 Blocks Miss on the NameNode UI After the Successful Rollback.....	567
7.29.15 Why Is "java.net.SocketException: No buffer space available" Reported When Data Is Written to HDFS.....	568
7.29.16 Why are There Two Standby NameNodes After the active NameNode Is Restarted?.....	569
7.29.17 When Does a Balance Process in HDFS, Shut Down and Fail to be Executed Again?.....	571
7.29.18 "This page can't be displayed" Is Displayed When Internet Explorer Fails to Access the Native HDFS UI.....	571
7.29.19 NameNode Fails to Be Restarted Due to EditLog Discontinuity.....	572
<b>8 Using HetuEngine.....</b>	<b>574</b>

8.1 Using HetuEngine from Scratch.....	574
8.2 HetuEngine Permission Management.....	575
8.2.1 HetuEngine Permission Management Overview.....	576
8.2.2 Creating a HetuEngine User.....	576
8.2.3 HetuEngine Ranger-based Permission Control.....	578
8.2.4 HetuEngine MetaStore-based Permission Control.....	578
8.2.4.1 Overview.....	578
8.2.4.2 Creating a HetuEngine Role.....	581
8.2.4.3 Configuring Permissions for Tables, Columns, and Databases.....	582
8.2.5 Permission Principles and Constraints.....	583
8.3 Creating HetuEngine Compute Instances.....	584
8.4 Configuring Data Sources.....	588
8.4.1 Before You Start.....	588
8.4.2 Configuring a Hive Data Source.....	589
8.4.2.1 Configuring a Co-deployed Hive Data Source.....	589
8.4.2.2 Configuring a Traditional Data Source.....	591
8.4.2.3 Configuring a Hudi Data Source.....	598
8.4.3 Configuring an HBase Data Source.....	599
8.4.4 Configuring a GaussDB Data Source.....	604
8.4.5 Configuring a HetuEngine Data Source.....	612
8.4.6 Configuring a ClickHouse Data Source.....	615
8.5 Managing Data Sources.....	621
8.5.1 Managing an External Data Source.....	621
8.6 Managing Compute Instances.....	622
8.6.1 Configuring Resource Groups.....	622
8.6.2 Adjusting the Number of Worker Nodes.....	630
8.6.3 Managing a HetuEngine Compute Instance.....	632
8.6.4 Importing and Exporting Compute Instance Configurations.....	634
8.6.5 Viewing the Instance Monitoring Page.....	635
8.6.6 Viewing Coordinator and Worker Logs.....	640
8.6.7 Using Resource Labels to Specify on Which Node Coordinators Should Run.....	641
8.7 Using the HetuEngine Client.....	642
8.8 Using the HetuEngine Cross-Source Function.....	643
8.8.1 Introduction to HetuEngine Cross-Source Function.....	644
8.8.2 Usage Guide of HetuEngine Cross-Source Function.....	645
8.9 Using HetuEngine Cross-Domain Function.....	648
8.9.1 Introduction to HetuEngine Cross-Source Function.....	648
8.9.2 HetuEngine Cross-Domain Function Usage.....	649
8.9.3 HetuEngine Cross-Domain Rate Limit Function.....	649
8.10 Using a Third-Party Visualization Tool to Access HetuEngine.....	651
8.10.1 Usage Instruction.....	651
8.10.2 Using DBeaver to Access HetuEngine.....	651

8.10.3 Using Tableau to Access HetuEngine.....	657
8.10.4 Using PowerBI to Access HetuEngine.....	659
8.10.5 Using Yonghong BI to Access HetuEngine.....	665
8.11 Function & UDF Development and Application.....	668
8.11.1 HetuEngine Function Plugin Development and Application.....	668
8.11.2 Hive UDF Development and Application.....	673
8.11.3 HetuEngine UDF Development and Application.....	676
8.12 Introduction to HetuEngine Logs.....	679
8.13 HetuEngine Performance Tuning.....	683
8.13.1 Adjusting the Yarn Service Configuration.....	683
8.13.2 Adjusting Cluster Node Resource Configurations.....	684
8.13.3 Adjusting Execution Plan Cache.....	687
8.13.4 Adjusting Metadata Cache.....	688
8.13.5 Modifying the CTE Configuration.....	689
8.14 Common Issues About HetuEngine.....	690
8.14.1 How Do I Perform Operations After the Domain Name Is Changed?.....	691
8.14.2 What Do I Do If Starting a Cluster on the Client Times Out?.....	691
8.14.3 How Do I Handle Data Source Loss?.....	691
8.14.4 How Do I Handle HetuEngine Alarms?.....	692
8.14.5 How Do I Do If Coordinators and Workers Cannot Be Started on the New Node?.....	692
<b>9 Using Hive.....</b>	<b>693</b>
9.1 Using Hive from Scratch.....	693
9.2 Configuring Hive Parameters.....	696
9.3 Hive SQL.....	698
9.4 Permission Management.....	700
9.4.1 Hive Permission.....	700
9.4.2 Creating a Hive Role.....	703
9.4.3 Configuring Permissions for Hive Tables, Columns, or Databases.....	706
9.4.4 Configuring Permissions to Use Other Components for Hive.....	709
9.5 Using a Hive Client.....	711
9.6 Using HDFS Colocation to Store Hive Tables.....	714
9.7 Using the Hive Column Encryption Function.....	715
9.8 Customizing Row Separators.....	716
9.9 Deleting Single-Row Records from Hive on HBase.....	717
9.10 Configuring HTTPS/HTTP-based REST APIs.....	718
9.11 Enabling or Disabling the Transform Function.....	718
9.12 Access Control of a Dynamic Table View on Hive.....	719
9.13 Specifying Whether the <b>ADMIN</b> Permissions Is Required for Creating Temporary Functions.....	720
9.14 Using Hive to Read Data in a Relational Database.....	720
9.15 Supporting Traditional Relational Database Syntax in Hive.....	722
9.16 Creating User-Defined Hive Functions.....	724
9.17 Enhancing beeline Reliability.....	726

9.18 Viewing Table Structures Using the show create Statement as Users with the select Permission.....	727
9.19 Writing a Directory into Hive with the Old Data Removed to the Recycle Bin.....	728
9.20 Inserting Data to a Directory That Does Not Exist.....	728
9.21 Creating Databases and Creating Tables in the Default Database Only as the Hive Administrator..	729
9.22 Disabling of Specifying the location Keyword When Creating an Internal Hive Table.....	730
9.23 Enabling the Function of Creating a Foreign Table in a Directory That Can Only Be Read.....	730
9.24 Authorizing Over 32 Roles in Hive.....	731
9.25 Restricting the Maximum Number of Maps for Hive Tasks.....	732
9.26 HiveServer Lease Isolation.....	732
9.27 Hive Supporting Transactions.....	733
9.28 Switching the Hive Execution Engine to Tez.....	738
9.29 Connecting Hive with External RDS.....	740
9.30 Redis-based CacheStore of HiveMetaStore.....	743
9.31 Hive Materialized View.....	745
9.32 Hive Supporting Reading Hudi Tables.....	748
9.33 Hive Supporting Cold and Hot Storage of Partitioned Metadata.....	752
9.34 Hive Supporting ZSTD Compression Formats.....	753
9.35 Hive Log Overview.....	754
9.36 Hive Performance Tuning.....	757
9.36.1 Creating Table Partitions.....	757
9.36.2 Optimizing Join.....	759
9.36.3 Optimizing Group By.....	761
9.36.4 Optimizing Data Storage.....	761
9.36.5 Optimizing SQL Statements.....	762
9.36.6 Optimizing the Query Function Using Hive CBO.....	763
9.37 Common Issues About Hive.....	765
9.37.1 How Do I Delete UDFs on Multiple HiveServers at the Same Time?.....	765
9.37.2 Why Cannot the DROP operation Be Performed on a Backed-up Hive Table?.....	766
9.37.3 How to Perform Operations on Local Files with Hive User-Defined Functions.....	767
9.37.4 How Do I Forcibly Stop MapReduce Jobs Executed by Hive?.....	767
9.37.5 How Do I Monitor the Hive Table Size?.....	768
9.37.6 How Do I Prevent Key Directories from Data Loss Caused by Misoperations of the <b>insert overwrite</b> Statement?.....	769
9.37.7 Why Is Hive on Spark Task Freezing When HBase Is Not Installed?.....	769
9.37.8 Error Reported When the WHERE Condition Is Used to Query Tables with Excessive Partitions in FusionInsight Hive.....	770
9.37.9 Why Cannot I Connect to HiveServer When I Use IBM JDK to Access the Beeline Client?.....	771
9.37.10 Description of Hive Table Location (Either Be an OBS or HDFS Path).....	771
9.37.11 Why Cannot Data Be Queried After the MapReduce Engine Is Switched After the Tez Engine Is Used to Execute Union-related Statements?.....	772
9.37.12 Why Does Hive Not Support Concurrent Data Writing to the Same Table or Partition?.....	772
9.37.13 Why Does Hive Not Support Vectorized Query?.....	772
9.37.14 Hive Configuration Problems.....	773

<b>10 Using Hudi.....</b>	<b>775</b>
10.1 Quick Start.....	775
10.2 Basic Operations.....	778
10.2.1 Hudi Table Schema.....	778
10.2.2 Write.....	779
10.2.2.1 Batch Write.....	779
10.2.2.2 Stream Write.....	782
10.2.2.3 Bootstrapping.....	784
10.2.2.4 Synchronizing Hudi Table Data to Hive.....	785
10.2.3 Read.....	787
10.2.3.1 Reading COW Table Views.....	788
10.2.3.2 Reading MOR Table Views.....	789
10.2.4 Data Management and Maintenance.....	790
10.2.4.1 Metadata Table.....	790
10.2.4.2 Clustering.....	791
10.2.4.3 Cleaning.....	793
10.2.4.4 Compaction.....	794
10.2.4.5 Savepoint.....	795
10.2.4.6 Single-Table Concurrent Write.....	796
10.2.5 Using the Hudi Client.....	797
10.2.5.1 Operating a Hudi Table Using hudi-cli.sh.....	797
10.2.6 Configuration Reference.....	799
10.2.6.1 Write Configuration.....	799
10.2.6.2 Configuration of Hive Table Synchronization.....	801
10.2.6.3 Index Configuration.....	803
10.2.6.4 Storage Configuration.....	806
10.2.6.5 Compaction and Cleaning Configurations.....	807
10.2.6.6 Metadata Table Configuration.....	810
10.2.6.7 Single-Table Concurrent Write Configuration.....	811
10.3 Hudi Performance Tuning.....	812
10.3.1 Performance Tuning Methods.....	812
10.3.2 Recommended Resource Configuration.....	812
10.4 Hudi SQL Syntax Reference.....	812
10.4.1 Constraints.....	812
10.4.2 DDL.....	813
10.4.2.1 CREATE TABLE.....	813
10.4.2.2 CREATE TABLE AS SELECT.....	815
10.4.2.3 DROP TABLE.....	817
10.4.2.4 SHOW TABLE.....	817
10.4.2.5 ALTER RENAME TABLE.....	818
10.4.2.6 ALTER ADD COLUMNS.....	819
10.4.2.7 TRUNCATE TABLE.....	819

10.4.3 DML.....	820
10.4.3.1 INSERT INTO.....	820
10.4.3.2 MERGE INTO.....	821
10.4.3.3 UPDATE.....	823
10.4.3.4 DELETE.....	824
10.4.3.5 COMPACTION.....	824
10.4.3.6 SET/RESET.....	825
10.5 Common Issues About Hudi.....	827
10.5.1 Data Write.....	827
10.5.1.1 Parquet/Avro schema Is Reported When Updated Data Is Written.....	827
10.5.1.2 UnsupportedOperationException Is Reported When Updated Data Is Written.....	828
10.5.1.3 SchemaCompatibilityException Is Reported When Updated Data Is Written.....	828
10.5.1.4 What Should I Do If Hudi Consumes Much Space in a Temporary Folder During Upsert?.....	828
10.5.2 Data Collection.....	829
10.5.2.1 IllegalArgumentException Is Reported When Kafka Is Used to Collect Data.....	829
10.5.2.2 HoodieException Is Reported When Data Is Collected.....	829
10.5.2.3 HoodieKeyException Is Reported When Data Is Collected.....	829
10.5.3 Hive Synchronization.....	830
10.5.3.1 SQLException Is Reported During Hive Data Synchronization.....	830
10.5.3.2 HoodieHiveSyncException Is Reported During Hive Data Synchronization.....	830
10.5.3.3 SemanticException Is Reported During Hive Data Synchronization.....	830
<b>11 Using Hue.....</b>	<b>832</b>
11.1 Using Hue from Scratch.....	832
11.2 Accessing the Hue Web UI.....	833
11.3 Hue Common Parameters.....	834
11.4 Using HiveQL Editor on the Hue Web UI.....	835
11.5 Using the Metadata Browser on the Hue Web UI.....	837
11.6 Using File Browser on the Hue Web UI.....	838
11.7 Using Job Browser on the Hue Web UI.....	841
11.8 Using HBase on the Hue Web UI.....	842
11.9 Typical Scenarios.....	843
11.9.1 HDFS on Hue.....	843
11.9.2 Hive on Hue.....	846
11.9.3 Oozie on Hue.....	848
11.10 Hue Log Overview.....	849
11.11 Common Issues About Hue.....	852
11.11.1 How Do I Solve the Problem that HQL Fails to Be Executed in Hue Using Internet Explorer?.....	852
11.11.2 Why Does the <b>use database</b> Statement Become Invalid When Hive Is Used?.....	853
11.11.3 What Can I Do If HDFS Files Fail to Be Accessed Using Hue WebUI?.....	853
11.11.4 What Should I Do If a Large File Fails to Be Uploaded on the Hue Page?.....	854
11.11.5 Hue Page Cannot Be Displayed When the Hive Service Is Not Installed in a Cluster.....	855
<b>12 Using Kafka.....</b>	<b>856</b>

12.1 Using Kafka from Scratch.....	856
12.2 Managing Kafka Topics.....	857
12.3 Querying Kafka Topics.....	859
12.4 Managing Kafka User Permissions.....	859
12.5 Managing Messages in Kafka Topics.....	862
12.6 Creating a Kafka Role.....	863
12.7 Kafka Common Parameters.....	864
12.8 Safety Instructions on Using Kafka.....	869
12.9 Kafka Specifications.....	872
12.10 Using the Kafka Client.....	873
12.11 Configuring Kafka HA and High Reliability Parameters.....	874
12.12 Changing the Broker Storage Directory.....	880
12.13 Checking the Consumption Status of Consumer Group.....	882
12.14 Kafka Balancing Tool Instructions.....	883
12.15 Kafka Token Authentication Mechanism Tool Usage.....	886
12.16 Kafka Feature Description.....	888
12.17 Using Kafka UI.....	889
12.17.1 Accessing Kafka UI.....	889
12.17.2 Kafka UI Overview.....	890
12.17.3 Creating a Topic on Kafka UI.....	892
12.17.4 Migrating a Partition on Kafka UI.....	893
12.17.5 Managing Topics on Kafka UI.....	894
12.17.6 Viewing Brokers on Kafka UI.....	897
12.17.7 Viewing a Consumer Group on Kafka UI.....	898
12.18 Introduction to Kafka Logs.....	900
12.19 Performance Tuning.....	903
12.19.1 Kafka Performance Tuning.....	903
12.20 Common Issues About Kafka.....	904
12.20.1 How Do I Solve the Problem that Kafka Topics Cannot Be Deleted?.....	904
<b>13 Using Loader.....</b>	<b>906</b>
13.1 Common Loader Parameters.....	906
13.2 Creating a Loader Role.....	908
13.3 Managing Loader Links.....	910
13.4 Importing Data.....	915
13.4.1 Overview.....	915
13.4.2 Importing Data Using Loader.....	917
13.4.3 Typical Scenario: Importing Data from an SFTP Server to HDFS or OBS.....	934
13.4.4 Typical Scenario: Importing Data from an SFTP Server to HBase.....	941
13.4.5 Typical Scenario: Importing Data from an SFTP Server to Hive.....	949
13.4.6 Typical Scenario: Importing Data from an SFTP Server to Spark.....	956
13.4.7 Typical Scenario: Importing Data from an FTP Server to HBase.....	962
13.4.8 Typical Scenario: Importing Data from a Relational Database to HDFS or OBS.....	970

13.4.9 Typical Scenario: Importing Data from a Relational Database to HBase.....	977
13.4.10 Typical Scenario: Importing Data from a Relational Database to Hive.....	984
13.4.11 Typical Scenario: Importing Data from a Relational Database to Spark.....	990
13.4.12 Typical Scenario: Importing Data from HDFS or OBS to HBase.....	996
13.4.13 Typical Scenario: Importing Data from a Relational Database to ClickHouse.....	1000
13.4.14 Typical Scenario: Importing Data from HDFS to ClickHouse.....	1005
13.5 Exporting Data.....	1009
13.5.1 Overview.....	1009
13.5.2 Using Loader to Export Data.....	1011
13.5.3 Typical Scenario: Exporting Data from HDFS/OBS to an SFTP Server.....	1023
13.5.4 Typical Scenario: Exporting Data from HBase to an SFTP Server.....	1030
13.5.5 Typical Scenario: Exporting Data from Hive to an SFTP Server.....	1035
13.5.6 Typical Scenario: Exporting Data from Spark to an SFTP Server.....	1040
13.5.7 Typical Scenario: Exporting Data from HDFS/OBS to a Relational Database.....	1045
13.5.8 Typical Scenario: Exporting Data from HBase to a Relational Database.....	1051
13.5.9 Typical Scenario: Exporting Data from Hive to a Relational Database.....	1056
13.5.10 Typical Scenario: Exporting Data from Spark to a Relational Database.....	1061
13.5.11 Typical Scenario: Importing Data from HBase to HDFS/OBS.....	1066
13.6 Job Management.....	1069
13.6.1 Migrating Loader Jobs in Batches.....	1070
13.6.2 Deleting Loader Jobs in Batches.....	1071
13.6.3 Importing Loader Jobs in Batches.....	1071
13.6.4 Exporting Loader Jobs in Batches.....	1072
13.6.5 Viewing Historical Job Information.....	1073
13.7 Operator Help.....	1075
13.7.1 Overview.....	1075
13.7.2 Input Operators.....	1078
13.7.2.1 CSV File Input.....	1078
13.7.2.2 Fixed File Input.....	1080
13.7.2.3 Table Input.....	1082
13.7.2.4 HBase Input.....	1084
13.7.2.5 HTML Input.....	1087
13.7.2.6 Hive input.....	1090
13.7.2.7 Spark Input.....	1092
13.7.3 Conversion Operators.....	1094
13.7.3.1 Long Date Conversion.....	1094
13.7.3.2 Null Value Conversion.....	1096
13.7.3.3 Constant Field Addition.....	1097
13.7.3.4 Random Value Conversion.....	1099
13.7.3.5 Concat Fields.....	1100
13.7.3.6 Extract Fields.....	1102
13.7.3.7 Modulo Integer.....	1104

13.7.3.8 String Cut.....	1105
13.7.3.9 EL Operation.....	1107
13.7.3.10 String Operations.....	1109
13.7.3.11 String Reverse.....	1111
13.7.3.12 String Trim.....	1112
13.7.3.13 Filter Rows.....	1114
13.7.3.14 Update Fields Operator.....	1115
13.7.4 Output Operators.....	1117
13.7.4.1 Hive output.....	1117
13.7.4.2 Spark Output.....	1120
13.7.4.3 Table Output .....	1123
13.7.4.4 File Output.....	1125
13.7.4.5 HBase Output.....	1127
13.7.4.6 ClickHouse Output.....	1129
13.7.5 Associating, Editing, Importing, or Exporting the Field Configuration of an Operator.....	1132
13.7.6 Using Macro Definitions in Configuration Items .....	1135
13.7.7 Operator Data Processing Rules.....	1136
13.8 Client Tool Description.....	1140
13.8.1 Running a Loader Job by Using Commands.....	1141
13.8.2 loader-tool Usage Guide.....	1145
13.8.3 loader-tool Usage Example.....	1154
13.8.4 schedule-tool Usage Guide.....	1157
13.8.5 schedule-tool Usage Example.....	1161
13.8.6 Using loader-backup to Back Up Job Data.....	1164
13.8.7 Open Source sqoop-shell Tool Usage Guide.....	1167
13.8.8 Example for Using the Open-Source sqoop-shell Tool (SFTP-HDFS).....	1179
13.8.9 Example for Using the Open-Source sqoop-shell Tool (Oracle-HBase).....	1190
13.9 Loader Log Overview.....	1201
13.10 Common Issues About Loader.....	1204
13.10.1 How to Resolve the Problem that Failed to Save Data When Using Internet Explorer 10 or Internet Explorer 11 ?.....	1204
13.10.2 Differences Among Connectors Used During the Process of Importing Data from the Oracle Database to HDFS.....	1205
<b>14 Using MapReduce.....</b>	<b>1207</b>
14.1 Converting MapReduce from the Single Instance Mode to the HA Mode.....	1207
14.2 Configuring the Log Archiving and Clearing Mechanism.....	1208
14.3 Reducing Client Application Failure Rate.....	1210
14.4 Transmitting MapReduce Tasks from Windows to Linux.....	1211
14.5 Configuring the Distributed Cache.....	1211
14.6 Configuring the MapReduce Shuffle Address.....	1213
14.7 Configuring the Cluster Administrator List.....	1214
14.8 Introduction to MapReduce Logs.....	1215
14.9 MapReduce Performance Tuning.....	1218

14.9.1 Optimization Configuration for Multiple CPU Cores.....	1218
14.9.2 Determining the Job Baseline.....	1223
14.9.3 Streamlining Shuffle.....	1225
14.9.4 AM Optimization for Big Tasks.....	1228
14.9.5 Speculative Execution.....	1229
14.9.6 Using Slow Start.....	1230
14.9.7 Optimizing Performance for Committing MR Jobs.....	1230
14.10 Common Issues About MapReduce.....	1231
14.10.1 Why Does It Take a Long Time to Run a Task Upon ResourceManager Active/Standby Switchover?.....	1231
14.10.2 Why Does a MapReduce Task Stay Unchanged for a Long Time?.....	1231
14.10.3 Why the Client Hangs During Job Running?.....	1232
14.10.4 Why Cannot HDFS_DELEGATION_TOKEN Be Found in the Cache?.....	1232
14.10.5 How Do I Set the Task Priority When Submitting a MapReduce Task?.....	1233
14.10.6 Why Physical Memory Overflow Occurs If a MapReduce Task Fails?.....	1233
14.10.7 After the Address of MapReduce JobHistoryServer Is Changed, Why the Wrong Page is Displayed When I Click the Tracking URL on the ResourceManager WebUI?.....	1235
14.10.8 MapReduce Job Failed in Multiple NameService Environment.....	1235
14.10.9 Why a Fault MapReduce Node Is Not Blacklisted?.....	1236
<b>15 Using Oozie.....</b>	<b>1237</b>
15.1 Using Oozie from Scratch.....	1237
15.2 Using the Oozie Client.....	1238
15.3 Enabling Oozie High Availability (HA).....	1240
15.4 Using Oozie Client to Submit an Oozie Job.....	1241
15.4.1 Submitting a Hive Job.....	1241
15.4.2 Submitting a Spark2x Job.....	1243
15.4.3 Submitting a Loader Job.....	1245
15.4.4 Submitting a DistCp Job.....	1247
15.4.5 Submitting Other Jobs.....	1249
15.5 Using Hue to Submit an Oozie Job.....	1252
15.5.1 Creating a Workflow.....	1252
15.5.2 Submitting a Workflow Job.....	1253
15.5.2.1 Submitting a Hive2 Job.....	1253
15.5.2.2 Submitting a Spark2x Job.....	1255
15.5.2.3 Submitting a Java Job.....	1256
15.5.2.4 Submitting a Loader Job.....	1256
15.5.2.5 Submitting a MapReduce Job.....	1257
15.5.2.6 Submitting a Sub-workflow Job.....	1258
15.5.2.7 Submitting a Shell Job.....	1259
15.5.2.8 Submitting an HDFS Job.....	1259
15.5.2.9 Submitting a DistCp Job.....	1260
15.5.2.10 Example of Mutual Trust Operations.....	1261
15.5.2.11 Submitting an SSH Job.....	1262

15.5.2.12 Submitting a Hive Script.....	1263
15.5.2.13 Submitting an Email Job.....	1263
15.5.3 Submitting a Coordinator Periodic Scheduling Job.....	1265
15.5.4 Submitting a Bundle Batch Processing Job.....	1266
15.5.5 Querying the Operation Results.....	1267
15.6 Oozie Log Overview.....	1267
15.7 Common Issues About Oozie.....	1270
15.7.1 How Do I Resolve the Problem that the Oozie Client Fails to Submit a MapReduce Job?.....	1270
15.7.2 Oozie Scheduled Tasks Are Not Executed on Time.....	1270
15.7.3 The Update of the share lib Directory of Oozie Does Not Take Effect.....	1271
<b>16 Using Ranger.....</b>	<b>1272</b>
16.1 Logging In to the Ranger Web UI.....	1272
16.2 Enabling Ranger Authentication.....	1274
16.3 Configuring Component Permission Policies.....	1275
16.4 Viewing Ranger Audit Information.....	1277
16.5 Configuring a Security Zone.....	1277
16.6 Changing the Ranger Data Source to LDAP for a Normal Cluster.....	1281
16.7 Viewing Ranger Permission Information.....	1282
16.8 Adding a Ranger Access Permission Policy for HDFS.....	1283
16.9 Adding a Ranger Access Permission Policy for HBase.....	1287
16.10 Adding a Ranger Access Permission Policy for Hive.....	1291
16.11 Adding a Ranger Access Permission Policy for Yarn.....	1300
16.12 Adding a Ranger Access Permission Policy for Spark2x.....	1303
16.13 Adding a Ranger Access Permission Policy for Kafka.....	1312
16.14 Adding a Ranger Access Permission Policy for HetuEngine.....	1321
16.15 Ranger Log Overview.....	1331
16.16 Common Issues About Ranger.....	1334
16.16.1 Why Ranger Startup Fails During the Cluster Installation?.....	1334
16.16.2 How Do I Determine Whether the Ranger Authentication Is Used for a Service?.....	1335
16.16.3 Why Cannot a New User Log In to Ranger After Changing the Password?.....	1335
16.16.4 When an HBase Policy Is Added or Modified on Ranger, Wildcard Characters Cannot Be Used to Search for Existing HBase Tables.....	1335
<b>17 Using Spark2x.....</b>	<b>1337</b>
17.1 Basic Operation.....	1337
17.1.1 Getting Started.....	1337
17.1.2 Configuring Parameters Rapidly.....	1340
17.1.3 Common Parameters.....	1349
17.1.4 Spark on HBase Overview and Basic Applications.....	1373
17.1.5 Spark on HBase V2 Overview and Basic Applications.....	1375
17.1.6 SparkSQL Permission Management(Security Mode).....	1377
17.1.6.1 Spark SQL Permissions.....	1377
17.1.6.2 Creating a Spark SQL Role.....	1382

17.1.6.3 Configuring Permissions for SparkSQL Tables, Columns, and Databases.....	1386
17.1.6.4 Configuring Permissions for SparkSQL to Use Other Components.....	1388
17.1.6.5 Configuring the Client and Server.....	1390
17.1.7 Scenario-Specific Configuration.....	1392
17.1.7.1 Configuring Multi-active Instance Mode.....	1392
17.1.7.2 Configuring the Multi-tenant Mode.....	1393
17.1.7.3 Configuring the Switchover Between the Multi-active Instance Mode and the Multi-tenant Mode .....	1395
17.1.7.4 Configuring the Size of the Event Queue.....	1396
17.1.7.5 Configuring Executor Off-Heap Memory.....	1397
17.1.7.6 Enhancing Stability in a Limited Memory Condition.....	1397
17.1.7.7 Viewing Aggregated Container Logs on the Web UI.....	1399
17.1.7.8 Configuring Whether to Display Spark SQL Statements Containing Sensitive Words.....	1400
17.1.7.9 Configuring Environment Variables in Yarn-Client and Yarn-Cluster Modes.....	1401
17.1.7.10 Configuring the Default Number of Data Blocks Divided by SparkSQL.....	1403
17.1.7.11 Configuring the Compression Format of a Parquet Table.....	1404
17.1.7.12 Configuring the Number of Lost Executors Displayed in WebUI.....	1405
17.1.7.13 Setting the Log Level Dynamically.....	1405
17.1.7.14 Configuring Whether Spark Obtains HBase Tokens.....	1407
17.1.7.15 Configuring LIFO for Kafka.....	1408
17.1.7.16 Configuring Reliability for Connected Kafka.....	1409
17.1.7.17 Configuring Streaming Reading of Driver Execution Results.....	1411
17.1.7.18 Filtering Partitions without Paths in Partitioned Tables.....	1413
17.1.7.19 Configuring Spark2x Web UI ACLs.....	1413
17.1.7.20 <b>Configuring Vector-based ORC Data Reading</b> .....	1415
17.1.7.21 Broaden Support for Hive Partition Pruning Predicate Pushdown.....	1417
17.1.7.22 Hive Dynamic Partition Overwriting Syntax.....	1417
17.1.7.23 Configuring the Column Statistics Histogram to Enhance the CBO Accuracy.....	1418
17.1.7.24 Configuring Local Disk Cache for JobHistory.....	1421
17.1.7.25 Configuring Spark SQL to Enable the Adaptive Execution Feature.....	1421
17.1.7.26 Configuring Event Log Rollover.....	1425
17.1.8 Adapting to the Third-party JDK When Ranger Is Used.....	1426
17.2 Spark2x Logs.....	1427
17.3 Obtaining Container Logs of a Running Spark Application.....	1430
17.4 Small File Combination Tools.....	1431
17.5 Using CarbonData for First Query.....	1434
17.6 Spark2x Performance Tuning.....	1435
17.6.1 Spark Core Tuning.....	1435
17.6.1.1 Data Serialization.....	1436
17.6.1.2 Optimizing Memory Configuration.....	1437
17.6.1.3 Setting the DOP.....	1437
17.6.1.4 Using Broadcast Variables.....	1438
17.6.1.5 Using the external shuffle service to improve performance.....	1438

17.6.1.6 Configuring Dynamic Resource Scheduling in Yarn Mode.....	1439
17.6.1.7 Configuring Process Parameters.....	1440
17.6.1.8 Designing the Direction Acyclic Graph (DAG).....	1442
17.6.1.9 Experience.....	1445
17.6.2 Spark SQL and DataFrame Tuning.....	1446
17.6.2.1 Optimizing the Spark SQL Join Operation.....	1446
17.6.2.2 Improving Spark SQL Calculation Performance Under Data Skew.....	1448
17.6.2.3 Optimizing Spark SQL Performance in the Small File Scenario.....	1450
17.6.2.4 Optimizing the INSERT...SELECT Operation.....	1451
17.6.2.5 Multiple JDBC Clients Concurrently Connecting to JDBCServer.....	1452
17.6.2.6 Optimizing Memory when Data Is Inserted into Dynamic Partitioned Tables.....	1453
17.6.2.7 Optimizing Small Files.....	1453
17.6.2.8 Optimizing the Aggregate Algorithms.....	1454
17.6.2.9 Optimizing Datasource Tables.....	1455
17.6.2.10 Merging CBO.....	1456
17.6.2.11 Optimizing SQL Query of Data of Multiple Sources.....	1458
17.6.2.12 SQL Optimization for Multi-level Nesting and Hybrid Join.....	1461
17.6.3 Spark Streaming Tuning.....	1463
17.6.4 Spark on OBS Tuning.....	1465
17.7 Common Issues About Spark2x.....	1465
17.7.1 Spark Core.....	1465
17.7.1.1 How Do I View Aggregated Spark Application Logs?.....	1465
17.7.1.2 Why Is the Return Code of Driver Inconsistent with Application State Displayed on ResourceManager WebUI?.....	1466
17.7.1.3 Why Cannot Exit the Driver Process?.....	1466
17.7.1.4 Why Does FetchFailedException Occur When the Network Connection Is Timed out.....	1467
17.7.1.5 How to Configure Event Queue Size If Event Queue Overflows?.....	1468
17.7.1.6 What Can I Do If the getApplicationReport Exception Is Recorded in Logs During Spark Application Execution and the Application Does Not Exit for a Long Time?.....	1469
17.7.1.7 What Can I Do If "Connection to ip:port has been quiet for xxx ms while there are outstanding requests" Is Reported When Spark Executes an Application and the Application Ends?.....	1470
17.7.1.8 Why Do Executors Fail to be Removed After the NodeManager Is Shut Down?.....	1471
17.7.1.9 What Can I Do If the Message "Password cannot be null if SASL is enabled" Is Displayed?.....	1472
17.7.1.10 What Should I Do If the Message "Failed to CREATE_FILE" Is Displayed in the Restarted Tasks When Data Is Inserted Into the Dynamic Partition Table?.....	1472
17.7.1.11 Why Tasks Fail When Hash Shuffle Is Used?.....	1473
17.7.1.12 What Can I Do If the Error Message "DNS query failed" Is Displayed When I Access the Aggregated Logs Page of Spark Applications?.....	1473
17.7.1.13 What Can I Do If Shuffle Fetch Fails Due to the "Timeout Waiting for Task" Exception?.....	1475
17.7.1.14 Why Does the Stage Retry due to the Crash of the Executor?.....	1475
17.7.1.15 Why Do the Executors Fail to Register Shuffle Services During the Shuffle of a Large Amount of Data?.....	1475
17.7.1.16 Why Does the Out of Memory Error Occur in NodeManager During the Execution of Spark Applications.....	1477

17.7.1.17 Why Does the Realm Information Fail to Be Obtained When SparkBench is Run on HiBench for the Cluster in Security Mode?.....	1478
17.7.2 Spark SQL and DataFrame.....	1479
17.7.2.1 What Do I have to Note When Using Spark SQL ROLLUP and CUBE?.....	1479
17.7.2.2 Why Spark SQL Is Displayed as a Temporary Table in Different Databases?.....	1480
17.7.2.3 How to Assign a Parameter Value in a Spark Command?.....	1481
17.7.2.4 What Directory Permissions Do I Need to Create a Table Using SparkSQL?.....	1481
17.7.2.5 Why Do I Fail to Delete the UDF Using Another Service?.....	1482
17.7.2.6 Why Cannot I Query Newly Inserted Data in a Parquet Hive Table Using SparkSQL?.....	1483
17.7.2.7 How to Use Cache Table?.....	1483
17.7.2.8 Why Are Some Partitions Empty During Repartition?.....	1484
17.7.2.9 Why Does 16 Terabytes of Text Data Fails to Be Converted into 4 Terabytes of Parquet Data?.....	1485
17.7.2.10 Why the Operation Fails When the Table Name Is TABLE?.....	1486
17.7.2.11 Why Is a Task Suspended When the ANALYZE TABLE Statement Is Executed and Resources Are Insufficient?.....	1486
17.7.2.12 If I Access a parquet Table on Which I Do not Have Permission, Why a Job Is Run Before "Missing Privileges" Is Displayed?.....	1487
17.7.2.13 Why Do I Fail to Modify MetaData by Running the Hive Command?.....	1488
17.7.2.14 Why Is "RejectedExecutionException" Displayed When I Exit Spark SQL?.....	1488
17.7.2.15 What Should I Do If the JDBCServer Process is Mistakenly Killed During a Health Check?.....	1488
17.7.2.16 Why No Result Is found When 2016-6-30 Is Set in the Date Field as the Filter Condition?.....	1489
17.7.2.17 Why Does the "--hivevar" Option I Specified in the Command for Starting spark-beeline Fail to Take Effect?.....	1490
17.7.2.18 Why Does the "Permission denied" Exception Occur When I Create a Temporary Table or View in Spark-beeline?.....	1490
17.7.2.19 Why Is the "Code of method ... grows beyond 64 KB" Error Message Displayed When I Run Complex SQL Statements?.....	1491
17.7.2.20 Why Is Memory Insufficient if 10 Terabytes of TPCDS Test Suites Are Consecutively Run in Beeline/JDBCServer Mode?.....	1491
17.7.2.21 Why Are Some Functions Not Available when Another JDBCServer Is Connected?.....	1492
17.7.2.22 Why Does an Exception Occur When I Drop Functions Created Using the Add Jar Statement?.....	1493
17.7.2.23 Why Does Spark2x Have No Access to DataSource Tables Created by Spark1.5?.....	1495
17.7.2.24 Why Does Spark-beeline Fail to Run and Error Message "Failed to create ThriftService instance" Is Displayed?.....	1495
17.7.3 Spark Streaming.....	1496
17.7.3.1 Streaming Task Prints the Same DAG Log Twice.....	1497
17.7.3.2 What Can I Do If Spark Streaming Tasks Are Blocked?.....	1498
17.7.3.3 What Should I Pay Attention to When Optimizing Spark Streaming Task Parameters?.....	1499
17.7.3.4 Why Does the Spark Streaming Application Fail to Be Submitted After the Token Validity Period Expires?.....	1499
17.7.3.5 Why does Spark Streaming Application Fail to Restart from Checkpoint When It Creates an Input Stream Without Output Logic?.....	1500
17.7.3.6 Why Is the Input Size Corresponding to Batch Time on the Web UI Set to 0 Records When Kafka Is Restarted During Spark Streaming Running?.....	1502

17.7.4 Why the Job Information Obtained from the restful Interface of an Ended Spark Application Is Incorrect?.....	1503
17.7.5 Why Cannot I Switch from the Yarn Web UI to the Spark Web UI?.....	1504
17.7.6 What Can I Do If an Error Occurs when I Access the Application Page Because the Application Cached by HistoryServer Is Recycled?.....	1505
17.7.7 Why Is not an Application Displayed When I Run the Application with the Empty Part File?.....	1506
17.7.8 Why Does Spark2x Fail to Export a Table with the Same Field Name?.....	1506
17.7.9 Why JRE fatal error after running Spark application multiple times?.....	1506
17.7.10 "This page can't be displayed" Is Displayed When Internet Explorer Fails to Access the Native Spark2x UI.....	1507
17.7.11 How Does Spark2x Access External Cluster Components?.....	1507
17.7.12 Why Does the Foreign Table Query Fail When Multiple Foreign Tables Are Created in the Same Directory?.....	1510
17.7.13 What Should I Do If the Native Page of an Application of Spark2x JobHistory Fails to Display During Access to the Page.....	1510
17.7.14 Spark Shuffle Exception Handling.....	1511
<b>18 Using Tez.....</b>	<b>1512</b>
18.1 Common Tez Parameters.....	1512
18.2 Accessing TezUI.....	1512
18.3 Log Overview.....	1513
18.4 Common Issues.....	1515
18.4.1 TezUI Cannot Display Tez Task Execution Details.....	1515
18.4.2 Error Occurs When a User Switches to the Tez Web UI.....	1515
18.4.3 Yarn Logs Cannot Be Viewed on the TezUI Page.....	1516
18.4.4 Table Data Is Empty on the TezUI HiveQueries Page.....	1516
<b>19 Using Yarn.....</b>	<b>1518</b>
19.1 Common Yarn Parameters.....	1518
19.2 Creating Yarn Roles.....	1521
19.3 Using the Yarn Client.....	1522
19.4 Configuring Resources for a NodeManager Role Instance.....	1524
19.5 Changing NodeManager Storage Directories.....	1525
19.6 Configuring Strict Permission Control for Yarn.....	1527
19.7 Configuring Container Log Aggregation.....	1528
19.8 Using CGroups with YARN.....	1535
19.9 Configuring the Number of ApplicationMaster Retries.....	1537
19.10 Configure the ApplicationMaster to Automatically Adjust the Allocated Memory.....	1537
19.11 Configuring the Access Channel Protocol.....	1539
19.12 Configuring Memory Usage Detection.....	1540
19.13 Configuring the Additional Scheduler WebUI.....	1541
19.14 Configuring Yarn Restart.....	1542
19.15 Configuring ApplicationMaster Work Preserving.....	1543
19.16 Configuring the Localized Log Levels.....	1545
19.17 Configuring Users That Run Tasks.....	1546

19.18 Yarn Log Overview.....	1547
19.19 Yarn Performance Tuning.....	1550
19.19.1 Preempting a Task.....	1550
19.19.2 Setting the Task Priority.....	1553
19.19.3 Optimizing Node Configuration.....	1554
19.20 Common Issues About Yarn.....	1560
19.20.1 Why Mounted Directory for Container is Not Cleared After the Completion of the Job While Using CGroups?.....	1560
19.20.2 Why the Job Fails with HDFS_DELEGATION_TOKEN Expired Exception?.....	1561
19.20.3 Why Are Local Logs Not Deleted After YARN Is Restarted?.....	1561
19.20.4 Why the Task Does Not Fail Even Though AppAttempts Restarts for More Than Two Times?...	1562
19.20.5 Why Is an Application Moved Back to the Original Queue After ResourceManager Restarts?...	1562
19.20.6 Why Does Yarn Not Release the Blacklist Even All Nodes Are Added to the Blacklist? .....	1562
19.20.7 Why Does the Switchover of ResourceManager Occur Continuously?.....	1563
19.20.8 Why Does a New Application Fail If a NodeManager Has Been in Unhealthy Status for 10 Minutes?.....	1564
19.20.9 What Is the Queue Replacement Policy?.....	1564
19.20.10 Why Does an Error Occur When I Query the ApplicationID of a Completed or Non-existing Application Using the RESTful APIs?.....	1565
19.20.11 Why May A Single NodeManager Fault Cause MapReduce Task Failures in the Superior Scheduling Mode?.....	1565
19.20.12 Why Are Applications Suspended After They Are Moved From Lost_and_Found Queue to Another Queue?.....	1566
19.20.13 How Do I Limit the Size of Application Diagnostic Messages Stored in the ZKstore?.....	1566
19.20.14 Why Does a MapReduce Job Fail to Run When a Non-ViewFS File System Is Configured as ViewFS?.....	1567
19.20.15 Why Do Reduce Tasks Fail to Run in Some OSs After the Native Task Feature is Enabled?.....	1568
<b>20 Using ZooKeeper.....</b>	<b>1570</b>
20.1 Using ZooKeeper from Scratch.....	1570
20.2 Common ZooKeeper Parameters.....	1572
20.3 Using a ZooKeeper Client.....	1573
20.4 Configuring the ZooKeeper Permissions.....	1574
20.5 Changing the ZooKeeper Storage Directory.....	1578
20.6 Configuring the ZooKeeper Connection.....	1580
20.7 Configuring ZooKeeper Response Timeout Interval.....	1582
20.8 Binding the Client to an IP Address.....	1583
20.9 Configuring the Port Range Bound to the Client.....	1584
20.10 Performing Special Configuration on ZooKeeper Clients in the Same JVM.....	1586
20.11 Configuring a Quota for a Znode.....	1588
20.12 ZooKeeper Log Overview.....	1590
20.13 Common Issues About ZooKeeper.....	1593
20.13.1 Why Do ZooKeeper Servers Fail to Start After Many znodes Are Created?.....	1593
20.13.2 Why Does the ZooKeeper Server Display the java.io.IOException: Len Error Log?.....	1595

20.13.3 Why Four Letter Commands Don't Work With Linux netcat Command When Secure Netty Configurations Are Enabled at Zookeeper Server?.....	1596
20.13.4 How Do I Check Which ZooKeeper Instance Is a Leader?.....	1597
20.13.5 Why Cannot the Client Connect to ZooKeeper using the IBM JDK?.....	1597
20.13.6 What Should I Do When the ZooKeeper Client Fails to Refresh a TGT?.....	1597
20.13.7 Why Is Message "Node does not exist" Displayed when A Large Number of Znodes Are Deleted Using the <b>deleteall</b> Command.....	1598
<b>21 Appendix.....</b>	<b>1599</b>
21.1 Modifying Cluster Service Configuration Parameters.....	1599
21.2 Accessing FusionInsight Manager.....	1600
21.3 Using an MRS Client.....	1603
21.3.1 Using an MRS Client on Nodes Inside a MRS Cluster.....	1603
21.3.2 Using an MRS Client on Nodes Outside a MRS Cluster.....	1604


# 1 Using CarbonData

## 1.1 Overview

### 1.1.1 CarbonData Overview

CarbonData is a new Apache Hadoop native data-store format. CarbonData allows faster interactive queries over PetaBytes of data using advanced columnar storage, index, compression, and encoding techniques to improve computing efficiency. In addition, CarbonData is also a high-performance analysis engine that integrates data sources with Spark.

Figure 1-1 Basic architecture of CarbonData




The purpose of using CarbonData is to provide quick response to ad hoc queries of big data. Essentially, CarbonData is an Online Analytical Processing (OLAP) engine, which stores data by using tables similar to those in Relational Database Management System (RDBMS). You can import more than 10 TB data to tables created in CarbonData format, and CarbonData automatically organizes and stores data using the compressed multi-dimensional indexes. After data is loaded to CarbonData, CarbonData responds to ad hoc queries in seconds.

CarbonData integrates data sources into the Spark ecosystem and you can query and analyze the data using Spark SQL. You can also use the third-party tool JDBCServer provided by Spark to connect to SparkSQL.

## Topology of CarbonData

CarbonData runs as a data source inside Spark. Therefore, CarbonData does not start any additional processes on nodes in clusters. CarbonData engine runs inside the Spark executor.

Figure 1-2 Topology of CarbonData



Data stored in CarbonData Table is divided into several CarbonData data files. Each time when data is queried, CarbonData Engine reads and filters data sets. CarbonData Engine runs as a part of the Spark Executor process and is responsible for handling a subset of data file blocks.

Table data is stored in HDFS. Nodes in the same Spark cluster can be used as HDFS data nodes.

## CarbonData Features

- SQL: CarbonData is compatible with Spark SQL and supports SQL query operations performed on Spark SQL.
- Simple Table dataset definition: CarbonData allows you to define and create datasets by using user-friendly Data Definition Language (DDL) statements. CarbonData DDL is flexible and easy to use, and can define complex tables.

- Easy data management: CarbonData provides various data management functions for data loading and maintenance. CarbonData supports bulk loading of historical data and incremental loading of new data. Loaded data can be deleted based on load time and a specific loading operation can be undone.
- CarbonData file format is a columnar store in HDFS. This format has many new column-based file storage features, such as table splitting and data compression. CarbonData has the following characteristics:
  - Stores data along with index: Significantly accelerates query performance and reduces the I/O scans and CPU resources, when there are filters in the query. CarbonData index consists of multiple levels of indices. A processing framework can leverage this index to reduce the task that needs to be scheduled and processed, and it can also perform skip scan in more finer grain unit (called blocklet) in task side scanning instead of scanning the whole file.
  - Operable encoded data: Through supporting efficient compression, CarbonData can query on compressed/encoded data. The data can be converted just before returning the results to the users, which is called late materialized.
  - Support for various use cases with one single data format: like interactive OLAP-style query, sequential access (big scan), and random access (narrow scan).

## Key Technologies and Advantages of CarbonData

- Quick query response: CarbonData features high-performance query. The query speed of CarbonData is 10 times of that of Spark SQL. It uses dedicated data formats and applies multiple index technologies and multiple push-down optimizations, providing quick response to TB-level data queries.
- Efficient data compression: CarbonData compresses data by combining the lightweight and heavyweight compression algorithms. This significantly saves 60% to 80% data storage space and the hardware storage cost.

## 1.1.2 Main Specifications of CarbonData

### Main Specifications of CarbonData

**Table 1-1** Main Specifications of CarbonData

Entity	Tested Value	Test Environment
Number of tables	10000	3 nodes. 4 vCPUs and 20 GB memory for each executor. Driver memory: 5 GB, 3 executors. Total columns: 107 String: 75 Int: 13 BigInt: 7 Timestamp: 6 Double: 6
Number of table columns	2000	3 nodes. 4 vCPUs and 20 GB memory for each executor. Driver memory: 5 GB, 3 executors.
Maximum size of a raw CSV file	200GB	17 cluster nodes. 150 GB memory and 25 vCPUs for each executor. Driver memory: 10 GB, 17 executors.
Number of CSV files in each folder	100 folders. Each folder has 10 files. The size of each file is 50 MB.	3 nodes. 4 vCPUs and 20 GB memory for each executor. Driver memory: 5 GB, 3 executors.
Number of load folders	10000	3 nodes. 4 vCPUs and 20 GB memory for each executor. Driver memory: 5 GB, 3 executors.

The memory required for data loading depends on the following factors:

- Number of columns
- Column values
- Concurrency (configured using **carbon.number.of.cores.while.loading**)
- Sort size in memory (configured using **carbon.sort.size**)
- Intermediate cache (configured using **carbon.graph.rowset.size**)

Data loading of an 8 GB CSV file that contains 10 million records and 300 columns with each row size being about 0.8 KB requires about 10 GB executor memory.

That is, set **carbon.sort.size** to **100000** and retain the default values for other parameters.

## Table Specifications

**Table 1-2** Table specifications

Entity	Tested Value
Number of secondary index tables	10
Number of composite columns in a secondary index table	5
Length of column name in a secondary index table (unit: character)	120
Length of a secondary index table name (unit: character)	120
Cumulative length of all secondary index table names + column names in an index table* (unit: character)	3800**

 **NOTE**

- \* Characters of column names in an index table refers to the upper limit allowed by Hive or the upper limit of available resources.
- \*\* Secondary index tables are registered using Hive and stored in HiveSERDEPROPERTIES in JSON format. The value of **SERDEPROPERTIES** supported by Hive can contain a maximum of 4,000 characters and cannot be changed.

## 1.2 Configuration Reference

This section provides the details of all the configurations required for the CarbonData System.

**Table 1-3** System configurations in **carbon.properties**

Parameter	Default Value	Description
carbon.ddl.base.hdfs.url	hdfs://hacluster/opt/data	<p>HDFS relative path from the HDFS base path, which is configured in <b>fs.defaultFS</b>. The path configured in <b>carbon.ddl.base.hdfs.url</b> will be appended to the HDFS path configured in <b>fs.defaultFS</b>. If this path is configured, you do not need to pass the complete path while dataload.</p> <p>For example, if the absolute path of the CSV file is <b>hdfs://10.18.101.155:54310/data/cnbc/2016/xyz.csv</b>, the path <b>hdfs://10.18.101.155:54310</b> will come from property <b>fs.defaultFS</b> and you can configure <b>/data/cnbc/</b> as <b>carbon.ddl.base.hdfs.url</b>.</p> <p>During data loading, you can specify the CSV path as <b>/2016/xyz.csv</b>.</p>
carbon.badRecords.location	-	Storage path of bad records. This path is an HDFS path. The default value is <b>Null</b> . If bad records logging or bad records operation redirection is enabled, the path must be configured by the user.
carbon.badRecords.action	fail	<p>The following are four types of actions for bad records:</p> <p><b>FORCE:</b> Data is automatically corrected by storing the bad records as NULL.</p> <p><b>REDIRECT:</b> Bad records are written to the raw CSV instead of being loaded.</p> <p><b>IGNORE:</b> Bad records are neither loaded nor written to the raw CSV.</p> <p><b>FAIL:</b> Data loading fails if any bad records are found.</p>
carbon.update.sync.folder	/tmp/carbondata	<p>Specifies the <b>modifiedTime.mdt</b> file path. You can set it to an existing path or a new path.</p> <p><b>NOTE</b> If you set this parameter to an existing path, ensure that all users can access the path and the path has the 777 permission.</p>

**Table 1-4** Performance configurations in **carbon.properties**

Parameter	Default Value	Description
<b>Data Loading Configuration</b>		

Parameter	Default Value	Description
carbon.sort.file.write.buffer.size	16384	CarbonData sorts data and writes it to a temporary file to limit memory usage. This parameter controls the size of the buffer used for reading and writing temporary files. The unit is bytes. The value ranges from 10240 to 10485760.
carbon.graph.rowset.size	100000	Rowset size exchanged in data loading graph steps. The value ranges from 500 to 1,000,000.
carbon.number.of.cores.while.loading	6	Number of cores used during data loading. The greater the number of cores, the better the compaction performance. If the CPU resources are sufficient, you can increase the value of this parameter.
carbon.sort.size	500000	Number of records to be sorted
carbon.enableXXHash	true	Hashmap algorithm used for hashkey calculation
carbon.number.of.cores.block.sort	7	Number of cores used for sorting blocks during data loading
carbon.max.driver.lru.cache.size	-1	Maximum size of LRU caching for data loading at the driver side. The unit is MB. The default value is <b>-1</b> , indicating that there is no memory limit for the caching. Only integer values greater than 0 are accepted.
carbon.max.executor.lru.cache.size	-1	Maximum size of LRU caching for data loading at the executor side. The unit is MB. The default value is <b>-1</b> , indicating that there is no memory limit for the caching. Only integer values greater than 0 are accepted. If this parameter is not configured, the value of <b>carbon.max.driver.lru.cache.size</b> is used.
carbon.merge.sort.prefetch	true	Whether to enable prefetch of data during merge sort while reading data from sorted temp files in the process of data loading
carbon.update.persist.enable	true	Configuration to enable the dataset of RDD/dataframe to persist data. Enabling this will reduce the execution time of UPDATE operation.
enable.unsafe.sort	true	Whether to use unsafe sort during data loading. Unsafe sort reduces the garbage collection during data load operation, resulting in better performance. The default value is <b>true</b> , indicating that unsafe sort is enabled.

Parameter	Default Value	Description
enable.offheap.sort	true	Whether to use off-heap memory for sorting of data during data loading
offheap.sort.chunk.size.inmb	64	Size of data chunks to be sorted, in MB. The value ranges from 1 to 1024.
carbon.unsafe.working.memory.in.mb	512	<p>Size of the unsafe working memory. This will be used for sorting data and storing column pages. The unit is MB.</p> <p>Memory required for data loading:  <code>carbon.number.of.cores.while.loading</code> [default value is 6] x Number of tables to load in parallel x <code>offheap.sort.chunk.size.inmb</code> [default value is 64 MB] + <code>carbon.blockletgroup.size.in.mb</code> [default value is 64 MB] + Current compaction ratio [64 MB/ 3.5])                      = Around 900 MB per table</p> <p>Memory required for data query:                      (SPARK_EXECUTOR_INSTANCES. [default value is 2] x (<code>carbon.blockletgroup.size.in.mb</code> [default value: 64 MB] + <code>carbon.blockletgroup.size.in.mb</code> [default value = 64 MB x 3.5] x Number of cores per executor [default value: 1])                      = ~ 600 MB</p>
carbon.sort.inmemory.storage.size.in.mb	512	Size of the intermediate sort data to be kept in the memory. Once the specified value is reached, the system writes data to the disk. The unit is MB.
sort.inmemory.size.inmb	1024	<p>Size of the intermediate sort data to be kept in the memory. Once the specified value is reached, the system writes data to the disk. The unit is MB.</p> <p>If <b>carbon.unsafe.working.memory.in.mb</b> and <b>carbon.sort.inmemory.storage.size.in.mb</b> are configured, you do not need to set this parameter. If this parameter has been configured, 20% of the memory is used for working memory <b>carbon.unsafe.working.memory.in.mb</b>, and 80% is used for sort storage memory <b>carbon.sort.inmemory.storage.size.in.mb</b>.</p> <p><b>NOTE</b>                      The value of <b>spark.yarn.executor.memoryOverhead</b> configured for Spark must be greater than the value of <b>sort.inmemory.size.inmb</b> configured for CarbonData. Otherwise, Yarn might stop the executor if off-heap access exceeds the configured executor memory.</p>

Parameter	Default Value	Description
carbon.blockletgroup.size.in.mb	64	The data is read as a group of blocklets which are called blocklet groups. This parameter specifies the size of each blocklet group. Higher value results in better sequential I/O access.  The minimum value is 16 MB. Any value less than 16 MB will be reset to the default value (64 MB).  The unit is MB.
enable.inmemory.merge.sort	false	Whether to enable <b>inmemorymerge sort</b> .
use.offheap.in.query.processing	true	Whether to enable <b>offheap</b> in query processing.
carbon.load.sort.scope	local_sort	Sort scope for the load operation. There are two types of sort: <b>batch_sort</b> and <b>local_sort</b> . If <b>batch_sort</b> is selected, the loading performance is improved but the query performance is reduced.
carbon.batch.sort.size.inmb	-	Size of data to be considered for batch sorting during data loading. The recommended value is less than 45% of the total sort data. The unit is MB.  <b>NOTE</b> If this parameter is not set, its value is about 45% of the value of <b>sort.inmemory.size.inmb</b> by default.
enable.unsafe.columnpage	true	Whether to keep page data in heap memory during data loading or query to prevent garbage collection bottleneck.
carbon.use.local.dir	false	Whether to use Yarn local directories for multi-disk data loading. If this parameter is set to <b>true</b> , Yarn local directories are used to load multi-disk data to improve data loading performance.
carbon.use.multiple.temp.dir	false	Whether to use multiple temporary directories for storing temporary files to improve data loading performance.
carbon.load.datamaps.parallel.db_name.table_name	NA	The value can be <b>true</b> or <b>false</b> . You can set the database name and table name to improve the first query performance of the table.
<b>Compaction Configuration</b>		

Parameter	Default Value	Description
carbon.number.of.cores.while.compacting	2	Number of cores to be used while compacting data. The greater the number of cores, the better the compaction performance. If the CPU resources are sufficient, you can increase the value of this parameter.
carbon.compaction.level.threshold	4,3	This configuration is for minor compaction which decides how many segments to be merged. For example, if this parameter is set to <b>2,3</b> , minor compaction is triggered every two segments. <b>3</b> is the number of level 1 compacted segments which is further compacted to new segment. The value ranges from 0 to 100.
carbon.major.compaction.size	1024	Major compaction size. Sum of the segments which is below this threshold will be merged. The unit is MB.
carbon.horizontal.compaction.enable	true	Whether to enable/disable horizontal compaction. After every DELETE and UPDATE statement, horizontal compaction may occur in case the incremental (DELETE/ UPDATE) files becomes more than specified threshold. By default, this parameter is set to <b>true</b> . You can set this parameter to <b>false</b> to disable horizontal compaction.
carbon.horizontal.update.compaction.threshold	1	Threshold limit on number of UPDATE delta files within a segment. In case the number of delta files goes beyond the threshold, the UPDATE delta files within the segment becomes eligible for horizontal compaction and are compacted into single UPDATE delta file. By default, this parameter is set to <b>1</b> . The value ranges from <b>1</b> to <b>10000</b> .
carbon.horizontal.delete.compaction.threshold	1	Threshold limit on number of DELETE incremental files within a block of a segment. In case the number of incremental files goes beyond the threshold, the DELETE incremental files for the particular block of the segment becomes eligible for horizontal compaction and are compacted into single DELETE incremental file. By default, this parameter is set to <b>1</b> . The value ranges from <b>1</b> to <b>10000</b> .
<b>Query Configuration</b>		
carbon.number.of.cores	4	Number of cores to be used during query

Parameter	Default Value	Description
carbon.limit.block.distribution.enable	false	Whether to enable the CarbonData distribution for limit query. The default value is <b>false</b> , indicating that block distribution is disabled for query statements that contain the keyword limit. For details about how to optimize this parameter, see <a href="#">Configurations for Performance Tuning</a> .
carbon.custom.block.distribution	false	Whether to enable Spark or CarbonData block distribution. By default, the value is <b>false</b> , indicating that Spark block distribution is enabled. To enable CarbonData block distribution, change the value to <b>true</b> .
carbon.infilter.subquery.pushdown.enable	false	If this is set to <b>true</b> and a Select query is triggered in the filter with subquery, the subquery is executed and the output is broadcast as IN filter to the left table. Otherwise, SortMergeSemiJoin is executed. You are advised to set this to <b>true</b> when IN filter subquery does not return too many records. For example, when the IN sub-sentence query returns 10,000 or fewer records, enabling this parameter will give the query results faster.  Example: <i>select * from flow_carbon_256b where cus_no in (select cus_no from flow_carbon_256b where dt&gt;='20260101' and dt&lt;='20260701' and txn_bk='tk_1' and txn_br='tr_1') limit 1000;</i>
carbon.scheduler.minRegisteredResourcesRatio	0.8	Minimum resource (executor) ratio needed for starting the block distribution. The default value is <b>0.8</b> , indicating that 80% of the requested resources are allocated for starting block distribution.
carbon.dynamicAllocation.schedulerTimeout	5	Maximum time that the scheduler waits for executors to be active. The default value is <b>5</b> seconds, and the maximum value is <b>15</b> seconds.
enable.unsafe.in.query.processing	true	Whether to use unsafe sort during query. Unsafe sort reduces the garbage collection during query, resulting in better performance. The default value is <b>true</b> , indicating that unsafe sort is enabled.
carbon.enable.vector.reader	true	Whether to enable vector processing for result collection to improve query performance
carbon.query.show.datamaps	true	<b>SHOW TABLES</b> lists all tables including the primary table and datamaps. To filter out the datamaps, set this parameter to <b>false</b> .
<b>Secondary Index Configuration</b>		

Parameter	Default Value	Description
carbon.secondary.index.creation.threads	1	Number of threads to concurrently process segments during secondary index creation. This property helps fine-tuning the system when there are a lot of segments in a table. The value ranges from 1 to 50.
carbon.si.lookup.partialstring	true	<ul style="list-style-type: none"> <li>When the parameter value is <b>true</b>, it includes indexes started with, ended with, and contained.</li> <li>When the parameter value is <b>false</b>, it includes only secondary indexes started with.</li> </ul>
carbon.si.segment.merge	true	<p>Enabling this property merges <b>.carbondata</b> files inside the secondary index segment. The merging will happen after the load operation. That is, at the end of the secondary index table load, small files are checked and merged.</p> <p><b>NOTE</b> Table Block Size is used as the size threshold for merging small files.</p>

**Table 1-5** Other configurations in **carbon.properties**

Parameter	Default Value	Description
<b>Data Loading Configuration</b>		
carbon.lock.type	HDFSLOCK	<p>Type of lock to be acquired during concurrent operations on a table.</p> <p>There are following types of lock implementation:</p> <ul style="list-style-type: none"> <li><b>LOCALLOCK:</b> Lock is created on local file system as a file. This lock is useful when only one Spark driver (or JDBCServer) runs on a machine.</li> <li><b>HDFSLOCK:</b> Lock is created on HDFS file system as a file. This lock is useful when multiple Spark applications are running and no ZooKeeper is running on a cluster.</li> </ul>
carbon.sort.intermediate.files.limit	20	Minimum number of intermediate files. After intermediate files are generated, sort and merge the files. For details about how to optimize this parameter, see <a href="#">Configurations for Performance Tuning</a> .
carbon.csv.read.buffer.size.byte	1048576	Size of CSV reading buffer

Parameter	Default Value	Description
carbon.merge.sort.reader.thread	3	Maximum number of threads used for reading intermediate files for final merging.
carbon.concurrent.lock.retries	100	Maximum number of retries used to obtain the concurrent operation lock. This parameter is used for concurrent loading.
carbon.concurrent.lock.retry.timeout.sec	1	Interval between the retries to obtain the lock for concurrent operations.
carbon.lock.retries	3	Maximum number of retries to obtain the lock for any operations other than import.
carbon.lock.retry.timeout.sec	5	Interval between the retries to obtain the lock for any operation other than import.
carbon.tempstore.location	/opt/Carbon/TempStoreLoc	Temporary storage location. By default, the <b>System.getProperty("java.io.tmpdir")</b> method is used to obtain the value. For details about how to optimize this parameter, see the description of <b>carbon.use.local.dir</b> in <a href="#">Configurations for Performance Tuning</a> .
carbon.load.log.counter	500000	Data loading records count in logs
SERIALIZATION_NULL_FORMAT	\N	Value to be replaced with NULL
carbon.skip.empty.line	false	Setting this property will ignore the empty lines in the CSV file during data loading.
carbon.load.datamaps.parallel	false	Whether to enable parallel datamap loading for all tables in all sessions. This property will improve the time to load datamaps into memory by distributing the job among executors, thus improving query performance.
<b>Merging Configuration</b>		
carbon.numberof.preserve.segments	0	If you want to preserve some number of segments from being compacted, then you can set this configuration. For example, if <b>carbon.numberof.preserve.segments</b> is set to <b>2</b> , the latest two segments will always be excluded from the compaction. No segments will be preserved by default.

Parameter	Default Value	Description
carbon.allowed.compaction.days	0	This configuration is used to control on the number of recent segments that needs to be merged.  For example, if this parameter is set to <b>2</b> , the segments which are loaded in the time frame of past 2 days only will get merged. Segments which are loaded earlier than 2 days will not be merged.  This configuration is disabled by default.
carbon.enable.auto.load.merge	false	Whether to enable compaction along with data loading.
carbon.merge.index.in.segment	true	This configuration enables to merge all the CarbonIndex files ( <b>.carbonindex</b> ) into a single MergeIndex file ( <b>.carbonindexmerge</b> ) upon data loading completion. This significantly reduces the delay in serving the first query.
<b>Query Configuration</b>		
max.query.execution.time	60	Maximum time allowed for one query to be executed.  The unit is minute.
carbon.enableMinMax	true	MinMax is used to improve query performance. You can set this to <b>false</b> to disable this function.
carbon.lease.recovery.retry.count	5	Maximum number of attempts that need to be made for recovering a lease on a file.  Minimum value: <b>1</b> Maximum value: <b>50</b>
carbon.lease.recovery.retry.interval	1000 (ms)	Interval or pause time after a lease recovery attempt is made on a file.  Minimum value: <b>1000</b> (ms) Maximum value: <b>10000</b> (ms)

**Table 1-6** Spark configuration reference in **spark-defaults.conf**

Parameter	Default Value	Description
spark.driver.memory	4G	Memory to be used for the driver process. SparkContext has been initialized. <b>NOTE</b> In client mode, do not use SparkConf to set this parameter in the application because the driver JVM has been started. To configure this parameter, configure it in the <b>--driver-memory</b> command-line option or in the default property file.
spark.executor.memory	4GB	Memory to be used for each executor process.
spark.sql.crossJoin.enabled	true	If the query contains a cross join, enable this property so that no error is thrown. In this case, you can use a cross join instead of a join for better performance.

Configure the following parameters in the **spark-defaults.conf** file on the Spark driver.

- In spark-sql mode:

**Table 1-7** Parameter description

Parameter	Value	Description
spark.driver.extraJavaOptions	-Dlog4j.configuration=file:/opt/client/Spark2x/spark/conf/log4j.properties - Djetty.version=x.y.z - Dzookeeper.server.principal=zookeeper/hadoop.<System domain name> - Djava.security.krb5.conf=/opt/client/KrbClient/kerberos/var/krb5kdc/krb5.conf - Djava.security.auth.login.config=/opt/client/Spark2x/spark/conf/jaas.conf - Dorg.xerial.snappy.tmpdir=/opt/client/Spark2x/tmp - Dcarbon.properties.filepath=/opt/client/Spark2x/spark/conf/carbon.properties - Djava.io.tmpdir=/opt/client/Spark2x/tmp	The default value <b>/opt/client/Spark2x/spark</b> indicates <b>CLIENT_HOME</b> of the client and is added to the end of the value of <b>spark.driver.extraJavaOptions</b> . This parameter is used to specify the path of the <b>carbon.properties</b> file in Driver. <b>NOTE</b> Spaces next to equal marks (=) are not allowed.

Parameter	Value	Description
spark.sql.session.state.builder	org.apache.spark.sql.hive.FIHiveACLSessionStateBuilder	Session state constructor.
spark.carbon.sqlastbuilder.classname	org.apache.spark.sql.hive.CarbonInternalSqlAstBuilder	AST constructor.
spark.sql.catalog.class	org.apache.spark.sql.hive.HiveACLExternalCatalog	Hive External catalog to be used. This parameter is mandatory if Spark ACL is enabled.
spark.sql.hive.implementation	org.apache.spark.sql.hive.HiveACLClientImpl	How to call the Hive client. This parameter is mandatory if Spark ACL is enabled.
spark.sql.hiveClient.isolation.enabled	false	This parameter is mandatory if Spark ACL is enabled.

- In JDBCServer mode:

**Table 1-8** Parameter description

Parameter	Value	Description
spark.driver.extraJavaOptions	-Xloggc:\${SPARK_LOG_DIR}/indexserver-omm-%p-gc.log -XX: +PrintGCDetails -XX:- OmitStackTracenFastThrow -XX: +PrintGCTimeStamps -XX: +PrintGCDateStamps - XX:MaxDirectMemorySize=512M - XX:MaxMetaspaceSize=512M -XX: +UseGCLogFileRotation - XX:NumberOfGCLogFiles=20 - XX:GCLogFileSize=10M - XX:OnOutOfMemoryError='kill -9 %p' - Djetty.version=x.y.z - Dorg.xerial.snappy.tmpdir=\${BIGDATA_HOME}/tmp/spark2x/JDBCServer/snappy_tmp - Djava.io.tmpdir=\${BIGDATA_HOME}/tmp/spark2x/JDBCServer/io_tmp - Dcarbon.properties.filepath=\${SPARK_CONF_DIR}/carbon.properties - Djdk.tls.ephemeralDHKeySize=20	The default value <code>\${SPARK_CONF_DIR}</code> depends on a specific cluster and is added to the end of the value of the <b>spark.driver.extraJavaOptions</b> parameter. This parameter is used to specify the path of the <b>carbon.properties</b> file in Driver.  <b>NOTE</b> Spaces next to equal marks (=) are not allowed.

Parameter	Value	Description
	48 - Dspark.ssl.keyStore=\${SPARK_CONF_DIR}/child.keystore#{java_stack_prefer}	
spark.sql.session.state.builder	org.apache.spark.sql.hive.FIHiveACLSessionStateBuilder	Session state constructor.
spark.carbon.sqlastbuilder.classname	org.apache.spark.sql.hive.CarbonInternalSqlAstBuilder	AST constructor.
spark.sql.catalog.class	org.apache.spark.sql.hive.HiveACLExternalCatalog	Hive External catalog to be used. This parameter is mandatory if Spark ACL is enabled.
spark.sql.hive.implementation	org.apache.spark.sql.hive.HiveACLClientImpl	How to call the Hive client. This parameter is mandatory if Spark ACL is enabled.
spark.sql.hiveClient.isolation.enabled	false	This parameter is mandatory if Spark ACL is enabled.

## 1.3 CarbonData Operation Guide

### 1.3.1 CarbonData Quick Start

This section describes how to create CarbonData tables, load data, and query data. This quick start provides operations based on the Spark Beeline client. If you want to use Spark shell, wrap the queries with **spark.sql()**.

**Table 1-9** CarbonData Quick Start

Operation	Description
<a href="#">Connecting to CarbonData</a>	Connect to CarbonData before performing any operations on CarbonData.
<a href="#">Creating a CarbonData Table</a>	Create a CarbonData table to load data and perform query operations.

Operation	Description
<a href="#">Loading Data to a CarbonData Table</a>	Load data from CSV to the created table.
<a href="#">Querying Data from a CarbonData Table</a>	Perform query operations such as filters and groupby.

## Connecting to CarbonData

- Use Spark SQL or Spark shell to connect to Spark and run Spark SQL commands.
- Start the JDBCServer and use a JDBC client (for example, Spark Beeline) to connect to the JDBCServer.

### NOTE

A user must belong to the data loading group for performing data loading operations. The default name of the data loading group is **ficommon**.

## Creating a CarbonData Table

After connecting Spark Beeline with the JDBCServer, create a CarbonData table to load data and perform query operations. Run the following commands to create a simple table:

```
create table x1 (imei string, deviceInformationId int, mac string, productdate timestamp, updatetime timestamp, gamePointId double, contractNumber double) STORED AS carbondata TBLPROPERTIES ('SORT_COLUMNS'=imei,mac);
```

The command output is as follows:

```
+-----+--+
| result |
+-----+--+
+-----+--+
No rows selected (1.551 seconds)
```

## Loading Data to a CarbonData Table

After you have created a CarbonData table, you can load the data from CSV to the created table.

### Loading data from a CSV file to a CarbonData table

Run the following command with required parameters to load data from CSV. The column names of the CarbonData table must match the column names of the CSV file.

```
LOAD DATA inpath 'hdfs://hacluster/data/x1_without_header.csv' into table x1 options('DELIMITER=', 'QUOTECHAR='','FILEHEADER'=imei, deviceinformationid,mac, productdate,updatetime, gamepointid,contractnumber');
```

In the preceding command, **x1\_without\_header.csv** and **x1** are used as examples.

The CSV example file is as follows:

```
13418592122,1001, MAC address, 2017-10-23 15:32:30,2017-10-24 15:32:30,62.50,74.56
13418592123 1002, MAC address, 2017-10-23 16:32:30,2017-10-24 16:32:30,17.80,76.28
13418592124,1003, MAC address, 2017-10-23 17:32:30,2017-10-24 17:32:30,20.40,92.94
13418592125 1004, MAC address, 2017-10-23 18:32:30,2017-10-24 18:32:30,73.84,8.58
13418592126,1005, MAC address, 2017-10-23 19:32:30,2017-10-24 19:32:30,80.50,88.02
13418592127 1006, MAC address, 2017-10-23 20:32:30,2017-10-24 20:32:30,65.77,71.24
13418592128,1007, MAC address, 2017-10-23 21:32:30,2017-10-24 21:32:30,75.21,76.04
13418592129,1008, MAC address, 2017-10-23 22:32:30,2017-10-24 22:32:30,63.30,94.40
13418592130, 1009, MAC address, 2017-10-23 23:32:30,2017-10-24 23:32:30,95.51,50.17
13418592131,1010, MAC address, 2017-10-24 00:32:30,2017-10-25 00:32:30,39.62,99.13
```

The command output is as follows:

```
+-----+
| Result |
+-----+
+-----+
No rows selected (3.039 seconds)
```

## Querying Data from a CarbonData Table

After a CarbonData table is created and the data is loaded, you can perform query operations as required. Some query operations are provided as examples.

- **Obtaining the number of records**

Run the following command to obtain the number of records in the CarbonData table:

```
select count(*) from x1;
```

- **Querying with the groupby condition**

Run the following command to obtain the **deviceinformationid** records without repetition in the CarbonData table:

```
select deviceinformationid,count (distinct deviceinformationid) from x1
group by deviceinformationid;
```

- **Querying with Filter**

Run the following command to obtain specific **deviceinformationid** records:

```
select * from x1 where deviceinformationid='1010';
```

## Using CarbonData on Spark-shell

If you need to use CarbonData on a Spark-shell, you need to create a CarbonData table, load data to the CarbonData table, and query data in CarbonData as follows:

```
spark.sql("CREATE TABLE x2(imei string, deviceInformationId int, mac string, productdate timestamp,
updateTime timestamp, gamePointId double, contractNumber double) STORED AS carbondata")
spark.sql("LOAD DATA inpath 'hdfs://hacluster/data/x1_without_header.csv' into table x2
options('DELIMITER',';', 'QUOTECHAR'='\",'FILEHEADER'='imei, deviceinformationid,mac,
productdate,updateTime, gamepointid,contractnumber')")
spark.sql("SELECT * FROM x2").show()
```

## 1.3.2 CarbonData Table Management

### 1.3.2.1 About CarbonData Table

#### Overview

In CarbonData, data is stored in entities called tables. CarbonData tables are similar to RDBMS tables. RDBMS data is stored in a table consisting of rows and columns. CarbonData tables store structured data, and have fixed columns and data types.

#### Supported Data Types

CarbonData tables support the following data types:

- Int
- String
- BigInt
- Smallint
- Char
- Varchar
- Boolean
- Decimal
- Double
- TimeStamp
- Date
- Array
- Struct
- Map

The following table describes supported data types and their respective values range.

**Table 1-10** CarbonData data types

Data Type	Value Range
Int	4-byte signed integer ranging from -2,147,483,648 to 2,147,483,647. <b>NOTE</b> If a non-dictionary column is of the <b>int</b> data type, it is internally stored as the <b>BigInt</b> type.
String	100,000 characters <b>NOTE</b> If the <b>CHAR</b> or <b>VARCHAR</b> data type is used in <b>CREATE TABLE</b> , the two data types are automatically converted to the String data type. If a column contains more than 32,000 characters, add the column to the <b>LONG_STRING_COLUMNS</b> attribute of the <b>tblproperties</b> table during table creation.

Data Type	Value Range
BigInt	64-bit value ranging from -9,223,372,036,854,775,808 to 9,223,372,036,854,775,807
SmallInt	-32,768 to 32,767
Char	A to Z and a to z
Varchar	A to Z, a to z, and 0 to 9
Boolean	<b>true</b> or <b>false</b>
Decimal	The default value is (10,0) and maximum value is (38,38). <b>NOTE</b> When query with filters, append <b>BD</b> to the number to achieve accurate results. For example, <b>select * from carbon_table where num = 1234567890123456.22BD.</b>
Double	64-bit value ranging from 4.9E-324 to 1.7976931348623157E308
TimeStamp	The default format is <b>yyyy-MM-dd HH:mm:ss.</b>
Date	The <b>DATE</b> data type is used to store calendar dates. The default format is <b>yyyy-MM-DD.</b>
Array<data_type>	N/A
Struct<col_name: data_type COMMENT col_comment, ...>	<b>NOTE</b> Currently, only two layers of complex types can be nested.
Map<primitive_type, data_type>	

### 1.3.2.2 Creating a CarbonData Table

#### Scenario

A CarbonData table must be created to load and query data. You can run the **Create Table** command to create a table. This command is used to create a table using custom columns.

#### Creating a Table with Self-Defined Columns

Users can create a table by specifying its columns and data types.

Sample command:

```
CREATE TABLE IF NOT EXISTS productdb.productSalesTable (  
  productNumber Int,  
  productName String,
```

```

storeCity String,
storeProvince String,
productCategory String,
productBatch String,
saleQuantity Int,
revenue Int)
STORED AS carbodata
TBLPROPERTIES (


```

The following table describes parameters of preceding commands.

**Table 1-11** Parameter description

Parameter	Description
productSalesTable	Table name. The table is used to load data for analysis. The table name consists of letters, digits, and underscores (_).
productdb	Database name. The database maintains logical connections with tables stored in it to identify and manage the tables. The database name consists of letters, digits, and underscores (_).
productName storeCity storeProvince productCategory productBatch saleQuantity revenue	Columns in the table. The columns are service entities for data analysis. The column name (field name) consists of letters, digits, and underscores (_).

Parameter	Description
table_blocksize	<p>Indicates the block size of data files used by the CarbonData table, in MB. The value ranges from <b>1</b> to <b>2048</b>. The default value is <b>1024</b>.</p> <p>If <b>table_blocksize</b> is too small, a large number of small files will be generated when data is loaded. This may affect the performance of HDFS.</p> <p>If <b>table_blocksize</b> is too large, during data query, the amount of block data that matches the index is large, and some blocks contain a large number of blocklets, affecting read concurrency and lowering query performance.</p> <p>You are advised to set the block size based on the data volume. For example, set the block size to 256 MB for GB-level data, 512 MB for TB-level data, and 1024 MB for PB-level data.</p>

 **NOTE**

- Measurement of all integer data is processed and displayed using the **BigInt** data type.
- CarbonData parses data strictly. Any data that cannot be parsed is saved as **null** in the table. For example, if the user loads the **double** value (3.14) to the **BigInt** column, the data is saved as **null**.
- The Short and Long data types used in the **Create Table** command are shown as **smallint** and **bigint** in the **DESCRIBE** command, respectively.
- You can run the **DESCRIBE** command to view the table data size and table index size.

## Operation Result

Run the command to create a table.

### 1.3.2.3 Deleting a CarbonData Table

#### Scenario

You can run the **DROP TABLE** command to delete a table. After a CarbonData table is deleted, its metadata and loaded data are deleted together.

#### Procedure

Run the following command to delete a CarbonData table:

Run the following command:

```
DROP TABLE [IF EXISTS] [db_name.]table_name;
```

Once this command is executed, the table is deleted from the system. In the command, **db\_name** is an optional parameter. If **db\_name** is not specified, the table named **table\_name** in the current database is deleted.

Example:

```
DROP TABLE productdb.productSalesTable;
```

Run the preceding command to delete the **productSalesTable** table from the **productdb** database.

## Operation Result

Deletes the table specified in the command from the system. After the table is deleted, you can run the **SHOW TABLES** command to check whether the table is successfully deleted. For details, see [SHOW TABLES](#).

### 1.3.2.4 Modify the CarbonData Table

#### SET and UNSET

When the **SET** command is executed, the new properties overwrite the existing ones.

- SORT SCOPE

The following is an example of the **SET SORT SCOPE** command:

```
ALTER TABLE tablename SET TBLPROPERTIES('SORT_SCOPE'='no_sort')
```

After running the **UNSET SORT SCOPE** command, the default value **NO\_SORT** is adopted.

The following is an example of the **UNSET SORT SCOPE** command:

```
ALTER TABLE tablename UNSET TBLPROPERTIES('SORT_SCOPE')
```

- SORT COLUMNS

The following is an example of the **SET SORT COLUMNS** command:

```
ALTER TABLE tablename SET TBLPROPERTIES('SORT_COLUMNS'='column1')
```

After this command is executed, the new value of **SORT\_COLUMNS** is used. Users can adjust the **SORT\_COLUMNS** based on the query results, but the original data is not affected. The operation does not affect the query performance of the original data segments which are not sorted by new **SORT\_COLUMNS**.

The **UNSET** command is not supported, but the **SORT\_COLUMNS** can be set to empty string instead of using the **UNSET** command.

```
ALTER TABLE tablename SET TBLPROPERTIES('SORT_COLUMNS'='')
```

#### NOTE

- The later version will enhance custom compaction to resort the old segments.
- The value of **SORT\_COLUMNS** cannot be modified in the streaming table.
- If the **inverted index** column is removed from **SORT\_COLUMNS**, **inverted index** will not be created in this column. However, the old configuration of **INVERTED\_INDEX** will be kept.

## 1.3.3 CarbonData Table Data Management

### 1.3.3.1 Loading Data

#### Scenario

After a CarbonData table is created, you can run the **LOAD DATA** command to load data to the table for query. Once data loading is triggered, data is encoded in CarbonData format and files in multi-dimensional and column-based format are compressed and copied to the HDFS path of CarbonData files for quick analysis and queries. The HDFS path can be configured in the **carbon.properties** file. For details, see [Configuration Reference](#).

### 1.3.3.2 Deleting Segments

#### Scenario

If you want to modify and reload the data because you have loaded wrong data into a table, or there are too many bad records, you can delete specific segments by segment ID or data loading time.

 **NOTE**

The segment deletion operation only deletes segments that are not compacted. You can run the **CLEAN FILES** command to clear compacted segments.

#### Deleting a Segment by Segment ID

Each segment has a unique ID. This segment ID can be used to delete the segment.

**Step 1** Obtain the segment ID.

Command:

**SHOW SEGMENTS FOR Table** *dbname.tablename LIMIT number\_of\_loads;*

Example:

**SHOW SEGMENTS FOR TABLE** *carbonTable;*

Run the preceding command to show all the segments of the table named **carbonTable**.

**SHOW SEGMENTS FOR TABLE** *carbonTable LIMIT 2;*

Run the preceding command to show segments specified by *number\_of\_loads*.

The command output is as follows:

ID	Status	Load Start Time	Load Time Taken	Partition	Data Size	Index Size	File Format
3	Success	2020-09-28 22:53:26.336	3.726S	{}	6.47KB	3.30KB	columnar_v3
2	Success	2020-09-28 22:53:01.702	6.688S	{}	6.47KB	3.30KB	columnar_v3

 NOTE

The output of the **SHOW SEGMENTS** command includes ID, Status, Load Start Time, Load Time Taken, Partition, Data Size, Index Size, and File Format. The latest loading information is displayed in the first line of the command output.

**Step 2** Run the following command to delete the segment after you have found the Segment ID:

Command:

```
DELETE FROM TABLE tableName WHERE SEGMENT.ID IN (load_sequence_id1,  
load_sequence_id2, ....);
```

Example:

```
DELETE FROM TABLE carbonTable WHERE SEGMENT.ID IN (1,2,3);
```

For details, see [DELETE SEGMENT by ID](#).

----End

## Deleting a Segment by Data Loading Time

You can delete a segment based on the loading time.

Command:

```
DELETE FROM TABLE db_name.table_name WHERE SEGMENT.STARTTIME  
BEFORE date_value;
```

Example:

```
DELETE FROM TABLE carbonTable WHERE SEGMENT.STARTTIME BEFORE  
'2017-07-01 12:07:20';
```

The preceding command can be used to delete all segments before 2017-07-01 12:07:20.

For details, see [DELETE SEGMENT by DATE](#).

## Result

Data of corresponding segments is deleted and is unavailable for query. You can run the **SHOW SEGMENTS** command to display the segment status and check whether the segment has been deleted.

 NOTE

- Segments are not physically deleted after the execution of the **DELETE SEGMENT** command. Therefore, if you run the **SHOW SEGMENTS** command to check the status of a deleted segment, it will be marked as **Marked for Delete**. If you run the **SELECT \* FROM tablename** command, the deleted segment will be excluded.
- The deleted segment will be deleted physically only when the next data loading reaches the maximum query execution duration, which is configured by the **max.query.execution.time** parameter. The default value of the parameter is 60 minutes.
- If you want to forcibly delete a physical segment file, run the **CLEAN FILES** command.

Example:

**CLEAN FILES FOR TABLE table1;**

This command will physically delete the segment file in the **Marked for delete** state.

If this command is executed before the time specified by **max.query.execution.time** arrives, the query may fail. **max.query.execution.time** indicates the maximum time allowed for a query, which is set in the **carbon.properties** file.

### 1.3.3.3 Combining Segments

#### Scenario

Frequent data access results in a large number of fragmented CarbonData files in the storage directory. In each data loading, data is sorted and indexing is performed. This means that an index is generated for each load. With the increase of data loading times, the number of indexes also increases. As each index works only on one loading, the performance of index is reduced. CarbonData provides loading and compression functions. In a compression process, data in each segment is combined and sorted, and multiple segments are combined into one large segment.

#### Prerequisites

Multiple data loadings have been performed.

#### Operation Description

There are three types of compaction: Minor, Major, and Custom.

- **Minor compaction:**  
In minor compaction, you can specify the number of loads to be merged. If **carbon.enable.auto.load.merge** is set, minor compaction is triggered for every data load. If any segments are available to be merged, then compaction will run parallel with data load.  
There are two levels in minor compaction:
  - Level 1: Merging of the segments which are not yet compacted
  - Level 2: Merging of the compacted segments again to form a larger segment
- **Major compaction:**  
Multiple segments can be merged into one large segment. You can specify the compaction size so that all segments below the size will be merged. Major compaction is usually done during the off-peak time.

- Custom compaction:  
In Custom compaction, you can specify the IDs of multiple segments to merge them into a large segment. The IDs of all the specified segments must exist and be valid. Otherwise, the compaction fails. Custom compaction is usually done during the off-peak time.

For details, see [ALTER TABLE COMPACTION](#).

**Table 1-12** Compaction parameters

Parameter	Default Value	Application Type	Description
carbon.enable.automerge	false	Minor	Whether to enable compaction along with data loading. <b>true:</b> Compaction is automatically triggered when data is loaded. <b>false:</b> Compaction is not triggered when data is loaded.
carbon.compaction.level.threshold	4,3	Minor	This configuration is for minor compaction which decides how many segments to be merged. For example, if this parameter is set to <b>2,3</b> , minor compaction is triggered every two segments and segments form a single level 1 compacted segment. When the number of compacted level 1 segments reach 3, compaction is triggered again to merge them to form a single level 2 segment. The compaction policy depends on the actual data size and available resources. The value ranges from 0 to 100.
carbon.major.compaction.size	1024 MB	Major	The major compaction size can be configured using this parameter. Sum of the segments which is below this threshold will be merged. For example, if this parameter is set to 1024 MB, and there are five segments whose sizes are 300 MB, 400 MB, 500 MB, 200 MB, and 100 MB used for major compaction, only segments whose total size is less than this threshold are compacted. In this example, only the segments whose sizes are 300 MB, 400 MB, 200 MB, and 100 MB are compacted.

Parameter	Default Value	Application Type	Description
carbon.numberof.preserve.segments	0	Minor/ Major	<p>If you want to preserve some number of segments from being compacted, then you can set this configuration.</p> <p>For example, if <b>carbon.numberof.preserve.segments</b> is set to <b>2</b>, the latest two segments will always be excluded from the compaction.</p> <p>By default, no segments are reserved.</p>
carbon.allowed.compaction.days	0	Minor/ Major	<p>This configuration is used to control on the number of recent segments that needs to be compacted.</p> <p>For example, if this parameter is set to <b>2</b>, the segments which are loaded in the time frame of past 2 days only will get merged. Segments which are loaded earlier than 2 days will not be merged.</p> <p>This configuration is disabled by default.</p>
carbon.number.of.cores.while.compacting	2	Minor/ Major	<p>Number of cores to be used while compacting data. The greater the number of cores, the better the compaction performance. If the CPU resources are sufficient, you can increase the value of this parameter.</p>
carbon.merge.index.in.segment	true	SEGMENT_INDEX	<p>If this parameter is set to <b>true</b>, all the Carbon index (.carbonindex) files in a segment will be merged into a single Index (.carbonindexmerge) file. This enhances the first query performance.</p>

## Reference

You are advised not to perform minor compaction on historical data. For details, see [How to Avoid Minor Compaction for Historical Data?](#).

## 1.3.4 CarbonData Data Migration

### Scenario

If you want to rapidly migrate CarbonData data from a cluster to another one, you can use the CarbonData backup and restoration commands. This method does not require data import in the target cluster, reducing required migration time.

### Prerequisites

The Spark2x client has been installed in a directory, for example, **/opt/client**, in two clusters. The source cluster is cluster A, and the target cluster is cluster B.

### Procedure

- Step 1** Log in to the node where the client is installed in cluster A as a client installation user.
- Step 2** Run the following commands to configure environment variables:  

```
source /opt/ficlient/bigdata_env  
source /opt/ficlient/Spark2x/component_env
```
- Step 3** If the cluster is in security mode, run the following command to authenticate the user. In normal mode, skip user authentication.  

```
kinit carbondatauser
```

*carbondatauser* indicates the user of the original data. That is, the user has the read and write permissions for the tables.
- Step 4** Run the following command to connect to the database and check the location for storing table data on HDFS:  

```
spark-beeline  
desc formatted Name of the table containing the original data;
```

**Location** in the displayed information indicates the directory where the data file resides.
- Step 5** Log in to the node where the client is installed in cluster B as a client installation user and configure the environment variables:  

```
source /opt/ficlient/bigdata_env  
source /opt/ficlient/Spark2x/component_env
```
- Step 6** If the cluster is in security mode, run the following command to authenticate the user. In normal mode, skip user authentication.  

```
kinit carbondatauser2
```

*carbondatauser2* indicates the user that uploads data.
- Step 7** Run the **spark-beeline** command to connect to the database.
- Step 8** Does the database that maps to the original data exist?

- If yes, go to [Step 9](#).
- If no, create a database with the same name and go to [Step 9](#).

**Step 9** Copy the original data from the HDFS directory in cluster A to the HDFS directory in cluster B.

When uploading data in cluster B, ensure that the upload directory has the directories with the same names as the database and table in the original directory and the upload user has the permission to write data to the upload directory. After the data is uploaded, the user has the permission to read and write the data.

For example, if the original data is stored in `/user/carboncadauser/warehouse/db1/tb1`, the data can be stored in `/user/carbondatauser2/warehouse/db1/tb1` in the new cluster.

**Step 10** In the client environment of cluster B, run the following command to generate the metadata associated with the table corresponding to the original data in Hive:

```
REFRESH TABLE $dbName.$tbName;
```

*\$dbName* indicates the database name, and *\$tbName* indicates the table name.

**Step 11** If the original table contains an index table, perform [Step 9](#) and [Step 10](#) to migrate the index table directory from cluster A to cluster B.

**Step 12** Run the following command to register an index table for the CarbonData table (skip this step if no index table is created for the original table):

```
REGISTER INDEX TABLE $tableName ON $maintable;
```

*\$tableName* indicates the index table name, and *\$maintable* indicates the table name.

----End

## 1.3.5 Migrating Data on CarbonData from Spark1.5 to Spark2x

### Migration Solution Overview

This migration guides you to migrate the CarbonData table data of Spark 1.5 to that of Spark2x.

#### NOTE

Before performing this operation, you need to stop the data import service of the CarbonData table in Spark 1.5 and migrate data to the CarbonData table of Spark2x at a time. After the migration is complete, use Spark2x to perform service operations.

Migration roadmap:

1. Use Spark 1.5 to migrate historical data to the intermediate table.
2. Use Spark2x to migrate data from the intermediate table to the target table and change the target table name to the original table name.
3. After the migration is complete, use Spark2x to operate data in the CarbonData table.

## Migration Solution and Commands

### Migrating Historical Data

- Step 1** Stop the CarbonData data import service, use spark-beeline of Spark 1.5 to view the ID and time of the latest segment in the CarbonData table, and record the segment ID.

**show segments for table dbname.tablename;**

- Step 2** Run spark-beeline of Spark 1.5 as the user who has created the original CarbonData table to create an intermediate table in ORC or Parquet format. Then import the data in the original CarbonData table to the intermediate table. After the import is complete, the services of the CarbonData table can be restored.

Create an ORC table.

**CREATE TABLE dbname.mid\_tablename\_orc STORED AS ORC as select \* from dbname.tablename;**

Create a Parquet table.

**CREATE TABLE dbname.mid\_tablename\_parq STORED AS PARQUET as select \* from dbname.tablename;**

In the preceding command, **dbname** indicates the database name and **tablename** indicates the name of the original CarbonData table.

- Step 3** Run spark-beeline of Spark2x as the user who has created the original CarbonData table. Run the table creation statement of the old table to create a CarbonData table.

#### NOTE

In the statement for creating a new table, the field sequence and type must be the same as those of the old table. In this way, the index column structure of the old table can be retained, which helps avoid errors caused by the use of **select \*** statement during data insertion.

Run the spark-beeline command of Spark 1.5 to view the table creation statement of the old table: **SHOW CREATE TABLE dbname.tablename;**

Create a CarbonData table named **dbname.new\_tablename**.

- Step 4** Run spark-beeline of Spark2x as the user who has created the original CarbonData table to load the intermediate table data in ORC (or PARQUET) format created in [Step 2](#) to the new table created in [Step 3](#). This step may take a long time (about 2 hours for 200 GB data). The following uses the ORC intermediate table as an example to describe the command for loading data:

**insert into dbname.new\_tablename select \***

**from dbname. mid\_tablename\_orc;**

- Step 5** Run spark-beeline of Spark2x as the user who has created the original CarbonData table to query and verify the data in the new table. If the data is correct, change the name of the original CarbonData table and then change the name of the new CarbonData table to the name of the original one.

**ALTER TABLE dbname.tablename RENAME TO dbname.old\_tablename;**

```
ALTER TABLE dbname.new_tablename RENAME TO dbname.tablename;
```

**Step 6** Complete the migration. In this case, you can use Spark2x to query the new table and rebuild the secondary index.

----End

## 1.4 CarbonData Performance Tuning

### 1.4.1 Tuning Guidelines

#### Query Performance Tuning

There are various parameters that can be tuned to improve the query performance in CarbonData. Most of the parameters focus on increasing the parallelism in processing and optimizing system resource usage.

- Spark executor count: Executors are basic entities of parallelism in Spark. Raising the number of executors can increase the amount of parallelism in the cluster. For details about how to configure the number of executors, see the Spark documentation.
- Executor core: The number of concurrent tasks that an executor can run are controlled in each executor. Increasing the number of executor cores will add more concurrent processing tasks to improve performance.
- HDFS block size: CarbonData assigns query tasks by allocating different blocks to different executors for processing. HDFS block is the partition unit. CarbonData maintains a global block level index in Spark driver, which helps to reduce the quantity of blocks that need to be scanned for a query. Higher block size means higher I/O efficiency and lower global index efficiency. Reversely, lower block size means lower I/O efficiency, higher global index efficiency, and greater memory consumption.
- Number of scanner threads: Scanner threads control the number of parallel data blocks that are processed by each task. By increasing the number of scanner threads, you can increase the number of data blocks that are processed in parallel to improve performance. The **carbon.number.of.cores** parameter in the **carbon.properties** file is used to configure the number of scanner threads. For example, **carbon.number.of.cores = 4**.
- B-Tree caching: The cache memory can be optimized using the B-Tree least recently used (LRU) caching. In the driver, the B-Tree LRU caching configuration helps free up the cache by releasing table segments which are not accessed or not used. Similarly, in the executor, the B-Tree LRU caching configuration will help release table blocks that are not accessed or used. For details, see the description of **carbon.max.driver.lru.cache.size** and **carbon.max.executor.lru.cache.size** in [Table 1-4](#).

#### CarbonData Query Process

When CarbonData receives a table query task, for example query for table A, the index data of table A will be loaded to the memory for the query process. When CarbonData receives a query task for table A again, the system does not need to load the index data of table A.

When a query is performed in CarbonData, the query task is divided into several scan tasks, namely, task splitting based on HDFS blocks. Scan tasks are executed by executors on the cluster. Tasks can run in parallel, partially parallel, or in sequence, depending on the number of executors and configured number of executor cores.

Some parts of a query task can be processed at the individual task level, such as **select** and **filter**. Some parts of a query task can be processed at the individual task level, such as **group-by**, **count**, and **distinct count**.

Some operations cannot be performed at the task level, such as **Having Clause** (filter after grouping) and **sort**. Operations which cannot be performed at the task level or can be only performed partially at the task level require data (partial results) transmission across executors on the cluster. The transmission operation is called shuffle.

The more the tasks are, the more data needs to be shuffled. This affects query performance.

The number of tasks is depending on the number of HDFS blocks and the number of blocks is depending on the size of each block. You are advised to configure proper HDFS block size to achieve a balance among increased parallelism, the amount of data to be shuffled, and the size of aggregate tables.

## Relationship Between Splits and Executors

If the number of splits is less than or equal to the executor count multiplied by the executor core count, the tasks are run in parallel. Otherwise, some tasks can start only after other tasks are complete. Therefore, ensure that the executor count multiplied by executor cores is greater than or equal to the number of splits. In addition, make sure that there are sufficient splits so that a query task can be divided into sufficient subtasks to ensure concurrency.

## Configuring Scanner Threads

The scanner threads property decides the number of data blocks to be processed. If there are too many data blocks, a large number of small data blocks will be generated, affecting performance. If there are few data blocks, the parallelism is poor and the performance is affected. Therefore, when determining the number of scanner threads, you are advised to consider the average data size within a partition and select a value that makes the data block not small. Based on experience, you are advised to divide a single block size (unit: MB) by 250 and use the result as the number of scanner threads.

The number of actual available vCPUs is an important factor to consider when you want to increase the parallelism. The number of vCPUs that conduct parallel computation must not exceed 75% to 80% of actual vCPUs.

The number of vCPUs is approximately equal to:

Number of parallel tasks x Number of scanner threads. Number of parallel tasks is the smaller value of number of splits or executor count x executor cores.

## Data Loading Performance Tuning

Tuning of data loading performance is different from that of query performance. Similar to query performance, data loading performance depends on the amount

of parallelism that can be achieved. In case of data loading, the number of worker threads decides the unit of parallelism. Therefore, more executors mean more executor cores and better data loading performance.

To achieve better performance, you can configure the following parameters in HDFS.

**Table 1-13** HDFS configuration

Parameter	Recommended Value
dfs.datanode.drop.cache.behind.reads	false
dfs.datanode.drop.cache.behind.writes	false
dfs.datanode.sync.behind.writes	true

## Compression Tuning

CarbonData uses a few lightweight compression and heavyweight compression algorithms to compress data. Although these algorithms can process any type of data, the compression performance is better if the data is ordered with similar values being together.

During data loading, data is sorted based on the order of columns in the table to achieve good compression performance.

Since CarbonData sorts data in the order of columns defined in the table, the order of columns plays an important role in the effectiveness of compression. If the low cardinality dimension is on the left, the range of data partitions after sorting is small and the compression efficiency is high. If a high cardinality dimension is on the left, a range of data partitions obtained after sorting is relatively large, and compression efficiency is relatively low.

## Memory Tuning

CarbonData provides a mechanism for memory tuning where data loading depends on the columns needed in the query. Whenever a query command is received, columns required by the query are fetched and data is loaded for those columns in memory. During this operation, if the memory threshold is reached, the least used loaded files are deleted to release memory space for columns required by the query.

### 1.4.2 Suggestions for Creating CarbonData Tables

#### Scenario

This section provides suggestions based on more than 50 test cases to help you create CarbonData tables with higher query performance.

**Table 1-14** Columns in the CarbonData table

Column name	Data type	Cardinality	Attribution
msname	String	30 million	dimension
BEGIN_TIME	bigint	10,000	dimension
host	String	1 million	dimension
dime_1	String	1,000	dimension
dime_2	String	500	dimension
dime_3	String	800	dimension
counter_1	numeric(20,0)	NA	measure
...	...	NA	measure
counter_100	numeric(20,0)	NA	measure

## Procedure

- If the to-be-created table contains a column that is frequently used for filtering, for example, this column is used in more than 80% of filtering scenarios,

implement optimization as follows:

Place this column in the first column of **sort\_columns**.

For example, if **msname** is the most frequently used filter criterion in a query, it is placed in the first column. Run the following command to create a table. The query performance is good if **msname** is used as the filter condition.

```
create table carbondata_table(
  msname String,
  ...
)STORED AS carbondata TBLPROPERTIES ('SORT_COLUMNS'='msname');
```

- If the to-be-created table has multiple columns which are frequently used to filter the results,

implement optimization as follows:

Create an index for the columns.

For example, if **msname**, **host**, and **dime\_1** are frequently used columns, the **sort\_columns** column sequence is "dime\_1-> host-> msname..." based on cardinality. Run the following command to create a table. The following command can improve the filtering performance of **dime\_1**, **host**, and **msname**.

```
create table carbondata_table(
  dime_1 String,
  host String,
  msname String,
  dime_2 String,
  dime_3 String,
  ...
)STORED AS carbondata
TBLPROPERTIES ('SORT_COLUMNS'='dime_1,host,msname');
```

- If the frequency of each column used for filtering is similar, implement optimization as follows:

**sort\_columns** is sorted in ascending order of cardinality.

Run the following command to create a table:

```
create table carbondata_table(  
  Dime_1 String,  
  BEGIN_TIME bigint,  
  HOST String,  
  msname String,  
  ...  
)STORED AS carbondata  
TBLPROPERTIES ('SORT_COLUMNS'='dime_2,dime_3,dime_1, BEGIN_TIME,host,msname');
```

- Create tables in ascending order of cardinalities. Then create secondary indexes for columns with more cardinalities. The statement for creating an index is as follows:

```
create index carbondata_table_index_msidsn on tablecarbondata_table (  
msname String) as 'carbondata' PROPERTIES ('table_blocksize'='128');  
create index carbondata_table_index_host on tablecarbondata_table (  
host String) as 'carbondata' PROPERTIES ('table_blocksize'='128');
```

- For columns of measure type, not requiring high accuracy, the numeric (20,0) data type is not required. You are advised to use the double data type to replace the numeric (20,0) data type to enhance query performance.

The result of performance analysis of test-case shows reduction in query execution time from 15 to 3 seconds, thereby improving performance by nearly 5 times. The command for creating a table is as follows:

```
create table carbondata_table(  
  Dime_1 String,  
  BEGIN_TIME bigint,  
  HOST String,  
  msname String,  
  counter_1 double,  
  counter_2 double,  
  ...  
  counter_100 double,  
)STORED AS carbondata  
;
```

- If values (**start\_time** for example) of a column are incremental:  
For example, if data is loaded to CarbonData every day, **start\_time** is incremental for each load. In this case, it is recommended that the **start\_time** column be put at the end of **sort\_columns**, because incremental values are efficient in using min/max index. The command for creating a table is as follows:

```
create table carbondata_table(  
  Dime_1 String,  
  HOST String,  
  msname String,  
  counter_1 double,  
  counter_2 double,  
  BEGIN_TIME bigint,  
  ...  
  counter_100 double,  
)STORED AS carbondata  
TBLPROPERTIES ( 'SORT_COLUMNS'='dime_2,dime_3,dime_1..BEGIN_TIME');
```

## 1.4.3 Configurations for Performance Tuning

### Scenario

This section describes the configurations that can improve CarbonData performance.

### Procedure

[Table 1-15](#) and [Table 1-16](#) describe the configurations about query of CarbonData.

**Table 1-15** Number of tasks started for the shuffle process

<b>Parameter</b>	spark.sql.shuffle.partitions
<b>Configuration File</b>	spark-defaults.conf
<b>Function</b>	Data query
<b>Scenario Description</b>	Number of tasks started for the shuffle process in Spark
<b>Tuning</b>	You are advised to set this parameter to one to two times as much as the executor cores. In an aggregation scenario, reducing the number from 200 to 32 can reduce the query time by two folds.

**Table 1-16** Number of executors and vCPUs, and memory size used for CarbonData data query

<b>Parameter</b>	spark.executor.cores spark.executor.instances spark.executor.memory
<b>Configuration File</b>	spark-defaults.conf
<b>Function</b>	Data query
<b>Scenario Description</b>	Number of executors and vCPUs, and memory size used for CarbonData data query

<b>Tuning</b>	In the bank scenario, configuring 4 vCPUs and 15 GB memory for each executor will achieve good performance. The two values do not mean the more the better. Configure the two values properly in case of limited resources. If each node has 32 vCPUs and 64 GB memory in the bank scenario, the memory is not sufficient. If each executor has 4 vCPUs and 12 GB memory, Garbage Collection may occur during query, time spent on query from increases from 3s to more than 15s. In this case, you need to increase the memory or reduce the number of vCPUs.
---------------	--

[Table 1-17](#), [Table 1-18](#), and [Table 1-19](#) describe the configurations for CarbonData data loading.

**Table 1-17** Number of vCPUs used for data loading

<b>Parameter</b>	carbon.number.of.cores.while.loading
<b>Configuration File</b>	carbon.properties
<b>Function</b>	Data loading
<b>Scenario Description</b>	Number of vCPUs used for data processing during data loading in CarbonData
<b>Tuning</b>	If there are sufficient CPUs, you can increase the number of vCPUs to improve performance. For example, if the value of this parameter is changed from 2 to 4, the CSV reading performance can be doubled.

**Table 1-18** Whether to use Yarn local directories for multi-disk data loading

<b>Parameter</b>	carbon.use.local.dir
<b>Configuration File</b>	carbon.properties
<b>Function</b>	Data loading
<b>Scenario Description</b>	Whether to use Yarn local directories for multi-disk data loading
<b>Tuning</b>	If this parameter is set to <b>true</b> , CarbonData uses local Yarn directories for multi-table load disk load balance, improving data loading performance.

**Table 1-19** Whether to use multiple directories during loading

<b>Parameter</b>	carbon.use.multiple.temp.dir
<b>Configuration File</b>	carbon.properties
<b>Function</b>	Data loading
<b>Scenario Description</b>	Whether to use multiple temporary directories to store temporary sort files
<b>Tuning</b>	If this parameter is set to <b>true</b> , multiple temporary directories are used to store temporary sort files during data loading. This configuration improves data loading performance and prevents single points of failure (SPOFs) on disks.

**Table 1-20** describes the configurations for CarbonData data loading and query.

**Table 1-20** Number of vCPUs used for data loading and query

<b>Parameter</b>	carbon.compaction.level.threshold
<b>Configuration File</b>	carbon.properties
<b>Function</b>	Data loading and query
<b>Scenario Description</b>	For minor compaction, specifies the number of segments to be merged in stage 1 and number of compacted segments to be merged in stage 2.
<b>Tuning</b>	Each CarbonData load will create one segment, if every load is small in size, it will generate many small files over a period of time impacting the query performance. Configuring this parameter will merge the small segments to one big segment which will sort the data and improve the performance.  The compaction policy depends on the actual data size and available resources. For example, a bank loads data once a day and at night when no query is performed. If resources are sufficient, the compaction policy can be 6 or 5.

**Table 1-21** Whether to enable data pre-loading when the index cache server is used

<b>Parameter</b>	carbon.indexserver.enable.prepriming
<b>Configuration File</b>	carbon.properties
<b>Function</b>	Data loading

<b>Scenario Description</b>	Enabling data pre-loading during the use of the index cache server can improve the performance of the first query.
<b>Tuning</b>	You can set this parameter to <b>true</b> to enable the pre-loading function. The default value is <b>false</b> .

## 1.5 CarbonData Access Control

The following table provides details about Hive ACL permissions required for performing operations on CarbonData tables.

### Prerequisites

Parameters listed in [Table 1-7](#) or [Table 1-8](#) have been configured.

### Hive ACL permissions

**Table 1-22** Hive ACL permissions required for CarbonData table-level operations

Scenario	Required Permission
DESCRIBE TABLE	SELECT (of table)
SELECT	SELECT (of table)
EXPLAIN	SELECT (of table)
CREATE TABLE	CREATE (of database)
CREATE TABLE As SELECT	CREATE (on database), INSERT (on table), RW on data file, and SELECT (on table)
LOAD	INSERT (of table) RW on data file
DROP TABLE	OWNER (of table)
DELETE SEGMENTS	DELETE (of table)
SHOW SEGMENTS	SELECT (of table)
CLEAN FILES	DELETE (of table)
INSERT OVERWRITE / INSERT INTO	INSERT (of table) RW on data file and SELECT (of table)
CREATE INDEX	OWNER (of table)
DROP INDEX	OWNER (of table)
SHOW INDEXES	SELECT (of table)
ALTER TABLE ADD COLUMN	OWNER (of table)
ALTER TABLE DROP COLUMN	OWNER (of table)

Scenario	Required Permission
ALTER TABLE CHANGE DATATYPE	OWNER (of table)
ALTER TABLE RENAME	OWNER (of table)
ALTER TABLE COMPACTION	INSERT (on table)
FINISH STREAMING	OWNER (of table)
ALTER TABLE SET STREAMING PROPERTIES	OWNER (of table)
ALTER TABLE SET TABLE PROPERTIES	OWNER (of table)
UPDATE CARBON TABLE	UPDATE (of table)
DELETE RECORDS	DELETE (of table)
REFRESH TABLE	OWNER (of main table)
REGISTER INDEX TABLE	OWNER (of table)
SHOW PARTITIONS	SELECT (on table)
ALTER TABLE ADD PARTITION	OWNER (of table)
ALTER TABLE DROP PARTITION	OWNER (of table)

 NOTE

- If tables in the database are created by multiple users, the **Drop database** command fails to be executed even if the user who runs the command is the owner of the database.
- In a secondary index, when the parent table is triggered, **insert** and **compaction** are triggered on the index table. If you select a query that has a filter condition that matches index table columns, you should provide selection permissions for the parent table and index table.
- The LockFiles folder and lock files created in the LockFiles folder will have full permissions, as the LockFiles folder does not contain any sensitive data.
- If you are using ACL, ensure you do not configure any path for DDL or DML which is being used by other process. You are advised to create new paths.  
Configure the path for the following configuration items:
  - 1) carbon.badRecords.location
  - 2) Db\_Path and other items during database creation
- For Carbon ACL in a non-security cluster, **hive.server2.enable.doAs** in the **hive-site.xml** file must be set to **false**. Then the query will run as the user who runs the hiveserver2 process.

## 1.6 CarbonData Syntax Reference

## 1.6.1 DDL

### 1.6.1.1 CREATE TABLE

#### Function

This command is used to create a CarbonData table by specifying the list of fields along with the table properties.

#### Syntax

```
CREATE TABLE [IF NOT EXISTS] [db_name.]table_name
[(col_name data_type, ...)]
STORED AS carbodata
[TBLPROPERTIES (property_name=property_value, ...)];
```

Additional attributes of all tables are defined in **TBLPROPERTIES**.

#### Parameter Description

**Table 1-23** CREATE TABLE parameters

Parameter	Description
db_name	Database name that contains letters, digits, and underscores (_).
col_name data_type	List with data types separated by commas (,). The column name contains letters, digits, and underscores (_). <b>NOTE</b> When creating a CarbonData table, do not use tupleId, PositionId, and PositionReference as column names because columns with these names are internally used by secondary index commands.
table_name	Table name of a database that contains letters, digits, and underscores (_).
STORED AS	The <b>carbodata</b> parameter defines and creates a CarbonData table.
TBLPROPERTIES	List of CarbonData table properties.

#### Precautions

Table attributes are used as follows:

- Block size

The block size of a data file can be defined for a single table using **TBLPROPERTIES**. The larger one between the actual size of the data file and the defined block size is selected as the actual block size of the data file in

HDFS. The unit is MB. The default value is 1024 MB. The value ranges from 1 MB to 2048 MB. If the value is beyond the range, the system reports an error.

Once the block size reaches the configured value, the write program starts a new block of CarbonData data. Data is written in multiples of the page size (32,000 records). Therefore, the boundary is not strict at the byte level. If the new page crosses the boundary of the configured block, the page is written to the new block instead of the current block.

```
TBLPROPERTIES('table_blocksize'='128')
```

 NOTE

- If a small block size is configured in the CarbonData table while the size of the data file generated by the loaded data is large, the block size displayed in HDFS is different from the configured value. This is because when data is written to a local block file for the first time, even though the size of the to-be-written data is larger than the configured value of the block size, data will still be written into the block. Therefore, the actual value of block size in HDFS is the larger value between the size of the data to be written and the configured block size.
- If **block.num** is less than the parallelism, the blocks are split into new blocks so that new blocks.num is greater than parallelism and all cores can be used. This optimization is called block distribution.
- **SORT\_SCOPE** specifies the sort scope during table creation. There are four types of sort scopes:
  - **GLOBAL\_SORT**: It improves query performance, especially for point queries. *TBLPROPERTIES('SORT\_SCOPE'='GLOBAL\_SORT')*
  - **LOCAL\_SORT**: Data is sorted locally (task-level sorting).
  - **NO\_SORT**: The default sorting mode is used. Data is loaded in unsorted manner, which greatly improves loading performance.

- **SORT\_COLUMNS**

This table property specifies the order of sort columns.

```
TBLPROPERTIES('SORT_COLUMNS'='column1, column3')
```

 NOTE

- If this attribute is not specified, no columns are sorted by default.
- If this property is specified but with empty argument, then the table will be loaded without sort. For example, *('SORT\_COLUMNS'='')*.
- **SORT\_COLUMNS** supports the string, date, timestamp, short, int, long, byte, and boolean data types.

- **RANGE\_COLUMN**

This property is used to specify a column to partition the input data by range. Only one column can be configured. During data import, you can use **global\_sort\_partitions** or **scale\_factor** to avoid generating small files.

```
TBLPROPERTIES('RANGE_COLUMN'='column1')
```

- **LONG\_STRING\_COLUMNS**

The length of a common string cannot exceed 32,000 characters. To store a string of more than 32,000 characters, set **LONG\_STRING\_COLUMNS** to the target column.

```
TBLPROPERTIES('LONG_STRING_COLUMNS'='column1, column3')
```

 **NOTE**

**LONG\_STRING\_COLUMNS** can be set only for columns of the STRING, CHAR, or VARCHAR type.

## Scenarios

### Creating a Table by Specifying Columns

The **CREATE TABLE** command is the same as that of Hive DDL. The additional configurations of CarbonData are provided as table properties.

```
CREATE TABLE [IF NOT EXISTS] [db_name.]table_name  
[(col_name data_type , ...)]  
STORED AS carbodata  
[TBLPROPERTIES (property_name=property_value, ...)];
```

## Examples

```
CREATE TABLE IF NOT EXISTS productdb.productSalesTable (  
productNumber Int,  
productName String,  
storeCity String,  
storeProvince String,  
productCategory String,  
productBatch String,  
saleQuantity Int,  
revenue Int)  
STORED AS carbodata  
TBLPROPERTIES (  
'table_blocksize'='128',  
'SORT_COLUMNS'='productBatch, productName')
```

## System Response

A table will be created and the success message will be logged in system logs.

### 1.6.1.2 CREATE TABLE As SELECT

## Function

This command is used to create a CarbonData table by specifying the list of fields along with the table properties.

## Syntax

```
CREATE TABLE [IF NOT EXISTS] [db_name.]table_name STORED AS carbodata  
[TBLPROPERTIES (key1=val1, key2=val2, ...)] AS select_statement;
```

## Parameter Description

**Table 1-24** CREATE TABLE parameters

Parameter	Description
db_name	Database name that contains letters, digits, and underscores (_).
table_name	Table name of a database that contains letters, digits, and underscores (_).
STORED AS	Used to store data in CarbonData format.
TBLPROPERTIES	List of CarbonData table properties. For details, see <a href="#">Precautions</a> .

## Precautions

N/A

## Examples

```
CREATE TABLE ctas_select_parquet STORED AS carbodata as select * from  
parquet_ctas_test;
```

## System Response

This example will create a Carbon table from any Parquet table and load all the records from the Parquet table.

### 1.6.1.3 DROP TABLE

## Function

This command is used to delete an existing table.

## Syntax

```
DROP TABLE [IF EXISTS] [db_name.]table_name;
```

## Parameter Description

**Table 1-25** DROP TABLE parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is selected.
table_name	Name of the table to be deleted

## Precautions

In this command, **IF EXISTS** and **db\_name** are optional.

## Example

```
DROP TABLE IF EXISTS productDatabase.productSalesTable;
```

## System Response

The table will be deleted.

### 1.6.1.4 SHOW TABLES

## Function

**SHOW TABLES** command is used to list all tables in the current or a specific database.

## Syntax

```
SHOW TABLES [IN db_name];
```

## Parameter Description

**Table 1-26** SHOW TABLE parameters

Parameter	Description
IN db_name	Name of the database. This parameter is required only when tables of this specific database are to be listed.

## Usage Guidelines

IN db\_Name is optional.

## Examples

```
SHOW TABLES IN ProductDatabase;
```

## System Response

All tables are listed.

### 1.6.1.5 ALTER TABLE COMPACTION

## Function

The **ALTER TABLE COMPACTION** command is used to merge a specified number of segments into a single segment. This improves the query performance of a table.

## Syntax

```
ALTER TABLE [db_name.]table_name COMPACT 'MINOR/MAJOR/  

    SEGMENT_INDEX';
```

```
ALTER TABLE [db_name.]table_name COMPACT 'CUSTOM' WHERE SEGMENT.ID IN  

    (id1, id2, ...);
```

## Parameter Description

**Table 1-27** ALTER TABLE COMPACTION parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is selected.
table_name	Table name.
MINOR	Minor compaction. For details, see <a href="#">Combining Segments</a> .
MAJOR	Major compaction. For details, see <a href="#">Combining Segments</a> .
SEGMENT_INDEX	This configuration enables you to merge all the CarbonData index files ( <b>.carbonindex</b> ) inside a segment to a single CarbonData index merge file ( <b>.carbonindexmerge</b> ). This enhances the first query performance. For more information, see <a href="#">Table 1-12</a> .
CUSTOM	Custom compaction. For details, see <a href="#">Combining Segments</a> .

## Precautions

N/A

## Examples

```
ALTER TABLE ProductDatabase COMPACT 'MINOR';
```

```
ALTER TABLE ProductDatabase COMPACT 'MAJOR';
```

```
ALTER TABLE ProductDatabase COMPACT 'SEGMENT_INDEX';
```

```
ALTER TABLE ProductDatabase COMPACT 'CUSTOM' WHERE SEGMENT.ID IN (0, 1);
```

## System Response

**ALTER TABLE COMPACTION** does not show the response of the compaction because it is run in the background.

If you want to view the response of minor and major compactions, you can check the logs or run the **SHOW SEGMENTS** command.

Example:

```

+-----+-----+-----+-----+-----+-----+-----+-----+
+--+
| ID | Status | Load Start Time | Load Time Taken | Partition | Data Size | Index Size | File
Format |
+-----+-----+-----+-----+-----+-----+-----+-----+
+--+
| 3 | Success | 2020-09-28 22:53:26.336 | 3.726S | {} | 6.47KB | 3.30KB | columnar_v3 |
| 2 | Success | 2020-09-28 22:53:01.702 | 6.688S | {} | 6.47KB | 3.30KB | columnar_v3 |
| 1 | Compacted | 2020-09-28 22:51:15.242 | 5.82S | {} | 6.50KB | 3.43KB |
columnar_v3 |
| 0.1 | Success | 2020-10-30 20:49:24.561 | 16.66S | {} | 12.87KB | 6.91KB | columnar_v3
|
| 0 | Compacted | 2020-09-28 22:51:02.6 | 6.819S | {} | 6.50KB | 3.43KB | columnar_v3
|
+-----+-----+-----+-----+-----+-----+-----+-----+
+--+

```

In the preceding information:

- **Compacted** indicates that data has been compacted.
- **0.1** indicates the compacting result of segment 0 and segment 1.

The compact operation does not incur any change to other operations.

Compacted segments, such as segment 0 and segment 1, become useless. To save space, before you perform other operations, run the **CLEAN FILES** command to delete compacted segments. For more information about the **CLEAN FILES** command, see [CLEAN FILES](#).

### 1.6.1.6 TABLE RENAME

#### Function

This command is used to rename an existing table.

#### Syntax

```
ALTER TABLE [db_name.]table_name RENAME TO new_table_name;
```

## Parameter Description

**Table 1-28** RENAME parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is selected.
table_name	Current name of the existing table
new_table_name	New name of the existing table

## Precautions

- Parallel queries (using table names to obtain paths for reading CarbonData storage files) may fail during this operation.
- The secondary index table cannot be renamed.

## Example

```
ALTER TABLE carbon RENAME TO carbondata;
```

```
ALTER TABLE test_db.carbon RENAME TO test_db.carbondata;
```

## System Response

The new table name will be displayed in the CarbonData folder. You can run **SHOW TABLES** to view the new table name.

### 1.6.1.7 ADD COLUMNS

## Function

This command is used to add a column to an existing table.

## Syntax

```
ALTER TABLE [db_name.]table_name ADD COLUMNS (col_name data_type,...)
TBLPROPERTIES ("COLUMNPROPERTIES.columnName.shared_column"='sharedFolder.sharedColumnName,...', 'DEFAULT.VALUE.COLUMN_NAME'='default_value');
```

## Parameter Description

**Table 1-29** ADD COLUMNS parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is selected.

Parameter	Description
table_name	Table name.
col_name data_type	Name of a comma-separated column with a data type. It consists of letters, digits, and underscores (_).  <b>NOTE</b> When creating a CarbonData table, do not name columns as tupleId, PositionId, and PositionReference because they will be used in UPDATE, DELETE, and secondary index commands.

## Precautions

- Only **shared\_column** and **default\_value** are read. If any other property name is specified, no error will be thrown and the property will be ignored.
- If no default value is specified, the default value of the new column is considered null.
- If filter is applied to the column, new columns will not be added during sort. New columns may affect query performance.

## Examples

- **ALTER TABLE carbon ADD COLUMNS (a1 INT, b1 STRING);**
- **ALTER TABLE carbon ADD COLUMNS (a1 INT, b1 STRING)  
TBLPROPERTIES ('COLUMNPROPERTIES.b1.shared\_column='sharedFolder.b1');**
- **ALTER TABLE carbon ADD COLUMNS (a1 INT, b1 STRING)  
TBLPROPERTIES ('DEFAULT.VALUE.a1='10');**

## System Response

The newly added column can be displayed by running the **DESCRIBE** command.

### 1.6.1.8 DROP COLUMNS

#### Function

This command is used to delete one or more columns from a table.

#### Syntax

**ALTER TABLE [db\_name.]table\_name DROP COLUMNS (col\_name, ...);**

## Parameter Description

**Table 1-30** DROP COLUMNS parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is selected.
table_name	Table name.
col_name	Name of a column in a table. Multiple columns are supported. It consists of letters, digits, and underscores (_).

## Precautions

After a column is deleted, at least one key column must exist in the schema. Otherwise, an error message is displayed, and the column fails to be deleted.

## Examples

Assume that the table contains four columns named a1, b1, c1, and d1.

- Delete a column:  
**ALTER TABLE *carbon* DROP COLUMNS (*b1*);**  
**ALTER TABLE *test\_db.carbon* DROP COLUMNS (*b1*);**
- Delete multiple columns:  
**ALTER TABLE *carbon* DROP COLUMNS (*b1,c1*);**  
**ALTER TABLE *test\_db.carbon* DROP COLUMNS (*b1,c1*);**

## System Response

If you run the **DESCRIBE** command, the deleted columns will not be displayed.

### 1.6.1.9 CHANGE DATA TYPE

## Function

This command is used to change the data type from INT to BIGINT or decimal precision from lower to higher.

## Syntax

```
ALTER TABLE [db_name.]table_name CHANGE col_name col_name  
changed_column_type;
```

## Parameter Description

**Table 1-31** CHANGE DATA TYPE parameters

Parameter	Description
db_name	Name of the database. If this parameter is left unspecified, the current database is selected.
table_name	Name of the table.
col_name	Name of columns in a table. Column names contain letters, digits, and underscores (_).
changed_column_type	The change in the data type.

## Usage Guidelines

- Change of decimal data type from lower precision to higher precision will only be supported for cases where there is no data loss.  
Example:
  - **Invalid scenario** - Change of decimal precision from (10,2) to (10,5) is not valid as in this case only scale is increased but total number of digits remain the same.
  - **Valid scenario** - Change of decimal precision from (10,2) to (12,3) is valid as the total number of digits are increased by 2 but scale is increased only by 1 which will not lead to any data loss.
- The allowed range is 38,38 (precision, scale) and is a valid upper case scenario which is not resulting in data loss.

## Examples

- Changing data type of column a1 from INT to BIGINT.  
**ALTER TABLE test\_db.carbon CHANGE a1 a1 BIGINT;**
- Changing decimal precision of column a1 from 10 to 18.  
**ALTER TABLE test\_db.carbon CHANGE a1 a1 DECIMAL(18,2);**

## System Response

By running DESCRIBE command, the changed data type for the modified column is displayed.

### 1.6.1.10 REFRESH TABLE

#### Function

This command is used to register Carbon table to Hive meta store catalogue from existing Carbon table data.

## Syntax

```
REFRESH TABLE db_name.table_name;
```

## Parameter Description

Table 1-32 REFRESH TABLE parameters

Parameter	Description
db_name	Name of the database. If this parameter is left unspecified, the current database is selected.
table_name	Name of the table.

## Usage Guidelines

- The new database name and the old database name should be same.
- Before executing this command the old table schema and data should be copied into the new database location.
- If the table is aggregate table, then all the aggregate tables should be copied to the new database location.
- For old store, the time zone of the source and destination cluster should be same.
- If old cluster used HIVE meta store to store schema, refresh will not work as schema file does not exist in file system.

## Examples

```
REFRESH TABLE dbcarbon.productSalesTable;
```

## System Response

By running this command, the Carbon table will be registered to Hive meta store catalogue from existing Carbon table data.

### 1.6.1.11 REGISTER INDEX TABLE

## Function

This command is used to register an index table with the primary table.

## Syntax

```
REGISTER INDEX TABLE indextable_name ON db_name.maintable_name;
```

## Parameter Description

**Table 1-33** REFRESH INDEX TABLE parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is selected.
indextable_name	Index table name.
maintable_name	Primary table name.

## Precautions

Before running this command, run **REFRESH TABLE** to register the primary table and secondary index table with the Hive metastore.

## Examples

```
REGISTER INDEX TABLE productNameIndexTable ON
productdb.productSalesTable;
```

## System Response

By running this command, the index table will be registered to the primary table.

### 1.6.1.12 REFRESH INDEX

## Function

This command is used to merge all segments for data files in the secondary index table.

## Syntax

- **REFRESH INDEX** *indextable\_name* ON TABLE *maintable\_name*  
This command is used to merge all segments for which data files are to be merged.
- **REFRESH INDEX** *indextable\_name* ON TABLE *maintable\_name* WHERE SEGMENT.ID IN (0,1,2..N)  
This command is used to merge a batch of specified segments.

## Parameter Description

**Table 1-34** REFRESH INDEX parameters

Parameter	Description
indextable_name	Name of an index table

Parameter	Description
maintable_name	Name of the primary table

## Precautions

To clear the data file of compacted segments, run the **CLEAN FILES** command on the secondary index table.

## Examples

```
REFRESH INDEX productNameIndexTable;
```

## System Response

After this command is executed, the number of data files in the secondary index table will be reduced.

## 1.6.2 DML

### 1.6.2.1 LOAD DATA

#### Function

This command is used to load user data of a particular type, so that CarbonData can provide good query performance.

#### NOTE

Only the raw data on HDFS can be loaded.

#### Syntax

```
LOAD DATA INPATH 'folder_path' INTO TABLE [db_name].table_name  
OPTIONS(property_name=property_value, ...);
```

#### Parameter Description

**Table 1-35** LOAD DATA parameters

Parameter	Description
folder_path	Path of the file or folder used for storing the raw CSV data.
db_name	Database name. If this parameter is not specified, the current database is used.
table_name	Name of a table in a database.

## Precautions

The following configuration items are involved during data loading:

- **DELIMITER:** Delimiters and quote characters provided in the load command. The default value is a comma (,).

*OPTIONS('DELIMITER=',', 'QUOTECHAR='')*

You can use '**DELIMITER**'='\t' to separate CSV data using tabs.

*OPTIONS('DELIMITER='\t')*

CarbonData also supports **\001** and **\017** as delimiters.

### NOTE

When the delimiter of CSV data is a single quotation mark ('), the single quotation mark must be enclosed in double quotation marks (" "). For example, 'DELIMITER='''.

- **QUOTECHAR:** Delimiters and quote characters provided in the load command. The default value is double quotation marks (").  
*OPTIONS('DELIMITER=',', 'QUOTECHAR='')*
- **COMMENTCHAR:** Comment characters provided in the load command. During data loading, if there is a comment character at the beginning of a line, the line is regarded as a comment line and data in the line will not be loaded. The default value is a pound key (#).  
*OPTIONS('COMMENTCHAR'='#')*
- **FILEHEADER:** If the source file does not contain any header, add a header to the **LOAD DATA** command.  
*OPTIONS('FILEHEADER'='column1,column2')*
- **ESCAPECHAR:** Is used to perform strict verification of the escape character on CSV files. The default value is backslash (\).  
*OPTIONS('ESCAPECHAR'='\')*

### NOTE

Enter **ESCAPECHAR** in the CSV data. **ESCAPECHAR** must be enclosed in double quotation marks (" "). For example, "a\b".

- Bad records handling:

In order for the data processing application to provide benefits, certain data integration is required. In most cases, data quality problems are caused by data sources.

Methods of handling bad records are as follows:

- Load all of the data before dealing with the errors.
- Clean or delete bad records before loading data or stop the loading when bad records are found.

There are many options for clearing source data during CarbonData data loading, as listed in [Table 1-36](#).

**Table 1-36** Bad Records Logger

Configuration Item	Default Value	Description
BAD_RECORDS_LOGGER_ENABLE	false	Whether to create logs with details about bad records
BAD_RECORDS_ACTION	FAIL	The four types of actions for bad records are as follows: <ul style="list-style-type: none"> <li>● <b>FORCE</b>: Auto-corrects the data by storing the bad records as NULL.</li> <li>● <b>REDIRECT</b>: Bad records are written to the raw CSV instead of being loaded.</li> <li>● <b>IGNORE</b>: Bad records are neither loaded nor written to the raw CSV.</li> <li>● <b>FAIL</b>: Data loading fails if any bad records are found.</li> </ul> <b>NOTE</b> In loaded data, if all records are bad records, <b>BAD_RECORDS_ACTION</b> is invalid and the load operation fails.
IS_EMPTY_DATA_BAD_RECORD	false	Whether empty data of a column to be considered as bad record or not. If this parameter is set to <b>false</b> , empty data ("",', or,) is not considered as bad records. If this parameter is set to <b>true</b> , empty data is considered as bad records.
BAD_RECORD_PATH	-	HDFS path where bad records are stored. The default value is <b>Null</b> . If bad records logging or bad records operation redirection is enabled, the path must be configured by the user.

Example:

```
LOAD DATA INPATH 'filepath.csv' INTO TABLE tablename
OPTIONS('BAD_RECORDS_LOGGER_ENABLE'='true',
'BAD_RECORD_PATH'='hdfs://hacluster/tmp/carbon',
'BAD_RECORDS_ACTION'='REDIRECT',
'IS_EMPTY_DATA_BAD_RECORD'='false');
```

 **NOTE**

If **REDIRECT** is used, CarbonData will add all bad records into a separate CSV file. However, this file must not be used for subsequent data loading because the content may not exactly match the source record. You must clean up the source record for further data ingestion. This option is used to remind you which records are bad.

- **MAXCOLUMNS:** (Optional) Specifies the maximum number of columns parsed by a CSV parser in a line.

*OPTIONS('MAXCOLUMNS'='400')*

**Table 1-37** MAXCOLUMNS

Name of the Optional Parameter	Default Value	Maximum Value
MAXCOLUMNS	2000	20000

**Table 1-38** Behavior chart of MAXCOLUMNS

MAXCOLUMNS Value	Number of Columns in the File Header	Final Value Considered
Not specified in Load options	5	2000
Not specified in Load options	6000	6000
40	7	Max (column count of file header, MAXCOLUMNS value)
22000	40	20000
60	Not specified in Load options	Max (Number of columns in the first line of the CSV file, MAXCOLUMNS value)

 **NOTE**

There must be sufficient executor memory for setting the maximum value of **MAXCOLUMNS Option**. Otherwise, data loading will fail.

- If **SORT\_SCOPE** is set to **GLOBAL\_SORT** during table creation, you can specify the number of partitions to be used when sorting data. If this parameter is not set or is set to a value less than **1**, the number of map tasks is used as the number of reduce tasks. It is recommended that each reduce task process 512 MB to 1 GB data.

*OPTIONS('GLOBAL\_SORT\_PARTITIONS'='2')*

 **NOTE**

To increase the number of partitions, you may need to increase the value of **spark.driver.maxResultSize**, as the sampling data collected in the driver increases with the number of partitions.

- **DATEFORMAT**: Specifies the date format of the table.

*OPTIONS('DATEFORMAT'='dateFormat')*

 **NOTE**

Date formats are specified by date pattern strings. The date pattern letters in Carbon are same as in JAVA.

- **TIMESTAMPFORMAT**: Specifies the timestamp of a table.
- *OPTIONS('TIMESTAMPFORMAT'='timestampFormat')*
- **SKIP\_EMPTY\_LINE**: Ignores empty rows in the CSV file during data loading.

*OPTIONS('SKIP\_EMPTY\_LINE'='TRUE/FALSE')*

- **Optional: SCALE\_FACTOR**: Used to control the number of partitions for **RANGE\_COLUMN, SCALE\_FACTOR**. The formula is as follows:

$splitSize = \max(blocklet\_size, (block\_size - blocklet\_size)) * scale\_factor$   
 $numPartitions = total\ size\ of\ input\ data / splitSize$

The default value is **3**. The value ranges from **1** to **300**.

*OPTIONS('SCALE\_FACTOR'='10')*

 **NOTE**

- If **GLOBAL\_SORT\_PARTITIONS** and **SCALE\_FACTOR** are used at the same time, only **GLOBAL\_SORT\_PARTITIONS** is valid.
- The compaction on **RANGE\_COLUMN** will use **LOCAL\_SORT** by default.

## Scenarios

To load a CSV file to a CarbonData table, run the following statement:

```
LOAD DATA INPATH 'folder path' INTO TABLE tablename  
OPTIONS(property_name=property_value, ...);
```

## Examples

```
LOAD DATA inpath 'hdfs://hacluster/src/test/resources/data.csv' INTO table  
carbontable
```

```
options('DELIMITER'=',',  
'QUOTECHAR'='\"',  
'COMMENTCHAR'='#',  
'ESCAPECHAR'='\\',  
'FILEHEADER'='empno,empname,designation,doj,  
workgroupcategory,workgroupcategoryname,  
deptno,deptname,projectcode,projectjoindate,  
projectenddate,attendance,utilization,salary',
```

```
'DATEFORMAT' = 'yyyy-MM-dd'
);
```

## System Response

Success or failure will be recorded in the driver logs.

### 1.6.2.2 UPDATE CARBON TABLE

## Function

This command is used to update the CarbonData table based on the column expression and optional filtering conditions.

## Syntax

- Syntax 1:  
**UPDATE <CARBON TABLE> SET (column\_name1, column\_name2, ... column\_name n) = (column1\_expression , column2\_expression , column3\_expression ... column n\_expression ) [ WHERE { <filter\_condition> } ];**
- Syntax 2:  
**UPDATE <CARBON TABLE> SET (column\_name1, column\_name2,) = (select sourceColumn1, sourceColumn2 from sourceTable [ WHERE { <filter\_condition> } ] ) [ WHERE { <filter\_condition> } ];**

## Parameter Description

Table 1-39 UPDATE parameters

Parameter	Description
CARBON TABLE	Name of the CarbonData table to be updated
column_name	Target column to be updated
sourceColumn	Column value of the source table that needs to be updated in the target table
sourceTable	Table from which the records are updated to the target table

## Precautions

Note the following before running this command:

- The UPDATE command fails if multiple input rows in the source table are matched with a single row in the target table.
- If the source table generates empty records, the UPDATE operation completes without updating the table.

- If rows in the source table do not match any existing rows in the target table, the UPDATE operation completes without updating the table.
- UPDATE is not allowed in the table with secondary index.
- In a subquery, if the source table and target table are the same, the UPDATE operation fails.
- The UPDATE operation fails if the subquery used in the UPDATE command contains an aggregate function or a GROUP BY clause.

For example, **update t\_carbn01 a set (a.item\_type\_code, a.profit) = ( select b.item\_type\_cd, sum(b.profit) from t\_carbn01b b where item\_type\_cd =2 group by item\_type\_code);**

In the preceding example, aggregate function **sum(b.profit)** and GROUP BY clause are used in the subquery. As a result, the UPDATE operation will fail.

- If the **carbon.input.segments** property has been set for the queried table, the UPDATE operation fails. To solve this problem, run the following statement before the query:

Syntax:

**SET carbon.input.segments. <database\_name>. <table\_name>=\***;

## Examples

- Example 1:  
**update carbonTable1 d set (d.column3,d.column5 ) = (select s.c33 ,s.c55 from sourceTable1 s where d.column1 = s.c11) where d.column1 = 'country' exists( select \* from table3 o where o.c2 > 1);**
- Example 2:  
**update carbonTable1 d set (c3) = (select s.c33 from sourceTable1 s where d.column1 = s.c11) where exists( select \* from iud.other o where o.c2 > 1);**
- Example 3:  
**update carbonTable1 set (c2, c5 ) = (c2 + 1, concat(c5 , "y" ));**
- Example 4:  
**update carbonTable1 d set (c2, c5 ) = (c2 + 1, "yx") where d.column1 = 'india';**
- Example 5:  
**update carbonTable1 d set (c2, c5 ) = (c2 + 1, "yx") where d.column1 = 'india' and exists( select \* from table3 o where o.column2 > 1);**

## System Response

Success or failure will be recorded in the driver log and on the client.

### 1.6.2.3 DELETE RECORDS from CARBON TABLE

#### Function

This command is used to delete records from a CarbonData table.

## Syntax

**DELETE FROM CARBON\_TABLE [WHERE expression];**

## Parameter Description

**Table 1-40** DELETE RECORDS parameters

Parameter	Description
CARBON TABLE	Name of the CarbonData table in which the DELETE operation is performed

## Precautions

- If a segment is deleted, all secondary indexes associated with the segment are deleted as well.
- If the **carbon.input.segments** property has been set for the queried table, the DELETE operation fails. To solve this problem, run the following statement before the query:

Syntax:

**SET carbon.input.segments. <database\_name>.<table\_name>=\***;

## Examples

- Example 1:  
**delete from columncarbonTable1 d where d.column1 = 'country';**
- Example 2:  
**delete from dest where column1 IN ('country1', 'country2');**
- Example 3:  
**delete from columncarbonTable1 where column1 IN (select column11 from sourceTable2);**
- Example 4:  
**delete from columncarbonTable1 where column1 IN (select column11 from sourceTable2 where column1 = 'USA');**
- Example 5:  
**delete from columncarbonTable1 where column2 >= 4;**

## System Response

Success or failure will be recorded in the driver log and on the client.

## 1.6.2.4 INSERT INTO CARBON TABLE

### Function

This command is used to add the output of the SELECT command to a Carbon table.

### Syntax

```
INSERT INTO [CARBON TABLE] [select query];
```

### Parameter Description

Table 1-41 INSERT INTO parameters

Parameter	Description
CARBON TABLE	Name of the CarbonData table to be inserted
select query	SELECT query on the source table (CarbonData, Hive, and Parquet tables are supported)

### Precautions

- A table has been created.
- You must belong to the data loading group in order to perform data loading operations. By default, the data loading group is named **ficommon**.
- CarbonData tables cannot be overwritten.
- The data type of the source table and the target table must be the same. Otherwise, data in the source table will be regarded as bad records.
- The **INSERT INTO** command does not support partial success. If bad records exist, the command fails.
- When you insert data of the source table to the target table, you cannot upload or update data of the source table.

To enable data loading or updating during the INSERT operation, set the following parameter to **true**.

**carbon.insert.persist.enable=true**

By default, the preceding parameters are set to **false**.

#### NOTE

Enabling this property will reduce the performance of the INSERT operation.

### Example

```
INSERT INTO CARBON select * from TABLENAME;
```

### System Response

Success or failure will be recorded in the driver logs.

### 1.6.2.5 DELETE SEGMENT by ID

#### Function

This command is used to delete segments by the ID.

#### Syntax

```
DELETE FROM TABLE db_name.table_name WHERE SEGMENT.ID IN  
(segment_id1,segment_id2);
```

#### Parameter Description

Table 1-42 DELETE SEGMENT parameters

Parameter	Description
segment_id	ID of the segment to be deleted.
db_name	Database name. If the parameter is not specified, the current database is used.
table_name	The name of the table in a specific database.

#### Usage Guidelines

Segments cannot be deleted from the stream table.

#### Examples

```
DELETE FROM TABLE CarbonDatabase.CarbonTable WHERE SEGMENT.ID IN  
(0);
```

```
DELETE FROM TABLE CarbonDatabase.CarbonTable WHERE SEGMENT.ID IN  
(0,5,8);
```

#### System Response

Success or failure will be recorded in the CarbonData log.

### 1.6.2.6 DELETE SEGMENT by DATE

#### Function

This command is used to delete segments by loading date. Segments created before a specific date will be deleted.

#### Syntax

```
DELETE FROM TABLE db_name.table_name WHERE SEGMENT.STARTTIME  
BEFORE date_value;
```

## Parameter Description

**Table 1-43** DELETE SEGMENT by DATE parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is used.
table_name	Name of a table in the specified database
date_value	Valid date when segments are started to be loaded. Segments before the date will be deleted.

## Precautions

Segments cannot be deleted from the stream table.

## Example

```
DELETE FROM TABLE db_name.table_name WHERE SEGMENT.STARTTIME  
BEFORE '2017-07-01 12:07:20';
```

STARTTIME indicates the loading start time of different loads.

## System Response

Success or failure will be recorded in CarbonData logs.

## 1.6.2.7 SHOW SEGMENTS

### Function

This command is used to list the segments of a CarbonData table.

### Syntax

```
SHOW SEGMENTS FOR TABLE [db_name.]table_name LIMIT number_of_loads;
```

## Parameter Description

**Table 1-44** SHOW SEGMENTS FOR TABLE parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is used.
table_name	Name of a table in the specified database
number_of_loads	Threshold of records to be listed

## Precautions

None

## Examples

**SHOW SEGMENTS FOR TABLE** *CarbonDatabase.CarbonTable* **LIMIT** 2;

## System Response

```

+-----+-----+-----+-----+-----+-----+-----+-----+
+
| ID | Status | Load Start Time | Load Time Taken | Partition | Data Size | Index Size | File Format |
+-----+-----+-----+-----+-----+-----+-----+-----+
+
| 3 | Success | 2020-09-28 22:53:26.336 | 3.726S | {} | 6.47KB | 3.30KB | columnar_v3 |
| 2 | Success | 2020-09-28 22:53:01.702 | 6.688S | {} | 6.47KB | 3.30KB | columnar_v3 |
+-----+-----+-----+-----+-----+-----+-----+-----+
+

```

### 1.6.2.8 CREATE SECONDARY INDEX

#### Function

This command is used to create secondary indexes in the CarbonData tables.

#### Syntax

```

CREATE INDEX index_name
ON TABLE [db_name].table_name (col_name1, col_name2)
AS 'carbondata'
PROPERTIES ('table_blocksize'='256');

```

#### Parameter Description

**Table 1-45** CREATE SECONDARY INDEX parameters

Parameter	Description
index_name	Index table name. It consists of letters, digits, and special characters (_).
db_name	Database name. It consists of letters, digits, and special characters (_).
table_name	Name of the database table. It consists of letters, digits, and special characters (_).
col_name	Name of a column in a table. Multiple columns are supported. It consists of letters, digits, and special characters (_).
table_blocksize	Block size of a data file. For details, see <a href="#">Block Size</a> .

## Precautions

**db\_name** is optional.

## Examples

- **CREATE INDEX productNameIndexTable on table productdb.productSalesTable (productName,city) as 'carbodata';**  
In this example, a secondary table named **productdb.productNameIndexTable** is created and index information of the provided column is loaded.
- **CREATE INDEX t1\_index1 on table t1 (c7\_Datatype\_Desc) AS 'carbodata' PROPERTIES('table\_blocksize'='256');**

## System Response

A secondary index table will be created. Index information related to the provided column will be loaded into the secondary index table. The success message will be recorded in system logs.

### 1.6.2.9 SHOW SECONDARY INDEXES

## Function

This command is used to list all secondary index tables in the CarbonData table.

## Syntax

**SHOW INDEXES ON db\_name.table\_name;**

## Parameter Description

**Table 1-46** SHOW SECONDARY INDEXES parameters

Parameter	Description
db_name	Database name. It consists of letters, digits, and special characters (_).
table_name	Name of the database table. It consists of letters, digits, and special characters (_).

## Precautions

**db\_name** is optional.

## Examples

**SHOW INDEXES ON productsales.product;**

## System Response

All index tables and corresponding index columns in a given CarbonData table will be listed.

### 1.6.2.10 DROP SECONDARY INDEX

#### Function

This command is used to delete the existing secondary index table in a specific table.

#### Syntax

```
DROP INDEX [IF EXISTS] index_name ON [db_name.]table_name;
```

#### Parameter Description

**Table 1-47** DROP SECONDARY INDEX parameters

Parameter	Description
<i>index_name</i>	Name of the index table. Table name contains letters, digits, and underscores (_).
<i>db_Name</i>	Name of the database. If the parameter is not specified, the current database is used.
<i>table_name</i>	Name of the table to be deleted.

#### Usage Guidelines

In this command, **IF EXISTS** and **db\_name** are optional.

#### Examples

```
DROP INDEX if exists productNameIndexTable ON productdb.productSalesTable;
```

#### System Response

Secondary Index Table will be deleted. Index information will be cleared in CarbonData table and the success message will be recorded in system logs.

### 1.6.2.11 CLEAN FILES

#### Function

After the **DELETE SEGMENT** command is executed, the deleted segments are marked as the **delete** state. After the segments are merged, the status of the original segments changes to **compacted**. The data files of these segments are

not physically deleted. If you want to forcibly delete these files, run the **CLEAN FILES** command.

However, running this command may result in a query command execution failure.

## Syntax

**CLEAN FILES FOR TABLE** *[db\_name.]table\_name* ;

## Parameter Description

**Table 1-48** CLEAN FILES FOR TABLE parameters

Parameter	Description
db_name	Database name. It consists of letters, digits, and underscores (_).
table_name	Name of the database table. It consists of letters, digits, and underscores (_).

## Precautions

None

## Examples

**CLEAN FILES FOR TABLE** *CarbonDatabase.CarbonTable*;

In this example, all the segments marked as **deleted** and **compacted** are physically deleted.

## System Response

Success or failure will be recorded in the driver logs.

## 1.6.2.12 SET/RESET

### Function

This command is used to dynamically add, update, display, or reset the CarbonData properties without restarting the driver.

### Syntax

- Add or Update parameter value:  
**SET** *parameter\_name=parameter\_value*  
This command is used to add or update the value of **parameter\_name**.
- Display property value:  
**SET** *parameter\_name*

- This command is used to display the value of **parameter\_name**.
- Display session parameter:  
**SET**  
This command is used to display all supported session parameters.
  - Display session parameters along with usage details:  
**SET -v**  
This command is used to display all supported session parameters and their usage details.
  - Reset parameter value:  
**RESET**  
This command is used to clear all session parameters.

## Parameter Description

**Table 1-49** SET parameters

Parameter	Description
parameter_name	Name of the parameter whose value needs to be dynamically added, updated, or displayed
parameter_value	New value of <b>parameter_name</b> to be set

## Precautions

The following table lists the properties which you can set or clear using the SET or RESET command.

**Table 1-50** Properties

Property	Description
carbon.options.bad.records.logger.enable	Whether to enable bad record logger.
carbon.options.bad.records.action	Operations on bad records, for example, force, redirect, fail, or ignore. For more information, see <a href="#">Bad record handling</a> .
carbon.options.is.empty.data.bad.record	Whether the empty data is considered as a bad record. For more information, see <a href="#">Bad record handling</a> .
carbon.options.sort.scope	Scope of the sort during data loading.
carbon.options.bad.record.path	HDFS path where bad records are stored.

Property	Description
carbon.custom.block.distribution	Whether to enable Spark or CarbonData block distribution.
enable.unsafe.sort	Whether to use unsafe sort during data loading. Unsafe sort reduces the garbage collection during data loading, thereby achieving better performance.
carbon.si.lookup.partialstring	<p>If this is set to <b>TRUE</b>, the secondary index uses the starts-with, ends-with, contains, and LIKE partition condition strings.</p> <p>If this is set to <b>FALSE</b>, the secondary index uses only the starts-with partition condition string.</p>
carbon.input.segments	<p>Segment ID to be queried. This property allows you to query a specified segment of a specified table. CarbonScan reads data only from the specified segment ID.</p> <p>Syntax:</p> <p><b>carbon.input.segments.</b>  <b>&lt;database_name&gt;. &lt;table_name&gt; = &lt;list of segment ids &gt;</b></p> <p>If you want to query a specified segment in multi-thread mode, you can use <b>CarbonSession.threadSet</b> instead of the <b>SET</b> statement.</p> <p>Syntax:</p> <p><b>CarbonSession.threadSet</b>  <b>("carbon.input.segments.</b>  <b>&lt;database_name&gt;. &lt;table_name&gt;","&lt;list of segment ids &gt;");</b></p> <p><b>NOTE</b>            You are advised not to set this property in the <b>carbon.properties</b> file because all sessions contain the segment list unless session-level or thread-level overwriting occurs.</p>

## Examples

- Add or Update:  
**SET enable.unsafe.sort=true**
- Display property value:  
**SET enable.unsafe.sort**

- Show the segment ID list, segment status, and other required details, and specify the segment list to be read:

**SHOW SEGMENTS FOR** *TABLE carbontable1;*

**SET** *carbon.input.segments.db.carbontable1 = 1, 3, 9;*

- Query a specified segment in multi-thread mode:

**CarbonSession.threadSet**

*("carbon.input.segments.default.carbon\_table\_Multi\_Thread", "1,3");*

- Use **CarbonSession.threadSet** to query segments in a multi-thread environment (Scala code is used as an example):

```
def main(args: Array[String]) {
  Future
  {
    CarbonSession.threadSet("carbon.input.segments.default.carbon_table_Multi_Thread", "1")
    spark.sql("select count(empno) from carbon_table_Multi_Thread").show()
  }
}
```

- Reset:

**RESET**

## System Response

- Success will be recorded in the driver log.
- Failure will be displayed on the UI.

### 1.6.3 Operation Concurrent Execution

Before performing **DDL** and **DML** operations, you need to obtain the corresponding locks. See **Table 1-51** for details about the locks that need to be obtained for each operation. The check mark (√) indicates that the lock is required. An operation can be performed only after all required locks are obtained.

You can check whether any two operations can be executed concurrently by using the following method: The first two lines in **Table 1-51** indicate two operations. If no column in the two lines is marked with the check mark (√), the two operations can be executed concurrently. That is, if the columns with check marks (√) in the two lines do not exist, the two operations can be executed concurrently.

**Table 1-51** List of obtaining locks for operations

Operation	MET DATA_ LOCK	COM PARTI TION_ LOCK	DRO P_ TABLE_ LOCK	DELE TE_ SEG MENT_ LOCK	CLEA N_ FILES_ LOCK	ALTE R_ PARTI TION_ LOCK	UPD ATE_ LOCK	STRE AMI NG_ LOCK	CON CURRE NT_ LOCK	SEG MENT_ LOCK
CREATE TABLE	-	-	-	-	-	-	-	-	-	-

Operation	METADATA_LOCK	COMPACTION_LOCK	DROP_TABLE_LOCK	DELETE_SEGMENT_LOCK	CLEANFILES_LOCK	ALTER_PARTITION_LOCK	UPDATE_LOCK	STREAMING_LOCK	CURRENT_LOAD_LOCK	SEGMENT_LOCK
CREATE TABLE AS SELECT	-	-	-	-	-	-	-	-	-	-
DROP TABLE	√	-	√	-	-	-	-	√	-	-
ALTER TABLE COMPACTION	-	√	-	-	-	-	√	-	-	-
TABLE RENAME	-	-	-	-	-	-	-	-	-	-
ADD COLUMNS	√	√	-	-	-	-	-	-	-	-
DROP COLUMNS	√	√	-	-	-	-	-	-	-	-
CHANGE DATA TYPE	√	√	-	-	-	-	-	-	-	-
REFRESH TABLE	-	-	-	-	-	-	-	-	-	-

Operation	METADATA_LOCK	COMPACTION_LOCK	DROP_TABLE_LOCK	DELETE_SEGMENT_LOCK	CLEANFILES_LOCK	ALTER_PARTITION_LOCK	UPDATE_LOCK	STREAMING_LOCK	CURRENT_LOAD_LOCK	SEGMENT_LOCK
REGISTER INDEX TABLE	√	-	-	-	-	-	-	-	-	-
REFRESH INDEX	-	√	-	-	-	-	-	-	-	-
LOAD DATA/INSERT INTO	-	-	-	-	-	-	-	-	√	√
UPDATE CARBON TABLE	√	√	-	-	-	-	√	-	-	-
DELETE RECORDS from CARBON TABLE	√	√	-	-	-	-	√	-	-	-
DELETE SEGMENT by ID	-	-	-	√	√	-	-	-	-	-

Operation	METADATA_LOCK	COMPACTIION_LOCK	DROP_TABLE_LOCK	DELETE_SEGMENT_LOCK	CLEANFILES_LOCK	ALTER_PARTITION_LOCK	UPDATE_LOCK	STREAMING_LOCK	CURRENT_LOAD_LOCK	SEGMENT_LOCK
DELETE SEGMENT by DATE	-	-	-	√	√	-	-	-	-	-
SHOW SEGMENTS	-	-	-	-	-	-	-	-	-	-
CREATE SECONDARY INDEX	√	√	-	√	-	-	-	-	-	-
SHOW SECONDARY INDEXES	-	-	-	-	-	-	-	-	-	-
DROP SECONDARY INDEX	√	-	√	-	-	-	-	-	-	-
CLEAN FILES	-	-	-	-	-	-	-	-	-	-
SET/RESET	-	-	-	-	-	-	-	-	-	-

Operation	METADATA_LOCK	COMPARTION_LOCK	DROP_TABLE_LOCK	DELETE_SEGMENT_LOCK	CLEANFILES_LOCK	ALTER_PARTITION_LOCK	UPDATE_LOCK	STREAMING_LOCK	CURRENT_LOAD_LOCK	SEGMENT_LOCK
Add Hive Partition	-	-	-	-	-	-	-	-	-	-
Drop Hive Partition	√	√	√	√	√	√	-	-	-	-
Drop Partition	√	√	√	√	√	√	-	-	-	-
Alter table set	√	√	-	-	-	-	-	-	-	-

## 1.6.4 API

This section describes the APIs and usage methods of Segment. All methods are in the org.apache.spark.util.CarbonSegmentUtil class.

The following methods have been abandoned:

```
/**
 * Returns the valid segments for the query based on the filter condition
 * present in carbonScanRdd.
 *
 * @param carbonScanRdd
 * @return Array of valid segments
 */
@deprecated def getFilteredSegments(carbonScanRdd: CarbonScanRDD[InternalRow]): Array[String];
```

## Usage Method

Use the following methods to obtain CarbonScanRDD from the query statement:

```
val df=carbon.sql("select * from table where age='12'")
val myscan=df.queryExecution.sparkPlan.collect {
case scan: CarbonDataSourceScan if scan.rdd.isInstanceOf[CarbonScanRDD[InternalRow]] => scan.rdd
case scan: RowDataSourceScanExec if scan.rdd.isInstanceOf[CarbonScanRDD[InternalRow]] => scan.rdd
}.head
val carbonrdd=myscan.asInstanceOf[CarbonScanRDD[InternalRow]]
```

Example:

```
CarbonSegmentUtil.getFilteredSegments(carbonrdd)
```

The filtered segment can be obtained by importing SQL statements.

```
/**
 * Returns an array of valid segment numbers based on the filter condition provided in the sql
```

```
* NOTE: This API is supported only for SELECT Sql (insert into,ctas,.. is not supported)
*
* @param sql
* @param sparkSession
* @return Array of valid segments
* @throws UnsupportedOperationException because Get Filter Segments API supports if and only
* if only one carbon main table is present in query.
*/
def getFilteredSegments(sql: String, sparkSession: SparkSession): Array[String];
```

#### Example:

```
CarbonSegmentUtil.getFilteredSegments("select * from table where age='12'", sparkSession)
```

Import the database name and table name to obtain the list of segments to be merged. The obtained segments can be used as parameters of the getMergedLoadName function.

```
/**
 * Identifies all segments which can be merged with MAJOR compaction type.
 * NOTE: This result can be passed to getMergedLoadName API to get the merged load name.
 *
 * @param sparkSession
 * @param tableName
 * @param dbName
 * @return list of LoadMetadataDetails
 */
def identifySegmentsToBeMerged(sparkSession: SparkSession,
tableName: String,
dbName: String) : util.List[LoadMetadataDetails];
```

#### Example:

```
CarbonSegmentUtil.identifySegmentsToBeMerged(sparkSession, "table_test","default")
```

Import the database name, table name, and obtain all segments which can be merged with CUSTOM compaction type. The obtained segments can be transferred as the parameter of the getMergedLoadName function.

```
/**
 * Identifies all segments which can be merged with CUSTOM compaction type.
 * NOTE: This result can be passed to getMergedLoadName API to get the merged load name.
 *
 * @param sparkSession
 * @param tableName
 * @param dbName
 * @param customSegments
 * @return list of LoadMetadataDetails
 * @throws UnsupportedOperationException if customSegments is null or empty.
 * @throws MalformedCarbonCommandException if segment does not exist or is not valid
 */
def identifySegmentsToBeMergedCustom(sparkSession: SparkSession,
tableName: String,
dbName: String,
customSegments: util.List[String]): util.List[LoadMetadataDetails];
```

#### Example:

```
val customSegments = new util.ArrayList[String]()
customSegments.add("1")
customSegments.add("2")
CarbonSegmentUtil.identifySegmentsToBeMergedCustom(sparkSession, "table_test","default",
customSegments)
```

If a segment list is specified, the merged load name is returned.

```
/**
 * Returns the Merged Load Name for given list of segments
 *
 */
```

```
* @param list of segments
* @return Merged Load Name
* @throws UnsupportedOperationException if list of segments is less than 1
*/
def getMergedLoadName(list: util.List[LoadMetadataDetails]): String;
```

Example:

```
val carbonTable = CarbonEnv.getCarbonTable(Option(databaseName), tableName)(sparkSession)
val loadMetadataDetails = SegmentStatusManager.readLoadMetadata(carbonTable.getMetadataPath)
CarbonSegmentUtil.getMergedLoadName(loadMetadataDetails.toList.asJava)
```

## 1.6.5 Spatial Indexes

### Quick Example

```
create table IF NOT EXISTS carbonTable
(
  COLUMN1 BIGINT,
  LONGITUDE BIGINT,
  LATITUDE BIGINT,
  COLUMN2 BIGINT,
  COLUMN3 BIGINT
)
STORED AS carbondata
TBLPROPERTIES
('SPATIAL_INDEX.mygeohash.type='geohash','SPATIAL_INDEX.mygeohash.sourcecolumns='longitude,
latitude','SPATIAL_INDEX.mygeohash.originLatitude'='39.850713','SPATIAL_INDEX.mygeohash.gridSize'='50','S
PATIAL_INDEX.mygeohash.minLongitude'='115.828503','SPATIAL_INDEX.mygeohash.maxLongitude'='720.000
000','SPATIAL_INDEX.mygeohash.minLatitude'='39.850713','SPATIAL_INDEX.mygeohash.maxLatitude'='720.0
00000','SPATIAL_INDEX='mygeohash','SPATIAL_INDEX.mygeohash.conversionRatio'='1000000','SORT_COLU
MNS'='column1,column2,column3,latitude,longitude');
```

### Introduction to Spatial Indexes

Spatial data includes multidimensional points, lines, rectangles, cubes, polygons, and other geometric objects. A spatial data object occupies a certain region of space, called spatial scope, characterized by its location and boundary. The spatial data can be either point data or region data.


- Point data: A point has a spatial extent characterized completely by its location. It does not occupy space and has no associated boundary. Point data consists of a collection of points in a two-dimensional space. Points can be stored as a pair of longitude and latitude.
- Region data: A region has a spatial extent with a location, and boundary. The location can be considered as the position of a fixed point in the region, such as its centroid. In two dimensions, the boundary can be visualized as a line (for finite regions, a closed loop). Region data contains a collection of regions.

Currently, only point data is supported, and it can be stored.

Longitude and latitude can be encoded as a unique GeoID. Geohash is a public-domain geocoding system invented by Gustavo Niemeyer. It encodes geographical locations into a short string of letters and digits. It is a hierarchical spatial data structure which subdivides the space into buckets of grid shape, which is one of the many applications of what is known as the Z-order curve, and generally the space-filling curve.

The Z value of a point in multiple dimensions is calculated by interleaving the binary representation of its coordinate value, as shown in the following figure.

When Geohash is used to create a GeoID, data is sorted by GeoID instead of longitude and latitude. Data is stored by spatial proximity.



## Creating a Table

### GeoHash encoding:

```
create table IF NOT EXISTS carbonTable
(
...
`LONGITUDE` BIGINT,
`LATITUDE` BIGINT,
...
)
STORED AS carbondata
TBLPROPERTIES
('SPATIAL_INDEX.mygeohash.type='geohash','SPATIAL_INDEX.mygeohash.sourcecolumns='longitude,
latitude','SPATIAL_INDEX.mygeohash.originLatitude='xx.xxxxxx','SPATIAL_INDEX.mygeohash.gridSize='xx','SP
ATIAL_INDEX.mygeohash.minLongitude='xxx.xxxxxx','SPATIAL_INDEX.mygeohash.maxLongitude='xxx.xxxxxx',
'SPATIAL_INDEX.mygeohash.minLatitude='xx.xxxxxx','SPATIAL_INDEX.mygeohash.maxLatitude='xxx.xxxxxx',
'SPATIAL_INDEX='mygeohash','SPATIAL_INDEX.mygeohash.conversionRatio='1000000','SORT_COLUMNS'='co
lumn1,column2,column3,latitude,longitude');
```

**SPATIAL\_INDEX** is a user-defined index handler. This handler allows users to create new columns from the table-structure column set. The new column name is the same as that of the handler name. The **type** and **sourcecolumns** properties of the handler are mandatory. Currently, the value of **type** supports only **geohash**. Carbon provides a default implementation class that can be easily used. You can extend the default implementation class to mount the customized implementation class of **geohash**. The default handler also needs to provide the following table properties:

- **SPATIAL\_INDEX.xxx.originLatitude**: specifies the origin latitude. (**Double** type.)

- **SPATIAL\_INDEX.xxx.gridSize**: specifies the grid length in meters. (**Int** type.)
- **SPATIAL\_INDEX.xxx.minLongitude**: specifies the minimum longitude. (**Double** type.)
- **SPATIAL\_INDEX.xxx.maxLongitude**: specifies the maximum longitude. (**Double** type.)
- **SPATIAL\_INDEX.xxx.minLatitude**: specifies the minimum latitude. (**Double** type.)
- **SPATIAL\_INDEX.xxx.maxLatitude**: specifies the maximum latitude. (**Double** type.)
- **SPATIAL\_INDEX.xxx.conversionRatio**: used to convert the small value of the longitude and latitude to an integer. (**Int** type.)

You can add your own table properties to the handlers in the above format and access them in your custom implementation class. **originLatitude**, **gridSize**, and **conversionRatio** are mandatory. Other parameters are optional in Carbon. You can use the **SPATIAL\_INDEX.xxx.class** property to specify their implementation classes.

The default implementation class can generate handler column values for **sourcecolumns** in each row and support query based on the **sourcecolumns** filter criteria. The generated handler column is invisible to users. Except the **SORT\_COLUMNS** table properties, no DDL commands or properties are allowed to contain the handler column.

#### NOTE

- By default, the generated handler column is regarded as the sorting column. If **SORT\_COLUMNS** does not contain any **sourcecolumns**, add the handler column to the end of the existing **SORT\_COLUMNS**. If the handler column has been specified in **SORT\_COLUMNS**, its order in **SORT\_COLUMNS** remains unchanged.
- If **SORT\_COLUMNS** contains any **sourcecolumns** but does not contain the handler column, the handler column is automatically inserted before **sourcecolumns** in **SORT\_COLUMNS**.
- If **SORT\_COLUMNS** needs to contain any **sourcecolumns**, ensure that the handler column is listed before the **sourcecolumns** so that the handler column can take effect during sorting.

#### GeoSOT encoding:

```
CREATE TABLE carbontable(  
...  
longitude DOUBLE,  
latitude DOUBLE,  
...)  
STORED AS carbondata  
TBLPROPERTIES ('SPATIAL_INDEX'='xxx',  
'SPATIAL_INDEX.xxx.type'='geosot',  
'SPATIAL_INDEX.xxx.sourcecolumns'='longitude, latitude',  
'SPATIAL_INDEX.xxx.level'='21',  
'SPATIAL_INDEX.xxx.class'='org.apache.carbondata.geo.GeoSOTIndex')
```

**Table 1-52** Parameter description

Parameter	Description
SPATIAL_INDEX	Specifies the spatial index. Its value is the same as the column name.
SPATIAL_INDEX.xxx.type	(Mandatory) The value is set to <b>geosot</b> .
SPATIAL_INDEX.xxx.source columns	(Mandatory) Specifies the source columns for calculating the spatial index. The value must be two existing columns of the double type.
SPATIAL_INDEX.xxx.level	(Optional) Specifies the columns for calculating the spatial index. The default value is <b>17</b> , through which you can obtain an accurate result and improve the computing performance.
SPATIAL_INDEX.xxx.class	(Optional) Specifies the implementation class of GeoSOT. The default value is <b>org.apache.carbondata.geo.GeoSOTIndex</b> .

Example:

```
create table geosot(
timevalue bigint,
longitude double,
latitude double)
stored as carbondata
TBLPROPERTIES ('SPATIAL_INDEX'='mygeosot',
'SPATIAL_INDEX.mygeosot.type'='geosot',
'SPATIAL_INDEX.mygeosot.level'='21', 'SPATIAL_INDEX.mygeosot.sourcecolumns'='longitude, latitude');
```

## Preparing Data

- Data file 1: **geosotdata.csv**  
timevalue,longitude,latitude  
1575428400000,116.285807,40.084087  
1575428400000,116.372142,40.129503  
1575428400000,116.187332,39.979316  
1575428400000,116.337069,39.951887  
1575428400000,116.359102,40.154684  
1575428400000,116.736367,39.970323  
1575428400000,116.720179,40.009893  
1575428400000,116.346961,40.13355  
1575428400000,116.302895,39.930753  
1575428400000,116.288955,39.999101  
1575428400000,116.17609,40.129953  
1575428400000,116.725575,39.981115  
1575428400000,116.266922,40.179415  
1575428400000,116.353706,40.156483  
1575428400000,116.362699,39.942444  
1575428400000,116.325378,39.963129
- Data file 2: **geosotdata2.csv**  
timevalue,longitude,latitude  
1575428400000,120.17708,30.326882  
1575428400000,120.180685,30.326327  
1575428400000,120.184976,30.327105  
1575428400000,120.189311,30.327549  
1575428400000,120.19446,30.329698  
1575428400000,120.186965,30.329133

```
1575428400000,120.177481,30.328911
1575428400000,120.169713,30.325614
1575428400000,120.164563,30.322243
1575428400000,120.171558,30.319613
1575428400000,120.176365,30.320687
1575428400000,120.179669,30.323688
1575428400000,120.181001,30.320761
1575428400000,120.187094,30.32354
1575428400000,120.193574,30.323651
1575428400000,120.186192,30.320132
1575428400000,120.190055,30.317464
1575428400000,120.195376,30.318094
1575428400000,120.160786,30.317094
1575428400000,120.168211,30.318057
1575428400000,120.173618,30.316612
1575428400000,120.181001,30.317316
1575428400000,120.185162,30.315908
1575428400000,120.192415,30.315871
1575428400000,120.161902,30.325614
1575428400000,120.164306,30.328096
1575428400000,120.197093,30.325985
1575428400000,120.19602,30.321651
1575428400000,120.198638,30.32354
1575428400000,120.165421,30.314834
```

## Importing Data

The GeoHash default implementation class extends the customized index abstract class. If the handler property is not set to a customized implementation class, the default implementation class is used. You can extend the default implementation class to mount the customized implementation class of **geohash**. The methods of the customized index abstract class are as follows:

- **Init** method: Used to extract, verify, and store the handler property. If the operation fails, the system throws an exception and displays the error information.
- **Generate** method: Used to generate indexes. It generates an index for each row of data.
- **Query** method: Used to generate an index value range list for given input.

The commands for importing data are the same as those for importing common Carbon tables.

```
LOAD DATA inpath '/tmp/geosotdata.csv' INTO TABLE geosot OPTIONS
('DELIMITER'=',');
```

```
LOAD DATA inpath '/tmp/geosotdata2.csv' INTO TABLE geosot OPTIONS
('DELIMITER'=',');
```

### NOTE

For details about **geosotdata.csv** and **geosotdata2.csv**, see [Preparing Data](#).

## Aggregate Query of Irregular Spatial Sets

### Query statements and filter UDFs

- Filtering data based on polygon  
**IN\_POLYGON(pointList)**  
UDF input parameter

Parameter	Type	Description
pointList	String	Enter multiple points as a string. Each point is presented as <b>longitude latitude</b> . Longitude and latitude are separated by a space. Each pair of longitude and latitude is separated by a comma (,). The longitude and latitude values at the start and end of the string must be the same.

UDF output parameter

Parameter	Type	Description
inOrNot	Boolean	Checks whether data is in the specified <b>polygon_list</b> .

Example:

```
select longitude, latitude from geosot where IN_POLYGON('116.321011 40.123503, 116.137676 39.947911, 116.560993 39.935276, 116.321011 40.123503');
```

- Filtering data based on the polygon list

**IN\_POLYGON\_LIST(polygonList, opType)**

UDF input parameters

Parameter	Type	Description
polygonList	String	Inputs multiple polygons as a string. Each polygon is presented as <b>POLYGON ((longitude1 latitude1, longitude2 latitude2, ...))</b> . Note that there is a space after <b>POLYGON</b> . Longitudes and latitudes are separated by spaces. Each pair of longitude and latitude is separated by a comma (,). The longitudes and latitudes at the start and end of a polygon must be the same. <b>IN_POLYGON_LIST</b> requires at least two polygons.  Example: POLYGON ((116.137676 40.163503, 116.137676 39.935276, 116.560993 39.935276, 116.137676 40.163503))

Parameter	Type	Description
opType	String	Performs union, intersection, and subtraction on multiple polygons. Currently, the following operation types are supported: <ul style="list-style-type: none"> <li>OR: A U B U C (Assume that three polygons A, B, and C are input.)</li> <li>AND: A ∩ B ∩ C</li> </ul>

UDF output parameter

Parameter	Type	Description
inOrNot	Boolean	Checks whether data is in the specified <b>polygon_list</b> .

Example:

```
select longitude, latitude from geosot where IN_POLYGON_LIST('POLYGON ((120.176433
30.327431,120.171283 30.322245,120.181411 30.314540, 120.190509 30.321653,120.185188
30.329358,120.176433 30.327431)), POLYGON ((120.191603 30.328946,120.184179
30.327465,120.181819 30.321464, 120.190359 30.315388,120.199242 30.324464,120.191603
30.328946))', 'OR');
```

- Filtering data based on the polyline list

**IN\_POLYLINE\_LIST(polylineList, bufferInMeter)**

UDF input parameters

Parameter	Type	Description
polylineList	String	Inputs multiple polylines as a string. Each polyline is presented as <b>LINSTRING (longitude1 latitude1, longitude2 latitude2, ...)</b> . Note that there is a space after <b>LINSTRING</b> . Longitudes and latitudes are separated by spaces. Each pair of longitude and latitude is separated by a comma (,).  A union will be output based on the data in multiple polylines.  Example: LINSTRING (116.137676 40.163503, 116.137676 39.935276, 116.260993 39.935276)
bufferInMeter	Float	Polyline buffer distance, in meters. Right angles are used at the end to create a buffer.

UDF output parameter

Parameter	Type	Description
inOrNot	Boolean	Checks whether data is in the specified <b>polyline_list</b> .

Example:

```
select longitude, latitude from geosot where IN_POLYLINE_LIST('LINESTRING (120.184179 30.327465, 120.191603 30.328946, 120.199242 30.324464, 120.190359 30.315388)', 65);
```

- Filtering data based on the GeoID range list

**IN\_POLYGON\_RANGE\_LIST(polygonRangeList, opType)**

UDF input parameters

Parameter	Type	Description
polygonRangeList	String	Inputs multiple rangeLists as a string. Each rangeList is presented as <b>RANGELIST (startGeold1 endGeold1, startGeold2 endGeold2, ...)</b> . Note that there is a space after <b>RANGELIST</b> . Start GeolDs and end GeolDs are separated by spaces. Each group of GeolD ranges is separated by a comma (,).  Example: RANGELIST (855279368848 855279368850, 855280799610 855280799612, 855282156300 855282157400)
opType	String	Performs union, intersection, and subtraction on multiple rangeLists. Currently, the following operation types are supported: <ul style="list-style-type: none"> <li>• OR: A U B U C (Assume that three rangeLists A, B, and C are input.)</li> <li>• AND: A ∩ B ∩ C</li> </ul>

UDF output parameter

Parameter	Type	Description
inOrNot	Boolean	Checks whether data is in the specified <b>polyRange_list</b> .

Example:

```
select mygeosot, longitude, latitude from geosot where IN_POLYGON_RANGE_LIST('RANGELIST
(526549722865860608 526549722865860618, 532555655580483584 532555655580483594)', 'OR');
```

- Performing polygon query

**IN\_POLYGON\_JOIN(GEO\_HASH\_INDEX\_COLUMN, POLYGON\_COLUMN)**

Perform join query on two tables. One is a spatial data table containing the longitude, latitude, and GeoHashIndex columns, and the other is a dimension table that saves polygon data.

During query, **IN\_POLYGON\_JOIN UDF**, **GEO\_HASH\_INDEX\_COLUMN**, and **POLYGON\_COLUMN** of the polygon table are used. **Polygon\_column** specifies the column containing multiple points (longitude and latitude pairs). The first and last points in each row of the Polygon table must be the same. All points in each row form a closed geometric shape.

UDF input parameters

Parameter	Type	Description
GEO_HASH_INDEX_COLUMN	Long	GeoHashIndex column of the spatial data table.
POLYGON_COLUMN	String	Polygon column of the polygon table, the value of which is represented by the string of polygon, for example, <b>POLYGON (( longitude1 latitude1, longitude2 latitude2, ...))</b> .

Example:

```
CREATE TABLE polygonTable(
polygon string,
poiType string,
poiid String)
STORED AS carbondata;

insert into polygonTable select 'POLYGON ((120.176433 30.327431,120.171283 30.322245,
120.181411 30.314540,120.190509 30.321653,120.185188 30.329358,120.176433 30.327431))','abc','1';

insert into polygonTable select 'POLYGON ((120.191603 30.328946,120.184179 30.327465,
120.181819 30.321464,120.190359 30.315388,120.199242 30.324464,120.191603 30.328946))','abc','2';

select t1.longitude,t1.latitude from geosot t1
inner join
(select polygon,poiid from polygonTable where poiType='abc') t2
on in_polygon_join(t1.mygeosot,t2.polygon) group by t1.longitude,t1.latitude;
```

- Performing range\_list query

**IN\_POLYGON\_JOIN\_RANGE\_LIST(GEO\_HASH\_INDEX\_COLUMN, POLYGON\_COLUMN)**

Use the **IN\_POLYGON\_JOIN\_RANGE\_LIST** UDF to associate the spatial data table with the polygon dimension table based on **Polygon\_RangeList**. By using a range list, you can skip the conversion between a polygon and a range list.

UDF input parameters

Parameter	Type	Description
GEO_HASH_INDEX_COLUMN	Long	GeoHashIndex column of the spatial data table.
POLYGON_COLUMN	String	Rangelist column of the Polygon table, the value of which is represented by the string of rangeList, for example, <b>RANGELIST (startGeoid1 endGeoid1, startGeoid2 endGeoid2, ...)</b> .

Example:

```
CREATE TABLE polygonTable(
polygon string,
poiType string,
poild String)
STORED AS carbondata;

insert into polygonTable select 'RANGELIST (526546455897309184 526546455897309284,
526549831217315840 526549831217315850, 532555655580483534 532555655580483584)', 'xyz', '2';

select t1.*
from geosot t1
inner join
(select polygon, poild from polygonTable where poiType='xyz') t2
on in_polygon_join_range_list(t1.mygeosot, t2.polygon);
```

### UDFs of spatial index tools

- Obtaining row number and column number of a grid converted from Geoid  
**GeoidToGridXy(geoid)**

UDF input parameter

Parameter	Type	Description
geoid	Long	Calculates the row number and column number of the grid based on Geoid.

UDF output parameter

Parameter	Type	Description
gridArray	Array[Int]	Returns the grid row and column numbers contained in Geoid in array. The first digit indicates the row number, and the second digit indicates the column number.

Example:

```
select longitude, latitude, mygeohash, GeoldToGridXy(mygeohash) as GridXY from geoTable;
```

- Converting longitude and latitude to Geold

**LatLngToGeold(latitude, longitude oriLatitude, gridSize)**

UDF input parameters

Parameter	Type	Description
longitude	Long	Longitude. Note: The value is an integer after conversion.
latitude	Long	Latitude. Note: The value is an integer after conversion.
oriLatitude	Double	Origin latitude, required for calculating Geold.
gridSize	Int	Grid size, required for calculating Geold.

UDF output parameter

Parameter	Type	Description
geold	Long	Returns a number that indicates the longitude and latitude after coding.

Example:

```
select longitude, latitude, mygeohash, LatLngToGeold(latitude, longitude, 39.832277, 50) as geold from geoTable;
```

- Converting Geold to longitude and latitude

**GeoldToLatLng(geold, oriLatitude, gridSize)**

UDF input parameters

Parameter	Type	Description
geold	Long	Calculates the longitude and latitude based on Geold.
oriLatitude	Double	Origin latitude, required for calculating the longitude and latitude.
gridSize	Int	Grid size, required for calculating the longitude and latitude.

 **NOTE**

GeoID is generated based on the grid coordinates, which are the grid center. Therefore, the calculated longitude and latitude are the longitude and latitude of the grid center. There may be an error ranging from 0 degree to half of the grid size between the calculated longitude and latitude and the longitude and latitude of the generated GeoID.

UDF output parameter

Parameter	Type	Description
latitudeAndLongitude	Array[Double]	Returns the longitude and latitude coordinates of the grid center that represent the GeoID in array. The first digit indicates the latitude, and the second digit indicates the longitude.

Example:

```
select longitude, latitude, mygeohash, GeoldToLatLng(mygeohash, 39.832277, 50) as LatitudeAndLongitude from geoTable;
```

- Calculating the upper-layer GeoID of the pyramid model

**ToUpperLayerGeold(geold)**

UDF input parameter

Parameter	Type	Description
geold	Long	Calculates the upper-layer GeoID of the pyramid model based on the input GeoID.

UDF output parameter

Parameter	Type	Description
geold	Long	Returns the upper-layer GeoID of the pyramid model.

Example:

```
select longitude, latitude, mygeohash, ToUpperLayerGeold(mygeohash) as upperLayerGeold from geoTable;
```

- Obtaining the GeoID range list using the input polygon

**ToRangeList(polygon, oriLatitude, gridSize)**

UDF input parameters

Parameter	Type	Description
polygon	String	Input polygon string, which is a pair of longitude and latitude. Longitude and latitude are separated by a space. Each pair of longitude and latitude is separated by a comma (,). The longitude and latitude at the start and end must be the same.
oriLatitude	Double	Origin latitude, required for calculating GeoID.
gridSize	Int	Grid size, required for calculating GeoID.

UDF output parameter

Parameter	Type	Description
geoidList	Buffer[Array[Long]]	Converts polygons into GeoID range lists.

Example:

```
select ToRangeList('116.321011 40.123503, 116.137676 39.947911, 116.560993 39.935276, 116.321011 40.123503', 39.832277, 50) as rangeList from geoTable;
```

- Calculating the upper-layer longitude of the pyramid model

**ToUpperLongitude (longitude, gridSize, oriLat)**

UDF input parameters

Parameter	Type	Description
longitude	Long	Input longitude, which is a long integer.
gridSize	Int	Grid size, required for calculating longitude.
oriLatitude	Double	Origin latitude, required for calculating longitude.

UDF output parameter

Parameter	Type	Description
longitude	Long	Returns the upper-layer longitude.

Example:

```
select ToUpperLongitude (-23575161504L, 50, 39.832277) as upperLongitude from geoTable;
```

- Calculating the upper-layer latitude of the pyramid model

**ToUpperLatitude(Latitude, gridSize, oriLat)**

UDF input parameters

Parameter	Type	Description
latitude	Long	Input latitude, which is a long integer.
gridSize	Int	Grid size, required for calculating latitude.
oriLatitude	Double	Origin latitude, required for calculating latitude.

UDF output parameter

Parameter	Type	Description
Latitude	Long	Returns the upper-layer latitude.

Example:

```
select ToUpperLatitude (-23575161504L, 50, 39.832277) as upperLatitude from geoTable;
```

- Converting longitude and latitude to GeoSOT

**LatLngToGridCode(latitude, longitude, level)**

UDF input parameters

Parameter	Type	Description
latitude	Double	Latitude.
longitude	Double	Longitude.
level	Int	Level. The value range is [0, 32].

UDF output parameter

Parameter	Type	Description
geold	Long	A number that indicates the longitude and latitude after GeoSOT encoding.

Example:

```
select LatLngToGridCode(39.930753, 116.302895, 21) as geold;
```

## 1.7 CarbonData Troubleshooting

### 1.7.1 Filter Result Is not Consistent with Hive when a Big Double Type Value Is Used in Filter

#### Symptom

When double data type values with higher precision are used in filters, incorrect values are returned by filtering results.

#### Possible Causes

When double data type values with higher precision are used in filters, values are rounded off before comparison. Therefore, values of double data type with different fraction part are considered same.

#### Troubleshooting Method

NA.

#### Procedure

To avoid this problem, use decimal data type when high precision data comparisons are required, such as financial applications, equality and inequality checks, and rounding operations.

#### Reference Information

NA.

### 1.7.2 Query Performance Deterioration

#### Symptom

The query performance fluctuates when the query is executed in different query periods.

#### Possible Causes


During data loading, the memory configured for each executor program instance may be insufficient, resulting in more Java GCs. When GC occurs, the query performance deteriorates.

#### Troubleshooting Method

On the Spark UI, the GC time of some executors is obviously higher than that of other executors, or all executors have high GC time.

## Procedure

Log in to Manager and choose **Cluster > Services > Spark2x**. On the displayed page, click the **Configurations** tab and then **All Configurations**, search for **spark.executor.memory** in the search box, and set its to a larger value.



The screenshot shows a configuration interface with a search bar containing 'spark.executor.memory' and a text input field containing '4G'.

## Reference

None

# 1.8 CarbonData FAQ

## 1.8.1 Why Is Incorrect Output Displayed When I Perform Query with Filter on Decimal Data Type Values?

### Question

Why is incorrect output displayed when I perform query with filter on decimal data type values?

For example:

```
select * from carbon_table where num = 1234567890123456.22;
```

Output:

```
+-----+-----+--+  
| name |    num    |  
+-----+-----+--+  
| IAA | 1234567890123456.22 |  
| IAA | 1234567890123456.21 |  
+-----+-----+--+
```

### Answer

To obtain accurate output, append BD to the number.

For example:

```
select * from carbon_table where num = 1234567890123456.22BD;
```

Output:

```
+-----+-----+--+  
| name |    num    |  
+-----+-----+--+  
| IAA | 1234567890123456.22 |  
+-----+-----+--+
```

## 1.8.2 How to Avoid Minor Compaction for Historical Data?

### Question

How to avoid minor compaction for historical data?

### Answer

If you want to load historical data first and then the incremental data, perform following steps to avoid minor compaction of historical data:

1. Load all historical data.
2. Configure the major compaction size to a value smaller than the segment size of historical data.
3. Run the major compaction once on historical data so that these segments will not be considered later for minor compaction.
4. Load the incremental data.
5. You can configure the minor compaction threshold as required.

For example:

1. Assume that you have loaded all historical data to CarbonData and the size of each segment is 500 GB.
2. Set the threshold of major compaction property to **carbon.major.compaction.size = 491520** (480 GB x 1024).
3. Run major compaction. All segments will be compacted because the size of each segment is more than configured size.
4. Perform incremental loading.
5. Configure the minor compaction threshold to **carbon.compaction.level.threshold = 6,6**.
6. Run minor compaction. As a result, only incremental data is compacted.

## 1.8.3 How to Change the Default Group Name for CarbonData Data Loading?

### Question

How to change the default group name for CarbonData data loading?

### Answer

By default, the group name for CarbonData data loading is **ficommon**. You can perform the following operation to change the default group name:

1. Edit the **carbon.properties** file.
2. Change the value of the key **carbon.dataload.group.name** as required. The default value is **ficommon**.

## 1.8.4 Why Does INSERT INTO CARBON TABLE Command Fail?

### Question

Why does the *INSERT INTO CARBON TABLE* command fail and the following error message is displayed?

```
Data load failed due to bad record
```

### Answer

The *INSERT INTO CARBON TABLE* command fails in the following scenarios:

- If the data type of source and target table columns are not the same, the data from the source table will be treated as bad records and the *INSERT INTO* command fails.
- If the result of aggregation function on a source column exceeds the maximum range of the target column, then the *INSERT INTO* command fails.

Solution:

You can use the cast function on corresponding columns when inserting records.

For example:

- a. Run the *DESCRIBE* command to query the target and source table.

```
DESCRIBE newcarbontable;
```

Result:

```
col1 int  
col2 bigint
```

```
DESCRIBE sourcetable;
```

Result:

```
col1 int  
col2 int
```

- b. Add the cast function to convert bigint value to integer.

```
INSERT INTO newcarbontable select col1, cast(col2 as integer) from  
sourcetable;
```

## 1.8.5 Why Is the Data Logged in Bad Records Different from the Original Input Data with Escape Characters?

### Question

Why is the data logged in bad records different from the original input data with escaped characters?

### Answer

An escape character is a backslash (\) followed by one or more characters. If the input records contain escape characters such as \t, \b, \n, \r, \f, \', \", \\ , java will process the escape character '\' and the following characters together to obtain the escaped meaning.

For example, if the CSV data type `2010\\10,test` is inserted to String,int type, the value is treated as bad records, because `test` cannot be converted to int. The value logged in the bad records is `2010\10` because java processes `\\` as `\`.

## 1.8.6 Why Data Load Performance Decreases due to Bad Records?

### Question

Why data load performance decreases due to bad records?

### Answer

If bad records are present in the data and `BAD_RECORDS_LOGGER_ENABLE` is `true` or `BAD_RECORDS_ACTION` is `redirect` then load performance will decrease due to extra I/O for writing failure reason in log file or redirecting the records to raw CSV.

## 1.8.7 Why INSERT INTO/LOAD DATA Task Distribution Is Incorrect and the Opened Tasks Are Less Than the Available Executors when the Number of Initial Executors Is Zero?

### Question

Why `INSERT INTO` or `LOAD DATA` task distribution is incorrect, and the opened tasks are less than the available executors when the number of initial executors is zero?

### Answer

In case of `INSERT INTO` or `LOAD DATA`, CarbonData distributes one task per node. If the executors are not allocated from the distinct nodes then CarbonData will launch fewer tasks.

#### Solution:

Configure higher value for the executor memory and core so that the yarn can launch only one executor per node.

1. Configure the number of the Executor cores.
  - Configure the `spark.executor.cores` in `spark-defaults.conf` or the `SPARK_EXECUTOR_CORES` in `spark-env.sh` appropriately.
  - Add `--executor-cores NUM` parameter to configure the cores during use the `spark-submit` command.
2. Configure the Executor memory.
  - Configure the `spark.executor.memory` in `spark-defaults.conf` or the `SPARK_EXECUTOR_MEMORY` in `spark-env.sh` appropriately.
  - Add `--executor-memory MEM` parameter to configure the memory during use the `spark-submit` command.

## 1.8.8 Why Does CarbonData Require Additional Executors Even Though the Parallelism Is Greater Than the Number of Blocks to Be Processed?

### Question

Why does CarbonData require additional executors even though the parallelism is greater than the number of blocks to be processed?

### Answer

CarbonData block distribution optimizes data processing as follows:

1. Optimize data processing parallelism.
2. Optimize parallel reading of block data.

To optimize parallel processing and parallel read, CarbonData requests executors based on the locality of blocks so that it can obtain executors on all nodes.

If you are using dynamic allocation, you need to configure the following properties:

1. Set **spark.dynamicAllocation.executorIdleTimeout** to 15 minutes (or the average query time).
2. Set **spark.dynamicAllocation.maxExecutors** correctly. The default value **2048** is not recommended. Otherwise, CarbonData will request the maximum number of executors.
3. For a bigger cluster, set **carbon.dynamicAllocation.schedulerTimeout** to a value ranging from 10 to 15 seconds. The default value is 5 seconds.
4. Set **carbon.scheduler.minRegisteredResourcesRatio** to a value ranging from 0.1 to 1.0. The default value is **0.8**. Block distribution can be started as long as the value of **carbon.scheduler.minRegisteredResourcesRatio** is within the range.

## 1.8.9 Why Data loading Fails During off heap?

### Question

Why Data Loading fails during off heap?

### Answer

YARN Resource Manager will consider (Java heap memory + **spark.yarn.am.memoryOverhead**) as memory limit, so during the off heap, the memory can exceed this limit. So you need to increase the memory by increasing the value of the parameter **spark.yarn.am.memoryOverhead**.

## 1.8.10 Why Do I Fail to Create a Hive Table?

### Question

Why do I fail to create a hive table?

### Answer

Creating a Hive table fails, when source table or sub query has more number of partitions. The implementation of the query requires a lot of tasks, then the number of files will be output a lot, resulting OOM in Driver.

It can be solved by using ***distribute by*** on suitable cardinality(distinct values) column in the statement of Hive table creation.

***distribute by*** clause limits number of hive table partitions. It considers cardinality of given column or **`spark.sql.shuffle.partitions`** which ever is minimal. For example, if **`spark.sql.shuffle.partitions`** is 200, but cardinality of column is 100, out files is 200, but the other 100 files are empty. So using very low cardinality column like 1 will cause data skew and will effect later query distribution.

So we suggest using the column with cardinality greater than **`spark.sql.shuffle.partitions`**. It can be greater than 2 to 3 times.

Example:

```
create table hivetable1 as select * from sourcetable1 distribute by col_age;
```

## 1.8.11 Why CarbonData tables created in V100R002C50RC1 not reflecting the privileges provided in Hive Privileges for non-owner?

### Question

Why CarbonData tables created in V100R002C50RC1 not reflecting the privileges provided in Hive Privileges for non-owner?

### Answer

The Hive ACL is implemented after the version V100R002C50RC1, hence the Hive ACL Privileges are not reflecting.

To support HIVE ACL Privileges for CarbonData tables created in V100R002C50RC1, following two ALTER TABLE commands must be executed by owner of the table.

```
ALTER TABLE $dbname.$tablename SET LOCATION '$carbon.store/$dbname/$tablename';
```

```
ALTER TABLE $dbname.$tablename SET SERDEPROPERTIES ('path'='$carbon.store/$dbname/$tablename');
```

Example:

Assume database name is 'carbondb', table name is 'carbontable', and CarbonData store location is 'hdfs://hacluster/user/hive/warehouse/carbon.store', then the commands should be executed is as follows:

```
ALTER TABLE carbondb.carbontable SET LOCATION 'hdfs://hacluster/user/hive/warehouse/carbon.store/carbondb/carbontable';
```

```
ALTER TABLE carbondb.carbontable SET SERDEPROPERTIES ('path'='hdfs://hacluster/user/hive/warehouse/carbon.store/carbondb/carbontable');
```

## 1.8.12 How Do I Logically Split Data Across Different Namespaces?

### Question

How do I logically split data across different namespaces?

### Answer

- Configuration:  
To logically split data across different namespaces, you must update the following configuration in the **core-site.xml** file of HDFS, Hive, and Spark.

#### NOTE

Changing the Hive component will change the locations of carbonstore and warehouse.

- Configuration in HDFS
  - **fs.defaultFS**: Name of the default file system. The URI mode must be set to **viewfs**. When **viewfs** is used, the permission part must be **ClusterX**.
  - **fs.viewfs.mountable.ClusterX.homedir**: Home directory base path. You can use the `getHomeDirectory()` method defined in **FileSystem/FileContext** to access the home directory.
  - **fs.viewfs.mountable.default.link.<dir\_name>**: ViewFS mount table.

Example:

```
<property>
<name>fs.defaultFS</name>
<value>viewfs://ClusterX</value>
</property>
<property>
<name>fs.viewfs.mounttable.ClusterX.link./folder1</name>
<value>hdfs://NS1/folder1</value>
</property>
<property>
<name>fs.viewfs.mounttable.ClusterX.link./folder2</name>
<value>hdfs://NS2/folder2</value>
</property>
```

- Configurations in Hive and Spark
  - fs.defaultFS**: Name of the default file system. The URI mode must be set to **viewfs**. When **viewfs** is used, the permission part must be **ClusterX**.
- Syntax:

```
LOAD DATA INPATH 'path to data' INTO TABLE table_name OPTIONS ('...');
```

 NOTE

When Spark is configured with the viewFS file system and attempts to load data from HDFS, users must specify a path such as **viewfs://** or a relative path as the file path in the **LOAD** statement.

- Example:

- Sample viewFS path:

```
LOAD DATA INPATH 'viewfs://ClusterX/dir/data.csv' INTO TABLE  
table_name OPTIONS ('...');
```

- Sample relative path:

```
LOAD DATA INPATH '/apps/input_data1.txt' INTO TABLE table_name;
```

## 1.8.13 Why Missing Privileges Exception is Reported When I Perform Drop Operation on Databases?

### Question

Why drop database cascade is throwing the following exception?

```
Error: org.apache.spark.sql.AnalysisException: Missing Privileges;(State=,code=0)
```

### Answer

This error is thrown when the owner of the database performs **drop database <database\_name> cascade** which contains tables created by other users.

## 1.8.14 Why the UPDATE Command Cannot Be Executed in Spark Shell?

### Question

Why the UPDATE command cannot be executed in Spark Shell?

### Answer

The syntax and examples provided in this document are about Beeline commands instead of Spark Shell commands.

To run the UPDATE command in Spark Shell, use the following syntax:

- Syntax 1

```
<carbon_context>.sql("UPDATE <CARBON TABLE> SET (column_name1,  
column_name2, ... column_name n) = (column1_expression ,  
column2_expression , column3_expression ... column n_expression)  
[ WHERE { <filter_condition> } ]");.show
```

- Syntax 2

```
<carbon_context>.sql("UPDATE <CARBON TABLE> SET (column_name1,  
column_name2,) = (select sourceColumn1, sourceColumn2 from  
sourceTable [ WHERE { <filter_condition> } ] ) [ WHERE  
{ <filter_condition> } ]");.show
```

Example:

If the context of CarbonData is **carbon**, run the following command:

```
carbon.sql("update carbonTable1 d set (d.column3,d.column5) = (select s.c33 ,s.c55 from sourceTable1 s where d.column1 = s.c11) where d.column1 = 'country' exists( select * from table3 o where o.c2 > 1);").show
```

## 1.8.15 How Do I Configure Unsafe Memory in CarbonData?

### Question

How do I configure unsafe memory in CarbonData?

### Answer

In the Spark configuration, the value of **spark.yarn.executor.memoryOverhead** must be greater than the sum of (**sort.inmemory.size.inmb + Netty offheapmemory required**), or the sum of (**carbon.unsafe.working.memory.in.mb + carbon.sort.inmemory.storage.size.in.mb + Netty offheapmemory required**). Otherwise, if off-heap access exceeds the configured executor memory, Yarn may stop the executor.

If **spark.shuffle.io.preferDirectBufs** is set to **true**, the netty transfer service in Spark takes off some heap memory (around 384 MB or 0.1 x executor memory) from **spark.yarn.executor.memoryOverhead**.

For details, see [Configuring Executor Off-Heap Memory](#).

## 1.8.16 Why Exception Occurs in CarbonData When Disk Space Quota is Set for Storage Directory in HDFS?

### Question

Why exception occurs in CarbonData when Disk Space Quota is set for the storage directory in HDFS?

### Answer

The data will be written to HDFS when you during create table, load table, update table, and so on. If the configured HDFS directory does not have sufficient disk space quota, then the operation will fail and throw following exception.

```
org.apache.hadoop.hdfs.protocol.DSQuotaExceededException:  
The DiskSpace quota of /user/tenant is exceeded:  
quota = 314572800 B = 300 MB but disk space consumed = 402653184 B = 384 MB at  
org.apache.hadoop.hdfs.server.namenode.DirectoryWithQuotaFeature.verifyStoragespaceQuota(DirectoryWith  
hQuotaFeature.java:211) at  
org.apache.hadoop.hdfs.server.namenode.DirectoryWithQuotaFeature.verifyQuota(DirectoryWithQuotaFeatu  
re.java:239) at  
org.apache.hadoop.hdfs.server.namenode.FSDirectory.verifyQuota(FSDirectory.java:941) at  
org.apache.hadoop.hdfs.server.namenode.FSDirectory.updateCount(FSDirectory.java:745)
```

If such exception occurs, configure a sufficient disk space quota for the tenant.

For example:

If the HDFS replication factor is 3 and HDFS default block size is 128 MB, then at least 384 MB (no. of block x block\_size x replication\_factor of the schema file = 1 x 128 x 3 = 384 MB) disk space quota is required to write a table schema file to HDFS.

 NOTE

In case of fact files, as the default block size is 1024 MB, the minimum space required is 3072 MB per fact file for data load.

## 1.8.17 Why Does Data Query or Loading Fail and "org.apache.carbondata.core.memory.MemoryException: Not enough memory" Is Displayed?

### Question

Why does data query or loading fail and "org.apache.carbondata.core.memory.MemoryException: Not enough memory" is displayed?

### Answer

This exception is thrown when the out-of-heap memory required for data query and loading in the executor is insufficient.

In this case, increase the values of **carbon.unsafe.working.memory.in.mb** and **spark.yarn.executor.memoryOverhead**.

For details, see [How Do I Configure Unsafe Memory in CarbonData?](#)

The memory is shared by data query and loading. Therefore, if the loading and query operations need to be performed at the same time, you are advised to set **carbon.unsafe.working.memory.in.mb** and **spark.yarn.executor.memoryOverhead** to a value greater than 2,048 MB.

The following formula can be used for estimation:

Memory required for data loading:

$\text{carbon.number.of.cores.while.loading [default value is 6] x Number of tables to load in parallel x offheap.sort.chunk.size.inmb [default value is 64 MB] + carbon.blockletgroup.size.in.mb [default value is 64 MB] + Current compaction ratio [64 MB/3.5]}$

= Around 900 MB per table

Memory required for data query:

$(\text{SPARK\_EXECUTOR\_INSTANCES. [default value is 2] x (carbon.blockletgroup.size.in.mb [default value: 64 MB] + carbon.blockletgroup.size.in.mb [default value = 64 MB x 3.5) x Number of cores per executor [default value: 1]})$

= ~ 600 MB

# 2 Using ClickHouse

---

## 2.1 Using ClickHouse from Scratch

ClickHouse is a column-based database oriented to online analysis and processing. It supports SQL query and provides good query performance. The aggregation analysis and query performance based on large and wide tables is excellent, which is one order of magnitude faster than other analytical databases.

### Prerequisites

You have installed the client, for example, in the `/opt/hadoopclient` directory. The client directory in the following operations is only an example. Change it to the actual installation directory. Before using the client, download and update the client configuration file, and ensure that the active management node of Manager is available.

### Procedure

- Step 1** Log in to the node where the client is installed as the client installation user.
- Step 2** Run the following command to go to the client installation directory:  
**cd /opt/hadoopclient**
- Step 3** Run the following command to configure environment variables:  
**source bigdata\_env**
- Step 4** If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the current user. The current user must have the permission to create ClickHouse tables. For details about how to bind a role to the user, see [ClickHouse User and Permission Management](#). If Kerberos authentication is disabled for the current cluster, skip this step.  
**kinit *Component service user***  
Example: **kinit clickhouseuser**
- Step 5** Run the client command of the ClickHouse component.

Run the **clickhouse -h** command to view the command help of ClickHouse.

The command output is as follows:

```
Use one of the following commands:
clickhouse local [args]
clickhouse client [args]
clickhouse benchmark [args]
clickhouse server [args]
clickhouse performance-test [args]
clickhouse extract-from-config [args]
clickhouse compressor [args]
clickhouse format [args]
clickhouse copier [args]
clickhouse obfuscator [args]
...
```

For details about how to use the command, see <https://clickhouse.tech/docs/en/operations/>.

The following table describes the parameters when the **clickhouse client** command is used to connect to the ClickHouse server.

**Table 2-1** Parameters of the clickhouse client command

Parameter	Description
--host	Host name of the server. The default value is <b>localhost</b> . You can use the host name or IP address of the node where the ClickHouse instance is located.
--port	Port for connection. <ul style="list-style-type: none"> <li>If the SSL security connection is used, the default port number is <b>9440</b>, the parameter <b>--secure</b> must be carried. For details about the port number, search for the <b>tcp_port_secure</b> parameter in the ClickHouseServer instance configuration.</li> <li>If non-SSL security connection is used, the default port number is <b>9000</b>, the parameter <b>--secure</b> does not need to be carried. For details about the port number, search for the <b>tcp_port</b> parameter in the ClickHouseServer instance configuration.</li> </ul>
--user	Username. <p>You can create the user on Manager and bind a role to the user. For details, see <a href="#">ClickHouse User and Permission Management</a>.</p> <ul style="list-style-type: none"> <li>If Kerberos authentication is enabled for the current cluster and the user authentication is successful, you do not need to carry the <b>--user</b> and <b>--password</b> parameters when logging in to the client as the authenticated user. You must create a user with this name on Manager because there is no default user in the Kerberos cluster scenario.</li> <li>If Kerberos authentication is not enabled for the current cluster, you can specify a user and its password created on Manager when logging in to the client. If the user is used for the first time, you need to log in to Manager to change the password. If the user and password parameters are not carried, user <b>default</b> is used for login by default.</li> </ul>

Parameter	Description
--password	Password. The default password is an empty string. This parameter is used together with the --user parameter. You can set a password when creating a user on Manager.
--query	Query to process when using non-interactive mode.
--database	Current default database. The default value is <b>default</b> , which is the default configuration on the server.
--multiline	If this parameter is specified, multiline queries are allowed. ( <b>Enter</b> only indicates line feed and does not indicate that the query statement is complete.)
--multiquery	If this parameter is specified, multiple queries separated with semicolons (;) can be processed. This parameter is valid only in non-interactive mode.
--format	Specified default format used to output the result.
--vertical	If this parameter is specified, the result is output in vertical format by default. In this format, each value is printed on a separate line, which helps to display a wide table.
--time	If this parameter is specified, the query execution time is printed to <b>stderr</b> in non-interactive mode.
--stacktrace	If this parameter is specified, stack trace information will be printed when an exception occurs.
--config-file	Name of the configuration file.
--secure	If this parameter is specified, the server will be connected in SSL mode.
--history_file	Path of files that record command history.
--param_<name>	Query with parameters. Pass values from the client to the server. For details, see <a href="https://clickhouse.tech/docs/en/interfaces/cli/#cli-queries-with-parameters">https://clickhouse.tech/docs/en/interfaces/cli/#cli-queries-with-parameters</a> .

- Using SSL for login when Kerberos authentication is disabled for the current cluster:

**clickhouse client --host** *IP address of the ClickHouse instance* **--user** *Username* **--password** *Password* **--port** 9000

- Using SSL for login when Kerberos authentication is enabled for the current cluster:

You must create a user on Manager because there is no default user. For details, see [ClickHouse User and Permission Management](#).

After the user authentication is successful, you do not need to carry the **--user** and **--password** parameters when logging in to the client as the authenticated user.

```
clickhouse client --host IP address of the ClickHouse instance --port 9440 --secure
```

 NOTE

You can log in to FusionInsight Manager and choose **Cluster > Services > ClickHouse > Instance** to obtain the service IP address of the ClickHouseServer instance.

----End

## 2.2 Common ClickHouse SQL Syntax

### 2.2.1 CREATE DATABASE: Creating a Database

This section describes the basic syntax and usage of the SQL statement for creating a ClickHouse database.

#### Basic Syntax

```
CREATE DATABASE [IF NOT EXISTS] Database_name [ON CLUSTER ClickHouse cluster name]
```

*ClickHouse cluster name* is **default\_cluster** by default.

 NOTE

The syntax **ON CLUSTER *ClickHouse cluster name*** enables the Data Definition Language (DDL) statement to be executed on all instances in the cluster at a time. You can run the following statement to obtain the cluster name from the **cluster** field:

```
select cluster,shard_num,replica_num,host_name from system.clusters;
```

#### Example

```
-- Create a database named test.  
CREATE DATABASE test ON CLUSTER default_cluster;  
-- After the creation is successful, run the query command for verification.  
show databases;
```

```
name  
default  
system  
test
```

### 2.2.2 CREATE TABLE: Creating a Table

This section describes the basic syntax and usage of the SQL statement for creating a ClickHouse table.

#### Basic Syntax

- Method 1: Creating a table named **table\_name** in the specified **database\_name** database.

If the table creation statement does not contain **database\_name**, the name of the database selected during client login is used by default.

```
CREATE TABLE [IF NOT EXISTS] [database_name.]table_name [ON CLUSTER ClickHouse cluster name]
```

```
(
  name1 [type1] [DEFAULT|MATERIALIZED|ALIAS expr1],
  name2 [type2] [DEFAULT|MATERIALIZED|ALIAS expr2],
  ...
) ENGINE = engine_name()
[PARTITION BY expr_list]
[ORDER BY expr_list]
```

 **CAUTION**

You are advised to use **PARTITION BY** to create table partitions when creating a ClickHouse table. The ClickHouse data migration tool migrates data based on table partitions. If you do not use **PARTITION BY** to create table partitions during table creation, the table data cannot be migrated on the GUI in [Using the ClickHouse Data Migration Tool](#).

- Method 2: Creating a table with the same structure as **database\_name2.table\_name2** and specifying a different table engine for the table  
If no table engine is specified, the created table uses the same table engine as **database\_name2.table\_name2**.  
**CREATE TABLE [IF NOT EXISTS] [database\_name.]table\_name AS [database\_name2.]table\_name2 [ENGINE = engine\_name]**
- Method 3: Using the specified engine to create a table with the same structure as the result of the **SELECT** clause and filling it with the result of the **SELECT** clause  
**CREATE TABLE [IF NOT EXISTS] [database\_name.]table\_name ENGINE = engine\_name AS SELECT ...**

## Example

```
-- Create a table named test in the default database and default_cluster cluster.
CREATE TABLE default.test ON CLUSTER default_cluster
(
  `EventDate` DateTime,
  `id` UInt64
)
ENGINE = ReplicatedMergeTree('/clickhouse/tables/{shard}/default/test', '{replica}')
PARTITION BY toYYYYMM(EventDate)
ORDER BY id
```

## 2.2.3 INSERT INTO: Inserting Data into a Table

This section describes the basic syntax and usage of the SQL statement for inserting data to a table in ClickHouse.

### Basic Syntax

- Method 1: Inserting data in standard format  
**INSERT INTO [database\_name.]table [(c1, c2, c3)] VALUES (v11, v12, v13), (v21, v22, v23), ...**

- Method 2: Using the **SELECT** result to insert data  
**INSERT INTO** *[database\_name.]table* [(c1, c2, c3)] **SELECT** ...

## Example

```
-- Insert data into the test2 table.
insert into test2 (id, name) values (1, 'abc'), (2, 'bbbb');
-- Query data in the test2 table.
select * from test2;
```

id	name
1	abc
2	bbbb

## 2.2.4 SELECT: Querying Table Data

This section describes the basic syntax and usage of the SQL statement for querying table data in ClickHouse.

### Basic Syntax

```
SELECT [DISTINCT] expr_list
[FROM [database_name.]table | (subquery) | table_function] [FINAL]
[SAMPLE sample_coeff]
[ARRAY JOIN ...]
[GLOBAL] [ANY|ALL|ASOF] [INNER|LEFT|RIGHT|FULL|CROSS] [OUTER|SEMI|
ANTI] JOIN (subquery)|table (ON <expr_list>)|(USING <column_list>)
[PREWHERE expr]
[WHERE expr]
[GROUP BY expr_list] [WITH TOTALS]
[HAVING expr]
[ORDER BY expr_list] [WITH FILL] [FROM expr] [TO expr] [STEP expr]
[LIMIT [offset_value, ]n BY columns]
[LIMIT [n, ]m] [WITH TIES]
[UNION ALL ...]
[INTO OUTFILE filename]
[FORMAT format]
```

## Example

```
-- View ClickHouse cluster information.
select * from system.clusters;
-- View the macros set for the current node.
select * from system.macros;
-- Check the database capacity.
select
sum(rows) as "Total number of rows",
formatReadableSize(sum(data_uncompressed_bytes)) as "Original size",
formatReadableSize(sum(data_compressed_bytes)) as "Compression size",
```

```

round(sum(data_compressed_bytes) / sum(data_uncompressed_bytes) * 100,
0) "Compression rate"
from system.parts;
-- Query the capacity of the test table. Add or modify the where clause based on the site
requirements.
select
sum(rows) as "Total number of rows",
formatReadableSize(sum(data_uncompressed_bytes)) as "Original size",
formatReadableSize(sum(data_compressed_bytes)) as "Compression size",
round(sum(data_compressed_bytes) / sum(data_uncompressed_bytes) * 100,
0) "Compression rate"
from system.parts
where table in ('test')
and partition like '2020-11-%'
group by table;

```

## 2.2.5 ALTER TABLE: Modifying a Table Structure

This section describes the basic syntax and usage of the SQL statement for modifying a table structure in ClickHouse.

### Basic Syntax

**ALTER TABLE** [*database\_name*].*name* [ON CLUSTER *cluster*] **ADD|DROP|CLEAR|COMMENT|MODIFY COLUMN** ...

#### NOTE

**ALTER** supports only MergeTree, Merge, and Distributed engine tables.

### Example

```

-- Add the test01 column to the t1 table.
ALTER TABLE t1 ADD COLUMN test01 String DEFAULT 'defaultvalue';
-- Query the modified table t1.
desc t1

```

name	type	default_type	default_expression	comment	codec_expression
ttl_expression					
id	UInt8				
name	String				
address	String				
test01	String	DEFAULT	'defaultvalue'		

```

-- Change the type of the name column in the t1 table to UInt8.
ALTER TABLE t1 MODIFY COLUMN name UInt8;
-- Query the modified table t1.
desc t1

```

name	type	default_type	default_expression	comment	codec_expression
ttl_expression					
id	UInt8				
name	UInt8				
address	String				
test01	String	DEFAULT	'defaultvalue'		

```

-- Delete the test01 column from the t1 table.
ALTER TABLE t1 DROP COLUMN test01;
-- Query the modified table t1.
desc t1

```

name	type	default_type	default_expression	comment	codec_expression
ttl_expression					
id	UInt8				
name	UInt8				
address	String				

## 2.2.6 DESC: Querying a Table Structure

This section describes the basic syntax and usage of the SQL statement for querying a table structure in ClickHouse.

### Basic Syntax

```
DESC|DESCRIBE TABLE [database_name.]table [INTO OUTFILE filename]  
[FORMAT format]
```

### Example

```
-- Query the t1 table structure.  
desc t1;  
+-----+-----+-----+-----+-----+-----+-----+  
| name | type | default_type | default_expression | comment | codec_expression | ttl_expression |  
+-----+-----+-----+-----+-----+-----+-----+  
| id   | UInt8 |               |                   |         |                   |               |  
| name | UInt8 |               |                   |         |                   |               |  
| address | String |               |                   |         |                   |               |  
+-----+-----+-----+-----+-----+-----+-----+
```

## 2.2.7 DROP: Deleting a Table

This section describes the basic syntax and usage of the SQL statement for deleting a ClickHouse table.

### Basic Syntax

```
DROP [TEMPORARY] TABLE [IF EXISTS] [database_name.]name [ON CLUSTER  
cluster]
```

### Example

```
-- Delete the t1 table.  
drop t1;
```

## 2.2.8 SHOW: Displaying Information About Databases and Tables

This section describes the basic syntax and usage of the SQL statement for displaying information about databases and tables in ClickHouse.

### Basic Syntax

```
show databases
```

```
show tables
```

### Example

```
-- Query database information.  
show databases;  
+-----+  
| name |  
| default |  
| system |  
| test |  
+-----+  
-- Query table information.
```

```
show tables;
+----+
| name |
+----+
| t1   |
+----+
| test |
+----+
| test2|
+----+
| test5|
+----+
```

## 2.2.9 Importing and Exporting File Data

This section describes the basic syntax and usage of the SQL statement for importing and exporting file data in ClickHouse.

- Importing data in CSV format

```
clickhouse client --host Host name or IP address of the ClickHouse instance
--database Database name --port Port number --secure --
format_csv_delimiter="CSV file delimiter" --query="INSERT INTO Table
name FORMAT CSV" < Host path where the CSV file is stored
```

Example

```
clickhouse client --host 10.5.208.5 --database testdb --port 21427 --secure --format_csv_delimiter=","
--query="INSERT INTO testdb.csv_table FORMAT CSV" < /opt/data.csv
```

You need to create a table in advance.

- Exporting data in CSV format

```
clickhouse client --host Host name or IP address of the ClickHouse instance
--database Database name --port Port number -m --secure --query="SELECT
* FROM Table name" > CSV file export path
```

Example

```
clickhouse client --host 10.5.208.5 --database testdb --port 21427 -m --secure --query="SELECT *
FROM test_table" > /opt/test.csv
```

- Importing data in Parquet format

```
cat Parquet file | clickhouse client --host Host name or IP address of the
ClickHouse instance --database Database name --port Port number -m --
secure --query="INSERT INTO Table name FORMAT Parquet"
```

Example

```
cat /opt/student.parquet | clickhouse client --host 10.5.208.5 --database testdb --port 21427 -m --
secure --query="INSERT INTO parquet_tab001 FORMAT Parquet"
```

- Exporting data in Parquet format

```
clickhouse client --host Host name or IP address of the ClickHouse instance
--database Database name --port Port number -m --secure --query="select
* from Table name FORMAT Parquet" > Parquet file export path
```

Example

```
clickhouse client --host 10.5.208.5 --database testdb --port 21427 -m --secure --query="select * from
test_table FORMAT Parquet" > /opt/student.parquet
```

- Importing data in ORC format

```
cat ORC file path | clickhouse client --host Host name or IP address of the
ClickHouse instance --database Database name --port Port number -m --
secure --query="INSERT INTO Table name FORMAT ORC"
```

Example

```
cat /opt/student.orc | clickhouse client --host 10.5.208.5 --database testdb --port 21427 -m --secure --
query="INSERT INTO orc_tab001 FORMAT ORC"
# Data in the ORC file can be exported from HDFS. For example:
hdfs dfs -cat /user/hive/warehouse/hivedb.db/emp_orc/000000_0_copy_1 | clickhouse client --host
10.5.208.5 --database testdb --port 21427 -m --secure --query="INSERT INTO orc_tab001 FORMAT
ORC"
```

- Exporting data in ORC format  
**clickhouse client --host** *Host name or IP address of the ClickHouse instance* **--database** *Database name* **--port** *Port number* **-m --secure --query="select \* from Table name FORMAT ORC" > ORC file export path**  
Example  

```
clickhouse client --host 10.5.208.5 --database testdb --port 21427 -m --secure --query="select * from csv_tab001 FORMAT ORC" > /opt/student.orc
```
- Importing data in JSON format  
**INSERT INTO Table name FORMAT JSONEachRow** *JSON string 1* *JSON string 2*  
Example  

```
INSERT INTO test_table001 FORMAT JSONEachRow {"PageViews":5, "UserID":"4324182021466249494", "Duration":146,"Sign":-1} {"UserID":"4324182021466249494","PageViews":6,"Duration":185,"Sign":1}
```
- Exporting data in JSON format  
**clickhouse client --host** *Host name or IP address of the ClickHouse instance* **--database** *Database name* **--port** *Port number* **-m --secure --query="SELECT \* FROM Table name FORMAT JSON|JSONEachRow|JSONCompact|..." > JSON file export path**  
Example  

```
# Export JSON file.
clickhouse client --host 10.5.208.5 --database testdb --port 21427 -m --secure --query="SELECT * FROM test_table FORMAT JSON" > /opt/test.json

# Export json(JSONEachRow).
clickhouse client --host 10.5.208.5 --database testdb --port 21427 -m --secure --query="SELECT * FROM test_table FORMAT JSONEachRow" > /opt/test_jsoneachrow.json

# Export json(JSONCompact).
clickhouse client --host 10.5.208.5 --database testdb --port 21427 -m --secure --query="SELECT * FROM test_table FORMAT JSONCompact" > /opt/test_jsoncompact.json
```

## 2.3 User Management and Authentication

### 2.3.1 ClickHouse User and Permission Management

#### User Permission Model

ClickHouse user permission management enables unified management of users, roles, and permissions on each ClickHouse instance in the cluster. You can use the permission management module of the Manager UI to create users, create roles, and bind the ClickHouse access permissions. User permissions are controlled by binding roles to users.

Resource management: [Table 2-2](#) lists the resources supported by ClickHouse permission management.

Resource permissions: [Table 2-3](#) lists the resource permissions supported by ClickHouse.

**Table 2-2** Permission management objects supported by ClickHouse

Resource	Integration	Remarks
Database	Yes (level 1)	-
Table	Yes (level 2)	-
View	Yes (level 2)	Same as tables

**Table 2-3** Resource permission list

Resource	Available Permission	Remarks
Database	CREATE	CREATE DATABASE/TABLE/VIEW/ DICTIONARY
Table/View	SELECT/INSERT	-

## Prerequisites

- The ClickHouse and Zookeeper services are running properly.
- When creating a database or table in the cluster, the **ON CLUSTER** statement is used to ensure that the metadata of the database and table on each ClickHouse node is the same.

### NOTE

After the permission is granted, it takes about 1 minute for the permission to take effect.

## Adding the ClickHouse Role

**Step 1** Log in to Manager and choose **System > Permission > Role**. On the **Role** page, click **Create Role**.

**Step 2** On the **Create Role** page, specify **Role Name**. In the **Configure Resource Permission** area, click the cluster name. On the service list page that is displayed, click the ClickHouse service.

Determine whether to create a role with ClickHouse administrator permission based on service requirements.

### NOTE

- The ClickHouse administrator has all the database operation permissions except the permissions to create, delete, and modify users and roles.
- Only the built-in user **clickhouse** of ClickHouse has the permission to manage users and roles.
- If yes, go to [Step 3](#).
- If no, go to [Step 4](#).

**Step 3** Select **SUPER\_USER\_GROUP** and click **OK**.

**Step 4** Click **ClickHouse Scope**. The ClickHouse database resource list is displayed. If you select **create**, the role has the create permission on the database.

Determine whether to grant the permission based on the service requirements.

- If yes, click **OK**.
- If no, go to [Step 5](#).

**Step 5** Click the resource name and select the *Database resource name to be operated*. On the displayed page, select **read** (SELECT permission) or **write** (INSERT permission) based on service requirements, and click **OK**.

----End

## Adding a User and Binding the ClickHouse Role to the User

**Step 1** Log in to Manager and choose **System > Permission > User** and click **Create**.

**Step 2** Select **Human-Machine** for **User Type** and set **Password** and **Confirm Password** to the password of the user.

### NOTE

- Username: The username cannot contain hyphens (-). Otherwise, the authentication will fail.
- Password: The password cannot contain special characters \$, ., and #. Otherwise, the authentication will fail.

**Step 3** In the **Role** area, click **Add**. In the displayed dialog box, select a role with the ClickHouse permission and click **OK** to add the role. Then, click **OK**.

**Step 4** Log in to the node where the ClickHouse client is installed and use the new username and password to connect to the ClickHouse service.

1. Run the following command to go to the client installation directory. For example, the client installation directory is `/opt/Bigdata/client`.

```
cd /opt/client
```

2. Run the following command to configure environment variables:

```
source bigdata_env
```

3. If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the current user. The user must have the permission to create ClickHouse tables. Therefore, you need to bind the corresponding role to the user. For details, see [ClickHouse User and Permission Management](#). If Kerberos authentication is disabled for the current cluster, skip this step.

```
kinit Component service user
```

Example: `kinit clickhouseuser`

4. Log in to the system as the new user.

```
clickhouse client --host IP address of the ClickHouse instance --user User  
added in Step 1 --password User password set in Step 2 --port ClickHouse  
port number
```

----End

## Granting Permissions Using the Client in Abnormal Scenarios

By default, the table metadata on each node of the ClickHouse cluster is the same. Therefore, the table information on a random ClickHouse node is collected on the permission management page of Manager. If the **ON CLUSTER** statement is not used when databases or tables are created on some nodes, the resource may fail to be displayed during permission management, and permissions may not be granted to the resource. To grant permissions on the local table on a single ClickHouse node, perform the following steps on the background client.

### NOTE

The following operations are performed based on the obtained roles, database or table names, and IP addresses of the node where the corresponding ClickHouseServer instance is located.

- You can log in to FusionInsight Manager and choose **Cluster > Services > ClickHouse > Instance** to obtain the service IP address of the ClickHouseServer instance.
- System domain name: The default value is **hadoop.com**. Log in to FusionInsight Manager and choose **System > Permission > Domain and Mutual Trust**. The value of **Local Domain** is the system domain name. Change the letters to lowercase letters when running a command.

**Step 1** Log in to the node where the ClickHouseServer instance is located as user **root**.

**Step 2** Run the following command to obtain the path of the **clickhouse.keytab** file:

```
ls ${BIGDATA_HOME}/FusionInsight_ClickHouse_*/install/FusionInsight-ClickHouse-*/clickhouse/keytab/clickhouse.keytab
```

**Step 3** Log in to the node where the client is installed as the client installation user.

**Step 4** Run the following command to go to the client installation directory. For example, the client installation directory is `/opt/Bigdata/client`.

```
cd /opt/client
```

**Step 5** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 6** Run the following command to connect to the ClickHouseServer instance:

If Kerberos authentication is enabled for the current cluster, run the following command:

```
clickhouse client --host IP address of the node where the ClickHouseServer instance is located --user clickhouse/hadoop.<System domain name> --password clickhouse.keytab path obtained in Step 2 --port ClickHouse port number --secure
```

If Kerberos authentication is disabled for the current cluster, run the following command:

```
clickhouse client --host IP address of the node where the ClickHouseServer instance is located --user clickhouse --port ClickHouse port number
```

**Step 7** Run the following statement to grant permissions to a database:

In the syntax for granting permissions, *DATABASE* indicates the name of the target database, and *role* indicates the target role.

```
GRANT [ON CLUSTER cluster_name] privilege ON {DATABASE|TABLE} TO {user / role}
```

For example, grant user **testuser** the CREATE permission on database **t2**:

```
GRANT CREATE ON m2 to testuser;
```

**Step 8** Run the following commands to grant permissions on the table or view. In the following command, *TABLE* indicates the name of the table or view to be operated, and *user* indicates the role to be operated.

Run the following command to grant the query permission on tables in a database:

```
GRANT SELECT ON TABLE TO user;
```

Run the following command to grant the write permission on tables in a database:

```
GRANT INSERT ON TABLE TO user;
```

 NOTE

For details about ClickHouse **GRANT** operations and permission description, visit <https://clickhouse.tech/docs/en/sql-reference/statements/grant/>.

**Step 9** Run the following command to exit the client:

```
quit;
```

```
----End
```

## 2.3.2 Setting the ClickHouse Username and Password

After a ClickHouse cluster is created, you can use the ClickHouse client to connect to the ClickHouse server. The default username is **default**.

This section describes how to set ClickHouse username and password after a ClickHouse cluster is successfully created.

 NOTE

**default** is the default internal user of ClickHouse. It is an ClickHouse administrator user available only in normal mode (kerberos authentication disabled).

### Setting the ClickHouse Username and Password

**Step 1** Log in to Manager and choose **Cluster > Services > ClickHouse**. Click the **Configurations** tab and then **All Configurations**.

**Step 2** Search for the **users.default.password** parameter in the search box and change its password, as shown in [Figure 2-1](#).

**Figure 2-1** Changing the default user password

Parameter	Value	Descripti				
ClickHouse						
users.default.password	<table border="1"><tr><td>Password</td><td>Confirm Password</td></tr><tr><td><input type="password" value="*****"/></td><td><input type="password" value="*****"/></td></tr></table>	Password	Confirm Password	<input type="password" value="*****"/>	<input type="password" value="*****"/>	>>[Des
Password	Confirm Password					
<input type="password" value="*****"/>	<input type="password" value="*****"/>					

**Step 3** Log in to the node where the client is installed and run the following command to switch to the client installation directory.

```
cd Cluster client installation directory
```

**Step 4** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 5** Log in to ClickHouse using the new password.

```
clickhouse client --host IP address of the ClickHouse instance --user default --password xxx
```

 **NOTE**

To obtain the service IP address of the ClickHouse instance, choose **Components > ClickHouse > Instances** on the cluster details page.

----End

## 2.4 ClickHouse Table Engine Overview

### Background

Table engines play a key role in ClickHouse to determine:

- Where to write and read data
- Supported query modes
- Whether concurrent data access is supported
- Whether indexes can be used
- Whether multi-thread requests can be executed
- Parameters used for data replication

This section describes MergeTree and Distributed engines, which are the most important and frequently used ClickHouse table engines.

For details about other table engines, visit <https://clickhouse.tech/docs/en/engines/table-engines>.

### MergeTree Family

Engines of the MergeTree family are the most universal and functional table engines for high-load tasks. They have the following key features:

- Data is stored by partition and block based on partitioning keys.
- Data index is sorted based on primary keys and the **ORDER BY** sorting keys.
- Data replication is supported by table engines prefixed with Replicated.
- Data sampling is supported.

When data is written, a table with this type of engine divides data into different folders based on the partitioning key. Each column of data in the folder is an independent file. A file that records serialized index sorting is created. This

structure reduces the volume of data to be retrieved during data reading, greatly improving query efficiency.

- MergeTree

**Syntax for creating a table:**

```
CREATE TABLE [IF NOT EXISTS] [db.]table_name [ON CLUSTER cluster]
(
  name1 [type1] [DEFAULT|MATERIALIZED|ALIAS expr1] [TTL expr1],
  name2 [type2] [DEFAULT|MATERIALIZED|ALIAS expr2] [TTL expr2],
  ...
  INDEX index_name1 expr1 TYPE type1(...) GRANULARITY value1,
  INDEX index_name2 expr2 TYPE type2(...) GRANULARITY value2
) ENGINE = MergeTree()
ORDER BY expr
[PARTITION BY expr]
[PRIMARY KEY expr]
[SAMPLE BY expr]
[TTL expr [DELETE|TO DISK 'xxx'|TO VOLUME 'xxx'], ...]
[SETTINGS name=value, ...]
```

**Example:**

```
CREATE TABLE default.test (
  name1 DateTime,
  name2 String,
  name3 String,
  name4 String,
  name5 Date,
  ...
) ENGINE = MergeTree()
PARTITION BY toYYYYMM(name5)
ORDER BY (name1, name2)
SETTINGS index_granularity = 8192
```

Parameters in the example are described as follows:

- **ENGINE = MergeTree()**: specifies the MergeTree engine.
- **PARTITION BY toYYYYMM(name4)**: specifies the partition. The sample data is partitioned by month, and a folder is created for each month.
- **ORDER BY**: specifies the sorting field. A multi-field index can be sorted. If the first field is the same, the second field is used for sorting, and so on.
- **index\_granularity = 8192**: specifies the index granularity. One index value is recorded for every 8,192 data records.

If the data to be queried exists in a partition or sorting field, the data query time can be greatly reduced.

- ReplacingMergeTree

Different from MergeTree, ReplacingMergeTree deletes duplicate entries with the same sorting key. ReplacingMergeTree is suitable for clearing duplicate data to save space, but it does not guarantee the absence of duplicate data. Generally, it is not recommended.

**Syntax for creating a table:**

```
CREATE TABLE [IF NOT EXISTS] [db.]table_name [ON CLUSTER cluster]
(
  name1 [type1] [DEFAULT|MATERIALIZED|ALIAS expr1],
  name2 [type2] [DEFAULT|MATERIALIZED|ALIAS expr2],
  ...
) ENGINE = ReplacingMergeTree([ver])
[PARTITION BY expr]
[ORDER BY expr]
[SAMPLE BY expr]
[SETTINGS name=value, ...]
```

- **SummingMergeTree**

When merging data parts in SummingMergeTree tables, ClickHouse merges all rows with the same primary key into one row that contains summed values for the columns with the numeric data type. If the primary key is composed in a way that a single key value corresponds to large number of rows, storage volume can be significantly reduced and the data query speed can be accelerated.

**Syntax for creating a table:**

```
CREATE TABLE [IF NOT EXISTS] [db.]table_name [ON CLUSTER cluster]
(
  name1 [type1] [DEFAULT|MATERIALIZED|ALIAS expr1],
  name2 [type2] [DEFAULT|MATERIALIZED|ALIAS expr2],
  ...
) ENGINE = SummingMergeTree([columns])
[PARTITION BY expr]
[ORDER BY expr]
[SAMPLE BY expr]
[SETTINGS name=value, ...]
```

**Example:**

Create a SummingMergeTree table named **testTable**.

```
CREATE TABLE testTable
(
  id UInt32,
  value UInt32
)
ENGINE = SummingMergeTree()
ORDER BY id
```

Insert data into the table.

```
INSERT INTO testTable Values(5,9),(5,3),(4,6),(1,2),(2,5),(1,4),(3,8);
INSERT INTO testTable Values(88,5),(5,5),(3,7),(3,5),(1,6),(2,6),(4,7),(4,6),(43,5),(5,9),(3,6);
```

Query all data in unmerged parts.

```
SELECT * FROM testTable
```

id	value
1	6
2	5
3	8
4	6
5	12

id	value
1	6
2	6
3	18
4	13
5	14
43	5
88	5

If ClickHouse has not summed up all rows and you need to aggregate data by ID, use the **sum** function and **GROUP BY** statement.

```
SELECT id, sum(value) FROM testTable GROUP BY id
```

id	sum(value)
4	19
3	26
88	5
2	11
5	26
1	12
43	5

Merge rows manually.

```
OPTIMIZE TABLE testTable
```

Query data in the **testTable** table again.

```
SELECT * FROM testTable
```

id	value
1	12
2	11
3	26
4	19
5	26
43	5
88	5

SummingMergeTree uses the **ORDER BY** sorting keys as the condition keys to aggregate data. That is, if sorting keys are the same, data records are merged into one and the specified merged fields are aggregated.

Data is pre-aggregated only when merging is executed in the background, and the merging execution time cannot be predicted. Therefore, it is possible that some data has been pre-aggregated and some data has not been aggregated. Therefore, the **GROUP BY** statement must be used during aggregation.

- **AggregatingMergeTree**

AggregatingMergeTree is a pre-aggregation engine used to improve aggregation performance. When merging partitions, the AggregatingMergeTree engine aggregates data based on predefined conditions, calculates data based on predefined aggregate functions, and saves the data in binary format to tables.

**Syntax for creating a table:**

```
CREATE TABLE [IF NOT EXISTS] [db.]table_name [ON CLUSTER cluster]
(
  name1 [type1] [DEFAULT|MATERIALIZED|ALIAS expr1],
  name2 [type2] [DEFAULT|MATERIALIZED|ALIAS expr2],
  ...
) ENGINE = AggregatingMergeTree()
[PARTITION BY expr]
[ORDER BY expr]
[SAMPLE BY expr]
[TTL expr]
[SETTINGS name=value, ...]
```

**Example:**

You do not need to set the AggregatingMergeTree parameter separately. When partitions are merged, data in each partition is aggregated based on the **ORDER BY** sorting key. You can set the aggregate functions to be used and column fields to be calculated by defining the AggregateFunction type, as shown in the following example:

```
create table test_table (
  name1 String,
  name2 String,
  name3 AggregateFunction(uniq,String),
  name4 AggregateFunction(sum,Int),
  name5 DateTime
) ENGINE = AggregatingMergeTree()
PARTITION BY toYYYYMM(name5)
ORDER BY (name1,name2)
PRIMARY KEY name1;
```

When data of the AggregateFunction type is written or queried, the **\*state** and **\*merge** functions need to be called. The asterisk (\*) indicates the

aggregate functions used for defining the field type. For example, the **uniq** and **sum** functions are specified for the **name3** and **name4** fields defined in the **test\_table**, respectively. Therefore, you need to call the **uniqState** and **sumState** functions and run the **INSERT** and **SELECT** statements when writing data into the table.

```
insert into test_table select '8','test1',uniqState('name1'),sumState(toInt32(100)),2021-04-30 17:18:00;
insert into test_table select '8','test1',uniqState('name1'),sumState(toInt32(200)),2021-04-30 17:18:00;
```

When querying data, you need to call the corresponding functions **uniqMerge** and **sumMerge**.

```
select name1,name2,uniqMerge(name3),sumMerge(name4) from test_table group by name1,name2;
┌ name1 ─┬ name2 ─┬ uniqMerge(name3) ─┬ sumMerge(name4) ─┐
│ 8      │ test1  │ 1                    │ 300              │
└────────┴────────┴──────────────────┴──────────────────┘
```

AggregatingMergeTree is more commonly used with materialized views, which are query views of other data tables at the upper layer. For details, visit <https://clickhouse.tech/docs/en/engines/table-engines/mergetree-family/aggregatingmergetree/>

- CollapsingMergeTree

CollapsingMergeTree defines a **Sign** field to record status of data rows. If **Sign** is **1**, the data in this row is valid. If **Sign** is **-1**, the data in this row needs to be deleted.

**Syntax for creating a table:**

```
CREATE TABLE [IF NOT EXISTS] [db.]table_name [ON CLUSTER cluster]
(
  name1 [type1] [DEFAULT|MATERIALIZED|ALIAS expr1],
  name2 [type2] [DEFAULT|MATERIALIZED|ALIAS expr2],
  ...
) ENGINE = CollapsingMergeTree(sign)
[PARTITION BY expr]
[ORDER BY expr]
[SAMPLE BY expr]
[SETTINGS name=value, ...]
```

**Example:**

For details about the example, visit <https://clickhouse.tech/docs/en/engines/table-engines/mergetree-family/collapsingmergetree/>.

- VersionedCollapsingMergeTree

The VersionedCollapsingMergeTree engine adds **Version** to the table creation statement to record the mapping between a **state** row and a **cancel** row in case that rows are out of order. The rows with the same primary key, same **Version**, and opposite **Sign** will be deleted during compaction.

**Syntax for creating a table:**

```
CREATE TABLE [IF NOT EXISTS] [db.]table_name [ON CLUSTER cluster]
(
  name1 [type1] [DEFAULT|MATERIALIZED|ALIAS expr1],
  name2 [type2] [DEFAULT|MATERIALIZED|ALIAS expr2],
  ...
) ENGINE = VersionedCollapsingMergeTree(sign, version)
[PARTITION BY expr]
[ORDER BY expr]
[SAMPLE BY expr]
[SETTINGS name=value, ...]
```

**Example:**

For details about the example, visit <https://clickhouse.tech/docs/en/engines/table-engines/mergetree-family/versionedcollapsingmergetree/>.

- GraphiteMergeTree  
The GraphiteMergeTree engine is used to store data in the time series database Graphite.

**Syntax for creating a table:**


```
CREATE TABLE [IF NOT EXISTS] [db.]table_name [ON CLUSTER cluster]
(
    Path String,
    Time DateTime,
    Value <Numeric_type>,
    Version <Numeric_type>
    ...
) ENGINE = GraphiteMergeTree(config_section)
[PARTITION BY expr]
[ORDER BY expr]
[SAMPLE BY expr]
[SETTINGS name=value, ...]
```

**Example:**

For details about the example, visit <https://clickhouse.tech/docs/en/engines/table-engines/mergetree-family/graphitemergetree/>.

## Replicated\*MergeTree Engines

All engines of the MergeTree family in ClickHouse prefixed with Replicated become MergeTree engines that support replicas.



Replicated series engines use ZooKeeper to synchronize data. When a replicated table is created, all replicas of the same shard are synchronized based on the information registered with ZooKeeper.

**Template for creating a Replicated engine:**

```
ENGINE = Replicated*MergeTree('Storage path in ZooKeeper', 'Replica name', ...)
```

Two parameters need to be specified for a Replicated engine:


- *Storage path in ZooKeeper*: specifies the path for storing table data in ZooKeeper. The path format is ***/clickhouse/tables/{shard}/Database name/ Table name***.
- *Replica name*: Generally, **{replica}** is used.

For details about the example, see [Creating a ClickHouse Table](#).

## Distributed Engine

The Distributed engine does not store any data. It serves as a transparent proxy for data shards and can automatically transmit data to each node in the cluster. Distributed tables need to work with other local data tables. Distributed tables distribute received read and write tasks to each local table where data is stored.

Figure 2-2 Working principle of the Distributed engine



**Template for creating a Distributed engine:**

```
ENGINE = Distributed(cluster_name, database_name, table_name, [sharding_key])
```

Parameters of a distributed table are described as follows:

- **cluster\_name:** specifies the cluster name. When a distributed table is read or written, the cluster configuration information is used to search for the corresponding ClickHouse instance node.
- **database\_name:** specifies the database name.
- **table\_name:** specifies the name of a local table in the database. It is used to map a distributed table to a local table.
- **sharding\_key** (optional): specifies the sharding key, based on which a distributed table distributes data to each local table.

**Example:**

```
-- Create a ReplicatedMergeTree local table named test.  
CREATE TABLE default.test ON CLUSTER default_cluster_1  
(  
  `EventDate` DateTime,  
  `id` UInt64  
)  
ENGINE = ReplicatedMergeTree('/clickhouse/tables/{shard}/default/test', '{replica}')  
PARTITION BY toYYYYMM(EventDate)  
ORDER BY id  
  
-- Create a distributed table named test_all based on the local table test.  
CREATE TABLE default.test_all ON CLUSTER default_cluster_1  
(  
  `EventDate` DateTime,  
  `id` UInt64  
)  
ENGINE = Distributed(default_cluster_1, default, test, rand())
```

**Rules for creating a distributed table:**

- When creating a distributed table, add **ON CLUSTER** *cluster\_name* to the table creation statement so that the statement can be executed once on a ClickHouse instance and then distributed to all instances in the cluster for execution.
- Generally, a distributed table is named in the following format: *Local table name\_all*. It forms a one-to-many mapping with local tables. Then, multiple local tables can be operated using the distributed table proxy.
- Ensure that the structure of a distributed table is the same as that of local tables. If they are inconsistent, no error is reported during table creation, but an exception may be reported during data query or insertion.

## 2.5 Creating a ClickHouse Table

ClickHouse implements the replicated table mechanism based on the ReplicatedMergeTree engine and ZooKeeper. When creating a table, you can specify an engine to determine whether the table is highly available. Shards and replicas of each table are independent of each other.

ClickHouse also implements the distributed table mechanism based on the Distributed engine. Views are created on all shards (local tables) for distributed query, which is easy to use. ClickHouse has the concept of data sharding, which is one of the features of distributed storage. That is, parallel read and write are used to improve efficiency.

The ClickHouse cluster table engine that uses Kunpeng as the CPU architecture does not support HDFS and Kafka.

### Viewing cluster and Other Environment Parameters of ClickHouse

**Step 1** Use the ClickHouse client to connect to the ClickHouse server by referring to [Using ClickHouse from Scratch](#).

**Step 2** Query the cluster identifier and other information about the environment parameters.

```
select cluster,shard_num,replica_num,host_name from system.clusters;
```

```
SELECT  
  cluster,  
  shard_num,  
  replica_num,  
  host_name  
FROM system.clusters
```

cluster	shard_num	replica_num	host_name
default_cluster_1	1	1	node-master1dOnG
default_cluster_1	1	2	node-group-1tXED0001
default_cluster_1	2	1	node-master2OXQS
default_cluster_1	2	2	node-group-1tXED0002
default_cluster_1	3	1	node-master3QsRI
default_cluster_1	3	2	node-group-1tXED0003

6 rows in set. Elapsed: 0.001 sec.

**Step 3** Query the shard and replica identifiers.

```
select * from system.macros;
```

```
SELECT *  
FROM system.macros
```

```
macro substitution
id      | 76
replica | node-master3QsRI
shard   | 3
-----|-----
```

3 rows in set. Elapsed: 0.001 sec.

----End

## Creating a Local Replicated Table and a distributed Table

**Step 1** Log in to the ClickHouse node using the client, for example, `clickhouse client --host node-master3QsRI --multiline --port 9440 --secure;`

 NOTE

*node-master3QsRI* is the value of **host\_name** obtained in **Step 2** in [Viewing cluster and Other Environment Parameters of ClickHouse](#).

**Step 2** Create a replicated table using the ReplicatedMergeTree engine.

For details about the syntax, see <https://clickhouse.tech/docs/en/engines/table-engines/mergetree-family/replication/#creating-replicated-tables>.

For example, run the following commands to create a ReplicatedMergeTree table named **test** on the **default\_cluster\_1** node and in the **default** database:

```
CREATE TABLE default.test ON CLUSTER default_cluster_1
(
  `EventDate` DateTime,
  `id` UInt64
)
ENGINE = ReplicatedMergeTree('/clickhouse/tables/{shard}/default/test',
'${replica}')
PARTITION BY toYYYYMM(EventDate)
ORDER BY id;
```

The parameters are described as follows:

- The **ON CLUSTER** syntax indicates the distributed DDL, that is, the same local table can be created on all instances in the cluster after the statement is executed once.
- **default\_cluster\_1** is the cluster identifier obtained in **Step 2** in [Viewing cluster and Other Environment Parameters of ClickHouse](#).

**CAUTION**

**ReplicatedMergeTree** engine receives the following two parameters:

- Storage path of the table data in ZooKeeper

The path must be in the **/clickhouse** directory. Otherwise, data insertion may fail due to insufficient ZooKeeper quota.

To avoid data conflict between different tables in ZooKeeper, the directory must be in the following format:

*/clickhouse/tables/{shard}/default/test*, in which **/clickhouse/tables/{shard}** is fixed, *default* indicates the database name, and *test* indicates the name of the created table.

- Replica name: Generally, **{replica}** is used.

```
CREATE TABLE default.test ON CLUSTER default_cluster_1
(
  `EventDate` DateTime,
  `id` UInt64
)
ENGINE = ReplicatedMergeTree('/clickhouse/tables/{shard}/default/test', '{replica}')
PARTITION BY toYYYYMM(EventDate)
ORDER BY id
```

host	port	status	error	num_hosts_remaining
node-group-1tXED0002	9000	0		5
node-group-1tXED0003	9000	0		4
node-master1dOnG	9000	0		3

host	port	status	error	num_hosts_remaining
node-master3QsRI	9000	0		2
node-group-1tXED0001	9000	0		1
node-master2OXQS	9000	0		0

6 rows in set. Elapsed: 0.189 sec.

**Step 3** Create a distributed table using the Distributed engine.

For example, run the following commands to create a distributed table named **test\_all** on the **default\_cluster\_1** node and in the **default** database:

```
CREATE TABLE default.test_all ON CLUSTER default_cluster_1
(
  `EventDate` DateTime,
  `id` UInt64
)
ENGINE = Distributed(default_cluster_1, default, test, rand());
```

```
CREATE TABLE default.test_all ON CLUSTER default_cluster_1
(
  `EventDate` DateTime,
  `id` UInt64
)
ENGINE = Distributed(default_cluster_1, default, test, rand())
```

host	port	status	error	num_hosts_remaining
------	------	--------	-------	---------------------

```
num_hosts_active
node-group-1tXED0002      | 9000 | 0 | 5 | 0 |
node-master3QsRI         | 9000 | 0 | 4 | 0 |
node-group-1tXED0003     | 9000 | 0 | 3 | 0 |
node-group-1tXED0001     | 9000 | 0 | 2 | 0 |
node-master1dOnG         | 9000 | 0 | 1 | 0 |
node-master2OXQS         | 9000 | 0 | 0 | 0 |
```

6 rows in set. Elapsed: 0.115 sec.

**NOTE**

**Distributed** requires the following parameters:

- **default\_cluster\_1** is the cluster identifier obtained in [Step 2 in Viewing cluster and Other Environment Parameters of ClickHouse](#).
- **default** indicates the name of the database where the local table is located.
- **test** indicates the name of the local table. In this example, it is the name of the table created in [Step 2](#).
- (Optional) Sharding key  
This key and the weight configured in the **config.xml** file determine the route for writing data to the distributed table, that is, the physical table to which the data is written. It can be the original data (for example, **site\_id**) of a column in the table or the result of the function call, for example, **rand()** is used in the preceding SQL statement. Note that data must be evenly distributed in this key. Another common operation is to use the hash value of a column with a large difference, for example, **intHash64(user\_id)**.

----End

## ClickHouse Table Data Operations

**Step 1** Log in to the ClickHouse node on the client. For example,

```
clickhouse client --host node-master3QsRI --multiline --port 9440 --secure;
```

**NOTE**

*node-master3QsRI* is the value of **host\_name** obtained in [Step 2 in Viewing cluster and Other Environment Parameters of ClickHouse](#).

**Step 2** After creating a table by referring to [Creating a Local Replicated Table and a distributed Table](#), you can insert data to the local table.

For example, run the following command to insert data to the local table **test**:

```
insert into test values(toDateTime(now()), rand());
```

**Step 3** Query the local table information.

For example, run the following command to query data information of the table **test** in [Step 2](#):

```
select * from test;
```

```
SELECT *
FROM test
```

EventDate	id
2020-11-05 21:10:42	1596238076

```
1 rows in set. Elapsed: 0.002 sec.
```

**Step 4** Query the distributed table.

For example, the distributed table **test\_all** is created based on table **test** in [Step 3](#). Therefore, the same data in table **test** can also be queried in table **test\_all**.

```
select * from test_all;
```

```
SELECT *  
FROM test_all
```

EventDate	id
2020-11-05 21:10:42	1596238076

```
1 rows in set. Elapsed: 0.004 sec.
```

**Step 5** Switch to the shard node with the same **shard\_num** and query the information about the current table. The same table data can be queried.

For example, run the **exit;** command to exit the original node.

Run the following command to switch to the **node-group-1tXED0003** node:

```
clickhouse client --host node-group-1tXED0003 --multiline --port 9440 --secure;
```

 **NOTE**

The **shard\_num** values of **node-group-1tXED0003** and **node-master3QsRI** are the same by performing [Step 2](#).

```
show tables;
```

```
SHOW TABLES
```

name
test
test_all

**Step 6** Query the local table data. For example, run the following command to query data in table **test** on the **node-group-1tXED0003** node:

```
select * from test;
```

```
SELECT *  
FROM test
```

EventDate	id
2020-11-05 21:10:42	1596238076

```
1 rows in set. Elapsed: 0.005 sec.
```

**Step 7** Switch to the shard node with different **shard\_num** value and query the data of the created table.

For example, run the following command to exit the **node-group-1tXED0003** node:

```
exit;
```

Switch to the **node-group-1tXED0001** node. The **shard\_num** values of **node-group-1tXED0001** and **node-master3QsRI** are different by performing [Step 2](#).

```
clickhouse client --host node-group-1tXED0001 --multiline --port 9440 --secure;
```

Query the local table **test**. Data cannot be queried on the different shard node because table **test** is a local table.

```
select * from test;
```

```
SELECT *  
FROM test
```

```
Ok.
```

Query data in the distributed table **test\_all**. The data can be queried properly.

```
select * from test_all;
```

```
SELECT *  
FROM test
```

EventDate	id
2020-11-05 21:12:19	3686805070

```
1 rows in set. Elapsed: 0.002 sec.
```

```
----End
```

## 2.6 Using the ClickHouse Data Migration Tool

The ClickHouse data migration tool can migrate some partitions of one or more partitioned MergeTree tables on several ClickHouseServer nodes to the same tables on other ClickHouseServer nodes. In the capacity expansion scenario, you can use this tool to migrate data from an original node to a new node to balance data after capacity expansion.

### Prerequisites

- The ClickHouse and Zookeeper services are running properly. The ClickHouseServer instances on the source and destination nodes are normal.
- The destination node has the data table to be migrated and the table is a partitioned MergeTree table.
- Before creating a migration task, ensure that all tasks for writing data to a table to be migrated have been stopped. After the task is started, you can only query the table to be migrated and cannot write data to or delete data from the table. Otherwise, data may be inconsistent before and after the migration.
- If automatic balancing is enabled, only a partitioned ReplicatedMergeTree table is migrated, and the partitioned table must have a corresponding distributed table.
- The ClickHouse data directory on the destination node has sufficient space.

### Procedure

- Step 1** Log in to Manager and choose **Cluster > Services > ClickHouse > Data Migration**. On the displayed page, click **Add Task**.

 NOTE

- The number of created migration tasks is limited. By default, a maximum of 20 migration tasks can be created. You can modify the number of migration tasks allowed by modifying the **max\_migration\_task\_number** configuration item on the ClickHouse configuration page of Manager. A migration task occupies a certain number of Znodes on ZooKeeper. Therefore, you are not advised to set the maximum number of migration tasks allowed to a large value.
- If the number of existing migration tasks exceeds the upper limit, no more migration tasks can be created. The system automatically deletes the earliest migration tasks that have been successfully executed. If no historical migration task is successfully executed, perform [Step 10](#) based on the site requirements and manually delete historical migration tasks.

**Step 2** On the page for creating a migration task, set the migration task parameters. For details, see [Table 2-4](#). After configuring the parameters, click **Next**. If **Automatic balancing** is not enabled, go to [Step 3](#). If **Automatic balancing** is enabled, go to [Step 5](#).

**Table 2-4** Migration task parameters

Parameter	Description
Task Name	Enter a specific task name. The value can contain 1 to 50 characters, including letters, digits, and underscores (_), and cannot be the same as that of an existing migration task.
Automatic balancing	Choose whether to enable <b>Automatic balancing</b> . <ul style="list-style-type: none"> <li>• If it is enabled, the system automatically selects the source and destination nodes to ensure that data in partitioned ReplicatedMergeTree tables corresponding to the distributed tables is evenly distributed on each node in the cluster.</li> <li>• If it is not enabled, you need to manually select the source and destination nodes.</li> </ul>
Task Type	<ul style="list-style-type: none"> <li>• <b>Scheduled Task</b>: When the scheduled task is selected, you can set <b>Started</b> to specify a time point later than the current time to execute the task.</li> <li>• <b>Immediate task</b>: The task is executed immediately after it is started.</li> </ul>
Started	Set this parameter when <b>Task Type</b> is set to <b>Scheduled Task</b> . The valid value is a time point within 90 days from now.
Maximum Bandwidth	Bandwidth upper limit of each ClickHouseServer node. The value ranges from 1 MB/s to 10,000 MB/s. In automatic balancing scenarios, increase the bandwidth as much as possible. Flow control is disabled by default.
Data Amount Migrated	Percentage of the amount of data migrated in each table to the total amount of data in the table. The value ranges from 0 to 100%. If this parameter is left blank, the value is set to 50% by default. This parameter is valid only when <b>Automatic balancing</b> is disabled.

**Step 3** On the **Select Node** page, select the data table to be migrated from the list on the left and click **OK**. In the list on the right, select the source node of the selected data table and click **Next**.

 **NOTE**

After a node is selected, other nodes that are replicas of the selected node are automatically selected as the source nodes.

**Step 4** On the **Select Data Table** page, select the host name of the destination node and click **Next**.

 **NOTE**

The destination node must be different from the source nodes. The selected source nodes are not displayed on the page.

**Step 5** Confirm the task information and click **Submit**.

The data migration tool automatically calculates the partitions to be migrated based on the size of the data table to be migrated and the value of **Data Amount Migrated** set on the **Add Task** page.

**Step 6** After the migration task is submitted, click **Start** in the **Operation** column. If the task is an immediate task, the task starts to be executed. If the task is a scheduled task, the countdown starts.

**Step 7** During the migration task execution, you can click **Cancel** to cancel the migration task. If the migration task is canceled, the migrated data on the destination node will not be rolled back.

---

 **CAUTION**

After a task with automatic balancing enabled is canceled, it will not stop immediately. It will stop after the table migration is complete. After a task with automatic balancing disabled is canceled, the task stops immediately. After the task stops, a partition may have been migrated to the destination node, but it is not deleted from the source node. In this case, duplicate data exists. Manually check whether the migrated partition still exists on the source node. If it still exists, check that the total data volume of the partition on the destination node is the same as that on the source node, and then delete the partition from the source node.

---

**Step 8** Choose **More > Details** to view details about the migration task.

**Step 9** After the migration is complete, choose **More > Results** to view the migration result.

In a non-automatic balancing task, you can view the migrated partitions of each table and the partition migration result. If the partition migration is not finished, the partition has been copied to the destination node but not deleted from the source node because the data volume of the partition on the source node is inconsistent with that of the partition on the destination node. In this case, check whether the data volume of the partition on the source node is consistent with that of the partition on the destination node, and then delete the partition from the source node.

**Step 10** After the migration is complete, choose **More > Delete** to delete the directories related to the migration task on ZooKeeper and the destination node.

----End

## 2.7 Monitoring of Slow ClickHouse Query Statements and Replication Table Data Synchronization

### 2.7.1 Slow Query Statement Monitoring

#### Scenario

The SQL statement query in ClickHouse is slow because the conditions such as partitions, where conditions, and indexes of SQL statements are set improperly. As a result, the overall performance of the database is affected. To solve this problem, MRS provides the function of monitoring slow ClickHouse query statements.

#### Ongoing Slow Queries

You can query information about slow SQL statements that are being executed but do not return any result.

- Procedure**  
 Log in to FusionInsight Manager and choose **Cluster > Services > ClickHouse**. On the displayed page, click the **Query Management** tab and then the **Ongoing Slow Queries** tab.
- Parameters**


**Table 2-5** Slow query parameters

Parameter	Description
Server Node IP Address	IP address of the ClickHouseServer instance. To view the IP address, log in to FusionInsight Manager and choose <b>Cluster &gt; Services &gt; ClickHouse</b> . On the displayed page, click the <b>Instance</b> tab.
Query ID	Unique ID generated internally.
Query	Slow query SQL statement.
Start Time	Time when the execution of a slow query SQL statement starts.
End Time	Time when the execution of a slow query SQL statement ends.
Duration (s)	Total execution time of a slow query SQL statement, in seconds.
User	ClickHouse user who executes a slow query SQL statement.

Parameter	Description
Client IP Address	IP address of the client that submits a slow query SQL statement.
Memory Used (MB)	Memory used by a slow query SQL statement, in MB.
Operation	You can click <b>Terminate</b> to terminate the slow query using a slow query SQL statement.

- **Filter conditions**

Select the query condition as required and filter the query results.



**Table 2-6** Filter conditions

Condition	Description
Slow query duration exceeding	Filters the slow queries based on the duration. The value can be <b>3 (s)</b> , <b>9 (s)</b> , <b>15 (s)</b> , or <b>25 (s)</b> .
By Query ID	Filters the slow queries based on the query ID.
By User	Filters the slow queries based on the ClickHouse user.
By Client IP Address	Filters the slow queries based on the IP address of the client that submits slow query SQL statements.

## Completed Queries

You can query information about slow SQL statements that have been executed and returned results.

Log in to FusionInsight Manager and choose **Cluster > Services > ClickHouse**. On the displayed page, click the **Query Management** tab and then the **Completed Queries** tab.

For details about slow query parameters and filter conditions, see [Table 2-5](#) and [Table 2-6](#), respectively.

## 2.7.2 Replication Table Data Synchronization Monitoring

### Scenario

MRS monitors the synchronization between multiple copies of data in the same shard of a Replicated\*MergeTree table.

### Constraints

Currently, you can monitor and query only Replicated\*MergeTree tables whose creation statements contain the key word **ON CLUSTER**.

### Replication Table Data Synchronization

- **Procedure**  
Log in to FusionInsight Manager and choose **Cluster > Services > ClickHouse**. On the displayed page, click the **Data Synchronization Status** tab.
- **Data synchronization parameters**

**Table 2-7** Data synchronization parameters

Parameter	Description
Data Tables	Names of Replicated*MergeTree tables.
Shard	ClickHouse shard where the data table is located.
Status	Data synchronization status. The options are as follows: <ul style="list-style-type: none"><li>• <b>No data</b>: The table has no data on this shard.</li><li>• <b>Synchronized</b>: The table has data on this shard, and multiple instance copies of the same shard are the same.</li><li>• <b>Not synchronized</b>: The table has data on this shard, but multiple instance copies of the same shard are not the same.</li></ul>
Details	Data synchronization details of the data table on the corresponding ClickHouseServer instance.

- **Filter conditions**  
You can select **By Data Tables** and enter a data table name in the search box to filter data tables.

## 2.8 Adaptive MV Usage in ClickHouse

### Scenario

Materialized views (MVs) are used in ClickHouse to save the precomputed result of time-consuming operations. When querying data, you can query the

materialized views rather than the original tables, thereby quickly obtaining the query result.

Currently, MVs are not easy to use in ClickHouse. Users can create one or more MVs based on the original table data as required. Once multiple MVs are created, you need to identify which MV is used and convert the query statement of an original table to that of an MV. In this way, the querying process is inefficient and prone to errors.

The problem mentioned above is readily solved since the adoption of adaptive MVs. When querying an original table, the corresponding MV of this table will be queried, which greatly improves the usability and efficiency of ClickHouse.

## Matching Rules of Adaptive MVs

To ensure that the SQL statement for querying an original table can be automatically converted to that for querying the corresponding MV, the following matching rules must be met:

- The table to be queried using an SQL statement must be associated with an MV.
- The AggregatingMergeTree engine must be used with MVs.
- Both the SELECT clause of SQL and MVs must contain aggregate functions.
- If the SQL query contains a GROUP BY clause, MVs must also contain this clause.
- If an MV contains a WHERE clause of SQL, the WHERE clause must be the same as that of the MV. This also applies to the PREWHERE and HAVING clauses.
- Fields to be queried using the SQL statements must exist in the MVs.
- If multiple MVs meet the preceding requirements, the SQL statement for querying the original table will be used.

For details about common matching failures of adaptive MVs, see [Common Matching Failures of MVs](#).

## Using Adaptive MVs

In the following operations, **local\_table** is the original table and **view\_table** is the MV created based on **local\_table**. Change the table creation and query statements based on the site requirements.

**Step 1** Use the ClickHouse client to connect to the default database. For details, see [Using ClickHouse from Scratch](#).

**Step 2** Run the following table creation statements to create the original table **local\_table**.

```
CREATE TABLE local_table
(
  id String,
  city String,
  code String,
  value UInt32,
  create_time DateTime,
  age UInt32
)
```

```
ENGINE = MergeTree  
PARTITION BY toDate(create_time)  
ORDER BY (id, city, create_time);
```

**Step 3** Create the MV **view\_table** based on **local\_table**.

```
CREATE MATERIALIZED VIEW view_table  
ENGINE = AggregatingMergeTree  
PARTITION BY toDate(create_time)  
ORDER BY (id, city, create_time)  
AS SELECT  
create_time,  
id,  
city,  
uniqState(code),  
sumState(value) AS value_new,  
minState(create_time) AS first_time,  
maxState(create_time) AS last_time  
FROM local_table  
WHERE create_time >= toDateTime('2021-01-01 00:00:00')  
GROUP BY id, city, create_time;
```

**Step 4** Insert data to the **local\_table** table.

```
INSERT INTO local_table values('1','zzz','code1',1,toDateTime('2021-01-02 00:00:00'), 10);  
INSERT INTO local_table values('2','kkk','code2',2,toDateTime('2020-01-01 00:00:00'), 20);  
INSERT INTO local_table values('3','ccc','code3',3,toDateTime('2022-01-01 00:00:00'), 30);
```

**Step 5** Run the following command to enable the adaptive MVs.

```
set adaptive_materilized_view = 1;
```

 **NOTE**

If the **adaptive\_materilized\_view** parameter is set to **1**, the adaptive MVs are enabled. If it is set to **0**, the adaptive MVs are disabled. The default value is **0**. **set adaptive\_materilized\_view = 1;** is a session-level command and needs to be reset each time the client connects to the server.

**Step 6** Query data in the **local\_table** table.

```
SELECT sum(value)  
FROM local_table  
WHERE create_time >= toDateTime('2021-01-01 00:00:00')  
┌sumMerge(value_new)┐  
4 |
```

**Step 7** Run the **explain syntax** command to view the execution plan of the SQL statement in step **Step 6**. According to the query result, **view\_table** is queried.

```
EXPLAIN SYNTAX  
SELECT sum(value)  
FROM local_table  
WHERE create_time >= toDateTime('2021-01-01 00:00:00')  
┌explain┐  
SELECT sumMerge(value_new) |  
FROM default.view_table |
```

----End

## Common Matching Failures of MVs

- When creating an MV, the aggregate functions must contain the State suffix. Otherwise, the corresponding MV cannot be matched. Example:  
## The MV **agg\_view** is created based on the original table **test\_table**. However, the count aggregate function does not contain the State suffix.

```
CREATE MATERIALIZED VIEW agg_view  
ENGINE = AggregatingMergeTree
```

```

PARTITION BY toDate(create_time)
ORDER BY (id)
AS SELECT
create_time,
id,
count(id)
FROM test_table
GROUP BY id,create_time;

```

# To ensure that the MV can be matched, the count aggregate function for creating the MV must contain the State suffix. The correct example is as follows:

```

CREATE MATERIALIZED VIEW agg_view
ENGINE = AggregatingMergeTree
PARTITION BY toDate(create_time)
ORDER BY (id)
AS SELECT
create_time,
id,
countState(id)
FROM test_table
GROUP BY id,create_time;

```

- Only if the WHERE clause of the statement for querying an original table is completely the same as that in an MV can the MV be matched.

For example, if the WHERE clause of the original table statement is **where a=b** while the WHERE clause of the MV is **where b=a**, the corresponding MV cannot be matched.

However, if the statement for querying the original table does not contain the database name, the corresponding MV can be matched. Example:

```

# The MV view_test is created based on db_test.table_test. The WHERE clause for querying the
original table contains the database name db_test.
CREATE MATERIALIZED VIEW db_test.view_test ENGINE = AggregatingMergeTree ORDER BY phone AS
SELECT
name,
phone,
uniqExactState(class) as uniq_class,
sumState(CRC32(phone))
FROM db_test.table_test
WHERE (class, name) GLOBAL IN
(
SELECT class, name FROM db_test.table_test
WHERE
name = 'zzzz'
AND class = 'calss one'
)
GROUP BY
name, phone;
# If the WHERE clause does not contain the database name db_test, the corresponding MV will be
matched.
USE db_test;
EXPLAIN SYNTAX
SELECT
name,
phone,
uniqExact(class) as uniq_class,
sum(CRC32(phone))
FROM table_test
WHERE (class, name) GLOBAL IN
(
SELECT class, name FROM table_test
WHERE
name = 'zzzz'
AND class = 'calss one'
)
GROUP BY
name, phone;

```

- If the GROUP BY clause contains functions, the corresponding MV can be matched only when the column field names in the functions are the same as those in an original table. Example:

```
# Create the MV agg_view based on test_table.
CREATE MATERIALIZED VIEW agg_view
ENGINE = AggregatingMergeTree
PARTITION BY toDate(create_time)
ORDER BY (id, city, create_time)
AS SELECT
create_time,
id,
city,
value as value1,
uniqState(code),
sumState(value) AS value_new,
minState(create_time) AS first_time,
maxState(create_time) AS last_time
FROM test_table
GROUP BY id, city, create_time, value1 % 2, value1;
# The corresponding MV can be matched if the statement is as follows:
SELECT uniq(code) FROM test_table GROUP BY id, city, value1 % 2;
# The corresponding MV cannot be matched if the statement is as follows:
SELECT uniq(code) FROM test_table GROUP BY id, city, value % 2;
```

- In a created MV, the FROM clause cannot be a SELECT statement. Otherwise, the corresponding MV will fail to be matched. In the following example, the FROM clause is a SELECT statement. In this case, the corresponding MV cannot be matched.

```
CREATE MATERIALIZED VIEW agg_view
ENGINE = AggregatingMergeTree
PARTITION BY toDate(create_time)
ORDER BY (id)
AS SELECT
create_time,
id,
countState(id)
FROM
(SELECT id, create_time FROM test_table)
GROUP BY id,create_time;
```

- When querying original tables or creating MVs, an aggregate function cannot be used together with another aggregate function or a common function. Example:

```
# Case 1: Multiple aggregate functions are used when querying an original table.
# Create an MV.
CREATE MATERIALIZED VIEW agg_view
ENGINE = AggregatingMergeTree
PARTITION BY toDate(create_time)
ORDER BY (id)
AS SELECT
create_time,
id,
countState(id)
FROM test_table
GROUP BY id,create_time;
# Two aggregate functions are used when querying the original table, leading to the MV matching failure.
SELECT count(id) + count(id) FROM test_table;
# Case 2: Multiple aggregate functions are used when creating an MV.
# Two countState(id) functions are used when creating the MV, leading to the MV matching failure.
CREATE MATERIALIZED VIEW agg_view
ENGINE = AggregatingMergeTree
PARTITION BY toDate(create_time)
ORDER BY (id)
AS SELECT
create_time,
id,
(countState(id) + countState(id)) AS new_count
```

```
FROM test_table
GROUP BY id,create_time;
# The corresponding MV cannot be matched when querying the original table.
SELECT new_count FROM test_table;
```

However, if the parameter of an aggregate function is the combination operation of fields, the corresponding MV can be matched.

```
CREATE MATERIALIZED VIEW agg_view
ENGINE = AggregatingMergeTree
PARTITION BY toDate(create_time)
ORDER BY (id)
AS SELECT
create_time,
id,
countState(id + id)
FROM test_table
GROUP BY id,create_time;
# The corresponding MV can be matched when querying the original table.
SELECT count(id + id) FROM test_table;
```

## 2.9 ClickHouse Log Overview

### Log Description

**Log path:** The default storage path of ClickHouse log files is as follows: `$(BIGDATA_LOG_HOME)/clickhouse`

**Log archive rule:** The automatic ClickHouse log compression function is enabled. By default, when the size of logs exceeds 100 MB, logs are automatically compressed into a log file named in the following format: `<Original log name>.[ID].gz`. A maximum of 10 latest compressed files are reserved by default. The number of compressed files can be configured on Manager.

**Table 2-8** ClickHouse log list

Log Type	Log File Name	Description
Run logs	<code>/var/log/Bigdata/clickhouse/clickhouseServer/clickhouse-server.err.log</code>	Path of ClickHouseServer error log files.
	<code>/var/log/Bigdata/clickhouse/clickhouseServer/checkService.log</code>	Path of key ClickHouseServer run log files.
	<code>/var/log/Bigdata/clickhouse/clickhouseServer/clickhouse-server.log</code>	
	<code>/var/log/Bigdata/clickhouse/balance/start.log</code>	Path of ClickHouseBalancer startup log files.
	<code>/var/log/Bigdata/clickhouse/balance/error.log</code>	Path of ClickHouseBalancer error log files.
	<code>/var/log/Bigdata/clickhouse/balance/access_http.log</code>	Path of ClickHouseBalancer run log files.

Log Type	Log File Name	Description
Data migration logs	<i>/var/log/Bigdata/clickhouse/migration/Data migration task name/clickhouse-copier_{timestamp}_{processId}/copier.log</i>	Run logs generated when you use the migration tool by referring to <a href="#">Using the ClickHouse Data Migration Tool</a> .
	<i>/var/log/Bigdata/clickhouse/migration/Data migration task name/clickhouse-copier_{timestamp}_{processId}/copier.err.log</i>	Error logs generated when you use the migration tool by referring to <a href="#">Using the ClickHouse Data Migration Tool</a> .
Audit log	<i>/var/log/Bigdata/audit/clickhouse/clickhouse-server.audit.log</i>	Path of ClickHouse audit log files.
Backup and recovery logs	<i>/var/log/Bigdata/clickhouse/clickhouseServer/backup.log</i>	Path of log files generated when ClickHouse performs the backup and restoration operations on Manager.

## Log Level

[Table 2-9](#) describes the log levels supported by ClickHouse.

Levels of run logs are error, warning, trace, information, and debug from the highest to the lowest priority. Run logs of equal or higher levels are recorded. The higher the specified log level, the fewer the logs recorded.

**Table 2-9** Log levels

Log Type	Level	Description
Run log	error	Logs of this level record error information about system running.
	warning	Logs of this level record exception information about the current event processing.
	trace	Logs of this level record trace information about the current event processing.
	information	Logs of this level record normal running status information about the system and events.

Log Type	Level	Description
	debug	Logs of this level record system running and debugging information.

To modify log levels, perform the following operations:

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster > Services > ClickHouse > Configurations**.
- Step 3** Select **All Configurations**.
- Step 4** On the menu bar on the left, select the log menu of the target role.
- Step 5** Select a desired log level.
- Step 6** Click **Save**. Then, click **OK**.

----End

 **NOTE**

The configurations take effect immediately without the need to restart the service.

## Log Format

The following table lists the ClickHouse log format:

**Table 2-10** Log formats

Log Type	Format	Example
Run log	<code>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt; &lt;Log level&gt; &lt;Name of the thread that generates the log&gt; &lt;Message in the log&gt; &lt;Location where the log event occurs&gt;</code>	<pre>2021.02.23 15:26:30.691301 [ 6085 ] {} &lt;Error&gt; DynamicQueryHandler: Code: 516, e.displayText() = DB::Exception: default: Authentication failed: password is incorrect or there is no user with such name, Stack trace (when copying this message, always include the lines below):  0. Poco::Exception::Exceptio n(std::__1::basic_string&lt;c har, std::__1::char_traits&lt;char &gt;, std::__1::allocator&lt;char&gt; &gt; const&amp;, int) @ 0x1250e59c</pre>

# 3 Using DBService

---

## 3.1 Configuring SSL for the HA Module

### Scenario

This section describes how to manually configure SSL for the HA module of DBService in the cluster where DBService is installed.

 **NOTE**

After this operation is performed, if you need to restore the SSL configuration, go to [Restoring SSL for the HA Module](#).

### Prerequisites

- The cluster has been installed.
- The `root-ca.crt` and `root-ca.pem` files in the `$BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0/security` directory on the active and standby DBService nodes are the same.

### Procedure

**Step 1** Log in to the DBService node where SSL needs to be configured as user `omm`.

**Step 2** Go to the `$BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0/sbin/` directory and run the following command:

```
./proceed_ha_ssl_cert.sh DBService installation directoryService IP address of the node
```

Example:

```
cd $BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0/sbin/
```

```
./proceed_ha_ssl_cert.sh $BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0 10.10.10.10
```

 NOTE

`$BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0` is the installation directory of DBService. Modify it based on site requirements.

**Step 3** Go to the `$BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0/ha/module/hacom/script/` directory and run the following command to restart the HA process:

```
./stop_ha.sh
```

```
./start_ha.sh
```

**Step 4** Run the following command on the preceding node to obtain the PID of the HA process:

```
ps -ef |grep "ha.bin" |grep DBSERVICE
```

**Step 5** Run the following command to check whether the protocol is changed to TCP:

```
netstat -nap | grep pid | grep -v unix
```

- If yes, no further action is required.
- If no, go to [Step 2](#).

(Not all processes could be identified, non-owned process info will not be shown, you would have to be root to see it all.)

```
tcp    0    0 127.0.0.1:20054      0.0.0.0:*          LISTEN      11896/ha.bin
tcp    0    0 10.10.10.10:20052   10.10.10.14:20052  ESTABLISHED 11896/ha.bin
tcp    0    0 10.10.10.10:20053   10.10.10.14:20053  ESTABLISHED 11896/ha.bin
```

----End

## 3.2 Restoring SSL for the HA Module

### Scenario

This section describes how to restore SSL for the HA module of DBService in the cluster where DBService is installed.

### Prerequisites

SSL has been enabled for the HA module of DBService.

 NOTE

Check whether SSL is enabled for the HA module of DBService.

Check `$BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0/ha/module/hacom/conf/hacom.xml`. If the file contains `<hadataproTOCOL value="ssl"></hadataproTOCOL>`, SSL is enabled.

### Procedure

**Step 1** Log in to the DBService node where SSL needs to be restored as user **omm**.

**Step 2** Run the following commands to restore the DBService configuration file **hacom\_local.xml**:

```
cd $BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-  
dbservice-2.7.0/ha/local/hacom/conf/  
cp hacom_local.xml $BIGDATA_HOME/tmp/  
cat hacom_local.xml | grep "ssl>" -n | cut -d':' -f1 | xargs | sed 's/ /,/g' |xargs -n  
1 -i sed -i '{d}' hacom_local.xml
```

**Step 3** Run the following commands to restore the DBService configuration file **hacom.xml**:

```
cd $BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-  
dbservice-2.7.0/ha/module/hacom/conf/  
cp hacom.xml $BIGDATA_HOME/tmp/  
sed -i 's#<hadataprotocol.*#<hadataprotocol value="udp"/>#g' hacom.xml  
sed -i 's#<rpcsupportssl.*#<rpcsupportssl value="true"/>#g' hacom.xml
```

 NOTE

`$BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0` is the installation directory of DBService. Modify it based on the upgrade environment.

**Step 4** Go to the `$BIGDATA_HOME/FusionInsight_BASE_x.x.x/install/FusionInsight-dbservice-2.7.0/ha/module/hacom/script/` directory and run the following command to restart the HA process:

```
./stop_ha.sh  
./start_ha.sh
```

**Step 5** Run the following command to obtain the PID of the HA process:

```
ps -ef |grep "ha.bin" |grep DBSERVICE
```

**Step 6** Run the following command to check whether the protocol is changed to TCP:

```
netstat -nap | grep pid | grep -v unix
```

- If yes, no further action is required.
- If no, contact O&M support.

```
[omm@host03]\>netstat -nap | grep 49989  
(Not all processes could be identified, non-owned process info  
will not be shown, you would have to be root to see it all.)  
tcp    0    0 127.0.0.1:20054      0.0.0.0:*           LISTEN  49989/ha.bin  
udp    0    0 10.10.10.10:20052   0.0.0.0:*           49989/ha.bin  
udp    0    0 10.10.10.10:20053   0.0.0.0:*           49989/ha.bin
```

----End

## 3.3 Configuring the Timeout Interval of DBService Backup Tasks

### Scenario

The default timeout interval of DBService backup tasks is 2 hours. When the data volume in DBService is too large, the backup task may fail to be executed because the timeout interval is reached.

This section describes how to customize the timeout interval of a DBService backup task.

### Prerequisites

- Clusters have been properly installed.
- DBService is running properly.

### Procedure

- Step 1** Log in to the active OMS node as user **omm** using PuTTY. In the `$ {CONTROLLER_HOME}/etc/om/controller.properties` configuration file, change the value of **controller.backup.conf.script.execute.timeout** to **1000000s** (Set the timeout interval based on the data volume of DBService).
- Step 2** Log in to the active OMS node as user **omm** using PuTTY and repeat step [Step 1](#).
- Step 3** Log in to the active OMS node as user **omm** using PuTTY, run the following command to query the ID of **BackupRecoveryPluginProcess** process, and stop the process.

```
jps|grep -i BackupRecoveryPluginProcess
```

```
kill -9 Queried process ID
```

- Step 4** Log in to FusionInsight Manager and perform the DBService backup task again.
- Step 5** Run the following command to check whether the **BackupRecoveryPluginProcess** process is started:

```
jps|grep -i BackupRecoveryPluginProcess
```

```
----End
```

## 3.4 DBService Log Overview

### Log Description

**Log path:** The default storage path of DBService log files is `/var/log/Bigdata/dbservice`.

- GaussDB: `/var/log/Bigdata/dbservice/DB` (GaussDB run log directory), `/var/log/Bigdata/dbservice/scriptlog/gaussdbinstall.log`

(GaussDB installation log), and **/var/log/gaussdbuninstall.log** (GaussDB uninstallation log).

- HA: **/var/log/Bigdata/dbservice/ha/runlog** (HA run log directory) and **/var/log/Bigdata/dbservice/ha/scriptlog** (HA script log directory)
- DBServer: **/var/log/Bigdata/dbservice/healthCheck** (Directory of service and process health check logs)  
**/var/log/Bigdata/dbservice/scriptlog** (run log directory), **/var/log/Bigdata/audit/dbservice/** (audit log directory)

Log archive rule: The automatic DBService log compression function is enabled. By default, when the size of logs exceeds 1 MB, logs are automatically compressed into a log file named in the following format: *<Original log file name>-[No.].gz*. A maximum of 20 latest compressed files are reserved.

 **NOTE**

Log archive rules cannot be modified.

**Table 3-1** DBService log list

Type	Log File Name	Description
DBServer run log	dbservice_serviceCheck.log	Run log file of the service check script
	dbservice_processCheck.log	Run log file of the process check script
	backup.log	Run logs of backup and restoration operations (The DBService backup and restoration operations need to be performed.)
	checkHaStatus.log	Log file of HA check records
	cleanupDBService.log	Uninstallation log file (You need to uninstall DBService logs.)
	componentUserManager.log	Log file that records the adding and deleting operations on the database by users (Services that depend on DBService need to be added.)
	install.log	Installation log file
	preStartDBService.log	Pre-startup log file

Type	Log File Name	Description
	start_dbserver.log	DBServer startup operation log file (DBService needs to be started.)
	stop_dbserver.log	DBServer stop operation log file (DBService needs to be stopped.)
	status_dbserver.log	Log file of the DBServer status check (You need to execute the <b>\$DBSERVICE_HOME/sbin/status-dbserver.sh</b> script.)
	modifyPassword.log	Run log file of changing the DBService password script. (You need to execute the <b>\$DBSERVICE_HOME/sbin/modifyDBPwd.sh</b> script.)
	modifyDBPwd_yyyy-mm-dd.log	Run log file that records the DBService password change tool (You need to execute the <b>\$DBSERVICE_HOME/sbin/modifyDBPwd.sh</b> script.)
	dbserver_switchover.log	Log for DBServer to execute the active/standby switchover script (the active/standby switchover needs to be performed)
GaussDB run log	gaussdb.log	Log file that records database running information
	gs_ctl-current.log	Log file that records operations performed by using the <b>gs_ctl</b> tool
	gs_guc-current.log	Log file that records operations, mainly parameter modification performed by using the <b>gs_guc</b> tool

Type	Log File Name	Description
	gaussdbinstall.log	GaussDB installation log file
	gaussdbuninstall.log	GaussDB uninstallation log file
HA script run log	floatip_ha.log	Log file that records the script of floating IP addresses
	gaussDB_ha.log	Log file that records the script of GaussDB resources
	ha_monitor.log	Log file that records the HA process monitoring information
	send_alarm.log	Alarm sending log file
	ha.log	HA run log file
DBService audit log	dbservice_audit.log	Audit log file that records DBService operations, such as backup and restoration operations

## Log Format

The following table lists the DBService log formats.

**Table 3-2** Log format

Type	Format	Example
Run log	[<yyyy-MM-dd HH:mm:ss> <Log level>: [< Name of the script that generates the log. Line number >]: < Message in the log>	[2020-12-19 15:56:42] INFO [postinstall.sh:653] Is cloud flag is false. (main)
Audit log	[<yyyy-MM-dd HH:mm:ss,SSS> UserName:<Username> UserIP:<User IP address> Operation:<Operation content> Result:<Operation results> Detail:<Detailed information>	[2020-05-26 22:00:23] UserName:omm UserIP: 192.168.10.21 Operation:DBService data backup Result: SUCCESS Detail: DBService data backup is successful.

# 4 Using Flink

---

## 4.1 Using Flink from Scratch

### Scenario

This section describes how to use Flink to run wordcount jobs.

### Prerequisites

- Flink has been installed in the MRS cluster and all components in the cluster are running properly.
- The cluster client has been installed, for example, in the `/opt/hadoopclient` directory.

### Procedure

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following commands to go to the client installation directory.

```
cd /opt/hadoopclient
```

**Step 3** Run the following command to initialize environment variables:

```
source /opt/hadoopclient/bigdata_env
```

**Step 4** If Kerberos authentication is enabled for the cluster, perform the following substeps. If Kerberos authentication is not enabled for the cluster, skip the following substeps.

1. Create a user, for example, **test**, for submitting Flink jobs.  
After a human-machine user is created, log in to FusionInsight Manager as the new user and change the initial password as prompted.

 **NOTE**

To submit or run jobs on Flink, the user must have the following permissions:

- If Ranger authentication is enabled, the current user must belong to the **hadoop** group or the user has been granted the **/flink** read and write permissions in Ranger.
- If Ranger authentication is disabled, the current user must belong to the **hadoop** group.

2. Log in to FusionInsight Manager and choose **System > Permission > User**. On the displayed page, locate the row that contains the added user, click **More** in the **Operation** column, and select **Download Authentication Credential** to download the authentication credential file of the user to the local PC and decompress the file.
3. Copy the decompressed **user.keytab** and **krb5.conf** files to the **/opt/hadoopclient/Flink/flink/conf** directory on the client node.
4. Log in to the client node and add the service IP address of the client node and the floating IP address of FusionInsight Manager to the **jobmanager.web.allow-access-address** configuration item in the **/opt/hadoopclient/Flink/flink/conf/flink-conf.yaml** file. Use commas (,) to separate the IP addresses.

**vi /opt/hadoopclient/Flink/flink/conf/flink-conf.yaml**

5. Configure security authentication.

Add the **keytab** path and username to the **/opt/hadoopclient/Flink/flink/conf/flink-conf.yaml** configuration file.

```
security.kerberos.login.keytab: <user.keytab file path>  
security.kerberos.login.principal: <Username>
```

Example:

```
security.kerberos.login.keytab: /opt/hadoopclient/Flink/flink/conf/user.keytab  
security.kerberos.login.principal: test
```

6. Configure security hardening by referring to [Authentication and Encryption](#). Run the following commands to set a password for submitting jobs.

```
cd /opt/hadoopclient/Flink/flink/bin
```

```
sh generate_keystore.sh
```

The script automatically changes the SSL-related parameter values in the **/opt/hadoopclient/Flink/flink/conf/flink-conf.yaml** file.

7. Configure paths for the client to access the **flink.keystore** and **flink.truststore** files.

- Absolute path

After the **generate\_keystore.sh** script is executed, the **flink.keystore** and **flink.truststore** file paths are automatically set to absolute paths in the **flink-conf.yaml** file by default. In this case, you need to place the **flink.keystore** and **flink.truststore** files in the **conf** directory to the absolute paths of the Flink client and each Yarn node, respectively.

- Relative path (recommended)

Perform the following steps to set the file paths of **flink.keystore** and **flink.truststore** to relative paths and ensure that the directory where the Flink client command is executed can directly access the relative paths.

- i. Create a directory, for example, **ssl**, in **/opt/hadoopclient/Flink/flink/conf/**.

- ```
cd /opt/hadoopclient/Flink/flink/conf/
mkdir ssl
```
- ii. Move the **flink.keystore** and **flink.truststore** files to the new paths.

```
mv flink.keystore ssl/
mv flink.truststore ssl/
```
  - iii. Change the values of the following parameters to relative paths in the **flink-conf.yaml** file:

```
vi /opt/hadoopclient/Flink/flink/conf/flink-conf.yaml
security.ssl.keystore: ssl/flink.keystore
security.ssl.truststore: ssl/flink.truststore
```

**Step 5** Run a wordcount job.

- Normal cluster (Kerberos authentication disabled)
  - Run the following commands to start a session and submit a job in the session:

```
yarn-session.sh -nm "session-name"
flink run /opt/hadoopclient/Flink/flink/examples/streaming/WordCount.jar
```
  - Run the following command to submit a single job on Yarn:

```
flink run -m yarn-cluster /opt/hadoopclient/Flink/flink/examples/streaming/WordCount.jar
```
- Security cluster (Kerberos authentication enabled)
  - If the **flink.keystore** and **flink.truststore** file paths are relative paths:
    - Run the following command in the directory at the same level as **ssl** to start the session and submit the job in the session. **ssl/** is a relative path.

```
cd /opt/hadoopclient/Flink/flink/conf/
yarn-session.sh -t ssl/ -nm "session-name"
```

```
...
Cluster started: Yarn cluster with application id application_1624937999496_0017
JobManager Web Interface: http://192.168.1.150:32261
```

Start a new client connection and submit the job:

```
source /opt/hadoopclient/bigdata_env
flink run /opt/hadoopclient/Flink/flink/examples/streaming/WordCount.jar
```

```
...
Job has been submitted with JobID 587d5498fff18d8b2501fdf7ebb9c4fb
Program execution finished
Job with JobID 587d5498fff18d8b2501fdf7ebb9c4fb has finished.
Job Runtime: 19917 ms
```
    - Run the following command to submit a single job on Yarn:

```
cd /opt/hadoopclient/Flink/flink/conf/
flink run -m yarn-cluster -yt ssl/ /opt/hadoopclient/Flink/flink/examples/streaming/WordCount.jar
```

```
...
Cluster started: Yarn cluster with application id application_1624937999496_0016
Job has been submitted with JobID e9c59fb48f44feae7b62dd90336d6d7f
Program execution finished
```

Job with JobID e9c59fb48f44feae7b62dd90336d6d7f has finished.  
Job Runtime: 18155 ms

- If the **flink.keystore** and **flink.truststore** file paths are absolute paths:
  - Run the following commands to start a session and submit a job in the session:
 


```
cd /opt/hadoopclient/Flink/flink/conf/
yarn-session.sh -nm "session-name"
flink run /opt/hadoopclient/Flink/flink/examples/streaming/WordCount.jar
```
  - Run the following command to submit a single job on Yarn:
 

```
flink run -m yarn-cluster /opt/hadoopclient/Flink/flink/examples/streaming/WordCount.jar
```

**Step 6** Log in to FusionInsight Manager as a running user, go to the native page of the Yarn service, find the application of the corresponding job, and click the application name to go to the job details page.

- If the job is not completed, click **Tracking URL** to go to the native Flink page and view the job running information.
- If the job submitted in a session has been completed, you can click **Tracking URL** to log in to the native Flink service page to view job information.

Figure 4-1 Application



----End

## 4.2 Viewing Flink Job Information

You can view Flink job information on the Yarn web UI.

### Prerequisites

The Flink service has been installed in a cluster.

## Accessing the Yarn Web UI

**Step 1** Log in to MRS Manager and click the **Services** tab. On the displayed page, select **Yarn > Yarn Summary**.

**Step 2** Click the link next to **ResourceManager WebUI** to go to the Yarn web UI page.

----End

## 4.3 Flink Configuration Management

### 4.3.1 Configuring Parameter Paths

All parameters of Flink must be set on a client. The path of a configuration file is as follows: **Client installation path/Flink/flink/conf/flink-conf.yaml**.

#### NOTE

- You are advised to modify the **flink-conf.yaml** configuration file on the client. The configuration format of the YAML file is *key: value*.  
Example: **taskmanager.heap.size: 1024mb**  
Note that a space is required between *key:* and *value*.
- If parameters are modified in the Flink service configuration, you need to download and install the client again after the configuration is complete.

### 4.3.2 JobManager & TaskManager

#### Scenarios

JobManager and TaskManager are main components of Flink. You can configure the parameters for different security and performance scenarios on the client.

#### Configuration Description

Main configuration items include communication port, memory management, connection retry, and so on.

**Table 4-1** Parameters

| Parameter             | Description                                     | Default Value | Mandatory |
|-----------------------|-------------------------------------------------|---------------|-----------|
| taskmanager.rpc.port  | IPC port range of TaskManager                   | 32326-32390   | No        |
| client.rpc.port       | Akka system listening port on the Flink client. | 32651-32720   | No        |
| taskmanager.data.port | Data exchange port range of TaskManager         | 32391-32455   | No        |

| Parameter                        | Description                                                                                                                                                                                                                                                                                                                                                                                         | Default Value | Mandatory |
|----------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| taskmanager.data.<br>ssl.enabled | Whether to enable secure sockets layer (SSL) encryption for data transfer between TaskManagers. This parameter is valid only when the global switch <b>security.ssl</b> is enabled.                                                                                                                                                                                                                 | false         | No        |
| jobmanager.heap.<br>size         | Size of the heap memory of JobManager. In <b>yarn-session</b> mode, the value can be transmitted by only the <b>-jm</b> parameter. In <b>yarn-cluster</b> mode, the value can be transmitted by only the <b>-yjm</b> parameter. If the value is smaller than <b>yarn.scheduler.minimum-allocation-mb</b> in the Yarn configuration file, the Yarn configuration value is used. Unit: B/KB/MB/GB/TB. | 1024mb        | No        |

| Parameter                     | Description                                                                                                                                                                                                                                                                                                                                                                                                | Default Value | Mandatory |
|-------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| taskmanager.heap.size         | Size of the heap memory of TaskManager. In <b>yarn-session</b> mode, the value can be transmitted by only the <b>-tm</b> parameter. In <b>yarn-cluster</b> mode, the value can be transmitted by only the <b>-ytm</b> parameter. If the value is smaller than <b>yarn.scheduler.minimum-allocation-mb</b> in the Yarn configuration file, the Yarn configuration value is used. The unit is B/KB/MB/GB/TB. | 1024mb        | No        |
| taskmanager.numberOfTaskSlots | Number of slots occupied by TaskManager. Generally, the value is configured as the number of cores of the Node. In <b>yarn-session</b> mode, the value can be transmitted by only the <b>-s</b> parameter. In <b>yarn-cluster</b> mode, the value can be transmitted by only the <b>-ys</b> parameter.                                                                                                     | 1             | No        |

| Parameter                           | Description                                                                                                                                                                                   | Default Value | Mandatory |
|-------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| parallelism.default                 | Default degree of parallelism, which is used for jobs for which the degree of parallelism is not specified                                                                                    | 1             | No        |
| taskmanager.network.numberOfBuffers | Number of TaskManager network transmission buffer stacks. If an error indicates insufficient system buffer, increase the parameter value.                                                     | 2048          | No        |
| taskmanager.memory.fraction         | Ratio of JVM heap memory that TaskManager reserves for sorting, hash tables, and caching of intermediate results.                                                                             | 0.7           | No        |
| taskmanager.memory.off-heap         | Whether TaskManager uses off-heap memory for sorting, hash tables and intermediate status. You are advised to enable this item for large memory needs to improve memory operation efficiency. | false         | Yes       |
| taskmanager.memory.segment-size     | Size of the memory buffer used by the memory manager and network stack<br>The unit is bytes.                                                                                                  | 32768         | No        |

| Parameter                               | Description                                                                                                                                                                                                                            | Default Value | Mandatory |
|-----------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| taskmanager.memory.preallocate          | Whether TaskManager allocates reserved memory space upon startup. You are advised to enable this item when off-heap memory is used.                                                                                                    | false         | No        |
| taskmanager.debug.memory.startLogThread | Enable this item for debugging Flink memory and garbage collection (GC)-related problems. TaskManager periodically collects memory and GC statistics, including the current utilization of heap and off-heap memory pools and GC time. | false         | No        |
| taskmanager.debug.memory.logIntervalMs  | Interval at which TaskManager periodically collects memory and GC statistics.                                                                                                                                                          | 0             | No        |
| taskmanager.maxRegistrationDuration     | Maximum duration of TaskManager registration on JobManager. If the actual duration exceeds the value, TaskManager is disabled.                                                                                                         | 5 min         | No        |

| Parameter                              | Description                                                                                                                                | Default Value                                                                                                                                                      | Mandatory |
|----------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|
| taskmanager.initial-registration-pause | Initial interval between two consecutive registration attempts. The value must contain a time unit (ms/s/min/h/d), for example, 5 seconds. | 500ms<br><b>NOTE</b><br>The time value and unit are separated by half-width spaces. ms/s/m/h/d indicates millisecond, second, minute, hour, and day, respectively. | No        |
| taskmanager.max-registration-pause     | Maximum registration retry interval in case of TaskManager registration failures. The unit is ms/s/m/h/d.                                  | 30s                                                                                                                                                                | No        |
| taskmanager.refused-registration-pause | Retry interval when a TaskManager registration connection is rejected by JobManager. The unit is ms/s/m/h/d.                               | 10s                                                                                                                                                                | No        |
| task.cancellation.interval             | Interval between two successive task cancellation attempts. The unit is millisecond.                                                       | 30000                                                                                                                                                              | No        |

| Parameter                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                         | Default Value | Mandatory |
|---------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| classloader.resolve-order | Class resolution policies defined when classes are loaded from user codes, which means whether to first check the user code JAR file ( <b>child-first</b> ) or the application class path ( <b>parent-first</b> ). The default setting indicates that the class is first loaded from the user code JAR file, which means that the user code JAR file can contain and load dependencies that are different from those used by Flink. | child-first   | No        |
| slot.idle.timeout         | Timeout for an idle slot in Slot Pool, in milliseconds.                                                                                                                                                                                                                                                                                                                                                                             | 50000         | No        |
| slot.request.timeout      | Timeout for requesting a slot from Slot Pool, in milliseconds.                                                                                                                                                                                                                                                                                                                                                                      | 300000        | No        |
| task.cancellation.timeout | Timeout of task cancellation, in milliseconds. If a task cancellation times out, a fatal TaskManager error may occur. If this parameter is set to <b>0</b> , no error is reported when a task cancellation times out.                                                                                                                                                                                                               | 180000        | No        |

| Parameter                                     | Description                                                                                                                                                                                                                                                                                                                                                                                 | Default Value | Mandatory |
|-----------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| taskmanager.network.detailed-metrics          | Indicates whether to enable the detailed metrics monitoring of network queue lengths.                                                                                                                                                                                                                                                                                                       | false         | No        |
| taskmanager.network.memory.buffer-per-channel | Maximum number of network buffers used by each output/input channel (sub-partition/incoming channel). In credit-based flow control mode, this indicates how much credit is in each input channel. It should be configured with at least 2 buffers to deliver good performance. One buffer is used to receive in-flight data in the sub-partition, and the other for parallel serialization. | 2             | No        |

| Parameter                                            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 | Default Value | Mandatory |
|------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| taskmanager.network.memory.floating-buffers-per-gate | Number of extra network buffers used by each output gate (result partition) or input gate, indicating the amount of floating credit shared among all input channels in credit-based flow control mode. Floating buffers are distributed based on the backlog feedback (real-time output buffers in sub-partitions) and can help mitigate back pressure caused by unbalanced data distribution among sub-partitions. Increase this value if the round-trip time between nodes is long and/or the number of machines in the cluster is large. | 8             | No        |

| Parameter                           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           | Default Value | Mandatory |
|-------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| taskmanager.network.memory.fraction | Ratio of JVM memory used for network buffers, which determines how many streaming data exchange channels a TaskManager can have at the same time and the extent of channel buffering. Increase this value or the values of <b>taskmanager.network.memory.min</b> and <b>taskmanager.network.memory.max</b> if the job is rejected or a warning indicating that the system does not have enough buffers is received. Note that the values of <b>taskmanager.network.memory.min</b> and <b>taskmanager.network.memory.max</b> may overwrite this value. | 0.1           | No        |
| taskmanager.network.memory.max      | Maximum memory size of the network buffer. The value must contain a unit (B/KB/MB/GB/TB).                                                                                                                                                                                                                                                                                                                                                                                                                                                             | 1 GB          | No        |

| Parameter                                   | Description                                                                                                                                                                             | Default Value | Mandatory |
|---------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| taskmanager.network.memory.min              | Minimum memory size of the network buffer. The value must contain a unit (B/KB/MB/GB/TB).                                                                                               | 64 MB         | No        |
| taskmanager.network.request-backoff.initial | Minimum backoff for partition requests of input channels.                                                                                                                               | 100           | No        |
| taskmanager.network.request-backoff.max     | Maximum backoff for partition requests of input channels.                                                                                                                               | 10000         | No        |
| taskmanager.registration.timeout            | Timeout for TaskManager registration. TaskManager will be terminated if it is not successfully registered within the specified time. The value must contain a time unit (ms/s/min/h/d). | 5 min         | No        |
| resourcemanager.taskmanager.timeout         | Timeout interval for releasing an idle TaskManager, in milliseconds.                                                                                                                    | 30000         | No        |

### 4.3.3 Blob

#### Scenarios

The Blob server on the JobManager node is used to receive JAR files uploaded by users on the client, send JAR files to TaskManager, and transfer log files. Flink provides some items for configuring the Blob server. You can configure them in the **flink-conf.yaml** configuration file.

#### Configuration Description

Users can configure the port, SSL, retry times, and concurrency.

**Table 4-2** Parameters

| Parameter                              | Description                                                                                                                                                       | Default Value  | Mandatory |
|----------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------|-----------|
| blob.server.port                       | Blob server port                                                                                                                                                  | 32456 to 32520 | No        |
| blob.service.ssl.enabled               | Indicates whether to enable the encryption for the blob transmission channel. This parameter is valid only when the global switch <b>security.ssl</b> is enabled. | true           | Yes       |
| blob.fetch.retries                     | Number of times that TaskManager tries to download blob files from JobManager.                                                                                    | 50             | No        |
| blob.fetch.num-concurrent              | Number of concurrent tasks for downloading blob files supported by JobManager.                                                                                    | 50             | No        |
| blob.fetch.backlog                     | Number of blob files, such as <b>.jar</b> files, to be downloaded in the queue supported by JobManager. The unit is count.                                        | 1000           | No        |
| library-cache-manager.cleanup.interval | Interval at which JobManager deletes the JAR files stored on the HDFS when the user cancels the Flink job. The unit is second.                                    | 3600           | No        |

### 4.3.4 Distributed Coordination (via Akka)

#### Scenarios

The Akka actor model is the basis of communications between the Flink client and JobManager, JobManager and TaskManager, as well as TaskManager and

TaskManager. Flink enables you to configure the Akka connection parameters in the **flink-conf.yaml** file based on the network environment or optimization policy.

## Configuration Description

You can configure timeout settings of message sending and waiting, and the Akka listening mechanism Deathwatch.

**Table 4-3** Parameters

| Parameter           | Description                                                                                                                                                                                                                           | Default Value | Mandatory |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| akka.ask.timeout    | Timeout duration of Akka asynchronous and block requests. If a Flink timeout failure occurs, this value can be increased. Timeout occurs when the machine processing speed is slow or the network is blocked. The unit is ms/s/m/h/d. | 10s           | No        |
| akka.lookup.timeout | Timeout duration for JobManager actor object searching. The unit is ms/s/m/h/d.                                                                                                                                                       | 10s           | No        |
| akka.framesize      | Maximum size of the message transmitted between JobManager and TaskManager. If a Flink error occurs because the message exceeds this limit, the value can be increased. The unit is b/B/KB/MB.                                        | 10485760b     | No        |

| Parameter                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   | Default Value | Mandatory |
|-------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| akka.watch.heartbeat.interval | <p>Heartbeat interval at which the Akka DeathWatch mechanism detects disconnected TaskManager. If TaskManager is frequently and incorrectly marked as disconnected due to heartbeat loss or delay, the value can be increased. The unit is ms/s/m/h/d.</p> <p><b>NOTE</b><br/>For detailed explanation of DeathWatch, see the Akka official website: <a href="http://doc.akka.io/docs/akka/snapshot/scala/remoting.html#failure-detector">http://doc.akka.io/docs/akka/snapshot/scala/remoting.html#failure-detector</a>.</p> | 10s           | No        |
| akka.watch.heartbeat.pause    | <p>Acceptable heartbeat pause for Akka DeathWatch mechanism. A small value indicates that irregular heartbeat is not accepted. The unit is ms/s/m/h/d.</p> <p><b>NOTE</b><br/>For detailed explanation of DeathWatch, see the Akka official website: <a href="http://doc.akka.io/docs/akka/snapshot/scala/remoting.html#failure-detector">http://doc.akka.io/docs/akka/snapshot/scala/remoting.html#failure-detector</a>.</p>                                                                                                 | 60s           | No        |

| Parameter            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                    | Default Value | Mandatory |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| akka.watch.threshold | <p>DeathWatch failure detection threshold. A small value may mark normal TaskManager as failed and a large value increases failure detection time.</p> <p><b>NOTE</b><br/>                     For detailed explanation of DeathWatch, see the Akka official website: <a href="http://doc.akka.io/docs/akka/snapshot/scala/remoting.html#failure-detector">http://doc.akka.io/docs/akka/snapshot/scala/remoting.html#failure-detector</a>.</p> | 12            | No        |
| akka.tcp.timeout     | <p>Timeout duration of Transmission Control Protocol (TCP) connection request. If TaskManager connection timeout occurs frequently due to the network congestion, the value can be increased. The unit is ms/s/m/h/d.</p>                                                                                                                                                                                                                      | 20s           | No        |

| Parameter                 | Description                                                                                                                                                                                                                                                                                | Default Value                                                           | Mandatory |
|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------|-----------|
| akka.throughput           | Number of messages processed by Akka in batches. After an operation, the processing thread is returned to the thread pool. A small value indicates the fair scheduling for actor message processing. A large value indicates improved overall performance but lowered scheduling fairness. | 15                                                                      | No        |
| akka.log.lifecycle.events | Switch of Akka remote time logging, which can be enabled for debugging.                                                                                                                                                                                                                    | false                                                                   | No        |
| akka.startup-timeout      | Timeout interval before a remote component fails to be started. The value must contain a time unit (ms/s/min/h/d).                                                                                                                                                                         | The default value is the same as the value of <b>akka.ask.timeout</b> . | No        |
| akka.ssl.enabled          | Switch of Akka communication SSL. This parameter is valid only when the global switch <b>security.ssl</b> is enabled.                                                                                                                                                                      | true                                                                    | Yes       |

| Parameter                                       | Description                                                                                                                                                                                                                                                      | Default Value | Mandatory |
|-------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| akka.client-socket-worker-pool.pool-size-factor | Factor that is used to determine the thread pool size. The pool size is calculated based on the following formula: $\text{ceil}(\text{available processors} * \text{factor})$ . The size is bounded by the <b>pool-size-min</b> and <b>pool-size-max</b> values. | 1.0           | No        |
| akka.client-socket-worker-pool.pool-size-max    | Maximum number of threads calculated based on the factor.                                                                                                                                                                                                        | 2             | No        |
| akka.client-socket-worker-pool.pool-size-min    | Minimum number of threads calculated based on the factor.                                                                                                                                                                                                        | 1             | No        |
| akka.client.timeout                             | Timeout duration of the client. The value must contain a time unit (ms/s/min/h/d).                                                                                                                                                                               | 60s           | No        |
| akka.server-socket-worker-pool.pool-size-factor | Factor that is used to determine the thread pool size. The pool size is calculated based on the following formula: $\text{ceil}(\text{available processors} * \text{factor})$ . The size is bounded by the <b>pool-size-min</b> and <b>pool-size-max</b> values. | 1.0           | No        |

| Parameter                                    | Description                                               | Default Value | Mandatory |
|----------------------------------------------|-----------------------------------------------------------|---------------|-----------|
| akka.server-socket-worker-pool.pool-size-max | Maximum number of threads calculated based on the factor. | 2             | No        |
| akka.server-socket-worker-pool.pool-size-min | Minimum number of threads calculated based on the factor. | 1             | No        |

### 4.3.5 SSL

#### Scenarios

When the secure Flink cluster is required, SSL-related configuration items must be set.

#### Configuration Description

Configuration items include the SSL switch, certificate, password, and encryption algorithm.

**Table 4-4** Parameters

| Parameter                      | Description                                 | Default Value                                                                                                                                                                                                                                       | Mandatory |
|--------------------------------|---------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|
| security.ssl.enabled           | Main switch of internal communication SSL.  | The value is automatically configured according to the cluster installation mode. <ul style="list-style-type: none"> <li>Security mode: The default value is <b>true</b>.</li> <li>Non-security mode: The default value is <b>false</b>.</li> </ul> | Yes       |
| security.ssl.keystore          | Java keystore file.                         | -                                                                                                                                                                                                                                                   | Yes       |
| security.ssl.keystore-password | Password used to decrypt the keystore file. | -                                                                                                                                                                                                                                                   | Yes       |

| Parameter                        | Description                                                                                                                                                                                                                                                                                 | Default Value                                                                                                                                                            | Mandatory |
|----------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|
| security.ssl.key-password        | Password used to decrypt the server key in the keystore file.                                                                                                                                                                                                                               | -                                                                                                                                                                        | Yes       |
| security.ssl.truststore          | <b>truststore</b> file containing the public CA certificates.                                                                                                                                                                                                                               | -                                                                                                                                                                        | Yes       |
| security.ssl.truststore-password | Password used to decrypt the truststore file.                                                                                                                                                                                                                                               | -                                                                                                                                                                        | Yes       |
| security.ssl.protocol            | SSL transmission protocol version.                                                                                                                                                                                                                                                          | TLSv1.2                                                                                                                                                                  | Yes       |
| security.ssl.algorithms          | Supported SSL standard algorithm. For details, see the Java official website: <a href="http://docs.oracle.com/javase/8/docs/technotes/guides/security/StandardNames.html#ciphersuites">http://docs.oracle.com/javase/8/docs/technotes/guides/security/StandardNames.html#ciphersuites</a> . | The default value: "TLS_DHE_RSA_WITH_AES_128_GCM_SHA256,TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256,TLS_DHE_RSA_WITH_AES_256_GCM_SHA384,TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384" | Yes       |

### 4.3.6 Network communication (via Netty)

#### Scenario

When Flink runs a job, data transmission and reverse pressure detection between tasks depend on Netty. In certain environments, **Netty** parameters should be configured.

#### Configuration Description

For advanced optimization, you can modify the following Netty configuration items. The default configuration can meet the requirements of tasks of large-scale clusters with high concurrent throughput. For details about the parameters, visit the Netty official website at <http://netty.io/>.

**Table 4-5** Parameter description

| Parameter                                          | Description                                                                                                                                                                | Default Value | Mandatory |
|----------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| taskmanager.network.netty.num-arenas               | Number of Netty memory blocks.                                                                                                                                             | 1             | No        |
| taskmanager.network.netty.server.numThreads        | Number of Netty server threads                                                                                                                                             | 1             | No        |
| taskmanager.network.netty.client.numThreads        | Number of Netty client threads                                                                                                                                             | 1             | No        |
| taskmanager.network.netty.client.connectTimeoutSec | Netty client connection timeout duration. Unit: second                                                                                                                     | 120           | No        |
| taskmanager.network.netty.sendReceiveBufferSize    | Size of Netty sending and receiving buffers. This defaults to the system buffer size ( <b>cat /proc/sys/net/ipv4/tcp_[rw]mem</b> ) and is 4 MB in modern Linux. Unit: byte | 4096          | No        |
| taskmanager.network.netty.transport                | Netty transport type, either <b>nio</b> or <b>epoll</b>                                                                                                                    | nio           | No        |

### 4.3.7 JobManager Web Frontend

#### Scenarios

When JobManager is started, the web server in the same process is also started.

- You can access the web server to obtain information about the current Flink cluster, including information about JobManager, TaskManager, and running jobs in the cluster.
- You can configure parameters of the web server.

#### Configuration Description

Configuration items include the port, temporary directory, display items, error redirection, and security-related items.

**Table 4-6** Parameters

| Parameter                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | Default Value                                                                 | Mandatory |
|------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------|-----------|
| flink.security.enable              | <p>When installing a Flink cluster, you are required to select <b>security mode</b> or <b>normal mode</b>.</p> <ul style="list-style-type: none"> <li>• If <b>security mode</b> is selected, the value of <b>flink.security.enable</b> is automatically set to <b>true</b>.</li> <li>• If <b>normal mode</b> is selected, the value of <b>flink.security.enable</b> is automatically set to <b>false</b>.</li> </ul> <p>If you want to check whether Flink cluster is in security mode or normal mode, view the value of <b>flink.security.enable</b>.</p> | The value is automatically configured based on the cluster installation mode. | No        |
| rest.bind-port                     | Web port. Value range: 32261-32325.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | 32261-32325                                                                   | No        |
| jobmanager.web.history             | Number of recent jobs to be displayed.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     | 5                                                                             | No        |
| jobmanager.web.checkpoints.disable | Indicates whether to disable checkpoint statistics.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | false                                                                         | No        |
| jobmanager.web.checkpoints.history | Number of checkpoint statistical records.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  | 10                                                                            | No        |

| Parameter                                         | Description                                                                                                                                 | Default Value | Mandatory |
|---------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| jobmanager.web.backpressure.cleanup-interval      | Interval for clearing unaccessed backpressure records. The unit is millisecond.                                                             | 600000        | No        |
| jobmanager.web.backpressure.refresh-interval      | Interval for updating backpressure records. The unit is millisecond.                                                                        | 60000         | No        |
| jobmanager.web.backpressure.num-samples           | Number of stack tracing records for reverse pressure calculation.                                                                           | 100           | No        |
| jobmanager.web.backpressure.delay-between-samples | Sampling interval for reverse pressure calculation. The unit is millisecond.                                                                | 50            | No        |
| jobmanager.web.ssl.enabled                        | Whether SSL encryption is enabled for web transmission. This parameter is valid only when the global switch <b>security.ssl</b> is enabled. | false         | Yes       |
| jobmanager.web.accesslog.enable                   | Switch to enable or disable web operation logs. The log is stored in <b>webaccess.log</b> .                                                 | true          | Yes       |
| jobmanager.web.x-frame-options                    | Value of the HTTP security header <b>X-Frame-Options</b> . The value can be <b>SAMEORIGIN</b> , <b>DENY</b> , or <b>ALLOW-FROM uri</b> .    | DENY          | Yes       |
| jobmanager.web.cache-directive                    | Whether the web page can be cached.                                                                                                         | no-store      | Yes       |

| Parameter                                  | Description                                                                                                            | Default Value           | Mandatory |
|--------------------------------------------|------------------------------------------------------------------------------------------------------------------------|-------------------------|-----------|
| jobmanager.web.expires-time                | Expiration duration of web page cache. The unit is millisecond.                                                        | 0                       | Yes       |
| jobmanager.web.allow-access-address        | Web access whitelist. IP addresses are separated by commas (.). Only IP addresses in the whitelist can access the web. | *                       | Yes       |
| jobmanager.web.access-control-allow-origin | Web page same-origin policy that prevents cross-domain attacks.                                                        | *                       | Yes       |
| jobmanager.web.refresh-interval            | Web page refresh interval. The unit is millisecond.                                                                    | 3000                    | Yes       |
| jobmanager.web.logout-timer                | Automatic logout interval when no operation is performed. The unit is millisecond.                                     | 600000                  | Yes       |
| jobmanager.web.403-redirect-url            | Web page access error 403. If 403 error occurs, the page switch to a specified page.                                   | Automatic configuration | Yes       |
| jobmanager.web.404-redirect-url            | Web page access error 404. If 404 error occurs, the page switch to a specified page.                                   | Automatic configuration | Yes       |
| jobmanager.web.415-redirect-url            | Web page access error 415. If 415 error occurs, the page switch to a specified page.                                   | Automatic configuration | Yes       |
| jobmanager.web.500-redirect-url            | Web page access error 500. If 500 error occurs, the page switch to a specified page.                                   | Automatic configuration | Yes       |

| Parameter                      | Description                                                                 | Default Value | Mandatory |
|--------------------------------|-----------------------------------------------------------------------------|---------------|-----------|
| rest.await-leader-timeout      | Time of the client waiting for the leader address. The unit is millisecond. | 30000         | No        |
| rest.client.max-content-length | Maximum content length that the client handles (unit: bytes).               | 104857600     | No        |
| rest.connection-timeout        | Maximum time for the client to establish a TCP connection (unit: ms).       | 15000         | No        |
| rest.idleness-timeout          | Maximum time for a connection to stay idle before failing (unit: ms).       | 300000        | No        |
| rest.retry.delay               | The time that the client waits between retries (unit: ms).                  | 3000          | No        |
| rest.retry.max-attempts        | The number of retry times if a retrievable operator fails.                  | 20            | No        |
| rest.server.max-content-length | Maximum content length that the server handles (unit: bytes).               | 104857600     | No        |
| rest.server.numThreads         | Maximum number of threads for the asynchronous processing of requests.      | 4             | No        |
| web.timeout                    | Timeout for web monitor (unit: ms).                                         | 10000         | No        |

## 4.3.8 File Systems

### Scenario

Result files are created when tasks are running. Flink enables you to configure parameters for file creation.

### Configuration Description

Configuration items include overwriting policy and directory creation.

**Table 4-7** Parameter description

| Parameter          | Description                                                                 | Default Value | Mandatory |
|--------------------|-----------------------------------------------------------------------------|---------------|-----------|
| fs.overwrite-files | Whether to overwrite the existing file by default when the file is written. | false         | No        |

| Parameter                         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | Default Value | Mandatory |
|-----------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| fs.output.always-create-directory | <p>When the degree of parallelism (DOP) of file writing programs is greater than 1, a directory is created under the output file path and different result files (one for each parallel writing program) are stored in the directory.</p> <ul style="list-style-type: none"> <li>• If this parameter is set to <b>true</b>, a directory is created for the writing program whose DOP is 1 and a result file is stored in the directory.</li> <li>• If this parameter is set to <b>false</b>, the file of the writing program whose DOP is 1 is created directly in the output path and no directory is created.</li> </ul> | false         | No        |

## 4.3.9 State Backend

### Scenarios

Flink enables HA and job exception, as well as job pause and recovery during version upgrade. Flink depends on state backend to store job states and on the restart strategy to restart a job. You can configure state backend and the restart strategy.

## Configuration Description

Configuration items include the state backend type, storage path, and restart strategy.

**Table 4-8** Parameters

| Parameter                             | Description                                                                                                                                                                                                                                                                                 | Default Value                                                                                                                                                                                               | Mandatory                  |
|---------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------|
| state.backend.fs.checkpointdir        | Path when the backend is set to <b>filesystem</b> . The path must be accessible by JobManager. Only the local mode is supported. In the cluster mode, use an HDFS path.                                                                                                                     | hdfs:///flink/checkpoints                                                                                                                                                                                   | No                         |
| state.savepoints.dir                  | Savepoint storage directory used by Flink to restore and update jobs. When a savepoint is triggered, the metadata of the savepoint is saved to this directory.                                                                                                                              | hdfs:///flink/savepoint                                                                                                                                                                                     | Mandatory in security mode |
| restart-strategy                      | Default restart policy, which is used for jobs for which no restart policy is specified. The options are as follows: <ul style="list-style-type: none"> <li>fixed-delay</li> <li>failure-rate</li> <li>none</li> </ul>                                                                      | none                                                                                                                                                                                                        | No                         |
| restart-strategy.fixed-delay.attempts | Number of retry times when the fixed-delay restart strategy is used. For details, see <a href="https://ci.apache.org/projects/flink/flink-docs-release-1.12/dev/task_failure_recover.html">https://ci.apache.org/projects/flink/flink-docs-release-1.12/dev/task_failure_recover.html</a> . | <ul style="list-style-type: none"> <li>If the checkpoint is enabled, the default value is the value of <b>Integer.MAX_VALUE</b>.</li> <li>If the checkpoint is disabled, the default value is 3.</li> </ul> | No                         |

| Parameter                                               | Description                                                                                                                                                                                                                                                                                                                                            | Default Value                                                                                                                                                                                                | Mandatory |
|---------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|
| restart-strategy.fixed-delay.delay                      | Retry interval when the fixed-delay strategy is used. The unit is ms/s/m/h/d.                                                                                                                                                                                                                                                                          | <ul style="list-style-type: none"> <li>If the checkpoint is enabled, the default value is 10s.</li> <li>If the checkpoint is disabled, the default value is the value of <b>akka.ask.timeout</b>.</li> </ul> | No        |
| restart-strategy.failure-rate.max-failures-per-interval | Maximum number of restart times in a specified period before a job fails when the fault rate policy is used. For details about the policies, see <a href="https://ci.apache.org/projects/flink/flink-docs-release-1.12/dev/task_failure_recover.html">https://ci.apache.org/projects/flink/flink-docs-release-1.12/dev/task_failure_recover.html</a> . | 1                                                                                                                                                                                                            | No        |
| restart-strategy.failure-rate.failure-rate-interval     | Retry interval when the failure-rate strategy is used. The unit is ms/s/m/h/d.                                                                                                                                                                                                                                                                         | 60 s                                                                                                                                                                                                         | No        |
| restart-strategy.failure-rate.delay                     | Retry interval when the failure-rate strategy is used. The unit is ms/s/m/h/d.                                                                                                                                                                                                                                                                         | The default value is the same as the value of <b>akka.ask.timeout</b> . For details, see <a href="#">Distributed Coordination (via Akka)</a> .                                                               | No        |

## 4.3.10 Kerberos-based Security

### Scenarios

Flink Kerberos configuration items must be configured in security mode.

## Configuration Description

The configuration items include **keytab**, **principal**, and **cookie** of Kerberos.

**Table 4-9** Parameters

| Parameter                         | Description                                                                                                                                                           | Default Value                                                                                                                                                                                                                                            | Mandatory |
|-----------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|
| security.kerberos.login.keytab    | Keytab file path. This parameter is a client parameter.                                                                                                               | Configure the parameter based on actual service requirements.                                                                                                                                                                                            | Yes       |
| security.kerberos.login.principal | A parameter on the client. If <b>security.kerberos.login.keytab</b> and <b>security.kerberos.login.principal</b> are both set, keytab certificate is used by default. | Configure the parameter based on actual service requirements.                                                                                                                                                                                            | No        |
| security.kerberos.login.contexts  | Contexts of the jass file generated by Flink. This parameter is a server parameter.                                                                                   | Client, KafkaClient                                                                                                                                                                                                                                      | Yes       |
| security.enable                   | Certificate enabling switch of the Flink internal module. This parameter is a client parameter.                                                                       | This parameter is configured automatically according to the cluster installation mode. <ul style="list-style-type: none"> <li>Security mode: The default value is <b>true</b>.</li> <li>Non-security mode: The default value is <b>false</b>.</li> </ul> | Yes       |
| security.cookie                   | Module certificate token. This parameter is a client parameter. It must be configured and cannot be left empty when <b>security.enable</b> is enabled.                | Configure the parameter based on actual service requirements.                                                                                                                                                                                            | Yes       |

## 4.3.11 HA

### Scenarios

The Flink HA mode depends on ZooKeeper. Therefore, ZooKeeper-related configuration items must be set.

### Configuration Description

Configuration items include the ZooKeeper address, path, and security certificate.

**Table 4-10** Parameters

| Parameter                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                | Default Value           | Mandatory |
|------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------|-----------|
| high-availability                  | <p>Whether HA is enabled. Only the following two modes are supported currently:</p> <ol style="list-style-type: none"> <li>1. none: Only a single JobManager is running. The checkpoint is disabled for JobManager.</li> <li>2. ZooKeeper: <ul style="list-style-type: none"> <li>• In non-Yarn mode, multiple JobManagers are supported and the leader JobManager is elected.</li> <li>• In Yarn mode, only one JobManager exists.</li> </ul> </li> </ol> | zookeeper               | No        |
| high-availability.zookeeper.quorum | ZooKeeper quorum address.                                                                                                                                                                                                                                                                                                                                                                                                                                  | Automatic configuration | No        |

| Parameter                                             | Description                                                                                                | Default Value                                                           | Mandatory |
|-------------------------------------------------------|------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------|-----------|
| high-availability.zookeeper.path.root                 | Root directory that Flink creates on ZooKeeper, storing metadata required in HA mode.                      | /flink                                                                  | No        |
| high-availability.storageDir                          | Directory for storing JobManager metadata of state backend. ZooKeeper stores only pointers to actual data. | hdfs:///flink/recovery                                                  | No        |
| high-availability.zookeeper.client.session-timeout    | Session timeout duration on the ZooKeeper client. The unit is millisecond.                                 | 60000                                                                   | No        |
| high-availability.zookeeper.client.connection-timeout | Connection timeout duration on the ZooKeeper client. The unit is millisecond.                              | 15000                                                                   | No        |
| high-availability.zookeeper.client.retry-wait         | Retry waiting time on the ZooKeeper client. The unit is millisecond.                                       | 5000                                                                    | No        |
| high-availability.zookeeper.client.max-retry-attempts | Maximum retry times on the ZooKeeper client.                                                               | 3                                                                       | No        |
| high-availability.job.delay                           | Delay of job restart when JobManager recovers.                                                             | The default value is the same as the value of <b>akka.ask.timeout</b> . | No        |

| Parameter                              | Description                                                                                                                                                                                                                                                                  | Default Value                                                                                                                                                                                                                                              | Mandatory |
|----------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|
| high-availability.zookeeper.client.acl | ACL (open creator) of the ZooKeeper node. For ACL options, see <a href="https://zookeeper.apache.org/doc/r3.5.1-alpha/zookeeperProgrammers.html#sc_BuiltinACLschemes">https://zookeeper.apache.org/doc/r3.5.1-alpha/zookeeperProgrammers.html#sc_BuiltinACLschemes</a> .     | This parameter is configured automatically according to the cluster installation mode. <ul style="list-style-type: none"> <li>Security mode: The default value is <b>creator</b>.</li> <li>Non-security mode: The default value is <b>open</b>.</li> </ul> | Yes       |
| zookeeper.sasl.disable                 | Simple authentication and security layer (SASL)-based certificate enable switch.                                                                                                                                                                                             | This parameter is configured automatically according to the cluster installation mode. <ul style="list-style-type: none"> <li>Security mode: The default value is <b>false</b>.</li> <li>Non-security mode: The default value is <b>true</b>.</li> </ul>   | Yes       |
| zookeeper.sasl.service-name            | <ul style="list-style-type: none"> <li>If the ZooKeeper server configures a service whose name is different from <b>ZooKeeper</b>, this configuration item can be set.</li> <li>If service names on the client and server are inconsistent, authentication fails.</li> </ul> | zookeeper                                                                                                                                                                                                                                                  | Yes       |

## 4.3.12 Environment

### Scenario

In scenarios raising special requirements on JVM configuration, users can use configuration items to transfer JVM parameters to the client, JobManager, and TaskManager.

### Configuration

Configuration items include JVM parameters.

**Table 4-11** Parameter description

| Parameter     | Description                                                                                                                                             | Default Value                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   | Mandatory |
|---------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------|
| env.java.opts | JVM parameter, which is transferred to the startup script, JobManager, TaskManager, and Yarn client. For example, transfer remote debugging parameters. | -<br>Xloggc:<LOG_DIR >/gc.log -XX:<br>+PrintGCDetails -XX:-<br>OmitStackTraceln-<br>FastThrow -XX:<br>+PrintGCTimeSta<br>mps -XX:<br>+PrintGCDateSta<br>mps -XX:<br>+UseGCLogFileRot<br>ation -<br>XX:NumberOfGCL<br>ogFiles=20 -<br>XX:GCLogFileSiz<br>e=20M -<br>Djdk.tls.ephemera<br>LDHKeySize=2048<br>-<br>Djava.library.path<br>=\$<br>{HADOOP_COMM<br>ON_HOME}/lib/<br>native -<br>Djava.net.preferIP<br>v4Stack=true -<br>Djava.net.preferIP<br>v6Addresses=false<br>-<br>Dbeetle.applicatio<br>n.home.path=/opt<br>/xxx/Bigdata/<br>common/runtime/<br>security/config | No        |

## 4.3.13 Yarn

### Scenario

Flink runs on a Yarn cluster and JobManager runs on ApplicationMaster. Certain configuration parameters of JobManager depend on Yarn. By setting Yarn-related configuration items, Flink is enabled to run better on Yarn.

### Configuration Description

The configuration items include the memory, virtual kernel, and port of the Yarn container.

**Table 4-12** Parameter description

| Parameter                      | Description                                                                                                                                                                                                                                                                   | Default Value | Mandatory |
|--------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|-----------|
| yarn.maximum-failed-containers | Maximum number of containers the system is going to reallocate in case of a container failure of TaskManager The default value is the number of TaskManagers when the Flink cluster is started.                                                                               | 5             | No        |
| yarn.application-attempts      | Number of ApplicationMaster restarts. The value is the maximum value in the validity interval that is set to Akka's timeout in Flink. After the restart, the IP address and port number of ApplicationMaster will change and you will need to connect to the client manually. | 2             | No        |

| Parameter                    | Description                                                                                          | Default Value                                         | Mandatory |
|------------------------------|------------------------------------------------------------------------------------------------------|-------------------------------------------------------|-----------|
| yarn.heartbeat-delay         | Time between heartbeats with the ApplicationMaster and Yarn ResourceManager in seconds. Unit: second | 5                                                     | No        |
| yarn.containers.vcores       | Number of virtual cores of each Yarn container                                                       | The default value is the number of TaskManager slots. | No        |
| yarn.application-master.port | ApplicationMaster port number setting. A port number range is supported.                             | 32586-32650                                           | No        |

## 4.3.14 Pipeline

### Scenarios

The Netty connection is used among multiple jobs to reduce latency. In this case, NettySink is used on the server and NettySource is used on the client for data transmission.

### Configuration Description

Configuration items include NettySink information storing path, range of NettySink listening port, whether to enable SSL encryption, domain of the network used for NettySink monitoring.

**Table 4-13** Parameters

| Parameter                                   | Description                                                                                                                                       | Default Value         | Mandatory                                                      |
|---------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------|----------------------------------------------------------------|
| nettyconnector.registerserver.topic.storage | Path (on a third-party server) to information about IP address, port numbers, and concurrency of NettySink. ZooKeeper is recommended for storage. | /flink/nettyconnector | No. However, if pipeline is enabled, the feature is mandatory. |

| Parameter                            | Description                                                                                                                                                             | Default Value                                             | Mandatory                                                      |
|--------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------|----------------------------------------------------------------|
| nettyconnector.sinkserver.port.range | Port range of NettySink.                                                                                                                                                | If MRS cluster is used, the default value is 28444-28843. | No. However, if pipeline is enabled, the feature is mandatory. |
| nettyconnector.ssl.enabled           | Whether SSL encryption for the communication between NettySink and NettySource is enabled. For details about the encryption key and protocol, see <a href="#">SSL</a> . | false                                                     | No. However, if pipeline is enabled, the feature is mandatory. |
| nettyconnector.message.delimiter     | Delimiter used to configure the message sent by NettySink to the NettySource, which is 2-4 bytes long, and cannot contain \n, #, or space.                              | The default value is \$._.                                | No. However, if pipeline is enabled, the feature is mandatory. |

## 4.4 Security Configuration

### 4.4.1 Security Features

#### Security Features of Flink

- All Flink cluster components support authentication.
  - The Kerberos authentication is supported between Flink cluster components and external components, such as Yarn, HDFS, and ZooKeeper.
  - The security cookie authentication between Flink cluster components, for example, Flink client and JobManager, JobManager and TaskManager, and TaskManager and TaskManager, are supported.
- SSL encrypted transmission is supported by Flink cluster components.
- SSL encrypted transmission between Flink cluster components, for example, Flink client and JobManager, JobManager and TaskManager, and TaskManager and TaskManager, are supported.
- Following security hardening approaches for Flink web are supported:

- Whitelist filtering. Flink web can only be accessed through Yarn proxy.
- Security header enhancement.
- In Flink clusters, ranges of listening ports of components can be configured.
- In HA mode, ACL control is supported.

## 4.4.2 Configuring Kafka

Sample project data of Flink is stored in Kafka. A user with Kafka permission can send data to Kafka and receive data from it.

**Step 1** Ensure that clusters, including HDFS, Yarn, Flink, and Kafka are installed.

**Step 2** Create a topic.

- Run Linux command line to create a topic. Before running commands, ensure that the kinit command, for example, **kinit flinkuser**, is run for authentication.

### NOTE

To create a Flink user, you need to have the permission to create Kafka topics.

The format of the command is shown as follows, in which **{zkQuorum}** indicates ZooKeeper cluster information and the format is *IP.port*, and **{Topic}** indicates the topic name.

**bin/kafka-topics.sh --create --zookeeper {zkQuorum}/kafka --replication-factor 1 --partitions 5 --topic {Topic}**

Assume the topic name is **topic 1**. The command for creating this topic is displayed as follows:

```
/opt/client/Kafka/kafka/bin/kafka-topics.sh --create --zookeeper
10.96.101.32:2181,10.96.101.251:2181,10.96.101.177:2181,10.91.8.160:2181/kafka --replication-factor
1 --partitions 5 --topic topic1
```

- Configure the permission of the topic on the server.  
Set the **allow.everyone.if.no.acl.found** parameter of Kafka Broker to **true**.

**Step 3** Perform the security authentication.

The Kerberos authentication, SSL encryption authentication, or Kerberos + SSL authentication mode can be used.

- **Kerberos authentication**

- Client configuration

In the Flink configuration file **flink-conf.yaml**, add configurations about Kerberos authentication. For example, add **KafkaClient** in **contexts** as follows:

```
security.kerberos.login.keytab: /home/demo//keytab/flinkuser.keytab
security.kerberos.login.principal: flinkuser
security.kerberos.login.contexts: Client,KafkaClient
security.kerberos.login.use-ticket-cache: false
```

- Running parameter

Running parameters about the **SASL\_PLAINTEXT** protocol are as follows:

```
--topic topic1 --bootstrap.servers 10.96.101.32:21007 --security.protocol SASL_PLAINTEXT --
sasl.kerberos.service.name kafka //10.96.101.32:21007 indicates the IP.port of the Kafka server.
```

- **SSL encryption**

- Configuration on the server  
Log in to FusionInsight Manager, choose **Cluster > Services > Kafka > Configurations**, and set **Type** to **All**. Search for **ssl.mode.enable** and set it to **true**.
- Configuration on the client
  - i. Log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > Kafka > More > Download Client** to download Kafka client.
  - ii. Use the **ca.crt** certificate file in the client root directory to generate the **truststore** file for the client.

Run the following command:

```
keytool -noprompt -import -alias myservcert -file ca.crt -keystore truststore.jks
```

The command execution result is similar to the following:

```
drwx-----, 5 zgd users 4096 Feb 4 16:22 .
drwxr-xr-x, 10 zgd users 4096 Jan 22 17:38 ..
-rwx-----, 1 zgd users 135 Jan 22 17:31 application.properties
-rwx-----, 1 zgd users 790 Jan 22 17:31 bigdata_env.sample
-rw-----, 1 zgd users 1322 Jan 22 17:31 ca.crt
-rwx-----, 1 zgd users 4508 Jan 22 17:31 conf.py
-rw-----, 1 zgd users 120 Jan 22 17:31 hosts
-rwx-----, 1 zgd users 745 Jan 22 17:31 install.bat
-rwx-----, 1 zgd users 15082 Jan 22 17:31 install.sh
drwx-----, 2 zgd users 4096 Jan 22 17:38 JDK
-rwx-----, 1 zgd users 37021723 Jan 22 17:31 jython-standalone-2.7.0.jar
drwx-----, 5 zgd users 4096 Jan 22 17:38 Kafka
drwx-----, 3 zgd users 4096 Jan 22 17:38 KrbClient
-rwx-----, 1 zgd users 473 Jan 22 17:31 log4j.properties
-rwx-----, 1 zgd users 2107 Jan 22 17:31 README
-rwx-----, 1 zgd users 6949 Jan 22 17:31 refreshConfig.sh
-rwx-----, 1 zgd users 1736 Jan 22 17:31 switchuser.py
-rw-r--r--, 1 root root 1004 Feb 4 16:22 truststore.jks
```

- iii. Run parameters.

The value of **ssl.truststore.password** must be the same as the password you entered when creating **truststore**. Run the following command to run parameters:

```
--topic topic1 --bootstrap.servers 10.96.101.32:9093 --security.protocol SSL --
ssl.truststore.location /home/zgd/software/FusionInsight_Kafka_ClientConfig/truststore.jks
--ssl.truststore.password XXX
```

- **Kerberos+SSL encryption**

After completing preceding configurations of the client and server of Kerberos and SSL, modify the port number and protocol type in running parameters to enable the Kerberos+SSL encryption mode.

```
--topic topic1 --bootstrap.servers 10.96.101.32:21009 --security.protocol SASL_SSL --
sasl.kerberos.service.name kafka --ssl.truststore.location /home/zgd/software/
FusionInsight_Kafka_ClientConfig/truststore.jks --ssl.truststore.password XXX
```

----End

### 4.4.3 Configuring Pipeline

1. File configuration
  - **nettyconnector.registerserver.topic.storage**: (Mandatory) Configures the path (on a third-party server) to information about IP address, port numbers, and concurrency of NettySink. For example:  
nettyconnector.registerserver.topic.storage: /flink/nettyconnector
  - **nettyconnector.sinkserver.port.range**: (Mandatory) Configures the range of port numbers of NettySink. For example:

```
nettyconnector.sinkserver.port.range: 28444-28843
```

- **nettyconnector.ssl.enabled**: Configures whether to enable SSL encryption between NettySink and NettySource. The default value is **false**. For example:

```
nettyconnector.ssl.enabled: true
```

2. Security authentication configuration
  - SASL authentication of ZooKeeper depends on the HA configuration in the **flink-conf.yaml** file.
  - SSL configurations such as keystore, truststore, keystore password, truststore password, and password inherit from **flink-conf.yaml**. For details, see [Encrypted Transmission](#).

## 4.5 Security Hardening

### 4.5.1 Authentication and Encryption

#### Security Authentication

Flink uses the following three authentication modes:

- Kerberos authentication: It is used between the Flink Yarn client and Yarn ResourceManager, JobManager and ZooKeeper, JobManager and HDFS, TaskManager and HDFS, Kafka and TaskManager, as well as TaskManager and ZooKeeper.
- Security cookie authentication: Security cookie authentication is used between Flink Yarn client and JobManager, JobManager and TaskManager, as well as TaskManager and TaskManager.
- Internal authentication of Yarn: The Internal authentication mechanism of Yarn is used between Yarn ResourceManager and ApplicationMaster (AM).

#### NOTE

- Flink JobManager and Yarn ApplicationMaster are in the same process.
- If Kerberos authentication is enabled for the user's cluster, Kerberos authentication is required.

**Table 4-14** Authentication modes

| Authen-<br>tication<br>Mode        | Descrip-<br>tion                                                                 | Configuration Method                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|------------------------------------|----------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Kerbero<br>s<br>authent<br>ication | Current<br>ly, only<br>keytab<br>authent<br>ication<br>mode is<br>support<br>ed. | <ol style="list-style-type: none"> <li>1. Download the user keytab from the KDC server, and place the keytab to a directory on the host of the Flink client.</li> <li>2. Configure the following parameters in the <b>flink-conf.yaml</b> file:               <ol style="list-style-type: none"> <li>a. Keytab path<br/> <code>security.kerberos.login.keytab: /home/flinkuser/keytab/abc222.keytab</code><br/>                     Note:<br/> <b>/home/flinkuser/keytab/abc222.keytab</b><br/>                     indicates the user directory.</li> <li>b. Principal name<br/> <code>security.kerberos.login.principal: abc222</code></li> <li>c. In HA mode, if ZooKeeper is configured, the Kerberos authentication configuration items must be configured as follows:<br/> <code>zookeeper.sasl.disable: false</code><br/> <code>security.kerberos.login.contexts: Client</code></li> <li>d. If you want to perform Kerberos authentication between Kafka client and Kafka broker, set the value as follows:<br/> <code>security.kerberos.login.contexts: Client,KafkaClient</code></li> </ol> </li> </ol> |

| Authentication Mode            | Description | Configuration Method                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|--------------------------------|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Security cookie authentication | -           | <p>1. In the <b>bin</b> directory of the Flink client, run the <b>generate_keystore.sh</b> script to generate security cookie, <b>flink.keystore</b>, and <b>flink.truststore</b>. Run the <b>sh generate_keystore.sh</b> command and enter the user-defined password. The password cannot contain #.</p> <p><b>NOTE</b><br/>After the script is executed, the <b>flink.keystore</b> and <b>flink.truststore</b> files are generated in the <b>conf</b> directory on the Flink client. In the <b>flink-conf.yaml</b> file, default values are specified for following parameters:</p> <ul style="list-style-type: none"> <li>• Set <b>security.ssl.keystore</b> to the absolute path of the <b>flink.keystore</b> file.</li> <li>• Set <b>security.ssl.truststore</b> to the absolute path of the <b>flink.truststore</b> file.</li> <li>• Set <b>security.cookie</b> to a random password automatically generated by the <b>generate_keystore.sh</b> script.</li> <li>• By default, <b>security.ssl.encrypt.enabled: false</b> is set in the <b>flink-conf.yaml</b> file by default. The <b>generate_keystore.sh</b> script sets <b>security.ssl.key-password</b>, <b>security.ssl.keystore-password</b>, and <b>security.ssl.truststore-password</b> to the password entered when the <b>generate_keystore.sh</b> script is called.</li> <li>• If ciphertext is required and <b>security.ssl.encrypt.enabled: true</b>, is set in the <b>flink-conf.yaml</b> file, the <b>generate_keystore.sh</b> script does not set <b>security.ssl.key-password</b>, <b>security.ssl.keystore-password</b>, and <b>security.ssl.truststore-password</b>. To obtain the values, use the Manager plaintext encryption API by running the following command: <b>curl -k -i -u Username:Password -X POST -HContent-type:application/json -d '{"plainText":"' Password"'}' https://x.x.x.x:28443/web/api/v2/tools/encrypt'</b><br/>In the preceding command, <i>Username:Password</i> indicates the user name and password for logging in to the system. The password of "plainText" indicates the one used to call the <b>generate_keystore.sh</b> script. <i>x.x.x.x</i> indicates the floating IP address of Manager.</li> </ul> <p>2. Set <b>security.enable: true</b> in the <b>flink-conf.yaml</b> file and check whether <b>security cookie</b> is configured successfully. Example:<br/>security.cookie: ae70acc9-9795-4c48-ad35-8b5adc8071744f605d1d-2726-432e-88ae-dd39bfec40a9</p> |

| Authen tication Mode             | Descrip tion                                                           | Configuration Method                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|----------------------------------|------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                  |                                                                        | <p><b>NOTE</b><br/>The validity period of the SSL certificate obtained by using the <b>generate_keystore.sh</b> script preset on the MRS client is 5 years.</p> <p>To disable the default SSL authentication mode, set <b>security.ssl.enabled</b> to <b>false</b> in the <b>flink-conf.yaml</b> file and comment out <b>security.ssl.key-password</b>, <b>security.ssl.keystore-password</b>, <b>security.ssl.keystore</b>, <b>security.ssl.truststore-password</b>, and <b>security.ssl.truststore</b>.</p> |
| Internal authent ication of Yarn | This authent ication mode does not need to be configu red by the user. | -                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |

 **NOTE**

One Flink cluster supports only one user. One user can create multiple Flink clusters.

## Encrypted Transmission

Flink uses following encrypted transmission modes:

- Encrypted transmission inside Yarn: It is used between the Flink Yarn client and Yarn ResourceManager, as well as Yarn ResourceManager and JobManager.
- SSL transmission: SSL transmission is used between Flink Yarn client and JobManager, JobManager and TaskManager, as well as TaskManager and TaskManager.
- Encrypted transmission inside Hadoop: The internal encrypted transmission mode of Hadoop used between JobManager and HDFS, TaskManager and HDFS, JobManager and ZooKeeper, as well as TaskManager and ZooKeeper.

 **NOTE**

Configuration about SSL encrypted transmission is mandatory while configuration about encryption of Yarn and Hadoop is not required.

To configure SSL encrypted transmission, configure the following parameters in the **flink-conf.yaml** file on the client:

1. Enable SSL and configure the SSL encryption algorithm. see [Table 4-15](#). Modify the parameters as required.

**Table 4-15** Parameter description

| Parameter                    | Example Value                                                                                                                                        | Description                                    |
|------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------|
| security.ssl.enabled         | true                                                                                                                                                 | Enable SSL.                                    |
| akka.ssl.enabled             | true                                                                                                                                                 | Enable Akka SSL.                               |
| blob.service.ssl.enabled     | true                                                                                                                                                 | Enable SSL for the Blob channel.               |
| taskmanager.data.ssl.enabled | true                                                                                                                                                 | Enable SSL transmissions between TaskManagers. |
| security.ssl.algorithms      | TLS_DHE_RSA_WITH_AES_128_GCM_SHA256,TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256 ,TLS_DHE_RSA_WITH_AES_256_GCM_SHA384,TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384 | Configure the SSL encryption algorithm.        |

 **NOTE**

Enabling SSL for data transmission between TaskManagers may pose great impact on the system performance.

2. In the **bin** directory of the Flink client, run the ***sh generate\_keystore.sh*** *<password>* command. For details, see [Authentication and Encryption](#). The configuration items in [Table 4-16](#) are set by default. You can also configure them manually.

**Table 4-16** Parameter description

| Parameter             | Example Value           | Description                                                                                                                                                     |
|-----------------------|-------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| security.ssl.keystore | \${path}/flink.keystore | Path for storing the <b>keystore</b> . <b>flink.keystore</b> indicates the name of the <b>keystore</b> file generated by the <b>generate_keystore.sh*</b> tool. |

| Parameter                        | Example Value             | Description                                                                                                                                                           |
|----------------------------------|---------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| security.ssl.keystore-password   | 123456                    | Password of the <b>keystore</b> . <b>123456</b> indicates a user-defined password is required.                                                                        |
| security.ssl.key-password        | 123456                    | Password of the SSL key. <b>123456</b> indicates a user-defined password is required.                                                                                 |
| security.ssl.truststore          | \${path}/flink.truststore | Path for storing the <b>truststore</b> . <b>flink.truststore</b> indicates the name of the <b>truststore</b> file generated by the <b>generate_keystore.sh*</b> tool. |
| security.ssl.truststore-password | 123456                    | Password of the <b>truststore</b> . <b>123456</b> indicates a user-defined password is required.                                                                      |

 **NOTE**

The **path** directory is a user-defined directory for storing configuration files of the SSL keystore and truststore. The commands vary according to the relative path and absolute path. For details, see [3](#) and [4](#).

- If the **keystore** or **truststore** file path is a relative path, the Flink client directory where the command is executed needs to access this relative path directly. Either of the following method can be used to transmit the keystore and truststore file:

- Add **-t** option to the **CLI yarn-session.sh** command to transfer the **keystore** and **truststore** file to execution nodes. Example:

```
./bin/yarn-session.sh -t ssl/
```

- Add **-yt** option to the **flink run** command to transfer the **keystore** and **truststore** file to execution nodes. Example:

```
./bin/flink run -yt ssl/ -ys 3 -m yarn-cluster -c  
org.apache.flink.examples.java.wordcount.WordCount /opt/client/Flink/flink/examples/batch/  
WordCount.jar
```

 **NOTE**

- In the preceding example, **ssl/** is the sub-directory of the Flink client directory. It is used to store configuration files of the SSL keystore and truststore.
  - The relative path of **ssl/** must be accessible from the current path where the Flink client command is run.
- If the keystore or truststore file path is an absolute path, the keystore and truststore files must exist in the absolute path on Flink Client and all nodes.

Either of the following methods can be used to execute applications. The **-t** or **-yt** option does not need to be added to transmit the **keystore** and **truststore** files.

- Run the **CLI `yarn-session.sh`** command of Flink to execute applications.

Example:

```
./bin/yarn-session.sh
```

- Run the **Flink `run`** command to execute applications. Example:

```
./bin/flink run -ys 3 -m yarn-cluster -c  
org.apache.flink.examples.java.wordcount.WordCount /opt/client/Flink/flink/examples/batch/  
WordCount.jar
```

## 4.5.2 ACL Control

In HA mode of Flink, ZooKeeper can be used to manage clusters and discover services. Zookeeper supports SASL ACL control. Only users who have passed the SASL (Kerberos) authentication have the permission to operate files on ZooKeeper. To enable SASL ACL control, perform following configurations in the Flink configuration file.

```
high-availability.zookeeper.client.acl: creator  
zookeeper.sasl.disable: false
```

For details about configuration items, see [Table 4-10](#).

## 4.5.3 Web Security

### Coding Specifications

Note: The same coding mode is used on the web service client and server to prevent garbled characters and to enable input verification.

Security hardening: apply UTF-8 to response messages of web server.

### Whitelist-based Filter of IP Addresses

Note: IP filter must be added to the web server to filter unauthorized requests from the source IP address and prevent unauthorized login.

Security: Add **jobmanager.web.allow-access-address** to enable the IP filter. By default, only Yarn users are supported.

#### NOTE

After the client is installed, you need to add the IP address of the client node to the **jobmanager.web.allow-access-address** configuration item.

### Preventing Sending the Absolute Paths to the Client

Note: If an absolute path is sent to a client, the directory structure of the server is exposed, increasing the risk that attackers know and attack the system.

Security hardening: If the Flink configuration file contains a parameter starting with a slash (/), the first-level directory is deleted.

## Same-origin Policy

If two URL protocols have same hosts and ports, they are of the same origin. Protocols of different origins cannot access each other, unless the source of the visitor is specified on the host of the service to be visited.

Security hardening: The default value of the header of the response header **Access-Control-Allow-Origin** is the IP address of ResourceManager on Yarn clusters. If the IP address is not from Yarn, mutual access is not allowed.

## Preventing Sensitive Information Disclosure

Web pages containing sensitive data must not be cached, to avoid leakage of sensitive information or data crosstalk among users who visit the internet through the proxy server.

Security hardening: Add **Cache-control**, **Pragma**, **Expires** security header. The default value is **Cache-Control: no-store**, **Pragma: no-cache**, and **Expires: 0**.

The security hardening stops contents interacted between Flink and web server from being cached.

## Anti-Hijacking

Since hotlinking and clickjacking use framing technologies, security hardening is required to prevent attacks.

Security hardening: Add **X-Frame-Options** security header to specify whether the browser will load the pages from **iframe**, **frame** or **object**. The default value is **X-Frame-Options: DENY**, indicating that no pages can be nested to **iframe**, **frame** or **object**.

## Logging calls of the Web Service APIs

Calls of the **Flink webmonitor restful** APIs are logged.

The **jobmanager.web.accesslog.enable** can be added in the **access log**. The default value is **true**. Logs are stored in a separate **webaccess.log** file.

## Cross-Site Request Forgery Prevention

In **Browser/Server** applications, CSRF must be prevented for operations involving server data modification, such as adding, modifying, and deleting. The CSRF forces end users to execute non-intended operations on the current web application.

Security hardening: Only two post APIs, one delete API, and get interfaces are reserve for modification requests. All other APIs are deleted.

## Troubleshooting

When the application is abnormal, exception information is filtered, logged, and returned to the client.

Security hardening

- A default error message page to filter information and log detailed error information.

- Four configuration parameters are added to ensure that the error page is switched to a specified URL provided by FusionInsight, preventing exposure of unnecessary information.

**Table 4-17** Parameter description

| Parameter                       | Description                                                                          | Default Value | Mandatory |
|---------------------------------|--------------------------------------------------------------------------------------|---------------|-----------|
| jobmanager.web.403-redirect-url | Web page access error 403. If 403 error occurs, the page switch to a specified page. | -             | Yes       |
| jobmanager.web.404-redirect-url | Web page access error 404. If 404 error occurs, the page switch to a specified page. | -             | Yes       |
| jobmanager.web.415-redirect-url | Web page access error 415. If 415 error occurs, the page switch to a specified page. | -             | Yes       |
| jobmanager.web.500-redirect-url | Web page access error 500. If 500 error occurs, the page switch to a specified page. | -             | Yes       |

## HTML5 Security

HTML5 is a next generation web development specification that provides new functions and extend the labels for developers. These new labels add the attack surfaces and may incur risks of attacks. For example, cross-domain resource sharing, storage on the client, WebWorker, WebRTC, and WebSocket.

Security hardening: Add the **Access-Control-Allow-Origin** parameter. For example, if you want to enable the cross-domain resource sharing, configure the **Access-Control-Allow-Origin** parameter of the HTTP response header.

### NOTE

Flink does not involve security risks of functions such as storage on the client, WebWorker, WebRTC, and WebSocket.

## 4.6 Security Statement

- All security functions of Flink are provided by the open source community or self-developed. Security features that need to be configured by users, such as authentication and SSL encrypted transmission, may affect performance.

- As a big data computing and analysis platform, Flink does not detect sensitive information. Therefore, you need to ensure that the input data is not sensitive.
- You can evaluate whether configurations are secure as required.
- For any security-related problems, contact O&M support.

## 4.7 Using the Flink Web UI

### 4.7.1 Overview

#### 4.7.1.1 Introduction to Flink Web UI

Flink web UI provides a web-based visual development platform. You only need to compile SQL statements to develop jobs, slashing the job development threshold. In addition, the exposure of platform capabilities allows service personnel to compile SQL statements for job development to quickly respond to requirements, greatly reducing the Flink job development workload.

#### Flink Web UI Features

The Flink web UI has the following features:

- Enterprise-class visual O&M: GUI-based O&M management, job monitoring, and standardization of Flink SQL statements for job development.
- Quick cluster connection: After configuring the client and user credential key file, you can quickly access a cluster using the cluster connection function.
- Quick data connection: You can access a component by configuring the data connection function. If **Data Connection Type** is set to **HDFS**, you need to create a cluster connection. If **Authentication Mode** is set to **KERBEROS** for other data connection types, you need to create a cluster connection. If **Authentication Mode** is set to **SIMPLE**, you do not need to create a cluster connection.
- Visual development platform: The input/output mapping table can be customized to meet the requirements of different input sources and output destinations.
- Easy to use GUI-based job management

#### Key Web UI Capabilities

[Table 4-18](#) shows the key capabilities provided by Flink web UI.

**Table 4-18** Key web UI capabilities


| Item                     | Description                                                                                                                               |
|--------------------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| Batch-Stream convergence | <ul style="list-style-type: none"><li>• Batch jobs and stream jobs can be processed with a unified set of Flink SQL statements.</li></ul> |

| Item                               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Flink SQL kernel capabilities      | <ul style="list-style-type: none"> <li>• Flink SQL supports customized window size, stream compute within 24 hours, and batch processing beyond 24 hours.</li> <li>• Flink SQL supports Kafka and HDFS reading. Data can be written to Kafka, and HDFS.</li> <li>• A job can define multiple Flink SQL jobs, and multiple metrics can be combined into one job for computing. If a job contains same primary keys as well as same inputs and outputs, the job supports the computing of multiple windows.</li> <li>• The AVG, SUM, COUNT, MAX, and MIN statistical methods are supported.</li> </ul>                                                                                                                                          |
| Flink SQL functions on the console | <ul style="list-style-type: none"> <li>• Cluster connection management allows you to configure clusters where services such as Kafka, and HDFS reside.</li> <li>• Data connection management allows you to configure services such as Kafka, and HDFS.</li> <li>• Data table management allows you to define data tables accessed by SQL statements and generate DDL statements.</li> <li>• Flink SQL job definition allows you to verify, parse, optimize, convert a job into a Flink job, and submit the job for running based on the entered SQL statements.</li> </ul>                                                                                                                                                                    |
| Flink job visual management        | <ul style="list-style-type: none"> <li>• Stream jobs and batch jobs can be defined in a visual manner.</li> <li>• Job resources, fault recovery policies, and checkpoint policies can be configured in a visual manner.</li> <li>• Status monitoring of stream and batch jobs are supported.</li> <li>• The Flink job O&amp;M is enhanced, including redirection of the native monitoring page.</li> </ul>                                                                                                                                                                                                                                                                                                                                    |
| Performance and reliability        | <ul style="list-style-type: none"> <li>• Stream processing supports 24-hour window aggregation computing and millisecond-level performance.</li> <li>• Batch processing supports 90-day window aggregation computing, which can be completed in minutes.</li> <li>• Invalid data of stream processing and batch processing can be filtered out.</li> <li>• When HDFS data is read, the data can be filtered based on the calculation period in advance.</li> <li>• If the job definition platform is faulty or the service is degraded, jobs cannot be redefined, but the computing of existing jobs is not affected.</li> <li>• The automatic restart mechanism is provided for job failures. You can configure restart policies.</li> </ul> |

### 4.7.1.2 Flink Web UI Application Process

The Flink web UI application process is shown as follows:

**Figure 4-2** Application process



**Table 4-19** Description of the Flink web UI application process

| Phase                                     | Description                                                                                                              | Reference Section                                                 |
|-------------------------------------------|--------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------|
| Creating an application                   | Applications can be used to isolate different upper-layer services.                                                      | <a href="#">Creating an Application on the Flink Web UI</a>       |
| Creating a cluster connection             | Different clusters can be accessed by configuring the cluster connection.                                                | <a href="#">Creating a Cluster Connection on the Flink Web UI</a> |
| Creating a data connection                | Different data services can be accessed, such as HDFS, Kafka, through the data connection.                               | <a href="#">Creating a Data Connection on the Flink Web UI</a>    |
| Creating a stream table                   | Data tables can be used to define basic attributes and parameters of source tables, dimension tables, and output tables. | <a href="#">Managing Tables on the Flink Web UI</a>               |
| Creating a SQL/JAR job (stream/batch job) | APIs can be used to define Flink jobs, including Flink SQL and Flink Jar jobs.                                           | <a href="#">Managing Jobs on the Flink Web UI</a>                 |

| Phase          | Description                                                                                            | Reference Section                                 |
|----------------|--------------------------------------------------------------------------------------------------------|---------------------------------------------------|
| Managing a job | A created job can be managed, including starting, developing, stopping, deleting, and editing the job. | <a href="#">Managing Jobs on the Flink Web UI</a> |

## 4.7.2 FlinkServer Permissions Management

### 4.7.2.1 Overview

User **admin** of Manager does not have the FlinkServer service operation permission. To perform FlinkServer service operations, you need to grant related permission to the user.

Applications (tenants) in FlinkServer are the maximum management scope, including cluster connection management, data connection management, application management, stream table management, and job management.

There are three types of resource permissions for FlinkServer, as shown in [Table 4-20](#).

**Table 4-20** FlinkServer resource permissions

| Name                        | Description                                                                                                                                                             | Remarks                                                                                                                                                |
|-----------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|
| Administrator permission    | Users who have the permission can edit and view all applications.                                                                                                       | This is the highest-level permission of FlinkServer. If you have the administrator permission, you have the permission on all applications by default. |
| Application edit permission | Users who have the permission can create, edit, and delete cluster connections and data connections. They can also create stream tables as well as create and run jobs. | In addition, users who have the permission can view current applications.                                                                              |
| Application view permission | Users who have the permission can view applications.                                                                                                                    | -                                                                                                                                                      |

### 4.7.2.2 Authentication Based on Users and Roles

This section describes how to create and configure a FlinkServer role on Manager as the system administrator. A FlinkServer role can be configured with administrator permission and the permissions to edit and view applications.

You need to set permissions for the specified user in FlinkServer so that they can update, query, and delete data.

## Prerequisites

The administrator has planned permissions based on business needs.

## Procedure

**Step 1** Log in to Manager.

**Step 2** Choose **System > Permission > Role**.

**Step 3** On the displayed page, click **Create Role** and specify **Role Name** and **Description**.

**Step 4** Set **Configure Resource Permission**.

FlinkServer permissions are as follows:

- **FlinkServer Admin Privilege:** highest-level permission. Users with the permission can perform service operations on all FlinkServer applications.
- **FlinkServer Application:** Users can set **application view** and **applications management** permissions on applications.

**Table 4-21** Setting a role

| Scenario                                       | Role Authorization                                                                                                                                                                                                                                                                                                      |
|------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Setting the administrator operation permission | In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> > <b>Flink</b> and select <b>FlinkServer Admin Privilege</b> .                                                                                                                                                             |
| Setting a specified permission on applications | <ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Flink</b> &gt; <b>FlinkServer Application</b>.</li> <li>2. In the <b>Permission</b> column, select <b>application view</b> or <b>applications management</b>.</li> </ol> |

**Step 5** Click **OK**. Return to role management page.

### NOTE

After the FlinkServer is created, create a FlinkServer user and bind the user to the role and user group.

----End

## 4.7.3 Accessing the Flink Web UI

### Scenario

After Flink is installed in an MRS cluster, you can connect to clusters and data as well as manage stream tables and jobs using the Flink web UI.

This section describes how to access the Flink web UI in an MRS cluster.

 **NOTE**

You are advised to use Google Chrome 50 or later to access the Flink web UI. The Internet Explorer may be incompatible with the Flink web UI.

## Impact on the System

Site trust must be added to the browser when you access Manager and the Flink web UI for the first time. Otherwise, the Flink web UI cannot be accessed.

## Procedure

**Step 1** Log in to FusionInsight Manager as a user with **FlinkServer Admin Privilege**. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Flink**.

**Step 2** On the right of **Flink WebUI**, click the link to access the Flink web UI.

The Flink web UI provides the following functions:

- System management:
  - Cluster connection management allows you to create, view, edit, test, and delete a cluster connection.
  - Data connection management allows you to create, view, edit, test, and delete a data connection. Data connection types include HDFS, Kafka.
  - Application management allows you to create, view, and delete an application.
- UDF management allows you to upload and manage UDF JAR packages and customize functions to extend SQL statements to meet personalized requirements.
- Stream table management allows you to create, view, edit, and delete a stream table.
- Job management allows you to create, view, start, develop, edit, stop, and delete a job.

----End

## 4.7.4 Creating an Application on the Flink Web UI

### Scenario

Applications can be used to isolate different upper-layer services.

### Creating an Application

**Step 1** Access the Flink web UI as a user with the FlinkServer management permission. For details, see [Accessing the Flink Web UI](#).

**Step 2** Choose **System Management > Application Management**.

**Step 3** Click **Create Application**. On the displayed page, set parameters by referring to [Table 4-22](#) and click **OK**.

**Table 4-22** Parameters for creating an application

| Parameter   | Description                                                                                                                                      |
|-------------|--------------------------------------------------------------------------------------------------------------------------------------------------|
| Application | Name of the application to be created. The name can contain a maximum of 32 characters. Only letters, digits, and underscores ( _ ) are allowed. |
| Description | Description of the application to be created. The value can contain a maximum of 85 characters.                                                  |

After the application is created, you can switch to the application to be operated in the upper left corner of the Flink web UI and develop jobs.

----End

## 4.7.5 Creating a Cluster Connection on the Flink Web UI

### Scenario

Different clusters can be accessed by configuring the cluster connection.

### Creating a Cluster Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Choose **System Management > Cluster Connection Management**. The **Cluster Connection Management** page is displayed.
- Step 3** Click **Create Cluster Connection**. On the displayed page, set parameters by referring to [Table 4-23](#) and click **OK**.

**Table 4-23** Parameters for creating a cluster connection

| Parameter                | Description                                                                                                                                                                                                          |
|--------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Cluster Connection Name  | Name of the cluster connection, which can contain a maximum of 100 characters. Only letters, digits, and underscores ( _ ) are allowed.                                                                              |
| Description              | Description of the cluster connection name.                                                                                                                                                                          |
| FusionInsight HD Version | Set a cluster version.                                                                                                                                                                                               |
| Secure Version           | <ul style="list-style-type: none"> <li>• If the secure version is used, select <b>Yes</b> for a security cluster. Enter the username and upload the user credential.</li> <li>• If not, select <b>No</b>.</li> </ul> |

| Parameter       | Description                                                                                                                                                                                                                                                                            |
|-----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Username        | The user must have the minimum permissions for accessing services in the cluster. The name can contain a maximum of 100 characters. Only letters, digits, and underscores ( _ ) are allowed.<br><br>This parameter is available only when <b>Secure Version</b> is set to <b>Yes</b> . |
| Client Profile  | Client profile of the cluster, in TAR format.                                                                                                                                                                                                                                          |
| User Credential | User authentication credential in FusionInsight Manager in TAR format.<br><br>This parameter is available only when <b>Secure Version</b> is set to <b>Yes</b> .<br><br>Files can be uploaded only after the username is entered.                                                      |

 **NOTE**

To obtain the cluster client configuration files, perform the following steps:

1. Log in to FusionInsight Manager and choose **Cluster > Dashboard**.
2. Choose **More > Download Client > Configuration Files Only**, select a platform type, and click **OK**.

To obtain the user credential, perform the following steps:

1. Log in to FusionInsight Manager and click **System**.
2. In the **Operation** column of the user, choose **More > Download Authentication Credential**, select a cluster, and click **OK**.

----End

## Editing a Cluster Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Choose **System Management > Cluster Connection Management**. The **Cluster Connection Management** page is displayed.
- Step 3** In the **Operation** column of the item to be modified, click **Edit**. On the displayed page, modify the connection information by referring to [Table 4-23](#) and click **OK**.

----End

## Testing a Cluster Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Choose **System Management > Cluster Connection Management**. The **Cluster Connection Management** page is displayed.
- Step 3** In the **Operation** column of the item to be tested, click **Test**.

----End

## Searching for a Cluster Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
  - Step 2** Choose **System Management > Cluster Connection Management**. The **Cluster Connection Management** page is displayed.
  - Step 3** In the upper right corner of the page, you can enter a search criterion to search for and view the cluster connection based on **Cluster Connection Name**.
- End

## Deleting a Cluster Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
  - Step 2** Choose **System Management > Cluster Connection Management**. The **Cluster Connection Management** page is displayed.
  - Step 3** In the **Operation** column of the item to be deleted, click **Delete**, and click **OK** in the displayed page.
- End

## 4.7.6 Creating a Data Connection on the Flink Web UI

### Scenario

Different data services can be accessed through data connections. Currently, FlinkServer supports HDFS, Kafka data connections.

### Creating a Data Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Choose **System Management > Data Connection Management**. The **Data Connection Management** page is displayed.
- Step 3** Click **Create Data Connection**. On the displayed page, select a data connection type, enter information by referring to [Table 4-24](#), and click **OK**.

**Table 4-24** Parameters for creating a data connection

| Parameter            | Description                                                                                                                        | Example Value |
|----------------------|------------------------------------------------------------------------------------------------------------------------------------|---------------|
| Data Connection Type | Type of the data connection, which can be <b>HDFS, Kafka</b> .                                                                     | -             |
| Data Connection Name | Name of the data connection, which can contain a maximum of 100 characters. Only letters, digits, and underscores (_) are allowed. | -             |

| Parameter           | Description                                                                                                                                                                                                                                                                                                                                                                                           | Example Value                       |
|---------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------|
| Cluster Connection  | Cluster connection name in configuration management.<br>This parameter is mandatory for HDFS data connections.                                                                                                                                                                                                                                                                                        | -                                   |
| Kafka broker        | Connection information about Kafka broker instances. The format is <i>IP address.Port number</i> . Use commas (,) to separate multiple instances.<br>This parameter is mandatory for Kafka data connections.                                                                                                                                                                                          | 192.168.0.1:21005,192.168.0.2:21005 |
| Authentication Mode | <ul style="list-style-type: none"> <li>● <b>SIMPLE</b>: indicates that the connected service is in non-security mode and does not need to be authenticated.</li> <li>● <b>KERBEROS</b>: indicates that the connected service is in security mode and the Kerberos protocol for security authentication is used for authentication.</li> </ul> This parameter is mandatory for Kafka data connections. | -                                   |

----End

## Editing a Data Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Choose **System Management > Data Connection Management**. The **Data Connection Management** page is displayed.
- Step 3** In the **Operation** column of the item to be modified, click **Edit**. On the displayed page, modify the connection information by referring to [Table 4-24](#) and click **OK**.

----End

## Testing a Data Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Choose **System Management > Data Connection Management**. The **Data Connection Management** page is displayed.
- Step 3** In the **Operation** column of the item to be tested, click **Test**.

----End

## Searching for a Data Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).

- Step 2** Choose **System Management > Data Connection Management**. The **Data Connection Management** page is displayed.
  - Step 3** In the upper right corner of the page, you can search for a data connection by name.
- End

## Deleting a Data Connection

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
  - Step 2** Choose **System Management > Data Connection Management**. The **Data Connection Management** page is displayed.
  - Step 3** In the **Operation** column of the item to be deleted, click **Delete**, and click **OK** in the displayed page.
- End

## 4.7.7 Managing Tables on the Flink Web UI

### Scenario

Data tables can be used to define basic attributes and parameters of source tables, dimension tables, and output tables.

### Creating a Stream Table

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Click **Table Management**. The table management page is displayed.
- Step 3** Click **Create Stream Table**. On the stream table creation page, set parameters by referring to [Table 4-25](#) and click **OK**.

**Table 4-25** Parameters for creating a stream table

| Parameter          | Description                                                                                                                                                                                 | Remarks                    |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------|
| Stream/ Table Name | Stream/Table name, which can contain 1 to 64 characters. Only letters, digits, and underscores (_) are allowed.                                                                             | Example: <b>flink_sink</b> |
| Description        | Stream/Table description information, which can contain 1 to 1024 characters.                                                                                                               | -                          |
| Mapping Table Type | Flink SQL does not provide the data storage function. Table creation is actually the creation of mapping for external data tables or storage. The value can be <b>Kafka</b> , <b>HDFS</b> . | -                          |

| Parameter        | Description                                                                                                                                                                                                                                                                             | Remarks                                                                                                                                                      |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Type             | Includes the data source table <b>Source</b> , data result table <b>Sink</b> . Tables included in different mapping table types are as follows: <ul style="list-style-type: none"> <li>• Kafka: <b>Source</b> and <b>Sink</b></li> <li>• HDFS: <b>Source</b> and <b>Sink</b></li> </ul> | -                                                                                                                                                            |
| Data Connection  | Name of the data connection.                                                                                                                                                                                                                                                            | -                                                                                                                                                            |
| Topic            | Kafka topic to be read. Multiple Kafka topics can be read. Use separators to separate topics. This parameter is available when <b>Mapping Table Type</b> is set to <b>Kafka</b> .                                                                                                       | -                                                                                                                                                            |
| File Path        | HDFS directory or a single file path to be transferred. This parameter is available when <b>Mapping Table Type</b> is set to <b>HDFS</b> .                                                                                                                                              | Example: <b>/user/sqoop/</b> or <b>/user/sqoop/example.csv</b>                                                                                               |
| Code             | Codes corresponding to different mapping table types are as follows: <ul style="list-style-type: none"> <li>• Kafka: <b>CSV</b> and <b>JSON</b></li> <li>• HDFS: <b>CSV</b></li> </ul>                                                                                                  | -                                                                                                                                                            |
| Prefix           | When <b>Mapping Table Type</b> is set to <b>Kafka</b> , <b>Type</b> is set to <b>Source</b> , and <b>Code</b> is set to <b>JSON</b> , this parameter indicates the hierarchical prefixes of multi-layer nested JSON, which are separated by commas (,).                                 | For example, <b>data,info</b> indicates that the content under <b>data</b> and <b>info</b> in the nested JSON file is used as the data input in JSON format. |
| Separator        | Meanings of this parameter corresponding to different mapping table types are as follows: This parameter is used to specify the separator between CSV fields. This parameter is available when <b>Code</b> is set to <b>CSV</b> .                                                       | Example: comma (,)                                                                                                                                           |
| Row Separator    | Line break in the file, including <b>\r</b> , <b>\n</b> , and <b>\r\n</b> . This parameter is available when <b>Mapping Table Type</b> is set to <b>HDFS</b> .                                                                                                                          | -                                                                                                                                                            |
| Column Separator | Field separator in the file. This parameter is available when <b>Mapping Table Type</b> is set to <b>HDFS</b> .                                                                                                                                                                         | Example: comma (,)                                                                                                                                           |

| Parameter              | Description                                                                                                                                                                                              | Remarks |
|------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------|
| Stream Table Structure | Stream/Table structure, including <b>Name</b> and <b>Type</b> .                                                                                                                                          | -       |
| Proctime               | System time, which is irrelevant to the data timestamp. That is, the time when the calculation is complete in Flink operators.<br>This parameter is available when <b>Type</b> is set to <b>Source</b> . | -       |
| Event Time             | Time when an event is generated, that is, the timestamp generated during data generation.<br>This parameter is available when <b>Type</b> is set to <b>Source</b> .                                      | -       |

----End

## Editing a Stream Table

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Click **Table Management**. The table management page is displayed.
- Step 3** In the **Operation** column of the item to be modified, click **Edit**. On the displayed page, modify the stream table information by referring to [Table 4-25](#) and click **OK**.

----End

## Searching for a stream table

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Click **Table Management**. The table management page is displayed.
- Step 3** In the upper right corner of the page, you can enter a keyword to search for stream table information.

----End

## Deleting a Stream Table

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Click **Table Management**. The table management page is displayed.
- Step 3** In the **Operation** column of the item to be deleted, click **Delete**, and click **OK** in the displayed page.

----End

## 4.7.8 Managing Jobs on the Flink Web UI

### Scenario

Define Flink jobs, including Flink SQL and Flink JAR jobs.

### Creating a Job

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Click **Job Management**. The job management page is displayed.
- Step 3** Click **Create Job**. On the displayed job creation page, set parameters by referring to [Table 4-26](#) and click **OK**. The job development page is displayed.

**Table 4-26** Parameters for creating a job

| Parameter   | Description                                                                                                      |
|-------------|------------------------------------------------------------------------------------------------------------------|
| Type        | Job type, which can be <b>Flink SQL</b> or <b>Flink Jar</b> .                                                    |
| Name        | Job name, which can contain a maximum of 64 characters. Only letters, digits, and underscores ( _ ) are allowed. |
| Task Type   | Type of the job data source, which can be a stream job or a batch job.                                           |
| Description | Job description, which can contain a maximum of 100 characters.                                                  |

- Step 4** (Optional) If you need to develop a job immediately, configure the job on the job development page.
  - Creating a Flink SQL job
    - a. Develop the job on the job development page.
    - b. Click **Check Semantic** to check the input content and click **Format SQL** to format SQL statements.
    - c. After the job SQL statements are developed, set running parameters by referring to [Table 4-27](#) and click **Save**.

**Table 4-27** Running parameters

| Parameter                    | Description                                                                                                   |
|------------------------------|---------------------------------------------------------------------------------------------------------------|
| Parallelism                  | Number of concurrent jobs. The value must be a positive integer containing a maximum of 64 characters.        |
| Maximum Operator Parallelism | Maximum parallelism of operators. The value must be a positive integer containing a maximum of 64 characters. |

| Parameter               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| JobManager Memory (MB)  | Memory of JobManager The minimum value is <b>512</b> and the value can contain a maximum of 64 characters.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| Submit Queue            | Queue to which a job is submitted. If this parameter is not set, the <b>default</b> queue is used. The queue name can contain a maximum of 30 characters. Only letters, digits, and underscores ( <code>_</code> ) are allowed.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| taskManager             | taskManager running parameters include: <ul style="list-style-type: none"> <li>▪ <b>Slots:</b> If this parameter is left blank, the default value <b>1</b> is used.</li> <li>▪ <b>Memory (MB):</b> The minimum value is <b>512</b>.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Enable CheckPoint       | Whether to enable CheckPoint. After CheckPoint is enabled, you need to configure the following information: <ul style="list-style-type: none"> <li>▪ <b>Time Interval (ms):</b> This parameter is mandatory.</li> <li>▪ <b>Mode:</b> This parameter is mandatory. The options are <b>EXACTLY_ONCE</b> and <b>AT_LEAST_ONCE</b>.</li> <li>▪ <b>Minimum Interval (ms):</b> The minimum value is <b>10</b>.</li> <li>▪ <b>Timeout Duration:</b> The minimum value is <b>10</b>.</li> <li>▪ <b>Maximum Parallelism:</b> The value must be a positive integer containing a maximum of 64 characters.</li> <li>▪ <b>Whether to clean up:</b> This parameter can be set to <b>Yes</b> or <b>No</b>.</li> <li>▪ <b>Whether to enable incremental checkpoints:</b> This parameter can be set to <b>Yes</b> or <b>No</b>.</li> </ul> |
| Failure Recovery Policy | Failure recovery policy of a job. The options are as follows: <ul style="list-style-type: none"> <li>▪ <b>fixed-delay:</b> You need to configure <b>Retry Times</b> and <b>Retry Interval (s)</b>.</li> <li>▪ <b>failure-rate:</b> You need to configure <b>Max Retry Times, Interval (min)</b>, and <b>Retry Interval (s)</b>.</li> <li>▪ <b>none</b></li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                          |

- d. Click **Submit** in the upper left corner to submit the job.
- Creating a Flink JAR job
  - a. Click **Select**, upload a local JAR file, and set parameters by referring to [Table 4-28](#).

**Table 4-28** Parameter configuration

| Parameter              | Description                                                                                                                                                                                                                                    |
|------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Local .jar File        | Upload a local JAR file. The size of the file cannot exceed 10 MB.                                                                                                                                                                             |
| Main Class             | Main-Class type. <ul style="list-style-type: none"> <li>▪ <b>Default:</b> By default, the class name is specified based on the <b>Mainfest</b> file in the JAR file.</li> <li>▪ <b>Specify:</b> Manually specify the class name.</li> </ul>    |
| Type                   | Class name.<br>This parameter is available when <b>Main Class</b> is set to <b>Specify</b> .                                                                                                                                                   |
| Class Parameter        | Class parameters of Main-Class (parameters are separated by spaces).                                                                                                                                                                           |
| Parallelism            | Number of concurrent jobs. The value must be a positive integer containing a maximum of 64 characters.                                                                                                                                         |
| JobManager Memory (MB) | Memory of JobManager The minimum value is <b>512</b> and the value can contain a maximum of 64 characters.                                                                                                                                     |
| Submit Queue           | Queue to which a job is submitted. If this parameter is not set, the <b>default</b> queue is used. The queue name can contain a maximum of 30 characters. Only letters, digits, and underscores (_) are allowed.                               |
| taskManager            | taskManager running parameters include: <ul style="list-style-type: none"> <li>▪ <b>Slots:</b> If this parameter is left blank, the default value <b>1</b> is used.</li> <li>▪ <b>Memory (MB):</b> The minimum value is <b>512</b>.</li> </ul> |

- b. Click **Save** to save the configuration and click **Submit** to submit the job.

**Step 5** Return to the job management page. You can view information about the created job, including job name, type, status, kind, and description.

----End

## Starting a Job

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
  - Step 2** Click **Job Management**. The job management page is displayed.
  - Step 3** In the **Operation** column of the job to be started, click **Start** to run the job. Jobs in the **Draft**, **Saved**, **Submission failed**, **Running succeeded**, **Running failed**, or **Stop** state can be started.
- End

## Developing a Job

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
  - Step 2** Click **Job Management**. The job management page is displayed.
  - Step 3** In the **Operation** column of the job to be developed, click **Develop** to go to the job development page. Develop a job by referring to [Step 4](#). You can view created stream tables and fields in the list on the left.
- End

## Editing the Job Name and Description

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
  - Step 2** Click **Job Management**. The job management page is displayed.
  - Step 3** In the **Operation** column of the item to be modified, click **Edit**, modify **Description**, and click **OK** to save the modification.
- End

## Viewing Job Details

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Click **Job Management**. The job management page is displayed.
- Step 3** In the **Operation** column of the item to be viewed, choose **More** > **Job Monitoring** to view the job running details.

 **NOTE**

You can only view details about jobs in the **Running** state.

----End

## Checkpoint Failure Recovery

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Click **Job Management**. The job management page is displayed.

**Step 3** In the Operation column of the item to be restored, click **More > Checkpoint Failure Recovery**. You can perform checkpoint failure recovery for jobs in the **Running failed**, **Running Succeeded**, or **Stop** state.

----End

## Filtering/Searching for Jobs

**Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).

**Step 2** Click **Job Management**. The job management page is displayed.

**Step 3** In the upper right corner of the page, you can obtain job information by selecting the job name, or enter a keyword to search for a job.

----End

## Stopping a Job

**Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).

**Step 2** Click **Job Management**. The job management page is displayed.

**Step 3** In the **Operation** column of the item to be stopped, click **Stop**. Jobs in the **Submitting**, **Submission succeeded**, or **Running** state can be stopped.

----End

## Deleting a Job

**Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).

**Step 2** Click **Job Management**. The job management page is displayed.

**Step 3** In the **Operation** column of the item to be deleted, click **Delete**, and click **OK** in the displayed page. Jobs in the **Draft**, **Saved**, **Submission failed**, **Running succeeded**, **Running failed**, or **Stop** state can be deleted.

----End

## 4.7.9 Managing UDFs on the Flink Web UI

### 4.7.9.1 Managing UDFs on the Flink Web UI

You can customize functions to extend SQL statements to meet personalized requirements. These functions are called user-defined functions (UDFs). You can upload and manage UDF JAR files on the Flink web UI and call UDFs when running jobs.

Flink supports the following three types of UDFs, as described in [Table 4-29](#).

**Table 4-29** Function classification

| Type                                      | Description                                                                                                                               |
|-------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------|
| User-defined Scalar function (UDF)        | Supports one or more input parameters and returns a single result value. For details, see <a href="#">UDF Java and SQL Examples</a> .     |
| User-defined aggregation function (UDAF)  | Aggregates multiple records into one value. For details, see <a href="#">UDAF Java and SQL Examples</a> .                                 |
| User-defined table-valued function (UDTF) | Supports one or more input parameters and returns multiple rows or columns. For details, see <a href="#">UDTF Java and SQL Examples</a> . |

## Prerequisites

You have prepared a UDF JAR file whose size does not exceed 200 MB.

## Uploading a UDF

- Step 1** Access the Flink web UI. For details, see [Accessing the Flink Web UI](#).
- Step 2** Click **UDF Management**. The **UDF Management** page is displayed.
- Step 3** Click **Add UDF**. Select and upload the prepared UDF JAR file for **Local .jar File**.
- Step 4** Enter the UDF name and description and click **OK**.

### NOTE

A maximum of 10 UDF names can be added. **Name** can be customized. **Type** must correspond to the UDF function in the uploaded UDF JAR file.

- Step 5** In the UDF list, you can view information about all UDFs in the current application.
- Step 6** (Optional) If you need to run or develop a job immediately, configure the job on the **Job Management** page.

Click **Job Management**. The job management page is displayed.

- Starting a UDF job: In the **Operation** column of the UDF job, click **Start**.
- Developing a UDF job: In the **Operation** column of the UDF job, click **Develop**. For details about related parameters, see [Creating a Flink SQL job](#).
- Stopping a UDF job: In the **Operation** column of the UDF job, click **Stop**.
- Deleting a UDF job: In the **Operation** column of the UDF job, click **Delete**. Only jobs in the **Stop** state can be deleted.
- Editing a UDF job: In the **Operation** column of the UDF job, click **Edit**. Only the description of a job can be modified.
- Viewing job details: In the **Operation** column of the UDF job, choose **More > Job Monitoring**.
- Performing checkpoint failure recovery: In the **Operation** column of the UDF job, choose **More > Checkpoint failure recovery** to recover the fault. You can

perform checkpoint failure recovery for jobs in the **Running failed**, **Running Succeeded**, or **Stop** state.

----End

## Editing a UDF

- Step 1** Upload a UDF JAR file. For details, see [Uploading a UDF](#).
- Step 2** In the **Operation** column of the UDF job, click **Edit**. The **Edit UDF** page is displayed.
- Step 3** Modify the information and click **OK**.

----End

## Deleting a UDF

- Step 1** Upload a UDF JAR file. For details, see [Uploading a UDF](#).
- Step 2** In the **Operation** column of the UDF job, click **Delete**. The **Delete UDF** page is displayed.
- Step 3** Confirm the information about the UDF to be deleted and click **OK**.

### NOTE

Only the UDFs that are not used can be deleted.

----End

## 4.7.9.2 UDF Java and SQL Examples

### UDF Java Example

```
package com.xxx.udf;
import org.apache.flink.table.functions.ScalarFunction;
public class UdfClass_UDF extends ScalarFunction {
    public int eval(String s) {
        return s.length();
    }
}
```

### UDF SQL Example

```
CREATE TEMPORARY FUNCTION udf as 'com.xxx.udf.UdfClass_UDF';
CREATE TABLE udfSource (a VARCHAR) WITH ('connector' = 'datagen','rows-per-second'='1');
CREATE TABLE udfSink (a VARCHAR,b int) WITH ('connector' = 'print');
INSERT INTO
    udfSink
SELECT
    a,
    udf(a)
FROM
    udfSource;
```

## 4.7.9.3 UDAF Java and SQL Examples

### UDAF Java Example

```
package com.xxx.udf;
import org.apache.flink.table.functions.AggregateFunction;
```

```
public class UdfClass_UDAF {
    public static class AverageAccumulator {
        public int sum;
    }
    public static class Average extends AggregateFunction<Integer, AverageAccumulator> {
        public void accumulate(AverageAccumulator acc, Integer value) {
            acc.sum += value;
        }
        @Override
        public Integer getValue(AverageAccumulator acc) {
            return acc.sum;
        }
        @Override
        public AverageAccumulator createAccumulator() {
            return new AverageAccumulator();
        }
    }
}
```

## UDAF SQL Example

```
CREATE TEMPORARY FUNCTION udaf as 'com.xxx.udf.UdfClass_UDAF$Average';
CREATE TABLE udfSource (a int) WITH ('connector' = 'datagen','rows-per-second'='1','fields.a.min'='1','fields.a.max'='3');
CREATE TABLE udfSink (b int,c int) WITH ('connector' = 'print');
INSERT INTO
    udfSink
SELECT
    a,
    udaf(a)
FROM
    udfSource group by a;
```

### 4.7.9.4 UDTF Java and SQL Examples

#### UDTF Java Example

```
package com.xxx.udf;
import org.apache.flink.api.java.tuple.Tuple2;
import org.apache.flink.table.functions.TableFunction;
public class UdfClass_UDTF extends TableFunction<Tuple2<String, Integer>> {
    public void eval(String str) {
        Tuple2<String, Integer> tuple2 = Tuple2.of(str, str.length());
        collect(tuple2);
    }
}
```

#### UDTF SQL Example

```
CREATE TEMPORARY FUNCTION udtf as 'com.xxx.udf.UdfClass_UDTF';
CREATE TABLE udfSource (a VARCHAR) WITH ('connector' = 'datagen','rows-per-second'='1');
CREATE TABLE udfSink (b VARCHAR,c int) WITH ('connector' = 'print');
INSERT INTO
    udfSink
SELECT
    str,
    strLength
FROM
    udfSource,lateral table(udtf(udfSource.a)) as T(str,strLength);
```

## 4.7.10 Interconnecting FlinkServer with External Components

### 4.7.10.1 Interconnecting FlinkServer with ClickHouse

#### Scenario

Flink interconnects with the ClickHouseBalancer instance of ClickHouse to read and write data, preventing ClickHouse traffic distribution problems.

#### Prerequisites

- Services such as ClickHouse, HDFS, Yarn, Flink, and HBase have been installed in the cluster.
- The client has been installed, for example, in `/opt/Bigdata/client`.

#### Mapping Between Flink SQL and ClickHouse Data Types

| Flink SQL Data Type | ClickHouse Data Type |
|---------------------|----------------------|
| BOOLEAN             | UInt8                |
| TINYINT             | Int8                 |
| SMALLINT            | Int16                |
| INTEGER             | Int32                |
| BIGINT              | Int64                |
| FLOAT               | Float32              |
| DOUBLE              | Float64              |
| CHAR                | String               |
| VARCHAR             | String               |
| VARBINARY           | FixedString          |
| DATE                | Date                 |
| TIMESTAMP           | DateTime             |
| DECIMAL             | Decimal              |

#### Procedure

- Step 1** Log in to the node where the client is installed as user **root**.
- Step 2** Run the following command to go to the client installation directory:  
**cd /opt/Bigdata/client**
- Step 3** Run the following command to configure environment variables:  
**source bigdata\_env**
- Step 4** If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the current user. The current user must have the

permission to create ClickHouse tables. If Kerberos authentication is disabled for the current cluster, skip this step:

**kinit** *Component service user*

Example: **kinit clickhouseuser**

**Step 5** Connect to the ClickHouse client. For details, see [Using ClickHouse from Scratch](#).

- Normal mode:  
**clickhouse client --host** *IP address of the ClickHouse instance* **--user** *Username* **--password** '*Password*' **--port** *ClickHouse port number*
- Security mode:  
**clickhouse client --host** *IP address of the ClickHouse instance* **--user** *Username* **--password** '*Password*' **--port** *ClickHouse port number* **--secure --multiline**

**Step 6** Run the following statements to create a replication table and a distributed table.

1. Create a replication table **default.test1**.

```
CREATE TABLE default.test1 on cluster default_cluster
(
  `pid` Int8,
  `uid` UInt8,
  `Int_16` Int16,
  `Int_32` Int32,
  `Int_64` Int64,
  `String_x` String,
  `String_y` String,
  `float_32` Float32,
  `float_64` Float64,
  `Decimal_x` Decimal32(2),
  `Date_x` Date,
  `DateTime_x` DateTime
)
ENGINE = ReplicatedReplacingMergeTree('/clickhouse/tables/{shard}/test1',{replica}')
PARTITION BY pid
ORDER BY (pid, DateTime_x);
```

2. Create a distributed table **test1\_all**.

```
CREATE TABLE test1_all ON CLUSTER default_cluster
(
  `pid` Int8,
  `uid` UInt8,
  `Int_16` Int16,
  `Int_32` Int32,
  `Int_64` Int64,
  `String_x` String,
  `String_y` String,
  `float_32` Float32,
  `float_64` Float64,
  `Decimal_x` Decimal32(2),
  `Date_x` Date,
  `DateTime_x` DateTime
)
ENGINE = Distributed(default_cluster, default, test1, rand());
```

**Step 7** Log in to Manager and choose **Cluster > Services > Flink**. In the **Basic Information** area, click the link on the right of **Flink WebUI** to access the Flink web UI.

**Step 8** Create a Flink SQL job and set **Task Type** to **Stream job**. For details, see [Creating a Job](#). On the job development page, configure the job parameters as follows and start the job. Select **Enable CheckPoint** in **Running Parameter** and set **Time Interval (ms)** to **60000**.

- If the current MRS cluster is in security mode, perform the following operations:

```

create table kafkasource(
`pid` TINYINT,
`uid` BOOLEAN,
`Int_16` SMALLINT,
`Int_32` INTEGER,
`Int_64` BIGINT,
`String_x` CHAR,
`String_y` VARCHAR(10),
`float_32` FLOAT,
`float_64` DOUBLE,
`Decimal_x` DECIMAL(9,2),
`Date_x` DATE,
`DateTime_x` TIMESTAMP
) with(
`connector` = 'kafka',
`topic` = 'input',
`properties.bootstrap.servers` = 'IP address of the Kafka broker instance:Kafka port number',
`properties.group.id` = 'group1',
`scan.startup.mode` = 'earliest-offset',
`format` = 'json',
`properties.sasl.kerberos.service.name` = 'kafka',
`properties.security.protocol` = 'SASL_PLAINTEXT',
`properties.kerberos.domain.name` = 'hadoop.System domain name'
);
CREATE TABLE cksink (
`pid` TINYINT,
`uid` BOOLEAN,
`Int_16` SMALLINT,
`Int_32` INTEGER,
`Int_64` BIGINT,
`String_x` CHAR,
`String_y` VARCHAR(10),
`float_32` FLOAT,
`float_64` DOUBLE,
`Decimal_x` DECIMAL(9,2),
`Date_x` DATE,
`DateTime_x` TIMESTAMP
) WITH (
`connector` = 'jdbc',
`url` = 'jdbc:clickhouse://ClickHouseBalancer instance IP address:21422/default?ssl=true&sslmode=none',
`username` = 'ClickHouse user. For details, see the note below.',
`password` = 'ClickHouse user password. For details, see the note below.',
`table-name` = 'test1_all',
`driver` = 'ru.yandex.clickhouse.ClickHouseDriver',
`sink.buffer-flush.max-rows` = '0',
`sink.buffer-flush.interval` = '60s'
);
Insert into cksink
select
*
from
kafkasource;

```

- If the current MRS cluster is in normal mode, perform the following operations:

```

create table kafkasource(
`pid` TINYINT,
`uid` BOOLEAN,
`Int_16` SMALLINT,
`Int_32` INTEGER,
`Int_64` BIGINT,
`String_x` CHAR,
`String_y` VARCHAR(10),
`float_32` FLOAT,
`float_64` DOUBLE,
`Decimal_x` DECIMAL(9,2),

```

```
`Date_x` DATE,  
`DateTime_x` TIMESTAMP  
) with(  
  'connector' = 'kafka',  
  'topic' = 'kinput',  
  'properties.bootstrap.servers' = 'IP address of the Kafka broker instance:Kafka port number',  
  'properties.group.id' = 'kafka_test',  
  'scan.startup.mode' = 'earliest-offset',  
  'format' = 'json'  
);  
CREATE TABLE cksink (  
  `pid` TINYINT,  
  `uid` BOOLEAN,  
  `Int_16` SMALLINT,  
  `Int_32` INTEGER,  
  `Int_64` BIGINT,  
  `String_x` CHAR,  
  `String_y` VARCHAR(10),  
  `float_32` FLOAT,  
  `float_64` DOUBLE,  
  `Decimal_x` DECIMAL(9,2),  
  `Date_x` DATE,  
  `DateTime_x` TIMESTAMP  
) WITH (  
  'connector' = 'jdbc',  
  'url' = 'jdbc:clickhouse://ClickHouseBalancer instance IP address:21425/default',  
  'table-name' = 'test1_all',  
  'driver' = 'ru.yandex.clickhouse.ClickHouseDriver',  
  'sink.buffer-flush.max-rows' = '0',  
  'sink.buffer-flush.interval' = '60s'  
);  
Insert into cksink  
select  
*  
from  
kafkasource;
```

 NOTE

- If an MRS cluster is in the security mode, the user in the **cksink** table must have related permissions on the ClickHouse tables. For details, see [ClickHouse User and Permission Management](#).
- Kafka port number
  - In security mode, the port number is the value of **sasl.port** (21007 by default).
  - In non-security mode, the port is the value of **port** (9092 by default). If the port number is set to **9092**, set **allow.everyone.if.no.acl.found** to **true**. The procedure is as follows:  
Log in to FusionInsight Manager and choose **Cluster > Services > Kafka**. On the displayed page, click **Configurations** and then **All Configurations**, search for **allow.everyone.if.no.acl.found**, set its value to **true**, and click **Save**.
- **21422**: HTTPS port number of the ClickHouseBalancer instance IP address.
- **21425**: HTTP port number of the ClickHouseBalancer instance IP address.
- For details about other JDBC connector parameters, visit the [Flink official website](#).
- Parameters for batch write: Flink stores data in the memory and then flushes the data to the database table when the trigger condition is met. The configurations are as follows:  
**sink.buffer-flush.max-rows**: Number of rows written to ClickHouse. The default value is **100**.  
**sink.buffer-flush.interval**: Interval for batch write. The default value is **1s**.  
If either of the two conditions is met, a sink operation is triggered. That is, data will be flushed to the database table.
  - Scenario 1: sink every 60s  
'sink.buffer-flush.max-rows' = '0',  
'sink.buffer-flush.interval' = '60s'
  - Scenario 2: sink every 100 rows  
'sink.buffer-flush.max-rows' = '100',  
'sink.buffer-flush.interval' = '0s'
  - Scenario 3: no sink  
'sink.buffer-flush.max-rows' = '0',  
'sink.buffer-flush.interval' = '0s'

**Step 9** On the job management page, check whether the job status is **Running**.

**Step 10** Execute the following script to write data to Kafka. For details, see [Managing Messages in Kafka Topics](#).

```
sh kafka-console-producer.sh --broker-list IP address of the node where the  
Kafka instance locates:Kafka port number --topic Topic name --producer.config ../  
config/producer.properties
```

For example, if the topic name is **kinput**, the script is **sh kafka-console-producer.sh --broker-list IP address of the node where the Kafka instance locates:Kafka port number --topic kinput --producer.config ../config/producer.properties**.

Enter the message content.

```
{"pid": "3", "uid": false, "Int_16": "6533", "Int_32": "429496294", "Int_64": "1844674407370955614", "String_x":  
"abc1", "String_y": "abc1defghi", "float_32": "0.1234", "float_64": "95.1", "Decimal_x": "0.451236414", "Date_x":  
"2021-05-29", "DateTime_x": "2021-05-21 10:05:10"},  
{"pid": "4", "uid": false, "Int_16": "6533", "Int_32": "429496294", "Int_64": "1844674407370955614", "String_x":  
"abc1", "String_y": "abc1defghi", "float_32": "0.1234", "float_64": "95.1", "Decimal_x": "0.4512314", "Date_x":  
"2021-05-29", "DateTime_x": "2021-05-21 10:05:10"}
```

Press **Enter** to send the message.

**Step 11** Interconnect with ClickHouse to query the table data.

```
clickhouse client --host IP address of the ClickHouse instance --user Username --password 'Password' --port ClickHouse port number --secure --multiline
```

Run the following command to check whether data is written to a specified ClickHouse table, for example, **test1\_all**.

```
select * from test1_all;
```

```
----End
```

## 4.7.10.2 Interconnecting FlinkServer with HBase

### Scenario

FlinkServer can be interconnected with HBase. The details are as follows:

- It can be interconnected with dimension tables and sink tables.
- When HBase and Flink are in the same cluster or clusters with mutual trust, FlinkServer can be interconnected with HBase.
- If HBase and Flink are in different clusters without mutual trust, Flink in a normal cluster can be interconnected with HBase in a normal cluster.

### Prerequisites

- The HDFS, Yarn, Flink, and HBase services have been installed in a cluster.
- The client that contains the HBase service has been installed, for example, in the **/opt/Bigdata/client** directory.

### Procedure

**Step 1** Log in to the node where the client is installed as the client installation user and copy all configuration files in the **/opt/Bigdata/client/HBase/hbase/conf/** directory of HBase to an empty directory of all nodes where FlinkServer is deployed, for example, **/tmp/client/HBase/hbase/conf/**.

Change the owner of the configuration file directory and its upper-layer directory on the FlinkServer node to **omm**.

```
chown omm: /tmp/client/HBase/hbase/conf/ -R
```

#### NOTE

- FlinkServer nodes:  
Log in to Manager, choose **Cluster > Services > Flink > Instance**, and check the **Service IP Address** of FlinkServer.
- If the node where a FlinkServer instance is located is the node where the HBase client is installed, skip this step on this node.

**Step 2** Log in to Manager, choose **Cluster > Services > Flink > Configurations > All Configurations**, search for the **HBASE\_CONF\_DIR** parameter, and enter the FlinkServer directory (for example, **/tmp/client/HBase/hbase/conf/**) to which the HBase configuration files are copied in **Step 1** in **Value**.

 NOTE

If the node where a FlinkServer instance is located is the node where the HBase client is installed, enter the `/opt/Bigdata/client/HBase/hbase/conf/` directory of HBase in **Value** of the `HBASE_CONF_DIR` parameter.

- Step 3** After the parameters are configured, click **Save**. After confirming the modification, click **OK**.
- Step 4** Click **Instance**, select all FlinkServer instances, choose **More > Restart Instance**, enter the password, and click **OK** to restart the instances.
- Step 5** Log in to Manager and choose **Cluster > Services > Flink**. In the **Basic Information** area, click the link on the right of **Flink WebUI** to access the Flink web UI.
- Step 6** Create a Flink SQL job and set Task Type to Stream job. For details, see [Creating a Job](#). On the job development page, configure the job parameters as follows and start the job.

Select **Enable CheckPoint** in **Running Parameter** and set **Time Interval (ms)** to **60000**.

The following example shows how to create a Flink SQL job:

```
CREATE TABLE ksource1 (  
  user_id STRING,  
  item_id STRING,  
  proctime as PROCTIME()  
) WITH (  
  'connector' = 'kafka',  
  'topic' = 'ksource1',  
  'properties.group.id' = 'group1',  
  'properties.bootstrap.servers' = 'IP address of the Kafka broker instance 1:Kafka port number,IP address of the Kafka broker instance 2:Kafka port number',  
  'format' = 'json',  
  'properties.sasl.kerberos.service.name' = 'kafka'  
)  
  
CREATE TABLE hsink1 (  
  rowkey STRING,  
  f1 ROW < item_id STRING >,  
  PRIMARY KEY (rowkey) NOT ENFORCED  
) WITH (  
  'connector' = 'hbase-2.2',  
  'table-name' = 'dim_province',  
  'zookeeper.quorum' = 'IP address of the ZooKeeper quorumpeer instance 1:ZooKeeper port number'IP address of the ZooKeeper quorumpeer instance 2:ZooKeeper port number'  
)  
  
INSERT INTO  
  hsink1  
SELECT  
  user_id as rowkey,  
  ROW(item_id) as f1  
FROM  
  ksource1;
```

 NOTE

- Kafka port number
  - In security mode, the port number is the value of **sasl.port** (21007 by default).
  - In non-security mode, the port is the value of **port** (9092 by default). If the port number is set to **9092**, set **allow.everyone.if.no.acl.found** to **true**. The procedure is as follows:  
Log in to FusionInsight Manager and choose **Cluster > Services > Kafka**. On the displayed page, click **Configurations** and then **All Configurations**, search for **allow.everyone.if.no.acl.found**, set its value to **true**, and click **Save**.
- IP address of the ZooKeeper quorumpeer instance  
To obtain IP addresses of all ZooKeeper quorumpeer instances, log in to FusionInsight Manager and choose **Cluster > Services > ZooKeeper**. On the displayed page, click **Instance** and view the IP addresses of all the hosts where the quorumpeer instances locate.
- Port number of the ZooKeeper client  
Log in to FusionInsight Manager and choose **Cluster > Service > ZooKeeper**. On the displayed page, click **Configurations** and check the value of **clientPort**. The default value is **24002**.

**Step 7** On the job management page, check whether the job status is **Running**.

**Step 8** Execute the following script to write data to Kafka. For details, see [Managing Messages in Kafka Topics](#).

```
sh kafka-console-producer.sh --broker-list IP address of the node where the Kafka instance locates:Kafka port number --topic Topic name
```

For example, if the topic name is **ksource1**, the script is **sh kafka-console-producer.sh --broker-list *IP address of the node where the Kafka instance locates*:*Kafka port number* --topic ksource1**.

Enter the message content.  

```
{"user_id": "3","item_id":"333333"},  
{"user_id": "4","item_id":"44444444"}
```

Press **Enter** to send the message.

**Step 9** Log in to the HBase client and view the table data. For details, see [Using an HBase Client](#).

```
hbase shel  
scan 'dim_province'  
----End
```

## Submitting a Job Using the Application

- If the Flink run mode is used, you are advised to use the **export HBASE\_CONF\_DIR= *HBase configuration directory***, for example, **export HBASE\_CONF\_DIR=/opt/hbaseconf**.
- If the Flink run-application mode is used, you can use either of the following methods to submit jobs:
  - (Recommended) Add the following configurations to a table creation statement.

| Parameter                                               | Description                                                      |
|---------------------------------------------------------|------------------------------------------------------------------|
| 'properties.hbase.rpc.protection' = 'authentication'    | This parameter must be consistent with that on the HBase server. |
| 'properties.hbase.security.authorization' = 'true'      | Authentication is enabled.                                       |
| 'properties.hbase.security.authentication' = 'kerberos' | Kerberos authentication is enabled.                              |

**Example:**

```
CREATE TABLE hsink1 (
  rowkey STRING,
  f1 ROW < q1 STRING >,
  PRIMARY KEY (rowkey) NOT ENFORCED
) WITH (
  'connector' = 'hbase-2.2',
  'table-name' = 'cc',
  'zookeeper.quorum' = 'x.x.x.x:24002',
  'properties.hbase.rpc.protection' = 'authentication',
  'properties.zookeeper.znode.parent' = '/hbase',
  'properties.hbase.security.authorization' = 'true',
  'properties.hbase.security.authentication' = 'kerberos'
);
```

- Add the HBase configuration to YarnShip.  
Example: Dyarn.ship-files=/opt/hbaseconf

### 4.7.10.3 Interconnecting FlinkServer with HDFS

#### Scenario

This section describes the data definition language (DDL) of HDFS as a sink table, as well as the WITH parameters and example code for creating a sink table, and provides guidance on how to perform operations on the FlinkServer job management page.

If your Kafka cluster is in security mode, the following example SQL statements can be used.

#### Prerequisites

- The HDFS, Yarn, and Flink services have been installed in a cluster.
- The client that contains the HDFS service has been installed, for example, in the **/opt/Bigdata/client** directory.
- You have created a user with **FlinkServer Admin Privilege**, for example, **flink\_admin**, to access the Flink web UI. For details, see [Authentication Based on Users and Roles](#).

#### Procedure

- Step 1** Log in to Manager as user **flink\_admin** and choose **Cluster > Services > Flink**. In the **Basic Information** area, click the link on the right of **Flink WebUI** to access the Flink web UI.

**Step 2** Create a Flink SQL job by referring to [Creating a Job](#). On the job development page, configure the job parameters as follows and start the job.

Select **Enable CheckPoint** in **Running Parameter** and set **Time Interval (ms)** to **60000**.

```
CREATE TABLE kafka_table (
  user_id STRING,
  order_amount DOUBLE,
  log_ts TIMESTAMP(3),
  WATERMARK FOR log_ts AS log_ts - INTERVAL '5' SECOND
) WITH (
  'connector' = 'kafka',
  'topic' = 'user_source',
  'properties.bootstrap.servers' = 'IP address of the Kafka broker instance:Kafka port number',
  'properties.group.id' = 'testGroup',
  'scan.startup.mode' = 'latest-offset',
  'format' = 'csv',
  --Ignore the CSV data that fails to be parsed.
  'csv.ignore-parse-errors' = 'true' ,--If the data is in JSON format, set 'json.ignore-parse-errors' to true.
  'properties.sasl.kerberos.service.name' = 'kafka',
  'properties.security.protocol' = 'SASL_PLAINTEXT',
  'properties.kerberos.domain.name' = 'hadoop.System domain name'
);

CREATE TABLE fs_table (
  user_id STRING,
  order_amount DOUBLE,
  dt STRING,
  `hour` STRING
) PARTITIONED BY (dt, `hour`) WITH ( --Date-specific file partitioning
  'connector'='filesystem',
  'path'='hdfs://sql/parquet',
  'format'='parquet',
  'sink.partition-commit.delay'='1 h',
  'sink.partition-commit.policy.kind'='success-file'
);
-- streaming sql, insert into file system table
INSERT INTO fs_table SELECT user_id, order_amount, DATE_FORMAT(log_ts, 'yyyy-MM-dd'),
DATE_FORMAT(log_ts, 'HH') FROM kafka_table;
```

#### NOTE

Kafka port number

- In security mode, the port number is the value of **sasl.port** (21007 by default).
- In non-security mode, the port is the value of **port** (9092 by default). If the port number is set to **9092**, set **allow.everyone.if.no.acl.found** to **true**. The procedure is as follows:

Log in to FusionInsight Manager and choose **Cluster > Services > Kafka**. On the displayed page, click **Configurations** and then **All Configurations**, search for **allow.everyone.if.no.acl.found**, set its value to **true**, and click **Save**.

**Step 3** On the job management page, check whether the job status is **Running**.

**Step 4** Execute the following commands to view the topic and write data to Kafka. For details, see [Managing Messages in Kafka Topics](#).

```
./kafka-topics.sh --list --zookeeper IP address of the ZooKeeper quorumpeer instance:ZooKeeper port number/kafka
```

```
sh kafka-console-producer.sh --broker-list IP address of the node where the Kafka instance locates:Kafka port number --topic Topic name --producer.config Client directory/Kafka/kafka/config/producer.properties
```

For example, if the topic name is **user\_source**, the script is **sh kafka-console-producer.sh --broker-list IP address of the node where the Kafka instance**

```
locates:Kafka port number --topic user_source --producer.config /opt/Bigdata/  
client/Kafka/kafka/config/producer.properties.
```

Enter the message content.

```
3,3333,"2021-09-10 14:00"  
4,4444,"2021-09-10 14:01"
```

Press **Enter** to send the message.

#### NOTE

- IP address of the ZooKeeper quorumpeer instance  
To obtain IP addresses of all ZooKeeper quorumpeer instances, log in to FusionInsight Manager and choose **Cluster > Services > ZooKeeper**. On the displayed page, click **Instance** and view the IP addresses of all the hosts where the quorumpeer instances locate.
- Port number of the ZooKeeper client  
Log in to FusionInsight Manager and choose **Cluster > Service > ZooKeeper**. On the displayed page, click **Configurations** and check the value of **clientPort**. The default value is **24002**.

**Step 5** Run the following command to check whether data is written from the HDFS directory to the sink table:

```
hdfs dfs -ls -R /sql/parquet
```

```
----End
```

## Interconnecting Flink with HDFS Partitions

- Customized partitioning  
Flink's file system supports partitions in the standard Hive format. You do not need to register partitions with a table catalog. Partitions are inferred based on the directory structure.

For example, a table that is partitioned based on the following directory is inferred to contain datetime and hour partitions.

```
path  
├── datetime=2021-09-03  
│   ├── hour=11  
│   │   ├── part-0.parquet  
│   │   └── part-1.parquet  
│   └── hour=12  
│       └── part-0.parquet  
└── datetime=2021-09-24  
    └── hour=6  
        └── part-0.parquet
```

- Rolling policy of partition files  
Data in the partition directories is split into part files. Each partition contains at least one part file, which is used to receive the data written by the subtask of the sink.

The following parameters describe the rolling policies of partition files.

| Parameter                             | Default Value | Type        | Description                                                               |
|---------------------------------------|---------------|-------------|---------------------------------------------------------------------------|
| sink.rolling-policy.file-size         | 128 MB        | Memory Size | Maximum size of a partition file before it is rolled.                     |
| sink.rolling-policy.rollover-interval | 30 minutes    | Duration    | Maximum duration that a partition file can stay open before it is rolled. |
| sink.rolling-policy.check-interval    | 1 minute      | Duration    | Interval for checking time-based rolling policies.                        |

- File merging

File compression is supported, allowing applications to have a shorter checkpoint interval without generating a large number of files.

 **NOTE**

Only files in a single checkpoint are compressed. That is, the number of generated files is at least the same as the number of checkpoints. Files are invisible before merged. They are visible after both the checkpoint and compression are complete. If file compression takes too much time, the checkpoint will be prolonged.

| Parameter            | Default Value | Type        | Description                                                                                                                                                                                                                               |
|----------------------|---------------|-------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| auto-compaction      | false         | Boolean     | Whether to enable automatic compression. Data will be written to temporary files. After a checkpoint is complete, the temporary files generated by the checkpoint are compressed. These temporary files are invisible before compression. |
| compaction.file-size | none          | Memory Size | Size of the target file to be compressed. The default value is the size of the file to be rolled.                                                                                                                                         |

- Partition commit

After a file is written to a partition, for example, a partition is added to Hive metastore (HMS) or a **\_SUCCESS** file is written to a directory, the downstream application needs to be notified. Triggers and policies are used to commit partition files.

- Trigger parameters for committing partition files

| Parameter                     | Default Value | Type     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-------------------------------|---------------|----------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| sink.partition-commit.trigger | process-time  | String   | <ul style="list-style-type: none"> <li>process-time: System time of the compute node. It does not need to extract the partition time or generate watermarks. If the current system time exceeds the system time generated when a partition is created plus the delay time, the partition should be submitted.</li> <li>partition-time: Time extracted from the partition. Watermarks are required. If the time for generating watermarks exceeds the time extracted from a partition plus the delay time, the partition should be submitted.</li> </ul> |
| sink.partition-commit.delay   | 0 s           | Duration | Partitions will not be committed before the delay time. If it is a daily partition, the value is <b>1 d</b> . If it is an hourly one, the value is <b>1 h</b> .                                                                                                                                                                                                                                                                                                                                                                                         |

- Policy parameters for committing partition files

| Parameter                          | Default Value | Type   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|------------------------------------|---------------|--------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| sink.partition-commit.policy.kind  | -             | String | <p>Policy for committing partitions:</p> <ul style="list-style-type: none"> <li><b>metastore</b>: used to add partitions to metastore. Only Hive tables support the metastore policy. The file system manages partitions based on the directory structure.</li> <li><b>success-file</b>: used to add <b>success-file</b> files to a directory.</li> <li>The two policies can be configured at the same time, that is, <b>'sink.partition-commit.policy.kind='metastore,success-file'</b>.</li> </ul> |
| sink.partition-commit.policy.class | -             | String | <p>Class that implements partition commit policy interfaces.</p> <p>This parameter takes effect only in the customized submission policies.</p>                                                                                                                                                                                                                                                                                                                                                      |

| Parameter                               | Default Value | Type   | Description                                                                                   |
|-----------------------------------------|---------------|--------|-----------------------------------------------------------------------------------------------|
| sink.partition-commit.success-file.name | _SUCCESS      | String | File name of the success-file partition commit policy. The default value is <b>_SUCCESS</b> . |

#### 4.7.10.4 Interconnecting FlinkServer with Hive

##### Scenario

Currently, FlinkServer interconnects with Hive MetaStore. Therefore, the MetaStore function must be enabled for Hive. Hive can be used as source, sink, and dimension tables.

If your Kafka cluster is in security mode, the following example SQL statements can be used.

##### Prerequisites

- Services such as HDFS, Yarn, Kafka, Flink, and Hive have been installed in the cluster.
- The client that contains the Hive service has been installed, for example, in the **/opt/Bigdata/client** directory.
- Flink 1.12.2 or later and Hive 3.1.0 or later are supported.
- You have created a user with **FlinkServer Admin Privilege**, for example, **flink\_admin**, to access the Flink web UI. For details, see [Authentication Based on Users and Roles](#).
- You have obtained the client configuration file and credential of the user for accessing the Flink web UI. For details, see "Note" in [Creating a Cluster Connection](#).

##### Procedure

The following uses the process of interconnecting a Kafka mapping table to Hive as an example.

**Step 1** Log in to the Flink web UI as user **flink\_admin**. For details, see [Accessing the Flink Web UI](#).

**Step 2** Create a cluster connection, for example, **flink\_hive**.

1. Choose **System Management > Cluster Connection Management**. The **Cluster Connection Management** page is displayed.
2. Click **Create Cluster Connection**. On the displayed page, enter information by referring to [Table 4-30](#) and click **Test**. After the test is successful, click **OK**.

**Table 4-30** Parameters for creating a cluster connection

| Parameter               | Description                                                                                                                                                                                                                                                                     | Example Value                         |
|-------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------|
| Cluster Connection Name | Name of the cluster connection, which can contain a maximum of 100 characters. Only letters, digits, and underscores ( _ ) are allowed.                                                                                                                                         | flink_hive                            |
| Description             | Description of the cluster connection name.                                                                                                                                                                                                                                     | -                                     |
| Version                 | Select a cluster version.                                                                                                                                                                                                                                                       | MRS 3                                 |
| Secure Version          | <ul style="list-style-type: none"> <li>- If the secure version is used, select <b>Yes</b> for a security cluster. Enter the username and upload the user credential.</li> <li>- If not, select <b>No</b>.</li> </ul>                                                            | Yes                                   |
| Username                | The user must have the minimum permissions for accessing services in the cluster. The name can contain a maximum of 100 characters. Only letters, digits, and underscores ( _ ) are allowed. This parameter is available only when <b>Secure Version</b> is set to <b>Yes</b> . | flink_admin                           |
| Client Profile          | Client profile of the cluster, in TAR format.                                                                                                                                                                                                                                   | -                                     |
| User Credential         | User authentication credential in FusionInsight Manager in TAR format. This parameter is available only when <b>Secure Version</b> is set to <b>Yes</b> . Files can be uploaded only after the username is entered.                                                             | User credential of <b>flink_admin</b> |

**Step 3** Create a Flink SQL job, for example, **flinktest1**.

1. Click **Job Management**. The job management page is displayed.
2. Click **Create Job**. On the displayed job creation page, set parameters by referring to [Table 4-31](#) and click **OK**. The job development page is displayed.

**Table 4-31** Parameters for creating a job

| Parameter | Description                                                                                                      | Example Value |
|-----------|------------------------------------------------------------------------------------------------------------------|---------------|
| Type      | Job type, which can be <b>Flink SQL</b> or <b>Flink Jar</b> .                                                    | Flink SQL     |
| Name      | Job name, which can contain a maximum of 64 characters. Only letters, digits, and underscores ( _ ) are allowed. | flinktest1    |

| Parameter   | Description                                                            | Example Value |
|-------------|------------------------------------------------------------------------|---------------|
| Task Type   | Type of the job data source, which can be a stream job or a batch job. | Stream job    |
| Description | Job description, which can contain a maximum of 100 characters.        | -             |

**Step 4** On the job development page, enter the following statements and click **Check Semantic** to check the input content.

```
CREATE TABLE test_kafka (
  user_id varchar,
  item_id varchar,
  cat_id varchar,
  zw_test timestamp
) WITH (
  'properties.bootstrap.servers' = 'IP address of the Kafka broker instance:Kafka port number',
  'format' = 'json',
  'topic' = 'zw_tset_kafka',
  'connector' = 'kafka',
  'scan.startup.mode' = 'latest-offset',
  'properties.sasl.kerberos.service.name' = 'kafka',
  'properties.security.protocol' = 'SASL_PLAINTEXT',
  'properties.kerberos.domain.name' = 'hadoop.System domain name'
);
CREATE CATALOG myhive WITH (
  'type' = 'hive',
  'hive-version' = '3.1.0',
  'default-database' = 'default',
  'cluster.name' = 'flink_hive'
);
use catalog myhive;
set table.sql-dialect = hive;create table user_behavior_hive_tbl_no_partition (
  user_id STRING,
  item_id STRING,
  cat_id STRING,
  ts timestamp
) PARTITIONED BY (dy STRING, ho STRING, mi STRING) stored as textfile TBLPROPERTIES (
  'partition.time-extractor.timestamp-pattern' = '$dy $ho:$mi:00',
  'sink.partition-commit.trigger' = 'process-time',
  'sink.partition-commit.delay' = '0S',
  'sink.partition-commit.policy.kind' = 'metastore,success-file'
);
INSERT into
  user_behavior_hive_tbl_no_partition
SELECT
  user_id,
  item_id,
  cat_id,
  zw_test,
  DATE_FORMAT(zw_test, 'yyyy-MM-dd'),
  DATE_FORMAT(zw_test, 'HH'),
  DATE_FORMAT(zw_test, 'mm')
FROM
  default_catalog.default_database.test_kafka;
```

 NOTE

- Kafka port number
  - In security mode, the port number is the value of **sasl.port** (21007 by default).
  - In non-security mode, the port is the value of **port** (9092 by default). If the port number is set to 9092, set **allow.everyone.if.no.acl.found** to **true**. The procedure is as follows:  
Log in to FusionInsight Manager and choose **Cluster > Services > Kafka**. On the displayed page, click **Configurations** and then **All Configurations**, search for **allow.everyone.if.no.acl.found**, set its value to **true**, and click **Save**.
- The value of '**cluster.name**' is the name of the cluster connection created in **Step 2**.
- For details about related parameters, visit Flink official website <http://flink.apache.org/>.

**Step 5** After the job is developed, select **Enable CheckPoint** in **Running Parameter** and set **Time Interval (ms)** to **60000**.

**Step 6** Click **Submit** in the upper left corner to submit the job.

**Step 7** After the job is successfully executed, choose **More > Job Monitoring** to view the job running details.

**Step 8** Execute the following commands to view the topic and write data to Kafka. For details, see [Managing Messages in Kafka Topics](#).

```
./kafka-topics.sh --list --zookeeper IP address of the ZooKeeper quorumpeer instance:ZooKeeper port number/kafka
```

```
sh kafka-console-producer.sh --broker-list IP address of the node where the Kafka instance locates:Kafka port number --topic Topic name --producer.config Client directory/Kafka/kafka/config/producer.properties
```

For example, if the topic name is **zw\_tset\_kafka**, the script is **sh kafka-console-producer.sh --broker-list IP address of the node where the Kafka instance locates:Kafka port number --topic zw\_tset\_kafka --producer.config /opt/Bigdata/client/Kafka/kafka/config/producer.properties**.

Enter the message content.

```
{"user_id": "3","item_id":"333333","cat_id":"cat333","zw_test":"2021-09-08 09:08:01"}  
{"user_id": "4","item_id":"444444","cat_id":"cat444","zw_test":"2021-09-08 09:08:01"}
```

Press **Enter** to send the message.

 NOTE

- IP address of the ZooKeeper quorumpeer instance  
To obtain IP addresses of all ZooKeeper quorumpeer instances, log in to FusionInsight Manager and choose **Cluster > Services > ZooKeeper**. On the displayed page, click **Instance** and view the IP addresses of all the hosts where the quorumpeer instances locate.
- Port number of the ZooKeeper client  
Log in to FusionInsight Manager and choose **Cluster > Service > ZooKeeper**. On the displayed page, click **Configurations** and check the value of **clientPort**. The default value is **24002**.

**Step 9** Run the following command to check whether data is written from the Hive table to the sink table:

**beeline**

```
select * from user_behavior_hive_tbl_no_partition;  
----End
```

### 4.7.10.5 Interconnecting FlinkServer with Hudi

#### Scenario

This section describes how to interconnect FlinkServer with Hudi through Flink SQL jobs.

#### Prerequisites

- The HDFS, Yarn, Flink, and Hudi services have been installed in a cluster.
- The client that contains the Hudi service has been installed, for example, in the `/opt/Bigdata/client` directory.
- Flink 1.12.2 or later and Hudi 0.9.0 or later are required.
- You have created a user with **FlinkServer Admin Privilege**, for example, `flink_admin`, to access the Flink web UI. For details, see [Authentication Based on Users and Roles](#).

### Flink Support for Read and Write Operations on Hudi Tables

[Table 4-32](#) lists the read and write operations supported by Flink on Hudi COW and MOR tables.

**Table 4-32** Flink support for read and write operations on Hudi tables

| Flink SQL    | COW table | MOR table |
|--------------|-----------|-----------|
| Batch write  | Supported | Supported |
| Batch read   | Supported | Supported |
| Stream write | Supported | Supported |
| Stream read  | Supported | Supported |

#### NOTE

Currently, Flink SQL allows you to read data from Hudi tables only in snapshot mode and read optimized mode.

#### Procedure

- Step 1** Log in to Manager as user `flink_admin` and choose **Cluster > Services > Flink**. In the **Basic Information** area, click the link on the right of **Flink WebUI** to access the Flink web UI.
- Step 2** Create a Flink SQL job by referring to [Creating a Job](#). On the job development page, configure the job parameters as follows and start the job.

Select **Enable CheckPoint** in **Running Parameter** and set **Time Interval (ms)** to **60000**.

 **NOTE**

- CheckPoint should be enabled on the Flink web UI because data is written to a Hudi table only when a Flink SQL job triggers CheckPoint. Adjust the CheckPoint interval based on service requirements. You are advised to set the interval to a large number.
- If the CheckPoint interval is too short, job exceptions may occur due to untimely data updates. It is recommended that the CheckPoint interval be configured at the minute level.
- Asynchronous compaction is required when a Flink SQL job writes an MOR table. For details about the parameter for controlling the compaction interval, visit Hudi official website <https://hudi.apache.org/docs/configurations.html>.
- The following shows a Flink SQL job writing data to an MOR table in stream mode. Only the Kafka JSON format is supported.

```
CREATE TABLE stream_mor(
  uuid VARCHAR(20),
  name VARCHAR(10),
  age INT,
  ts INT,
  `p` VARCHAR(20)
) PARTITIONED BY (`p`) WITH (
  'connector' = 'hudi',
  'path' = 'hdfs://hacluster/tmp/hudi/stream_mor',
  'table.type' = 'MERGE_ON_READ'
);

CREATE TABLE kafka(
  uuid VARCHAR(20),
  name VARCHAR(10),
  age INT,
  ts INT,
  `p` VARCHAR(20)
) WITH (
  'connector' = 'kafka',
  'topic' = 'writehudi',
  'properties.bootstrap.servers' = 'IP address of the Kafka broker instance.Kafka port number',
  'properties.group.id' = 'testGroup1',
  'scan.startup.mode' = 'latest-offset',
  'format' = 'json'
);

insert into
stream_mor
select
*
from
kafka;
```

- The following shows a Flink SQL job writing data to a COW table in stream mode:

```
CREATE TABLE stream_write_cow(
  uuid VARCHAR(20),
  name VARCHAR(10),
  age INT,
  ts INT,
  `p` VARCHAR(20)
) PARTITIONED BY (`p`) WITH (
  'connector' = 'hudi',
  'path' = 'hdfs://hacluster/tmp/hudi/stream_cow'
);

CREATE TABLE kafka(
  uuid VARCHAR(20),
  name VARCHAR(10),
```

```
age INT,  
ts INT,  
`p` VARCHAR(20)  
) WITH (  
'connector' = 'kafka',  
'topic' = 'writehudi',  
'properties.bootstrap.servers' = 'IP address of the Kafka broker instance.Kafka port number',  
'properties.group.id' = 'testGroup1',  
'scan.startup.mode' = 'latest-offset',  
'format' = 'json'  
);  
  
insert into  
stream_write_cow  
select  
*  
from  
kafka;
```

- The following shows a Flink SQL job reading an MOR table.

```
CREATE TABLE hudi_read_spark_mor(  
uuid VARCHAR(20),  
name VARCHAR(10),  
age INT,  
ts INT,  
`p` VARCHAR(20)  
) PARTITIONED BY (`p`) WITH (  
'connector' = 'hudi',  
'path' = 'hdfs://hacluster/tmp/default/tb_hudimor',  
'table.type' = 'MERGE_ON_READ'  
);  
  
CREATE TABLE kafka(  
uuid VARCHAR(20),  
name VARCHAR(10),  
age INT,  
ts timestamp(6)INT,  
`p` VARCHAR(20)  
) WITH (  
'connector' = 'kafka',  
'topic' = 'writehudi',  
'properties.bootstrap.servers' = 'IP address of the Kafka broker instance.Kafka port number',  
'properties.group.id' = 'testGroup1',  
'scan.startup.mode' = 'latest-offset',  
'format' = 'json'  
);  
  
insert into  
hudi_read_spark_mor  
select  
*  
from  
kafka;
```

#### NOTE

Kafka port number

- In security mode, the port number is the value of **sasl.port** (21007 by default).
- In non-security mode, the port is the value of **port** (9092 by default). If the port number is set to **9092**, set **allow.everyone.if.no.acl.found** to **true**. The procedure is as follows:

Log in to FusionInsight Manager and choose **Cluster > Services > Kafka**. On the displayed page, click **Configurations** and then **All Configurations**, search for **allow.everyone.if.no.acl.found**, set its value to **true**, and click **Save**.

**Step 3** After data is written to the Hudi table by a Flink SQL job and is read by Spark and Hive, use **run\_hive\_sync\_tool.sh** to synchronize the data in the Hudi table to Hive.

For details about the synchronization method, see [Synchronizing Hudi Table Data to Hive](#).

---

**NOTICE**

Ensure that no partition is added before the synchronization. After the synchronization, new partitions cannot be read.

---

----End

## 4.7.10.6 Interconnecting FlinkServer with Kafka

### Scenario

This section describes the data definition language (DDL) of Kafka as a source or sink table, as well as the WITH parameters and example code for creating a table, and provides guidance on how to perform operations on the FlinkServer job management page.

If your Kafka cluster is in security mode, the following example SQL statements can be used.

### Prerequisites

- The HDFS, Yarn, Kafka, and Flink services have been installed in a cluster.
- The client that contains the Kafka service has been installed, for example, in the `/opt/Bigdata/client` directory.
- You have created a user with **FlinkServer Admin Privilege**, for example, `flink_admin`, to access the Flink web UI. For details, see [Authentication Based on Users and Roles](#).

### Procedure

**Step 1** Log in to Manager as user `flink_admin` and choose **Cluster > Services > Flink**. In the **Basic Information** area, click the link on the right of **Flink WebUI** to access the Flink web UI.

**Step 2** Create a Flink SQL job by referring to [Creating a Job](#). On the job development page, configure the job parameters as follows and start the job.

Select **Enable CheckPoint** in **Running Parameter** and set **Time Interval (ms)** to **60000**.

```
CREATE TABLE KafkaSource (  
  `user_id` VARCHAR,  
  `user_name` VARCHAR,  
  `age` INT  
) WITH (  
  'connector' = 'kafka',  
  'topic' = 'test_source',  
  'properties.bootstrap.servers' = 'IP address of the Kafka broker instance:Kafka port number',  
  'properties.group.id' = 'testGroup',  
  'scan.startup.mode' = 'latest-offset',  
  'format' = 'csv',  
  'properties.sasl.kerberos.service.name' = 'kafka',  
  'properties.security.protocol' = 'SASL_PLAINTEXT',
```

```
'properties.kerberos.domain.name' = 'hadoop.System domain name'
);
CREATE TABLE KafkaSink(
  `user_id` VARCHAR,
  `user_name` VARCHAR,
  `age` INT
) WITH (
  'connector' = 'kafka',
  'topic' = 'test_sink',
  'properties.bootstrap.servers' = 'IP address of the Kafka broker instance:Kafka port number',
  'scan.startup.mode' = 'latest-offset',
  'value.format' = 'csv',
  'properties.sasl.kerberos.service.name' = 'kafka',
  'properties.security.protocol' = 'SASL_PLAINTEXT',
  'properties.kerberos.domain.name' = 'hadoop.System domain name'
);
Insert into
  KafkaSink
select
  *
from
  KafkaSource;
```

 **NOTE**

Kafka port number

- In security mode, the port number is the value of **sasl.port** (21007 by default).
- In non-security mode, the port is the value of **port** (9092 by default). If the port number is set to **9092**, set **allow.everyone.if.no.acl.found** to **true**. The procedure is as follows:

Log in to FusionInsight Manager and choose **Cluster > Services > Kafka**. On the displayed page, click **Configurations** and then **All Configurations**, search for **allow.everyone.if.no.acl.found**, set its value to **true**, and click **Save**.

**Step 3** On the job management page, check whether the job status is **Running**.

**Step 4** Execute the following commands to view the topic and write data to Kafka. For details, see [Managing Messages in Kafka Topics](#).

```
./kafka-topics.sh --list --zookeeper IP address of the ZooKeeper quorumpeer instance:ZooKeeper port number/kafka
```

```
sh kafka-console-producer.sh --broker-list IP address of the node where the Kafka instance locates:Kafka port number --topic Topic name --producer.config Client directory/Kafka/kafka/config/producer.properties
```

For example, if the topic name is **test\_source**, the script is **sh kafka-console-producer.sh --broker-list IP address of the node where the Kafka instance locates:Kafka port number --topic test\_source --producer.config /opt/Bigdata/client/Kafka/kafka/config/producer.properties**.

Enter the message content.

```
1,clw,33
```

Press **Enter** to send the message.

 **NOTE**

- IP address of the ZooKeeper quorumpeer instance  
To obtain IP addresses of all ZooKeeper quorumpeer instances, log in to FusionInsight Manager and choose **Cluster > Services > ZooKeeper**. On the displayed page, click **Instance** and view the IP addresses of all the hosts where the quorumpeer instances locate.
- Port number of the ZooKeeper client  
Log in to FusionInsight Manager and choose **Cluster > Service > ZooKeeper**. On the displayed page, click **Configurations** and check the value of **clientPort**. The default value is **24002**.

**Step 5** Run the following commands to check whether data is written from the Kafka topic to the sink table:

```
sh kafka-console-consumer.sh --topic Topic name --bootstrap-server IP address of the Kafka broker instance:Kafka port number --consumer.config /opt/Bigdata/client/Kafka/kafka/config/consumer.properties
```

----End

## WITH Parameters

| Parameter                    | Mandatory                                                                                                                                     | Type   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------|--------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| connector                    | Yes                                                                                                                                           | String | Connector to be used. <b>kafka</b> is used for Kafka.                                                                                                                                                                                                                                                                                                                                                                                                   |
| topic                        | <ul style="list-style-type: none"> <li>• Yes (Kafka functions as a sink table.)</li> <li>• No (Kafka functions as a source table.)</li> </ul> | String | Topic name. <ul style="list-style-type: none"> <li>• When the Kafka is used as a source table, this parameter indicates the name of the topic from which data is read. Topic list is supported. Topics are separated by semicolons (;), for example, <b>Topic-1; Topic-2</b>.</li> <li>• When Kafka is used as a sink table, this parameter indicates the name of the topic to which data is written. Topic list is not supported for sinks.</li> </ul> |
| topic-pattern                | No (Kafka functions as a source table.)                                                                                                       | String | Topic pattern.<br>This parameter is available when Kafka is used as a source table. The topic name must be a regular expression.<br><b>NOTE</b><br><b>topic-pattern</b> and <b>topic</b> cannot be set at the same time.                                                                                                                                                                                                                                |
| properties.bootstrap.servers | Yes                                                                                                                                           | String | List of Kafka brokers, which are separated by commas (,).                                                                                                                                                                                                                                                                                                                                                                                               |

| Parameter           | Mandatory                                | Type   | Description                                                                |
|---------------------|------------------------------------------|--------|----------------------------------------------------------------------------|
| properties.group.id | Yes (Kafka functions as a source table.) | String | Kafka user group ID.                                                       |
| format              | Yes                                      | String | Format of the value used for deserializing and serializing Kafka messages. |
| properties.*        | No                                       | String | Authentication-related parameters that need to be added in security mode.  |

## 4.8 Deleting Residual Information About Flink Tasks

### Scenario

If a Flink task stops unexpectedly, some directories may reside in the ZooKeeper and HDFS services. To delete the residual directories, set **ClearUpEnabled** to **true**.

### Prerequisites

A FlinkServer instance has been installed in a cluster and is running properly.

### Procedure

- Step 1** Log in to Manager.
- Step 2** Choose **Cluster > Services > Flink**. On the displayed page, click the **Configurations** tab and then **All Configurations**, search for parameter **ClearUpEnabled**, and set it to **true**. For details about related parameters, see [Table 4-33](#).

**Table 4-33** Parameters for deleting the residual directories

| Parameter      | Description                                                                                                                                                           | Default Value | Value Range    |
|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|----------------|
| ClearUpEnabled | Specifies whether to delete the residual directories. Set this parameter to <b>true</b> if residual directories need to be deleted; set it to <b>false</b> otherwise. | true          | true and false |

| Parameter                     | Description                                                          | Default Value | Value Range      |
|-------------------------------|----------------------------------------------------------------------|---------------|------------------|
| ClearUpPeriod                 | Specifies the period for deleting residual directories, in minutes.  | 1440          | 1440~2147483647  |
| TrashDirectoryRetentionPeriod | Specifies the period for retaining residual directories, in minutes. | 10080         | 10080~2147483647 |

**Step 3** Click **Save**.

#### NOTICE

- This function deletes only the residual directories in the **/flink\_base** directory of the ZooKeeper service and the **/flink/recovery** directory of the HDFS service. User-defined directories will not be deleted.
- This function does not delete the **checkpoints** directory of the HDFS service. You need to manually delete it.

----End

## 4.9 Flink Log Overview

### Log Description

#### Log path:

- Run logs of a Flink job: **`\${BIGDATA\_DATA\_HOME}/hadoop/data\${i}/nm/containerlogs/application\_\${appid}/container\_\${\$contid}**

#### NOTE

The logs of executing tasks are stored in the preceding path. After the execution is complete, the Yarn configuration determines whether these logs are gathered to the HDFS directory.

- FlinkResource run logs: **/var/log/Bigdata/flink/flinkResource**
- FlinkServer run logs: **/var/log/Bigdata/flink/flinkserver**
- FlinkServer audit logs: **/var/log/Bigdata/audit/flink/flinkserver**

#### Log archive rules:

1. FlinkResource run logs:
  - By default, service logs are backed up each time when the log size reaches 20 MB. A maximum of 20 logs can be reserved without being compressed.

- You can set the log size and number of compressed logs on the Manager page or modify the corresponding configuration items in **log4j-cli.properties**, **log4j.properties**, and **log4j-session.properties** in **/opt/client/Flink/flink/conf/** on the client. **/opt/client** is the client installation directory.

**Table 4-34** FlinkResource log list

| Type                   | Name             | Description              |
|------------------------|------------------|--------------------------|
| FlinkResource run logs | checkService.log | Health check log         |
|                        | kinit.log        | Initialization log       |
|                        | postinstall.log  | Service installation log |
|                        | prestart.log     | Prestart script log      |
|                        | start.log        | Startup log              |

2. FlinkServer service logs and audit logs

- By default, FlinkServer service logs and audit logs are backed up each time when the log size reaches 100 MB. The service logs are stored for a maximum of 30 days, and audit logs are stored for a maximum of 90 days.
- You can set the log size and number of compressed logs on the Manager page or modify the corresponding configuration items in **log4j-cli.properties**, **log4j.properties**, and **log4j-session.properties** in **/opt/client/Flink/flink/conf/** on the client. **/opt/client** is the client installation directory.

**Table 4-35** FlinkServer log list

| Type                 | Name                                           | Description                                                   |
|----------------------|------------------------------------------------|---------------------------------------------------------------|
| FlinkServer run logs | checkService.log                               | Health check log                                              |
|                      | cleanup.log                                    | Cleanup log file for instance installation and uninstallation |
|                      | flink-omm-client- <i>IP</i> .log               | Job startup log                                               |
|                      | flinkserver_YYYYMMDD-x.log.gz                  | Service archive log                                           |
|                      | flinkserver.log                                | Service log                                                   |
|                      | flinkserver--- <i>pidxxx</i> -gc.log.x.current | GC log                                                        |
|                      | kinit.log                                      | Initialization log                                            |
|                      | postinstall.log                                | Service installation log                                      |

| Type                   | Name                                | Description         |
|------------------------|-------------------------------------|---------------------|
|                        | prestart.log                        | Prestart script log |
|                        | start.log                           | Startup log         |
|                        | stop.log                            | Stop log            |
| FlinkServer audit logs | flinkserver_audit_YYYYMMDD-x.log.gz | Audit archive log   |
|                        | flinkserver_audit.log               | Audit log           |

## Log Level

**Table 4-36** describes the log levels supported by Flink. The priorities of log levels are ERROR, WARN, INFO, and DEBUG in descending order. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 4-36** Log levels

| Level | Description                                                   |
|-------|---------------------------------------------------------------|
| ERROR | Error information about the current event processing          |
| WARN  | Exception information about the current event processing      |
| INFO  | Normal running status information about the system and events |
| DEBUG | System information and system debugging information           |

To modify log levels, perform the following steps:

- Step 1** Go to the **All Configurations** page of Flink by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** On the menu bar on the left, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Save the configuration. In the displayed dialog box, click **OK** to make the configurations take effect.

----End

 NOTE

- After the configuration is complete, you do not need to restart the service. Download the client again for the configuration to take effect.
- You can also change the configuration items corresponding to the log level in **log4j-cli.properties**, **log4j.properties**, and **log4j-session.properties** in **/opt/client/Flink/flink/conf/** on the client. **/opt/client** is the client installation directory.
- When a job is submitted using a client, a log file is generated in the **log** folder on the client. The default umask value is **0022**. Therefore, the default log permission is **644**. To change the file permission, you need to change the umask value. For example, to change the umask value of user **omm**:
  - Add **umask 0026** to the end of the **/home/omm/.baskrc** file.
  - Run the **source /home/omm/.baskrc** command to make the file permission take effect.

## Log Format

Table 4-37 Log formats

| Type    | Format                                                                                                                                                                                                    | Example                                                                                                                                                                                                                                                                |
|---------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Run log | <i>&lt;yyyy-MM-dd<br/>HH:mm:ss,SSS&gt; &lt;Log<br/>level&gt; &lt;Name of the<br/>thread that generates<br/>the log&gt; &lt;Message in the<br/>log&gt; &lt;Location where<br/>the log event occurs&gt;</i> | 2019-06-27 21:30:31,778<br>  INFO   [flink-<br>akka.actor.default-<br>dispatcher-3]  <br>TaskManager<br>container_e10_14982906<br>98388_0004_02_000007<br>has started.  <br>org.apache.flink.yarn.Yar<br>nFlinkResourceManager<br>(FlinkResourceManag-<br>er.java:368) |

## 4.10 Flink Performance Tuning

### 4.10.1 Optimization DataStream

#### 4.10.1.1 Memory Configuration Optimization

##### Scenarios

The computing of Flink depends on memory. If the memory is insufficient, the performance of Flink will be greatly deteriorated. One solution is to monitor garbage collection (GC) to evaluate the memory usage. If the memory becomes the performance bottleneck, optimize the memory usage according to the actual situation.

If **Full GC** is frequently reported in the Container GC on the Yarn that monitors the node processes, the GC needs to be optimized.

 **NOTE**

In the **env.java.opts** configuration item of the **conf/flink-conf.yaml** file on the client, add the **-Xloggc:<LOG\_DIR>/gc.log -XX:+PrintGCDetails -XX:-OmitStackTraceInFastThrow -XX:+PrintGCTimeStamps -XX:+PrintGCDateStamps -XX:+UseGCLogFileRotation -XX:NumberOfGCLogFiles=20 -XX:GCLogFileSize=20M** parameter. The GC log is configured by default.

## Procedure

- Optimize GC.  
Adjust the ratio of tenured generation memory to young generation memory. In the **conf/flink-conf.yaml** configuration file on the client, add the **-XX:NewRatio** parameter to the **env.java.opts** configuration item. For example, **-XX:NewRatio=2** indicates that ratio of tenured generation memory to young generation memory is 2:1, that is, the young generation memory occupies one third and tenured generation memory occupies two thirds.
- When developing Flink applications, optimize the partitioning or grouping operation of `DataStream`.
  - If partitioning causes data skew, partitions need to be optimized.
  - Do not perform concurrent operations, because some operations, `WindowAll` for example, to `DataStream` do not support parallelism.
  - Do not use `setKeyBy` to string type.

### 4.10.1.2 Configuring DOP

#### Scenario

The degree of parallelism (DOP) indicates the number of tasks to be executed concurrently. It determines the number of data blocks after the operation. Configuring the DOP will optimize the number of tasks, data volume of each task, and the host processing capability.

Query the CPU and memory usage. If data and tasks are not evenly distributed among nodes, increase the DOP for even distribution.

#### Procedure

Configure the DOP at one of the following layers (the priorities of which are in the descending order) based on the actual memory, CPU, data, and application logic conditions:

- Operator

Call the **setParallelism()** method to specify the DOP of an operator, data source, and sink. For example:

```
final StreamExecutionEnvironment env = StreamExecutionEnvironment.getExecutionEnvironment();  
  
DataStream<String> text = [...]  
DataStream<Tuple2<String, Integer>> wordCounts = text  
    .flatMap(new LineSplitter())  
    .keyBy(0)
```

```
.timeWindow(Time.seconds(5))  
.sum(1).setParallelism(5);  
  
wordCounts.print();  
env.execute("Word Count Example");
```

- Execution environment

Flink runs in the execution environment which defines a default DOP for operators, data source and data sink.

Call the **setParallelism()** method to specify the default DOP of the execution environment. Example:

```
final StreamExecutionEnvironment env = StreamExecutionEnvironment.getExecutionEnvironment();  
env.setParallelism(3);  
DataStream<String> text = [...]  
DataStream<Tuple2<String, Integer>> wordCounts = [...]  
wordCounts.print();  
env.execute("Word Count Example");
```

- Client

Specify the DOP when submitting jobs to Flink on the client. If you use the CLI client, specify the DOP using the **-p** parameter. Example:

```
./bin/flink run -p 10 ../examples/*WordCount-java*.jar
```

- System

On the Flink client, modify the **parallelism.default** parameter in the **flink-conf.yaml** file under the conf to specify the DOP for all execution environments.

### 4.10.1.3 Configuring Process Parameters

#### Scenario

In Flink on Yarn mode, there are JobManagers and TaskManagers. JobManagers and TaskManagers schedule and run tasks.

Therefore, configuring parameters of JobManagers and TaskManagers can optimize the execution performance of a Flink application. Perform the following steps to optimize the Flink cluster performance.

#### Procedure

**Step 1** Configure JobManager memory.

JobManagers are responsible for task scheduling and message communications between TaskManagers and ResourceManagers. JobManager memory needs to be increased as the number of tasks and the DOP increases.

JobManager memory needs to be configured based on the number of tasks.

- When running the **yarn-session** command, add the **-jm MEM** parameter to configure the memory.
- When running the **yarn-cluster** command, add the **-yjm MEM** parameter to configure the memory.

**Step 2** Configure the number of TaskManagers.

Each core of a TaskManager can run a task at the same time. Increasing the number of TaskManagers has the same effect as increasing the DOP. Therefore,

you can increase the number of TaskManagers to improve efficiency when there are sufficient resources.

**Step 3** Configure the number of TaskManager slots.

Multiple cores of a TaskManager can process multiple tasks at the same time. This has the same effect as increasing the DOP. However, the balance between the number of cores and the memory must be maintained, because all cores of a TaskManager share the memory.

- When running the **yarn-session** command, add the **-s NUM** parameter to configure the number of slots.
- When running the **yarn-cluster** command, add the **-ys NUM** parameter to configure the number of slots.

**Step 4** Configure TaskManager memory.

TaskManager memory is used for task execution and communication. A large-size task requires more resources. In this case, you can increase the memory.

- When running the **yarn-session** command, add the **-tm MEM** parameter to configure the memory.
- When running the **yarn-cluster** command, add the **-ytm MEM** parameter to configure the memory.

----End

#### 4.10.1.4 Optimizing the Design of Partitioning Method

##### Scenarios

The divide of tasks can be optimized by optimizing the partitioning method. If data skew occurs in a certain task, the whole execution process is delayed. Therefore, when designing the partitioning method, ensure that partitions are evenly assigned.

##### Procedure

Partitioning methods are as follows:

- **Random partitioning:** randomly partitions data.  
`dataStream.shuffle();`
- **Rebalancing (round-robin partitioning):** evenly partitions data based on round-robin. The partitioning method is useful to optimize data with data skew.  
`dataStream.rebalance();`
- **Rescaling:** assign data to downstream subsets in the form of round-robin. The partitioning method is useful if you want to deliver data from each parallel instance of a data source to subsets of some mappers without the using `rebalance ()`, that is, the complete rebalance operation.  
`dataStream.rescale();`
- **Broadcast:** broadcast data to all partitions.  
`dataStream.broadcast();`

- **User-defined partitioning:** use a user-defined partitioner to select a target task for each element. The user-defined partitioning allows user to partition data based on a certain feature to achieve optimized task execution.

The following is an example:

```
// fromElements builds simple Tuple2 stream
DataStream<Tuple2<String, Integer>> dataStream = env.fromElements(Tuple2.of("hello",1),
Tuple2.of("test",2), Tuple2.of("world",100));

// Defines the key value used for partitioning. Adding one to the value equals to the id.
Partitioner<Tuple2<String, Integer>> strPartitioner = new Partitioner<Tuple2<String, Integer>>() {
    @Override
    public int partition(Tuple2<String, Integer> key, int numPartitions) {
        return (key.f0.length() + key.f1) % numPartitions;
    }
};

// The Tuple2 data is used as the basis for partitioning.

dataStream.partitionCustom(strPartitioner, new KeySelector<Tuple2<String, Integer>, Tuple2<String,
Integer>>() {
    @Override
    public Tuple2<String, Integer> getKey(Tuple2<String, Integer> value) throws Exception {
        return value;
    }
}).print();
```

### 4.10.1.5 Configuring the Netty Network Communication

#### Scenarios

The communication of Flink is based on Netty network. The network performance determines the data switching speed and task execution efficiency. Therefore, the performance of Flink can be optimized by optimizing the Netty network.

#### Procedure

In the **conf/flink-conf.yaml** file on the client, change configurations as required. Exercise caution when changing default values, because default values are optimal.

- **taskmanager.network.netty.num-arenas:** Specifies the number of arenas of Netty. The default value is **taskmanager.numberOfTaskSlots**.
- **taskmanager.network.netty.server.numThreads** and **taskmanager.network.netty.client.numThreads:** specify the number of threads on the client and server. The default value is **taskmanager.numberOfTaskSlots**.
- **taskmanager.network.netty.client.connectTimeoutSec:** specifies the timeout interval for connection of TaskManager client. The default value is **120s**.
- **taskmanager.network.netty.sendReceiveBufferSize:** specifies the buffer size of the Netty network. The default value is the buffer size (cat /proc/sys/net/ipv4/tcp\_[rw]mem) of the system and the value is usually 4 MB.
- **taskmanager.network.netty.transport:** specifies the transmission method of the Netty network. The default value is **nio**. The value can only be **nio** and **epoll**.

### 4.10.1.6 Summarization

#### Avoiding Data Skew

If data skew occurs (certain data volume is large), the execution time of tasks is inconsistent even if no garbage collection is performed.

- Redefine keys. Use keys of smaller granularity to optimize the task size.
- Modify the DOP.
- Call the rebalance operation to balance data partitions.

#### Setting Timeout Interval for the Buffer

- During the execution of tasks, data is switched through network switching. You can configure the `setBufferTimeout` parameter to specify the timeout interval for the buffer.
- If `setBufferTimeout` is set to `-1`, the refreshing operation is performed when the buffer full, maximizing the throughput. If `setBufferTimeout` is set to `0`, the refreshing operation is performed each time data is received, minimizing the delay. If `setBufferTimeout` is set to a value greater than `0`, the refreshing operation is performed after the buffer times out.

The following is an example:

```
env.setBufferTimeout(timeoutMillis);  
env.generateSequence(1,10).map(new MyMapper()).setBufferTimeout(timeoutMillis);
```

## 4.11 Common Flink Shell Commands

Before running the Flink shell commands, perform the following steps:

**Step 1** Install the Flink client in a directory, for example, `/opt/client`.

**Step 2** Run the following command to initialize environment variables:

```
source /opt/client/bigdata_env
```

**Step 3** If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the user. If Kerberos authentication is disabled, skip this step.

```
kinit Service user
```

**Step 4** Run the related commands according to [Table 4-38](#).

**Table 4-38** Flink Shell commands

| Command         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         | Description                                                            |
|-----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------|
| yarn-session.sh | <p><b>-at,--applicationType &lt;arg&gt;</b>: Defines the Yarn application type.</p> <p><b>-D &lt;property=value&gt;</b>: Configures dynamic parameter.</p> <p><b>-d,--detached</b>: Disables the interactive mode and starts a separate Flink Yarn session.</p> <p><b>-h,--help</b>: Displays the help information about the Yarn session CLI.</p> <p><b>-id,--applicationId &lt;arg&gt;</b>: Binds to a running Yarn session.</p> <p><b>-j,--jar &lt;arg&gt;</b>: Sets the path of the user's JAR file.</p> <p><b>-jm,--jobManagerMemory &lt;arg&gt;</b>: Sets the JobManager memory.</p> <p><b>-m,--jobmanager &lt;arg&gt;</b>: Address of the JobManager (master) to which to connect. Use this parameter to connect to a specified JobManager.</p> <p><b>-nl,--nodeLabel &lt;arg&gt;</b>: Specifies the nodeLabel of the Yarn application.</p> <p><b>-nm,--name &lt;arg&gt;</b>: Customizes a name for the application on Yarn.</p> <p><b>-q,--query</b>: Queries available Yarn resources.</p> <p><b>-qu,--queue &lt;arg&gt;</b>: Specifies a Yarn queue.</p> <p><b>-s,--slots &lt;arg&gt;</b>: Sets the number of slots for each TaskManager.</p> <p><b>-t,--ship &lt;arg&gt;</b>: specifies the directory of the file to be sent.</p> <p><b>-tm,--taskManagerMemory &lt;arg&gt;</b>: sets the TaskManager memory.</p> <p><b>-yd,--yarndetached</b>: starts Yarn in the detached mode.</p> <p><b>-z,--zookeeperNamespace &lt;args&gt;</b>: specifies the namespace of ZooKeeper.</p> <p><b>-h</b>: Gets help information.</p> | Start a resident Flink cluster to receive tasks from the Flink client. |

| Command   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            | Description                                                                                                                                                                                                                                                                                                                |
|-----------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| flink run | <p><b>-c,--class &lt;classname&gt;</b>: Specifies a class as the entry for running programs.</p> <p><b>-C,--classpath &lt;url&gt;</b>: Specifies classpath.</p> <p><b>-d,--detached</b>: Runs a job in the detached mode.</p> <p><b>-files,--dependencyFiles &lt;arg&gt;</b>: File on which the Flink program depends.</p> <p><b>-n,--allowNonRestoredState</b>: A state that cannot be restored can be skipped during restoration from a snapshot point in time. For example, if an operator in the program is deleted, you need to add this parameter when restoring the snapshot point.</p> <p><b>-m,--jobmanager &lt;host:port&gt;</b>: Specifies the JobManager.</p> <p><b>-p,--parallelism &lt;parallelism&gt;</b>: Specifies the job DOP, which will overwrite the DOP parameter in the configuration file.</p> <p><b>-q,--sysoutLogging</b>: Disables the function of outputting Flink logs to the console.</p> <p><b>-s,--fromSavepoint &lt;savepointPath&gt;</b>: Specifies a savepoint path for recovering jobs.</p> <p><b>-z,--zookeeperNamespace &lt;zookeeperNamespace&gt;</b>: specifies the namespace of ZooKeeper.</p> <p><b>-yat,--yarnapplicationType &lt;arg&gt;</b>: Defines the Yarn application type.</p> <p><b>-yD &lt;arg&gt;</b>: Dynamic parameter configuration.</p> <p><b>-yd,--yarndetached</b>: Starts Yarn in the detached mode.</p> <p><b>-yh,--yarnhelp</b>: Obtains the Yarn help.</p> <p><b>-yid,--yarnapplicationId &lt;arg&gt;</b>: Binds a job to a Yarn session.</p> <p><b>-yj,--yarnjar &lt;arg&gt;</b>: Sets the path to Flink jar file.</p> | <p>Submit a Flink job.</p> <ol style="list-style-type: none"> <li>1. The <b>-y*</b> parameter is used in the <b>yarn-cluster</b> mode.</li> <li>2. If the parameter is not <b>-y*</b>, you need to run the <b>yarn-session</b> command to start the Flink cluster before running this command to submit a task.</li> </ol> |

| Command    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | Description                                               |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------|
|            | <p><b>-yjm,--yarnjobManagerMemory &lt;arg&gt;</b>: Sets the JobManager memory (MB).</p> <p><b>-ynm,--yarnname &lt;arg&gt;</b>: Customizes a name for the application on Yarn.</p> <p><b>-yq,--yarnquery</b>: Queries available Yarn resources (memory and CPUs).</p> <p><b>-yqu,--yarnqueue &lt;arg&gt;</b>: Specifies a Yarn queue.</p> <p><b>-ys,--yarnslots</b>: Sets the number of slots for each TaskManager.</p> <p><b>-yt,--yarnship &lt;arg&gt;</b>: Specifies the path of the file to be sent.</p> <p><b>-ytm,--yarntaskManagerMemory &lt;arg&gt;</b>: Sets the TaskManager memory (MB).</p> <p><b>-yz,--yarnzookeeperNamespace &lt;arg&gt;</b>: Specifies the namespace of ZooKeeper. The value must be the same as the value of <b>yarn-session.sh -z</b>.</p> <p><b>-h</b>: Gets help information.</p> |                                                           |
| flink info | <p><b>-c,--class &lt;classname&gt;</b>: Specifies a class as the entry for running programs.</p> <p><b>-p,--parallelism &lt;parallelism&gt;</b>: Specifies the DOP for running programs.</p> <p><b>-h</b>: Gets help information.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              | Display the execution plan (JSON) of the running program. |
| flink list | <p><b>-a,--all</b>: displays all jobs.</p> <p><b>-m,--jobmanager &lt;host:port&gt;</b>: specifies the JobManager.</p> <p><b>-r,--running</b>: displays only jobs in the running state.</p> <p><b>-s,--scheduled</b>: displays only jobs in the scheduled state.</p> <p><b>-z,--zookeeperNamespace &lt;zookeeperNamespace&gt;</b>: specifies the namespace of ZooKeeper.</p> <p><b>-yid,--yarnapplicationId &lt;arg&gt;</b>: binds a job to a Yarn session.</p> <p><b>-h</b>: gets help information.</p>                                                                                                                                                                                                                                                                                                            | Query running programs in the cluster.                    |

| Command         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   | Description                                                                                                                                                          |
|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| flink stop      | <p><b>-d,--drain</b>: sends MAX_WATERMARK before the savepoint is triggered and the job is stopped.</p> <p><b>-p,--savepointPath &lt;savepointPath&gt;</b>: path for storing savepoints. The default value is <b>state.savepoints.dir</b>.</p> <p><b>-m,--jobmanager &lt;host:port&gt;</b>: specifies the JobManager.</p> <p><b>-z,--zookeeperNamespace &lt;zookeeperNamespace&gt;</b>: specifies the namespace of ZooKeeper.</p> <p><b>-yid,--yarnapplicationId &lt;arg&gt;</b>: binds a job to a Yarn session.</p> <p><b>-h</b>: gets help information.</p> | <p>Forcibly stop a running job (only streaming jobs are supported).</p> <p><b>StoppableFunction</b> needs to be implemented on the source side in service code).</p> |
| flink cancel    | <p><b>-m,--jobmanager &lt;host:port&gt;</b>: specifies the JobManager.</p> <p><b>-s,--withSavepoint &lt;targetDirectory&gt;</b>: triggers a savepoint when a job is canceled. The default directory is <b>state.savepoints.dir</b>.</p> <p><b>-z,--zookeeperNamespace &lt;zookeeperNamespace&gt;</b>: specifies the namespace of ZooKeeper.</p> <p><b>-yid,--yarnapplicationId &lt;arg&gt;</b>: binds a job to a Yarn session.</p> <p><b>-h</b>: gets help information.</p>                                                                                   | <p>Cancel a running job.</p>                                                                                                                                         |
| flink savepoint | <p><b>-d,--dispose &lt;arg&gt;</b>: specifies a directory for storing the savepoint.</p> <p><b>-m,--jobmanager &lt;host:port&gt;</b>: specifies the JobManager.</p> <p><b>-z,--zookeeperNamespace &lt;zookeeperNamespace&gt;</b>: specifies the namespace of ZooKeeper.</p> <p><b>-yid,--yarnapplicationId &lt;arg&gt;</b>: binds a job to a Yarn session.</p> <p><b>-h</b>: gets help information.</p>                                                                                                                                                       | <p>Trigger a savepoint.</p>                                                                                                                                          |

| Command                                                        | Description                                       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|----------------------------------------------------------------|---------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>source Client installation directory/ bigdata_env</code> | None                                              | <p>Import client environment variables.</p> <p>Restriction: If the user uses a custom script (for example, <b>A.sh</b>) and runs this command in the script, variables cannot be imported to the <b>A.sh</b> script. If variables need to be imported to the custom script <b>A.sh</b>, the user needs to use the secondary calling method.</p> <p>For example, first call the <b>B.sh</b> script in the <b>A.sh</b> script, and then run this command in the <b>B.sh</b> script. Parameters can be imported to the <b>A.sh</b> script but cannot be imported to the <b>B.sh</b> script.</p> |
| <code>start-scala-shell.sh</code>                              | local   remote <host> <port>   yarn: running mode | Start the scala shell.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| <code>sh generate_key store.sh</code>                          | -                                                 | Run the <b>generate_keystore.sh</b> script to generate security cookie, <b>flink.keystore</b> , and <b>flink.truststore</b> . You need to enter a user-defined password that does not contain number signs (#).                                                                                                                                                                                                                                                                                                                                                                              |

----End

# 5 Using Flume

---

## 5.1 Using Flume from Scratch

### Scenario

You can use Flume to import collected log information to Kafka.

### Prerequisites

- A streaming cluster with Kerberos authentication enabled has been created.
- The Flume client has been installed on the node where logs are generated, for example, `/opt/Flumeclient`. For details about how to install the Flume client, see . The client directory in the following operations is only an example. Change it to the actual installation directory.
- The streaming cluster can properly communicate with the node where logs are generated.

### Using the Flume Client

#### NOTE

You do not need to perform [Step 2](#) to [Step 6](#) for a normal cluster.

#### **Step 1** Install the client.

For details, see .

#### **Step 2** Copy the configuration file of the authentication server from the Master1 node to the *Flume client installation directory*/**fusioninsight-flume-Flume component version number**/**conf** directory on the node where the Flume client resides.

The full file path is `${BIGDATA_HOME}/FusionInsight_BASE_XXX/1_X_KerberosClient/etc/kdc.conf`. In the preceding path, **XXX** indicates the product version number. **X** indicates a random number. Change it based on the site requirements. The file must be saved by the user who installs the Flume client, for example, user **root**.

**Step 3** Check the service IP address of any node where the Flume role is deployed.

Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Flume > Instance**. Check the service IP address of any node where the Flume role is deployed.

**Step 4** Copy the user authentication file from this node to the *Flume client installation directory/fusioninsight-flume-Flume component version number/conf* directory on the Flume client node.

The full file path is `${BIGDATA_HOME}/FusionInsight_Porter_XXX/install/FusionInsight-Flume-Flume component version number/flume/conf/flume.keytab`.

In the preceding paths, **XXX** indicates the product version number. Change it based on the site requirements. The file must be saved by the user who installs the Flume client, for example, user **root**.

**Step 5** Copy the **jaas.conf** file from this node to the **conf** directory on the Flume client node.

The full file path is `${BIGDATA_HOME}/FusionInsight_Current/1_X_Flume/etc/jaas.conf`.

In the preceding path, **X** indicates a random number. Change it based on the site requirements. The file must be saved by the user who installs the Flume client, for example, user **root**.

**Step 6** Log in to the Flume client node and go to the client installation directory. Run the following command to modify the file:

```
vi conf/jaas.conf
```

Change the full path of the user authentication file defined by **keyTab** to the **Flume client installation directory/fusioninsight-flume-Flume component version number/conf** saved in [Step 4](#), and save the modification and exit.

**Step 7** Run the following command to modify the **flume-env.sh** configuration file of the Flume client:

```
vi Flume client installation directory/fusioninsight-flume-Flume component version number/conf/flume-env.sh
```

Add the following information after **-XX:+UseCMSCompactAtFullCollection**:

```
-Djava.security.krb5.conf=Flume client installation directory/fusioninsight-flume-1.9.0/conf/kdc.conf -  
Djava.security.auth.login.config=Flume client installation directory/fusioninsight-flume-1.9.0/conf/jaas.conf -  
Dzookeeper.request.timeout=120000
```

For example, **"-XX:+UseCMSCompactAtFullCollection -  
Djava.security.krb5.conf=Flume client installation directory/fusioninsight-flume-Flume component version number/conf/kdc.conf -  
Djava.security.auth.login.config=Flume client installation directory/fusioninsight-flume-Flume component version number/conf/jaas.conf -  
Dzookeeper.request.timeout=120000"**

Change *Flume client installation directory* to the actual installation directory. Then save and exit.

**Step 8** Run the following command to restart the Flume client:

```
cd Flume client installation directory/fusioninsight-flume-Flume component version number/bin
```

```
./flume-manage.sh restart
```

Example:

```
cd /opt/FlumeClient/fusioninsight-flume-Flume component version number/bin
```

```
./flume-manage.sh restart
```

**Step 9** Configure jobs based on actual service scenarios.

- Some parameters can be configured for MRS 3.x or later on Manager. For details, see [Non-Encrypted Transmission](#) or [Encrypted Transmission](#).
- Set the parameters in the **properties.properties** file. The following uses SpoolDir Source+File Channel+Kafka Sink as an example.

Run the following command on the node where the Flume client is installed to configure and save a job in **properties.properties** (Flume client configuration file) based on service requirements by referring to [Flume Service Configuration Guide](#):

```
vi Flume client installation directory/fusioninsight-flume-Flume component version number/conf/properties.properties
```

```
#####  
#####  
client.sources = static_log_source  
client.channels = static_log_channel  
client.sinks = kafka_sink  
#####  
#####  
#LOG_TO_HDFS_ONLINE_1  
  
client.sources.static_log_source.type = spooldir  
client.sources.static_log_source.spoolDir = Monitoring directory  
client.sources.static_log_source.fileSuffix = .COMPLETED  
client.sources.static_log_source.ignorePattern = ^$  
client.sources.static_log_source.trackerDir = Metadata storage path during transmission  
client.sources.static_log_source.maxBlobLength = 16384  
client.sources.static_log_source.batchSize = 51200  
client.sources.static_log_source.inputCharset = UTF-8  
client.sources.static_log_source.deserializer = LINE  
client.sources.static_log_source.selector.type = replicating  
client.sources.static_log_source.fileHeaderKey = file  
client.sources.static_log_source.fileHeader = false  
client.sources.static_log_source.basenameHeader = true  
client.sources.static_log_source.basenameHeaderKey = basename  
client.sources.static_log_source.deletePolicy = never  
  
client.channels.static_log_channel.type = file  
client.channels.static_log_channel.dataDirs = Data cache path. Multiple paths, separated by commas  
(,), can be configured to improve performance.  
client.channels.static_log_channel.checkpointDir = Checkpoint storage path  
client.channels.static_log_channel.maxFileSize = 2146435071  
client.channels.static_log_channel.capacity = 1000000  
client.channels.static_log_channel.transactionCapacity = 612000  
client.channels.static_log_channel.minimumRequiredSpace = 524288000  
  
client.sinks.kafka_sink.type = org.apache.flume.sink.kafka.KafkaSink  
client.sinks.kafka_sink.kafka.topic = Topic to which data is written, for example, flume_test  
client.sinks.kafka_sink.kafka.bootstrap.servers = XXX.XXX.XXX.XXX:Kafka port  
number,XXX.XXX.XXX.XXX:Kafka port number,XXX.XXX.XXX.XXX:Kafka port number  
client.sinks.kafka_sink.flumeBatchSize = 1000  
client.sinks.kafka_sink.kafka.producer.type = sync  
client.sinks.kafka_sink.kafka.security.protocol = SASL_PLAINTEXT
```

```
client.sinks.kafka_sink.kafka.kerberos.domain.name = Kafka domain name. This parameter is mandatory for a security cluster; for example, hadoop.xxx.com.
client.sinks.kafka_sink.requiredAcks = 0

client.sources.static_log_source.channels = static_log_channel
client.sinks.kafka_sink.channel = static_log_channel
```

 **NOTE**

- **client.sinks.kafka\_sink.kafka.topic:** Topic to which data is written. If the topic does not exist in Kafka, it is automatically created by default.
- **client.sinks.kafka\_sink.kafka.bootstrap.servers:** List of Kafka Brokers, which are separated by commas (,). By default, the port is **21007** for a security cluster and **9092** for a normal cluster.
- **client.sinks.kafka\_sink.kafka.security.protocol:** The value is **SASL\_PLAINTEXT** for a security cluster and **PLAINTEXT** for a normal cluster.
- **client.sinks.kafka\_sink.kafka.kerberos.domain.name:**

You do not need to set this parameter for a normal cluster. For a security cluster, the value of this parameter is the value of **kerberos.domain.name** in the Kafka cluster.

In the preceding paths, **X** indicates a random number. Change it based on site requirements. The file must be saved by the user who installs the Flume client, for example, user **root**.

**Step 10** After the parameters are set and saved, the Flume client automatically loads the content configured in **properties.properties**. When new log files are generated by `spoolDir`, the files are sent to Kafka producers and can be consumed by Kafka consumers. For details, see [Managing Messages in Kafka Topics](#).

----End

## 5.2 Overview

Flume is a distributed, reliable, and highly available system for aggregating massive logs, which can efficiently collect, aggregate, and move massive log data from different data sources and store the data in a centralized data storage system. Various data senders can be customized in the system to collect data. Additionally, Flume provides simple data processes capabilities and writes data to data receivers (which is customizable).

Flume consists of the client and server, both of which are FlumeAgents. The server corresponds to the FlumeServer instance and is directly deployed in a cluster. The client can be deployed inside or outside the cluster. The client-side and service-side FlumeAgents work independently and provide the same functions.

The client-side FlumeAgent needs to be independently installed. Data can be directly imported to components such as HDFS and Kafka. Additionally, the client-side and service-side FlumeAgents can also work together to provide services.


### Process

The process for collecting logs using Flume is as follows:

1. Installing the flume client
2. Configuring the Flume server and client parameters

3. Collecting and querying logs using the Flume client
4. Stopping and uninstalling the Flume client

**Figure 5-1** Log collection process



## Flume Client

A Flume client consists of the source, channel, and sink. The source sends the data to the channel, and then the sink transmits the data from the channel to the external device. [Table 5-1](#) describes Flume modules.

**Table 5-1** Module description

| Name   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|--------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Source | <p>A source receives or generates data and sends the data to one or multiple channels. The source can work in either data-driven or polling mode.</p> <p>Typical sources include:</p> <ul style="list-style-type: none"><li>• Sources that are integrated with the system and receives data, such as Syslog and Netcat</li><li>• Sources that automatically generate event data, such as Exec and SEQ</li><li>• IPC sources that are used for communication between agents, such as Avro</li></ul> <p>A Source must associate with at least one channel.</p> |

| Name    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|---------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Channel | <p>A channel is used to buffer data between a source and a sink. After the sink transmits the data to the next channel or the destination, the cache is deleted automatically.</p> <p>The persistency of the channels varies with the channel types:</p> <ul style="list-style-type: none"> <li>• Memory channel: non-persistency</li> <li>• File channel: persistency implemented based on write-ahead logging (WAL)</li> <li>• JDBC channel: persistency implemented based on the embedded database</li> </ul> <p>Channels support the transaction feature to ensure simple sequential operations. A channel can work with sources and sinks of any quantity.</p> |
| Sink    | <p>Sink is responsible for sending data to the next hop or final destination and removing the data from the channel after successfully sending the data.</p> <p>Typical sinks include:</p> <ul style="list-style-type: none"> <li>• Sinks that send storage data to the final destination, such as HDFS and Kafka</li> <li>• Sinks that are consumed automatically, such as Null Sink</li> <li>• IPC sinks that are used for communication between agents, such as Avro</li> </ul> <p>A sink must associate with at least one channel.</p>                                                                                                                          |

A Flume client can have multiple sources, channels, and sinks. A source can send data to multiple channels, and then multiple sinks send the data out of the client.

Multiple Flume clients can be cascaded. That is, a sink can send data to the source of another client.

## Supplementary Information

1. Flume provides the following reliability measures:
  - The transaction mechanism is implemented between sources and channels, and between channels and sinks.
  - The sink processor supports the failover and load balancing (load\_balance) mechanisms.

The following is an example of the load balancing (load\_balance) configuration:

```
server.sinkgroups=g1
server.sinkgroups.g1.sinks=k1 k2
server.sinkgroups.g1.processor.type=load_balance
server.sinkgroups.g1.processor.backoff=true
server.sinkgroups.g1.processor.selector=random
```

2. The following are precautions for the aggregation and cascading of multiple Flume clients:

- Avro or Thrift protocol can be used for cascading.
  - When the aggregation end contains multiple nodes, evenly distribute the clients to these nodes. Do not connect all the clients to a single node.
3. The Flume client can contain multiple independent data flows. That is, multiple sources, channels, and sinks can be configured in the **properties.properties** configuration file. These components can be linked to form multiple flows.

For example, to configure two data flows in a configuration, run the following commands:

```
server.sources = source1 source2
server.sinks = sink1 sink2
server.channels = channel1 channel2

#dataflow1
server.sources.source1.channels = channel1
server.sinks.sink1.channel = channel1

#dataflow2
server.sources.source2.channels = channel2
server.sinks.sink2.channel = channel2
```

## 5.3 Installing the Flume Client on Clusters

### Scenario

To use Flume to collect logs, you must install the Flume client on a log host.

### Prerequisites

- A cluster with the Flume component has been created.
- The log host is in the same VPC and subnet with the MRS cluster. Log in to the node where the client is installed. For details, see [Using an MRS Client on Nodes Outside a MRS Cluster](#).
- You have obtained the username and password for logging in to the log host.
- The installation directory is automatically created if it does not exist. If it exists, the directory must be left blank. The directory path cannot contain any space.

### Procedure

**Step 1** Obtain the software package.

Log in to the FusionInsight Manager. Choose **Cluster** > *Name of the target cluster* > **Services** > **Flume**. On the Flume service page that is displayed, choose **More** > **Download Client** in the upper right corner and set **Select Client Type** to **Complete Client** to download the Flume service client file.

The file name of the client is **FusionInsight\_Cluster\_<Cluster ID>\_Flume\_Client.tar**. This section takes the client file **FusionInsight\_Cluster\_1\_Flume\_Client.tar** as an example.

**Step 2** Upload the software package.

Upload the software package to a directory, for example, **/opt/client** on the node where the Flume service client will be installed as user **user**.

 **NOTE**

**user** is the user who installs and runs the Flume client.

**Step 3** Decompress the software package.

Log in to the node where the Flume service client is to be installed as user **user**. Go to the directory where the installation package is installed, for example, **/opt/client**, and run the following command to decompress the installation package to the current directory:

```
cd /opt/client
```

```
tar -xvf FusionInsight_Cluster_1_Flume_Client.tar
```

**Step 4** Verify the software package.

Run the **sha256sum -c** command to verify the decompressed file. If **OK** is returned, the verification is successful. Example:

```
sha256sum -c FusionInsight_Cluster_1_Flume_ClientConfig.tar.sha256
```

```
FusionInsight_Cluster_1_Flume_ClientConfig.tar: OK
```

**Step 5** Decompress the package.

```
tar -xvf FusionInsight_Cluster_1_Flume_ClientConfig.tar
```

**Step 6** Check whether the number of clients is 1.

- If yes, use the independent installation mode and go to [Step 7](#). The installation is complete.
- If no, use the batch installation mode and go to [Step 8](#).

**Step 7** Run the following command in the Flume client installation directory to install the client to a specified directory (for example, **opt/FlumeClient**): After the client is installed successfully, the installation is complete.

```
cd /opt/client/FusionInsight_Cluster_1_Flume_ClientConfig/Flume/FlumeClient
```

```
./install.sh -d /opt/FlumeClient -f MonitorServerService IP address or host name  
of the role -c User service configuration filePath for storing properties.properties -s  
CPU threshold -l /var/log/Bigdata -e FlumeServer service IP address or host name  
-n Flume
```

 NOTE

- **-d**: Flume client installation path
- (Optional) **-f**: IP addresses or host names of two MonitorServer roles. The IP addresses or host names are separated by commas (.). If this parameter is not configured, the Flume client does not send alarm information to MonitorServer and information about the client cannot be viewed on the FusionInsight Manager GUI.
- (Optional) **-c**: Service configuration file, which needs to be generated by the user based on the service. For details about how to generate the file on the configuration tool page of the Flume server, see [Flume Service Configuration Guide](#). Upload the file to any directory on the node where the client is to be installed. If this parameter is not specified during the installation, you can upload the generated service configuration file **properties.properties** to the **/opt/FlumeClient/fusioninsight-flume-1.9.0/conf** directory after the installation.
- (Optional) **-s**: cgroup threshold. The value is an integer ranging from 1 to 100 x *N*. *N* indicates the number of CPU cores. The default threshold is **-1**, indicating that the processes added to the cgroup are not restricted by the CPU usage.
- (Optional) **-l**: Log path. The default value is **/var/log/Bigdata**. The user **user** must have the write permission on the directory. When the client is installed for the first time, a subdirectory named **flume-client** is generated. After the installation, subdirectories named **flume-client-*n*** will be generated in sequence. The letter *n* indicates a sequence number, which starts from 1 in ascending order. In the **/conf/** directory of the Flume client installation directory, modify the **ENV\_VARS** file and search for the **FLUME\_LOG\_DIR** attribute to view the client log path.
- (Optional) **-e**: Service IP address or host name of FlumeServer, which is used to receive statistics for the monitoring indicator reported by the client.
- (Optional) **-n**: Name of the Flume client. You can choose **Cluster > Name of the desired cluster > Service > Flume > Flume Management** on FusionInsight Manager to view the client name on the corresponding node.
- If the following error message is displayed, run the **export JAVA\_HOME=*JDK path*** command.  
JAVA\_HOME is null in current user,please install the JDK and set the JAVA\_HOME
- IBM JDK does not support **-Xloggc**. You must change **-Xloggc** to **-Xverboseglog** in **flume/conf/flume-env.sh**. For 32-bit JDK, the value of **-Xmx** must not exceed 3.25 GB.
- When installing a cross-platform client in a cluster, go to the **/opt/client/FusionInsight\_Cluster\_1\_Flume\_ClientConfig/Flume/FusionInsight-Flume-1.9.0.tar.gz** directory to install the Flume client.

**Step 8** Go to the directory for installing clients in batches.

```
cd /opt/client/FusionInsight_Cluster_1_Flume_ClientConfig/Flume/  
FlumeClient/batch_install
```

 NOTE

When installing a cross-platform client in a cluster, go to the **/opt/client/FusionInsight\_Cluster\_1\_Flume\_ClientConfig/Flume/FusionInsight-Flume-1.9.0.tar.gz** directory to install the Flume client.

**Step 9** Configure the **host\_info.cfg** file. The format of the configuration file is as follows:

```
host_ip="",user="",password="",install_path="",flume_config_file="",monitor_server  
_ip="",log_path="",flume_server_ip="",cgroup_threshold="",client_name=""
```

 NOTE

- (Mandatory) *host\_ip*: IP address of the node where the Flume client is to be installed.
- (Mandatory) *user*: User name for logging in to the node where the Flume client is to be installed remotely.
- (Mandatory) *password*: Password for logging in to the Flume client to be installed remotely.
- (Mandatory) **install\_path**: Installation path of the Flume client.
- (Optional) **flume\_config\_file**: Configuration file for Flume running. You are advised to specify this configuration file during Flume installation. If you do not set this parameter, retain the value "" and do not delete the parameter.
- (Optional) **monitor\_server\_ip**: Service IP address of the Flume MonitorServer in the cluster. You can check the IP address on FusionInsight Manager. You can select either of the two IP addresses. If the IP address is not configured, the client does not send alarm information to the cluster in the scenario where a process is faulty.
- (Optional) **log\_path**: Path for storing Flume run logs. If this parameter is not set, logs are recorded in `/var/log/Bigdata/flume-client-Index` by default. Index value: If there is only one client in this path, the value is 1. If there are multiple clients, the index value is incremented by 1.
- (Optional) **flume\_server\_ip**: Service IP address of the Flume server. The indicator information of the client is reported to the cluster from this node. The indicator information about the client can be displayed on the web client. If the indicator information is not configured, the client does not display the indicator information.
- (Optional) **cgroup\_threshold**: cgroup threshold. The value is an integer ranging from 1 to  $100 \times N$ . *N* indicates the number of CPU cores. The default threshold is **-1**, indicating that the processes added to the cgroup are not restricted by the CPU usage.
- (Optional) **client\_name**: Client name. The client name is displayed on the client monitoring page. If the client name is not configured, the client name is empty.

**Step 10** Run the following command to install the Flume client in batches.

```
./batch_install.sh -p /opt/client/FusionInsight_Cluster_1_Flume_Client.tar
```

**Step 11** Delete the password information from the **host\_info.cfg** file.

After the batch installation is complete, delete the password information from the **host\_info.cfg** file immediately. Otherwise, the password may be disclosed.

----End

## 5.4 Viewing Flume Client Logs

### Scenario

You can view logs to locate faults.

### Prerequisites

The Flume client has been installed.

### Procedure

**Step 1** Go to the Flume client log directory (`/var/log/Bigdata` by default).

**Step 2** Run the following command to view the log file:

```
ls -lR flume-client-*
```

A log file is shown as follows:

```
flume-client-1/flume:
total 7672
-rw-----, 1 root root    0 Sep  8 19:43 Flume-audit.log
-rw-----, 1 root root 1562037 Sep 11 06:05 FlumeClient.2017-09-11_04-05-09.[1].log.zip
-rw-----, 1 root root 6127274 Sep 11 14:47 FlumeClient.log
-rw-----, 1 root root   2935 Sep  8 22:20 flume-root-20170908202009-pid72456-gc.log.0.current
-rw-----, 1 root root   2935 Sep  8 22:27 flume-root-20170908202634-pid78789-gc.log.0.current
-rw-----, 1 root root   4382 Sep  8 22:47 flume-root-20170908203137-pid84925-gc.log.0.current
-rw-----, 1 root root   4390 Sep  8 23:46 flume-root-20170908204918-pid103920-gc.log.0.current
-rw-----, 1 root root   3196 Sep  9 10:12 flume-root-20170908215351-pid44372-gc.log.0.current
-rw-----, 1 root root   2935 Sep  9 10:13 flume-root-20170909101233-pid55119-gc.log.0.current
-rw-----, 1 root root   6441 Sep  9 11:10 flume-root-20170909101631-pid59301-gc.log.0.current
-rw-----, 1 root root    0 Sep  9 11:10 flume-root-20170909111009-pid119477-gc.log.0.current
-rw-----, 1 root root  92896 Sep 11 13:24 flume-root-20170909111126-pid120689-gc.log.0.current
-rw-----, 1 root root   5588 Sep 11 14:46 flume-root-20170911132445-pid42259-gc.log.0.current
-rw-----, 1 root root   2576 Sep 11 13:24 prestartDetail.log
-rw-----, 1 root root   3303 Sep 11 13:24 startDetail.log
-rw-----, 1 root root   1253 Sep 11 13:24 stopDetail.log

flume-client-1/monitor:
total 8
-rw-----, 1 root root  141 Sep  8 19:43 flumeMonitorChecker.log
-rw-----, 1 root root  2946 Sep 11 13:24 flumeMonitor.log
```

In the log file, **FlumeClient.log** is the run log of the Flume client.

----End

## 5.5 Stopping or Uninstalling the Flume Client

### Scenario

You can stop and start the Flume client or uninstall the Flume client when the Flume data ingestion channel is not required.

### Procedure

- Stop the Flume client of the Flume role.  
Assume that the Flume client installation path is **/opt/FlumeClient**. Run the following command to stop the Flume client:

```
cd /opt/FlumeClient/fusioninsight-flume-Flume component version
number/bin
```

```
./flume-manage.sh stop
```

If the following information is displayed after the command execution, the Flume client is successfully stopped.

```
Stop Flume PID=120689 successful..
```

 NOTE

The Flume client will be automatically restarted after being stopped. If you do not need automatic restart, run the following command:

```
./flume-manage.sh stop force
```

If you want to restart the Flume client, run the following command:

```
./flume-manage.sh start force
```

- Uninstall the Flume client of the Flume role.

Assume that the Flume client installation path is **/opt/FlumeClient**. Run the following command to uninstall the Flume client:

```
cd /opt/FlumeClient/fusioninsight-flume-Flume component version  
number/inst  
./uninstall.sh
```

## 5.6 Using the Encryption Tool of the Flume Client

### Scenario

You can use the encryption tool provided by the Flume client to encrypt some parameter values in the configuration file.

### Prerequisites

The Flume client has been installed.

### Procedure

**Step 1** Log in to the Flume client node and go to the client installation directory, for example, **/opt/FlumeClient**.

**Step 2** Run the following command to switch the directory:

```
cd fusioninsight-flume-Flume component version number/bin
```

**Step 3** Run the following command to encrypt information:

```
./genPwFile.sh
```

Input the information that you want to encrypt twice.

**Step 4** Run the following command to query the encrypted information:

```
cat password.property
```

 NOTE

If the encryption parameter is used for the Flume server, you need to perform encryption on the corresponding Flume server node. You need to run the encryption script as user **omm** for encryption.

----End

## 5.7 Flume Service Configuration Guide

This configuration guide describes how to configure common Flume services. For non-common Source, Channel, and Sink configuration, see the user manual provided by the Flume community. You can obtain the user manual at <http://flume.apache.org/releases/1.9.0.html>.

### NOTE

- Parameters in bold in the following tables are mandatory.
- The value of **BatchSize** of the Sink must be less than that of **transactionCapacity** of the Channel.
- Only some parameters of Source, Channel, and Sink are displayed on the Flume configuration tool page. For details, see the following configurations.
- The Customer Source, Customer Channel, and Customer Sink displayed on the Flume configuration tool page need to be configured based on self-developed code. The following common configurations are not displayed.

### Common Source Configurations

- **Avro Source**

An Avro source listens to the Avro port, receives data from the external Avro client, and places data into configured channels. Common configurations are as follows:

**Table 5-2** Common configurations of an Avro source

| Parameter | Default Value | Description                                                                         |
|-----------|---------------|-------------------------------------------------------------------------------------|
| channels  | -             | Specifies the channel connected to the source. Multiple channels can be configured. |
| type      | avro          | Specifies the type of the avro source, which must be <b>avro</b> .                  |
| bind      | -             | Specifies the listening host name/IP address.                                       |
| port      | -             | Specifies the bound listening port. Ensure that this port is not occupied.          |
| threads   | -             | Specifies the maximum number of source threads.                                     |

| Parameter           | Default Value | Description                                                                                                                                                                                                                                                                                |
|---------------------|---------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| compression-type    | none          | Specifies the message compression format, which can be set to <b>none</b> or <b>deflate</b> . <b>none</b> indicates that data is not compressed, while <b>deflate</b> indicates that data is compressed.                                                                                   |
| compression-level   | 6             | Specifies the data compression level, which ranges from <b>1</b> to <b>9</b> . The larger the value is, the higher the compression rate is.                                                                                                                                                |
| ssl                 | false         | Specifies whether to use SSL encryption. If this parameter is set to <b>true</b> , the values of <b>keystore</b> and <b>keystore-password</b> must be specified.                                                                                                                           |
| truststore-type     | JKS           | Specifies the Java trust store type, which can be set to <b>JKS</b> or <b>PKCS12</b> .<br><b>NOTE</b><br>Different passwords are used to protect the key store and private key of <b>JKS</b> , while the same password is used to protect the key store and private key of <b>PKCS12</b> . |
| truststore          | -             | Specifies the Java trust store file.                                                                                                                                                                                                                                                       |
| truststore-password | -             | Specifies the Java trust store password.                                                                                                                                                                                                                                                   |

| Parameter         | Default Value | Description                                                                                                                                                                                                                                                                                                 |
|-------------------|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| keystore-type     | JKS           | Specifies the keystore type set after SSL is enabled, which can be set to <b>JKS</b> or <b>PKCS12</b> .<br><b>NOTE</b><br>Different passwords are used to protect the key store and private key of <b>JKS</b> , while the same password is used to protect the key store and private key of <b>PKCS12</b> . |
| keystore          | -             | Specifies the keystore file path set after SSL is enabled. This parameter is mandatory if SSL is enabled.                                                                                                                                                                                                   |
| keystore-password | -             | Specifies the keystore password set after SSL is enabled. This parameter is mandatory if SSL is enabled.                                                                                                                                                                                                    |
| trust-all-certs   | false         | Specifies whether to disable the check for the SSL server certificate. If this parameter is set to <b>true</b> , the SSL server certificate of the remote source is not checked. You are not advised to perform this operation during the production.                                                       |
| exclude-protocols | SSLv3         | Specifies the excluded protocols. The entered protocols must be separated by spaces. The default value is <b>SSLv3</b> .                                                                                                                                                                                    |
| ipFilter          | false         | Specifies whether to enable the IP address filtering.                                                                                                                                                                                                                                                       |

| Parameter      | Default Value | Description                                                                                                                                                                                                                                                                                                                             |
|----------------|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ipFilter.rules | -             | Specifies the rules of <i>N</i> network <b>ipFilters</b> . Host names or IP addresses must be separated by commas (.). If this parameter is set to <b>true</b> , there are two configuration rules: allow and forbidden. The configuration format is as follows:<br>ipFilterRules=allow:ip:127.*,<br>allow:name:localhost,<br>deny:ip:* |

- **SpoolDir Source**

SpoolDir Source monitors and transmits new files that have been added to directories in real-time mode. Common configurations are as follows:

**Table 5-3** Common configurations of a Spooling Directory source

| Parameter  | Default Value       | Description                                                                                                                                            |
|------------|---------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------|
| channels   | -                   | Specifies the channel connected to the source. Multiple channels can be configured.                                                                    |
| type       | spooldir            | Specifies the type of the spooling source, which must be set to <b>spooldir</b> .                                                                      |
| spoolDir   | -                   | Specifies the monitoring directory of the Spooldir source. A Flume running user must have the read, write, and execution permissions on the directory. |
| monTime    | 0<br>(Disabled<br>) | Specifies the thread monitoring threshold. When the update time exceeds the threshold, the source is restarted. Unit: second                           |
| fileSuffix | .COMPLETED          | Specifies the suffix added after file transmission is complete.                                                                                        |

| Parameter                  | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                                                               |
|----------------------------|---------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| deletePolicy               | never         | Specifies the source file deletion policy after file transmission is complete. The value can be either <b>never</b> or <b>immediate</b> . <b>never</b> indicates that the source file is not deleted after file transmission is complete, while <b>immediate</b> indicates that the source file is immediately deleted after file transmission is complete.                                                               |
| ignorePattern              | ^\$           | Specifies the regular expression of a file to be ignored. The default value is ^\$, indicating that spaces are ignored.                                                                                                                                                                                                                                                                                                   |
| includePattern             | ^\.*\$        | Specifies the regular expression that contains a file. This parameter can be used together with <b>ignorePattern</b> . If a file meets both <b>ignorePattern</b> and <b>includePattern</b> , the file is ignored. In addition, when a file starts with a period (.), the file will not be filtered.                                                                                                                       |
| trackerDir                 | .flumespool   | Specifies the metadata storage path during data transmission.                                                                                                                                                                                                                                                                                                                                                             |
| batchSize                  | 1000          | Specifies the number of events written to the channel in batches.                                                                                                                                                                                                                                                                                                                                                         |
| decodeErrorPolicy          | FAIL          | Specifies the code error policy.<br><b>NOTE</b><br>If a code error occurs in the file, set <b>decodeErrorPolicy</b> to <b>REPLACE</b> or <b>IGNORE</b> . Flume will skip the code error and continue to collect subsequent logs.                                                                                                                                                                                          |
| deserializer               | LINE          | Specifies the file parser. The value can be either <b>LINE</b> or <b>BufferedLine</b> . <ul style="list-style-type: none"> <li>When the value is set to <b>LINE</b>, characters read from the file are transcoded one by one.</li> <li>When the value is set to <b>BufferedLine</b>, one line or multiple lines of characters read from the file are transcoded in batches, which delivers better performance.</li> </ul> |
| deserializer.maxLineLength | 2048          | Specifies the maximum length for resolution by line.                                                                                                                                                                                                                                                                                                                                                                      |

| Parameter                 | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------------|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| deserializer.maxBatchLine | 1             | Specifies the maximum number of lines for resolution by line. If multiple lines are set, <b>maxLineLength</b> must be set to a corresponding multiplier.<br><b>NOTE</b><br>When configuring the Interceptor, take the multi-line combination into consideration to avoid data loss. If the Interceptor cannot process combined lines, set this parameter to 1.                                            |
| selector.type             | replicating   | Specifies the selector type. The value can be either <b>replicating</b> or <b>multiplexing</b> . <b>replicating</b> indicates that data is replicated and then transferred to each channel so that each channel receives the same data, while <b>multiplexing</b> indicates that a channel is selected based on the value of the header in the event and each channel has different data.                 |
| interceptors              | -             | Specifies the interceptor. Multiple interceptors are separated by spaces.                                                                                                                                                                                                                                                                                                                                 |
| inputCharset              | UTF-8         | Specifies the encoding format of a read file. The encoding format must be the same as that of the data source file that has been read. Otherwise, an error may occur during character parsing.                                                                                                                                                                                                            |
| fileHeader                | false         | Specifies whether to add the file name (including the file path) to the event header.                                                                                                                                                                                                                                                                                                                     |
| fileHeaderKey             | -             | Specifies that the data storage structure in header is set in the <key,value> mode. Parameters <b>fileHeaderKey</b> and <b>fileHeader</b> must be used together. Following is an example if <b>fileHeader</b> is set to true:<br>Define <b>fileHeaderKey</b> as <b>file</b> . When the / <b>root/a.txt</b> file is read, <b>fileHeaderKey</b> exists in the header in the <b>file=/root/a.txt</b> format. |
| basenameHeader            | false         | Specifies whether to add the file name (excluding the file path) to the event header.                                                                                                                                                                                                                                                                                                                     |

| Parameter                | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|--------------------------|---------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| basenameHeaderKey        | -             | Specifies that the data storage structure in header is set in the <key,value> mode. Parameters <b>basenameHeaderKey</b> and <b>basenameHeader</b> must be used together. Following is an example if <b>basenameHeader</b> is set to true:<br><br>Define <b>basenameHeaderKey</b> as <b>file</b> . When the <b>a.txt</b> file is read, <b>basenameHeaderKey</b> exists in the header in the <b>file=a.txt</b> format.                                                                                                                                                                                                                                                                             |
| pollDelay                | 500           | Specifies the delay for polling new files in the monitoring directory. Unit: milliseconds                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| recursiveDirectorySearch | false         | Specifies whether to monitor new files in the subdirectory of the configured directory.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| consumeOrder             | oldest        | Specifies the consumption order of files in a directory. If this parameter is set to <b>oldest</b> or <b>youngest</b> , the sequence of files to be read is determined by the last modification time of files in the monitored directory. If there are a large number of files in the directory, it takes a long time to search for <b>oldest</b> or <b>youngest</b> files. If this parameter is set to <b>random</b> , an earlier created file may not be read for a long time. If this parameter is set to <b>oldest</b> or <b>youngest</b> , it takes a long time to find the latest and the earliest file. The options are as follows: <b>random</b> , <b>youngest</b> , and <b>oldest</b> . |
| maxBackoff               | 4000          | Specifies the maximum time to wait between consecutive attempts to write to a channel if the channel is full. If the time exceeds the threshold, an exception is thrown. The corresponding source starts to write at a smaller time value. Each time the source attempts, the digital exponent increases until the current specified value is reached. If data cannot be written, the data write fails. Unit: second                                                                                                                                                                                                                                                                             |
| emptyFileEvent           | true          | Specifies whether to collect empty file information and send it to the sink end. The default value is <b>true</b> , indicating that empty file information is sent to the sink end. This parameter is valid only for HDFS Sink. Taking HDFS Sink as an example, if this parameter is set to <b>true</b> and an empty file exists in the <b>spoolDir</b> directory, an empty file with the same name will be created in the <b>hdfs.path</b> directory of HDFS.                                                                                                                                                                                                                                   |

 NOTE

SpoolDir Source ignores the last line feed character of each event when data is reading by row. Therefore, Flume does not calculate the data volume counters used by the last line feed character.

- **Kafka Source**

A Kafka source consumes data from Kafka topics. Multiple sources can consume data of the same topic, and the sources consume different partitions of the topic. Common configurations are as follows:

**Table 5-4** Common configurations of a Kafka source

| Parameter               | Default Value                             | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|-------------------------|-------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| channels                | -                                         | Specifies the channel connected to the source. Multiple channels can be configured.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| type                    | org.apache.flume.source.kafka.KafkaSource | Specifies the type of the Kafka source, which must be set to <b>org.apache.flume.source.kafka.KafkaSource</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
| kafka.bootstrap.servers | -                                         | Specifies the bootstrap address port list of Kafka. If Kafka has been installed in the cluster and the configuration has been synchronized to the server, you do not need to set this parameter on the server. The default value is the list of all brokers in the Kafka cluster. This parameter must be configured on the client. Use commas (,) to separate multiple values of <i>IP address:Port number</i> . The rules for matching ports and security protocols must be as follows: port 21007 matches the security mode (SASL_PLAINTEXT), and port 9092 matches the common mode (PLAINTEXT). |
| kafka.topics            | -                                         | Specifies the list of subscribed Kafka topics, which are separated by commas (,).                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| kafka.topics.regex      | -                                         | Specifies the subscribed topics that comply with regular expressions. <b>kafka.topics.regex</b> has a higher priority than <b>kafka.topics</b> and will overwrite <b>kafka.topics</b> .                                                                                                                                                                                                                                                                                                                                                                                                            |

| Parameter            | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                               |
|----------------------|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| monTime              | 0 (Disabled)  | Specifies the thread monitoring threshold. When the update time exceeds the threshold, the source is restarted. Unit: second                                                                                                                                                                                                                                                              |
| nodatotime           | 0 (Disabled)  | Specifies the alarm threshold. An alarm is triggered when the duration that Kafka does not release data to subscribers exceeds the threshold. Unit: second This parameter can be configured in the <b>properties.properties</b> file.                                                                                                                                                     |
| batchSize            | 1000          | Specifies the number of events written to the channel in batches.                                                                                                                                                                                                                                                                                                                         |
| batchDuration Millis | 1000          | Specifies the maximum duration of topic data consumption at a time, expressed in milliseconds.                                                                                                                                                                                                                                                                                            |
| keepTopicInHeader    | false         | Specifies whether to save topics in the event header. If the parameter value is <b>true</b> , topics configured in Kafka Sink become invalid.                                                                                                                                                                                                                                             |
| setTopicHeader       | true          | If this parameter is set to <b>true</b> , the topic name defined in <b>topicHeader</b> is stored in the header.                                                                                                                                                                                                                                                                           |
| topicHeader          | topic         | When <b>setTopicHeader</b> is set to <b>true</b> , this parameter specifies the name of the topic received by the storage device. If the property is used with that of Kafka Sink <b>topicHeader</b> , be careful not to send messages to the same topic cyclically.                                                                                                                      |
| useFlumeEventFormat  | false         | By default, an event is transferred from a Kafka topic to the body of the event in the form of bytes. If this parameter is set to <b>true</b> , the Avro binary format of Flume is used to read events. When used together with the <b>parseAsFlumeEvent</b> parameter with the same name in KafkaSink or KakfaChannel, any set <b>header</b> generated from the data source is retained. |

| Parameter                       | Default Value  | Description                                                                                                                                                                                                                                                                                |
|---------------------------------|----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| keepPartitionInHeader           | false          | Specifies whether to save partition IDs in the event header. If the parameter value is <b>true</b> , Kafka Sink writes data to the corresponding partition.                                                                                                                                |
| kafka.consumer.group.id         | flume          | Specifies the Kafka consumer group ID. Sources or proxies having the same ID are in the same consumer group.                                                                                                                                                                               |
| kafka.security.protocol         | SASL_PLAINTEXT | Specifies the Kafka security protocol. The parameter value must be set to PLAINTEXT in a common cluster. The rules for matching ports and security protocols must be as follows: port 21007 matches the security mode (SASL_PLAINTEXT), and port 9092 matches the common mode (PLAINTEXT). |
| Other Kafka Consumer Properties | -              | Specifies other Kafka configurations. This parameter can be set to any consumption configuration supported by Kafka, and the <b>.kafka</b> prefix must be added to the configuration.                                                                                                      |

- **Taildir Source**

A Taildir source monitors file changes in a directory and automatically reads the file content. In addition, it can transmit data in real time. Common configurations are as follows:

**Table 5-5** Common configurations of a Taildir source

| Parameter  | Default Value | Description                                                                                   |
|------------|---------------|-----------------------------------------------------------------------------------------------|
| channels   | -             | Specifies the channel connected to the source. Multiple channels can be configured.           |
| type       | TAILDIR       | Specifies the type of the taildir source, which must be set to TAILDIR.                       |
| filegroups | -             | Specifies the group name of a collection file directory. Group names are separated by spaces. |

| Parameter                              | Default Value  | Description                                                                                                                                                                                                                                                                                                                                                                              |
|----------------------------------------|----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| filegroups.<filegroupName>.parentDir   | -              | Specifies the parent directory. The value must be an absolute path.                                                                                                                                                                                                                                                                                                                      |
| filegroups.<filegroupName>.filePattern | -              | Specifies the relative file path of the file group's parent directory. Directories can be included and regular expressions are supported. It must be used together with <b>parentDir</b> .                                                                                                                                                                                               |
| positionFile                           | -              | Specifies the metadata storage path during data transmission.                                                                                                                                                                                                                                                                                                                            |
| headers.<filegroupName>.<headerKey>    | -              | Specifies the key-value of an event when data of a group is being collected.                                                                                                                                                                                                                                                                                                             |
| byteOffsetHeader                       | false          | Specifies whether each event header contains the event location information in the source file. If the parameter value is true, the location information is saved in the byteoffset variable.                                                                                                                                                                                            |
| maxBatchCount                          | Long.MAX_VALUE | Specifies the maximum number of batches that can be consecutively read from a file. If the monitored directory reads multiple files consecutively and one of the files is written at a rapid rate, other files may fail to be processed. This is because the file that is written at a high speed will be in an infinite read loop. In this case, set this parameter to a smaller value. |
| skipToEnd                              | false          | Specifies whether Flume can locate the latest location of a file and read the latest data after restart. If the parameter value is true, Flume locates and reads the latest file data after restart.                                                                                                                                                                                     |
| idleTimeout                            | 120000         | Specifies the idle duration during file reading, expressed in milliseconds. If file content is not changed in the preset time duration, close the file. If data is written to this file after the file is closed, open the file and read data.                                                                                                                                           |
| writePosInterval                       | 3000           | Specifies the interval for writing metadata to a file, expressed in milliseconds.                                                                                                                                                                                                                                                                                                        |

| Parameter     | Default Value    | Description                                                                                                                                                                                                                                                                                                                                                                                                  |
|---------------|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| batchSize     | 1000             | Specifies the number of events written to the channel in batches.                                                                                                                                                                                                                                                                                                                                            |
| monTime       | 0<br>(Disabled ) | Specifies the thread monitoring threshold. When the update time exceeds the threshold, the source is restarted. Unit: second                                                                                                                                                                                                                                                                                 |
| fileHeader    | false            | Specifies whether to add the file name (including the file path) to the event header.                                                                                                                                                                                                                                                                                                                        |
| fileHeaderKey | file             | Specifies that the data storage structure in header is set in the <key,value> mode. Parameters <b>fileHeaderKey</b> and <b>fileHeader</b> must be used together. Following is an example if <b>fileHeader</b> is set to true:<br><br>Define <b>fileHeaderKey</b> as <b>file</b> . When the <b>/root/a.txt</b> file is read, <b>fileHeaderKey</b> exists in the header in the <b>file=/root/a.txt</b> format. |

- **Http Source**

An HTTP source receives data from an external HTTP client and sends the data to the configured channels. Common configurations are as follows:

**Table 5-6** Common configurations of an HTTP source

| Parameter | Default Value | Description                                                                         |
|-----------|---------------|-------------------------------------------------------------------------------------|
| channels  | -             | Specifies the channel connected to the source. Multiple channels can be configured. |
| type      | http          | Specifies the type of the http source, which must be set to http.                   |
| bind      | -             | Specifies the listening host name/IP address.                                       |
| port      | -             | Specifies the bound listening port. Ensure that this port is not occupied.          |

| Parameter             | Default Value                            | Description                                                                                                                                                                                      |
|-----------------------|------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| handler               | org.apache.flume.source.http.JSONHandler | Specifies the message parsing method of an HTTP request. Two formats are supported: JSON (org.apache.flume.source.http.JSONHandler) and BLOB (org.apache.flume.sink.solr.morphline.BlobHandler). |
| handler.*             | -                                        | Specifies handler parameters.                                                                                                                                                                    |
| exclude-protocols     | SSLv3                                    | Specifies the excluded protocols. The entered protocols must be separated by spaces. The default value is <b>SSLv3</b> .                                                                         |
| include-cipher-suites | -                                        | Specifies the included protocols. The entered protocols must be separated by spaces. If this parameter is left empty, all protocols are supported by default.                                    |
| enableSSL             | false                                    | Specifies whether SSL is enabled in HTTP. If this parameter is set to <b>true</b> , the values of <b>keystore</b> and <b>keystore-password</b> must be specified.                                |
| keystore-type         | JKS                                      | Specifies the keystore type, which can be <b>JKS</b> or <b>PKCS12</b> .                                                                                                                          |
| keystore              | -                                        | Specifies the keystore path set after SSL is enabled in HTTP.                                                                                                                                    |
| keystorePassword      | -                                        | Specifies the keystore password set after SSL is enabled in HTTP.                                                                                                                                |

- **Thrift Source**

Thrift Source monitors the thrift port, receives data from the external Thrift clients, and puts the data into the configured channel. Common configurations are as follows:

| Parameter | Default Value | Description                                                                         |
|-----------|---------------|-------------------------------------------------------------------------------------|
| channels  | -             | Specifies the channel connected to the source. Multiple channels can be configured. |
| type      | thrift        | Specifies the type of the thrift source, which must be set to <b>thrift</b> .       |
| bind      | -             | Specifies the listening host name/IP address.                                       |

| Parameter         | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-------------------|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| port              | -             | Specifies the bound listening port. Ensure that this port is not occupied.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| threads           | -             | Specifies the maximum number of worker threads that can be run.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| kerberos          | false         | Specifies whether Kerberos authentication is enabled.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| agent-keytab      | -             | Specifies the address of the keytab file used by the server. The machine-machine account must be used. You are advised to use <b>flume/conf/flume_server.keytab</b> in the Flume service installation directory.                                                                                                                                                                                                                                                                                                                                                                                                                        |
| agent-principal   | -             | Specifies the principal of the security user used by the server. The principal must be a machine-machine account. You are advised to use the default user of Flume: <code>flume_server/hadoop.&lt;system domain name&gt;@&lt;system domain name&gt;</code><br><b>NOTE</b><br><code>flume_server/hadoop.&lt;system domain name&gt;</code> is the username. All letters in the system domain name contained in the username are lowercase letters. For example, <b>Local Domain</b> is set to <b>9427068F-6EFA-4833-B43E-60CB641E5B6C.COM</b> , and the username is <b>flume_server/hadoop.9427068f-6efa-4833-b43e-60cb641e5b6c.com</b> . |
| compression-type  | none          | Specifies the message compression format, which can be set to <b>none</b> or <b>deflate</b> . <b>none</b> indicates that data is not compressed, while <b>deflate</b> indicates that data is compressed.                                                                                                                                                                                                                                                                                                                                                                                                                                |
| ssl               | false         | Specifies whether to use SSL encryption. If this parameter is set to <b>true</b> , the values of <b>keystore</b> and <b>keystore-password</b> must be specified.                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
| keystore-type     | JKS           | Specifies the keystore type set after SSL is enabled.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| keystore          | -             | Specifies the keystore file path set after SSL is enabled. This parameter is mandatory if SSL is enabled.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| keystore-password | -             | Specifies the keystore password set after SSL is enabled. This parameter is mandatory if SSL is enabled.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |

## Common Channel Configurations

- **Memory Channel**

A memory channel uses memory as the cache. Events are stored in memory queues. Common configurations are as follows:

**Table 5-7** Common configurations of a memory channel

| Parameter           | Default Value                 | Description                                                                                                                                                                                                                                                                                                            |
|---------------------|-------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| type                | -                             | Specifies the type of the memory channel, which must be set to <b>memory</b> .                                                                                                                                                                                                                                         |
| capacity            | 10000                         | Specifies the maximum number of events cached in a channel.                                                                                                                                                                                                                                                            |
| transactionCapacity | 1000                          | Specifies the maximum number of events accessed each time.<br><b>NOTE</b> <ul style="list-style-type: none"> <li>• The parameter value must be greater than the batchSize of the source and sink.</li> <li>• The value of <b>transactionCapacity</b> must be less than or equal to that of <b>capacity</b>.</li> </ul> |
| channelFullcount    | 10                            | Specifies the channel full count. When the count reaches the threshold, an alarm is reported.                                                                                                                                                                                                                          |
| keep-alive          | 3                             | Specifies the waiting time of the Put and Take threads when the transaction or channel cache is full. Unit: second                                                                                                                                                                                                     |
| byteCapacity        | 80% of the maximum JVM memory | Specifies the total bytes of all event bodies in a channel. The default value is the 80% of the maximum JVM memory (indicated by <b>-Xmx</b> ). Unit: bytes                                                                                                                                                            |

| Parameter                    | Default Value | Description                                         |
|------------------------------|---------------|-----------------------------------------------------|
| byteCapacityBufferPercentage | 20            | Specifies the percentage of bytes in a channel (%). |

- **File Channel**

A file channel uses local disks as the cache. Events are stored in the folder specified by **dataDirs**. Common configurations are as follows:

**Table 5-8** Common configurations of a file channel

| Parameter            | Default Value                                                                                                                   | Description                                                                                                                                     |
|----------------------|---------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
| type                 | -                                                                                                                               | Specifies the type of the file channel, which must be set to <b>file</b> .                                                                      |
| checkpointDir        | \${BIGDATA_DATA_HOME}/<br>hadoop/data1~N/flume/<br>checkpoint<br><b>NOTE</b><br>This path is changed with the custom data path. | Specifies the checkpoint storage directory.                                                                                                     |
| dataDirs             | \${BIGDATA_DATA_HOME}/<br>hadoop/data1~N/flume/data<br><b>NOTE</b><br>This path is changed with the custom data path.           | Specifies the data cache directory. Multiple directories can be configured to improve performance. The directories are separated by commas (,). |
| maxFileSize          | 2146435071                                                                                                                      | Specifies the maximum size of a single cache file, expressed in bytes.                                                                          |
| minimumRequiredSpace | 524288000                                                                                                                       | Specifies the minimum idle space in the cache, expressed in bytes.                                                                              |
| capacity             | 1000000                                                                                                                         | Specifies the maximum number of events cached in a channel.                                                                                     |

| Parameter           | Default Value | Description                                                                                                                                                                                                                                                                                                        |
|---------------------|---------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| transactionCapacity | 10000         | Specifies the maximum number of events accessed each time.<br><b>NOTE</b> <ul style="list-style-type: none"> <li>The parameter value must be greater than the batchSize of the source and sink.</li> <li>The value of <b>transactionCapacity</b> must be less than or equal to that of <b>capacity</b>.</li> </ul> |
| channelFullCount    | 10            | Specifies the channel full count. When the count reaches the threshold, an alarm is reported.                                                                                                                                                                                                                      |
| useDualCheckpoints  | false         | Specifies the backup checkpoint. If this parameter is set to <b>true</b> , the <b>backupCheckpointDir</b> parameter value must be set.                                                                                                                                                                             |
| backupCheckpointDir | -             | Specifies the path of the backup checkpoint.                                                                                                                                                                                                                                                                       |
| checkpointInterval  | 30000         | Specifies the check interval, expressed in seconds.                                                                                                                                                                                                                                                                |
| keep-alive          | 3             | Specifies the waiting time of the Put and Take threads when the transaction or channel cache is full. Unit: second                                                                                                                                                                                                 |
| use-log-replay-v1   | false         | Specifies whether to enable the old reply logic.                                                                                                                                                                                                                                                                   |
| use-fast-replay     | false         | Specifies whether to enable the queue reply.                                                                                                                                                                                                                                                                       |
| checkpointOnClose   | true          | Specifies that whether a checkpoint is created when a channel is disabled.                                                                                                                                                                                                                                         |

- **Memory File Channel**

A memory file channel uses both memory and local disks as its cache and supports message persistence. It provides similar performance as a memory channel and better performance than a file channel. This channel is currently experimental and not recommended for use in production. The following table describes common configuration items: Common configurations are as follows:

**Table 5-9** Common configurations of a memory file channel

| Parameter           | Default Value                              | Description                                                                                                                                                                                                                                                                                                                    |
|---------------------|--------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| type                | org.apache.flume.channel.MemoryFileChannel | Specifies the type of the memory file channel, which must be set to <b>org.apache.flume.channel.MemoryFileChannel</b> .                                                                                                                                                                                                        |
| capacity            | 50000                                      | Specifies the maximum number of events cached in a channel.                                                                                                                                                                                                                                                                    |
| transactionCapacity | 5000                                       | Specifies the maximum number of events processed by a transaction.<br><b>NOTE</b> <ul style="list-style-type: none"> <li>• The parameter value must be greater than the batchSize of the source and sink.</li> <li>• The value of <b>transactionCapacity</b> must be less than or equal to that of <b>capacity</b>.</li> </ul> |

| Parameter            | Default Value                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----------------------|-------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| subqueueByteCapacity | 20971520                      | <p>Specifies the maximum size of events that can be stored in a subqueue, expressed in bytes.</p> <p>A memory file channel uses both queues and subqueues to cache data. Events are stored in a subqueue, and subqueues are stored in a queue.</p> <p><b>subqueueCapacity</b> and <b>subqueueInterval</b> determine the size of events that can be stored in a subqueue. <b>subqueueCapacity</b> specifies the capacity of a subqueue, and <b>subqueueInterval</b> specifies the duration that a subqueue can store events. Events in a subqueue are sent to the destination only after the subqueue reaches the upper limit of <b>subqueueCapacity</b> or <b>subqueueInterval</b>.</p> <p><b>NOTE</b><br/>The value of <b>subqueueByteCapacity</b> must be greater than the number of events specified by <b>batchSize</b>.</p> |
| subqueueInterval     | 2000                          | Specifies the maximum duration that a subqueue can store events, expressed in milliseconds.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| keep-alive           | 3                             | <p>Specifies the waiting time of the Put and Take threads when the transaction or channel cache is full.</p> <p>Unit: second</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
| dataDir              | -                             | Specifies the cache directory for local files.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   |
| byteCapacity         | 80% of the maximum JVM memory | Specifies the channel cache capacity.<br>Unit: bytes                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| compression-type     | None                          | Specifies the message compression format, which can be set to <b>none</b> or <b>deflate</b> . <b>none</b> indicates that data is not compressed, while <b>deflate</b> indicates that data is compressed.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
| channelFullCount     | 10                            | Specifies the channel full count. When the count reaches the threshold, an alarm is reported.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |

The following is a configuration example of a memory file channel:

```
server.channels.c1.type = org.apache.flume.channel.MemoryFileChannel
server.channels.c1.dataDir = /opt/flume/mfdata
server.channels.c1.subqueueByteCapacity = 20971520
server.channels.c1.subqueueInterval=2000
server.channels.c1.capacity = 500000
server.channels.c1.transactionCapacity = 40000
```

- **Kafka Channel**

A Kafka channel uses a Kafka cluster as the cache. Kafka provides high availability and multiple copies to prevent data from being immediately consumed by sinks when Flume or Kafka Broker crashes.

**Table 5-10** Common configurations of a Kafka channel

| Parameter               | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|-------------------------|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| type                    | -             | Specifies the type of the Kafka channel, which must be set to <b>org.apache.flume.channel.kafka.KafkaChannel</b> .                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| kafka.bootstrap.servers | -             | Specifies the bootstrap address port list of Kafka.<br><br>If Kafka has been installed in the cluster and the configuration has been synchronized to the server, you do not need to set this parameter on the server. The default value is the list of all brokers in the Kafka cluster. This parameter must be configured on the client. Use commas (,) to separate multiple values of <i>IP address:Port number</i> .<br><br>The rules for matching ports and security protocols must be as follows: port 21007 matches the security mode (SASL_PLAINTEXT), and port 9092 matches the common mode (PLAINTEXT). |

| Parameter                        | Default Value | Description                                                                                                                                                                                                                                                                                                                                                  |
|----------------------------------|---------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| kafka.topic                      | flume-channel | Specifies the Kafka topic used by the channel to cache data.                                                                                                                                                                                                                                                                                                 |
| kafka.consumer.group.id          | flume         | Specifies the data group ID obtained from Kafka. This parameter cannot be left blank.                                                                                                                                                                                                                                                                        |
| parseAsFlumeEvent                | true          | Specifies whether data is parsed into Flume events.                                                                                                                                                                                                                                                                                                          |
| migrateZookeeperOffsets          | true          | Specifies whether to search for offsets in ZooKeeper and submit them to Kafka when there is no offset in Kafka.                                                                                                                                                                                                                                              |
| kafka.consumer.auto.offset.reset | latest        | Specifies where to consume if there is no offset record, which can be set to <b>earliest</b> , <b>latest</b> , or <b>none</b> . <b>earliest</b> indicates that the offset is reset to the initial point, <b>latest</b> indicates that the offset is set to the latest position, and <b>none</b> indicates that an exception is thrown if there is no offset. |

| Parameter                        | Default Value  | Description                                                                                                                                                                                                                                                                                                                                                          |
|----------------------------------|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| kafka.producer.security.protocol | SASL_PLAINTEXT | Specifies the Kafka producer security protocol. The rules for matching ports and security protocols must be as follows: port 21007 matches the security mode (SASL_PLAINTEXT), and port 9092 matches the common mode (PLAINTEXT).<br><b>NOTE</b><br>If the parameter is not displayed, click + in the lower left corner of the dialog box to display all parameters. |
| kafka.consumer.security.protocol | SASL_PLAINTEXT | Specifies the Kafka consumer security protocol. The rules for matching ports and security protocols must be as follows: port 21007 matches the security mode (SASL_PLAINTEXT), and port 9092 matches the common mode (PLAINTEXT).                                                                                                                                    |
| pollTimeout                      | 500            | Specifies the maximum timeout interval for the consumer to invoke the poll function. Unit: milliseconds                                                                                                                                                                                                                                                              |
| ignoreLongMessage                | false          | Specifies whether to discard oversized messages.                                                                                                                                                                                                                                                                                                                     |
| messageMaxLength                 | 1000012        | Specifies the maximum length of a message written by Flume to Kafka.                                                                                                                                                                                                                                                                                                 |

## Common Sink Configurations

- **HDFS Sink**

An HDFS sink writes data into HDFS. Common configurations are as follows:

**Table 5-11** Common configurations of an HDFS sink

| Parameter              | Default Value   | Description                                                                                                                                                                                                                                             |
|------------------------|-----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| channel                | -               | Specifies the channel connected to the sink.                                                                                                                                                                                                            |
| type                   | hdfs            | Specifies the type of the hdfs sink, which must be set to <b>hdfs</b> .                                                                                                                                                                                 |
| hdfs.path              | -               | Specifies the data storage path in HDFS. The value must start with <b>hdfs://hacluster/</b> .                                                                                                                                                           |
| monTime                | 0<br>(Disabled) | Specifies the thread monitoring threshold. When the update time exceeds the threshold, the sink is restarted. Unit: second                                                                                                                              |
| hdfs.inUseSuffix       | .tmp            | Specifies the suffix of the HDFS file to which data is being written.                                                                                                                                                                                   |
| hdfs.rollInterval      | 30              | Specifies the interval for file rolling, expressed in seconds.                                                                                                                                                                                          |
| hdfs.rollSize          | 1024            | Specifies the size for file rolling, expressed in bytes.                                                                                                                                                                                                |
| hdfs.rollCount         | 10              | Specifies the number of events for file rolling.<br><b>NOTE</b><br>Parameters <b>rollInterval</b> , <b>rollSize</b> , and <b>rollCount</b> can be configured at the same time. The parameter meeting the requirements takes precedence for compression. |
| hdfs.idleTimeout       | 0               | Specifies the timeout interval for closing idle files automatically, expressed in seconds.                                                                                                                                                              |
| hdfs.batchSize         | 1000            | Specifies the number of events written into HDFS in batches.                                                                                                                                                                                            |
| hdfs.kerberosPrincipal | -               | Specifies the Kerberos principal of HDFS authentication. This parameter is mandatory in a secure mode, but not required in a common mode.                                                                                                               |
| hdfs.kerberosKeytab    | -               | Specifies the Kerberos keytab of HDFS authentication. This parameter is not required in a common mode, but in a secure mode, the Flume running user must have the permission to access <b>keyTab</b> path in the <b>jaas.conf</b> file.                 |

| Parameter                | Default Value                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|--------------------------|------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| hdfs.fileCloseByEvent    | true                         | Specifies whether to close the HDFS file when the last event of the source file is received.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
| hdfs.batchCallTimeout    | -                            | <p>Specifies the timeout control duration when events are written into HDFS in batches. Unit: milliseconds</p> <p>If this parameter is not specified, the timeout duration is controlled when each event is written into HDFS. When the value of <b>hdfs.batchSize</b> is greater than 0, configure this parameter to improve the performance of writing data into HDFS.</p> <p><b>NOTE</b><br/>The value of <b>hdfs.batchCallTimeout</b> depends on <b>hdfs.batchSize</b>. A greater <b>hdfs.batchSize</b> requires a larger <b>hdfs.batchCallTimeout</b>. If the value of <b>hdfs.batchCallTimeout</b> is too small, writing events to HDFS may fail.</p> |
| serializer.appendNewline | true                         | Specifies whether to add a line feed character ( <b>\n</b> ) after an event is written to HDFS. If a line feed character is added, the data volume counters used by the line feed character will not be calculated by HDFS sinks.                                                                                                                                                                                                                                                                                                                                                                                                                           |
| hdfs.filePrefix          | over_<br>%<br>{base<br>name} | Specifies the file name prefix after data is written to HDFS.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| hdfs.fileSuffix          | -                            | Specifies the file name suffix after data is written to HDFS.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| hdfs.inUsePrefix         | -                            | Specifies the prefix of the HDFS file to which data is being written.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
| hdfs.fileType            | DataStream                   | <p>Specifies the HDFS file format, which can be set to <b>SequenceFile</b>, <b>DataStream</b>, or <b>CompressedStream</b>.</p> <p><b>NOTE</b><br/>If the parameter is set to <b>SequenceFile</b> or <b>DataStream</b>, output files are not compressed, and the <b>codeC</b> parameter cannot be configured. However, if the parameter is set to <b>CompressedStream</b>, the output files are compressed, and the <b>codeC</b> parameter must be configured together.</p>                                                                                                                                                                                  |

| Parameter              | Default Value | Description                                                                                                                                                                                                               |
|------------------------|---------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| hdfs.codeC             | -             | Specifies the file compression format, which can be set to <b>gzip</b> , <b>bzip2</b> , <b>lzo</b> , <b>lzop</b> , or <b>snappy</b> .                                                                                     |
| hdfs.maxOpenFiles      | 5000          | Specifies the maximum number of HDFS files that can be opened. If the number of opened files reaches this value, the earliest opened files are closed.                                                                    |
| hdfs.writeFormat       | Writable      | Specifies the file write format, which can be set to <b>Writable</b> or <b>Text</b> .                                                                                                                                     |
| hdfs.callTimeout       | 10000         | Specifies the timeout control duration each time events are written into HDFS, expressed in milliseconds.                                                                                                                 |
| hdfs.threadsPoolSize   | -             | Specifies the number of threads used by each HDFS sink for HDFS I/O operations.                                                                                                                                           |
| hdfs.rollTimerPoolSize | -             | Specifies the number of threads used by each HDFS sink to schedule the scheduled file rolling.                                                                                                                            |
| hdfs.round             | false         | Specifies whether to round off the timestamp value. If this parameter is set to true, all time-based escape sequences (except %t) are affected.                                                                           |
| hdfs.roundUnit         | second        | Specifies the unit of the timestamp value that has been rounded off, which can be set to <b>second</b> , <b>minute</b> , or <b>hour</b> .                                                                                 |
| hdfs.useLocalTimestamp | true          | Specifies whether to enable the local timestamp. The recommended parameter value is <b>true</b> .                                                                                                                         |
| hdfs.closeTries        | 0             | Specifies the maximum attempts for the <b>hdfs sink</b> to stop renaming a file. If the parameter is set to the default value <b>0</b> , the sink does not stop renaming the file until the file is successfully renamed. |

| Parameter          | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|--------------------|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| hdfs.retryInterval | 180           | Specifies the interval of request for closing the HDFS file, expressed in seconds.<br><b>NOTE</b><br>For each closing request, there are multiple RPCs working on the NameNode back and forth, which may make the NameNode overloaded if the parameter value is too small. Also, when the parameter is set to <b>0</b> , the Sink will not attempt to close the file, but opens the file or uses <b>.tmp</b> as the file name extension, if the first closing attempt fails. |
| hdfs.failcount     | 10            | Specifies the number of times that data fails to be written to HDFS. If the number of times that the sink fails to write data to HDFS exceeds the parameter value, an alarm indicating abnormal data transmission is reported.                                                                                                                                                                                                                                               |

- **Avro Sink**

An Avro sink converts events into Avro events and sends them to the monitoring ports of the hosts. Common configurations are as follows:

**Table 5-12** Common configurations of an Avro sink

| Parameter  | Default Value | Description                                                                |
|------------|---------------|----------------------------------------------------------------------------|
| channel    | -             | Specifies the channel connected to the sink.                               |
| type       | -             | Specifies the type of the avro sink, which must be set to <b>avro</b> .    |
| hostname   | -             | Specifies the bound host name or IP address.                               |
| port       | -             | Specifies the bound listening port. Ensure that this port is not occupied. |
| batch-size | 1000          | Specifies the number of events sent in a batch.                            |

| Parameter       | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|-----------------|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| client.type     | DEFAULT       | <p>Specifies the client instance type. Set this parameter based on the communication protocol used by the configured model. The options are as follows:</p> <ul style="list-style-type: none"> <li>• <b>DEFAULT</b>: The client instance of the AvroRPC type is returned.</li> <li>• <b>OTHER</b>: NULL is returned.</li> <li>• <b>THRIFT</b>: The client instance of the Thrift RPC type is returned.</li> <li>• <b>DEFAULT_LOADBALANCING</b>: The client instance of the LoadBalancing RPC type is returned.</li> <li>• <b>DEFAULT_FAILOVER</b>: The client instance of the Failover RPC type is returned.</li> </ul> |
| ssl             | false         | <p>Specifies whether to use SSL encryption. If this parameter is set to <b>true</b>, the values of <b>keystore</b> and <b>keystore-password</b> must be specified.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| truststore-type | JKS           | <p>Specifies the Java trust store type, which can be set to <b>JKS</b> or <b>PKCS12</b>.</p> <p><b>NOTE</b><br/>Different passwords are used to protect the key store and private key of <b>JKS</b>, while the same password is used to protect the key store and private key of <b>PKCS12</b>.</p>                                                                                                                                                                                                                                                                                                                     |
| truststore      | -             | <p>Specifies the Java trust store file.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |

| Parameter                 | Default Value | Description                                                                                                                                                                                        |
|---------------------------|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| truststore-password       | -             | Specifies the Java trust store password.                                                                                                                                                           |
| keystore-type             | JKS           | Specifies the keystore type set after SSL is enabled.                                                                                                                                              |
| keystore                  | -             | Specifies the keystore file path set after SSL is enabled. This parameter is mandatory if SSL is enabled.                                                                                          |
| keystore-password         | -             | Specifies the keystore password after SSL is enabled. This parameter is mandatory if SSL is enabled.                                                                                               |
| connect-timeout           | 20000         | Specifies the timeout for the first connection, expressed in milliseconds.                                                                                                                         |
| request-timeout           | 20000         | Specifies the maximum timeout for a request after the first request, expressed in milliseconds.                                                                                                    |
| reset-connection-interval | 0             | Specifies the interval between a connection failure and a second connection, expressed in seconds. If the parameter is set to <b>0</b> , the system continuously attempts to perform a connection. |

| Parameter         | Default Value | Description                                                                                                                                                                                                                                                                                        |
|-------------------|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| compression-type  | none          | Specifies the compression type of the batch data, which can be set to <b>none</b> or <b>deflate</b> . <b>none</b> indicates that data is not compressed, while <b>deflate</b> indicates that data is compressed. This parameter value must be the same as that of the AvroSource compression-type. |
| compression-level | 6             | Specifies the compression level of batch data, which can be set to <b>1</b> to <b>9</b> . A larger value indicates a higher compression rate.                                                                                                                                                      |
| exclude-protocols | SSLv3         | Specifies the excluded protocols. The entered protocols must be separated by spaces. The default value is <b>SSLv3</b> .                                                                                                                                                                           |

- **HBase Sink**

An HBase sink writes data into HBase. Common configurations are as follows:

**Table 5-13** Common configurations of an HBase sink

| Parameter    | Default Value | Description                                                                                                                |
|--------------|---------------|----------------------------------------------------------------------------------------------------------------------------|
| channel      | -             | Specifies the channel connected to the sink.                                                                               |
| type         | -             | Specifies the type of the HBase sink, which must be set to <b>hbase</b> .                                                  |
| table        | -             | Specifies the HBase table name.                                                                                            |
| columnFamily | -             | Specifies the HBase column family.                                                                                         |
| monTime      | 0 (Disabled)  | Specifies the thread monitoring threshold. When the update time exceeds the threshold, the sink is restarted. Unit: second |

| Parameter          | Default Value | Description                                                                                                                                                                                                                             |
|--------------------|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| batchSize          | 1000          | Specifies the number of events written into HBase in batches.                                                                                                                                                                           |
| kerberosPrincipal  | -             | Specifies the Kerberos principal of HBase authentication. This parameter is mandatory in a secure mode, but not required in a common mode.                                                                                              |
| kerberosKeytab     | -             | Specifies the Kerberos keytab of HBase authentication. This parameter is not required in a common mode, but in a secure mode, the Flume running user must have the permission to access <b>keyTab</b> path in the <b>jaas.cof</b> file. |
| coalesceIncrements | true          | Specifies whether to perform multiple operations on the same hbase cell in a same processing batch. Setting this parameter to <b>true</b> improves performance.                                                                         |

- **Kafka Sink**

A Kafka sink writes data into Kafka. Common configurations are as follows:

**Table 5-14** Common configurations of a Kafka sink

| Parameter | Default Value | Description                                                                                               |
|-----------|---------------|-----------------------------------------------------------------------------------------------------------|
| channel   | -             | Specifies the channel connected to the sink.                                                              |
| type      | -             | Specifies the type of the kafka sink, which must be set to <b>org.apache.flume.sink.kafka.KafkaSink</b> . |

| Parameter               | Default Value  | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|-------------------------|----------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| kafka.bootstrap.servers | -              | Specifies the bootstrap address port list of Kafka. If Kafka has been installed in the cluster and the configuration has been synchronized to the server, you do not need to set this parameter on the server. The default value is the list of all brokers in the Kafka cluster. The client must be configured with this parameter. If there are multiple values, use commas (,) to separate the values. The rules for matching ports and security protocols must be as follows: port 21007 matches the security mode (SASL_PLAINTEXT), and port 9092 matches the common mode (PLAINTEXT). |
| monTime                 | 0 (Disabled)   | Specifies the thread monitoring threshold. When the update time exceeds the threshold, the sink is restarted. Unit: second                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| kafka.producer.acks     | 1              | Successful write is determined by the number of received acknowledgement messages about replicas. The value <b>0</b> indicates that no confirm message needs to be received, the value <b>1</b> indicates that the system is only waiting for only the acknowledgement information from a leader, and the value <b>-1</b> indicates that the system is waiting for the acknowledgement messages of all replicas. If this parameter is set to <b>-1</b> , data loss can be avoided in some leader failure scenarios.                                                                         |
| kafka.topic             | -              | Specifies the topic to which data is written. This parameter is mandatory.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| flumeBatchSize          | 1000           | Specifies the number of events written into Kafka in batches.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
| kafka.security.protocol | SASL_PLAINTEXT | Specifies the Kafka security protocol. The parameter value must be set to PLAINTEXT in a common cluster. The rules for matching ports and security protocols must be as follows: port 21007 matches the security mode (SASL_PLAINTEXT), and port 9092 matches the common mode (PLAINTEXT).                                                                                                                                                                                                                                                                                                  |

| Parameter                       | Default Value | Description                                                                                                                                                                                                                                                                                                                                                                                   |
|---------------------------------|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ignoreLongMessage               | false         | Specifies whether to discard oversized messages.                                                                                                                                                                                                                                                                                                                                              |
| messageMaxLength                | 1000012       | Specifies the maximum length of a message written by Flume to Kafka.                                                                                                                                                                                                                                                                                                                          |
| defaultPartitionId              | -             | Specifies the Kafka partition ID to which the events of a channel is transferred. The <b>partitionIdHeader</b> value overwrites this parameter value. By default, if this parameter is left blank, events will be distributed by the Kafka Producer's partitioner (by a specified key or a partitioner customized by <b>kafka.partitionner.class</b> ).                                       |
| partitionIdHeader               | -             | When you set this parameter, the sink will take the value of the field named using the value of this property from the event header and send the message to the specified partition of the topic. If the value does not have a valid partition, <b>EventDeliveryException</b> is thrown. If the header value already exists, this setting overwrites the <b>defaultPartitionId</b> parameter. |
| Other Kafka Producer Properties | -             | Specifies other Kafka configurations. This parameter can be set to any production configuration supported by Kafka, and the <b>.kafka</b> prefix must be added to the configuration.                                                                                                                                                                                                          |

- **Thrift Sink**

A Thrift sink converts events to Thrift events and sends them to the monitoring port of the configured host. Common configurations are as follows:

**Table 5-15** Common configurations of a Thrift sink

| Parameter | Default Value | Description                                                                 |
|-----------|---------------|-----------------------------------------------------------------------------|
| channel   | -             | Specifies the channel connected to the sink.                                |
| type      | thrift        | Specifies the type of the thrift sink, which must be set to <b>thrift</b> . |

| Parameter        | Default Value | Description                                                                                                                                                                                                          |
|------------------|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| hostname         | -             | Specifies the bound host name or IP address.                                                                                                                                                                         |
| port             | -             | Specifies the bound listening port. Ensure that this port is not occupied.                                                                                                                                           |
| batch-size       | 1000          | Specifies the number of events sent in a batch.                                                                                                                                                                      |
| connect-timeout  | 20000         | Specifies the timeout for the first connection, expressed in milliseconds.                                                                                                                                           |
| request-timeout  | 20000         | Specifies the maximum timeout for a request after the first request, expressed in milliseconds.                                                                                                                      |
| kerberos         | false         | Specifies whether Kerberos authentication is enabled.                                                                                                                                                                |
| client-keytab    | -             | Specifies the path of the client <b>keytab</b> file. The Flume running user must have the access permission on the authentication file.                                                                              |
| client-principal | -             | Specifies the principal of the security user used by the client.                                                                                                                                                     |
| server-principal | -             | Specifies the principal of the security user used by the server.                                                                                                                                                     |
| compression-type | none          | Specifies the compression type of data sent by Flume, which can be set to <b>none</b> or <b>deflate</b> . <b>none</b> indicates that data is not compressed, while <b>deflate</b> indicates that data is compressed. |

| Parameter                 | Default Value | Description                                                                                                                                                                                        |
|---------------------------|---------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| maxConnections            | 5             | Specifies the maximum size of the connection pool for Flume to send data.                                                                                                                          |
| ssl                       | false         | Specifies whether to use SSL encryption.                                                                                                                                                           |
| truststore-type           | JKS           | Specifies the Java trust store type.                                                                                                                                                               |
| truststore                | -             | Specifies the Java trust store file.                                                                                                                                                               |
| truststore-password       | -             | Specifies the Java trust store password.                                                                                                                                                           |
| reset-connection-interval | 0             | Specifies the interval between a connection failure and a second connection, expressed in seconds. If the parameter is set to <b>0</b> , the system continuously attempts to perform a connection. |

## Precautions

- What are the reliability measures of Flume?
    - Use the transaction mechanisms between Source and Channel as well as between Channel and Sink.
    - Configure the failover and load\_balance mechanisms for Sink Processor. The following shows a load balancing example. For details, see <http://flume.apache.org/releases/1.9.0.html>.
- ```
server.sinkgroups=g1
server.sinkgroups.g1.sinks=k1 k2
server.sinkgroups.g1.processor.type=load_balance
server.sinkgroups.g1.processor.backoff=true
server.sinkgroups.g1.processor.selector=random
```
- What are the precautions for the aggregation and cascading of multiple Flume agents?
    - Avro or Thrift protocol can be used for cascading.
    - When the aggregation end contains multiple nodes, evenly distribute the agents and do not aggregate all agents on a single node.

## 5.8 Flume Configuration Parameter Description

Some parameters can be configured on Manager.

## Overview

This section describes how to configure the sources, channels, and sinks of Flume, and modify the configuration items of each module.

Log in to FusionInsight Manager and choose **Cluster > Services > Flume**. On the displayed page, click the **Configuration Tool** tab to configure the **source**, **channel**, and **sink** parameters. Parameters such as **channels** and **type** are configured only in the client configuration file **properties.properties**, the path of which is *Flume client installation directory/fusioninsight-flume-Flume version/conf/properties.properties*.

### NOTE

You must input encrypted information for some configurations. For details on how to encrypt information, see [Using the Encryption Tool of the Flume Client](#).

## Common Source Configurations

- **Avro Source**

An Avro source listens to the Avro port, receives data from the external Avro client, and places data into configured channels. [Table 5-16](#) lists common configurations.

**Table 5-16** Common configurations of an Avro source

Parameter	Default Value	Description
channels	-	<p>Specifies the channel connected to the source. Multiple channels can be configured. Use spaces to separate them.</p> <p>In a single proxy process, sources and sinks are connected through channels. A source instance corresponds to multiple channels, but a sink instance corresponds only to one channel.</p> <p>The format is as follows:</p> <pre>&lt;Agent &gt;.sources.&lt;Source&gt;.channels = &lt;channel1&gt; &lt;channel2&gt; &lt;channel3&gt;... &lt;Agent &gt;.sinks.&lt;Sink&gt;.channels = &lt;channel1&gt;</pre> <p>This parameter can be configured only in the <b>properties.properties</b> file.</p>

Parameter	Default Value	Description
type	avro	Specifies the type, which is set to <b>avro</b> . The type of each source is a fixed value. This parameter can be configured only in the <b>properties.properties</b> file.
bind	-	Specifies the host name or IP address associated with the source.
port	-	Specifies the bound port number.
ssl	false	Specifies whether to use SSL encryption. <ul style="list-style-type: none"> <li>• true</li> <li>• false</li> </ul>
truststore-type	JKS	Specifies the Java trust store type. Set this parameter to <b>JKS</b> or other truststore types supported by Java.
truststore	-	Specifies the Java trust store file.
truststore-password	-	Specifies the Java trust store password.
keystore-type	JKS	Specifies the key storage type. Set this parameter to <b>JKS</b> or other truststore types supported by Java.
keystore	-	Specifies the key storage file.
keystore-password	-	Specifies the key storage password.

- **SpoolDir Source**

A SpoolDir source monitors and transmits new files that have been added to directories in quasi-real-time mode. Common configurations are as follows:

**Table 5-17** Common configurations of a SpoolDir source

Parameter	Default Value	Description
channels	-	Specifies the channel connected to the source. Multiple channels can be configured. This parameter can be configured only in the <b>properties.properties</b> file.

Parameter	Default Value	Description
type	spooldir	Type, which is set to <b>spooldir</b> . This parameter can be configured only in the <b>properties.properties</b> file.
monTime	0 (Disabled)	Specifies the thread monitoring threshold. When the update time exceeds the threshold, the source is restarted. Unit: second
spoolDir	-	Specifies the monitoring directory.
fileSuffix	.COMPLETED	Specifies the suffix added after file transmission is complete.
deletePolicy	never	Specifies the source file deletion policy after file transmission is complete. The value can be either <b>never</b> or <b>immediate</b> .
ignorePattern	^\$	Specifies the regular expression of a file to be ignored.
trackerDir	.flumespool	Specifies the metadata storage path during data transmission.
batchSize	1000	Specifies the source transmission granularity.
decodeErrorPolicy	FAIL	Specifies the code error policy. This parameter can be configured only in the <b>properties.properties</b> file. The value can be <b>FAIL</b> , <b>REPLACE</b> , or <b>IGNORE</b> . <b>FAIL</b> : Generate an exception and fail the parsing. <b>REPLACE</b> : Replace the characters that cannot be identified with other characters, such as U+FFFD. <b>IGNORE</b> : Discard character strings that cannot be parsed. <b>NOTE</b> If a code error occurs in the file, set <b>decodeErrorPolicy</b> to <b>REPLACE</b> or <b>IGNORE</b> . Flume will skip the code error and continue to collect subsequent logs.

Parameter	Default Value	Description
deserializer	LINE	Specifies the file parser. The value can be either <b>LINE</b> or <b>BufferedLine</b> . <ul style="list-style-type: none"> <li>When the value is set to <b>LINE</b>, characters read from the file are transcoded one by one.</li> <li>When the value is set to <b>BufferedLine</b>, one line or multiple lines of characters read from the file are transcoded in batches, which delivers better performance.</li> </ul>
deserializer.maxLineLength	2048	Specifies the maximum length for resolution by line, ranging from 0 to 2,147,483,647.
deserializer.maxBatchLine	1	Specifies the maximum number of lines for resolution by line. If multiple lines are set, <b>maxLineLength</b> must be set to a corresponding multiplier. For example, if <b>maxBatchLine</b> is set to <b>2</b> , <b>maxLineLength</b> is set to <b>4096</b> (2048 x 2).
selector.type	replicating	Specifies the selector type. The value can be either <b>replicating</b> or <b>multiplexing</b> . <ul style="list-style-type: none"> <li><b>replicating</b> indicates that the same content is sent to each channel.</li> <li><b>multiplexing</b> indicates that the content is sent only to certain channels according to the distribution rule.</li> </ul>
interceptors	-	Specifies the interceptor. For details, see the <a href="#">Flume official document</a> . This parameter can be configured only in the <b>properties.properties</b> file.

 **NOTE**

The Spooling source ignores the last line feed character of each event when data is read by line. Therefore, Flume does not calculate the data volume counters used by the last line feed character.

- **Kafka Source**

A Kafka source consumes data from Kafka topics. Multiple sources can consume data of the same topic, and the sources consume different partitions of the topic. Common configurations are as follows:

**Table 5-18** Common configurations of a Kafka source

Parameter	Default Value	Description
channels	-	Specifies the channel connected to the source. Multiple channels can be configured.  This parameter can be configured only in the <b>properties.properties</b> file.
type	org.apache.flume.source.kafka.KafkaSource	Specifies the type, which is set to <b>org.apache.flume.source.kafka.KafkaSource</b> .  This parameter can be configured only in the <b>properties.properties</b> file.
monTime	0 (Disabled)	Specifies the thread monitoring threshold. When the update time exceeds the threshold, the source is restarted. Unit: second
nodatotime	0 (Disabled)	Specifies the alarm threshold. An alarm is triggered when the duration that Kafka does not release data to subscribers exceeds the threshold. Unit: second
batchSize	1000	Specifies the number of events written into a channel at a time.
batchDurationMillis	1000	Specifies the maximum duration of topic data consumption at a time, expressed in milliseconds.
keepTopicInHeader	false	Specifies whether to save topics in the event header. If topics are saved, topics configured in Kafka sinks become invalid. <ul style="list-style-type: none"> <li>• true</li> <li>• false</li> </ul> This parameter can be configured only in the <b>properties.properties</b> file.

Parameter	Default Value	Description
keepPartitionIn-Header	false	Specifies whether to save partition IDs in the event header. If partition IDs are saved, Kafka sinks write data to the corresponding partitions. <ul style="list-style-type: none"> <li>• true</li> <li>• false</li> </ul> This parameter can be set only in the properties.properties file.
kafka.bootstrap.servers	-	Specifies the list of Broker addresses, which are separated by commas.
kafka.consumer.group.id	-	Specifies the Kafka consumer group ID.
kafka.topics	-	Specifies the list of subscribed Kafka topics, which are separated by commas (,).
kafka.topics.regex	-	Specifies the subscribed topics that comply with regular expressions. <b>kafka.topics.regex</b> has a higher priority than <b>kafka.topics</b> and will overwrite <b>kafka.topics</b> .
kafka.security.protocol	SASL_PLAINTEXT	Specifies the security protocol of Kafka. The value must be set to <b>PLAINTEXT</b> for clusters in which Kerberos authentication is disabled.
kafka.kerberos.domain.name	-	Specifies the value of <b>default_realm</b> of Kerberos in the Kafka cluster, which should be configured only for security clusters.  This parameter can be set only in the properties.properties file.
Other Kafka Consumer Properties	-	Specifies other Kafka configurations. This parameter can be set to any consumption configuration supported by Kafka, and the <b>.kafka</b> prefix must be added to the configuration.  This parameter can be set only in the properties.properties file.

- **Taildir Source**

A Taildir source monitors file changes in a directory and automatically reads the file content. In addition, it can transmit data in real time. [Table 5-19](#) lists common configurations.

**Table 5-19** Common configurations of a Taildir source

Parameter	Default Value	Description
channels	-	Specifies the channel connected to the source. Multiple channels can be configured.  This parameter can be set only in the properties.properties file.
type	taildir	Specifies the type, which is set to <b>taildir</b> .  This parameter can be set only in the properties.properties file.
filegroups	-	Specifies the group name of a collection file directory. Group names are separated by spaces.
filegroups.<filegroup Name>.parentDir	-	Specifies the parent directory. The value must be an absolute path.  This parameter can be set only in the properties.properties file.
filegroups.<filegroup Name>.filePattern	-	Specifies the relative file path of the file group's parent directory. Directories can be included and regular expressions are supported. It must be used together with <b>parentDir</b> .  This parameter can be set only in the properties.properties file.
positionFile	-	Specifies the metadata storage path during data transmission.
headers.<filegroup Name>.<headerKey>	-	Specifies the key-value of an event when data of a group is being collected.  This parameter can be set only in the properties.properties file.
byteOffsetHeader	false	Specifies whether each event header should contain the location information about the event in the source file. The location information is saved in the <b>byteoffset</b> variable.

Parameter	Default Value	Description
skipToEnd	false	Specifies whether Flume can locate the latest location of a file and read the latest data after restart.
idleTimeout	120000	Specifies the idle duration during file reading, expressed in milliseconds. If the file data is not changed in this idle period, the source closes the file. If data is written into this file after it is closed, the source opens the file and reads data.
writePosInterval	3000	Specifies the interval for writing metadata to a file, expressed in milliseconds.
batchSize	1000	Specifies the number of events written to the channel in batches.
monTime	0 (Disabled)	Specifies the thread monitoring threshold. When the update time exceeds the threshold, the source is restarted. Unit: second

- **Http Source**

An HTTP source receives data from an external HTTP client and sends the data to the configured channels. [Table 5-20](#) lists common configurations.

**Table 5-20** Common configurations of an HTTP source

Parameter	Default Value	Description
channels	-	Specifies the channel connected to the source. Multiple channels can be configured. This parameter can be set only in the properties.properties file.
type	http	Specifies the type, which is set to <b>http</b> . This parameter can be set only in the properties.properties file.
bind	-	Specifies the name or IP address of the bound host.
port	-	Specifies the bound port.

Parameter	Default Value	Description
handler	org.apache.flume.source.http.JSONHandler	Specifies the message parsing method of an HTTP request. The following methods are supported: <ul style="list-style-type: none"> <li><b>org.apache.flume.source.http.JSONHandler</b>: JSON</li> <li><b>org.apache.flume.sink.solr.morphline.BlobHandler</b>: BLOB</li> </ul>
handler.*	-	Specifies handler parameters.
enableSSL	false	Specifies whether SSL is enabled in HTTP.
keystore	-	Specifies the keystore path set after SSL is enabled in HTTP.
keystorePassword	-	Specifies the keystore password set after SSL is enabled in HTTP.

## Common Channel Configurations

- **Memory Channel**

A memory channel uses memory as the cache. Events are stored in memory queues. [Table 5-21](#) lists common configurations.

**Table 5-21** Common configurations of a memory channel

Parameter	Default Value	Description
type	-	Specifies the type, which is set to <b>memory</b> . This parameter can be set only in the properties.properties file.
capacity	10000	Specifies the maximum number of events cached in a channel.
transactionCapacity	1000	Specifies the maximum number of events accessed each time.
channelFullcount	10	Specifies the channel full count. When the count reaches the threshold, an alarm is reported.

- **File Channel**

A file channel uses local disks as the cache. Events are stored in the folder specified by **dataDirs**. [Table 5-22](#) lists common configurations.

**Table 5-22** Common configurations of a file channel

Parameter	Default Value	Description
type	-	Specifies the type, which is set to <b>file</b> . This parameter can be set only in the properties.properties file.
checkpointDir	\${BIGDATA_DATA_HOME}/flume/checkpoint	Specifies the checkpoint storage directory.
dataDirs	\${BIGDATA_DATA_HOME}/flume/data	Specifies the data cache directory. Multiple directories can be configured to improve performance. The directories are separated by commas (,).
maxFileSize	2146435071	Specifies the maximum size of a single cache file, expressed in bytes.
minimumRequired-Space	524288000	Specifies the minimum idle space in the cache, expressed in bytes.
capacity	1000000	Specifies the maximum number of events cached in a channel.
transactionCapacity	10000	Specifies the maximum number of events accessed each time.
channelfullcount	10	Specifies the channel full count. When the count reaches the threshold, an alarm is reported.

- **Kafka Channel**

A Kafka channel uses a Kafka cluster as the cache. Kafka provides high availability and multiple copies to prevent data from being immediately consumed by sinks when Flume or Kafka Broker crashes. [Table 10 Common configurations of a Kafka channel](#) lists common configurations.

**Table 5-23** Common configurations of a Kafka channel

Parameter	Default Value	Description
type	-	Specifies the type, which is set to <b>org.apache.flume.channel.kafka.KafkaChannel</b> . This parameter can be set only in the properties.properties file.

Parameter	Default Value	Description
kafka.bootstrap.servers	-	Specifies the list of Brokers in the Kafka cluster.
kafka.topic	flume-channel	Specifies the Kafka topic used by the channel to cache data.
kafka.consumer.group.id	flume	Specifies the Kafka consumer group ID.
parseAsFlumeEvent	true	Specifies whether data is parsed into Flume events.
migrateZookeeper-Offsets	true	Specifies whether to search for offsets in ZooKeeper and submit them to Kafka when there is no offset in Kafka.
kafka.consumer.auto.offset.reset	latest	Consumes data from the specified location when there is no offset.
kafka.producer.security.protocol	SASL_PLAINTEXT	Specifies the Kafka producer security protocol.
kafka.consumer.security.protocol	SASL_PLAINTEXT	Specifies the Kafka consumer security protocol.

## Common Sink Configurations

- **HDFS Sink**

An HDFS sink writes data into HDFS. [Table 5-24](#) lists common configurations.

**Table 5-24** Common configurations of an HDFS sink

Parameter	Default Value	Description
channel	-	Specifies the channel connected to the sink. This parameter can be set only in the properties.properties file.
type	hdfs	Specifies the type, which is set to <b>hdfs</b> . This parameter can be set only in the properties.properties file.
monTime	0 (Disabled)	Specifies the thread monitoring threshold. When the update time exceeds the threshold, the sink is restarted. Unit: second
hdfs.path	-	Specifies the HDFS path.

Parameter	Default Value	Description
hdfs.inUseSuffix	.tmp	Specifies the suffix of the HDFS file to which data is being written.
hdfs.rollInterval	30	Specifies the interval for file rolling, expressed in seconds.
hdfs.rollSize	1024	Specifies the size for file rolling, expressed in bytes.
hdfs.rollCount	10	Specifies the number of events for file rolling.
hdfs.idleTimeout	0	Specifies the timeout interval for closing idle files automatically, expressed in seconds.
hdfs.batchSize	1000	Specifies the number of events written into HDFS at a time.
hdfs.kerberosPrincipal	-	Specifies the Kerberos username for HDFS authentication. This parameter is not required for a cluster in which Kerberos authentication is disabled.
hdfs.kerberosKeytab	-	Specifies the Kerberos keytab of HDFS authentication. This parameter is not required for a cluster in which Kerberos authentication is disabled.
hdfs.fileCloseByEvent	true	Specifies whether to close the file when the last event is received.
hdfs.batchCallTimeout	-	<p>Specifies the timeout control duration each time events are written into HDFS, expressed in milliseconds.</p> <p>If this parameter is not specified, the timeout duration is controlled when each event is written into HDFS. When the value of <b>hdfs.batchSize</b> is greater than 0, configure this parameter to improve the performance of writing data into HDFS.</p> <p><b>NOTE</b> The value of <b>hdfs.batchCallTimeout</b> depends on <b>hdfs.batchSize</b>. A greater <b>hdfs.batchSize</b> requires a larger <b>hdfs.batchCallTimeout</b>. If the value of <b>hdfs.batchCallTimeout</b> is too small, writing events to HDFS may fail.</p>

Parameter	Default Value	Description
serializer.appendNewLine	true	Specifies whether to add a line feed character (\n) after an event is written to HDFS. If a line feed character is added, the data volume counters used by the line feed character will not be calculated by HDFS sinks.

- **Avro Sink**

An Avro sink converts events into Avro events and sends them to the monitoring ports of the hosts. [Table 5-25](#) lists common configurations.

**Table 5-25** Common configurations of an Avro sink

Parameter	Default Value	Description
channel	-	Specifies the channel connected to the sink. This parameter can be set only in the properties.properties file.
type	-	Specifies the type, which is set to <b>avro</b> . This parameter can be set only in the properties.properties file.
hostname	-	Specifies the name or IP address of the bound host.
port	-	Specifies the monitoring port.
batch-size	1000	Specifies the number of events sent in a batch.
ssl	false	Specifies whether to use SSL encryption.
truststore-type	JKS	Specifies the Java trust store type.
truststore	-	Specifies the Java trust store file.
truststore-password	-	Specifies the Java trust store password.
keystore-type	JKS	Specifies the key storage type.
keystore	-	Specifies the key storage file.
keystore-password	-	Specifies the key storage password.

- **HBase Sink**

An HBase sink writes data into HBase. [Table 5-26](#) lists common configurations.

**Table 5-26** Common configurations of an HBase sink

Parameter	Default Value	Description
channel	-	Specifies the channel connected to the sink. This parameter can be set only in the properties.properties file.
type	-	Specifies the type, which is set to <b>hbase</b> . This parameter can be set only in the properties.properties file.
table	-	Specifies the HBase table name.
monTime	0 (Disabled)	Specifies the thread monitoring threshold. When the update time exceeds the threshold, the sink is restarted. Unit: second
columnFamily	-	Specifies the HBase column family.
batchSize	1000	Specifies the number of events written into HBase at a time.
kerberosPrincipal	-	Specifies the Kerberos username for HBase authentication. This parameter is not required for a cluster in which Kerberos authentication is disabled.
kerberosKeytab	-	Specifies the Kerberos keytab of HBase authentication. This parameter is not required for a cluster in which Kerberos authentication is disabled.

- **Kafka Sink**

A Kafka sink writes data into Kafka. [Table 5-27](#) lists common configurations.

**Table 5-27** Common configurations of a Kafka sink

Parameter	Default Value	Description
channel	-	Specifies the channel connected to the sink. This parameter can be set only in the properties.properties file.
type	-	Specifies the type, which is set to <b>org.apache.flume.sink.kafka.Kafka Sink</b> . This parameter can be set only in the properties.properties file.

Parameter	Default Value	Description
kafka.bootstrap.servers	-	Specifies the list of Kafka Brokers, which are separated by commas.
monTime	0 (Disabled)	Specifies the thread monitoring threshold. When the update time exceeds the threshold, the sink is restarted. Unit: second
kafka.topic	default-flume-topic	Specifies the topic where data is written.
flumeBatchSize	1000	Specifies the number of events written into Kafka at a time.
kafka.security.protocol	SASL_PLAINTEXT	Specifies the security protocol of Kafka. The value must be set to <b>PLAINTEXT</b> for clusters in which Kerberos authentication is disabled.
kafka.kerberos.domain.name	-	Specifies the Kafka domain name. This parameter is mandatory for a security cluster. This parameter can be set only in the properties.properties file.
Other Kafka Producer Properties	-	Specifies other Kafka configurations. This parameter can be set to any production configuration supported by Kafka, and the <b>.kafka</b> prefix must be added to the configuration. This parameter can be set only in the properties.properties file.

## 5.9 Using Environment Variables in the properties.properties File

### Scenario

This section describes how to use environment variables in the **properties.properties** configuration file.

### Prerequisites

The Flume service is running properly and the Flume client has been installed.

## Procedure

**Step 1** Log in to the node where the Flume client is installed as user **root**.

**Step 2** Switch to the following directory:

```
cd Flume client installation directory/fusioninsight-flume-Flume component version/conf
```

**Step 3** Add environment variables to the **flume-env.sh** file in the directory.

- Format:

```
export Variable name=Variable value
```

- Example:

```
JAVA_OPTS="-Xms2G -Xmx4G -XX:CMSFullGCsBeforeCompaction=1 -XX:+UseConcMarkSweepGC -XX:+CMSParallelRemarkEnabled -XX:+UseCMSCompactAtFullCollection -DpropertiesImplementation=org.apache.flume.node.EnvVarResolverProperties"
export TAILDIR_PATH=/tmp/flumetest/201907/20190703/1/*log.*
```

**Step 4** Restart the Flume instance process.

1. Log in to FusionInsight Manager.
2. Choose **Cluster** > **Services** > **Flume**. On the page that is displayed, click the **Instance** tab, select all Flume instances, and choose **More** > **Restart Instance**. In the displayed **Verify Identity** dialog box, enter the password, and click **OK**.

### NOTICE

Do not restart the Flume service on FusionInsight Manager after **flume-env.sh** takes effect on the server. Otherwise, the user-defined environment variables will be lost. You only need to restart the corresponding instances on FusionInsight Manager.

**Step 5** In the *Flume client installation directory*/fusioninsight-flume-*Flume component version number*/conf/**properties.properties** configuration file, reference variables in the  **$\${Variable name}$**  format. The following is an example:

```
client.sources.s1.type = TAILDIR
client.sources.s1.filegroups = f1
client.sources.s1.filegroups.f1 =  $\${TAILDIR\_PATH}$ 
client.sources.s1.positionFile = /tmp/flumetest/201907/20190703/1/taildir_position.json
client.sources.s1.channels = c1
```

#### NOTICE

- Ensure that **flume-env.sh** takes effect before you go to **Step 5** to configure the **properties.properties** file.
- If you configure file on the local host, upload the file on FusionInsight Manager by performing the following steps. The user-defined environment variables may be lost if the operations are not performed in the correct sequence.
  1. Log in to FusionInsight Manager.
  2. Choose **Cluster > Services > Flume**. On the page that is displayed, click the **Configurations** tab, select the Flume instance, and click **Upload File** next to **flume.config.file** to upload the **properties.properties** file.

----End

## 5.10 Non-Encrypted Transmission

### 5.10.1 Configuring Non-encrypted Transmission

#### Scenario

This section describes how to configure Flume server and client parameters after the cluster and the Flume service are installed to ensure proper running of the service.

#### NOTE

By default, the cluster network environment is secure and the SSL authentication is not enabled during the data transmission process. For details about how to use the encryption mode, see [Configuring the Encrypted Transmission](#).

#### Prerequisites

- The cluster and Flume service have been installed.
- The network environment of the cluster is secure.

#### Procedure

**Step 1** Configure the client parameters of the Flume role.

1. Use the Flume configuration tool on FusionInsight Manager to configure the Flume role client parameters and generate a configuration file.
  - a. Log in to FusionInsight Manager. Choose **Cluster > Services > Flume > Configuration Tool**.
  - b. Set **Agent Name** to **client**. Select and drag the source, channel, and sink to be used to the GUI on the right, and connect them.  
For example, use SpoolDir Source, File Channel, and Avro Sink, as shown in [Figure 5-2](#).

**Figure 5-2** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by referring to [Table 5-28](#) based on the actual environment.

**NOTE**

- If the client parameters of the Flume role have been configured, you can obtain the existing client parameter configuration file from *client installation directory/fusioninsight-flume-1.9.0/conf/properties.properties* to ensure that the configuration is in concordance with the previous. Log in to FusionInsight Manager, choose **Cluster > Services > Flume > Configuration > Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
- d. Click **Export** to save the **properties.properties** configuration file to the local server.

**Table 5-28** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
ssl	<p>Specifies whether to enable the SSL authentication. (You are advised to enable this function to ensure security.)</p> <p>Only Sources of the Avro type have this configuration item.</p> <ul style="list-style-type: none"> <li>▪ <b>true</b> indicates that the function is enabled.</li> <li>▪ <b>false</b> indicates that the function is not enabled.</li> </ul>	false

- 2. Upload the **properties.properties** file to **flume/conf/** under the installation directory of the Flume client.


**Step 2** Configure the server parameters of the Flume role and upload the configuration file to the cluster.

- 1. Use the Flume configuration tool on the FusionInsight Manager portal to configure the server parameters and generate the configuration file.

- a. Log in to FusionInsight Manager. Choose **Cluster > Services > Flume > Configuration Tool**.
- b. Set **Agent Name** to **server**. Select and drag the source, channel, and sink to be used to the GUI on the right, and connect them.

For example, use Avro Source, File Channel, and HDFS Sink, as shown in [Figure 5-3](#).

**Figure 5-3** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by referring to [Table 5-29](#) based on the actual environment.

**NOTE**

- If the server parameters of the Flume role have been configured, you can choose **Cluster > Services > Flume > Instance** on FusionInsight Manager. Then select the corresponding Flume role instance and click the **Download** button behind the **flume.config.file** parameter on the **Instance Configurations** page to obtain the existing server parameter configuration file. Choose **Cluster > Service > Flume > Configurations > Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
  - A unique checkpoint directory needs to be configured for each File Channel.
- d. Click **Export** to save the **properties.properties** configuration file to the local server.

**Table 5-29** Parameters to be modified of the Flume role server

Parameter	Description	Example Value
ssl	<p>Specifies whether to enable the SSL authentication. (You are advised to enable this function to ensure security.)</p> <p>Only Sources of the Avro type have this configuration item.</p> <ul style="list-style-type: none"> <li>▪ <b>true</b> indicates that the function is enabled.</li> <li>▪ <b>false</b> indicates that the function is not enabled.</li> </ul>	false

2. Log in to FusionInsight Manager and choose **Cluster > Services > Flume**. On the **Instances** tab page, click **Flume**.
3. Select the Flume role of the node where the configuration file is to be uploaded, choose **Instance Configurations > Import** beside the **flume.config.file**, and select the **properties.properties** file.

 **NOTE**

- An independent server configuration file can be uploaded to each Flume instance.
  - This step is required for updating the configuration file. Modifying the configuration file on the background is an improper operation because the modification will be overwritten after configuration synchronization.
4. Click **Save**, and then click **OK**.
  5. Click **Finish**.

----End

## 5.10.2 Typical Scenario: Collecting Local Static Logs and Uploading Them to Kafka

### Scenario

This section describes how to use Flume client to collect static logs from a local host and save them to the topic list (test1) of Kafka.

 **NOTE**

By default, the cluster network environment is secure and the SSL authentication is not enabled during the data transmission process. For details about how to use the encryption mode, see [Configuring the Encrypted Transmission](#). The configuration applies to scenarios where only the Flume is configured, for example, Spooldir Source+Memory Channel+Kafka Sink.

### Prerequisites

- The cluster, Kafka, and Flume service have been installed.
- The Flume client has been installed. For details about how to install the client, see [Installing the Flume Client on Clusters](#).
- The network environment of the cluster is secure.
- The system administrator has understood service requirements and prepared Kafka administrator **flume\_kafka**.

### Procedure


#### Step 1 Set Flume parameters.

Use the Flume configuration tool on Manager to configure the Flume role client parameters and generate a configuration file.

1. Log in to FusionInsight Manager. Choose **Cluster > Services > Flume > Configuration Tool**.
2. Set **Agent Name** to **client**. Select and drag the source, channel, and sink to be used to the GUI on the right, and connect them.

Use SpoolDir Source, Memory Channel, and Kafka Sink.

**Figure 5-4** Example for the Flume configuration tool



3. Double-click the source, channel, and sink. Set corresponding configuration parameters by referring to **Table 5-30** based on the actual environment.

**NOTE**

- If you want to continue using the **properties.properties** file by modifying it, log in to FusionInsight Manager, choose **Cluster > Services**. On the page that is displayed, choose **Flume**. On the displayed page, click the **Configuration Tool** tab, click **Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
4. Click **Export** to save the **properties.properties** configuration file to the local server.

**Table 5-30** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test
spoolDir	Specifies the directory where the file to be collected resides. This parameter cannot be left blank. The directory needs to exist and have the write, read, and execute permissions on the flume running user.	/srv/BigData/hadoop/data1/zb
trackerDir	Specifies the path for storing the metadata of files collected by Flume.	/srv/BigData/hadoop/data1/tracker

Parameter	Description	Example Value
batchSize	Specifies the number of events that Flume sends in a batch (number of data pieces). A larger value indicates higher performance and lower timeliness.	61200
kafka.topics	Specifies the list of subscribed Kafka topics, which are separated by commas (.). This parameter cannot be left blank.	test1
kafka.bootstrap.servers	Specifies the bootstrap IP address and port list of Kafka. The default value is all Kafkabrokers in the Kafka cluster.	192.168.101.10:21007

**Step 2** Upload the configuration file.

Upload the file exported in [Step 1.4](#) to the *Flume client installation directory/fusioninsight-flume-Flume component version number/conf* directory of the cluster

**Step 3** Verify log transmission.

1. Log in to the Kafka client.

```
cd /Client installation directory/Kafka/kafka
kinit flume_kafka (Enter the password.)
```

2. Read data from a Kafka topic.

```
bin/kafka-console-consumer.sh --topic topic name --bootstrap-server Kafka service IP address of the node where the role instance is located: 21007 --consumer.config config/consumer.properties --from-beginning
```

The system displays the contents of the file to be collected.

```
[root@host1 kafka]# bin/kafka-console-consumer.sh --topic test1 --bootstrap-server 192.168.101.10:21007 --consumer.config config/consumer.properties --from-beginning
Welcome to flume
```

----End

## 5.10.3 Typical Scenario: Collecting Local Static Logs and Uploading Them to HDFS

### Scenario

This section describes how to use Flume client to collect static logs from a local PC and save them to the `/flume/test` directory on HDFS.

#### NOTE

By default, the cluster network environment is secure and the SSL authentication is not enabled during the data transmission process. For details about how to use the encryption mode, see [Configuring the Encrypted Transmission](#). The configuration applies to scenarios where only the Flume is configured, for example, SpoolDir Source+Memory Channel+HDFS Sink.

### Prerequisites

- The cluster, HDFS, and Flume service have been installed.
- The Flume client has been installed. For details about how to install the client, see [Installing the Flume Client on Clusters](#).
- The network environment of the cluster is secure.
- User `flume_hdfs` has been created, and the HDFS directory and data used for log verification have been authorized to the user.

### Procedure

**Step 1** On FusionInsight Manager, choose **System > Permission > User**, select user `flume_hdfs`, and choose **More > Download Authentication Credential** to download the Kerberos certificate file of user `flume_hdfs` and save it to the local host.


**Step 2** Set Flume parameters.

Use Flume on FusionInsight Manager to configure the Flume role client parameters and generate a configuration file.

1. Log in to FusionInsight Manager. Choose **Cluster > Services > Flume > Configuration Tool**.
2. Set **Agent Name** to `client`. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.

Use SpoolDir Source, Memory Channel, and HDFS Sink.

**Figure 5-5** Example for the Flume configuration tool



3. Double-click the source, channel, and sink. Set corresponding configuration parameters by referring to [Table 5-31](#) based on the actual environment.

 **NOTE**

- If you want to continue using the **properties.properties** file by modifying it, log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services**. On the page that is displayed, choose **Flume**. On the displayed page, click the **Configuration Tool** tab, click **Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
4. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-31** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test
spoolDir	Specifies the directory where the file to be collected resides. This parameter cannot be left blank. The directory needs to exist and have the write, read, and execute permissions on the flume running user.	/srv/BigData/hadoop/data1/zb
trackerDir	Specifies the path for storing the metadata of files collected by Flume.	/srv/BigData/hadoop/data1/tracker
batch-size	Specifies the number of events that Flume sends in a batch.	61200
hdfs.path	Specifies the HDFS data write directory. This parameter cannot be left blank.	hdfs://hacluster/flume/test
hdfs.inUsePrefix	Specifies the prefix of the file that is being written to HDFS.	TMP_
hdfs.batchSize	Specifies the maximum number of events that can be written to HDFS once.	61200

Parameter	Description	Example Value
hdfs.kerberosPrincipal	Specifies the Kerberos authentication user, which is mandatory in security versions. This configuration is required only in security clusters.	flume_hdfs
hdfs.kerberosKeytab	Specifies the keytab file path for Kerberos authentication, which is mandatory in security versions. This configuration is required only in security clusters.	/opt/test/conf/ user.keytab  <b>NOTE</b> Obtain the <b>user.keytab</b> file from the Kerberos certificate file of the user <b>flume_hdfs</b> . In addition, ensure that the user who installs and runs the Flume client has the read and write permissions on the <b>user.keytab</b> file.
hdfs.useLocalTimeStamp	Specifies whether to use the local time. Possible values are <b>true</b> and <b>false</b> .	true


**Step 3** Upload the configuration file.

Upload the file exported in [Step 2.4](#) to the *Flume client installation directory*/**fusioninsight-flume-Flume component version number**/conf directory of the cluster

**Step 4** Verify log transmission.

1. Log in to FusionInsight Manager as a user who has the management permission on HDFS. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > HDFS**. On the page that is displayed, click the **NameNode(Node name,Active)** link next to **NameNode WebUI** to go to the HDFS web UI. On the displayed page, choose **Utilities > Browse the file system**.
2. Check whether the data is generated in the **/flume/test** directory on the HDFS.

**Figure 5-6** Checking HDFS directories and files



----End

## 5.10.4 Typical Scenario: Collecting Local Dynamic Logs and Uploading Them to HDFS

### Scenario

This section describes how to use Flume client to collect dynamic logs from a local PC and save them to the `/flume/test` directory on HDFS.

#### NOTE

By default, the cluster network environment is secure and the SSL authentication is not enabled during the data transmission process. For details about how to use the encryption mode, see [Configuring the Encrypted Transmission](#). The configuration applies to scenarios where only the Flume is configured, for example, Taildir Source+Memory Channel+HDFS Sink.

### Prerequisites

- The cluster, HDFS, and Flume service have been installed.
- The Flume client has been installed. For details about how to install the client, see [Installing the Flume Client on Clusters](#).
- The network environment of the cluster is secure.
- You have created user `flume_hdfs` and authorized the HDFS directory and data to be operated during log verification. For details, see [Adding a Ranger Access Permission Policy for HDFS](#).

### Procedure


**Step 1** On FusionInsight Manager, choose **System > User** and choose **More > Download Authentication Credential** to download the Kerberos certificate file of user `flume_hdfs` and save it to the local host.

**Step 2** Set Flume parameters.

Use the Flume configuration tool on FusionInsight Manager to configure the Flume role client parameters and generate a configuration file.

1. Log in to FusionInsight Manager and choose **Cluster > Services**. On the page that is displayed, choose **Flume**. On the displayed page, click the **Configuration Tool** tab.
2. Set **Agent Name** to `client`. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.  
Use Taildir Source, Memory Channel, and HDFS Sink.

**Figure 5-7** Example for the Flume configuration tool



3. Double-click the source, channel, and sink. Refer to [Table 5-32](#) to set corresponding configuration parameters based on the actual environment.

 **NOTE**

- If you want to continue using the **properties.properties** file by modifying it, log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services**. On the page that is displayed, choose **Flume**. On the displayed page, click the **Configuration Tool** tab, click **Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
4. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-32** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test
filegroups	Specifies the file group list name. This parameter cannot be left blank. Values are separated by spaces	epgtest
positionFile	Specifies the location where the collected file information (file name and location from which the file collected) is saved. This parameter cannot be left blank. The file does not need to be created manually, but the Flume running user needs to have the write permission on its upper-level directory.	/home/omm/flume/ positionfile
batch-size	Specifies the number of events that Flume sends in a batch.	61200
hdfs.path	Specifies the HDFS data write directory. This parameter cannot be left blank.	hdfs://hacluster/flume/ test
hdfs.inUsePrefix	Specifies the prefix of the file that is being written to HDFS.	TMP_

Parameter	Description	Example Value
hdfs.batchSize	Specifies the maximum number of events that can be written to HDFS once.	61200
hdfs.kerberosPrincipal	Specifies the Kerberos authentication user, which is mandatory in security versions. This configuration is required only in security clusters.	flume_hdfs
hdfs.kerberosKeytab	Specifies the keytab file path for Kerberos authentication, which is mandatory in security versions. This configuration is required only in security clusters.	/opt/test/conf/ user.keytab  <b>NOTE</b> Obtain the <b>user.keytab</b> file from the Kerberos certificate file of the user <b>flume_hdfs</b> . In addition, ensure that the user who installs and runs the Flume client has the read and write permissions on the <b>user.keytab</b> file.
hdfs.useLocalTimeStamp	Specifies whether to use the local time. Possible values are <b>true</b> and <b>false</b> .	true


**Step 3** Upload the configuration file.

Upload the file exported in [Step 2.4](#) to the *Flume client installation directory/fusioninsight-flume-Flume component version number/conf* directory of the cluster

**Step 4** Verify log transmission.

1. Log in to FusionInsight Manager as a user who has the management permission on HDFS. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > HDFS**. On the page that is displayed, click the **NameNode(Node name,Active)** link next to **NameNode WebUI** to go to the HDFS web UI. On the displayed page, choose **Utilities > Browse the file system**.
2. Check whether the data is generated in the **/flume/test** directory on the HDFS.

**Figure 5-8** Checking HDFS directories and files



----End

## 5.10.5 Typical Scenario: Collecting Logs from Kafka and Uploading Them to HDFS

### Scenario

This section describes how to use Flume client to collect logs from the Topic list (test1) of Kafka and save them to the **/flume/test** directory on HDFS.

#### NOTE

By default, the cluster network environment is secure and the SSL authentication is not enabled during the data transmission process. For details about how to use the encryption mode, see [Configuring the Encrypted Transmission](#). The configuration applies to scenarios where only the Flume is configured, for example, Kafka Source+Memory Channel+HDFS Sink.

### Prerequisites

- The cluster, HDFS, Kafka, and Flume service have been installed.
- The Flume client has been installed. For details about how to install the client, see [Installing the Flume Client on Clusters](#).
- The network environment of the cluster is secure.
- You have created user **flume\_hdfs** and authorized the HDFS directory and data to be operated during log verification. For details, see [Adding a Ranger Access Permission Policy for HDFS](#).

### Procedure

**Step 1** On FusionInsight Manager, choose **System > User** and choose **More > Download Authentication Credential** to download the Kerberos certificate file of user **flume\_hdfs** and save it to the local host.


**Step 2** Configure the client parameters of the Flume role.

Use the Flume configuration tool on FusionInsight Manager to configure the Flume role client parameters and generate a configuration file.

1. Log in to FusionInsight Manager and choose **Cluster > Services**. On the page that is displayed, choose **Flume**. On the displayed page, click the **Configuration Tool** tab.
2. Set **Agent Name** to **client**. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.

For example, use Kafka Source, Memory Channel, and HDFS Sink.

**Figure 5-9** Example for the Flume configuration tool



3. Double-click the source, channel, and sink. Set corresponding configuration parameters by seeing [Table 5-33](#) based on the actual environment.

**NOTE**

- If you want to continue using the **properties.properties** file by modifying it, log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services**. On the page that is displayed, choose **Flume**. On the displayed page, click the **Configuration Tool** tab, click **Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
4. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-33** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test
kafka.topics	Specifies the subscribed Kafka topic list, in which topics are separated by commas (.). This parameter cannot be left blank.	test1
kafka.consumer.group.id	Specifies the data group ID obtained from Kafka. This parameter cannot be left blank.	flume
kafka.bootstrap.servers	Specifies the bootstrap IP address and port list of Kafka. The default value is all Kafka lists in a Kafka cluster. If Kafka has been installed in the cluster and its configurations have been synchronized, this parameter can be left blank.	192.168.101.10:9092

Parameter	Description	Example Value
batchSize	Specifies the number of events that Flume sends in a batch (number of data pieces).	61200
hdfs.path	Specifies the HDFS data write directory. This parameter cannot be left blank.	hdfs://hacluster/flume/test
hdfs.inUsePrefix	Specifies the prefix of the file that is being written to HDFS.	TMP_
hdfs.batchSize	Specifies the maximum number of events that can be written to HDFS once.	61200
hdfs.kerberosPrincipal	Specifies the Kerberos authentication user, which is mandatory in security versions. This configuration is required only in security clusters.	flume_hdfs
hdfs.kerberosKeytab	Specifies the keytab file path for Kerberos authentication, which is mandatory in security versions. This configuration is required only in security clusters.	/opt/test/conf/user.keytab <b>NOTE</b> Obtain the <b>user.keytab</b> file from the Kerberos certificate file of the user <b>flume_hdfs</b> . In addition, ensure that the user who installs and runs the Flume client has the read and write permissions on the <b>user.keytab</b> file.
hdfs.useLocalTimestamp	Specifies whether to use the local time. Possible values are <b>true</b> and <b>false</b> .	true


**Step 3** Upload the configuration file.

Upload the file exported in [Step 2.4](#) to the *Flume client installation directory*/**fusioninsight-flume-Flume component version number**/conf directory of the cluster

**Step 4** Verify log transmission.

1. Log in to FusionInsight Manager as a user who has the management permission on HDFS. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > HDFS**. On the page that is displayed, click the **NameNode(Node name,Active)** link next to **NameNode WebUI** to go to the HDFS web UI. On the displayed page, choose **Utilities > Browse the file system**.
2. Check whether the data is generated in the **/flume/test** directory on the HDFS.

**Figure 5-10** Checking HDFS directories and files



----End

## 5.10.6 Typical Scenario: Collecting Logs from Kafka and Uploading Them to HDFS Through the Flume Client

### Scenario

This section describes how to use Flume client to collect logs from the Topic list (test1) of Kafka client and save them to the **/flume/test** directory on HDFS.

#### NOTE

By default, the cluster network environment is secure and the SSL authentication is not enabled during the data transmission process. For details about how to use the encryption mode, see [Configuring the Encrypted Transmission](#).

### Prerequisites

- The cluster, HDFS, Kafka, and Flume service have been installed.
- The Flume client has been installed. For details about how to install the client, see [Installing the Flume Client on Clusters](#).
- You have created user **flume\_hdfs** and authorized the HDFS directory and data to be operated during log verification. For details, see [Adding a Ranger Access Permission Policy for HDFS](#).
- The network environment of the cluster is secure.


### Procedure

- Step 1** On FusionInsight Manager, choose **System > User** and choose **More > Download Authentication Credential** to download the Kerberos certificate file of user **flume\_hdfs** and save it to the local host.
- Step 2** Configure the client parameters of the Flume role.
  1. Use the Flume configuration tool on FusionInsight Manager to configure the Flume role client parameters and generate a configuration file.

- a. Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume** > **Configuration Tool**.
- b. Set **Agent Name** to **client**. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.

For example, use Kafka Source, File Channel, and HDFS Sink, as shown in [Figure 5-11](#).

**Figure 5-11** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by seeing [Table 5-34](#) based on the actual environment.

**NOTE**

- If the client parameters of the Flume role have been configured, you can obtain the existing client parameter configuration file from *client installation directory/fusioninsight-flume-1.9.0/conf/properties.properties* to ensure that the configuration is in concordance with the previous. Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume** > **Configuration Tool** > **Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
- d. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-34** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test
kafka.topics	Specifies the subscribed Kafka topic list, in which topics are separated by commas (,). This parameter cannot be left blank.	test1

Parameter	Description	Example Value
kafka.consumer.group.id	Specifies the data group ID obtained from Kafka. This parameter cannot be left blank.	flume
kafka.bootstrap.servers	Specifies the bootstrap IP address and port list of Kafka. The default value is all Kafka lists in a Kafka cluster. If Kafka has been installed in the cluster and its configurations have been synchronized, this parameter can be left blank.	192.168.101.10:21007
batchSize	Specifies the number of events that Flume sends in a batch (number of data pieces).	61200
dataDirs	Specifies the directory for storing buffer data. The run directory is used by default. Configuring multiple directories on disks can improve transmission efficiency. Use commas (,) to separate multiple directories. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/data</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.	/srv/BigData/hadoop/data1/flume/data

Parameter	Description	Example Value
checkpointDir	Specifies the directory for storing the checkpoint information, which is under the run directory by default. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/checkpoint</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.	/srv/BigData/hadoop/data1/flume/checkpoint
transactionCapacity	Specifies the transaction size, that is, the number of events in a transaction that can be processed by the current Channel. The size cannot be smaller than the batchSize of Source. Setting the same size as batchSize is recommended.	61200
hdfs.path	Specifies the HDFS data write directory. This parameter cannot be left blank.	hdfs://hacluster/flume/test
hdfs.inUsePrefix	Specifies the prefix of the file that is being written to HDFS.	TMP_
hdfs.batchSize	Specifies the maximum number of events that can be written to HDFS once.	61200

Parameter	Description	Example Value
hdfs.kerberosPrincipal	Specifies the Kerberos authentication user, which is mandatory in security versions. This configuration is required only in security clusters.	flume_hdfs
hdfs.kerberosKeytab	Specifies the keytab file path for Kerberos authentication, which is mandatory in security versions. This configuration is required only in security clusters.	/opt/test/conf/ user.keytab  <b>NOTE</b> Obtain the <b>user.keytab</b> file from the Kerberos certificate file of the user <b>flume_hdfs</b> . In addition, ensure that the user who installs and runs the Flume client has the read and write permissions on the <b>user.keytab</b> file.
hdfs.useLocalTimeStamp	Specifies whether to use the local time. Possible values are <b>true</b> and <b>false</b> .	true

2. Upload the **properties.properties** file to **flume/conf/** under the installation directory of the Flume client.
3. To connect the Flume client to the HDFS, you need to add the following configuration:
  - a. Download the Kerberos certificate of account **flume\_hdfs** and obtain the **krb5.conf** configuration file. Upload the configuration file to the **fusioninsight-flume-1.9.0/conf/** directory on the node where the client is installed.
  - b. In **fusioninsight-flume-1.9.0/conf/**, create the **jaas.conf** configuration file.

**vi jaas.conf**

```
KafkaClient {
com.sun.security.auth.module.Krb5LoginModule required
useKeyTab=true
keyTab="/opt/test/conf/user.keytab"
principal="flume_hdfs@<System domain name>"
useTicketCache=false
storeKey=true
debug=true;
};
```

Values of **keyTab** and **principal** vary depending on the actual situation.


- c. Obtain configuration files **core-site.xml** and **hdfs-site.xml** from **/opt/FusionInsight\_Cluster\_<Cluster ID>\_Flume\_ClientConfig/Flume/config** and upload them to **fusioninsight-flume-1.9.0/conf/**.

- Restart the Flume service.  
**flume-manager.sh restart**

**Step 3** Verify log transmission.

- Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Name of the desired cluster > Services > HDFS**, click the HDFS WebUI link of **NameNode (Node name, Active)** to go to the HDFS WebUI, and choose **Utilities > Browse the file system**.
- Check whether the data is generated in the **/flume/test** directory on the HDFS.

**Figure 5-12** Checking HDFS directories and files



----End

## 5.10.7 Typical Scenario: Collecting Local Static Logs and Uploading Them to HBase

### Scenario

This section describes how to use Flume client to collect static logs from a local computer and upload them to the **flume\_test** table of HBase.

**NOTE**

By default, the cluster network environment is secure and the SSL authentication is not enabled during the data transmission process. For details about how to use the encryption mode, see [Configuring the Encrypted Transmission](#). The configuration can apply to scenarios where only the client or the server is configured, for example, Client/Server:Spooldir Source+File Channel+HBase Sink.

### Prerequisites

- The cluster, HBase, and Flume service have been installed.
- The Flume client has been installed. For details about how to install the client, see [Installing the Flume Client on Clusters](#).
- The network environment of the cluster is secure.
- An HBase table has been created by running the **create 'flume\_test', 'cf'** command.
- The system administrator has understood service requirements and prepared HBase administrator **flume\_hbase**.

## Procedure

**Step 1** On FusionInsight Manager, choose **System > User** and choose **More > Download Authentication Credential** to download the Kerberos certificate file of user **flume\_hbase** and save it to the local host.

**Step 2** Configure the client parameters of the Flume role.

1. Use the Flume configuration tool on FusionInsight Manager to configure the Flume role client parameters and generate a configuration file.
  - a. Log in to FusionInsight Manager and choose **Cluster > Name of the desired cluster > Services > Flume > Configuration Tool**.
  - b. Set **Agent Name** to **client**. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them. Use SpoolDir Source, File Channel, and Avro Sink, as shown in [Figure 5-13](#).

**Figure 5-13** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by seeing [Table 5-35](#) based on the actual environment.

### NOTE

- If the client parameters of the Flume role have been configured, you can obtain the existing client parameter configuration file from *client installation directory/fusioninsight-flume-1.9.0/conf/properties.properties* to ensure that the configuration is in concordance with the previous. Log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > Flume > Configuration Tool > Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
- d. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-35** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test

Parameter	Description	Example Value
spoolDir	Specifies the directory where the file to be collected resides. This parameter cannot be left blank. The directory needs to exist and have the write, read, and execute permissions on the flume running user.	/srv/BigData/hadoop/data1/zb
trackerDir	Specifies the path for storing the metadata of files collected by Flume.	/srv/BigData/hadoop/data1/tracker
batchSize	Specifies the number of events that Flume sends in a batch (number of data pieces). A larger value indicates higher performance and lower timeliness.	61200
dataDirs	Specifies the directory for storing buffer data. The run directory is used by default. Configuring multiple directories on disks can improve transmission efficiency. Use commas (,) to separate multiple directories. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/data</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.	/srv/BigData/hadoop/data1/flume/data

Parameter	Description	Example Value
checkpointDir	Specifies the directory for storing the checkpoint information, which is under the run directory by default. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/checkpoint</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.	/srv/BigData/hadoop/data1/flume/checkpoint
transactionCapacity	Specifies the transaction size, that is, the number of events in a transaction that can be processed by the current Channel. The size cannot be smaller than the batchSize of Source. Setting the same size as batchSize is recommended.	61200
hostname	Specifies the name or IP address of the host whose data is to be sent. This parameter cannot be left blank. Name or IP address must be configured to be the name or IP address that the Avro source associated with it.	192.168.108.11

Parameter	Description	Example Value
port	Specifies the port that sends the data. This parameter cannot be left blank. It must be consistent with the port that is monitored by the connected Avro Source.	21154
ssl	Specifies whether to enable the SSL authentication. (You are advised to enable this function to ensure security.) Only Sources of the Avro type have this configuration item. <ul style="list-style-type: none"> <li>▪ <b>true</b> indicates that the function is enabled.</li> <li>▪ <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	false

2. Upload the **properties.properties** file to **flume/conf/** under the installation directory of the Flume client.

**Step 3** Configure the server parameters of the Flume role and upload the configuration file to the cluster.

1. Use the Flume configuration tool on the FusionInsight Manager portal to configure the server parameters and generate the configuration file.
  - a. Log in to FusionInsight Manager and choose **Cluster > Name of the desired cluster > Services > Flume > Configuration Tool**.
  - b. Set **Agent Name** to **server**. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.  
For example, use Avro Source, File Channel, and HBase Sink, as shown in [Figure 5-14](#).

**Figure 5-14** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by seeing [Table 5-36](#) based on the actual environment.

 NOTE

- If the server parameters of the Flume role have been configured, you can choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume** > **Instance** on FusionInsight Manager. Then select the corresponding Flume role instance and click the **Download** button behind the **flume.config.file** parameter on the **Instance Configurations** page to obtain the existing server parameter configuration file. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume** > **Configuration Tool** > **Import**, import the file, and modify the configuration items related to non-encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
  - A unique checkpoint directory needs to be configured for each File Channel.
- d. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-36** Parameters to be modified of the Flume role server

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test
bind	Specifies the IP address to which Avro Source is bound. This parameter cannot be left blank. It must be configured as the IP address that the server configuration file will upload.	192.168.108.11
port	Specifies the ID of the port that the Avro Source monitors. This parameter cannot be left blank. It must be configured as an unused port.	21154
ssl	Specifies whether to enable the SSL authentication. (You are advised to enable this function to ensure security.) Only Sources of the Avro type have this configuration item. <ul style="list-style-type: none"> <li>▪ <b>true</b> indicates that the function is enabled.</li> <li>▪ <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	false

Parameter	Description	Example Value
dataDirs	Specifies the directory for storing buffer data. The run directory is used by default. Configuring multiple directories on disks can improve transmission efficiency. Use commas (,) to separate multiple directories. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/data</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.	/srv/BigData/hadoop/data1/flumeserver/data
checkpointDir	Specifies the directory for storing the checkpoint information, which is under the run directory by default. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/checkpoint</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.	/srv/BigData/hadoop/data1/flumeserver/checkpoint
transactionCapacity	Specifies the transaction size, that is, the number of events in a transaction that can be processed by the current Channel. The size cannot be smaller than the batchSize of Source. Setting the same size as batchSize is recommended.	61200
table	Specifies the HBase table name. This parameter cannot be left blank.	flume_test
columnFamily	Specifies the HBase column family name. This parameter cannot be left blank.	cf
batchSize	Specifies the maximum number of events written to HBase by Flume in a batch.	61200

Parameter	Description	Example Value
kerberosPrincipal	Specifies the Kerberos authentication user, which is mandatory in security versions. This configuration is required only in security clusters.	flume_hbase
kerberosKeytab	Specifies the file path for Kerberos authentication, which is mandatory in security versions. This configuration is required only in security clusters.	/opt/test/conf/user.keytab <b>NOTE</b> Obtain the <b>user.keytab</b> file from the Kerberos certificate file of the user <b>flume_hbase</b> . In addition, ensure that the user who installs and runs the Flume client has the read and write permissions on the <b>user.keytab</b> file.

2. Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume**. On the displayed page, click the **Flume** role on the **Instance** tab page.
3. Select the Flume role of the node where the configuration file is to be uploaded, choose **Instance Configurations** > **Import** beside the **flume.config.file**, and select the **properties.properties** file.

 **NOTE**

- An independent server configuration file can be uploaded to each Flume instance.
  - This step is required for updating the configuration file. Modifying the configuration file on the background is an improper operation because the modification will be overwritten after configuration synchronization.
4. Click **Save**, and then click **OK**.
  5. Click **Finish**.

**Step 4** Verify log transmission.

1. Go to the directory where the HBase client is installed.  
**cd /Client installation directory/ HBase/hbase**  
**kinit flume\_hbase** (Enter the password.)
2. Run the **hbase shell** command to access the HBase client.
3. Run the **scan 'flume\_test'** statement. Logs are written in the HBase column family by line.

```
hbase(main):001:0> scan 'flume_test'
ROW                               COLUMN
+CELL

2017-09-18 16:05:36,394 INFO [hconnection-0x415a3f6a-shared--pool2-t1] ipc.AbstractRpcClient:
RPC Server Kerberos principal name for service=ClientService is hbase/hadoop.<system domain
name>@<system domain name>
```

```
default4021ff4a-9339-4151-a4d0-00f20807e76d      column=cf:pCol,  
timestamp=1505721909388, value=Welcome to  
flume  
incRow      column=cf:iCol, timestamp=1505721909461, value=  
\x00\x00\x00\x00\x00\x00\x00\x00\x01  
2 row(s) in 0.3660 seconds
```

----End

## 5.11 Encrypted Transmission

### 5.11.1 Configuring the Encrypted Transmission

#### Scenario

This section describes how to configure the server and client parameters of the Flume service (including the Flume and MonitorServer roles) after the cluster is installed to ensure proper running of the service.

#### Prerequisites

The cluster and Flume service have been installed.

#### Procedure

**Step 1** Generate the certificate trust lists of the server and client of the Flume role respectively.

1. Remotely log in to the node using ECM where the Flume server is to be installed as user **omm**. Go to the **\${BIGDATA\_HOME}/FusionInsight\_Porter\_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin** directory.

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin
```

#### NOTE

The version 8.1.2.2 is used as an example. Replace it with the actual version number.

2. Run the following command to generate and export the server and client certificates of the Flume role:

```
sh geneJKS.sh -f sNetty12@ -g cNetty12@
```

The generated certificate is saved in the **\${BIGDATA\_HOME}/FusionInsight\_Porter\_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf** path .

- **flume\_sChat.jks** is the certificate library of the Flume role server.  
**flume\_sChat.crt** is the exported file of the **flume\_sChat.jks** certificate. **-f** indicates the password of the certificate and certificate library.
- **flume\_cChat.jks** is the certificate library of the Flume role client.  
**flume\_cChat.crt** is the exported file of the **flume\_cChat.jks** certificate. **-g** indicates the password of the certificate and certificate library.
- **flume\_sChatt.jks** and **flume\_cChatt.jks** are the SSL certificate trust lists of the Flume server and client, respectively.

 **NOTE**

All user-defined passwords involved in this section (such as *sNetty12@*) must meet the following requirements:

- The password must contain at least four types of uppercase letters, lowercase letters, digits, and special characters.
- The password must contain 8 to 64 characters.
- It is recommended that the user-defined passwords be changed periodically (for example, every three months), and certificates and trust lists be generated again to ensure security.

**Step 2** Configure the server parameters of the Flume role and upload the configuration file to the cluster.

1. Remotely log in to any node where the Flume role is located as user **omm** using ECM. Run the following command to go to the `/${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin` directory:

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin
```

2. Run the following command to generate and obtain Flume server keystore password, trust list password, and keystore-password encrypted private key information. Enter the password twice and confirm the password. It is the password of the **flume\_sChat.jks** certificate library, for example, *sNetty12@*.

```
./genPwFile.sh
```


```
cat password.property
```

```
password=D03C2D03D97CBA3F4FD2491A40CAA5E0
```

3. Use the Flume configuration tool on the FusionInsight Manager portal to configure the server parameters and generate the configuration file.
  - a. Log in to FusionInsight Manager. Choose **Services > Flume > Configuration Tool**.
  - b. Set **Agent Name** to **server**. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.

For example, use Avro Source, File Channel, and HDFS Sink, as shown in [Figure 5-15](#).

**Figure 5-15** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by seeing [Table 5-37](#) based on the actual environment.

 NOTE

- If the server parameters of the Flume role have been configured, you can choose **Services > Flume > Instance** on FusionInsight Manager. Then select the corresponding Flume role instance and click the **Download** button behind the **flume.config.file** parameter on the **Instance Configurations** page to obtain the existing server parameter configuration file. Choose **Services > Flume > Import** to change the relevant configuration items of encrypted transmission after the file is imported.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
- d. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-37** Parameters to be modified of the Flume role server

Parameter	Description	Example Value
ssl	Specifies whether to enable the SSL authentication. (You are advised to enable this function to ensure security.) <ul style="list-style-type: none"> <li>▪ <b>true</b> indicates that the function is enabled.</li> <li>▪ <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true
keystore	Indicates the server certificate.	\${BIGDATA_HOME}/ FusionInsight_Porter _8.1.2.2/install/ FusionInsight- Flume-1.9.0/flume/ conf/flume_sChat.jks
keystore-password	Specifies the password of the key library, which is the password required to obtain the keystore information. Enter the value of password obtained in <a href="#">Step 2.2</a> .	D03C2D03D97CBA3 F4FD2491A40CAA5E 0
truststore	Indicates the SSL certificate trust list of the server.	\${BIGDATA_HOME}/ FusionInsight_Porter _8.1.2.2/install/ FusionInsight- Flume-1.9.0/flume/ conf/ flume_sChatt.jks

Parameter	Description	Example Value
truststore-password	Specifies the trust list password, which is the password required to obtain the truststore information.  Enter the value of password obtained in <a href="#">Step 2.2</a> .	D03C2D03D97CBA3 F4FD2491A40CAA5E 0

- Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume**. On the displayed page, click the **Flume** role under **Role**.
- Select the Flume role of the node where the configuration file is to be uploaded, choose **Instance Configurations** > **Import** beside the **flume.config.file**, and select the **properties.properties** file.

 **NOTE**

- An independent server configuration file can be uploaded to each Flume instance.
  - This step is required for updating the configuration file. Modifying the configuration file on the background is an improper operation because the modification will be overwritten after configuration synchronization.
- Click **Save**, and then click **OK**. Click **Finish**.

**Step 3** Set the client parameters of the Flume role.

- Run the following commands to copy the generated client certificate (**flume\_cChat.jks**) and client trust list (**flume\_cChatt.jks**) to the client directory, for example, **/opt/flume-client/fusionInsight-flume-1.9.0/conf/**. (The Flume client must have been installed.) **10.196.26.1** is the service plane IP address of the node where the client resides.

```
scp ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/flume_cChat.jks user@10.196.26.1:/opt/flume-client/fusionInsight-flume-1.9.0/conf/
```

```
scp ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/flume_cChatt.jks user@10.196.26.1:/opt/flume-client/fusionInsight-flume-1.9.0/conf/
```

 **NOTE**

- When copying the client certificate, you need to enter the password of user **user** of the host (for example, **10.196.26.1**) where the client resides.
- Log in to the node where the Flume client is decompressed as user **user**. Run the following command to go to the client directory **opt/flume-client/fusionInsight-flume-1.9.0/bin**.  
**cd opt/flume-client/fusionInsight-flume-1.9.0/bin**
  - Run the following command to generate and obtain Flume client keystore password, trust list password, and keystore-password encrypted private key information. Enter the password twice and confirm the password. The password is the same as the password of the certificate whose alias is *flumechatclient* and the password of the *flume\_cChat.jks* certificate library, for example *cNetty12@*.

```
./genPwFile.sh
```

```
cat password.property
```

```
password=4FD2491A40CAA5E0D03C2D03D97CBA3F
```

**NOTE**

If the following error message is displayed, run the export `JAVA_HOME=JDK path` command.

```
JAVA_HOME is null in current user,please install the JDK and set the JAVA_HOME
```

4. Use the Flume configuration tool on FusionInsight Manager to configure the Flume role client parameters and generate a configuration file.
  - a. Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume** > **Configuration Tool**.
  - b. Set **Agent Name** to **client**. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.  
For example, use SpoolDir Source, File Channel, and Avro Sink, as shown in [Figure 5-16](#).

**Figure 5-16** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by seeing [Table 5-38](#) based on the actual environment.

**NOTE**

- If the client parameters of the Flume role have been configured, you can obtain the existing client parameter configuration file from `client installation directory/fusioninsight-flume-1.9.0/conf/properties.properties` to ensure that the configuration is in concordance with the previous. Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume** > **Configuration Tool** > **Import**, import the file, and modify the configuration items related to encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
  - A unique checkpoint directory needs to be configured for each File Channel.
- d. Click **Export** to save the `properties.properties` configuration file to the local.

**Table 5-38** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
ssl	<p>Indicates whether to enable the SSL authentication. (You are advised to enable this function to ensure security.)</p> <ul style="list-style-type: none"> <li>▪ <b>true</b> indicates that the function is enabled.</li> <li>▪ <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true
keystore	Specified the client certificate.	/opt/flume-client/fusionInsight-flume-1.9.0/conf/flume_cChat.jks
keystore-password	<p>Specifies the password of the key library, which is the password required to obtain the keystore information.</p> <p>Enter the value of password obtained in <a href="#">Step 3.3</a>.</p>	4FD2491A40CAA5E0D03C2D03D97CBA3F
truststore	Indicates the SSL certificate trust list of the client.	/opt/flume-client/fusionInsight-flume-1.9.0/conf/flume_cChatt.jks
truststore-password	<p>Specifies the trust list password, which is the password required to obtain the truststore information.</p> <p>Enter the value of password obtained in <a href="#">Step 3.3</a>.</p>	4FD2491A40CAA5E0D03C2D03D97CBA3F

5. Upload the **properties.properties** file to **flume/conf/** under the installation directory of the Flume client.

**Step 4** Generate the certificate and trust list of the server and client of the MonitorServer role respectively.

1. Log in to the host using ECM with the MonitorServer role assigned as user **omm**.

Go to the `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin` directory.

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin
```

2. Run the following command to generate and export the server and client certificates of the MonitorServer role:

```
sh geneJKS.sh -m sKitty12@ -n cKitty12@
```

The generated certificate is saved in the `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf` path. Where:

- **ms\_sChat.jks** is the certificate library of the MonitorServer role server. **ms\_sChat.crt** is the exported file of the **ms\_sChat.jks** certificate. **-m** indicates the password of the certificate and certificate library.
- **ms\_cChat.jks** is the certificate library of the MonitorServer role client. **ms\_cChat.crt** is the exported file of the **ms\_cChat.jks** certificate. **-n** indicates the password of the certificate and certificate library.
- **ms\_sChatt.jks** and **ms\_cChatt.jks** are the SSL certificate trust lists of the MonitorServer server and client, respectively.

**Step 5** Set the server parameters of the MonitorServer role.

1. Run the following command to generate and obtain MonitorServer server keystore password, trust list password, and keystore-password encrypted private key information. Enter the password twice and confirm the password. The password is the same as the password of the certificate whose alias is *mschatserver* and the password of the *ms\_sChat.jks* certificate library, for example *sKitty12@*.

```
./genPwFile.sh
```

```
cat password.property
```

```
password=AA5E0D03C2D4FD24CBA3F91A40C03D97
```

2. Run the following command to open the `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/service/application.properties` file: Modify related parameters based on the description in [Table 5-39](#), save the modification, and exit.

```
vi ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/service/application.properties
```

**Table 5-39** Parameters to be modified of the MonitorServer role server

Parameter	Description	Example Value
ssl_need_kspas swd_decrypt_k ey	Specifies whether to enable the user-defined key encryption and decryption function. (You are advised to enable this function to ensure security.)  <ul style="list-style-type: none"> <li>- <b>true</b> indicates that the function is enabled.</li> <li>- <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true
ssl_server_enab le	Indicates whether to enable the SSL authentication. (You are advised to enable this function to ensure security.)  <ul style="list-style-type: none"> <li>- <b>true</b> indicates that the function is enabled.</li> <li>- <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true
ssl_server_key_ store	Set this parameter based on the specific storage location.	\${BIGDATA_HOME}/ FusionInsight_Porter_8.1.2.2 /install/FusionInsight- Flume-1.9.0/flume/conf/ ms_sChat.jks
ssl_server_trust _key_store	Set this parameter based on the specific storage location.	\${BIGDATA_HOME}/ FusionInsight_Porter_8.1.2.2 /install/FusionInsight- Flume-1.9.0/flume/conf/ ms_sChatt.jks
ssl_server_key_ store_password	Indicates the client certificate password. Set this parameter based on the actual situation of certificate creation (the plaintext key used to generate the certificate).  Enter the value of password obtained in <a href="#">Step 5.1</a> .	AA5E0D03C2D4FD24CBA3F 91A40C03D97

Parameter	Description	Example Value
ssl_server_trust_key_store_password	Specifies the trustkeystore password. Set this parameter based on the actual situation of certificate creation (the plaintext key used to generate the trust list). Enter the value of password obtained in <a href="#">Step 5.1</a> .	AA5E0D03C2D4FD24CBA3F91A40C03D97
ssl_need_client_auth	Indicates whether to enable the client authentication. (You are advised to enable this function to ensure security.) <ul style="list-style-type: none"> <li>- <b>true</b> indicates that the function is enabled.</li> <li>- <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true

- Restart the MonitorServer instance. Choose **Services > Flume > Instance > MonitorServer**, select the MonitorServer instance, and choose **More > Restart Instance**. Enter the administrator password and click **OK**. After the restart is complete, click **Finish**.

**Step 6** Set the client parameters of the MonitorServer role.

- Run the following commands to copy the generated client certificate (**ms\_cChat.jks**) and client trust list (**ms\_cChatt.jks**) to the **/opt/flume-client/fusionInsight-flume-1.9.0/conf/** client directory. **10.196.26.1** is the service plane IP address of the node where the client resides.  

```
scp ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/ms_cChat.jks user@10.196.26.1:/opt/flume-client/fusionInsight-flume-1.9.0/conf/
scp ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/ms_cChatt.jks user@10.196.26.1:/opt/flume-client/fusionInsight-flume-1.9.0/conf/
```
- Log in to the node where the Flume client is located as **user**. Run the following command to go to the client directory **/opt/flume-client/fusionInsight-flume-1.9.0/bin**.  

```
cd /opt/flume-client/fusionInsight-flume-1.9.0/bin
```
- Run the following command to generate and obtain MonitorServer client keystore password, trust list password, and keystore-password encrypted private key information. Enter the password twice and confirm the password. The password is the same as the password of the certificate whose alias is *mschatclient* and the password of the *ms\_cChat.jks* certificate library, for example *cKitty12@*.  

```
./genPwFile.sh
```

**cat password.property**

```
password=BA3F91A40C03D97AA5E0D03C2D4FD24C
```

4. Run the following command to open the `/opt/flume-client/fusionInsight-flume-1.9.0/conf/service/application.properties` file. (`/opt/flume-client/fusionInsight-flume-1.9.0` is the directory where the client software is installed.) Modify related parameters based on the description in [Table 5-40](#), save the modification, and exit.

```
vi /opt/flume-client/fusionInsight-flume-1.9.0/flume/conf/service/application.properties
```

**Table 5-40** Parameters to be modified of the MonitorServer role client

Parameter	Description	Example Value
ssl_need_kspas swd_decrypt_k ey	Indicates whether to enable the user-defined key encryption and decryption function. (You are advised to enable this function to ensure security.)  - <b>true</b> indicates that the function is enabled. - <b>false</b> indicates that the client authentication function is not enabled.	true
ssl_client_enab le	Indicates whether to enable the SSL authentication. (You are advised to enable this function to ensure security.)  - <b>true</b> indicates that the function is enabled. - <b>false</b> indicates that the client authentication function is not enabled.	true
ssl_client_key_s tore	Set this parameter based on the specific storage location.	<code>\${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/ms_cChat.jks</code>
ssl_client_trust _key_store	Set this parameter based on the specific storage location.	<code>\${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/ms_cChatt.jks</code>

Parameter	Description	Example Value
ssl_client_key_store_password	Specifies the keystore password. Set this parameter based on the actual situation of certificate creation (the plaintext key used to generate the certificate). Enter the value of <b>password</b> obtained in <a href="#">Step 6.3</a> .	BA3F91A40C03D97AA5E0D03C2D4FD24C
ssl_client_trust_key_store_password	Specifies the trustkeystore password. Set this parameter based on the actual situation of certificate creation (the plaintext key used to generate the trust list). Enter the value of <b>password</b> obtained in <a href="#">Step 6.3</a> .	BA3F91A40C03D97AA5E0D03C2D4FD24C
ssl_need_client_auth	Indicates whether to enable the client authentication. (You are advised to enable this function to ensure security.) <ul style="list-style-type: none"> <li>- <b>true</b> indicates that the function is enabled.</li> <li>- <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true

----End

## 5.11.2 Typical Scenario: Collecting Local Static Logs and Uploading Them to HDFS

### Scenario

This section describes how to use Flume client to collect static logs from a local PC and save them to the **/flume/test** directory on HDFS.

### Prerequisites

- The cluster, HDFS and Flume services, and Flume client have been installed.
- User **flume\_hdfs** has been created, and the HDFS directory and data used for log verification have been authorized to the user.

## Procedure

**Step 1** Generate the certificate trust lists of the server and client of the Flume role respectively.

1. Log in to the node where the Flume server is located as user **omm**. Go to the `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin` directory.

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin
```

2. Run the following command to generate and export the server and client certificates of the Flume role:

```
sh geneJKS.sh -f sNetty12@ -g cNetty12@
```

The generated certificate is saved in the `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf` path .

- **flume\_sChat.jks** is the certificate library of the Flume role server. **flume\_sChat.crt** is the exported file of the **flume\_sChat.jks** certificate. **-f** indicates the password of the certificate and certificate library.
- **flume\_cChat.jks** is the certificate library of the Flume role client. **flume\_cChat.crt** is the exported file of the **flume\_cChat.jks** certificate. **-g** indicates the password of the certificate and certificate library.
- **flume\_sChatt.jks** and **flume\_cChatt.jks** are the SSL certificate trust lists of the Flume server and client, respectively.

### NOTE

All user-defined passwords involved in this section (such as `sNetty12@`) must meet the following requirements:

- Contain at least four types of the following: uppercase letters, lowercase letters, digits, and special characters.
- Contain at least eight characters and a maximum of 64 characters.
- It is recommended that the user-defined passwords be changed periodically (for example, every three months), and certificates and trust lists be generated again to ensure security.

**Step 2** On FusionInsight Manager, choose **System > User** and choose **More > Download Authentication Credential** to download the Kerberos certificate file of user **flume\_hdfs** and save it to the local host.

**Step 3** Configure the server parameters of the Flume role and upload the configuration file to the cluster.

1. Log in to any node where the Flume role is located as user **omm**. Run the following command to go to the `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin` directory:

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin
```

2. Run the following command to generate and obtain Flume server keystore password, trust list password, and keystore-password encrypted private key information. Enter the password twice and confirm the password. It is the password of the **flume\_sChat.jks** certificate library, for example, `sNetty12@`.

**./genPwFile.sh**

**cat password.property**

```
password=D03C2D03D97CBA3F4FD2491A40CAA5E0
```

3. Use the Flume configuration tool on the FusionInsight Manager portal to configure the server parameters and generate the configuration file.
  - a. Log in to FusionInsight Manager and choose **Cluster > Name of the desired cluster > Services > Flume > Configuration Tool**.
  - b. Set **Agent Name** to **server**. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.  
For example, use Avro Source, File Channel, and HDFS Sink, as shown in [Figure 5-17](#).

**Figure 5-17** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by seeing [Table 5-41](#) based on the actual environment.

**NOTE**

- If the server parameters of the Flume role have been configured, you can choose **Cluster > Name of the desired cluster > Services > Flume > Instance** on FusionInsight Manager. Then select the corresponding Flume role instance and click the **Download** button behind the **flume.config.file** parameter on the **Instance Configurations** page to obtain the existing server parameter configuration file. Choose **Cluster > Name of the desired cluster > Services > Flume > Configuration Tool > Import**, import the file, and modify the configuration items related to encrypted transmission.
    - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
    - A unique checkpoint directory needs to be configured for each File Channel.
- d. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-41** Parameters to be modified of the Flume role server

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test

Parameter	Description	Example Value
bind	Specifies the IP address to which Avro Source is bound. This parameter cannot be left blank. It must be configured as the IP address that the server configuration file will upload.	192.168.108.11
port	Specifies the IP address to which Avro Source is bound. This parameter cannot be left blank. It must be configured as an unused port.	21154
ssl	Indicates whether to enable the SSL authentication. (You are advised to enable this function to ensure security.) Only Sources of the Avro type have this configuration item. <ul style="list-style-type: none"> <li>▪ <b>true</b> indicates that the function is enabled.</li> <li>▪ <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true
keystore	Indicates the server certificate.	<pre> \${BIGDATA_HOME}/ FusionInsight_Porter _8.1.2.2/install/ FusionInsight- Flume-1.9.0/flume/ conf/flume_sChat.jks </pre>
keystore- password	Specifies the password of the key library, which is the password required to obtain the keystore information. Enter the value of <b>password</b> obtained in <a href="#">Step 3.2</a> .	D03C2D03D97CBA3 F4FD2491A40CAA5E 0
truststore	Indicates the SSL certificate trust list of the server.	<pre> \${BIGDATA_HOME}/ FusionInsight_Porter _8.1.2.2/install/ FusionInsight- Flume-1.9.0/flume/ conf/ flume_sChatt.jks </pre>

Parameter	Description	Example Value
truststore-password	Specifies the trust list password, which is the password required to obtain the truststore information.  Enter the value of <b>password</b> obtained in <a href="#">Step 3.2</a> .	D03C2D03D97CBA3 F4FD2491A40CAA5E 0
dataDirs	Specifies the directory for storing buffer data. The run directory is used by default. Configuring multiple directories on disks can improve transmission efficiency. Use commas (,) to separate multiple directories. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/data</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.	/srv/BigData/ hadoop/data1/ flumeserver/data
checkpointDir	Specifies the directory for storing the checkpoint information, which is under the run directory by default. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/checkpoint</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.	/srv/BigData/ hadoop/data1/ flumeserver/ checkpoint
transactionCapacity	Specifies the transaction size, that is, the number of events in a transaction that can be processed by the current Channel. The size cannot be smaller than the batchSize of Source. Setting the same size as batchSize is recommended.	61200
hdfs.path	Specifies the HDFS data write directory. This parameter cannot be left blank.	hdfs://hacluster/ flume/test
hdfs.inUsePrefix	Specifies the prefix of the file that is being written to HDFS.	TMP_

Parameter	Description	Example Value
hdfs.batchSize	Specifies the maximum number of events that can be written to HDFS once.	61200
hdfs.kerberosPrincipal	Specifies the Kerberos authentication user, which is mandatory in security versions. This configuration is required only in security clusters.	flume_hdfs
hdfs.kerberosKeytab	Specifies the keytab file path for Kerberos authentication, which is mandatory in security versions. This configuration is required only in security clusters.	/opt/test/conf/user.keytab <b>NOTE</b> Obtain the <b>user.keytab</b> file from the Kerberos certificate file of the user <b>flume_hdfs</b> . In addition, ensure that the user who installs and runs the Flume client has the read and write permissions on the <b>user.keytab</b> file.
hdfs.useLocalTimeStamp	Specifies whether to use the local time. Possible values are <b>true</b> and <b>false</b> .	true

4. Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume**. On the displayed page, click the **Flume** role under **Role**.
5. Select the Flume role of the node where the configuration file is to be uploaded, choose **Instance Configurations** > **Import** beside the **flume.config.file**, and select the **properties.properties** file.

 **NOTE**

- An independent server configuration file can be uploaded to each Flume instance.
  - This step is required for updating the configuration file. Modifying the configuration file on the background is an improper operation because the modification will be overwritten after configuration synchronization.
6. Click **Save**, and then click **OK**.
  7. Click **Finish**.

**Step 4** Configure the client parameters of the Flume role.

1. Run the following commands to copy the generated client certificate (**flume\_cChat.jks**) and client trust list (**flume\_cChatt.jks**) to the client directory, for example, **/opt/flume-client/fusionInsight-flume-1.9.0/conf/**. (The Flume client must have been installed.) **10.196.26.1** is the service plane IP address of the node where the client resides.

```
scp ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/flume_cChat.jks user@10.196.26.1:/opt/flume-client/fusionInsight-flume-1.9.0/conf/
```

```
scp ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/flume_cChatt.jks user@10.196.26.1:/opt/flume-client/fusionInsight-flume-1.9.0/conf/
```

 NOTE

When copying the client certificate, you need to enter the password of user **user** of the host (for example, **10.196.26.1**) where the client resides.

2. Log in to the node where the Flume client is decompressed as user **user**. Run the following command to go to the client directory **/opt/flume-client/fusionInsight-flume-1.9.0/bin**.

```
cd opt/flume-client/fusionInsight-flume-1.9.0/bin
```

3. Run the following command to generate and obtain Flume client keystore password, trust list password, and keystore-password encrypted private key information. Enter the password twice and confirm the password. The password is the same as the password of the certificate whose alias is *flumechatclient* and the password of the *flume\_cChat.jks* certificate library, for example *cNetty12@*.

```
./genPwFile.sh
```

```
cat password.property
```

```
password=4FD2491A40CAA5E0D03C2D03D97CBA3F
```

 NOTE


If the following error message is displayed, run the export **JAVA\_HOME=JDKpath** command.

```
JAVA_HOME is null in current user,please install the JDK and set the JAVA_HOME
```

4. Use the Flume configuration tool on FusionInsight Manager to configure the Flume role client parameters and generate a configuration file.
  - a. Log in to FusionInsight Manager and choose **Cluster > Name of the desired cluster > Services > Flume > Configuration Tool**.
  - b. Set **Agent Name** to **client**. Select the source, channel, and sink to be used, drag them to the GUI on the right, and connect them.

Use SpoolDir Source, File Channel, and Avro Sink, as shown in [Figure 5-18](#).

**Figure 5-18** Example for the Flume configuration tool



- c. Double-click the source, channel, and sink. Set corresponding configuration parameters by seeing [Table 5-42](#) based on the actual environment.

 NOTE

- If the client parameters of the Flume role have been configured, you can obtain the existing client parameter configuration file from *client installation directory/fusioninsight-flume-1.9.0/conf/properties.properties* to ensure that the configuration is in concordance with the previous. Log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > Flume > Configuration Tool > Import**, import the file, and modify the configuration items related to encrypted transmission.
  - It is recommended that the numbers of Sources, Channels, and Sinks do not exceed 40 during configuration file import. Otherwise, the response time may be very long.
- d. Click **Export** to save the **properties.properties** configuration file to the local.

**Table 5-42** Parameters to be modified of the Flume role client

Parameter	Description	Example Value
Name	The value must be unique and cannot be left blank.	test
spoolDir	Specifies the directory where the file to be collected resides. This parameter cannot be left blank. The directory needs to exist and have the write, read, and execute permissions on the flume running user.	/srv/BigData/hadoop/data1/zb
trackerDir	Specifies the path for storing the metadata of files collected by Flume.	/srv/BigData/hadoop/data1/tracker
batch-size	Specifies the number of events that Flume sends in a batch.	61200

Parameter	Description	Example Value
dataDirs	<p>Specifies the directory for storing buffer data. The run directory is used by default. Configuring multiple directories on disks can improve transmission efficiency. Use commas (,) to separate multiple directories. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/data</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.</p>	/srv/BigData/hadoop/data1/flume/data
checkpointDir	<p>Specifies the directory for storing the checkpoint information, which is under the run directory by default. If the directory is inside the cluster, the <b>/srv/BigData/hadoop/dataX/flume/checkpoint</b> directory can be used. <b>dataX</b> ranges from data1 to dataN. If the directory is outside the cluster, it needs to be independently planned.</p>	/srv/BigData/hadoop/data1/flume/checkpoint

Parameter	Description	Example Value
transactionCapacity	Specifies the transaction size, that is, the number of events in a transaction that can be processed by the current Channel. The size cannot be smaller than the batchSize of Source. Setting the same size as batchSize is recommended.	61200
hostname	Specifies the name or IP address of the host whose data is to be sent. This parameter cannot be left blank. Name or IP address must be configured to be the name or IP address that the Avro source associated with it.	192.168.108.11
port	Specifies the IP address to which Avro Sink is bound. This parameter cannot be left blank. It must be consistent with the port that is monitored by the connected Avro Source.	21154

Parameter	Description	Example Value
ssl	<p>Specifies whether to enable the SSL authentication. (You are advised to enable this function to ensure security.)</p> <p>Only Sources of the Avro type have this configuration item.</p> <ul style="list-style-type: none"> <li>▪ <b>true</b> indicates that the function is enabled.</li> <li>▪ <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true
keystore	Specifies the <b>flume_cChat.jks</b> certificate generated on the server.	/opt/flume-client/fusionInsight-flume-1.9.0/conf/flume_cChat.jks
keystore-password	Specifies the password of the key library, which is the password required to obtain the keystore information.  Enter the value of <b>password</b> obtained in <a href="#">Step 4.3</a> .	D03C2D03D97CBA3F4 FD2491A40CAA5E0
truststore	Indicates the SSL certificate trust list of the server.	/opt/flume-client/fusionInsight-flume-1.9.0/conf/flume_cChat.jks
truststore-password	Specifies the trust list password, which is the password required to obtain the truststore information.  Enter the value of <b>password</b> obtained in <a href="#">Step 4.3</a> .	D03C2D03D97CBA3F4 FD2491A40CAA5E0

5. Upload the **properties.properties** file to **flume/conf/** under the installation directory of the Flume client.

**Step 5** Generate the certificate and trust list of the server and client of the MonitorServer role respectively.

1. Log in to the host with the MonitorServer role assigned as user **omm**.

Go to the **\${BIGDATA\_HOME}/FusionInsight\_Porter\_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin** directory.

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/bin
```

2. Run the following command to generate and export the server and client certificates of the MonitorServer role:

```
sh geneJKS.sh -m sKitty12@ -n cKitty12@
```

The generated certificate is saved in the **\${BIGDATA\_HOME}/FusionInsight\_Porter\_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf** path. Where:

- **ms\_sChat.jks** is the certificate library of the MonitorServer role server. **ms\_sChat.crt** is the exported file of the **ms\_sChat.jks** certificate. **-m** indicates the password of the certificate and certificate library.
- **ms\_cChat.jks** is the certificate library of the MonitorServer role client. **ms\_cChat.crt** is the exported file of the **ms\_cChat.jks** certificate. **-n** indicates the password of the certificate and certificate library.
- **ms\_sChatt.jks** and **ms\_cChatt.jks** are the SSL certificate trust lists of the MonitorServer server and client, respectively.

**Step 6** Set the server parameters of the MonitorServer role.

1. Run the following command to generate and obtain MonitorServer server keystore password, trust list password, and keystore-password encrypted private key information. Enter the password twice and confirm the password. The password is the same as the password of the certificate whose alias is *mschatserver* and the password of the *ms\_sChat.jks* certificate library, for example *sKitty12@*.

```
./genPwFile.sh
```

```
cat password.property
```

```
password=AA5E0D03C2D4FD24CBA3F91A40C03D97
```

2. Run the following command to open the **\${BIGDATA\_HOME}/FusionInsight\_Porter\_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/service/application.properties** file: Modify related parameters based on the description in [Table 5-43](#), save the modification, and exit.

```
vi ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/service/application.properties
```

**Table 5-43** Parameters to be modified of the MonitorServer role server

Parameter	Description	Example Value
ssl_need_kspas swd_decrypt_k ey	Indicates whether to enable the user-defined key encryption and decryption function. (You are advised to enable this function to ensure security.)  <ul style="list-style-type: none"> <li>- <b>true</b> indicates that the function is enabled.</li> <li>- <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true
ssl_server_enab le	Indicates whether to enable the SSL authentication. (You are advised to enable this function to ensure security.)  <ul style="list-style-type: none"> <li>- <b>true</b> indicates that the function is enabled.</li> <li>- <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true
ssl_server_key_ store	Set this parameter based on the specific storage location.	\${BIGDATA_HOME}/ FusionInsight_Porter_8.1.2.2 /install/FusionInsight- Flume-1.9.0/flume/conf/ ms_sChat.jks
ssl_server_trust _key_store	Set this parameter based on the specific storage location.	\${BIGDATA_HOME}/ FusionInsight_Porter_8.1.2.2 /install/FusionInsight- Flume-1.9.0/flume/conf/ ms_sChatt.jks
ssl_server_key_ store_password	Indicates the client certificate password. Set this parameter based on the actual situation of certificate creation (the plaintext key used to generate the certificate).  Enter the value of <b>password</b> obtained in <b>Step 6.1</b> .	AA5E0D03C2D4FD24CBA3F 91A40C03D97

Parameter	Description	Example Value
ssl_server_trust_key_store_password	Indicates the client trust list password. Set this parameter based on the actual situation of certificate creation (the plaintext key used to generate the trust list). Enter the value of <b>password</b> obtained in <a href="#">Step 6.1</a> .	AA5E0D03C2D4FD24CBA3F91A40C03D97
ssl_need_client_auth	Indicates whether to enable the client authentication. (You are advised to enable this function to ensure security.) <ul style="list-style-type: none"> <li>- <b>true</b> indicates that the function is enabled.</li> <li>- <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true

- Restart the MonitorServer instance. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume** > **Instance** > **MonitorServer**, select the configured MonitorServer instance, and choose **More** > **Restart Instance**. Enter the administrator password and click **OK**. After the restart is complete, click **Finish**.

**Step 7** Set the client parameters of the MonitorServer role.

- Run the following commands to copy the generated client certificate (**ms\_cChat.jks**) and client trust list (**ms\_cChatt.jks**) to the **/opt/flume-client/fusionInsight-flume-1.9.0/conf/** client directory. **10.196.26.1** is the service plane IP address of the node where the client resides.

```
scp ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/ms_cChat.jks user@10.196.26.1:/opt/flume-client/fusionInsight-flume-1.9.0/conf/
```

```
scp ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Flume-1.9.0/flume/conf/ms_cChatt.jks user@10.196.26.1:/opt/flume-client/fusionInsight-flume-1.9.0/conf/
```

- Log in to the node where the Flume client is located as user **user**. Run the following command to go to the client directory **/opt/flume-client/fusionInsight-flume-1.9.0/bin**.

```
cd /opt/flume-client/fusionInsight-flume-1.9.0/bin
```

- Run the following command to generate and obtain MonitorServer client keystore password, trust list password, and keystore-password encrypted private key information. Enter the password twice and confirm the password. The password is the same as the password of the certificate whose alias is

*mschatclient* and the password of the *ms\_cChat.jks* certificate library, for example *cKitty12@*.

```
./genPwFile.sh
```

```
cat password.property
```

```
password=BA3F91A40C03D97AA5E0D03C2D4FD24C
```

4. Run the following command to open the `/opt/flume-client/fusionInsight-flume-1.9.0/conf/service/application.properties` file. (`/opt/flume-client/fusionInsight-flume-1.9.0` is the directory where the client is installed.) Modify related parameters based on the description in [Table 5-44](#), save the modification, and exit.

```
vi /opt/flume-client/fusionInsight-flume-1.9.0/conf/service/application.properties
```

**Table 5-44** Parameters to be modified of the MonitorServer role client


Parameter	Description	Example Value
ssl_need_kspas swd_decrypt_k ey	Indicates whether to enable the user-defined key encryption and decryption function. (You are advised to enable this function to ensure security.)  – <b>true</b> indicates that the function is enabled. – <b>false</b> indicates that the client authentication function is not enabled.	true
ssl_client_enab le	Indicates whether to enable the SSL authentication. (You are advised to enable this function to ensure security.)  – <b>true</b> indicates that the function is enabled. – <b>false</b> indicates that the client authentication function is not enabled.	true
ssl_client_key_s tore	Set this parameter based on the specific storage location.	\${BIGDATA_HOME}/ FusionInsight_Porter_8.1.2.2 /install/FusionInsight- Flume-1.9.0/flume/conf/ ms_cChat.jks
ssl_client_trust _key_store	Set this parameter based on the specific storage location.	\${BIGDATA_HOME}/ FusionInsight_Porter_8.1.2.2 /install/FusionInsight- Flume-1.9.0/flume/conf/ ms_cChatt.jks

Parameter	Description	Example Value
ssl_client_key_store_password	Specifies the keystore password. Set this parameter based on the actual situation of certificate creation (the plaintext key used to generate the certificate). Enter the value of <b>password</b> obtained in <a href="#">Step 7.3</a> .	BA3F91A40C03D97AA5E0D03C2D4FD24C
ssl_client_trust_key_store_password	Specifies the trustkeystore password. Set this parameter based on the actual situation of certificate creation (the plaintext key used to generate the trust list). Enter the value of <b>password</b> obtained in <a href="#">Step 7.3</a> .	BA3F91A40C03D97AA5E0D03C2D4FD24C
ssl_need_client_auth	Indicates whether to enable the client authentication. (You are advised to enable this function to ensure security.) <ul style="list-style-type: none"> <li>- <b>true</b> indicates that the function is enabled.</li> <li>- <b>false</b> indicates that the client authentication function is not enabled.</li> </ul>	true

**Step 8** Verify log transmission.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster** > *Name of the desired cluster* > **Services** > **HDFS**, click the HDFS WebUI link to go to the HDFS WebUI, and choose **Utilities** > **Browse the file system**.
2. Check whether the data is generated in the **/flume/test** directory on the HDFS.

**Figure 5-19** Checking HDFS directories and files



----End

## 5.12 Viewing Flume Client Monitoring Information

### Scenario

The Flume client outside the FusionInsight cluster is a part of the end-to-end data collection. Both the Flume client outside the cluster and the Flume server in the cluster need to be monitored. Users can use FusionInsight Manager to monitor the Flume client and view the monitoring indicators of the Source, Sink, and Channel of the client as well as the client process status.

### Procedure

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Flume** > **Flume Management** to view the current Flume client list and process status.
- Step 3** Click the **Instance ID**, and view client monitoring metrics in the **Current** area.
- Step 4** Click **History**. The page for querying historical monitoring data is displayed. Select a time range and click **View** to view the monitoring data within the time range.

----End

## 5.13 Connecting Flume to Kafka in Security Mode

### Scenario

This section describes how to connect to Kafka using the Flume client in security mode.

### Procedure

- Step 1** Create a **jaas.conf** file and save it to  **$\${Flume\ client\ installation\ directory}\conf$** . The content of the **jaas.conf** file is as follows:

```
KafkaClient {
  com.sun.security.auth.module.Krb5LoginModule required
  useKeyTab=true
  keyTab="/opt/test/conf/user.keytab"
  principal="flume_hdfs@<System domain name>"
  useTicketCache=false
  storeKey=true
  debug=true;
};
```

Set **keyTab** and **principal** based on site requirements. The configured **principal** must have certain kafka permissions.

**Step 2** Configure services. Set the port number of **kafka.bootstrap.servers** to **21007**, and set **kafka.security.protocol** to **SASL\_PLAINTEXT**.

**Step 3** If the domain name of the cluster where Kafka is located is changed, change the value of *-Dkerberos.domain.name* in the **flume-env.sh** file in *`\${Flume client installation directory}`/conf/* based on the site requirements.

**Step 4** Upload the configured **properties.properties** file to *`\${Flume client installation directory}`/conf/*.

----End

## 5.14 Connecting Flume with Hive in Security Mode

### Scenario

This section describes how to use Flume to connect to Hive (version 3.1.0) in the cluster.

### Prerequisites

Flume and Hive have been correctly installed in the cluster. The services are running properly, and no alarm is reported.

### Procedure


**Step 1** Import the following JAR packages to the lib directory (client/server) of the Flume instance to be tested as user **omm**:

- antlr-2.7.7.jar
- antlr-runtime-3.4.jar
- calcite-core-1.16.0.jar
- hadoop-mapreduce-client-core-3.1.1.jar
- hive-beeline-3.1.0.jar
- hive-cli-3.1.0.jar
- hive-common-3.1.0.jar
- hive-exec-3.1.0.jar
- hive-hcatalog-core-3.1.0.jar
- hive-hcatalog-pig-adapter-3.1.0.jar
- hive-hcatalog-server-extensions-3.1.0.jar
- hive-hcatalog-streaming-3.1.0.jar
- hive-metastore-3.1.0.jar
- hive-service-3.1.0.jar
- libfb303-0.9.3.jar
- hadoop-plugins-1.0.jar

You can obtain the JAR package from the Hive installation directory and restart the Flume process to ensure that the JAR package is loaded to the running environment.

**Step 2** Set Hive configuration items.

On FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > Hive > Configurations > All Configurations > HiveServer > Customization > hive.server.customized.configs**.



Example configurations:

Name	Value
hive.support.concurrency	true
hive.exec.dynamic.partition.mode	nonstrict
hive.txn.manager	org.apache.hadoop.hive.ql.lockmgr.DbTxnManager
hive.compactor.initiator.on	true
hive.compactor.worker.threads	1

**Step 3** Prepare the system user **flume\_hive** who has the supergroup and Hive permissions, install the client, and create the required Hive table.

Example:

1. The cluster client has been correctly installed. For example, the installation directory is **/opt/client**.
2. Run the following command to authenticate the user:  

```
cd /opt/client
source bigdata_env
kinit flume_hive
```
3. Run the **beeline** command and run the following table creation statement:  

```
create table flume_multi_type_part(id string, msg string)
partitioned by (country string, year_month string, day string)
clustered by (id) into 5 buckets
stored as orc TBLPROPERTIES('transactional'='true');
```
4. Run the **select \* from Table name;** command to query data in the table.  
 In this case, the number of data records in the table is **0**.

**Step 4** Prepare related configuration files. Assume that the client installation package is stored in **/opt/FusionInsight\_Cluster\_1\_Services\_ClientConfig**.

1. Obtain the following files from the **\$Client decompression directory/Hive/config** directory:

- hivesite-site.xml
  - hive-site.xml
2. Obtain the following files from the *\$Client decompression directory/HDFS/config* directory:  
core-site.xml
  3. Create a directory on the host where the Flume instance is started and save the prepared files to the created directory.  
Example: **/opt/hivesink-conf/hive-site.xml**.
  4. Copy all property configurations in the **hivesite-site.xml** file to the **hive-site.xml** file and ensure that the configurations are placed before the original configurations.  
Data is loaded in sequence in Hive.

 **NOTE**

Ensure that the Flume running user **omm** has the read and write permissions on the directory where the configuration file is stored.

**Step 5** Observe the result.

On the Hive client, run the **select \* from Table name;** command. Check whether the corresponding data has been written to the Hive table.

----End

## Examples

Flume configuration example (SpoolDir--Mem--Hive):

```
server.sources = spool_source
server.channels = mem_channel
server.sinks = Hive_Sink

#config the source
server.sources.spool_source.type = spooldir
server.sources.spool_source.spoolDir = /tmp/testflume
server.sources.spool_source.montime =
server.sources.spool_source.fileSuffix = .COMPLETED
server.sources.spool_source.deletePolicy = never
server.sources.spool_source.trackerDir = flumespool
server.sources.spool_source.ignorePattern = ^$
server.sources.spool_source.batchSize = 20
server.sources.spool_source.inputCharset =UTF-8
server.sources.spool_source.selector.type = replicating
server.sources.spool_source.fileHeader = false
server.sources.spool_source.fileHeaderKey = file
server.sources.spool_source.basenameHeaderKey= basename
server.sources.spool_source.deserializer = LINE
server.sources.spool_source.deserializer.maxBatchLine= 1
server.sources.spool_source.deserializer.maxLineLength= 2048
server.sources.spool_source.channels = mem_channel

#config the channel
server.channels.mem_channel.type = memory
server.channels.mem_channel.capacity =10000
server.channels.mem_channel.transactionCapacity= 2000
server.channels.mem_channel.channelfullcount= 10
server.channels.mem_channel.keep-alive = 3
server.channels.mem_channel.byteCapacity =
server.channels.mem_channel.byteCapacityBufferPercentage= 20

#config the sink
```

```
server.sinks.Hive_Sink.type = hive
server.sinks.Hive_Sink.channel = mem_channel
server.sinks.Hive_Sink.hive.metastore = thrift://{any MetaStore service IP address}:21088
server.sinks.Hive_Sink.hive.hiveSite = /opt/hivesink-conf/hive-site.xml
server.sinks.Hive_Sink.hive.coreSite = /opt/hivesink-conf/core-site.xml
server.sinks.Hive_Sink.hive.metastoreSite = /opt/hivesink-conf/hivemeatastore-site.xml
server.sinks.Hive_Sink.hive.database = default
server.sinks.Hive_Sink.hive.table = flume_multi_type_part
server.sinks.Hive_Sink.hive.partition = Tag,%Y-%m,%d
server.sinks.Hive_Sink.hive.txnsPerBatchAsk= 100
server.sinks.Hive_Sink.hive.autoCreatePartitions= true
server.sinks.Hive_Sink.useLocalTimeStamp = true
server.sinks.Hive_Sink.batchSize = 1000
server.sinks.Hive_Sink.hive.kerberosPrincipal= super1
server.sinks.Hive_Sink.hive.kerberosKeytab= /opt/mykeytab/user.keytab
server.sinks.Hive_Sink.round = true
server.sinks.Hive_Sink.roundValue = 10
server.sinks.Hive_Sink.roundUnit = minute
server.sinks.Hive_Sink.serializer = DELIMITED
server.sinks.Hive_Sink.serializer.delimiter= ";"
server.sinks.Hive_Sink.serializer.serdeSeparator= ','
server.sinks.Hive_Sink.serializer.fieldnames= id,msg
```

## 5.15 Configuring the Flume Service Model

### 5.15.1 Overview

Guide a reasonable Flume service configuration by providing performance differences between Flume common modules, to avoid a nonstandard overall service performance caused when a frontend Source and a backend Sink do not match in performance.

Only single channels are compared for description.

### 5.15.2 Service Model Configuration Guide

During Flume service configuration and module selection, the ultimate throughput of a sink must be greater than the maximum throughput of a source. Otherwise, in extreme load scenarios, the write speed of the source to a channel is greater than the read speed of sink from channel. Therefore, the channel is fully occupied due to frequent usage, and the performance is affected. The maximum throughput of common modules is:

Avro Source = Avro Sink > Kafka Source > Kafka Sink > HDFS Sink > SpoolDir Source > HBase Sink > Taildir Source > Solr Sink

Avro Source and Avro Sink are usually used in pairs to transfer data between multiple Flume Agents. Therefore, Avro Source and Avro Sink do not become a performance bottleneck in general scenarios.

### Inter-Module Performance

Based on comparison between the limit performances of modules, Kafka Sink and HDFS Sink can meet the throughput requirements when the front-end is SpoolDir Source. However, HBase Sink and Solr Sink could become performance bottlenecks due to the low write performances thereof. As a result, data is stacked in Channel. If you have to use HBase Sink, Solr Sink, or other sinks that are prone to become

performance bottlenecks, you can use **Channel Selector** or **Sink Group** to meet performance requirements.

## Channel Selector

A channel selector allows a source to connect to multiple channels. Data of the source can be distributed or copied by selecting different types of selectors. Currently, a channel selector provided by Flume can be a replicating channel selector or a multiplexing channel selector.

**Replicating:** indicates that the data of the source is synchronized to all channels.

**Multiplexing:** indicates that based on the value of a specific field of the header of an event, a channel is selected to send the data. In this way, the data is distributed based on a service type.

- Replicating configuration example:

```
client.sources = kafkasource
client.channels = channel1 channel2
client.sources.kafkasource.type = org.apache.flume.source.kafka.KafkaSource
client.sources.kafkasource.kafka.topics = topic1,topic2
client.sources.kafkasource.kafka.consumer.group.id = flume
client.sources.kafkasource.kafka.bootstrap.servers = 10.69.112.108:21007
client.sources.kafkasource.kafka.security.protocol = SASL_PLAINTEXT
client.sources.kafkasource.batchDurationMillis = 1000
client.sources.kafkasource.batchSize = 800
client.sources.kafkasource.channels = channel1 c el2

client.sources.kafkasource.selector.type = replicating
client.sources.kafkasource.selector.optional = channel2
```

**Table 5-45** Parameters in the Replicating configuration example

Parameter	Default Value	Description
Selector.type	replicating	Selector type. Set this parameter to <b>replicating</b> .
Selector.optional	-	Optional channel. Configure this parameter as a list.

- Multiplexing configuration example:

```
client.sources = kafkasource
client.channels = channel1 channel2
client.sources.kafkasource.type = org.apache.flume.source.kafka.KafkaSource
client.sources.kafkasource.kafka.topics = topic1,topic2
client.sources.kafkasource.kafka.consumer.group.id = flume
client.sources.kafkasource.kafka.bootstrap.servers = 10.69.112.108:21007
client.sources.kafkasource.kafka.security.protocol = SASL_PLAINTEXT
client.sources.kafkasource.batchDurationMillis = 1000
client.sources.kafkasource.batchSize = 800
client.sources.kafkasource.channels = channel1 channel2

client.sources.kafkasource.selector.type = multiplexing
client.sources.kafkasource.selector.header = myheader
client.sources.kafkasource.selector.mapping.topic1 = channel1
client.sources.kafkasource.selector.mapping.topic2 = channel2
client.sources.kafkasource.selector.default = channel1
```

**Table 5-46** Parameters in the Multiplexing configuration example

Parameter	Default Value	Description
Selector.type	replicating	Selector type. Set this parameter to <b>multiplexing</b> .
Selector.header	Flume.selector.header	-
Selector.default	-	-
Selector.mapping.*	-	-

In a multiplexing selector example, select a field whose name is topic from the header of the event. When the value of the topic field in the header is topic1, send the event to a channel 1; or when the value of the topic field in the header is topic2, send the event to a channel 2.

Selectors need to use a specific header of an event in a source to select a channel, and need to select a proper header based on a service scenario to distribute data.

## SinkGroup

When the performance of a backend single sink is insufficient, and high reliability or heterogeneous output is required, you can use a sink group to connect a specified channel to multiple sinks, thereby meeting use requirements. Currently, Flume provides two types of sink processors to manage sinks in a sink group. The types are load balancing and failover.

**Failover:** Indicates that there is only one active sink in the sink group each time, and the other sinks are on standby and inactive. When the active sink becomes faulty, one of the inactive sinks is selected based on priorities to take over services, so as to ensure that data is not lost. This is used in high-reliability scenarios.

**Load balancing:** Indicates that all sinks in the sink group are active. Each sink obtains data from the channel and processes the data. In addition, during running, loads of all sinks in the sink group are balanced. This is used in performance improvement scenarios.

- Load balancing configuration examples:

```
client.sources = source1
client.sinks = sink1 sink2
client.channels = channel1

client.sinkgroups = g1
client.sinkgroups.g1.sinks = sink1 sink2
client.sinkgroups.g1.processor.type = load_balance
client.sinkgroups.g1.processor.backoff = true
client.sinkgroups.g1.processor.selector = random

client.sinks.sink1.type = logger
client.sinks.sink1.channel = channel1

client.sinks.sink2.type = logger
client.sinks.sink2.channel = channel1
```

**Table 5-47** Parameters of Load Balancing configuration examples

Parameter	Default Value	Description
sinks	-	Specifies the sink list of the sink group. Multiple sinks are separated by spaces.
processor.type	default	Specifies the type of a processor. Set this parameter to <b>load_balance</b> .
processor.backoff	false	Indicates whether to back off failed sinks exponentially.
processor.selector	round_robin	Specifies the selection mechanism. It must be round_robin, random, or a customized class that inherits AbstractSinkSelector.
processor.selector.maxTimeOut	30000	Specifies the time for masking a faulty sink. The default value is 30,000 ms.

- Failover configuration examples:

```

client.sources = source1
client.sinks = sink1 sink2
client.channels = channel1

client.sinkgroups = g1
client.sinkgroups.g1.sinks = sink1 sink2
client.sinkgroups.g1.processor.type = failover
client.sinkgroups.g1.processor.priority.sink1 = 10
client.sinkgroups.g1.processor.priority.sink2 = 5
client.sinkgroups.g1.processor.maxpenalty = 10000

client.sinks.sink1.type = logger
client.sinks.sink1.channel = channel1

client.sinks.sink2.type = logger
client.sinks.sink2.channel = channel1
    
```

**Table 5-48** Parameters in the **failover** configuration example

Parameter	Default Value	Description
sinks	-	Specifies the sink list of the sink group. Multiple sinks are separated by spaces.

Parameter	Default Value	Description
processor.type	default	Specifies the type of a processor. Set this parameter to <b>failover</b> .
processor.priority.<sink Name>	-	Priority. <sinkName> must be defined in description of sinks. A sink having a higher priority is activated earlier. A larger value indicates a higher priority. <b>Note:</b> If there are multiple sinks, their priorities must be different. Otherwise, only one of them takes effect.
processor.maxpenalty	30000	Specifies the maximum backoff time of failed sinks (unit: ms).

## Interceptors

The Flume interceptor supports modification or discarding of basic unit events during data transmission. You can specify the class name list of built-in interceptors in Flume or develop customized interceptors to modify or discard events. The following table lists the built-in interceptors in Flume. A complex example is used in this section. Other users can configure and use interceptions as required. For details, visit the following website:

<http://flume.apache.org/releases/content/1.9.0/FlumeUserGuide.html>

### NOTE

1. The interceptor is used between the sources and channels of Flume. Most sources provide parameters for configuring interceptors. You can set the parameters as required.
2. Flume allows multiple interceptors to be configured for a source. The interceptor names are separated by spaces.
3. The specified interceptor sequence is the order in which they are called.
4. The contents inserted by the interceptor in the header can be read and used in sink.

**Table 5-49** Types of built-in interceptors in Flume

Interceptor Type	Description
Timestamp Interceptor	The interceptor inserts a timestamp into the header of an event.

Interceptor Type	Description
Host Interceptor	The interceptor inserts the IP address or host name of the node where the agent is located into the Header of an event.
Remove Header Interceptor	The interceptor discards the corresponding event based on the strings that matches the regular expression contained in the event header.
UUID Interceptor	The interceptor generates a UUID string for the header of each event.
Search and Replace Interceptor	The interceptor provides a simple string-based search and replacement function based on Java regular expressions. The rule is the same as that of Java <code>Matcher.replaceAll()</code> .
Regex Filtering Interceptor	The interceptor uses the body of an event as a text file and matches the configured regular expression to filter events. The provided regular expression can be used to exclude or include events.
Regex Extractor Interceptor	The interceptor extracts content from the original events using a regular expression and adds the content to the header of events.

**Regex Filtering Interceptor** is used as an example to describe how to use the interceptor. (For other types of interceptions, see the configuration provided on the official website.)

**Table 5-50** Parameter configuration for **Regex Filtering Interceptor**

Parameter	Default Value	Description
type	-	Specifies the component type name. The value must be <b>regex_filter</b> .
regex	-	Specifies the regular expression used to match events.
excludeEvents	false	By default, the matched events are collected. If this parameter is set to <b>true</b> , the matched events are deleted and the unmatched events are retained.

Configuration example (netcat tcp is used as the source, and logger is used as the sink). After configuring the preceding parameters, run the **telnet** *Host name or IP*

`address 44444` command on the host where the Linux operating system is run, and enter a string that complies with the regular expression and another does not comply with the regular expression. The log shows that only the matched string is transmitted.

```
#define the source, channel, sink
server.sources = r1

server.channels = c1
server.sinks = k1

#config the source
server.sources.r1.type = netcat
server.sources.r1.bind = ${Host IP address}
server.sources.r1.port = 44444
server.sources.r1.interceptors= i1
server.sources.r1.interceptors.i1.type= regex_filter
server.sources.r1.interceptors.i1.regex= (flume)(myflume)
server.sources.r1.interceptors.i1.excludeEvents= false
server.sources.r1.channels = c1

#config the channel
server.channels.c1.type = memory
server.channels.c1.capacity = 1000
server.channels.c1.transactionCapacity = 100
#config the sink
server.sinks.k1.type = logger
server.sinks.k1.channel = c1
```

## 5.16 Introduction to Flume Logs

### Log Description

**Log path:** The default path of Flume log files is `/var/log/Bigdata/Role name`.

- FlumeServer: `/var/log/Bigdata/flume/flume`
- FlumeClient: `/var/log/Bigdata/flume-client-n/flume`
- MonitorServer: `/var/log/Bigdata/flume/monitor`

**Log archive rule:** The automatic Flume log compression function is enabled. By default, when the size of logs exceeds 50 MB , logs are automatically compressed into a log file named in the following format: `<Original log file name>-<yyyy-mm-dd_hh-mm-ss>.[ID].log.zip`. A maximum of 20 latest compressed files are reserved. The number of compressed files can be configured on the Manager portal.

**Table 5-51** Flume log list

Type	Name	Description
Run logs	<code>/flume/flumeServer.log</code>	Log file that records FlumeServer running environment information.
	<code>/flume/install.log</code>	FlumeServer installation log file
	<code>/flume/flumeServer-gc.log.&lt;No.&gt;</code>	GC log file of the FlumeServer process

Type	Name	Description
	/flume/prestartDetail.log	Work log file before the FlumeServer startup
	/flume/startDetail.log	Startup log file of the Flume process
	/flume/stopDetail.log	Shutdown log file of the Flume process
	/monitor/monitorServer.log	Log file that records MonitorServer running environment information
	/monitor/startDetail.log	Startup log file of the MonitorServer process
	/monitor/stopDetail.log	Shutdown log file of the MonitorServer process
	function.log	External function invoking log file
	threadDump-<DATE>.log	The jstack log file to be printed when the NodeAgent delivers a service stop command

## Log Level

**Table 5-52** describes the log levels supported by Flume.

Levels of run logs are FATAL, ERROR, WARN, INFO, and DEBUG from the highest to the lowest priority. Run logs of equal or higher levels are recorded. The higher the specified log level, the fewer the logs recorded.

**Table 5-52** Log level

Type	Level	Description
Run log	FATAL	Logs of this level record critical error information about system running.
	ERROR	Logs of this level record error information about system running.
	WARN	Logs of this level record exception information about the current event processing.

Type	Level	Description
	INFO	Logs of this level record normal running status information about the system and events.
	DEBUG	Logs of this level record the system information and system debugging information.

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of Flume by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** On the menu bar on the left, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Save the configuration. In the displayed dialog box, click **OK** to make the configurations take effect.

----End

 **NOTE**

The configurations take effect immediately without the need to restart the service.

## Log Format

The following table lists the Flume log formats.

**Table 5-53** Log format

Type	Format	Example
Run logs	<i>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt; &lt;Log level&gt; &lt;Name of the thread that generates the log&gt; &lt;Message in the log&gt; &lt;Location where the log event occurs&gt;</i>	2014-12-12 11:54:57,316   INFO   [main]   log4j dynamic load is start.   org.apache.flume.tools.LogDynamicLoad.start(LogDynamicLoad.java:59)
	<i>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt;&lt;Username&gt;&lt;User IP&gt;&lt;Time&gt;&lt;Operation&gt;&lt;Resource&gt;&lt;Result&gt;&lt;Detail&gt;</i>	2014-12-12 23:04:16,572   INFO   [SinkRunner-PollingRunner-DefaultSinkProcessor]   SRCIP=null OPERATION=close

## 5.17 Flume Client Cgroup Usage Guide

### Scenario

This section describes how to join and log out of a cgroup, query the cgroup status, and change the cgroup CPU threshold.

### Procedure

- **Join Cgroup**

Assume that the Flume client installation path is `/opt/FlumeClient`, and the cgroup CPU threshold is 50%. Run the following command to join a cgroup:

```
cd /opt/FlumeClient/fusioninsight-flume-1.9.0/bin
./flume-manage.sh cgroup join 50
```

 **NOTE**

- This command can be used to join a cgroup and change the cgroup CPU threshold.
- The value of the CPU threshold of a cgroup ranges from 1 to 100 x *N*. *N* indicates the number of CPU cores.

- **Check Cgroup status**

Assume that the Flume client installation path is `/opt/FlumeClient`. Run the following commands to query the cgroup status:

```
cd /opt/FlumeClient/fusioninsight-flume-1.9.0/bin
./flume-manage.sh cgroup status
```

- **Exit Cgroup**

Assume that the Flume client installation path is `/opt/FlumeClient`. Run the following commands to exit cgroup:

```
cd /opt/FlumeClient/fusioninsight-flume-1.9.0/bin
./flume-manage.sh cgroup exit
```

 **NOTE**

- After the client is installed, the default cgroup is automatically created. If the `-s` parameter is not configured during client installation, the default value `-1` is used. The default value indicates that the agent process is not restricted by the CPU usage.
- Joining or exiting a cgroup does not affect the agent process. Even if the agent process is not started, the joining or exiting operation can be performed successfully, and the operation will take effect after the next startup of the agent process.
- After the client is uninstalled, the cgroups created during the client installation are automatically deleted.

## 5.18 Secondary Development Guide for Flume Third-Party Plug-ins

### Scenario

This section describes how to perform secondary development for third-party plug-ins.

### Prerequisites

- You have obtained the third-party JAR package.
- You have installed Flume server or client.

### Procedure

**Step 1** Compress the self-developed code into a JAR package.

**Step 2** Create a directory for the plug-in.

1. Access the **\$FLUME\_HOME/plugins.d** path and run the following command to create a directory:

```
mkdir thirdPlugin
cd thirdPlugin
mkdir lib libext native
```

The command output is displayed as follows:

```
[root@: plugins.d]#mkdir thirdPlugin
[root@: plugins.d]#ll
total 8
drwxr-x-- 3 root root 4096 native
drwxr-xr-x 2 root root 4096 thirdPlugin
[root@: plugins.d]#cd thirdPlugin/
[root@: thirdPlugin]#mkdir lib libext native
[root@: thirdPlugin]#ll
total 12
drwxr-xr-x 2 root root 4096 lib
drwxr-xr-x 2 root root 4096 libext
drwxr-xr-x 2 root root 4096 native
[root@: thirdPlugin]#
```

2. Place the third-party JAR package in the **\$FLUME\_HOME/plugins.d/thirdPlugin/lib** directory. If the JAR package depends on other JAR packages, place the depended JAR packages to the **\$FLUME\_HOME/ plugins.d/ thirdPlugin/libext** directory, and place the local library files in **\$FLUME\_HOME/ plugins.d/ thirdPlugin/native**.

**Step 3** Configure the **properties.properties** file in **\$FLUME\_HOME/conf/**.

For details about how to set parameters in the **properties.properties** file, see the parameter list in the **properties.properties** file in the corresponding typical scenario [Non-Encrypted Transmission](#) and [Encrypted Transmission](#).

 NOTE

- **\$FLUME\_HOME** indicates the Flume installation path. Set this parameter based on the site requirements (server or client) when configuring third-party plug-ins.
- **thirdPlugin** is the name of the third-party plugin.

----End

## 5.19 Common Issues About Flume

Flume logs are stored in **/var/log/Bigdata/flume/flume/flumeServer.log**. Most data transmission exceptions and data transmission failures are recorded in logs. You can run the following command:

**tailf /var/log/Bigdata/flume/flume/flumeServer.log**

- Problem: After the configuration file is uploaded, an exception occurs. After the configuration file is uploaded again, the scenario requirements are still not met, but no exception is recorded in the log.

Solution: Restart the Flume process, run the **kill -9 Process code** to kill the process code, and view the logs.

- Issue: "**java.lang.IllegalArgumentException: Keytab is not a readable file: /opt/test/conf/user.keytab**" is displayed when HDFS is connected.

Solution: Grant the read and write permissions to the Flume running user.

- Problem: The following error is reported when the Flume client is connected to Kafka:

Caused by: java.io.IOException: /opt/FlumeClient/fusioninsight-flume-1.9.0/cof//jaas.conf (No such file or directory)

Solution: Add the **jaas.conf** configuration file and save it to the **conf** directory of the Flume client.

**vi jaas.conf**

```
KafkaClient {
com.sun.security.auth.module.Krb5LoginModule required
useKeyTab=true
keyTab="/opt/test/conf/user.keytab"
principal="flume_hdfs@<System domain name>"
useTicketCache=false
storeKey=true
debug=true;
};
```

Values of **keyTab** and **principal** vary depending on the actual situation.

- Problem: The following error is reported when the Flume client is connected to HBase:

Caused by: java.io.IOException: /opt/FlumeClient/fusioninsight-flume-1.9.0/cof//jaas.conf (No such file or directory)

Solution: Add the **jaas.conf** configuration file and save it to the **conf** directory of the Flume client.

**vi jaas.conf**

```
Client {
com.sun.security.auth.module.Krb5LoginModule required
useKeyTab=true
keyTab="/opt/test/conf/user.keytab"
principal="flume_hbase@<System domain name>"
useTicketCache=false
```

```
storeKey=true  
debug=true;  
};
```

Values of **keyTab** and **principal** vary depending on the actual situation.

- Question: After the configuration file is submitted, the Flume Agent occupies resources. How do I restore the Flume Agent to the state when the configuration file is not uploaded?

Solution: Submit an empty **properties.properties** file.

# 6 Using HBase

## 6.1 Using HBase from Scratch

HBase is a column-based distributed storage system that features high reliability, performance, and scalability. This section describes how to use HBase from scratch, including how to update the client on the Master node in the cluster, create a table using the client, insert data in the table, modify the table, read data from the table, delete table data, and delete the table.

### Background

Suppose a user develops an application to manage users who use service A in an enterprise. The procedure of operating service A on the HBase client is as follows:

- Create the **user\_info** table.
- Add users' educational backgrounds and titles to the table.
- Query user names and addresses by user ID.
- Query information by user name.
- Deregister users and delete user data from the user information table.
- Delete the user information table after service A ends.

**Table 6-1** User information

ID	Name	Gender	Age	Address
12005000201	A	Male	19	City A
12005000202	B	Female	23	City B
12005000203	C	Male	26	City C
12005000204	D	Male	18	City D
12005000205	E	Female	21	City E
12005000206	F	Male	32	City F

ID	Name	Gender	Age	Address
12005000207	G	Female	29	City G
12005000208	H	Female	30	City H
12005000209	I	Male	26	City I
12005000210	J	Male	25	City J

## Prerequisites

The client has been installed. For example, the client is installed in the `/opt/client` directory. The client directory in the following operations is only an example. Change it to the actual installation directory. Before using the client, download and update the client configuration file, and ensure that the active management node of Manager is available.

## Procedure

**Step 1** Use the client on the active management node.

- Log in to the node where the client is installed as the client installation user and run the following command to switch to the client directory:  
**cd /opt/client**
- Run the following command to configure environment variables:  
**source bigdata\_env**
- If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the current user. The current user must have the permission to create HBase tables. For details about how to configure a role with corresponding permissions, see . To bind a role to a user, see . If Kerberos authentication is disabled for the current cluster, skip this step.  
**kinit MRS cluster user**  
For example, **kinit hbaseuser**.
- Run the following HBase client command:  
**hbase shell**

**Step 2** Run the following commands on the HBase client to implement service A.

- Create the **user\_info** user information table according to [Table 6-1](#) and add data to it.

```
create 'user_info',{NAME => 'i'}
```

For example, to add information about the user whose ID is **12005000201**, run the following commands:

```
put 'user_info','12005000201','i:name','A'
```

```
put 'user_info','12005000201','i:gender','Male'
```

```
put 'user_info','12005000201','i:age','19'
```

```
put 'user_info','12005000201','i:address','City A'
```

2. Add users' educational backgrounds and titles to the **user\_info** table.  
For example, to add educational background and title information about user 12005000201, run the following commands:  

```
put 'user_info','12005000201','i:degree','master'  
put 'user_info','12005000201','i:pose','manager'
```
  3. Query user names and addresses by user ID.  
For example, to query the name and address of user 12005000201, run the following command:  

```
scan'user_info',  
{STARTROW=>'12005000201',STOPROW=>'12005000201',COLUMNS=>['i:na  
me','i:address']}
```
  4. Query information by user name.  
For example, to query information about user A, run the following command:  

```
scan'user_info',{FILTER=>"SingleColumnValueFilter('i','name',=,'binary:A')"
```
  5. Delete user data from the user information table.  
All user data needs to be deleted. For example, to delete data of user 12005000201, run the following command:  

```
delete'user_info','12005000201','i'
```
  6. Delete the user information table.  

```
disable'user_info';drop 'user_info'
```
- End

## 6.2 Creating HBase Roles

### Scenario

This section guides the system administrator to create and configure an HBase role on Manager. The HBase role can set HBase administrator permissions and read (R), write (W), create (C), execute (X), or manage (A) permissions for HBase tables and column families.

Users can create a table, query/delete/insert/update data, and authorize others to access HBase tables after they set the corresponding permissions for the specified databases or tables on HDFS.

#### NOTE

- HBase roles can be created in security mode, but cannot be created in normal mode.
- If the current component uses Ranger for permission control, you need to configure related policies based on Ranger for permission management. For details, see [Adding a Ranger Access Permission Policy for HBase](#).

### Prerequisites

- The system administrator has understood the service requirements.
- You have logged in to Manager.

## Procedure

- Step 1** On Manager, choose **System > Permission > Role**.
- Step 2** On the displayed page, click **Create Role** and enter a **Role Name** and **Description**.
- Step 3** Set **Permission**. For details, see [Table 6-2](#).

HBase permissions:

- HBase Scope: Authorizes HBase tables. The minimum permission is read (R) and write (W) for columns.
- HBase administrator permission: HBase administrator permissions.

### NOTE

Users have the read (R), write (W), create (C), execute (X), and administrate (A) permissions for the tables created by themselves.

**Table 6-2** Setting a role

Task	Role Authorization
Setting the HBase administrator permission	In <b>Configure Resource Permission</b> , choose <i>Name of the desired cluster</i> > <b>HBase</b> and select <b>HBase Administrator Permission</b> .
Setting the permission for users to create tables	<ol style="list-style-type: none"> <li>1. In <b>Configure Resource Permission</b>, choose <i>Name of the desired cluster</i> &gt; <b>HBase</b> &gt; <b>HBase Scope</b>.</li> <li>2. Click <b>global</b>.</li> <li>3. In the <b>Permission</b> column of the specified namespace, select <b>Create</b> and <b>Execute</b>. For example, select <b>Create</b> and <b>Execute</b> for the default namespace <b>default</b>.</li> </ol>
Setting the permission for users to write data to tables	<ol style="list-style-type: none"> <li>1. In <b>Configure Resource Permission</b>, choose <i>Name of the desired cluster</i> &gt; <b>HBase</b> &gt; <b>HBase Scope</b> &gt; <b>global</b>.</li> <li>2. In the <b>Permission</b> column of the specified namespace, select <b>Write</b>. For example, select <b>Write</b> for the default namespace <b>default</b>. By default, HBase sub-objects inherit the permission from the parent object.</li> </ol>
Setting the permission for users to read data from tables	<ol style="list-style-type: none"> <li>1. In <b>Configure Resource Permission</b>, choose <i>Name of the desired cluster</i> &gt; <b>HBase</b> &gt; <b>HBase Scope</b> &gt; <b>global</b>.</li> <li>2. In the <b>Permission</b> column of the specified namespace, select <b>Read</b>. For example, select <b>Read</b> for the default namespace <b>default</b>. By default, HBase sub-objects inherit the permission from the parent object.</li> </ol>

Task	Role Authorization
Setting the permission for users to manage namespaces or tables	<ol style="list-style-type: none"> <li>1. In <b>Configure Resource Permission</b>, choose <i>Name of the desired cluster</i> &gt; <b>HBase</b> &gt; <b>HBase Scope</b> &gt; <b>global</b>.</li> <li>2. In the <b>Permission</b> column of the specified namespace, select <b>Manage</b>. For example, select <b>Manage</b> for the default namespace <b>default</b>.</li> </ol>
Setting the permission for reading data from or writing data to columns	<ol style="list-style-type: none"> <li>1. In <b>Configure Resource Permission</b>, select <i>Name of the desired cluster</i> &gt; <b>HBase</b> &gt; <b>HBase Scope</b> &gt; <b>global</b> and click the specified namespace to display the tables in the namespace.</li> <li>2. Click a table.</li> <li>3. Click a column family.</li> <li>4. Confirm whether you want to create a role? <ul style="list-style-type: none"> <li>- If yes, enter the column name in the <b>Resource Name</b> text box. Use commas (,) to separate multiple columns. Select <b>Read</b> or <b>Write</b>. If there are no columns with the same name in the HBase table, a newly created column with the same name as the existing column has the same permission as the existing one. The column permission is set successfully.</li> <li>- If no, modify the column permission of the existing HBase role. The columns for which the permission has been separately set are displayed in the table. Go to <b>Step 3.5</b>.</li> </ul> </li> <li>5. To add column permissions for a role, enter the column name in the <b>Resource Name</b> text box and set the column permissions. To modify column permissions for a role, enter the column name in the <b>Resource Name</b> text box and set the column permissions. Alternatively, you can directly modify the column permissions in the table. If the column permissions are modified in the table and column permissions with the same name are added, the settings cannot be saved. You are advised to modify the column permission of a role directly in the table. The search function is supported.</li> </ol>

**Step 4** Click **OK**, and return to the **Role** page.

----End

## 6.3 Using an HBase Client

### Scenario

This section describes how to use the HBase client in an O&M scenario or a service scenario.

### Prerequisites

- The client has been installed. For example, the installation directory is **/opt/hadoopclient**. The client directory in the following operations is only an example. Change it to the actual installation directory.
- Service component users are created by the administrator as required.  
A machine-machine user needs to download the **keytab** file and a human-machine user needs to change the password upon the first login.
- If a non-**root** user uses the HBase client, ensure that the owner of the HBase client directory is this user. Otherwise, run the following command to change the owner.

```
chown user:group -R Client installation directory/HBase
```

### Using the HBase Client

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to go to the client directory:

```
cd /opt/hadoopclient
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the current user. The current user must have the permission to create HBase tables. For details about how to configure a role with corresponding permissions, see [To bind a role to a user](#), see [. If Kerberos authentication is disabled for the current cluster, skip this step.](#)

```
kinit Component service user
```

For example, **kinit hbaseuser**.

**Step 5** Run the following HBase client command:

```
hbase shell
```

```
----End
```

### Common HBase client commands

The following table lists common HBase client commands. For more commands, see <http://hbase.apache.org/2.2/book.html>.

**Table 6-3** HBase client commands

Command	Description
create	Used to create a table, for example, <b>create 'test', 'f1', 'f2', 'f3'</b> .
disable	Used to disable a specified table, for example, <b>disable 'test'</b> .
enable	Used to enable a specified table, for example, <b>enable 'test'</b> .
alter	Used to alter the table structure. You can run the <b>alter</b> command to add, modify, or delete column family information and table-related parameter values, for example, <b>alter 'test', {NAME =&gt; 'f3', METHOD =&gt; 'delete'}</b> .
describe	Used to obtain the table description, for example, <b>describe 'test'</b> .
drop	Used to delete a specified table, for example, <b>drop 'test'</b> . Before deleting a table, you must stop it.
put	Used to write the value of a specified cell, for example, <b>put 'test','r1','f1:c1','myvalue1'</b> . The cell location is unique and determined by the table, row, and column.
get	Used to get the value of a row or the value of a specified cell in a row, for example, <b>get 'test','r1'</b> .
scan	Used to query table data, for example, <b>scan 'test'</b> . The table name and scanner must be specified in the command.

## 6.4 Configuring HBase Replication

### Scenario

As a key feature to ensure high availability of the HBase cluster system, HBase cluster replication provides HBase with remote data replication in real time. It provides basic O&M tools, including tools for maintaining and re-establishing active/standby relationships, verifying data, and querying data synchronization progress. To achieve real-time data replication, you can replicate data from the HBase cluster to another one.

### Prerequisites

- The active and standby clusters have been successfully installed and started (the cluster status is **Running** on the **Active Clusters** page), and you have the administrator rights of the clusters.
- The network between the active and standby clusters is normal and ports can be used properly.
- Cross-cluster mutual trust has been configured. For details, see .
- If historical data exists in the active cluster and needs to be synchronized to the standby cluster, cross-cluster replication must be configured for the active and standby clusters. For details, see [Enabling Cross-Cluster Copy](#).

- Time is consistent between the active and standby clusters and the Network Time Protocol (NTP) service on the active and standby clusters uses the same time source.
- Mapping relationships between the names of all hosts in the active and standby clusters and service IP addresses have been configured in the `/etc/hosts` file by appending `192.**.*.*.* host1` to the `hosts` file.
- The network bandwidth between the active and standby clusters is determined based on service volume, which cannot be less than the possible maximum service volume.

## Constraints

- Despite that HBase cluster replication provides the real-time data replication function, the data synchronization progress is determined by several factors, such as the service loads in the active cluster and the health status of processes in the standby cluster. In normal cases, the standby cluster should not take over services. In extreme cases, system maintenance personnel and other decision makers determine whether the standby cluster takes over services according to the current data synchronization indicators.
- Currently, the replication function supports only one active cluster and one standby cluster in HBase.
- Typically, do not perform operations on data synchronization tables in the standby cluster, such as modifying table properties or deleting tables. If any misoperation on the standby cluster occurs, data synchronization between the active and standby clusters will fail and data of the corresponding table in the standby cluster will be lost.
- If the replication function of HBase tables in the active cluster is enabled for data synchronization, after modifying the structure of a table in the active cluster, you need to manually modify the structure of the corresponding table in the standby cluster to ensure table structure consistency.

## Procedure

**Enable the replication function for the active cluster to synchronize data written by Put.**

- Step 1** Go to the **All Configurations** page of the HBase service. For details, see [Modifying Cluster Service Configuration Parameters](#).

 **NOTE**

If the **Components** tab is not displayed on the cluster details page, synchronize the IAM user first. (In the **Dashboard** area of the cluster details page, click **Click to synchronize** on the right of **IAM User Sync** to synchronize IAM users.)

- Step 2** Choose **RegionServer > Replication** and check whether the value of **hbase.replication** is **true**. If the value is **false**, set **hbase.replication** to **true**.
- Step 3** (Optional) Set configuration items listed in [Table 6-4](#). You can set the parameters based on the description or use the default values.

**Table 6-4** Optional configuration items

Navigation Path	Parameter	Default Value	Description
HMaster > Performance	hbase.master.logcleaner.ttl	600000	Time to live (TTL) of HLog files. If the value is set to <b>604800000</b> (unit: millisecond), the retention period of HLog is 7 days.
	hbase.master.cleaner.interval	60000	Interval for the HMaster to delete historical HLog files. The HLog that exceeds the configured period will be automatically deleted. You are advised to set it to the maximum value to save more HLogs.
RegionServer > Replication	replication.source.size.capacity	16777216	Maximum size of edits, in bytes. If the edit size exceeds the value, HLog edits will be sent to the standby cluster.
	replication.source.nb.capacity	25000	Maximum number of edits, which is another condition for triggering HLog edits to be sent to the standby cluster. After data in the active cluster is synchronized to the standby cluster, the active cluster reads and sends data in HLog according to this parameter value. This parameter is used together with <b>replication.source.size.capacity</b> .
	replication.source.maxretriesmultiplier	10	Maximum number of retries when an exception occurs during replication.
	replication.source.sleepforretries	1000	Retry interval (unit: ms)
	hbase.regionserver.replication.handler.count	6	Number of replication RPC server instances on RegionServer

**Enable the replication function for the active cluster to synchronize data written by bulkload.**

**Step 4** Determine whether to enable bulkload replication.

 NOTE

If bulkload import is used and data needs to be synchronized, you need to enable Bulkload replication.

If yes, go to [Step 5](#).

If no, go to [Step 9](#).

**Step 5** Go to the **All Configurations** page of the HBase service parameters by referring to [Modifying Cluster Service Configuration Parameters](#).

**Step 6** On the HBase configuration interface of the active and standby clusters, search for **hbase.replication.cluster.id** and modify it. It specifies the HBase ID of the active and standby clusters. For example, the HBase ID of the active cluster is set to **replication1** and the HBase ID of the standby cluster is set to **replication2** for connecting the active cluster to the standby cluster. To save data overhead, the parameter value length is not recommended to exceed 30.

**Step 7** On the HBase configuration interface of the standby cluster, search for **hbase.replication.conf.dir** and modify it. It specifies the HBase configurations of the active cluster client used by the standby cluster and is used for data replication when the bulkload data replication function is enabled. The parameter value is a path name, for example, **/home**.

 NOTE

- When bulkload replication is enabled, you need to manually place the HBase client configuration files (**core-site.xml**, **hdfs-site.xml**, and **hbase-site.xml**) in the active cluster on all RegionServer nodes in the standby cluster. The actual path for placing the configuration file is **\${hbase.replication.conf.dir}/\${hbase.replication.cluster.id}**. For example, if **hbase.replication.conf.dir** of the standby cluster is set to **/home** and **hbase.replication.cluster.id** of the active cluster is set to **replication1**, the actual path for placing the configuration files in the standby cluster is **/home/replication1**. You also need to change the corresponding directory and file permissions by running the **chown -R omm:wheel /home/replication1** command.
- You can obtain the client configuration files from the client in the active cluster, for example, the **/opt/client/HBase/hbase/conf** path. For details about how to update the configuration file, see .

**Step 8** On the HBase configuration page of the active cluster, search for and change the value of **hbase.replication.bulkload.enabled** to **true** to enable bulkload replication.

### Restarting the HBase service and install the client

**Step 9** Save the configurations and restart HBase.

**Step 10** In the active and standby clusters. For details about how to update the client configuration file, see .

### Synchronize table data of the active cluster. (Skip this step if the active cluster has no data.)

**Step 11** Access the HBase shell of the active cluster as user **hbase**.

1. On the active management node where the client has been updated, run the following command to go to the client directory:

```
cd /opt/client
```

2. Run the following command to configure environment variables:  
**source bigdata\_env**
3. If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the current user. If Kerberos authentication is disabled for the current cluster, skip this step.  
**kinit hbase**
4. Run the following HBase client command:  
**hbase shell**

**Step 12** Check whether historical data exists in the standby cluster. If historical data exists and data in the active and standby clusters must be consistent, delete data from the standby cluster first.

1. On the HBase shell of the standby cluster, run the **list** command to view the existing tables in the standby cluster.
2. Delete data tables from the standby cluster based on the output list.  
**disable 'tableName'**  
**drop 'tableName'**

**Step 13** After HBase replication is configured and data synchronization is enabled, check whether tables and data exist in the active cluster and whether the historical data needs to be synchronized to the standby cluster.

Run the **list** command to check the existing tables in the active cluster and run the **scan 'tableName'** command to check whether the tables contain historical data.

- If tables exist and data needs to be synchronized, go to [Step 14](#).
- If no, no further action is required.

**Step 14** The HBase replication configuration does not support automatic synchronization of historical data in tables. You need to back up the historical data of the active cluster and then manually synchronize the historical data to the standby cluster.

Manual synchronization refers to the synchronization of a single table that is implemented by Export, distcp, and Import.

The process for manually synchronizing data of a single table is as follows:

1. Export table data from the active cluster.  
**hbase org.apache.hadoop.hbase.mapreduce.Export -Dhbase.mapreduce.include.deleted.rows=true** *Table name Directory where the source data is stored*  
Example: **hbase org.apache.hadoop.hbase.mapreduce.Export -Dhbase.mapreduce.include.deleted.rows=true t1 /user/hbase/t1**
2. Copy the data that has been exported to the standby cluster.  
**hadoop distcp** *Directory for storing source data in the active cluster* **hdfs://ActiveNameNodeIP:9820/** *Directory for storing source data in the standby cluster*  
**ActiveNameNodeIP** indicates the IP address of the active NameNode in the standby cluster.

Example: **hadoop distcp /user/hbase/t1 hdfs://192.168.40.2:9820/user/hbase/t1**

3. Import data to the standby cluster as the HBase table user of the standby cluster.

**hbase org.apache.hadoop.hbase.mapreduce.Import -**

*Dimport.bulk.output=Directory where the output data is stored in the standby cluster Table name Directory where the source data is stored in the standby cluster*

**hbase org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles**

*Directory where the output data is stored in the standby cluster Table name*

For example, **hbase org.apache.hadoop.hbase.mapreduce.Import -**

**Dimport.bulk.output=/user/hbase/output\_t1 t1 /user/hbase/t1** and

**hbase org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles /user/hbase/output\_t1 t1**

**Add the replication relationship between the active and standby clusters.**

- Step 15** Run the following command on the HBase Shell to create the replication synchronization relationship between the active cluster and the standby cluster:

```
add_peer 'Standby cluster ID', CLUSTER_KEY => 'ZooKeeper address of the standby cluster',{HDFS_CONFS => true}
```

- *Standby cluster ID* indicates an ID for the active cluster to recognize the standby cluster. It is recommended that the ID contain letters and digits.
- The ZooKeeper address of the standby cluster includes the service IP address of ZooKeeper, the port for listening to client connections, and the HBase root directory of the standby cluster on ZooKeeper.
- **{HDFS\_CONFS => true}** indicates that the default HDFS configuration of the active cluster will be synchronized to the standby cluster. This parameter is used for HBase of the standby cluster to access HDFS of the active cluster. If bulkload replication is disabled, you do not need to use this parameter.

Suppose the standby cluster ID is replication2 and the ZooKeeper address of the standby cluster is **192.168.40.2,192.168.40.3,192.168.40.4:2181:/hbase**.

 **NOTE**

1. Obtain the ZooKeeper service IP address.  
Log in to the MRS console, click the cluster name, and choose **Components > ZooKeeper > Instances** to obtain the ZooKeeper service IP address.
2. On the ZooKeeper service parameter configuration page, search for clientPort, which is the port for the client to connect to the server.
3. Run the **list\_peers** command to check whether the replication relationship between the active and standby clusters is added. If the following information is displayed, the relationship is successfully added.  

```
hbase(main):003:0> list_peers
PEER_ID CLUSTER_KEY ENDPOINT_CLASSNAME STATE REPLICATE_ALL NAMESPACES
TABLE_CFS BANDWIDTH SERIAL
replication2 192.168.0.13,192.168.0.177,192.168.0.25:2181:/hbase ENABLED true 0 false
```

**Specify the data writing status for the active and standby clusters.**

- Step 16** On the HBase shell of the active cluster, run the following command to retain the data writing status:

### **set\_clusterState\_active**

The command is run successfully if the following information is displayed:

```
hbase(main):001:0> set_clusterState_active  
=> true
```

**Step 17** On the HBase shell of the standby cluster, run the following command to retain the data read-only status:

### **set\_clusterState\_standby**

The command is run successfully if the following information is displayed:

```
hbase(main):001:0> set_clusterState_standby  
=> true
```

### **Enable the HBase replication function to synchronize data.**

**Step 18** Check whether a namespace exists in the HBase service instance of the standby cluster and the namespace has the same name as the namespace of the HBase table for which the replication function is to be enabled.

On the HBase shell of the standby cluster, run the **list\_namespace** command to query the namespace.

- If the same namespace exists, go to [Step 19](#).
- If the same namespace does not exist, on the HBase shell of the standby cluster, run the following command to create a namespace with the same name and go to [Step 19](#):

```
create_namespace'ns1
```

**Step 19** On the HBase shell of the active cluster, run the following command to enable real-time replication for tables in the active cluster. This ensures that modified data in the active cluster can be synchronized to the standby cluster in real time.

You can only synchronize data of one HTable at one time.

```
enable_table_replication 'Table name'
```

#### NOTE

- If the standby cluster does not contain a table with the same name as the table for which real-time synchronization is to be enabled, the table is automatically created.
- If a table with the same name as the table for which real-time synchronization is to be enabled exists in the standby cluster, the structures of the two tables must be the same.
- If the encryption algorithm SMS4 or AES is configured for '*Table name*', the function for synchronizing data from the active cluster to the standby cluster cannot be enabled for the HBase table.
- If the standby cluster is offline or has tables with the same name but different structures, the replication function cannot be enabled.

If the standby cluster is offline, start it.

If the standby cluster has a table with the same name but different structure, modify the table structure to make it as the same as the table structure of the active cluster. On the HBase shell of the standby cluster, run the **alter** command to change the password by referring to the example.

**Step 20** On the HBase shell of the active cluster, run the following command to enable the real-time replication function for the active cluster to synchronize the HBase permission table:

### enable\_table\_replication 'hbase:acl'

#### NOTE

After the permission of the active HBase source data table is modified, to ensure that the standby cluster can properly read data, modify the role permission for the standby cluster.

### Check the data synchronization status for the active and standby clusters.

**Step 21** Run the following command on the HBase client to check the synchronized data of the active and standby clusters. After the replication function is enabled, you can run this command to check whether the newly synchronized data is consistent.

```
hbase org.apache.hadoop.hbase.mapreduce.replication.VerifyReplication --  
starttime=Start time --endtime=End time Column family name ID of the standby  
cluster Table name
```

#### NOTE

- The start time must be earlier than the end time.
- The value of **starttime** and **endtime** must be in the timestamp format. You need to run **date -d "2015-09-30 00:00:00" +%s** to change a common time format to a timestamp format. The command output is a 10-digit number (accurate to second), but HBase identifies a 13-digit number (accurate to millisecond). Therefore, you need to add three zeros (000) to the end of the command output.

### Switch over active and standby clusters.

#### NOTE

1. If the standby cluster needs to be switched over to the active cluster, reconfigure the active/standby relationship by referring to [Step 1](#) to [Step 10](#) and [Step 15](#) to [Step 20](#).
2. Do not perform [Step 11](#) to [Step 14](#).

----End

## Related Commands

**Table 6-5** HBase replication

Operation	Command	Description
Set up the active/standby relationship.	<p><b>add_peer</b> <i>'Standby cluster ID',CLUSTER_KEY =&gt;'Standby cluster address'</i></p> <p>Examples:</p> <p><b>add_peer</b> '1',CLUSTER_KEY =&gt; 'zk1,zk2,zk3:2181:/hbase'</p> <p><b>add_peer</b> '1',CLUSTER_KEY =&gt; 'zk1,zk2,zk3:2181:/hbase1'</p>	Set up the relationship between the active cluster and the standby cluster. To enable bulkload replication, run the <b>add_peer</b> <i>'Standby cluster ID',CLUSTER_KEY =&gt; 'Standby cluster address'</i> command, configure <b>hbase.replication.conf.dir</b> , and manually copy the HBase client configuration file in the active cluster to all RegionServer nodes in the standby cluster. For details, see <a href="#">Step 4</a> to <a href="#">11</a> .
Remove the active/standby relationship.	<p><b>remove_peer</b> <i>'Standby cluster ID'</i></p> <p>Example:</p> <p><b>remove_peer</b> '1'</p>	Remove standby cluster information from the active cluster.
Query the active/standby relationship.	<b>list_peers</b>	Query standby cluster information (mainly Zookeeper information) in the active cluster.
Enable the real-time user table synchronization function.	<p><b>enable_table_replication</b> <i>'Table name'</i></p> <p>Example:</p> <p><b>enable_table_replication</b> 't1'</p>	Synchronize user tables from the active cluster to the standby cluster.
Disable the real-time user table synchronization function.	<p><b>disable_table_replication</b> <i>'Table name'</i></p> <p>Example:</p> <p><b>disable_table_replication</b> 't1'</p>	Do not synchronize user tables from the active cluster to the standby cluster.

Operation	Command	Description
Verify data of the active and standby clusters.	<b>bin/hbase</b> <b>org.apache.hadoop.hbase.mapreduce.replication.VerifyReplication</b> <i>--starttime --endtime Column family name Standby cluster ID Table name</i>	Verify whether data of the specified table is the same between the active cluster and the standby cluster. The description of the parameters in this command is as follows: <ul style="list-style-type: none"> <li>• Start time: If start time is not specified, the default value <b>0</b> will be used.</li> <li>• End time: If end time is not specified, the time when the current operation is submitted will be used by default.</li> <li>• Table name: If a table name is not entered, all user tables for which the real-time synchronization function is enabled will be verified by default.</li> </ul>
Switch the data writing status.	<b>set_clusterState_active</b> <b>set_clusterState_standby</b>	Specifies whether data can be written to the cluster HBase tables.

## 6.5 Enabling Cross-Cluster Copy

### Scenario

DistCp is used to copy the data stored on HDFS from a cluster to another cluster. DistCp depends on the cross-cluster copy function, which is disabled by default. This function needs to be enabled in both clusters.

This section describes how to enable cross-cluster copy.

### Impact on the System

Yarn needs to be restarted to enable the cross-cluster copy function and cannot be accessed during the restart.

### Prerequisites

The **hadoop.rpc.protection** parameter of the two HDFS clusters must be set to the same data transmission mode, which can be **privacy** (encryption enabled) or **authentication** (encryption disabled).

 NOTE

Go to the **All Configurations** page by referring to [Modifying Cluster Service Configuration Parameters](#) and search for **hadoop.rpc.protection**.

## Procedure

- Step 1** Go to the **All Configurations** page of the Yarn service. For details, see [Modifying Cluster Service Configuration Parameters](#).

 NOTE

If the **Components** tab is not displayed on the cluster details page, complete IAM user synchronization first. (In the **Dashboard** area of the cluster details page, click **Click to synchronize** on the right of **IAM User Sync** to synchronize IAM users.)

- Step 2** In the navigation pane, choose **Yarn > Distcp**.

- Step 3** Set **haclusterX.remotenn1** of **dfs.namenode.rpc-address** to the service IP address and RPC port number of one NameNode instance of the peer cluster, and set **haclusterX.remotenn2** to the service IP address and RPC port number of the other NameNode instance of the peer cluster. Enter a value in the *IP address:port* format.

 NOTE

You can log in to FusionInsight Manager, and choose **Cluster > Name of the desired cluster > Services > HDFS > Instance** to obtain the service IP address of the NameNode instance.

**dfs.namenode.rpc-address.haclusterX.remotenn1** and **dfs.namenode.rpc-address.haclusterX.remotenn2** do not distinguish active and standby NameNode instances. The default NameNode RPC port is 9820 and cannot be modified on MRS Manager.

For example, **10.1.1.1:9820** and **10.1.1.2:9820**.

- Step 4** Save the configuration. On the **Dashboard** tab page, and choose **More > Restart Service** to restart the Yarn service.

**Operation succeeded** is displayed. Click **Finish**. The Yarn service is started successfully.

- Step 5** Log in to the other cluster and repeat the preceding operations.

----End

## 6.6 Supporting Full-Text Index

You can create tables and indexes using **createTable** of **org.apache.luna.client.LunaAdmin** and specify table names, column family names, requests for creating indexes, as well as the directory path for storing mapping files. You can also add indexes to existing tables using **addCollection** and obtain tables to perform a scan operation by using **getTable** of **org.apache.luna.client.LunaAdmin**.

The column name and column family name of a table consist of letters, digits, and underscores (\_) but cannot contain any special characters.

HBase tables with a full-text index have the following limitations:

- Disaster recovery, backup, and restoration are not supported.
- Rows and column families cannot be deleted.
- Tight consistency is not supported by the query on Solr.

## Code Snippet Example

The following code snippet belongs to the `testFullTextScan` method in the `LunaSample` class of the `hbase.examples` package.

```
public static void testFullTextScan() throws Exception {
    /**
     * Create create request of Solr. Specify collection name, confset name,
     * number of shards, and number of replication factor.
     */
    Create create = new Create();
    create.setCollectionName(COLLECTION_NAME);
    create.setConfigName(CONFSET_NAME);
    create.setNumShards(NUM_OF_SHARDS);
    create.setReplicationFactor(NUM_OF_REPLICATIONFACTOR);
    /**
     * Create mapping. Specify index fields(mandatory) and non-index
     * fields(optional).
     */
    List<ColumnField> indexedFields = new ArrayList<ColumnField>();
    indexedFields.add(new ColumnField("name", "f:n"));
    indexedFields.add(new ColumnField("cat", "f:t"));
    indexedFields.add(new ColumnField("features", "f:d"));
    Mapping mapping = new Mapping(indexedFields);
    /**
     * Create table descriptor of HBase.
     */
    HTableDescriptor desc = new HTableDescriptor(HBASE_TABLE);
    desc.addFamily(new HColumnDescriptor(TABLE_FAMILY));
    /**
     * Create table and collection at the same time.
     */
    LunaAdmin admin = null;
    try {
        admin = new AdminSingleton().getAdmin();
        admin.deleteTable(HBASE_TABLE);
        if (!admin.tableExists(HBASE_TABLE)) {
            admin.createTable(desc, Bytes.toByteArrays(new String[] { "0", "1", "2", "3", "4" }),
                create, mapping);
        }
    }
    /**
     * Put data.
     */
    Table table = admin.getTable(HBASE_TABLE);
    int i = 0;
    while (i < 5) {
        byte[] row = Bytes.toBytes(i + "+sohrowkey");
        Put put = new Put(row);
        put.addColumn(TABLE_FAMILY, Bytes.toBytes("n"), Bytes.toBytes("ZhangSan" + i));
        put.addColumn(TABLE_FAMILY, Bytes.toBytes("t"), Bytes.toBytes("CO" + i));
        put.addColumn(TABLE_FAMILY, Bytes.toBytes("d"), Bytes.toBytes("Male, Leader of M.O" + i));
        table.put(put);
        i++;
    }

    /**
     * Scan table.
     */
    Scan scan = new Scan();
    SolrQuery query = new SolrQuery();
    query.setQuery("name:ZhangSan1 AND cat:CO1");
}
```

```

Filter filter = new FullTextFilter(query, COLLECTION_NAME);
scan.setFilter(filter);
ResultScanner scanner = table.getScanner(scan);
LOG.info("-----records-----");
for (Result r = scanner.next(); r != null; r = scanner.next()) {
    for (Cell cell : r.rawCells()) {
        LOG.info(Bytes.toString(CellUtil.cloneRow(cell)) + ":"
            + Bytes.toString(CellUtil.cloneFamily(cell)) + ","
            + Bytes.toString(CellUtil.cloneQualifier(cell)) + ","
            + Bytes.toString(CellUtil.cloneValue(cell)));
    }
}
LOG.info("-----end-----");
/**
 * Delete collection.
 */
admin.deleteCollection(HBASE_TABLE, COLLECTION_NAME);

/**
 * Delete table.
 */
admin.deleteTable(HBASE_TABLE);
} catch (IOException e) {
    e.printStackTrace();
} finally {
    /**
     * When everything done, close LunaAdmin.
     */
    admin.close();
}
}

```

## Precautions

- Tables and indexes to be created must be unique.
- Use LunaAdmin only to obtain tables to perform a scan operation.

## 6.7 Using the ReplicationSyncUp Tool

### Prerequisites

1. Active and standby clusters have been installed and started.
2. Time is consistent between the active and standby clusters and the NTP service on the active and standby clusters uses the same time source.
3. When the HBase service of the active cluster is stopped, the ZooKeeper and HDFS services must be started and run.
4. ReplicationSyncUp must be run by the system user who starts the HBase process.
5. In security mode, ensure that the HBase system user of the standby cluster has the read permission on HDFS of the active cluster. This is because that it will update the ZooKeeper nodes and HDFS files of the HBase system.
6. When HBase of the active cluster is faulty, the ZooKeeper, file system, and network of the active cluster are still available.

### Scenarios

The replication mechanism can use WAL to synchronize the state of a cluster with the state of another cluster. After HBase replication is enabled, if the active cluster

is faulty, ReplicationSyncUp synchronizes incremental data from the active cluster to the standby cluster using the information from the ZooKeeper node. After data synchronization is complete, the standby cluster can be used as an active cluster.

## Parameter Configuration

Parameter	Description	Default Value
hbase.replication.bulkload.enabled	Whether to enable the bulkload data replication function. The parameter value type is Boolean. To enable the bulkload data replication function, set this parameter to <b>true</b> for the active cluster.	<b>false</b>
hbase.replication.cluster.id	ID of the source HBase cluster. After the bulkload data replication is enabled, this parameter is mandatory and must be defined in the source cluster. The parameter value type is String.	-

## Tool Usage

Run the following command on the client of the active cluster:

```
hbase org.apache.hadoop.hbase.replication.regionserver.ReplicationSyncUp - Dreplication.sleep.before.failover=1
```

### NOTE

**replication.sleep.before.failover** indicates sleep time required for replication of the remaining data when RegionServer fails to start. You are advised to set this parameter to 1 second to quickly trigger replication.

## Precautions

1. When the active cluster is stopped, this tool obtains the WAL processing progress and WAL processing queue from the ZooKeeper Node (RS znode) and copies the queues that are not copied to the standby cluster.
2. RegionServer of each active cluster has its own znode under the replication node of ZooKeeper in the standby cluster. It contains one znode of each peer cluster.
3. If RegionServer is faulty, each RegionServer in the active cluster receives a notification through the watcher and attempts to lock the znode of the faulty RegionServer, including its queues. The successfully created RegionServer transfers all queues to the znode of its own queue. After queues are transferred, they are deleted from the old location.
4. When the active cluster is stopped, ReplicationSyncUp synchronizes data between active and standby clusters using the information from the

ZooKeeper node. In addition, WALs of the RegionServer znode will be moved to the standby cluster.

## Restrictions and Limitations

If the standby cluster is stopped or the peer relationship is closed, the tool runs normally but the peer relationship cannot be replicated.

# 6.8 Using HIndex

## 6.8.1 Introduction to HIndex

### Scenarios

HBase is a distributed storage database of the Key-Value type. Data in tables is sorted by dictionary based on row keys. If you query data by specifying a row key or scan data in a specific row key range, HBase can help you quickly locate the data to be read. In most cases, you need to query data whose column value is *XXX*. HBase provides the filter function to enable you to query data with a specific column value. All data is scanned in the sequence of row keys and is matched with the specific column value until the required data is found. To obtain the required data, the filter will scan some unnecessary data. As a result, the filter function cannot meet the requirements for high-performance, frequent queries.

HBase HIndex is designed to address these issues. HBase HIndex provides HBase with the capability of indexing based on specific column values, making queries faster.

 NOTE

- Rolling upgrade is not supported for index data.
- Composite index: You must add or delete all columns that participate in composite indexes. Otherwise, the data may be inconsistent.
- You should not explicitly configure any split policy to a data table where an index has been created.
- The mutation operations are not supported, such as increment and append.
- Index of the column with **maxVersions** greater than 1 is not supported.
- The value size of a column for which an index is added cannot exceed 32 KB.
- When the user data is deleted because TTL of the column family is invalid, the corresponding index data will not be deleted immediately. The index data will be deleted during major compaction.
- After an index is created, the TTL of the user column family must not be changed.
  - If the TTL of the column family is changed to a larger value after an index is created, delete the index and create one again. Otherwise, some generated index data may be deleted before the deletion of user data.
  - If the TTL of the column family is changed to a smaller value after an index is created, the index may be deleted after the deletion of user data.
- After disaster recovery is enabled for HBase tables, a secondary index is created in the active cluster and index table changes are not automatically synchronized to the standby cluster. To implement disaster recovery in this case, perform the following operations:
  1. After the secondary index is created in the active table, create a secondary index with the same schema and name using the same method in the standby cluster.
  2. In the active cluster, manually set **REPLICATION\_SCOPE** of the index column family (default value: **d**) to **1**.

## Parameter Configuration

1. Go to the **All Configurations** page of the HBase service. For details, see [Modifying Cluster Service Configuration Parameters](#).
2. View parameters on the HBase configurations page.

Navigation Path	Parameter	Default Value	Description
HMaster > System	hbase.coprocessor.master.classes	org.apache.hadoop.hbase.hindex.server.master.HIndexMasterCoprocessor,com.xxx.hadoop.hbase.backup.services.RecoveryCoprocessor,org.apache.ranger.authorization.hbase.RangerAuthorizationCoprocessor,org.apache.hadoop.hbase.security.access.ReadOnlyClusterEnabler,org.apache.hadoop.hbase.rsgroup.RSGroupAdminEndpoint	This coprocessor is used to handle Master-level operations after the HIndex function is enabled, for example, creating an index meta table, adding an index, and deleting an index, a table, and index metadata.
RegionServer > RegionServer	hbase.coprocessor.regionserver.classes	org.apache.hadoop.hbase.hindex.server.regionserver.HIndexRegionServerCoprocessor,org.apache.hadoop.hbase.JMXListener,org.apache.ranger.authorization.hbase.RangerAuthorizationCoprocessor	This coprocessor is used to handle the operations that the Master delivers to RegionServer after the HIndex function is enabled.

Navigation Path	Parameter	Default Value	Description
	hbase.coprocessor.region.classes	org.apache.hadoop.hbase.hindex.server.regionserver.HIndexRegionCoprocessor,org.apache.hadoop.hbase.security.token.TokenProvider,com.xxx.hadoop.hbase.backup.services.RecoveryCoprocessor,org.apache.ranger.authorization.hbase.RangerAuthorizationCoprocessor,org.apache.hadoop.hbase.security.access.SecureBulkLoadEndpoint,org.apache.hadoop.hbase.security.access.ReadOnlyClusterEnabler,org.apache.hadoop.hbase.coprocessor.MetaTableMetrics	This coprocessor is used to operate data in the Region after the HIndex function is enabled.

 NOTE

1. The preceding default values need to be configured after the HBase HIndex function is enabled. In MRS clusters that support the HBase HIndex function, the values have been configured by default.
2. Ensure that the **master** parameter is configured on HMaster and the **region** and **regionserver** parameters are configured on RegionServer.

## Related Interfaces

The APIs that use HIndex are in the **org.apache.hadoop.hbase.hindex.client.HIndexAdmin** class. The following table describes the related APIs.

Operation	API	Description	Precautions
Add an index.	addIndices()	Add an index to a table without data. Calling this API will add the specified index to a table but skips index data generation. Therefore, after this operation, the index cannot be used for the scanning and filtering operations. This API applies to scenarios where users want to add indexes in batches to tables that have a large amount of pre-existing user data. The specific operation is to use external tools such as the TableIndexer tool to build index data.	<ul style="list-style-type: none"> <li>• An index cannot be modified once it is added. To modify the index, you need to delete the old index and then create a new one.</li> <li>• Do not create two indexes on the same column with different index names. Otherwise, storage and processing resources will be wasted.</li> <li>• Indexes cannot be added to a system table.</li> <li>• The append and increment operations are not supported when data is put into the index column.</li> <li>• If any fault occurs on the client except <b>DoNotRetryIOException</b>, you need to try again.</li> <li>• An index column family is selected from the following conditions in sequence based on availability: <ul style="list-style-type: none"> <li>– Typically, the default index column family is <b>d</b>. However, if the value of <b>hindex.default</b>.</li> </ul> </li> </ul>

Operation	API	Description	Precautions
	addIndicesWithData()	<p>Add an index to a table with data. This API is used to add the specified index to the table and create index data for the existing user data. Alternatively, the API can be called to generate an index and then generate index data when the user data is being stored. Therefore, after this operation, the index can be used for the scanning and filtering operations immediately.</p>	<p><b>family.name</b> is set, the value will be used.</p> <ul style="list-style-type: none"> <li>- Symbol #, @, \$, or %</li> <li>- #0, @ 0, \$ 0, %0, #1, @ 1 ...to #255, @ 255, \$ 255, %255</li> <li>- Throw exceptions.</li> </ul> <ul style="list-style-type: none"> <li>• You can use the HIndex TableIndexer tool to add indexes without building index data.</li> </ul>
Delete an index.	dropIndices()	<p>This API is used to delete an index only. It deletes the specified index from a table but skips the corresponding index data. After this operation, the index cannot be used for the scanning and filtering operations. The cluster automatically deletes old index data during major compaction.</p> <p>This API applies to scenarios where a table contains a large amount of index data and <b>dropIndicesWithData()</b> is unavailable. In addition, you can use the TableIndexer tool to delete indexes and index data.</p>	<ul style="list-style-type: none"> <li>• An index can be disabled when it is in the <b>ACTIVE</b>, <b>INACTIVE</b>, or <b>DROPPING</b> state.</li> <li>• If you use <b>dropIndices()</b> to delete an index, ensure that the index data has been deleted before the index is added to the table with the same index name (that is, major compaction has been completed).</li> <li>• If you delete an index, the following information will also be deleted: <ul style="list-style-type: none"> <li>- A column family with an index</li> <li>- Any one of column families in a combination index</li> </ul> </li> </ul>

Operation	API	Description	Precautions
	dropIndicesWithData()	Delete index data. This API deletes the specified index and all index data corresponding to the index in a user table. After this operation, the index is completely deleted from the table and is no longer used for the scanning and filtering operations.	<ul style="list-style-type: none"> <li>Indexes and index data can be deleted together using the HIndexTableIndexer tool.</li> </ul>
Enable/Disable an index.	disableIndices()	This API disables all indexes specified by a user so that they are no longer used for the scanning and filtering operations.	<ul style="list-style-type: none"> <li>An index can be enabled when the index is in the <b>ACTIVE</b>, <b>INACTIVE</b>, or <b>BUILDING</b> state.</li> <li>An index can be disabled when the index is in the <b>ACTIVE</b> or <b>INACTIVE</b> state.</li> <li>Before disabling an index, ensure that the index data is consistent with the user data. If no new data is added to the table when the index is disabled, the index data is consistent with the user data.</li> <li>When enabling an index, you can use the TableIndexer tool to build index data to ensure data consistency.</li> </ul>
	enableIndices()	This API enables all indexes specified by a user so that they can be used for the scanning and filtering operations.	
View the created index.	listIndices()	This API is used to list all indexes of a specified table.	N/A

## Querying Data Based on Indexes

You can use a filter to query data in a user table with an index. The query result of a user table with a single or combination index is the same as that of a table without an index, but the table with an index provides higher data query performance than the table without an index.

The index usage rules are as follows:

- Scenario 1: A single index is created for one or more columns.
  - When this column is used for AND or OR query filtering, an index can improve query performance.  
Example: `Filter_Condition(IndexCol1)AND / OR Filter_Condition(IndexCol2)`
  - When you use **Index Column AND Non-Index Column** for filtering in the query, the index can improve query performance.  
Example: `Filter_Condition(IndexCol1)AND Filter_Condition(IndexCol2)AND Filter_Condition(NonIndexCol1)`
  - When you use **Index Column OR Non-Index Column** for filtering in the query but do not use an index, query performance will not be improved.  
Example: `Filter_Condition(IndexCol1)AND / OR Filter_Condition(IndexCol2) OR Filter_Condition(NonIndexCol1)`
- Scenario 2: A combination index is created for multiple columns.
  - When the columns to be queried are all or part of the combination index and have the same order as the combination index, using the index improves query performance.  
For example, create a combination index for C1, C2, and C3.
    - The index takes effect in the following situations:  
`Filter_Condition(IndexCol1)AND Filter_Condition(IndexCol2)AND Filter_Condition(IndexCol3)`  
`Filter_Condition(IndexCol1)AND Filter_Condition(IndexCol2)`  
`FILTER_CONDITION(IndexCol1)`
    - The index does not take effect in the following situations:  
`Filter_Condition(IndexCol2)AND Filter_Condition(IndexCol3)`  
`Filter_Condition(IndexCol1)AND Filter_Condition(IndexCol3)`  
`FILTER_CONDITION(IndexCol2)`  
`FILTER_CONDITION(IndexCol3)`
  - When you use **Index Column AND Non-Index Column** for filtering in the query, the index can improve query performance.  
Examples:  
`Filter_Condition(IndexCol1)AND Filter_Condition(NonIndexCol1)`  
`Filter_Condition(IndexCol1)AND Filter_Condition(IndexCol2)AND Filter_Condition(NonIndexCol1)`
  - When you use **Index Column OR Non-Index Column** for filtering in the query but do not use an index, query performance will not be improved.  
Examples:  
`Filter_Condition(IndexCol1)OR Filter_Condition(NonIndexCol1)`  
`(Filter_Condition(IndexCol1)AND Filter_Condition(IndexCol2))OR(Filter_Condition(NonIndexCol1))`
  - When multiple columns are used for query, you can specify a value range for only the last column in the combination index and set other columns to specified values

For example, create a combination index for C1, C2, and C3. In a range query, only the value range of C3 can be set. The filter criteria are "C1 = XXX, C2 = XXX, and C3 = Value range."

## Query Policy Selection

Use **SingleColumnValueFilter** or **SingleColumnRangeFilter**. It will provide the definite value **column\_family:qualifierpair** (called **col1**) in filter criteria.

If **col1** is the first index column in the table, any index in the table can be a candidate index used during the query. The following provides an example:

If there is an index on **col1**, the index can be used as a candidate index because **col1** is the first and the only column of the index. If there is another index on **col1** and **col2**, you can consider this index as a candidate index because **col1** is the first column in the index list. However, if there is an index on **col2** and **col1**, this index cannot be used as a candidate index because the first column in the index list is not **col1**.

The most suitable method to use the index now is that when there are multiple candidate indexes, select the most suitable index for scanning data.

You can use the following solutions to learn how to select the best index policy.

- It is better to fully match.  
Scenario: There are two indexes available, one for **col1&col2** and the other for **col1**.  
In this scenario, the second index is better than the first one, because it scans less index data.
- If there are multiple candidate multi-column indexes, select an index with fewer index columns.  
Scenario: There are two indexes available, one for **col1&col2** and the other for **col1&col2&col3**.  
In this case, you had better use the index on **col1&col2**, because it scans less index data.

 NOTE

- During a query based on an index, the index state must be **ACTIVE**. You can call the **listIndices()** API to view the index state.
- To query the correct data based on the index, ensure the consistency between index data and user data.
- Run the following command to perform a complex query on the HBase shell client (assuming that an index has been created for the specified column):  
**scan 'tablename', {FILTER => "SingleColumnValueFilter(family, qualifier, compareOp, comparator, filterIfMissing, latestVersionOnly)"}**  
Example: **scan 'test', {FILTER => "SingleColumnValueFilter('info', 'age', =, 'binary:26', true, true)"}**  
In the preceding scenario, if you want to save the row where no column is found in the result, you should not create any index in any such column, because if the column to be queried does not exist, the row will be filtered out when SCVF is used to scan the index columns. When the SCVF whose **filterIfMissing** is **false** (default value) scans non-index columns, rows where no column is queried will also be returned in the result. Therefore, to avoid inconsistent query results, you are advised to set **filterIfMissing** to **true** after creating SCVF for the index column.
- Run the following command on the HBase shell client to view the index data created for user data:  
**scan 'tablename', {ATTRIBUTES => {'FETCH\_INDEX\_DATA' => 'true'}}**

## 6.8.2 Loading Index Data in Batches

### Scenarios

HBase provides the ImportTsv&LoadIncremental tool to load user data in batches. HBase also provides the HIndexImportTsv tool to load both the user data and index data in batches. HIndexImportTsv inherits all functions of the HBase batch data loading tool ImportTsv. If a table is not created before the HIndexImportTsv tool is executed, an index will be created when the table is created, and index data is generated when user data is generated.

### Procedure

1. Run the following commands to import data to HDFS:

```
hdfs dfs -mkdir <inputdir>
```

```
hdfs dfs -put <local_data_file> <inputdir>
```

For example, define the data file **data.txt** as follows:

```
12005000201,Zhang San,Male,19,City a, Province a  
12005000202,Li Wanting,Female,23,City b, Province b  
12005000203,Wang Ming,Male,26,City c, Province c  
12005000204,Li Gang,Male,18,City d, Province d  
12005000205,Zhao Enru,Female,21,City e, Province e  
12005000206,Chen Long,Male,32,City f, Province f  
12005000207,Zhou Wei,Female,29,City g, Province g  
12005000208,Yang Yiwen,Female,30,City h, Province h  
12005000209,Xu Bing,Male,26,City i, Province i  
12005000210,Xiao Kai,Male,25,City j, Province j
```

Run the following commands:

```
hdfs dfs -mkdir /datadirImport
```

```
hdfs dfs -put data.txt /datadirImport
```

2. Go to HBase shell and run the following command to create the **bulkTable** table:

```
create 'bulkTable', {NAME => 'info',COMPRESSION => 'SNAPPY',  
DATA_BLOCK_ENCODING => 'FAST_DIFF'},{NAME=>'address'}
```

After the execution is complete, exit the HBase shell.

3. Run the following commands to generate an HFile file (StoreFiles):

```
hbase org.apache.hadoop.hbase.index.mapreduce.HIndexImportTsv -  
Dimporttsv.separator=<separator>
```

```
-Dimporttsv.bulk.output=</path/for/output> -
```

```
Dindexspecs.to.add=<indexspecs> -Dimporttsv.columns=<columns>  
tableName <inputdir>
```

- **-Dimport.separator**: indicates a separator, for example, -  
**Dimport.separator=','**.
- **-Dimport.bulk.output=</path/for/output>**: indicates the output path of the execution result. You need to specify a path that does not exist.
- **<columns>**: Indicates the mapping of the imported data in a table, for example, -  
**Dimporttsv.columns=HBASE\_ROW\_KEY,info:name,info:gender,info:age, address:city,address:province**.
- **<tablename>**: Indicates the name of a table to be operated.
- **<inputdir>**: Indicates the directory where data is loaded in batches.
- **-Dindexspecs.to.add=<indexspecs>**: Indicates the mapping between an index name and a column, for example, -  
**Dindexspecs.to.add='index\_bulk=>info:[age->String]'**. The index composition can be represented as follows:

```
indexNameN=>familyN :[columnQualifierN-> columnQualifierDataType],  
[columnQualifierM-> columnQualifierDataType];familyM:  
[columnQualifierO-> columnQualifierDataType]# indexNameN=>  
familyM: [columnQualifierO-> columnQualifierDataType]
```

Column qualifiers are separated by commas (,).

Example: "index1 => f1:[c1-> String],[c2-> String]"

Column families are separated by semicolons (;).

Example: "index1 => f1:[c1-> String],[c2-> String]; f2:[c3-> Long]"

Multiple indexes are separated by pound keys (#).

Example: "index1 => f1:[c1-> String],[c2-> String]; f2:[c3-> Long]#index2  
=> f2:[c3-> Long]"

The following data types are supported by columns.

Available data types are as follows: STRING, INTEGER, FLOAT, LONG, DOUBLE, SHORT, BYTE, CHAR

#### NOTE

Data types can also be transferred in lowercase.

For example, run the following command:

```
hbase org.apache.hadoop.hbase.index.mapreduce.HIndexImportTsv -  
Dimporttsv.separator=',' -Dimporttsv.bulk.output=/dataOutput -  
Dindexspecs.to.add='index_bulk=>info:[age->String]' -
```

**Dimporttsv.columns=HBASE\_ROW\_KEY,info:name,info:gender,info:age,address:city,address:province bulkTable /datadirImport/data.txt**

Command output:

```
[root@shap000000406 opt]# hbase org.apache.hadoop.hbase.hindex.mapreduce.HIndexImportTsv -
Dimporttsv.separator=';' -Dimporttsv.bulk.output=/dataOutput -Dindexspecs.to.add='index_bulk=>info:
[age->String]' -
Dimporttsv.columns=HBASE_ROW_KEY,info:name,info:gender,info:age,address:city,address:province
bulkTable /datadirImport/data.txt
2018-05-08 21:29:16,059 INFO [main] mapreduce.HFileOutputFormat2: Incremental table bulkTable
output configured.
2018-05-08 21:29:16,069 INFO [main] client.ConnectionManager$HConnectionImplementation:
Closing master protocol: MasterService
2018-05-08 21:29:16,069 INFO [main] client.ConnectionManager$HConnectionImplementation:
Closing zookeeper sessionId=0x80007c2cb4fd5b4d
2018-05-08 21:29:16,072 INFO [main] zookeeper.ZooKeeper: Session: 0x80007c2cb4fd5b4d closed
2018-05-08 21:29:16,072 INFO [main-EventThread] zookeeper.ClientCnxn: EventThread shut down
for session: 0x80007c2cb4fd5b4d
2018-05-08 21:29:16,379 INFO [main] client.ConfiguredRMFailoverProxyProvider: Failing over to 147
2018-05-08 21:29:17,328 INFO [main] input.FileInputFormat: Total input files to process : 1
2018-05-08 21:29:17,413 INFO [main] mapreduce.JobSubmitter: number of splits:1
2018-05-08 21:29:17,430 INFO [main] Configuration.deprecation: io.bytes.per.checksum is
deprecated. Instead, use dfs.bytes-per.checksum
2018-05-08 21:29:17,687 INFO [main] mapreduce.JobSubmitter: Submitting tokens for job:
job_1525338489458_0002
2018-05-08 21:29:18,100 INFO [main] impl.YarnClientImpl: Submitted application
application_1525338489458_0002
2018-05-08 21:29:18,136 INFO [main] mapreduce.Job: The url to track the job: http://
shap000000407:8088/proxy/application_1525338489458_0002/
2018-05-08 21:29:18,136 INFO [main] mapreduce.Job: Running job: job_1525338489458_0002
2018-05-08 21:29:28,248 INFO [main] mapreduce.Job: Job job_1525338489458_0002 running in uber
mode : false
2018-05-08 21:29:28,249 INFO [main] mapreduce.Job: map 0% reduce 0%
2018-05-08 21:29:38,344 INFO [main] mapreduce.Job: map 100% reduce 0%
2018-05-08 21:29:51,421 INFO [main] mapreduce.Job: map 100% reduce 100%
2018-05-08 21:29:51,428 INFO [main] mapreduce.Job: Job job_1525338489458_0002 completed
successfully
2018-05-08 21:29:51,523 INFO [main] mapreduce.Job: Counters: 50
```

4. Run the following command to import the generated HFile to HBase:

**hbase org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles </  
path/for/output> <tablename>**

For example, run the following command:

**hbase org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles /  
dataOutput bulkTable**

Command output:

```
[root@shap000000406 opt]# hbase org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles /
dataOutput bulkTable
2018-05-08 21:30:01,398 WARN [main] mapreduce.LoadIncrementalHFiles: Skipping non-directory
hdfs://hacluster/dataOutput/_SUCCESS
2018-05-08 21:30:02,006 INFO [LoadIncrementalHFiles-0] hfile.CacheConfig: Created cacheConfig:
CacheConfig:disabled
2018-05-08 21:30:02,006 INFO [LoadIncrementalHFiles-2] hfile.CacheConfig: Created cacheConfig:
CacheConfig:disabled
2018-05-08 21:30:02,006 INFO [LoadIncrementalHFiles-1] hfile.CacheConfig: Created cacheConfig:
CacheConfig:disabled
2018-05-08 21:30:02,085 INFO [LoadIncrementalHFiles-2] compress.CodecPool: Got brand-new
decompressor [.snappy]
2018-05-08 21:30:02,120 INFO [LoadIncrementalHFiles-0] mapreduce.LoadIncrementalHFiles: Trying
to load hfile=hdfs://hacluster/dataOutput/address/042426c252f74e859858c7877b95e510
first=12005000201 last=12005000210
2018-05-08 21:30:02,120 INFO [LoadIncrementalHFiles-2] mapreduce.LoadIncrementalHFiles: Trying
to load hfile=hdfs://hacluster/dataOutput/info/f3995920ae0247a88182f637aa031c49
first=12005000201 last=12005000210
2018-05-08 21:30:02,128 INFO [LoadIncrementalHFiles-1] mapreduce.LoadIncrementalHFiles: Trying
to load hfile=hdfs://hacluster/dataOutput/d/c53b252248af42779f29442ab84f86b8 first=\x00index_bulk
```

```
\x00\x00\x00\x00\x00\x00\x00\x0018\x00\x0012005000204 last=\x00index_bulk
\x00\x00\x00\x00\x00\x00\x00\x0032\x00\x0012005000206
2018-05-08 21:30:02,231 INFO [main] client.ConnectionManager$HConnectionImplementation:
Closing master protocol: MasterService
2018-05-08 21:30:02,231 INFO [main] client.ConnectionManager$HConnectionImplementation:
Closing zookeeper sessionid=0x81007c2cf0f55cc5
2018-05-08 21:30:02,235 INFO [main] zookeeper.ZooKeeper: Session: 0x81007c2cf0f55cc5 closed
2018-05-08 21:30:02,235 INFO [main-EventThread] zookeeper.ClientCnxn: EventThread shut down
for session: 0x81007c2cf0f55cc5
```

## 6.8.3 Using an Index Generation Tool

### Scenarios

To quickly create indexes for user data, HBase provides the `TableIndexer` tool for you to create, add, and delete indexes using MapReduce functions. The application scenarios are as follows:

- You want to add an index for a specified column in a table where a large amount of data exists. However, if you use the `addIndicesWithData()` API to add an index, index data corresponding to the related user data will be generated, which is time-consuming. If you use `addIndices()` to create an index, index data corresponding to user data will not be generated. Therefore, to create index data for user data, you can use the `TableIndexer` tool to create an index.

- If the index data is inconsistent with the user data, the tool can be used to rebuild index data.

If you temporarily disable the index, put new data to the disabled index column, and then directly enable the index from the disabled state, index data and user data may be inconsistent. Therefore, you must rebuild all index data before using it again.

- You can use the `TableIndexer` tool to completely delete a large amount of existing index data from a user table.
- For user tables that do not have indexes, this tool allows you to add and build indexes at the same time.

### How to Use

- **Adding a new index to a user table**

The command is as follows:

```
hbase org.apache.hadoop.hbase.hindex.mapreduce.TableIndexer -  
Dtablename.to.index=tablename -Dindexspecs.to.add='idx_0=>cf_0:[q_0-  
>string],[q_1];cf_1:[q_2],[q_3]#idx_1=>cf_1:[q_4]'
```

The following parameters are required.

- **tablename.to.index**: Indicates the name of a table for which an index is created.
- **indexspecs.to.add**: Indicates the mapping between the index name and the column in the corresponding user table.
- **scan.caching** (optional): Contains an integer value, indicating the number of cached rows to be transmitted to the scanner during data table scanning.

The parameters in the preceding command are described as follows:

- **idx\_1**: Indicates an index name.
- **cf\_0**: Indicates the name of a column family.
- **q\_0**: Indicates the name of a column.
- **string**: Indicates a data type. The parameter value can be STRING, INTEGER, FLOAT, LONG, DOUBLE, SHORT, BYTE, or CHAR.

 **NOTE**

- The pound key (#) is used to separate indexes. The semicolon (;) is used to separate column families. The comma (,) is used to separate column qualifiers.
- The column name and its data type must be included in '[]'.
- Column names and their data types are separated by '->'.
- If the data type of a specific column is not specified, the default data type (string) is used.
- If **scan.caching** is not configured, the default value **1000** is used.
- The user table must exist.
- The index specified in the table must not exist.
- If a column family named **d** exists in the user table, you must use the TableIndexer tool to build index data.

After the preceding command is executed, the specified index is added to the table and is in INACTIVE state. This behavior is similar to the **addIndices()** API.

- **Creating index data for existing indexes in a user table**

The command is as follows:

```
hbase org.apache.hadoop.hbase.hindex.mapreduce.TableIndexer -  
Dtablename.to.index=tablename -Dindexnames.to.build = 'idx_0#idx_1'
```

The following parameters are required.

- **tablename.to.index**: Indicates the name of a table for which an index is created.
- **indexspecs.to.build**: Indicates an index name.
- **scan.caching** (optional): Contains an integer value, indicating the number of cached rows to be transmitted to the scanner during data table scanning.

The parameters in the preceding command are described as follows:

- **idx\_1**: Indicates an index name.

 **NOTE**

- The pound key (#) is used to separate index names.
- If **scan.caching** is not configured, the default value **1000** is used.
- The user table must exist.

After the preceding command is executed, the specified index is set to the ACTIVE state. Users can use them when scanning data.

- **Deleting the existing indexes and their data from a user table**

The command is as follows:

```
hbase org.apache.hadoop.hbase.hindex.mapreduce.TableIndexer -  
Dtablename.to.index=tablename -Dindexnames.to.drop='idx_0#idx_1'
```

The following parameters are required.

- **tablename.to.index**: Indicates the name of a table for which an index is created.
- **indexnames.to.drop**: Indicates the name of the index that should be deleted with its data (must exist in the table).
- **scan.caching** (optional): Contains an integer value, indicating the number of cached rows to be transmitted to the scanner during data table scanning.

The parameters in the preceding command are described as follows:

- **idx\_1**: Indicates an index name.

 **NOTE**

- The pound key (#) is used to separate index names.
- If **scan.caching** is not configured, the default value **1000** is used.
- The user table must exist.

After the preceding command is executed, the specified index is deleted from the table.

- **Adding new indexes to user tables and building data based on existing data**

The command is as follows:

```
hbase org.apache.hadoop.hbase.hindex.mapreduce.TableIndexer -  
Dtablename.to.index=tablename -Dindexspecs.to.add='idx_0 => cf_0:[q_0-  
> string],[q_1];cf_1:[q_2],[q_3]#idx_1 => cf_1:[q_4]' -  
Dindexnames.to.build='idx_0'
```

 **NOTE**

- The parameters are the same as the previous ones.
- The user table must exist.
- The indexes specified in **indexspecs.to.add** must not exist in the table.
- The index names specified in **indexnames.to.build** must exist in the table or be part of the value of **indexspecs.to.add**.

After the preceding command is executed, all indexes specified in **indexspecs.to.add** will be added to this table, and index data will be built for all specified indexes using **indexnames.to.build**.

## 6.9 Configuring HBase DR

### Scenario

HBase disaster recovery (DR), a key feature that is used to ensure high availability (HA) of the HBase cluster system, provides the real-time remote DR function for HBase. HBase DR provides basic O&M tools, including tools for maintaining and re-establishing DR relationships, verifying data, and querying data synchronization progress. To implement real-time DR, back up data of an HBase cluster to another HBase cluster. DR in the HBase table common data writing and BulkLoad batch data writing scenarios is supported.

## Prerequisites

- The active and standby clusters are successfully installed and started, and you have the administrator permissions on the clusters.
- Ensure that the network connection between the active and standby clusters is normal and ports are available.
- If the active cluster is deployed in security mode and is not managed by one FusionInsight Manager, cross-cluster trust relationship has been configured for the active and standby clusters.. If the active cluster is deployed in normal mode, no cross-cluster mutual trust is required.
- Cross-cluster replication has been configured for the active and standby clusters. For details, see [Enabling Cross-Cluster Copy](#).
- Time is consistent between the active and standby clusters and the NTP service on the active and standby clusters uses the same time source.
- The mapping between host names and service IP addresses of all nodes in the active and standby clusters have been configured in the **hosts** file of these nodes.

### NOTE

If the client of the active cluster is installed on a node outside the cluster, the mapping between host names and service IP addresses of all nodes in the active and standby clusters must have been configured in the **hosts** file of these nodes.

- The network bandwidth between the active and standby clusters is determined based on service volume, which cannot be less than the possible maximum service volume.
- The MRS versions of the active and standby clusters must be the same.
- The scale of the standby cluster must be greater than or equal to that of the active cluster.

## Constraints

- Although DR provides the real-time data replication function, the data synchronization progress is affected by many factors, such as the service volume in the active cluster and the health status of the standby cluster. In normal cases, the standby cluster should not take over services. In extreme cases, system maintenance personnel and other decision makers determine whether the standby cluster takes over services according to the current data synchronization indicators.
- HBase clusters must be deployed in active/standby mode.
- Table-level operations on the DR table of the standby cluster are forbidden, such as modifying the table attributes and deleting the table. Misoperations on the standby cluster will cause data synchronization failure of the active cluster. As a result, table data in the standby cluster is lost.
- If the DR data synchronization function is enabled for HBase tables of the active cluster, the DR table structure of the standby cluster needs to be modified to ensure table structure consistency between the active and standby clusters during table structure modification.

## Procedure

### Configuring the common data writing DR parameters for the active cluster

- Step 1** Log in to Manager of the active cluster.
- Step 2** Choose **Cluster** > *Name of the desired cluster* > **Services** > **HBase** > **Configurations** and click **All Configurations**. The HBase configuration page is displayed.
- Step 3** (Optional) **Table 6-6** describes the optional configuration items during HBase DR. You can set the parameters based on the description or use the default values.

**Table 6-6** Optional configuration items

Navigation Path	Parameter	Default Value	Description
HMaster > Performance	hbase.master.logcleaner.ttl	600000	Specifies the retention period of HLog. If the value is set to <b>604800000</b> (unit: millisecond), the retention period of HLog is 7 days.
	hbase.master.cleaner.interval	60000	Interval for the HMaster to delete historical HLog files. The HLog that exceeds the configured period will be automatically deleted. You are advised to set it to the maximum value to save more HLogs.
RegionServer > Replication	replication.source.size.capacity	16777216	Maximum size of edits, in bytes. If the edit size exceeds the value, HLog edits will be sent to the standby cluster.
	replication.source.nb.capacity	25000	Maximum number of edits, which is another condition for triggering HLog edits to be sent to the standby cluster. After data in the active cluster is synchronized to the standby cluster, the active cluster reads and sends data in HLog according to this parameter value. This parameter is used together with <b>replication.source.size.capacity</b> .
	replication.source.maxretriesmultiplier	10	Maximum number of retries when an exception occurs during replication.
	replication.source.sleepforretries	1000	Retry interval (Unit: ms)

Navigation Path	Parameter	Default Value	Description
	hbase.regionserver.replication.handler.count	6	Number of replication RPC server instances on RegionServer

### Configuring the BulkLoad batch data writing DR parameters for the active cluster

**Step 4** Determine whether to enable the BulkLoad batch data writing DR function.

If yes, go to [Step 5](#).

If no, go to [Step 8](#).

**Step 5** Choose **Cluster** > *Name of the desired cluster* > **Services** > **HBase** > **Configurations** and click **All Configurations**. The HBase configuration page is displayed.

**Step 6** Search for **hbase.replication.bulkload.enabled** and change its value to **true** to enable the BulkLoad batch data writing DR function.

**Step 7** Search for **hbase.replication.cluster.id** and change the HBase ID of the active cluster. The ID is used by the standby cluster to connect to the active cluster. The value can contain uppercase letters, lowercase letters, digits, and underscores (\_), and cannot exceed 30 characters.

### Restarting the HBase service and install the client

**Step 8** Click **Save**. In the displayed dialog box, click **OK**. Restart the HBase service.

**Step 9** In the active and standby clusters, choose **Cluster** > *Name of the desired cluster* > **Service** > **HBase** > **More** > **Download Client** to download the client and install it.

### Adding the DR relationship between the active and standby clusters

**Step 10** Log in as user **hbase** to the HBase shell page of the active cluster.

**Step 11** Run the following command on HBase Shell to create the DR synchronization relationship between the active cluster HBase and the standby cluster HBase.

```
add_peer 'Standby cluster ID', CLUSTER_KEY => "ZooKeeper service IP address in the standby cluster", CONFIG => {"hbase.regionserver.kerberos.principal" => "Standby cluster RegionServer principal", "hbase.master.kerberos.principal" => "Standby cluster HMaster principal"}
```

- The standby cluster ID indicates the ID for the active cluster to recognize the standby cluster. Enter an ID. The value can be specified randomly. Digits are recommended.
- The ZooKeeper address of the standby cluster includes the service IP address of ZooKeeper, the port for listening to client connections, and the HBase root directory of the standby cluster on ZooKeeper.

- Search for **hbase.master.kerberos.principal** and **hbase.regionserver.kerberos.principal** in the HBase **hbase-site.xml** configuration file of the standby cluster.

For example, to add the DR relationship between the active and standby clusters, run the **add\_peer** '*Standby cluster ID*', **CLUSTER\_KEY** =>

```
"192.168.40.2,192.168.40.3,192.168.40.4:24002:/hbase", CONFIG =>
{"hbase.regionserver.kerberos.principal" => "hbase/
hadoop.hadoop.com@HADOOP.COM", "hbase.master.kerberos.principal" =>
"hbase/hadoop.hadoop.com@HADOOP.COM"}
```

**Step 12** (Optional) If the BulkLoad batch data write DR function is enabled, the HBase client configuration of the active cluster must be copied to the standby cluster.

- Create the **/hbase/replicationConf/hbase.replication.cluster.id of the active cluster** directory in the HDFS of the standby cluster.
- HBase client configuration file, which is copied to the **/hbase/replicationConf/hbase.replication.cluster.id of the active cluster** directory of the HDFS of the standby cluster.

Example: **hdfs dfs -put HBase/hbase/conf/core-site.xml HBase/hbase/conf/hdfs-site.xml HBase/hbase/conf/yarn-site.xml hdfs://NameNode IP.25000/hbase/replicationConf/source\_cluster**

#### Enabling HBase DR to synchronize data

**Step 13** Check whether a naming space exists in the HBase service instance of the standby cluster and the naming space has the same name as the naming space of the HBase table for which the DR function is to be enabled.

- If the same namespace exists, go to [Step 14](#).
- If no, create a naming space with the same name in the HBase shell of the standby cluster and go to [Step 14](#).

**Step 14** In the HBase shell of the active cluster, run the following command as user **hbase** to enable the real-time DR function for the table data of the active cluster to ensure that the data modified in the active cluster can be synchronized to the standby cluster in real time.

You can only synchronize the data of one HTable at a time.

```
enable_table_replication 'table name'
```

 NOTE

- If the standby cluster does not contain a table with the same name as the table for which real-time synchronization is to be enabled, the table is automatically created.
- If a table with the same name as the table for which real-time synchronization is to be enabled exists in the standby cluster, the structures of the two tables must be the same.
- If the encryption algorithm SMS4 or AES is configured for '*Table name*', the function for synchronizing data from the active cluster to the standby cluster cannot be enabled for the HBase table.
- If the standby cluster is offline or has tables with the same name but different structures, the DR function cannot be enabled.
- If the DR data synchronization function is enabled for some Phoenix tables in the active cluster, the standby cluster cannot have common HBase tables with the same names as the Phoenix tables in the active cluster. Otherwise, the DR function fails to be enabled or the tables with the names in the standby cluster cannot be used properly.
- If the DR data synchronization function is enabled for Phoenix tables in the active cluster, you need to enable the DR data synchronization function for the metadata tables of the Phoenix tables. The metadata tables include SYSTEM.CATALOG, SYSTEM.FUNCTION, SYSTEM.SEQUENCE, and SYSTEM.STATS.
- If the DR data synchronization function is enabled for HBase tables of the active cluster, after adding new indexes to HBase tables, you need to manually add secondary indexes to DR tables in the standby cluster to ensure secondary index consistency between the active and standby clusters.

**Step 15** (Optional) If HBase does not use Ranger, run the following command as user **hbase** in the HBase shell of the active cluster to enable the real-time permission to control data DR function for the HBase tables in the active cluster.

```
enable_table_replication 'hbase:acl'
```

### Creating Users

**Step 16** Log in to FusionInsight Manager of the standby cluster, choose **System > Permission > Role > Create Role** to create a role, and add the same permission for the standby data table to the role based on the permission of the HBase source data table of the active cluster.

**Step 17** Choose **System > Permission > User > Create** to create a user. Set the **User Type** to **Human-Machine** or **Machine-Machine** based on service requirements and add the user to the created role. Access the HBase DR data of the standby cluster as the newly created user.

 NOTE

- After the permission of the active HBase source data table is modified, to ensure that the standby cluster can properly read data, modify the role permission for the standby cluster.
- If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. For details, see [Adding a Ranger Access Permission Policy for HBase](#).

### Synchronizing the table data of the active cluster

**Step 18** After HBase DR is configured and data synchronization is enabled, check whether tables and data exist in the active cluster and whether the historical data needs to be synchronized to the standby cluster.

- If yes, a table exists and data needs to be synchronized. Log in as the HBase table user to the node where the HBase client of the active cluster is installed

and run the kinit username to authenticate the identity. The user must have the read and write permissions on tables and the execute permission on the **hbase:meta** table. Then go to [Step 19](#).

- If no, no further action is required.

**Step 19** The HBase DR configuration does not support automatic synchronization of historical data in tables. You need to back up the historical data of the active cluster and then manually restore the historical data in the standby cluster.

Manual recovery refers to the recovery of a single table, which can be performed through Export, DistCp, or Import.

To manually recover a single table, perform the following steps:

1. Export table data from the active cluster.

**hbase org.apache.hadoop.hbase.mapreduce.Export -**  
**Dhbase.mapreduce.include.deleted.rows=true** *Table name Directory where the source data is stored*

Example: **hbase org.apache.hadoop.hbase.mapreduce.Export -**  
**Dhbase.mapreduce.include.deleted.rows=true t1 /user/hbase/t1**

2. Copy the data that has been exported to the standby cluster.

**hadoop distcp** *directory where the source data is stored on the active cluster*  
**hdfs://ActiveNameNodeIP:8020/directory where the source data is stored on the standby cluster**

**ActiveNameNodeIP** indicates the IP address of the active NameNode in the standby cluster.

Example: **hadoop distcp /user/hbase/t1 hdfs://192.168.40.2:8020/user/hbase/t1**

3. Import data to the standby cluster as the HBase table user of the standby cluster.

On the HBase shell screen of the standby cluster, run the following command as user **hbase** to retain the data writing status:

**set\_clusterState\_active**

The command is run successfully if the following information is displayed:

```
hbase(main):001:0> set_clusterState_active  
=> true
```

**hbase org.apache.hadoop.hbase.mapreduce.Import -**  
**Dimport.bulk.output=Directory where the output data is stored in the standby cluster** *Table name Directory where the source data is stored in the standby cluster*

**hbase org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles**  
**Directory where the output data is stored in the standby cluster** *Table name*

Example:

```
hbase(main):001:0> set_clusterState_active  
=> true
```

**hbase org.apache.hadoop.hbase.mapreduce.Import -**  
**Dimport.bulk.output=/user/hbase/output\_t1 t1 /user/hbase/t1**

**hbase org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles /user/hbase/output\_t1 t1**

**Step 20** Run the following command on the HBase client to check the synchronized data of the active and standby clusters. After the DR data synchronization function is enabled, you can run this command to check whether the newly synchronized data is consistent.

**hbase org.apache.hadoop.hbase.mapreduce.replication.VerifyReplication --starttime=*Start time* --endtime=*End time* *Column family name* *ID of the standby cluster* *Table name***

 **NOTE**

- The start time must be earlier than the end time.
- The values of **starttime** and **endtime** must be in the timestamp format. You need to run **date -d "2015-09-30 00:00:00" +%s** to change a common time format to a timestamp format.

**Specify the data writing status for the active and standby clusters.**

**Step 21** On the HBase shell screen of the active cluster, run the following command as user **hbase** to retain the data writing status:

**set\_clusterState\_active**

The command is run successfully if the following information is displayed:

```
hbase(main):001:0> set_clusterState_active  
=> true
```

**Step 22** On the HBase shell screen of the standby cluster, run the following command as user **hbase** to retain the data read-only status:

**set\_clusterState\_standby**

The command is run successfully if the following information is displayed:

```
hbase(main):001:0> set_clusterState_standby  
=> true
```

**----End**

## Related Commands

**Table 6-7** HBase DR

Operation	Command	Description
Set up a DR relationship.	<pre>add_peer '<i>Standby cluster ID</i>, CLUSTER_KEY =&gt; "<i>Standby cluster ZooKeeper service IP address</i>", CONFIG =&gt; {"hbase.regionserver.kerberos.principal" =&gt; "<i>Standby cluster RegionServer principal</i>", "hbase.master.kerberos.principal" =&gt; "<i>Standby cluster HMaster principal</i>"}</pre> <p><b>add_peer '1','zk1,zk2,zk3:2181:/hbase1'</b> 2181: port number of ZooKeeper in the cluster</p>	<p>Set up the relationship between the active cluster and the standby cluster.</p> <p>If BulkLoad batch data write DR is enabled:</p> <ul style="list-style-type: none"> <li>• Create the <b>/hbase/replicationConf/hbase.replication.cluster.id of the active cluster</b> directory in the HDFS of the standby cluster.</li> <li>• HBase client configuration file, which is copied to the <b>/hbase/replicationConf/hbase.replication.cluster.id of the active cluster</b> directory of the HDFS of the standby cluster.</li> </ul>
Remove the DR relationship.	<pre>remove_peer '<i>Standby cluster ID</i>'</pre> <p>Example: <b>remove_peer '1'</b></p>	Remove standby cluster information from the active cluster.
Querying the DR Relationship	<b>list_peers</b>	Query standby cluster information (mainly Zookeeper information) in the active cluster.
Enable the real-time user table synchronization function.	<pre>enable_table_replication '<i>Table name</i>'</pre> <p>Example: <b>enable_table_replication 't1'</b></p>	Synchronize user tables from the active cluster to the standby cluster.
Disable the real-time user table synchronization function.	<pre>disable_table_replication '<i>Table name</i>'</pre> <p>Example: <b>disable_table_replication 't1'</b></p>	Do not synchronize user tables from the active cluster to the standby cluster.

Operation	Command	Description
<p>Verify data of the active and standby clusters.</p>	<p><b>bin/hbase</b>  <b>org.apache.hadoop.hbase.mapreduce.replication.VerifyReplication</b> <i>--starttime=Start time --endtime=End time Column family name Standby cluster ID Table name</i></p>	<p>Verify whether data of the specified table is the same between the active cluster and the standby cluster.</p> <p>The description of the parameters in this command is as follows:</p> <ul style="list-style-type: none"> <li>● Start time: If start time is not specified, the default value <b>0</b> will be used.</li> <li>● End time: If end time is not specified, the time when the current operation is submitted will be used by default.</li> <li>● Table name: If a table name is not entered, all user tables for which the real-time synchronization function is enabled will be verified by default.</li> </ul>
<p>Switch the data writing status.</p>	<p><b>set_clusterState_active</b>  <b>set_clusterState_standby</b></p>	<p>Specifies whether data can be written to the cluster HBase tables.</p>

Operation	Command	Description
Add or update the active cluster HDFS configurations saved in the peer cluster.	<b>hdfs dfs -put -f HBase/hbase/conf/core-site.xml HBase/hbase/conf/hdfs-site.xml HBase/hbase/conf/yarn-site.xml hdfs://Standby cluster NameNode IP:PORT/hbase/replicationConf/Active cluster/hbase.replication.cluster.id</b>	<p>Enable DR for data including bulkload data. When HDFS parameters are modified in the active cluster, the modification cannot be automatically synchronized from the active cluster to the standby cluster. You need to manually run the command to synchronize configuration. The affected parameters are as follows:</p> <ul style="list-style-type: none"> <li>• fs.defaultFS</li> <li>• dfs.client.failover.proxy.provider.hacluster</li> <li>• dfs.client.failover.connection.retries.on.timeouts</li> <li>• dfs.client.failover.connection.retries</li> </ul> <p>For example, change <b>fs.defaultFS</b> to <b>hdfs://hacluster_sale</b>, HBase client configuration file, which is copied to the <b>/hbase/replicationConf/hbase.replication.cluster.id of the active cluster</b> directory of the HDFS of the standby cluster.</p>

## 6.10 Performing an HBase DR Service Switchover

### Scenario

The system administrator can configure HBase cluster DR to improve system availability. If the active cluster in the DR environment is faulty and the connection to the HBase upper-layer application is affected, you need to configure the standby cluster information for the HBase upper-layer application so that the application can run in the standby cluster.

### Impact on the System

After a service switchover, data written to the standby cluster is not synchronized to the active cluster by default. Add the active cluster is recovered, the data newly generated in the standby cluster needs to be synchronized to the active cluster by backup and recovery. If automatic data synchronization is required, you need to switch over the active and standby HBase DR clusters.

## Procedure

**Step 1** Log in to FusionInsight Manager of the standby cluster.

**Step 2** Download and install the HBase client.

**Step 3** On the HBase client of the standby cluster, run the following command as user **hbase** to enable the data writing status in the standby cluster.

```
kinit hbase
```

```
hbase shell
```

```
set_clusterState_active
```

The command is run successfully if the following information is displayed:

```
hbase(main):001:0> set_clusterState_active  
=> true
```

**Step 4** Check whether the original configuration files **hbase-site.xml**, **core-site.xml**, and **hdfs-site.xml** of the HBase upper-layer application are modified to adapt to the application running.

- If yes, update the related content to the new configuration file and replace the old configuration file.
- If no, use the new configuration file to replace the original configuration file of the HBase upper-layer application.

**Step 5** Configure the network connection between the host where the HBase upper-layer application is located and the standby cluster.

### NOTE

If the host where the client is installed is not a node in the cluster, configure network connections for the client to prevent errors when you run commands on the client.

1. Ensure that the host where the client is installed can communicate with the hosts listed in the **hosts** file in the directory where the client installation package is decompressed.
2. If the host where the client is located is not a node in the cluster, you need to set the mapping between the host name and the IP address (service plan) in the `/etc/hosts` file on the host. The host names and IP addresses must be mapped one by one.

**Step 6** Set the time of the host where the HBase upper-layer application is located to be the same as that of the standby cluster. The time difference must be less than 5 minutes.

**Step 7** Check the authentication mode of the active cluster.

- If the security mode is used, go to [Step 8](#).
- If the normal mode is used, no further action is required.

**Step 8** Obtain the **keytab** and **krb5.conf** configuration files of the HBase upper-layer application user.

1. On FusionInsight Manager of the standby cluster, choose **System > Permission > User**.

2. Locate the row that contains the target user, click **More > Download Authentication Credential** in the **Operation** column, and download the **keytab** file to the local PC.
3. Decompress the package to obtain **user.keytab** and **krb5.conf**.

**Step 9** Use the **user.keytab** and **krb5.conf** files to replace the original files in the HBase upper-layer application.

**Step 10** Stop upper-layer applications.

**Step 11** Determine whether to switch over the active and standby HBase clusters. If the switchover is not performed, data will not be synchronized.

- If yes, switch over the active and standby HBase DR clusters. For details, see [Performing an HBase DR Active/Standby Cluster Switchover](#). Then, go to [Step 12](#).
- If no, go to [Step 12](#).

**Step 12** Start the upper-layer services.

----End

## 6.11 Configuring HBase Data Compression and Encoding

### Scenario

HBase encodes data blocks in HFiles to reduce duplicate keys in KeyValues, reducing used space. Currently, the following data block encoding modes are supported: NONE, PREFIX, DIFF, FAST\_DIFF, and ROW\_INDEX\_V1. NONE indicates that data blocks are not encoded. HBase also supports compression algorithms for HFile compression. The following algorithms are supported by default: NONE, GZ, SNAPPY, and ZSTD. NONE indicates that HFiles are not compressed.

The two methods are used on the HBase column family. They can be used together or separately.

### Prerequisites

- You have installed an HBase client. For example, the client is installed in **opt/client**.
- If authentication has been enabled for HBase, you must have the corresponding operation permissions. For example, you must have the creation (C) or administration (A) permission on the corresponding namespace or higher-level items to create a table, and the creation (C) or administration (A) permission on the created table or higher-level items to modify a table. For details about how to grant permissions, see [Creating HBase Roles](#).

### Procedure

#### Setting data block encoding and compression algorithms during creation

- **Method 1: Using hbase shell**

- a. Log in to the node where the client is installed as the client installation user.
- b. Run the following command to go to the client directory:  
**cd /opt/client**
- c. Run the following command to configure environment variables:  
**source bigdata\_env**
- d. If the Kerberos authentication is enabled for the current cluster, run the following command to authenticate the user. If Kerberos authentication is disabled for the current cluster, skip this step:  
**kinit Component service user**  
For example, **kinit hbaseuser**.
- e. Run the following HBase client command:  
**hbase shell**
- f. Create a table.  
**create 't1', {NAME => 'f1', COMPRESSION => 'SNAPPY', DATA\_BLOCK\_ENCODING => 'FAST\_DIFF'}**

 **NOTE**

- *t1*: indicates the table name.
- *f1*: indicates the column family name.
- *SNAPPY*: indicates the column family uses the SNAPPY compression algorithm.
- *FAST\_DIFF*: indicates FAST\_DIFF is used for encoding.
- The parameter in the braces specifies the column family. You can specify multiple column families using multiple braces and separate them by commas (,). For details about table creation statements, run the **help 'create'** statement in the HBase shell.

- **Method 2: Using Java APIs**

The following code snippet shows only how to set the encoding and compression modes of a column family when creating a table.

```
TableDescriptorBuilder htd = TableDescriptorBuilder.newBuilder(TableName.valueOf("t1")); // Create a descriptor for table t1.
ColumnFamilyDescriptorBuilder hcd =
ColumnFamilyDescriptorBuilder.newBuilder(Bytes.toBytes("f1")); // Create a builder for column family f1.
hcd.setDataBlockEncoding(DataBlockEncoding.FAST_DIFF); // Set the encoding mode of column family f1 to FAST_DIFF.
hcd.setCompressionType(Compression.Algorithm.SNAPPY); // Set the compression algorithm of column family f1 to SNAPPY.
htd.setColumnFamily(hcd.build()) // Add the column family f1 to the descriptor of table t1.
```

### Setting or modifying the data block encoding mode and compression algorithm for an existing table

- **Method 1: Using hbase shell**

- a. Log in to the node where the client is installed as the client installation user.
- b. Run the following command to go to the client directory:  
**cd /opt/client**

- c. Run the following command to configure environment variables:  
**source bigdata\_env**
  - d. If the Kerberos authentication is enabled for the current cluster, run the following command to authenticate the user. If Kerberos authentication is disabled for the current cluster, skip this step:  
**kinit Component service user**  
For example, **kinit hbaseuser**.
  - e. Run the following HBase client command:  
**hbase shell**
  - f. Run the following command to modify the table:  
**alter 't1', {NAME => 'f1', COMPRESSION => 'SNAPPY',  
DATA\_BLOCK\_ENCODING => 'FAST\_DIFF'}**
- **Method 2: Using Java APIs**

The following code snippet shows only how to modify the encoding and compression modes of a column family in an existing table. For complete code for modifying a table and how to use the code to modify a table, see "HBase Development Guide".

```
TableDescriptor htd = admin.getDescriptor(TableName.valueOf("t1")); // Obtain the descriptor of table t1.
ColumnFamilyDescriptor originCF = htd.getColumnFamily(Bytes.toBytes("f1")); // Obtain the descriptor of column family f1.
builder.ColumnFamilyDescriptorBuilder hcd = ColumnFamilyDescriptorBuilder.newBuilder(originCF); // Create a builder based on the existing column family attributes.
hcd.setDataBlockEncoding(DataBlockEncoding.FAST_DIFF); // Change the encoding mode of the column family to FAST_DIFF.
hcd.setCompressionType(Compression.Algorithm.SNAPPY); // Change the compression algorithm of the column family to SNAPPY.
admin.modifyColumnFamily(TableName.valueOf("t1"), hcd.build()); // Submit to the server to modify the attributes of column family f1.
```

After the modification, the encoding and compression modes of the existing HFile will take effect after the next compaction.

## 6.12 Performing an HBase DR Active/Standby Cluster Switchover

### Scenario

The HBase cluster in the current environment is a DR cluster. Due to some reasons, the active and standby clusters need to be switched over. That is, the standby cluster becomes the active cluster, and the active cluster becomes the standby cluster.

### Impact on the System

After the active and standby clusters are switched over, data cannot be written to the original active cluster, and the original standby cluster becomes the active cluster to take over upper-layer services.

### Procedure

#### Ensuring that upper-layer services are stopped

**Step 1** Ensure that the upper-layer services have been stopped. If not, perform operations by referring to [Performing an HBase DR Service Switchover](#).

**Disabling the write function of the active cluster**

**Step 2** Download and install the HBase client.

**Step 3** On the HBase client of the standby cluster, run the following command as user **hbase** to disable the data write function of the standby cluster:

**kinit hbase**

**hbase shell**

**set\_clusterState\_standby**

The command is run successfully if the following information is displayed:

```
hbase(main):001:0> set_clusterState_standby  
=> true
```

**Checking whether the active/standby synchronization is complete**

**Step 4** Run the following command to ensure that the current data has been synchronized (SizeOfLogQueue=0 and SizeOfLogToReplicate=0 are required). If the values are not 0, wait and run the following command repeatedly until the values are 0.

**status 'replication'**

**Disabling synchronization between the active and standby clusters**

**Step 5** Query all synchronization clusters and obtain the value of **PEER\_ID**.

**list\_peers**

**Step 6** Delete all synchronization clusters.

**remove\_peer 'Standby cluster ID'**

Example:

**remove\_peer '1'**

**Step 7** Query all synchronized tables.

**list\_replicated\_tables**

**Step 8** Disable all synchronized tables queried in the preceding step.

**disable\_table\_replication 'Table name'**

Example:

**disable\_table\_replication 't1'**

**Performing an active/standby switchover**

**Step 9** Reconfigure HBase DR. For details, see [Configuring HBase DR](#).

----End

## 6.13 Community BulkLoad Tool

The Apache HBase official website provides the function of importing data in batches. For details, see the description of the **Import** and **ImportTsv** tools at <http://hbase.apache.org/2.2/book.html#tools>.

## 6.14 Configuring the MOB

### Scenario

In the actual application scenario, data in various sizes needs to be stored, for example, image data and documents. Data whose size is smaller than 10 MB can be stored in HBase. HBase can yield the best read-and-write performance for data whose size is smaller than 100 KB. If the size of data stored in HBase is greater than 100 KB or even reaches 10 MB and the same number of data files are inserted, the total data amount is large, causing frequent compaction and split, high CPU consumption, high disk I/O frequency, and low performance.

MOB data (100 KB to 10 MB data) is stored in a file system (such as the HDFS) in the HFile format. Files are centrally managed using the `expiredMobFileCleaner` and `Sweeper` tools. The addresses and size of files are stored in the HBase store as values. This greatly decreases the compaction and split frequency in HBase and improves performance.

The MOB function of HBase is enabled by default. For details about related configuration items, see [Table 6-8](#). To use the MOB function, you need to specify the MOB mode for storing data in the specified column family when creating a table or modifying table attributes.

### Configuration Description

To enable the HBase MOB function, you need to specify the MOB mode for storing data in the specified column family when creating a table or modifying table attributes.

Use code to declare that the MOB mode for storing data is used:

```
HColumnDescriptor hcd = new HColumnDescriptor("f");  
hcd.setMobEnabled(true);
```

Use code to declare that the MOB mode for storing data is used, the unit of `MOB_THRESHOLD` is byte:

```
hbase(main):009:0> create 't3',{NAME => 'd', MOB_THRESHOLD => '102400', IS_MOB => 'true'}
```

```
0 row(s) in 0.3450 seconds
```

```
=> Hbase::Table - t3  
hbase(main):010:0> describe 't3'  
Table t3 is ENABLED
```

```
t3
```

```
COLUMN FAMILIES DESCRIPTION
```

```
{NAME => 'd', MOB_THRESHOLD => '102400', VERSIONS => '1', KEEP_DELETED_CELLS => 'FALSE',
DATA_BLOCK_ENCODING => 'NONE',
TTL => 'FOREVER', MIN_VERSIONS => '0', REPLICATION_SCOPE => '0', BLOOMFILTER => 'ROW',
IN_MEMORY => 'false', IS_MOB => 'true', COMPRESSION => 'NONE', BLOCKCACHE => 'true', BLOCKSIZE =>
'65536'}
```

1 row(s) in 0.0170 seconds

**Navigation path for setting parameters:**

On FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **HBase** > **Configurations** > **All Configurations**. Enter a parameter name in the search box.

**Table 6-8** Parameter description

Parameter	Description	Default Value
hbase.mob.file.cache.size	Size of the opened file handle cache. If this parameter is set to a large value, more file handles can be cached, reducing the frequency of opening and closing files. However, if this parameter is set to a large value, too many file handles will be opened. The default value is <b>1000</b> . This parameter is configured on the ResionServer.	1000
hbase.mob.cache.evict.period	Expiration time of cached MOB files in the MOB cache, in seconds.	3600
hbase.mob.cache.evict.remain.ratio	Ratio of the number of retained files after MOB cache reclamation to the number of cached files. <b>hbase.mob.cache.evict.remain.ratio</b> is an algorithm factor. When the number of cached MOB files reaches the product of <b>hbase.mob.file.cache.size</b> <b>hbase.mob.cache.evict.remain.ratio</b> , cache reclamation is triggered.	0.5
hbase.master.mob.ttl.cleaner.period	Interval for deleting expired files, in seconds. The default value is one day (86,400 seconds). <b>NOTE</b> If the validity period of an MOB file expires, that is, the file has been created for more than 24 hours, the MOB file will be deleted by the tool for deleting expired MOB files.	86400

## 6.15 Configuring Secure HBase Replication

### Scenario

This topic provides the procedure to configure the secure HBase replication during cross-realm Kerberos setup in security mode.

## Prerequisites

- Mapping for all the FQDNs to their realms should be defined in the Kerberos configuration file.
- The passwords and keytab files of **ONE.COM** and **TWO.COM** must be the same.

## Procedure

### Step 1 Create krbtgt principals for the two realms.

For example, if you have two realms called **ONE.COM** and **TWO.COM**, you need to add the following principals: **krbtgt/ONE.COM@TWO.COM** and **krbtgt/TWO.COM@ONE.COM**.

Add these two principals at both realms.

```
kadmin: addprinc -e "<enc_type_list>" krbtgt/ONE.COM@TWO.COM  
kadmin: addprinc -e "<enc_type_list>" krbtgt/TWO.COM@ONE.COM
```

#### NOTE

There must be at least one common keytab mode between these two realms.

### Step 2 Add rules for creating short names in Zookeeper.

**Dzookeeper.security.auth\_to\_local** is a parameter of the ZooKeeper server process. Following is an example rule that illustrates how to add support for the realm called **ONE.COM**. The principal has two members (such as **service/instance@ONE.COM**).

```
Dzookeeper.security.auth_to_local=RULE:[2:$1@$0](.*@\QONE.COM\E$s)/@\QONE.COM\E$//DEFAULT
```

The above code example adds support for the **ONE.COM** realm in a different realm. Therefore, in the case of replication, you must add a rule for the master cluster realm in the slave cluster realm. **DEFAULT** is for defining the default rule.

### Step 3 Add rules for creating short names in the Hadoop processes.

The following is the **hadoop.security.auth\_to\_local** property in the **core-site.xml** file in the slave cluster HBase processes. For example, to add support for the **ONE.COM** realm:

```
<property>  
<name>hadoop.security.auth_to_local</name>  
<value>RULE:[2:$1@$0](.*@\QONE.COM\E$s)/@\QONE.COM\E$//DEFAULT</value>  
</property>
```

#### NOTE

If replication for bulkload data is enabled, then the same property for supporting the slave realm needs to be added in the **core-site.xml** file in the master cluster HBase processes.

Example:

```
<property>  
<name>hadoop.security.auth_to_local</name>  
<value>RULE:[2:$1@$0](.*@\QTWO.COM\E$s)/@\QTWO.COM\E$//DEFAULT</value>  
</property>
```

----End

## 6.16 Configuring Region In Transition Recovery Chore Service

### Scenario

In a faulty environment, there are possibilities that a region may be stuck in transition for longer duration due to various reasons like slow region server response, unstable network, ZooKeeper node version mismatch. During region transition, client operation may not work properly as some regions will not be available.

### Configuration

A chore service should be scheduled at HMaster to identify and recover regions that stay in the transition state for a long time.

The following table describes the parameters for enabling this function.

**Table 6-9** Parameters

Parameter	Description	Default Value
hbase.region.assignment.auto.recovery.enabled	Configuration parameter used to enable/disable the region assignment recovery thread feature.	true

## 6.17 Using a Secondary Index

### Scenario

HIndex enables HBase indexing based on specific column values, making the retrieval of data highly efficient and fast.

### Constraints

- Column families are separated by semicolons (;).
- Columns and data types must be contained in square brackets ([]).
- The column data type is specified by using -> after the column name.
- If the column data type is not specified, the default data type (string) is used.
- The number sign (#) is used to separate two index details.
- The following is an optional parameter:  
-Dscan.caching: number of cached rows when the data table is scanned.  
The default value is set to 1000.
- Indexes are created for a single region to repair damaged indexes.

This function is not used to generate new indexes.

## Procedure

**Step 1** Install the HBase client. For details, see [Using an HBase Client](#).

**Step 2** Go to the client installation directory, for example, `/opt/client`.

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** If the cluster is in security mode, run the following command to authenticate the user. In normal mode, user authentication is not required.

```
kinit Component service user
```

**Step 5** Run the following command to access HIndex:

```
hbase org.apache.hadoop.hbase.hindex.mapreduce.TableIndexer
```

**Table 6-10** Common HIndex commands

Description	Command
Add Index	TableIndexer-Dtablename.to.index=table1 - Dindexspecs.to.add='IDX1=>cf1:[q1->datatype],[q2],[q3];cf2: [q1->datatype],[q2->datatype]#IDX2=>cf1:[q5]'
Create Index	TableIndexer -Dtablename.to.index=table1 - Dindexnames.to.build='IDX1#IDX2'
Delete Index	TableIndexer -Dtablename.to.index=table1 - Dindexnames.to.drop='IDX1#IDX2'
Disable Index	TableIndexer -Dtablename.to.index=table1 - Dindexnames.to.disable='IDX1#IDX2'
Add and Create Index	TableIndexer -Dtablename.to.index=table1 - Dindexspecs.to.add='IDX1=>cf1:[q1->datatype],[q2],[q3];cf2: [q1->datatype],[q2->datatype]#IDX2=>cf1:[q5] - Dindexnames.to.build='IDX1'
Create Index for a Single Region	TableIndexer -Dtablename.to.index=table1 - Dregion.to.index=regionEncodedName - Dindexnames.to.build='IDX1#IDX2'

 NOTE

- **IDX1**: indicates the index name.
- **cf1**: indicates the column family name.
- **q1**: indicates the column name.
- **datatype**: indicates the data type, including String, Integer, Double, Float, Long, Short, Byte and Char.

----End

## 6.18 HBase Log Overview

### Log Description

**Log path:** The default storage path of HBase logs is `/var/log/Bigdata/hbase/Role name`.

- HMaster: `/var/log/Bigdata/hbase/hm` (run logs) and `/var/log/Bigdata/audit/hbase/hm` (audit logs)
- RegionServer: `/var/log/Bigdata/hbase/rs` (run logs) and `/var/log/Bigdata/audit/hbase/rs` (audit logs)
- ThriftServer: `/var/log/Bigdata/hbase/ts2` (run logs, **ts2** is the instance name) and `/var/log/Bigdata/audit/hbase/ts2` (audit logs, **ts2** is the instance name)

**Log archive rule:** The automatic log compression and archiving function of HBase is enabled. By default, when the size of a log file exceeds 30 MB, the log file is automatically compressed. The naming rule of a compressed log file is as follows: `<Original log name>-<yyyy-mm-dd_hh-mm-ss>.[ID].log.zip` A maximum of 20 latest compressed files are reserved. The number of compressed files can be configured on the Manager portal.

**Table 6-11** HBase log list

Type	Name	Description
Run logs	hbase-<SSH_USER>-<process_name>-<hostname>.log	HBase system log that records the startup time, startup parameters, and most logs generated when the HBase system is running.
	hbase-<SSH_USER>-<process_name>-<hostname>.out	Log that records the HBase running environment information.
	<process_name>-<SSH_USER>-<DATE>-<PID>-gc.log	Log that records HBase junk collections.
	checkServiceDetail.log	Log that records whether the HBase service starts successfully.

Type	Name	Description
	hbase.log	Log generated when the HBase service health check script and some alarm check scripts are executed.
	sendAlarm.log	Log that records alarms reported after execution of HBase alarm check scripts.
	hbase-haCheck.log	Log that records the active and standby status of HMaster
	stop.log	Log that records the startup and stop processes of HBase.
Audit logs	hbase-audit- <process_name>.log	Log that records HBase security audit.

## Log Level

**Table 6-12** describes the log levels supported by HBase. The priorities of log levels are FATAL, ERROR, WARN, INFO, and DEBUG in descending order. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 6-12** Log levels

Level	Description
FATAL	Logs of this level record fatal error information about the current event processing that may result in a system crash.
ERROR	Logs of this level record error information about the current event processing, which indicates that system running is abnormal.
WARN	Logs of this level record abnormal information about the current event processing. These abnormalities will not result in system faults.
INFO	Logs of this level record normal running status information about the system and events.
DEBUG	Logs of this level record the system information and system debugging information.

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of the HBase service. For details, see [Modifying Cluster Service Configuration Parameters](#).

- Step 2** On the left menu bar, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Save the configuration. In the displayed dialog box, click **OK** to make the configurations take effect.

 **NOTE**

The configurations take effect immediately without the need to restart the service.

----End

## Log Formats

The following table lists the HBase log formats.

**Table 6-13** Log formats

Type	Component	Format	Example
Run logs	HMaster	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> <Thread that generates the log>  <Message in the log>  <Location of the log event>	2020-01-19 16:04:53,558   INFO   main   env:HBASE_THRIFT_OPTS=   org.apache.hadoop.hbase.u til.ServerCommandLine.log ProcessInfo(ServerComma ndLine.java:113)
	RegionServer	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> <Thread that generates the log>  <Message in the log>  <Location of the log event>	2020-01-19 16:05:18,589   INFO   regionserver16020- SendThread(linux-k6da: 2181)   Client will use GSSAPI as SASL mechanism.   org.apache.zookeeper.clien t.ZooKeeperSaslClient \$1.run(ZooKeeperSaslClien t.java:285)
	ThriftServer	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> <Thread that generates the log>  <Message in the log>  <Location of the log event>	2020-02-16 09:42:55,371   INFO   main   loaded properties from hadoop- metrics2.properties   org.apache.hadoop.metrics 2.impl.MetricsConfig.loadFi rst(MetricsConfig.java:111)

Type	Component	Format	Example
Audit logs	HMaster	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> <Thread that generates the log> <Message in the log> <Location of the log event>	2020-02-16 09:42:40,934   INFO   master:linux-k6da:16000   Master: [master:linux-k6da:16000] start operation called.   org.apache.hadoop.hbase.master.HMaster.run(HMaster.java:581)
	RegionServer	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> <Thread that generates the log> <Message in the log> <Location of the log event>	2020-02-16 09:42:51,063   INFO   main   RegionServer: [regionserver16020] start operation called.   org.apache.hadoop.hbase.regionserver.HRegionServer.startRegionServer(HRegionServer.java:2396)
	ThriftServer	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> <Thread that generates the log> <Message in the log> <Location of the log event>	2020-02-16 09:42:55,512   INFO   main   thrift2 server start operation called.   org.apache.hadoop.hbase.thrift2.ThriftServer.main(ThriftServer.java:421)

## 6.19 HBase Performance Tuning

### 6.19.1 Improving the BulkLoad Efficiency

#### Scenario

BulkLoad uses MapReduce jobs to directly generate files that comply with the internal data format of HBase, and then loads the generated StoreFiles to a running cluster. Compared with HBase APIs, BulkLoad saves more CPU and network resources.

ImportTSV is an HBase table data loading tool.

#### Prerequisites

When using BulkLoad, the output path of the file has been specified using the **Dimporttsv.bulk.output** parameter.

## Procedure

Add the following parameter to the BulkLoad command when performing a batch loading task:

**Table 6-14** Parameter for improving BulkLoad efficiency

Parameter	Description	Value
- Dimporttsv.map per.class	The construction of key-value pairs is moved from the user-defined mapper to reducer to improve performance. The mapper only needs to send the original text in each row to the reducer. The reducer parses the record in each row and creates a key-value) pair.  <b>NOTE</b> When this parameter is set to <b>org.apache.hadoop.hbase.mapreduce.TsvImporterByteMapper</b> , this parameter is used only when the batch loading command without the <i>HBASE_CELL_VISIBILITY OR HBASE_CELL_TTL</i> option is executed. The <b>org.apache.hadoop.hbase.mapreduce.TsvImporterByteMapper</b> provides better performance.	org.apache.hadoop.hbase.mapreduce.TsvImporterByteMapper and org.apache.hadoop.hbase.mapreduce.TsvImporterTextMapper

## 6.19.2 Improving Put Performance

### Scenario

In the scenario where a large number of requests are continuously put, setting the following two parameters to **false** can greatly improve the Put performance.

- **hbase.regionserver.wal.durable.sync**
- **hbase.regionserver.hfile.durable.sync**

When the performance is improved, there is a low probability that data is lost if three DataNodes are faulty at the same time. Exercise caution when configuring the parameters in scenarios that have high requirements on data reliability.

### Procedure

Navigation path for setting parameters:

On FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **HBase** > **Configurations** > **All Configurations**. Enter the parameter name in the search box, and change the value.

**Table 6-15** Parameters for improving put performance

Parameter	Description	Value
hbase.wal.hsync	Specifies whether to enable WAL file durability to make the WAL data persistence on disks. If this parameter is set to <b>true</b> , the performance is affected because each WAL file is synchronized to the disk by the Hadoop fsync.	false
hbase.hfile.hsync	Specifies whether to enable the HFile durability to make data persistence on disks. If this parameter is set to true, the performance is affected because each Hfile file is synchronized to the disk by the Hadoop fsync.	false

### 6.19.3 Optimizing Put and Scan Performance

#### Scenario

HBase has many configuration parameters related to read and write performance. The configuration parameters need to be adjusted based on the read/write request loads. This section describes how to optimize read and write performance by modifying the RegionServer configurations.

#### Procedure

- JVM GC parameters
  - Suggestions on setting the RegionServer **GC\_OPTS** parameter:
    - Set **-Xms** and **-Xmx** to the same value based on your needs. Increasing the memory can improve the read and write performance. For details, see the description of **hfile.block.cache.size** in [Table 6-17](#) and **hbase.regionserver.global.memstore.size** in [Table 6-16](#).
    - Set **-XX:NewSize** and **-XX:MaxNewSize** to the same value. You are advised to set the value to **512M** in low-load scenarios and **2048M** in high-load scenarios.
    - Set **X-XX:CMSInitiatingOccupancyFraction** to be less than and equal to 90, and it is calculated as follows: **100 x (hfile.block.cache.size + hbase.regionserver.global.memstore.size + 0.05)**.
    - **-XX:MaxDirectMemorySize** indicates the non-heap memory used by the JVM. You are advised to set this parameter to **512M** in low-load scenarios and **2048M** in high-load scenarios.

 NOTE

The **-XX:MaxDirectMemorySize** parameter is not used by default. If you need to set this parameter, add it to the **GC\_OPTS** parameter.

- Put parameters  
RegionServer processes the data of the put request and writes the data to memstore and HLog.
  - When the size of memstore reaches the value of **hbase.hregion.memstore.flush.size**, memstore is updated to HDFS to generate HFiles.
  - Compaction is triggered when the number of HFiles in the column cluster of the current region reaches the value of **hbase.hstore.compaction.min**.
  - If the number of HFiles in the column cluster of the current region reaches the value of **hbase.hstore.blockingStoreFiles**, the operation of refreshing the memstore and generating HFiles is blocked. As a result, the put request is blocked.

**Table 6-16** Put parameters

Parameter	Description	Default Value
hbase.wal.hsync	Indicates whether each WAL is persistent to disks. For details, see <a href="#">Improving Put Performance</a> .	true
hbase.hfile.hsync	Indicates whether HFile write operations are persistent to disks. For details, see <a href="#">Improving Put Performance</a> .	true
hbase.hregion.memstore.flush.size	If the size of MemStore (unit: Byte) exceeds a specified value, MemStore is flushed to the corresponding disk. The value of this parameter is checked by each thread running <b>hbase.server.thread.wakefrequency</b> . It is recommended that you set this parameter to an integer multiple of the HDFS block size. You can increase the value if the memory is sufficient and the put load is heavy.	134217728

Parameter	Description	Default Value
hbase.regionserver.global.memstore.size	Updates the size of all MemStores supported by the RegionServer before locking or forcible flush. It is recommended that you set this parameter to <b>hbase.hregion.memstore.flush.size x Number of regions with active writes/ RegionServer GC -Xmx</b> . The default value is <b>0.4</b> , indicating that 40% of RegionServer GC -Xmx is used.	0.4
hbase.hstore.flusher.count	Indicates the number of memstore flush threads. You can increase the parameter value in heavy-put-load scenarios.	2
hbase.regionserver.thread.compaction.small	Indicates the number of small compaction threads. You can increase the parameter value in heavy-put-load scenarios.	10
hbase.hstore.blockingStoreFiles	If the number of HStoreFile files in a Store exceeds the specified value, the update of the HRegion will be locked until a compression is completed or the value of <b>base.hstore.blockingWaitTime</b> is exceeded. Each time MemStore is flushed, a StoreFile file is written into MemStore. Set this parameter to a larger value in heavy-put-load scenarios.	15

- Scan parameters

**Table 6-17** Scan parameters

Parameter	Description	Default Value
hbase.client.scanner.timeout.period	Client and RegionServer parameters, indicating the lease timeout period of the client executing the scan operation. You are advised to set this parameter to an integer multiple of 60000 ms. You can set this parameter to a larger value when the read load is heavy. The unit is milliseconds.	60000
hfile.block.cache.size	Indicates the data cache percentage in the RegionServer GC -Xmx. You can increase the parameter value in heavy-read-load scenarios, in order to improve cache hit ratio and performance. It indicates the percentage of the maximum heap (-Xmx setting) allocated to the block cache of HFiles or StoreFiles.	When offheap is disabled, the default value is <b>0.25</b> . When offheap is enabled, the default value is <b>0.1</b> .

- Handler parameters

**Table 6-18** Handler parameters

Parameter	Description	Default Value
hbase.regionserver.handler.count	Indicates the number of RPC server instances on RegionServer. The recommended value ranges from 200 to 400.	200
hbase.regionserver.metahandler.count	Indicates the number of program instances for processing prioritized requests. The recommended value ranges from 200 to 400.	200

## 6.19.4 Improving Real-time Data Write Performance

### Scenario

Scenarios where data needs to be written to HBase in real time, or large-scale and consecutive put scenarios

### Prerequisites

The HBase put or delete interface can be used to save data to HBase.

### Procedure

- **Data writing server tuning**

Parameter portal:

Go to the **All Configurations** page of the HBase service. For details, see [Modifying Cluster Service Configuration Parameters](#).

**Table 6-19** Configuration items that affect real-time data writing

Parameter	Description	Default Value
hbase.wal.hsync	Controls the synchronization degree when HLogs are written to the HDFS. If the value is <b>true</b> , HDFS returns only when data is written to the disk. If the value is <b>false</b> , HDFS returns when data is written to the OS cache. Set the parameter to <b>false</b> to improve write performance.	true
hbase.hfile.hsync	Controls the synchronization degree when HFiles are written to the HDFS. If the value is <b>true</b> , HDFS returns only when data is written to the disk. If the value is <b>false</b> , HDFS returns when data is written to the OS cache. Set the parameter to <b>false</b> to improve write performance.	true

Parameter	Description	Default Value
GC_OPTS	<p>You can increase HBase memory to improve HBase performance because read and write operations are performed in HBase memory. <b>HeapSize</b> and <b>NewSize</b> need to be adjusted. When you adjust <b>HeapSize</b>, set <b>Xms</b> and <b>Xmx</b> to the same value to avoid performance problems when JVM dynamically adjusts <b>HeapSize</b>. Set <b>NewSize</b> to 1/8 of <b>HeapSize</b>.</p> <ul style="list-style-type: none"> <li>• <b>HMaster</b>: If HBase clusters enlarge and the number of Regions grows, properly increase the <b>GC_OPTS</b> parameter value of the HMaster.</li> <li>• <b>RegionServer</b>: A RegionServer needs more memory than an HMaster. If sufficient memory is available, increase the <b>HeapSize</b> value.</li> </ul> <p><b>NOTE</b> When the value of <b>HeapSize</b> for the active HMaster is 4 GB, the HBase cluster can support 100,000 regions. Empirically, each time 35,000 regions are added to the cluster, the value of <b>HeapSize</b> must be increased by 2 GB. It is recommended that the value of <b>HeapSize</b> for the active HMaster not exceed 32 GB.</p>	<ul style="list-style-type: none"> <li>• HMaster -server - Xms4G - Xmx4G - XX:NewSize= 512M - XX:MaxNewSi ze=512M - XX:Metaspac eSize=128M - XX:MaxMetas paceSize=512 M -XX: +UseConcMa rkSweepGC - XX: +CMSParallel RemarkEnabl ed - XX:CMSInitiat ingOccupanc yFraction=65 -XX: +PrintGCDeta ils - Dsun.rmi.dgc. client.gcInter val=0x7FFFFFF FFFFFFFFFE - Dsun.rmi.dgc. server.gcInter val=0x7FFFFFF FFFFFFFFFE - XX:- OmitStackTra ceInFastThro w -XX: +PrintGCTim eStamps -XX: +PrintGCDate Stamps -XX: +UseGCLogFi leRotation - XX:NumberO fGCLogFiles= 10 - XX:GCLogFile Size=1M</li> <li>• Region Server</li> </ul>

Parameter	Description	Default Value
		-server - Xms6G - Xmx6G - XX:NewSize= 1024M - XX:MaxNewSi ze=1024M - XX:Metaspac eSize=128M - XX:MaxMetas paceSize=512 M -XX: +UseConcMa rkSweepGC - XX: +CMSParallel RemarkEnabl ed - XX:CMSInitiat ingOccupanc yFraction=65 -XX: +PrintGC Deta ils - Dsun.rmi.dgc. client.gcInter val=0x7FFFFFF FFFFFFFFE - Dsun.rmi.dgc. server.gcInter val=0x7FFFFFF FFFFFFFFE - XX:- OmitStackTra ceInFastThro w -XX: +PrintGCTim eStamps -XX: +PrintGCDate Stamps -XX: +UseGCLogFi leRotation - XX:NumberO fGCLogFiles= 10 - XX:GCLogFile Size=1M

Parameter	Description	Default Value
hbase.regionserver.handler.count	<p>Indicates the number of RPC server instances started on RegionServer. If the parameter is set to an excessively large value, threads will compete fiercely. If the parameter is set to an excessively small value, requests will be waiting for a long time in RegionServer, reducing the processing capability. You can add threads based on resources.</p> <p>It is recommended that the value be set to <b>100</b> to <b>300</b> based on the CPU usage.</p>	200
hbase.hregion.max.filesize	<p>Indicates the maximum size of an HStoreFile, in bytes. If the size of any HStoreFile exceeds the value of this parameter, the managed Hregion is divided into two parts.</p>	10737418240
hbase.hregion.memstore.flush.size	<p>On the RegionServer, when the size of memstore that exists in memory of write operations exceeds <b>memstore.flush.size</b>, MemStoreFlusher performs the Flush operation to write the memstore to the corresponding store in the format of HFile.</p> <p>If RegionServer memory is sufficient and active Regions are few, increase the parameter value and reduce compaction times to improve system performance.</p> <p>The Flush operation may be delayed after it takes place. Write operations continue and memstore keeps increasing during the delay. The maximum size of memstore is: <b>memstore.flush.size</b> x <b>hbase.hregion.memstore.block.multiplier</b>. When the memstore size exceeds the maximum value, write operations are blocked. Properly increasing the value of <b>hbase.hregion.memstore.block.multiplier</b> can reduce the blocks and make performance become more stable. Unit: byte</p>	134217728

Parameter	Description	Default Value
<p>hbase.regionserver.global.memstore.size</p>	<p>Updates the size of all MemStores supported by the RegionServer before locking or forcible flush. On the RegionServer, the MemStoreFlusher thread performs the flush. The thread regularly checks memory occupied by write operations. When the total memory volume occupied by write operations exceeds the threshold, MemStoreFlusher performs the flush. Larger memstore will be flushed first and then smaller ones until the occupied memory is less than the threshold.</p> <p>Threshold =                      hbase.regionserver.global.memstore.size x                      hbase.regionserver.global.memstore.size.lower.limit x HBase_HEAPSIZE</p> <p><b>NOTE</b>                      The sum of the parameter value and the value of <b>hfile.block.cache.size</b> cannot exceed 0.8, that is, memory occupied by read and write operations cannot exceed 80% of <b>HeapSize</b>, ensuring stable running of other operations.</p>	<p>0.4</p>

Parameter	Description	Default Value
hbase.hstore.blockingStoreFiles	<p>Check whether the number of files is larger than the value of <b>hbase.hstore.blockingStoreFiles</b> before you flush regions.</p> <p>If it is larger than the value of <b>hbase.hstore.blockingStoreFiles</b>, perform a compaction and configure <b>hbase.hstore.blockingWaitTime</b> to 90s to make the flush delay for 90s. During the delay, write operations continue and the memstore size keeps increasing and exceeds the threshold (<b>memstore.flush.size</b> x <b>hbase.hregion.memstore.block.multiplier</b>), blocking write operations. After compaction is complete, a large number of writes may be generated. As a result, the performance fluctuates sharply.</p> <p>Increase the value of <b>hbase.hstore.blockingStoreFiles</b> to reduce block possibilities.</p>	15
hbase.regionserver.thread.compaction.throttle	<p>The compression whose size is greater than the value of this parameter is executed by the large thread pool. The unit is bytes. Indicates a threshold of a total file size for compaction during a Minor Compaction. The total file size affects execution duration of a compaction. If the total file size is large, other compactions or flushes may be blocked.</p>	1610612736
hbase.hstore.compaction.max	<p>Indicates the maximum number of HStoreFiles on which minor compaction is performed each time. The functions of the parameter and <b>hbase.hstore.compaction.max.size</b> are similar. Both are used to limit the execution duration of one compaction.</p>	10

Parameter	Description	Default Value
hbase.hstore.compaction.max.size	<p>If the size of an HFile is larger than the parameter value, the HFile will not be compacted in a Minor Compaction but can be compacted in a Major Compaction.</p> <p>The parameter is used to prevent HFiles of large sizes from being compacted. After a Major Compaction is forbidden, multiple HFiles can exist in a Store and will not be merged into one HFile, without affecting data access performance. The unit is byte.</p>	9223372036854775807
hbase.hregion.majorcompaction	<p>Main compression interval of all HStoreFile files in a region. The unit is milliseconds. Execution of Major Compactions consumes much system resources and will affect system performance during peak hours.</p> <p>If service updates, deletion, and reclamation of expired data space are infrequent, set the parameter to <b>0</b> to disable Major Compactions.</p> <p>If you must perform a Major Compaction to reclaim more space, increase the parameter value and configure the <b>hbase.offpeak.end.hour</b> and <b>hbase.offpeak.start.hour</b> parameters to make the Major Compaction be triggered in off-peak hours.</p>	604800000

Parameter	Description	Default Value
<ul style="list-style-type: none"> <li>hbase.regionserver.maxlogs</li> <li>hbase.regionserver.hlog.blocksize</li> </ul>	<ul style="list-style-type: none"> <li>Indicates the threshold for the number of HLog files that are not flushed on a RegionServer. If the number of HLog files is greater than the threshold, the RegionServer forcibly performs flush operations.</li> <li>Indicates the maximum size of an HLog file. If the size of an HLog file is greater than the value of this parameter, a new HLog file is generated. The old HLog file is disabled and archived.</li> </ul> <p>The two parameters determine the number of HLogs that are not flushed in a RegionServer. When the data volume is less than the total size of memstore, the flush operation is forcibly triggered due to excessive HLog files. In this case, you can adjust the values of the two parameters to avoid forcible flush. Unit: byte</p>	<ul style="list-style-type: none"> <li>32</li> <li>134217728</li> </ul>

- Data writing client tuning**

It is recommended that data is written in Put List mode if necessary, which greatly improves write performance. The length of each put list needs to be set based on the single put size and parameters of the actual environment. You are advised to do some basic tests before configuring parameters.

- Data table writing design optimization**

**Table 6-20** Parameters affecting real-time data writing

Parameter	Description	Default Value
COMPRESSION	<p>The compression algorithm compresses blocks in HFiles. For compressible data, configure the compression algorithm to efficiently reduce disk I/Os and improve performance.</p> <p><b>NOTE</b> Some data cannot be efficiently compressed. For example, a compressed figure can hardly be compressed again. The common compression algorithm is SNAPPY, because it has a high encoding/decoding speed and acceptable compression rate.</p>	NONE

Parameter	Description	Default Value
BLOCKSIZE	Different block sizes affect HBase data read and write performance. You can configure sizes for blocks in an HFile. Larger blocks have a higher compression rate. However, they have poor performance in random data read, because HBase reads data in a unit of blocks.  Set the parameter to 128 KB or 256 KB to improve data write efficiency without greatly affecting random read performance. The unit is byte.	65536
IN_MEMORY	Whether to cache table data in the memory first, which improves data read performance. If you will frequently access some small tables, set the parameter.	false

## 6.19.5 Improving Real-time Data Read Performance

### Scenario

HBase data needs to be read.

### Prerequisites

The get or scan interface of HBase has been invoked and data is read in real time from HBase.

### Procedure

- **Data reading server tuning**

Parameter portal:

Go to the **All Configurations** page of the HBase service. For details, see [Modifying Cluster Service Configuration Parameters](#).

**Table 6-21** Configuration items that affect real-time data reading

Parameter	Description	Default Value
GC_OPTS	<p>You can increase HBase memory to improve HBase performance because read and write operations are performed in HBase memory.</p> <p><b>HeapSize</b> and <b>NewSize</b> need to be adjusted. When you adjust <b>HeapSize</b>, set <b>Xms</b> and <b>Xmx</b> to the same value to avoid performance problems when JVM dynamically adjusts <b>HeapSize</b>. Set <b>NewSize</b> to 1/8 of <b>HeapSize</b>.</p> <ul style="list-style-type: none"> <li>• <b>HMaster</b>: If HBase clusters enlarge and the number of Regions grows, properly increase the <b>GC_OPTS</b> parameter value of the HMaster.</li> <li>• <b>RegionServer</b>: A RegionServer needs more memory than an HMaster. If sufficient memory is available, increase the <b>HeapSize</b> value.</li> </ul> <p><b>NOTE</b> When the value of <b>HeapSize</b> for the active HMaster is 4 GB, the HBase cluster can support 100,000 regions. Empirically, each time 35,000 regions are added to the cluster, the value of <b>HeapSize</b> must be increased by 2 GB. It is recommended that the value of <b>HeapSize</b> for the active HMaster not exceed 32 GB.</p>	<ul style="list-style-type: none"> <li>• HMaster -server - Xms4G - Xmx4G - XX:NewSize =512M - XX:MaxNew Size=512M - XX:Metaspa ceSize=128 M - XX:MaxMet aspaceSize= 512M -XX: +UseConcM arkSweepG C -XX: +CMSParall elRemarkEn abled - XX:CMSIniti atingOccup ancyFractio n=65 -XX: +PrintGCDe tails - Dsun.rmi.dg c.client.gcln terval=0x7F FFFFFFFFFF FFE - Dsun.rmi.dg c.server.gcln terval=0x7F FFFFFFFFFF FFE -XX:- OmitStackTr aceInFastTh row -XX: +PrintGCTi meStamps - XX: +PrintGC Da teStamps - XX: +UseGCLog FileRotation -</li> </ul>

Parameter	Description	Default Value
		<p>XX:NumberOfGCLogFiles=10 - XX:GCLogFileSize=1M</p> <ul style="list-style-type: none"> <li>Region Server           <ul style="list-style-type: none"> <li>-server -</li> <li>Xms6G -</li> <li>Xmx6G -</li> <li>XX:NewSize=1024M -</li> <li>XX:MaxNewSize=1024M -</li> <li>-</li> <li>XX:MetaspaceSize=128M -</li> <li>XX:MaxMetaspaceSize=512M -XX:</li> <li>+UseConcMarkSweepGC -XX:</li> <li>+CMSParallelRemarkEnabled -</li> <li>XX:CMSInitiatingOccupancyFraction=65 -XX:</li> <li>+PrintGCDetails -</li> <li>Dsun.rmi.dgc.client.gcInterval=0x7FFFFFFF -</li> <li>Dsun.rmi.dgc.server.gcInterval=0x7FFFFFFF -XX:-</li> <li>OmitStackTraceInFastThread -XX:</li> <li>+PrintGCTimeStamps -</li> <li>XX:</li> <li>+PrintGCData</li> </ul> </li> </ul>

Parameter	Description	Default Value
		teStamps - XX: +UseGCLog FileRotation - XX:Number OfGCLogFil es=10 - XX:GCLogFil eSize=1M
hbase.regionserver.ha ndler.count	Indicates the number of requests that RegionServer can process concurrently. If the parameter is set to an excessively large value, threads will compete fiercely. If the parameter is set to an excessively small value, requests will be waiting for a long time in RegionServer, reducing the processing capability. You can add threads based on resources. It is recommended that the value be set to 100 to 300 based on the CPU usage.	200
hfile.block.cache.size	HBase cache sizes affect query efficiency. Set cache sizes based on query modes and query record distribution. If random query is used to reduce the hit ratio of the buffer, you can reduce the buffer size.	When <b>offheap</b> is disabled, the default value is <b>0.25</b> . When <b>offheap</b> is enabled, the default value is <b>0.1</b> .

 **NOTE**

If read and write operations are performed at the same time, the performance of the two operations affects each other. If flush and compaction operations are frequently performed due to data writes, a large number of disk I/O operations are occupied, affecting read performance. If a large number of compaction operations are blocked due to write operations, multiple HFiles exist in the region, affecting read performance. Therefore, if the read performance is unsatisfactory, you need to check whether the write configurations are proper.

- **Data reading client tuning**

When scanning data, you need to set **caching** (the number of records read from the server at a time. The default value is **1**.). If the default value is used, the read performance will be extremely low.

If you do not need to read all columns of a piece of data, specify the columns to be read to reduce network I/O.

If you only need to read the row key, add a filter (FirstKeyOnlyFilter or KeyOnlyFilter) that only reads the row key.

- **Data table reading design optimization**

**Table 6-22** Parameters affecting real-time data reading

Parameter	Description	Default Value
COMPRESSION	The compression algorithm compresses blocks in HFiles. For compressible data, configure the compression algorithm to efficiently reduce disk I/Os and improve performance.  <b>NOTE</b> Some data cannot be efficiently compressed. For example, a compressed figure can hardly be compressed again. The common compression algorithm is SNAPPY, because it has a high encoding/decoding speed and acceptable compression rate.	NONE
BLOCKSIZE	Different block sizes affect HBase data read and write performance. You can configure sizes for blocks in an HFile. Larger blocks have a higher compression rate. However, they have poor performance in random data read, because HBase reads data in a unit of blocks.  Set the parameter to 128 KB or 256 KB to improve data write efficiency without greatly affecting random read performance. The unit is byte.	65536
DATA_BLOCK_ENCODING	Encoding method of the block in an HFile. If a row contains multiple columns, set <b>FAST_DIFF</b> to save data storage space and improve performance.	NONE

## 6.19.6 Optimizing JVM Parameters

### Scenario

When the number of clusters reaches a certain scale, the default settings of the Java virtual machine (JVM) cannot meet the cluster requirements. In this case, the cluster performance deteriorates or the clusters may be unavailable. Therefore, JVM parameters must be properly configured based on actual service conditions to improve the cluster performance.

### Procedure

**Navigation path for setting parameters:**

The JVM parameters related to the HBase role must be configured in the **hbase-env.sh** file in the **`\${BIGDATA\_HOME}/FusionInsight\_HD\_\*/install/FusionInsight-HBase-2.2.3/hbase/conf/`** directory.

Each role has JVM parameter configuration variables, as shown in [Table 6-23](#).

**Table 6-23** HBase-related JVM parameter configuration variables

Variable	Affected Role
HBASE_OPTS	All roles of HBase
SERVER_GC_OPTS	All roles on the HBase server, such as Master and RegionServer
CLIENT_GC_OPTS	Client process of HBase
HBASE_MASTER_OPTS	Master of HBase
HBASE_REGIONSERVER_OPTS	RegionServer of HBase
HBASE_THRIFT_OPTS	Thrift of HBase

**Configuration example:**

```
export HADOOP_NAMENODE_OPTS="-Dhadoop.security.logger=${HADOOP_SECURITY_LOGGER:-INFO,RFAS} -Dhdfs.audit.logger=${HDFS_AUDIT_LOGGER:-INFO,NullAppender}
$HADOOP_NAMENODE_OPTS"
```

## 6.20 Common Issues About HBase

### 6.20.1 Why Does a Client Keep Failing to Connect to a Server for a Long Time?

**Question**

A HBase server is faulty and cannot provide services. In this case, when a table operation is performed on the HBase client, why is the operation suspended and no response is received for a long time?

**Answer**

**Problem Analysis**

When the HBase server malfunctions, the table operation request from the HBase client is tried for several times and times out. The default timeout value is **Integer.MAX\_VALUE (2147483647 ms)**. The table operation request is retired constantly during such a long period of time and is suspended at last.

**Solution**

The HBase client provides two configuration items to configure the retry and timeout of the client. **Table 6-24** describes them.


Set the following parameters in the *Client installation path/HBase/hbase/conf/hbase-site.xml* configuration file:

**Table 6-24** Configuration parameters of retry and timeout

Parameter	Description	Default Value
hbase.client.operation.timeout	Client operation timeout period You need to manually add the information to the configuration file.	2147483647 ms
hbase.client.retries.number	Maximum retry times supported by all retryable operations.	35

**Figure 6-1** describes the working principles of retry and timeout.

**Figure 6-1** Process for HBase client operation retry timeout



The process indicates that a suspension occurs if the preceding parameters are not configured based on site requirements. It is recommended that a proper timeout period be set based on scenarios. If the operation takes a long time, set a long timeout period. If the operation takes a short time, set a short timeout period. The number of retries can be set to **(hbase.client.retries.number)\*60\*1000(ms)**. The timeout period can be slightly greater than **hbase.client.operation.timeout**.

## 6.20.2 Operation Failures Occur in Stopping BulkLoad On the Client

### Question

Why submitted operations fail by stopping BulkLoad on the client during BulkLoad data importing?

### Answer

When BulkLoad is enabled on the client, a partitioner file is generated and used to demarcate the range of Map task data inputting. The file is automatically deleted when BulkLoad exists on the client. In general, if all map tasks are enabled and running, the termination of BulkLoad on the client does not cause the failure of submitted operations. However, due to the retry and speculative execution mechanism of Map tasks, a Map task is performed again if failures of the Reduce task to download the data of the completed Map task exceed the limit. In this case, if BulkLoad already exists on the client, the retry Map task fails and the operation failure occurs because the partitioner file is missing. Therefore, it is recommended not to stop BulkLoad on the client during BulkLoad data importing.

## 6.20.3 Why May a Table Creation Exception Occur When HBase Deletes or Creates the Same Table Consecutively?

### Question

When HBase consecutively deletes and creates the same table, why may a table creation exception occur?

### Answer

Execution process: Disable Table > Drop Table > Create Table > Disable Table > Drop Table > And more

1. When a table is disabled, HMaster sends an RPC request to RegionServer, and RegionServer brings the region offline. When the time required for closing a region on RegionServer exceeds the timeout period for HBase HMaster to wait for the region to enter the RIT state, HMaster considers that the region is offline by default. Actually, the region may be in the flush memstore phase.
2. After an RPC request is sent to close a region, HMaster checks whether all regions in the table are offline. If the closure times out, HMaster considers that the regions are offline and returns a message indicating that the regions are successfully closed.
3. After the closure is successful, the data directory corresponding to the HBase table is deleted.

4. After the table is deleted, the data directory is recreated by the region that is still in the flush memstore phase.
5. When the table is created again, the **temp** directory is copied to the HBase data directory. However, the HBase data directory is not empty. As a result, when the HDFS rename API is called, the data directory changes to the last layer of the **temp** directory and is appended to the HBase data directory, for example, **\$rootDir/data/\$nameSpace/\$tableName/\$tableName**. In this case, the table fails to be created.

#### Troubleshooting Method

When this problem occurs, check whether the HBase data directory corresponding to the table exists. If it exists, rename the directory.

The HBase data directory consists of **\$rootDir/data/\$nameSpace/\$tableName**, for example, **hdfs://hacluster/hbase/data/default/TestTable**. **\$rootDir** is the HBase root directory, which can be obtained by configuring **hbase.rootdir.perms** in **hbase-site.xml**. The **data** directory is a fixed directory of HBase. **\$nameSpace** indicates the nameSpace name. **\$tableName** indicates the table name.

## 6.20.4 Why Other Services Become Unstable If HBase Sets up A Large Number of Connections over the Network Port?

### Question

Why other services become unstable if HBase sets up a large number of connections over the network port?

### Answer

When the OS command ***lsof*** or ***netstat*** is run, it is found that many TCP connections are in the CLOSE\_WAIT state and the owner of the connections is HBase RegionServer. This can cause exhaustion of network ports or limit exceeding of HDFS connections, resulting in instability of other services. The HBase CLOSE\_WAIT phenomenon is the HBase mechanism.

The reason why HBase CLOSE\_WAIT occurs is as follows: HBase data is stored in the HDFS as HFile, which can be called StoreFiles. HBase functions as the client of the HDFS. When HBase creates a StoreFile or starts loading a StoreFile, it creates an HDFS connection. When the StoreFile is created or loaded successfully, the HDFS considers that the task is completed and transfers the connection close permission to HBase. However, HBase may choose not to close the connection to ensure real-time response; that is, HBase may maintain the connection so that it can quickly access the corresponding data file upon request. In this case, the connection is in the CLOSE\_WAIT, which indicates that the connection needs to be closed by the client.

When a StoreFile will be created: HBase executes the Flush operation.

When Flush is executed: The data written by HBase is first stored in memstore. The Flush operation is performed only when the usage of memstore reaches the threshold or the ***flush*** command is run to write data into the HDFS.

To resolve the issue, use either of the following methods:

Because of the HBase connection mechanism, the number of StoreFiles must be restricted to reduce the occupation of HBase ports. This can be achieved by triggering HBase's the compaction action, that is, HBase file merging.

Method 1: On HBase shell client, run *major\_compact*.

Method 2: Compile HBase client code to invoke the compact method of the HBaseAdmin class to trigger HBase's compaction action.

If the HBase port occupation issue cannot be resolved through compact, it indicates that the HBase usage has reached the bottleneck. In such a case, you are advised to perform the following:

- Check whether the initial number of Regions configured in the table is appropriate.
- Check whether useless data exists.

If useless data exists, delete the data to reduce the number of storage files for the HBase. If the preceding conditions are not met, then you need to consider a capacity expansion.

## 6.20.5 Why Does the HBase BulkLoad Task (One Table Has 26 TB Data) Consisting of 210,000 Map Tasks and 10,000 Reduce Tasks Fail?

### Question

The HBase bulkLoad task (a single table contains 26 TB data) has 210,000 maps and 10,000 reduce tasks, and the task fails.

### Answer

#### ZooKeeper I/O bottleneck observation methods:

1. On the monitoring page of Manager, check whether the number of ZooKeeper requests on a single node exceeds the upper limit.
2. View ZooKeeper and HBase logs to check whether a large number of I/O Exception Timeout or SocketTimeout Exception exceptions occur.

#### Optimization suggestions:

1. Change the number of ZooKeeper instances to 5 or more. You are advised to set **peerType** to **observer** to increase the number of observers.
2. Control the number of concurrent maps of a single task or reduce the memory for running tasks on each node to lighten the node load.
3. Upgrade ZooKeeper data disks, such as SSDs.

## 6.20.6 How Do I Restore a Region in the RIT State for a Long Time?

### Question

How do I restore a region in the RIT state for a long time?

### Answer

Log in to the HMaster WebUI, choose **Procedure & Locks** in the navigation tree, and check whether any process ID is in the **Waiting** state. If yes, run the following command to release the procedure lock:

```
hbase hbck -j /opt/client/HBase/hbase/tools/hbase-hbck2-*.jar bypass -o pid
```

Check whether the state is in the **Bypass** state. If the procedure on the UI is always in **RUNNABLE(Bypass)** state, perform an active/standby switchover. Run the **assigns** command to bring the region online again.

```
hbase hbck -j /opt/client/HBase/hbase/tools/hbase-hbck2-*.jar assigns -o  
regionName
```

## 6.20.7 Why Does HMaster Exits Due to Timeout When Waiting for the Namespace Table to Go Online?

### Question

Why does HMaster exit due to timeout when waiting for the namespace table to go online?

### Answer

During the HMaster active/standby switchover or startup, HMaster performs WAL splitting and region recovery for the RegionServer that failed or was stopped previously.

Multiple threads are running in the background to monitor the HMaster startup process.

- **TableNamespaceManager**  
This is a help class, which is used to manage the allocation of namespace tables and monitoring table regions during HMaster active/standby switchover or startup. If the namespace table is not online within the specified time (**hbase.master.namespace.init.timeout**, which is 3,600,000 ms by default), the thread terminates HMaster abnormally.
- **InitializationMonitor**  
This is an initialization thread monitoring class of the primary HMaster, which is used to monitor the initialization of the primary HMaster. If a thread fails to be initialized within the specified time (**hbase.master.initializationmonitor.timeout**, which is 3,600,000 ms by default), the thread terminates HMaster abnormally. If **hbase.master.initializationmonitor.haltontimeout** is started, the default value is **false**.



```
at org.apache.hadoop.hbase.client.RpcRetryingCaller.callWithoutRetries(RpcRetryingCaller.java:200)
at org.apache.hadoop.hbase.client.ClientScanner.call(ClientScanner.java:323)
```

At the same time, the following log is displayed on RegionServer:

```
2015-12-15 02:45:44,551 | WARN | PriorityRpcServer.handler=7,queue=1,port=16020 | (responseTooSlow):
{"call":"Scan(org.apache.hadoop.hbase.protobuf.generated.ClientProtos$ScanRequest)
","starttimems":1450118730780,"responsesize":416,"method":"Scan","processingtimems":
13770,"client":"10.91.8.175:41182","queuetimems":0,"class":"HRegionServer"} |
org.apache.hadoop.hbase.ipc.RpcServer.logResponse(RpcServer.java:2221)
2015-12-15 02:45:57,722 | WARN | PriorityRpcServer.handler=3,queue=1,port=16020 | (responseTooSlow):
{"call":"Scan(org.apache.hadoop.hbase.protobuf.generated.ClientProtos$ScanRequest)","starttimems":
1450118746297,"responsesize":416,
"method":"Scan","processingtimems":11425,"client":"10.91.8.175:41182","queuetimems":
1746,"class":"HRegionServer"} | org.apache.hadoop.hbase.ipc.RpcServer.logResponse(RpcServer.java:2221)
2015-12-15 02:47:21,668 | INFO | LruBlockCacheStatsExecutor | totalSize=7.54 GB, freeSize=369.52 MB,
max=7.90 GB, blockCount=406107,
accesses=35400006, hits=16803205, hitRatio=47.47%, , cachingAccesses=31864266, cachingHits=14806045,
cachingHitsRatio=46.47%,
evictions=17654, evicted=16642283, evictedPerRun=942.69189453125 |
org.apache.hadoop.hbase.io.hfile.LruBlockCache.logStats(LruBlockCache.java:858)
2015-12-15 02:52:21,668 | INFO | LruBlockCacheStatsExecutor | totalSize=7.51 GB, freeSize=395.34 MB,
max=7.90 GB, blockCount=403080,
accesses=35685793, hits=16933684, hitRatio=47.45%, , cachingAccesses=32150053, cachingHits=14936524,
cachingHitsRatio=46.46%,
evictions=17684, evicted=16800617, evictedPerRun=950.046142578125 |
org.apache.hadoop.hbase.io.hfile.LruBlockCache.logStats(LruBlockCache.java:858)
```

## Answer

The memory allocated to RegionServer is too small and the number of Regions is too large. As a result, the memory is insufficient during the running, and the server responds slowly to the client. Modify the following memory allocation parameters in the **hbase-site.xml** configuration file of RegionServer:

**Table 6-25** RegionServer memory allocation parameters

Parameter	Description	Default Value
GC_OPTS	Initial memory and maximum memory allocated to RegionServer in startup parameters.	-Xms8G -Xmx8G
hfile.block.cache.size	Percentage of the maximum heap (-Xmx setting) allocated to the block cache of HFiles or StoreFiles.	When <b>offheap</b> is disabled, the default value is <b>0.25</b> . When <b>offheap</b> is enabled, the default value is <b>0.1</b> .

## 6.20.9 Why Modified and Deleted Data Can Still Be Queried by Using the Scan Command?

### Question

Why modified and deleted data can still be queried by using the **scan** command?

```
scan '<table_name>',{FILTER=>"SingleColumnValueFilter('<column_family>','column',=,'binary:<value>')"}
```

## Answer

Because of the scalability of HBase, all values specific to the versions in the queried column are all matched by default, even if the values have been modified or deleted. For a row where column matching has failed (that is, the column does not exist in the row), the HBase also queries the row.

If you want to query only the new values and rows where column matching is successful, you can use the following statement:

```
scan '<table_name>',  
{FILTER=>"SingleColumnValueFilter('<column_family>','column',=,'binary:<value>',true,true)"}
```

This command can filter all rows where column query has failed. It queries only the latest values of the current data in the table; that is, it does not query the values before modification or the deleted values.

### NOTE

The related parameters of **SingleColumnValueFilter** are described as follows:

SingleColumnValueFilter(final byte[] family, final byte[] qualifier, final CompareOp compareOp, ByteArrayComparable comparator, final boolean filterIfMissing, final boolean latestVersionOnly)

Parameter description:

- family: family of the column to be queried.
- qualifier: column to be queried.
- compareOp: comparison operation, such as = and >.
- comparator: target value to be queried.
- filterIfMissing: whether a row is filtered out if the queried column does not exist. The default value is false.
- latestVersionOnly: whether values of the latest version are queried. The default value is false.

## 6.20.10 Why "java.lang.UnsatisfiedLinkError: Permission denied" exception thrown while starting HBase shell?

### Question

Why "java.lang.UnsatisfiedLinkError: Permission denied" exception thrown while starting HBase shell?

### Answer

During HBase shell execution JRuby create temporary files under **java.io.tmpdir** path and default value of **java.io.tmpdir** is **/tmp**. If NOEXEC permission is set to /tmp directory then HBase shell start will fail with "java.lang.UnsatisfiedLinkError: Permission denied" exception.

So "java.io.tmpdir" must be set to a different path in HBASE\_OPTS/CLIENT\_GC\_OPTS if NOEXEC is set to /tmp directory.

## 6.20.11 When does the RegionServers listed under "Dead Region Servers" on HMaster WebUI gets cleared?

### Question

When does the RegionServers listed under "Dead Region Servers" on HMaster WebUI gets cleared?

### Answer

When an online RegionServer goes down abruptly, it is displayed under "Dead Region Servers" in the HMaster WebUI. When dead RegionServer restarts and reports back to HMaster successfully, the "Dead Region Servers" in the HMaster WebUI gets cleared.

The "Dead Region Servers" is also gets cleared, when the HMaster failover operation is performed successfully.

In cases when an Active HMaster hosting some regions is abruptly killed, Backup HMaster will become the new Active HMater and displays previous Active HMaster as dead RegionServer.

## 6.20.12 Why Are Different Query Results Returned After I Use Same Query Criteria to Query Data Successfully Imported by HBase bulkload?

### Question

If the data to be imported by HBase bulkload has identical rowkeys, the data import is successful but identical query criteria produce different query results.

### Answer

Data with an identical rowkey is loaded into HBase in the order in which data is read. The data with the latest timestamp is considered to be the latest data. By default, data is not queried by timestamp. Therefore, if you query for data with an identical rowkey, only the latest data is returned.

While data is being loaded by bulkload, the memory processes the data into HFiles quickly, leading to the possibility that data with an identical rowkey has a same timestamp. In this case, identical query criteria may produce different query results.

To avoid this problem, ensure that the same data file does not contain identical rowkeys while you are creating tables or loading data.

## 6.20.13 What Should I Do If I Fail to Create Tables Due to the FAILED\_OPEN State of Regions?

### Question

What should I do if I fail to create tables due to the FAILED\_OPEN state of Regions?

### Answer

If a network, HDFS, or Active HMaster fault occurs during the creation of tables, some Regions may fail to go online and therefore enter the FAILED\_OPEN state. In this case, tables fail to be created.

The tables that fail to be created due to the preceding mentioned issue cannot be repaired. To solve this problem, perform the following operations to delete and re-create the tables:

1. Run the following command on the cluster client to repair the state of the tables:  
**hbase hbck -fixTableStates**
2. Enter the HBase shell and run the following commands to delete the tables that fail to be created:  
*truncate '<table\_name>'*  
*disable '<table\_name>'*  
*drop '<table\_name>'*
3. Create the tables using the recreation command.

## 6.20.14 How Do I Delete Residual Table Names in the /hbase/table-lock Directory of ZooKeeper?

### Question

In security mode, names of tables that failed to be created are unnecessarily retained in the table-lock node (default directory is /hbase/table-lock) of ZooKeeper. How do I delete these residual table names?

### Answer

Perform the following steps:

1. On the client, run the kinit command as the hbase user to obtain a security certificate.
2. Run the **hbase zkcli** command to launch the ZooKeeper Command Line Interface (zkCLI).
3. Run the **ls /hbase/table** command on the zkCLI to check whether the table name of the table that fails to be created exists.
  - If the table name exists, no further operation is required.

- If the table name does not exist, run `ls /hbase/table-lock` to check whether the table name of the table fail to be created exist. If the table name exists, run the `delete /hbase/table-lock/<table>` command to delete the table name. In the `delete /hbase/table-lock/<table>` command, `<table>` indicates the residual table name.

## 6.20.15 Why Does HBase Become Faulty When I Set a Quota for the Directory Used by HBase in HDFS?

### Question

Why does HBase become faulty when I set quota for the directory used by HBase in HDFS?

### Answer

The flush operation of a table is to write memstore data to HDFS.

If the HDFS directory does not have sufficient disk space quota, the flush operation will fail and the region server will stop.

```
Caused by: org.apache.hadoop.hdfs.protocol.DSQuotaExceededException: The DiskSpace quota of /hbase/
data/<namespace>/<tableName> is exceeded: quota = 1024 B = 1 KB but disk space consumed = 402655638
B = 384.00 MB
?at
org.apache.hadoop.hdfs.server.namenode.DirectoryWithQuotaFeature.verifyStoragespaceQuota(DirectoryWith
hQuotaFeature.java:211)
?at
org.apache.hadoop.hdfs.server.namenode.DirectoryWithQuotaFeature.verifyQuota(DirectoryWithQuotaFeatu
re.java:239)
?at org.apache.hadoop.hdfs.server.namenode.FSDirectory.verifyQuota(FSDirectory.java:882)
?at org.apache.hadoop.hdfs.server.namenode.FSDirectory.updateCount(FSDirectory.java:711)
?at org.apache.hadoop.hdfs.server.namenode.FSDirectory.updateCount(FSDirectory.java:670)
?at org.apache.hadoop.hdfs.server.namenode.FSDirectory.addBlock(FSDirectory.java:495)
```

In the preceding exception, the disk space quota of the `/hbase/data/<namespace>/<tableName>` table is 1 KB, but the memstore data is 384.00 MB. Therefore, the flush operation fails and the region server stops.

When the region server is terminated, HMaster replays the WAL file of the terminated region server to restore data. The disk space quota is limited. As a result, the replay operation of the WAL file fails, and the HMaster process exits unexpectedly.

```
2016-07-28 19:11:40,352 | FATAL | MASTER_SERVER_OPERATIONS-10-91-9-131:16000-0 | Caught throwable
while processing event M_SERVER_SHUTDOWN |
org.apache.hadoop.hbase.master.HMaster.abort(HMaster.java:2474)
java.io.IOException: failed log splitting for 10-91-9-131,16020,1469689987884, will retry
?at org.apache.hadoop.hbase.master.handler.ServerShutdownHandler.resubmit(ServerShutdownHandler.java:
365)
?at org.apache.hadoop.hbase.master.handler.ServerShutdownHandler.process(ServerShutdownHandler.java:
220)
?at org.apache.hadoop.hbase.executor.EventHandler.run(EventHandler.java:129)
?at java.util.concurrent.ThreadPoolExecutor.runWorker(ThreadPoolExecutor.java:1142)
?at java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:617)
?at java.lang.Thread.run(Thread.java:745)
Caused by: java.io.IOException: error or interrupted while splitting logs in [hdfs://hacluster/hbase/WALs/<RS-
Hostname>,<RS-Port>,<startcode>-splitting] Task = installed = 6 done = 3 error = 3
?at org.apache.hadoop.hbase.master.SplitLogManager.splitLogDistributed(SplitLogManager.java:290)
?at org.apache.hadoop.hbase.master.MasterFileSystem.splitLog(MasterFileSystem.java:402)
?at org.apache.hadoop.hbase.master.MasterFileSystem.splitLog(MasterFileSystem.java:375)
```

Therefore, you cannot set the quota value for the HBase directory in HDFS. If the exception occurs, perform the following operations:

- Step 1** Run the `kinit Username` command on the client to enable the HBase user to obtain security authentication.
- Step 2** Run the `hdfs dfs -count -q /hbase/data/<namespace>/<tableName>` command to check the allocated disk space quota.
- Step 3** Run the following command to cancel the quota limit and restore HBase:
- ```
hdfs dfsadmin -clrSpaceQuota /hbase/data/<namespace>/<tableName>
```
- End

## 6.20.16 Why HMaster Times Out While Waiting for Namespace Table to be Assigned After Rebuilding Meta Using OfflineMetaRepair Tool and Startups Failed

### Question

Why HMaster times out while waiting for namespace table to be assigned after rebuilding meta using OfflineMetaRepair tool and startups failed?

HMaster abort with following FATAL message,

```
2017-06-15 15:11:07,582 FATAL [Hostname:16000.activeMasterManager] master.HMaster: Unhandled exception. Starting shutdown.  
java.io.IOException: Timedout 120000ms waiting for namespace table to be assigned  
    at org.apache.hadoop.hbase.master.TableNamespaceManager.start(TableNamespaceManager.java:98)  
    at org.apache.hadoop.hbase.master.HMaster.initNamespace(HMaster.java:1054)  
    at org.apache.hadoop.hbase.master.HMaster.finishActiveMasterInitialization(HMaster.java:848)  
    at org.apache.hadoop.hbase.master.HMaster.access$600(HMaster.java:199)  
    at org.apache.hadoop.hbase.master.HMaster$2.run(HMaster.java:1871)  
    at java.lang.Thread.run(Thread.java:745)
```

### Answer

When meta is rebuilt by OfflineMetaRepair tool then HMaster wait for all region server's WAL split during start up to avoid the data inconsistency problem. HMaster trigger user regions assignment once WAL split completes. So when the cluster is in the unusual scenario, there are chances WAL splitting may take long time which depends on multiple factors like too many WALs, slow I/O, region servers are not stable etc.

HMaster should be able to finish all region server WAL splitting successfully. Perform the following steps.

1. Make sure cluster is stable, no other problem exist. If any problem occurs, please correct them first.
2. Configure a large value to `hbase.master.initializationmonitor.timeout` parameters, default value is **3600000** milliseconds.
3. Restart HBase service.



default average number of regions on each RegionServer, that is, 2,000), the adjustment solution is (actual specifications/default specifications) x Default time.

Set the **splitlog** parameter in the **hbase-site.xml** file on the server. [Table 6-26](#) describes the parameter.

**Table 6-26** Description of the **splitlog** parameter

| Parameter                      | Description                                                                                  | Default Value |
|--------------------------------|----------------------------------------------------------------------------------------------|---------------|
| hbase.splitlog.manager.timeout | Timeout period for receiving worker response by the distributed SplitLog management program. | 600000        |

## 6.20.18 Why Does the ImportTsv Tool Display "Permission denied" When the Same Linux User as and a Different Kerberos User from the Region Server Are Used?

### Question

When the same Linux user (for example, user **omm**) as and a different Kerberos user (for example, user **admin**) from the Region Server are used, why does the ImportTsv tool fail to be executed and the error message "Permission denied" is displayed?

```
Exception in thread "main" org.apache.hadoop.security.AccessControlException: Permission denied:
user=admin, access=WRITE, inode="/user/omm-bulkload/hbase-staging/
partitions_cab16de5-87c2-4153-9cca-a6f4ed4278a6":hbase:hadoop:drwx--x--x
    at org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.check(FSPermissionChecker.java:342)
    at org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.check(FSPermissionChecker.java:315)
    at
org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.checkPermission(FSPermissionChecker.java:
231)
    at
com.xxx.hadoop.adapter.hdfs.plugin.HWAccessControlEnforce.checkPermission(HWAccessControlEnforce.java:
69)
    at
org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.checkPermission(FSPermissionChecker.java:
190)
    at org.apache.hadoop.hdfs.server.namenode.FSDirectory.checkPermission(FSDirectory.java:1789)
    at org.apache.hadoop.hdfs.server.namenode.FSDirectory.checkPermission(FSDirectory.java:1773)
    at org.apache.hadoop.hdfs.server.namenode.FSDirectory.checkAncestorAccess(FSDirectory.java:1756)
    at org.apache.hadoop.hdfs.server.namenode.FSNamesystem.startFileInternal(FSNamesystem.java:2490)
    at org.apache.hadoop.hdfs.server.namenode.FSNamesystem.startFileInt(FSNamesystem.java:2425)
    at org.apache.hadoop.hdfs.server.namenode.FSNamesystem.startFile(FSNamesystem.java:2308)
    at org.apache.hadoop.hdfs.server.namenode.NameNodeRpcServer.create(NameNodeRpcServer.java:
745)
    at
org.apache.hadoop.hdfs.protocolPB.ClientNamenodeProtocolServerSideTranslatorPB.create(ClientNamenodeP
rotocolServerSideTranslatorPB.java:434)
    at org.apache.hadoop.hdfs.protocol.proto.ClientNamenodeProtocolProtos$ClientNamenodeProtocol
$2.callBlockingMethod(ClientNamenodeProtocolProtos.java)
    at org.apache.hadoop.ipc.ProtobufRpcEngine$Server$ProtoBufRpcInvoker.call(ProtobufRpcEngine.java:
616)
    at org.apache.hadoop.ipc.RPC$Server.call(RPC.java:973)
    at org.apache.hadoop.ipc.Server$Handler$1.run(Server.java:2260)
    at org.apache.hadoop.ipc.Server$Handler$1.run(Server.java:2256)
    at java.security.AccessController.doPrivileged(Native Method)
    at javax.security.auth.Subject.doAs(Subject.java:422)
```

```
at org.apache.hadoop.security.UserGroupInformation.doAs(UserGroupInformation.java:1781)
at org.apache.hadoop.ipc.Server$Handler.run(Server.java:2254)
```

## Answer

The ImportTsv tool creates a partition file in the HBase temporary directory specified by **hbase.fs.tmp.dir** in the *Client installation path /HBase/hbase/conf/hbase-site.xml* file. Therefore, the client (Kerberos user) must have the **rwX** permission on the specified temporary directory to perform the ImportTsv operation. The default value of **hbase.fs.tmp.dir** is **/user/\${user.name}/hbase-staging** (for example, **/user/omm/hbase-staging**). **\${user.name}** indicates the OS username (user **omm**). The client (Kerberos user, for example, user **admin**) does not have the **rwX** permission on the directory.

To solve the preceding problem, perform the following steps:

1. On the client, set **hbase.fs.tmp.dir** to the directory of the current Kerberos user (for example, **/user/admin/hbase-staging**), or provide the **rwX** permission required by the configured directory for the client (Kerberos user).
2. Perform the ImportTsv operation again.

## 6.20.19 Insufficient Rights When a Tenant Accesses Phoenix

### Question

When a tenant accesses Phoenix, a message is displayed indicating that the tenant has insufficient rights.

### Answer

You need to associate the HBase service and Yarn queues when creating a tenant.

The tenant must be granted additional rights to perform operations on Phoenix, that is, the RWX permission on the Phoenix system table.

Example:

Tenant **hbase** has been created. Log in to the HBase Shell as user **admin** and run the **scan 'hbase:acl'** command to query the role of the tenant. The role is **hbase\_1450761169920** (in the format of tenant name\_timestamp).

Run the following commands to grant rights to the tenant (if the Phoenix system table has not been generated, log in to the Phoenix client as user **admin** first and then grant rights on the HBase Shell):

```
grant '@hbase_1450761169920','RWX','SYSTEM.CATALOG'
```

```
grant '@hbase_1450761169920','RWX','SYSTEM.FUNCTION'
```

```
grant '@hbase_1450761169920','RWX','SYSTEM.SEQUENCE'
```

```
grant '@hbase_1450761169920','RWX','SYSTEM.STATS'
```

Create user **phoenix** and bind it with tenant **hbase**, so that tenant **hbase** can access the Phoenix client as user **phoenix**.

## 6.20.20 What Can I Do When HBase Fails to Recover a Task and a Message Is Displayed Stating "Rollback recovery failed"?

### Question

The system automatically rolls back data after an HBase recovery task fails. If "Rollback recovery failed" is displayed, the rollback fails. After the rollback fails, data stops being processed and the junk data may be generated. How can I resolve this problem?

### Answer

You need to manually clear the junk data before performing the backup or recovery task next time.

- Step 1** Install the cluster client in `/opt/client`.
- Step 2** Run `source /opt/client/bigdata_env` as the client installation user to configure the environment variable.
- Step 3** Run `kinit admin` for administrator authentication.
- Step 4** Run `zkCli.sh -server business IP address of ZooKeeper:2181` to connect to the ZooKeeper.
- Step 5** Run `deleteall /recovering` to delete the junk data. Run `quit` to disconnect ZooKeeper.

#### NOTE

Running this command will cause data loss. Exercise caution.

- Step 6** Run `hdfs dfs -rm -f -r /user/hbase/backup` to delete temporary data.
- Step 7** On Manager, view related snapshot name information from recovery task records.  
Snapshot [ *snapshot name* ] is created successfully before recovery.
- Step 8** Switch to the client, run `hbase shell`, and then `delete_all_snapshot 'snapshot name.*'` to delete the temporary snapshot.

----End

## 6.20.21 How Do I Fix Region Overlapping?

### Question

When the HBaseFsch tool is used to check the region status, if the log contains **ERROR: (regions region1 and region2) There is an overlap in the region chain** or **ERROR: (region region1) Multiple regions have the same startkey: xxx**, overlapping exists in some regions. How do I solve this problem?

### Answer

To rectify the fault, perform the following steps:

- Step 1** Run the `hbase hbck -repair tableName` command to restore the table that contains overlapping.
- Step 2** Run the `hbase hbck tableName` command to check whether overlapping exists in the restored table.
- If overlapping does not exist, go to [Step 3](#).
  - If overlapping exists, go to [Step 1](#).
- Step 3** Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **HBase** > **More** > **Perform HMaster Switchover** to complete the HMaster active/standby switchover.
- Step 4** Run the `hbase hbck tableName` command to check whether overlapping exists in the restored table.
- If overlapping does not exist, no further action is required.
  - If overlapping still exists, start from [Step 1](#) to perform the recovery again.
- End

## 6.20.22 Why Does RegionServer Fail to Be Started When GC Parameters Xms and Xmx of HBase RegionServer Are Set to 31 GB?

### Question

Check the `hbase-omm-*.out` log of the node where RegionServer fails to be started. It is found that the log contains **An error report file with more information is saved as: /tmp/hs\_err\_pid\*.log**. Check the `/tmp/hs_err_pid*.log` file. It is found that the log contains **#Internal Error (vtableStubs\_aarch64.cpp: 213), pid=9456, tid=0x0000ffff97fdd200 and #guarantee(\_\_ pc() <= s->code\_end()) failed: overflowed buffer**, indicating that the problem is caused by JDK. How do I solve this problem?

### Answer

To rectify the fault, perform the following steps:

- Step 1** Run the `su - omm` command on a node where RegionServer fails to be started to switch to user `omm`.
- Step 2** Run the `java -XX:+PrintFlagsFinal -version |grep HeapBase` command as user `omm`. Information similar to the following is displayed:
- ```
uintx HeapBaseMinAddress = 2147483648 {pd product}
```
- Step 3** Change the values of `-Xms` and `-Xmx` in `GC_OPTS` to values that are not between `32G-HeapBaseMinAddress` and `32G`, excluding the values of `32G` and `32G-HeapBaseMinAddress`.
- Step 4** Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **HBase** > **Instance**, select the failed instance, and choose **More** > **Restart Instance** to restart the failed instance.
- End

## 6.20.23 Why Does the LoadIncrementalHFiles Tool Fail to Be Executed and "Permission denied" Is Displayed When Nodes in a Cluster Are Used to Import Data in Batches?

### Question

Why does the LoadIncrementalHFiles tool fail to be executed and "Permission denied" is displayed when a Linux user is manually created in a normal cluster and DataNode in the cluster is used to import data in batches?

```
2020-09-20 14:53:53,808 WARN [main] shortcircuit.DomainSocketFactory: error creating DomainSocket
java.net.ConnectException: connect(2) error: Permission denied when trying to connect to '/var/run/
FusionInsight-HDFS/dn_socket'
    at org.apache.hadoop.net.unix.DomainSocket.connect0(Native Method)
    at org.apache.hadoop.net.unix.DomainSocket.connect(DomainSocket.java:256)
    at org.apache.hadoop.hdfs.shortcircuit.DomainSocketFactory.createSocket(DomainSocketFactory.java:168)
    at org.apache.hadoop.hdfs.client.impl.BlockReaderFactory.nextDomainPeer(BlockReaderFactory.java:804)
    at
org.apache.hadoop.hdfs.client.impl.BlockReaderFactory.createShortCircuitReplicaInfo(BlockReaderFactory.java
:526)
    at org.apache.hadoop.hdfs.shortcircuit.ShortCircuitCache.create(ShortCircuitCache.java:785)
    at org.apache.hadoop.hdfs.shortcircuit.ShortCircuitCache.fetchOrCreate(ShortCircuitCache.java:722)
    at org.apache.hadoop.hdfs.client.impl.BlockReaderFactory.getBlockReaderLocal(BlockReaderFactory.java:
483)
    at org.apache.hadoop.hdfs.client.impl.BlockReaderFactory.build(BlockReaderFactory.java:360)
    at org.apache.hadoop.hdfs.DFSInputStream.getBlockReader(DFSInputStream.java:663)
    at org.apache.hadoop.hdfs.DFSInputStream.blockSeekTo(DFSInputStream.java:594)
    at org.apache.hadoop.hdfs.DFSInputStream.readWithStrategy(DFSInputStream.java:776)
    at org.apache.hadoop.hdfs.DFSInputStream.read(DFSInputStream.java:845)
    at java.io.DataInputStream.readFully(DataInputStream.java:195)
    at org.apache.hadoop.hbase.io.hfile.FixedFileTrailer.readFromStream(FixedFileTrailer.java:401)
    at org.apache.hadoop.hbase.io.hfile.HFile.isHFileFormat(HFile.java:651)
    at org.apache.hadoop.hbase.io.hfile.HFile.isHFileFormat(HFile.java:634)
    at org.apache.hadoop.hbase.tool.LoadIncrementalHFiles.visitBulkHFiles(LoadIncrementalHFiles.java:1090)
    at org.apache.hadoop.hbase.tool.LoadIncrementalHFiles.discoverLoadQueue(LoadIncrementalHFiles.java:
1006)
    at org.apache.hadoop.hbase.tool.LoadIncrementalHFiles.prepareHFileQueue(LoadIncrementalHFiles.java:
257)
    at org.apache.hadoop.hbase.tool.LoadIncrementalHFiles.doBulkLoad(LoadIncrementalHFiles.java:364)
    at org.apache.hadoop.hbase.tool.LoadIncrementalHFiles.run(LoadIncrementalHFiles.java:1263)
    at org.apache.hadoop.hbase.tool.LoadIncrementalHFiles.run(LoadIncrementalHFiles.java:1276)
    at org.apache.hadoop.hbase.tool.LoadIncrementalHFiles.run(LoadIncrementalHFiles.java:1311)
    at org.apache.hadoop.util.ToolRunner.run(ToolRunner.java:76)
    at org.apache.hadoop.hbase.tool.LoadIncrementalHFiles.main(LoadIncrementalHFiles.java:1333)
```

### Answer

If the client that the LoadIncrementalHFiles tool depends on is installed in the cluster and is on the same node as DataNode, HDFS creates short-circuit read during the execution of the tool to improve performance. The short-circuit read depends on the `/var/run/FusionInsight-HDFS` directory (`dfs.domain.socket.path`). The default permission on this directory is `750`. This user does not have the permission to operate the directory.

To solve the preceding problem, perform the following operations:

Method 1: Create a user (recommended).

#### Step 1 Create a user on Manager. By default, the user group contains the `ficommon` group.

```
[root@xxx-xxx-xxx-xxx ~]# id test
uid=20038(test) gid=9998(ficommon) groups=9998(ficommon)
```

**Step 2** Import data again.

----End

Method 2: Change the owner group of the current user.

**Step 1** Add the user to the **ficommon** group.

```
[root@xxx-xxx-xxx-xxx ~]# usermod -a -G ficommon test  
[root@xxx-xxx-xxx-xxx ~]# id test  
uid=2102(test) gid=2102(test) groups=2102(test),9998(ficommon)
```

**Step 2** Import data again.

----End

## 6.20.24 Why Is the Error Message "import argparse" Displayed When the Phoenix sqlline Script Is Used?

### Question

When the sqlline script is used on the client, the error message "import argparse" is displayed.

### Answer

**Step 1** Log in to the node where the HBase client is installed as user **root**. Perform security authentication using the **hbase** user.

**Step 2** Go to the directory where the sqlline script of the HBase client is stored and run the **python3 sqlline.py** command.

----End

## 6.20.25 How Do I Deal with the Restrictions of the Phoenix BulkLoad Tool?

### Question

When the indexed field data is updated, if a batch of data exists in the user table, the BulkLoad tool cannot update the global and partial mutable indexes.

### Answer

#### Problem Analysis

1. Create a table.

```
CREATE TABLE TEST_TABLE(  
DATE varchar not null,  
NUM integer not null,  
SEQ_NUM integer not null,  
ACCOUNT1 varchar not null,  
ACCOUNTDES varchar,  
FLAG varchar,  
SALL double,  
CONSTRAINT PK PRIMARY KEY (DATE,NUM,SEQ_NUM,ACCOUNT1)  
);
```

2. Create a global index.

```
CREATE INDEX TEST_TABLE_INDEX ON
TEST_TABLE(ACCOUNT1,DATE,NUM,ACCOUNTDES,SEQ_NUM);
```

3. Insert data.

```
UPSERT INTO TEST_TABLE
(DATE,NUM,SEQ_NUM,ACCOUNT1,ACCOUNTDES,FLAG,SALL) values
('20201001',30201001,13,'367392332','sffa1','');
```

4. Execute the BulkLoad task to update data.

```
hbase org.apache.phoenix.mapreduce.CsvBulkLoadTool -t TEST_TABLE -
i /tmp/test.csv, where the content of test.csv is as follows:
```

20201001	30201001	13	367392332	sffa888	1231243	23
----------	----------	----	-----------	---------	---------	----

5. Symptom: The existing index data cannot be directly updated. As a result, two pieces of index data exist.

```
+-----+-----+-----+-----+-----+
|:ACCOUNT1 | :DATE | :NUM | 0:ACCOUNTDES | :SEQ_NUM |
+-----+-----+-----+-----+-----+
| 367392332 | 20201001 | 30201001 | sffa1 | 13 |
| 367392332 | 20201001 | 30201001 | sffa888 | 13 |
+-----+-----+-----+-----+-----+
```

### Solution

- Step 1** Delete the old index table.

```
DROP INDEX TEST_TABLE_INDEX ON TEST_TABLE;
```

- Step 2** Create an index table in asynchronous mode.

```
CREATE INDEX TEST_TABLE_INDEX ON
TEST_TABLE(ACCOUNT1,DATE,NUM,ACCOUNTDES,SEQ_NUM) ASYNC;
```

- Step 3** Recreate a index.

```
hbase org.apache.phoenix.mapreduce.index.IndexTool --data-table
TEST_TABLE --index-table TEST_TABLE_INDEX --output-path /user/test_table
```

----End

## 6.20.26 Why a Message Is Displayed Indicating that the Permission is Insufficient When CTBase Connects to the Ranger Plug-ins?

### Question

When CTBase accesses the HBase service with the Ranger plug-ins enabled and you are creating a cluster table, a message is displayed indicating that the permission is insufficient.

```
ERROR: Create ClusterTable failed. Error: org.apache.hadoop.hbase.security.AccessDeniedException:
Insufficient permissions for user 'ctbase2@HADOOP.COM' (action=create)
at org.apache.ranger.authorization.hbase.AuthorizationSession.publishResults(AuthorizationSession.java:278)
at
```

```
org.apache.ranger.authorization.hbase.RangerAuthorizationCoproces
sor.authorizeAccess(RangerAuthorizati
onCoprocesor.java:654)
at
org.apache.ranger.authorization.hbase.RangerAuthorizationCoproces
sor.requirePermission(RangerAuthorizati
onCoprocesor.java:772)
at
org.apache.ranger.authorization.hbase.RangerAuthorizationCoproces
sor.preCreateTable(RangerAuthorizati
onCoprocesor.java:943)
at
org.apache.ranger.authorization.hbase.RangerAuthorizationCoproces
sor.preCreateTable(RangerAuthorizati
onCoprocesor.java:428)
at org.apache.hadoop.hbase.master.MasterCoprocesorHost$12.call(M
asterCoprocesorHost.java:351)
at org.apache.hadoop.hbase.master.MasterCoprocesorHost$12.call(M
asterCoprocesorHost.java:348)
at org.apache.hadoop.hbase.coprocesor.CoprocesorHost
$ObserverOperationWithoutResult.callObserver(CoprocesorHost.java:581)
at org.apache.hadoop.hbase.coprocesor.CoprocesorHost.execOperati
on(CoprocesorHost.java:655)
at org.apache.hadoop.hbase.master.MasterCoprocesorHost.preCreat
eTable(MasterCoprocesorHost.java:
348)
at org.apache.hadoop.hbase.master.HMaster$5.run(HMaster.java:2192)
at
org.apache.hadoop.hbase.master.procedure.MasterProcedureUtil.sub
mitProcedure(MasterProcedureUtil.java:
134)
at org.apache.hadoop.hbase.master.HMaster.createTable(HMaster.ja
va:2189)
at org.apache.hadoop.hbase.master.MasterRpcServices.createTable(M
asterRpcServices.java:711)
at org.apache.hadoop.hbase.shaded.protobuf.generated.MasterProtos
$MasterService
$2.callBlockingMethod(MasterProtos.java)
at org.apache.hadoop.hbase.ipc.RpcServer.call(RpcServer.java:458)
at org.apache.hadoop.hbase.ipc.CallRunner.run(CallRunner.java:133)
at org.apache.hadoop.hbase.ipc.RpcExecutor$Handler.run(RpcExecuto
r.java:338)
at org.apache.hadoop.hbase.ipc.RpcExecutor$Handler.run(RpcExecuto
r.java:318)
```

## Answer

CTBase users can configure permission policies on the Ranger page and grant the READ, WRITE, CREATE, ADMIN, and EXECUTE permissions to the CTBase metadata table `_ctmeta_`, cluster table, and index table.

# 7 Using HDFS

---

## 7.1 Configuring Memory Management

### Scenario

In HDFS, each file object needs to register corresponding information in the NameNode and occupies certain storage space. As the number of files increases, if the original memory space cannot store the corresponding information, you need to change the memory size.

### Configuration Description

**Navigation path for setting parameters:**

Go to the **All Configurations** page of HDFS by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-1** Parameter description

Parameter	Description	Default Value
GC_PROFILE	<p>The NameNode memory size depends on the size of FsImage, which can be calculated based on the following formula: FsImage size = Number of files x 900 bytes. You can estimate the memory size of the NameNode of HDFS based on the calculation result.</p> <p>The value range of this parameter is as follows:</p> <ul style="list-style-type: none"> <li>● <b>high:</b> 4 GB</li> <li>● <b>medium:</b> 2 GB</li> <li>● <b>low:</b> 256 MB</li> <li>● <b>custom:</b> The memory size can be set according to the data size in GC_OPTS.</li> </ul>	custom
GC_OPTS	<p>JVM parameter used for garbage collection (GC). This parameter is valid only when <b>GC_PROFILE</b> is set to <b>custom</b>. Ensure that the <b>GC_OPT</b> parameter is set correctly. Otherwise, the process will fail to be started.</p> <p><b>NOTICE</b> Exercise caution when you modify the configuration. If the configuration is incorrect, the services are unavailable.</p>	<p>-Xms2G -Xmx4G - XX:NewSize=128M - XX:MaxNewSize=256M - XX:MetaspaceSize=128M - XX:MaxMetaspaceSize=128M - XX:+UseConcMarkSweepGC -XX: +CMSParallelRemarkEnabled - XX:CMSInitiatingOccupancyFrac- tion=65 -XX:+PrintGCDetails - Dsun.rmi.dgc.client.gcInterval=0 x7FFFFFFFFFFFFFFE - Dsun.rmi.dgc.server.gcInterval=0 x7FFFFFFFFFFFFFFE -XX:- OmitStackTraceInFastThrow -XX: +PrintGCDateStamps -XX: +UseGCLogFileRotation - XX:NumberOfGCLogFiles=10 - XX:GCLogFileSize=1M - Djdk.tls.ephemeralDHKeySize=2 048</p>

## 7.2 Creating an HDFS Role

### Scenario

This section describes how to create and configure an HDFS role on FusionInsight Manager. The HDFS role is granted the rights to read, write, and execute HDFS directories or files.

A user has the complete permission on the created HDFS directories or files, that is, the user can directly read data from and write data to as well as authorize others to access the HDFS directories or files.

#### NOTE

- An HDFS role can be created only in security mode.
- If the current component uses Ranger for permission control, HDFS policies must be configured based on Ranger for permission management. For details, see [Adding a Ranger Access Permission Policy for HDFS](#).

### Prerequisites

The MRS cluster administrator has understood the service requirements.

### Procedure

**Step 1** Log in to FusionInsight Manager, and choose **System > Permission > Role**.

**Step 2** On the displayed page, click **Create Role** and fill in **Role Name** and **Description**.

**Step 3** Configure the resource permission. For details, see [Table 7-2](#).

**File System:** HDFS directory and file permission

Common HDFS directories are as follows:

- **flume:** Flume data storage directory
- **hbase:** HBase data storage directory
- **mr-history:** MapReduce task information storage directory
- **tmp:** temporary data storage directory
- **user:** user data storage directory

**Table 7-2** Setting a role

Task	Operation
Setting the HDFS administrator permission	In the <b>Configure Resource Permission</b> area, choose <i>Name of the desired cluster</i> > HDFS, and select <b>Cluster Admin Operations</b> . <b>NOTE</b> The setting takes effect after the HDFS service is restarted.

Task	Operation
Setting the permission for users to check and recover HDFS	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> area, choose <i>Name of the desired cluster</i> &gt; HDFS &gt; <b>File System</b>.</li> <li>2. Locate the save path of specified directories or files on HDFS.</li> <li>3. In the <b>Permission</b> column of the specified directories or files, select <b>Read</b> and <b>Execute</b>.</li> </ol>
Setting the permission for users to read directories or files of other users	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> area, choose <i>Name of the desired cluster</i> &gt; HDFS &gt; <b>File System</b>.</li> <li>2. Locate the save path of specified directories or files on HDFS.</li> <li>3. In the <b>Permission</b> column of the specified directories or files, select <b>Read</b> and <b>Execute</b>.</li> </ol>
Setting the permission for users to write data to files of other users	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> area, choose <i>Name of the desired cluster</i> &gt; HDFS &gt; <b>File System</b>.</li> <li>2. Locate the save path of specified files on HDFS.</li> <li>3. In the <b>Permission</b> column of the specified files, select <b>Write</b> and <b>Execute</b>.</li> </ol>
Setting the permission for users to create or delete sub-files or sub-directories in the directory of other users	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> area, choose <i>Name of the desired cluster</i> &gt; HDFS &gt; <b>File System</b>.</li> <li>2. Locate the path where the specified directory is saved in the HDFS.</li> <li>3. In the <b>Permission</b> column of the specified directories, select <b>Write</b> and <b>Execute</b>.</li> </ol>
Setting the permission for users to execute directories or files of other users	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> area, choose <i>Name of the desired cluster</i> &gt; HDFS &gt; <b>File System</b>.</li> <li>2. Locate the save path of specified directories or files on HDFS.</li> <li>3. In the <b>Permission</b> column of the specified directories or files, select <b>Execute</b>.</li> </ol>

Task	Operation
Setting the permission for allowing subdirectories to inherit all permissions of their parent directories	<ol style="list-style-type: none"><li>1. In the <b>Configure Resource Permission</b> area, choose <i>Name of the desired cluster</i> &gt; HDFS &gt; <b>File System</b>.</li><li>2. Locate the save path of specified directories or files on HDFS.</li><li>3. In the <b>Permission</b> column of the specified directories or files, select <b>Recursive</b>.</li></ol>

**Step 4** Click **OK**, and return to the **Role** page.

----End

## 7.3 Using the HDFS Client

### Scenario

This section describes how to use the HDFS client in an O&M scenario or service scenario.

### Prerequisites

- The client has been installed.  
For example, the installation directory is **/opt/hadoopclient**. The client directory in the following operations is only an example. Change it to the actual installation directory.
- Service component users are created by the MRS cluster administrator as required. In security mode, machine-machine users need to download the keytab file. A human-machine user needs to change the password upon the first login. (This operation is not required in normal mode.)

### Using the HDFS Client

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to go to the client installation directory:

```
cd /opt/hadoopclient
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** If the cluster is in security mode, run the following command to authenticate the user. In normal mode, user authentication is not required.

```
kinit Component service user
```

**Step 5** Run the HDFS Shell command. Example:

```
hdfs dfs -ls /
----End
```

## Common HDFS Client Commands

The following table lists common HDFS client commands.

For more commands, see [https://hadoop.apache.org/docs/stable/hadoop-project-dist/hadoop-common/CommandsManual.html#User\\_Commands](https://hadoop.apache.org/docs/stable/hadoop-project-dist/hadoop-common/CommandsManual.html#User_Commands).

**Table 7-3** Common HDFS client commands

Command	Description	Example
<b>hdfs dfs -mkdir</b> <i>Folder name</i>	Used to create a folder.	<b>hdfs dfs -mkdir /tmp/mydir</b>
<b>hdfs dfs -ls</b> <i>Folder name</i>	Used to view a folder.	<b>hdfs dfs -ls /tmp</b>
<b>hdfs dfs -put</b> <i>Local file on the client node</i>	Used to upload a local file to a specified HDFS path.	<b>hdfs dfs -put /opt/test.txt /tmp</b> Upload the <b>/opt/test.txt</b> file on the client node to the <b>/tmp</b> directory of HDFS.
<b>hdfs dfs -get</b> <i>Specified file on HDFS Specified path on the client node</i>	Used to download the HDFS file to the specified local path.	<b>hdfs dfs -get /tmp/test.txt /opt/</b> Download the <b>/tmp/test.txt</b> file on HDFS to the <b>/opt</b> path on the client node.
<b>hdfs dfs -rm -r -f</b> <i>Specified folder on HDFS</i>	Used to delete a folder.	<b>hdfs dfs -rm -r -f /tmp/mydir</b>

## Client-related FAQs

1. What do I do when the HDFS client exits abnormally and error message "java.lang.OutOfMemoryError" is displayed after the HDFS client command is running?

This problem occurs because the memory required for running the HDFS client exceeds the preset upper limit (128 MB by default). You can change the memory upper limit of the client by modifying **CLIENT\_GC\_OPTS** in *<Client installation path>/HDFS/component\_env*. For example, if you want to set the upper limit to 1 GB, run the following command:

```
CLIENT_GC_OPTS="-Xmx1G"
```

After the modification, run the following command to make the modification take effect:

```
source <Client installation path>/bigdata_env
```

2. How can i set the log level when the HDFS client is running?

By default, the logs generated during the running of the HDFS client are printed to the console. The default log level is INFO. To enable the DEBUG log

level for fault locating, run the following command to export an environment variable:

```
export HADOOP_ROOT_LOGGER=DEBUG,console
```

Then run the HDFS Shell command to generate the DEBUG logs.

If you want to print INFO logs again, run the following command:

```
export HADOOP_ROOT_LOGGER=INFO,console
```

## 7.4 Running the DistCp Command

### Scenario

DistCp is a tool used to perform large-amount data replication between clusters or in a cluster. It uses MapReduce tasks to implement distributed copy of a large amount of data.

### Prerequisites

- The Yarn client or a client that contains Yarn has been installed. For example, the installation directory is **/opt/client**.
- Service users of each component are created by the MRS cluster administrator based on service requirements. In security mode, machine-machine users need to download the keytab file. A human-machine user must change the password upon the first login. (Not involved in normal mode)
- To copy data between clusters, you need to enable the inter-cluster data copy function on both clusters.

### Procedure

**Step 1** Log in to the node where the client is installed.

**Step 2** Run the following command to go to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** If the cluster is in security mode, the user group to which the user executing the DistCp command belongs must be **supergroup** and the user run the following command to perform user authentication. In normal mode, user authentication is not required.

```
kinit Component service user
```

**Step 5** Run the DistCp command. The following provides an example:

```
hadoop distcp hdfs://hacluster/source hdfs://hacluster/target
```

```
----End
```

## Common Usage of DistCp

1. The following is an example of the commonest usage of DistCp:

```
hadoop distcp -numListstatusThreads 40 -update -delete -prbugpaxtq hdfs://cluster1/source hdfs://cluster2/target
```

### NOTE

In the preceding command:

- **-numListstatusThreads** specifies the number of threads for creating the list of 40 copied files.
  - **-update -delete** specifies that files at the source location and the target location are synchronized, and that files with excessive target locations are deleted. If you need to copy files incrementally, delete **-delete**.
  - If **-prbugpaxtq** and **-update** are used, it indicates that the status information of the copied file is also updated.
  - **hdfs://cluster1/source** indicates the source location, and **hdfs://cluster2/target** indicates the target location.
2. The following is an example of data copy between clusters:

```
hadoop distcp hdfs://cluster1/foo/bar hdfs://cluster2/bar/foo
```

### NOTE

The network between cluster1 and cluster2 must be reachable, and the two clusters must use the same HDFS version or compatible HDFS versions.

3. The following are multiple examples of data copy in a source directory:

```
hadoop distcp hdfs://cluster1/foo/a \  
hdfs://cluster1/foo/b \  
hdfs://cluster2/bar/foo
```

The preceding command is used to copy the folders a and b of cluster1 to the **/bar/foo** directory of cluster2. The effect is equivalent to that of the following commands:

```
hadoop distcp -f hdfs://cluster1/srclist \  
hdfs://cluster2/bar/foo
```

The content of **srclist** is as follows. Before running the DistCp command, upload the **srclist** file to HDFS.

```
hdfs://cluster1/foo/a  
hdfs://cluster1/foo/b
```

4. **-update** indicates that a to-be-copied file does not exist in the target location, or the content of the copied file in the target location is updated; and **-overwrite** is used to overwrite existing files in the target location.

The following is an example of the difference between no option and any one of the two options (either **update** or **overwrite**) that is added:

Assume that the structure of a file at the source location is as follows:

```
hdfs://cluster1/source/first/1  
hdfs://cluster1/source/first/2  
hdfs://cluster1/source/second/10  
hdfs://cluster1/source/second/20
```

Commands without options are as follows:

```
hadoop distcp hdfs://cluster1/source/first hdfs://cluster1/source/second hdfs://cluster2/target
```

By default, the preceding command creates the **first** and **second** folders at the target location. Therefore, the copy results are as follows:

```
hdfs://cluster2/target/first/1  
hdfs://cluster2/target/first/2  
hdfs://cluster2/target/second/10  
hdfs://cluster2/target/second/20
```

The command with any one of the two options (for example, **update**) is as follows:

```
hadoop distcp -update hdfs://cluster1/source/first hdfs://cluster1/source/second hdfs://cluster2/target
```

The preceding command copies only the content at the source location to the target location. Therefore, the copy results are as follows:

```
hdfs://cluster2/target/1
hdfs://cluster2/target/2
hdfs://cluster2/target/10
hdfs://cluster2/target/20
```

 **NOTE**

- If files with the same name exist in multiple source locations, the DistCp command fails.
- If neither **update** nor **overwrite** is used and the file to be copied already exists in the target location, the file will be skipped.
- When **update** is used, if the file to be copied already exists in the target location but the file content is different, the file content in the target location is updated.
- When **overwrite** is used, if the file to be copied already exists in the target location, the file in the target location is still overwritten.

5. The following table describes other command options:

**Table 7-4** Other command options

Option	Description
-p[rbugpcaxtq]	When <b>-update</b> is also used, the status information of a copied file is updated even if the content of the copied file is not updated. <b>r</b> : number of copies <b>b</b> : size of a block <b>u</b> : user to which the files belong <b>g</b> : user group to which the user belongs <b>p</b> : permission <b>c</b> : check and type <b>a</b> : access control <b>t</b> : timestamp <b>q</b> : quota information
-i	Failures ignored during copying
-log <logdir>	Path of the specified log
-v	Additional information in the specified log
-m <num_maps>	Maximum number of concurrent copy tasks that can be executed at the same time
-numListstatusThreads	Number of threads for constituting the list of copied files. This option increases the running speed of DistCp.
-overwrite	File at the target location that is to be overwritten

Option	Description
-update	A file at the target location is updated if the size and check of a file at the source location are different from those of the file at the target location.
-append	When <b>-update</b> is also used, the content of the file at the source location is added to the file at the target location.
-f <urilist_uri>	Content of the <urilist_uri> file is used as the file list to be copied.
-filters	A local file is specified whose content contains multiple regular expressions. If the file to be copied matches a regular expression, the file is not copied.
-async	The <b>distcp</b> command is run asynchronously.
-atomic {-tmp <tmp_dir>}	An atomic copy can be performed. You can add a temporary directory during copying.
-bandwidth	The transmission bandwidth of each copy task. Unit: MB/s.
-delete	The files that exist in the target location is deleted but do not exist in the source location. This option is usually used with <b>-update</b> , and indicates that files at the source location are synchronized with those at the target location and the redundant files at the target location are deleted.
-diff <oldSnapshot> <newSnapshot>	The differences between the old and new versions are copied to a file in the old version at the target location.
-skipcrccheck	Whether to skip the cyclic redundancy check (CRC) between the source file and the target file.
-strategy {dynamic uniformsize}	The policy for copying a task. The default policy is <b>uniformsize</b> , that is, each copy task copies the same number of bytes.
-preserveec	Whether to retain the erasure code (EC) policy.

## FAQs of DistCp

1. When you run the DistCp command, if the content of some copied files is large, you are advised to change the timeout period of MapReduce that executes the copy task. It can be implemented by specifying the **mapreduce.task.timeout** in the DistCp command. For example, run the following command to change the timeout to 30 minutes:  

```
hadoop distcp -Dmapreduce.task.timeout=1800000 hdfs://cluster1/source hdfs://cluster2/target
```

Or, you can also use **filters** to exclude the large files out of the copy process. The command example is as follows:

```
hadoop distcp -filters /opt/client/filterfile hdfs://cluster1/source hdfs://cluster2/target
```

In the preceding command, *filterfile* indicates a local file, which contains multiple expressions used to match the path of a file that is not copied. The following is an example:

```
.*excludeFile1.*  
.*excludeFile2.*
```

2. If the DistCp command unexpectedly quits, the error message "java.lang.OutOfMemoryError" is displayed.

This is because the memory required for running the copy command exceeds the preset memory limit (default value: 128 MB). You can change the memory upper limit of the client by modifying **CLIENT\_GC\_OPTS** in *<Client installation path>/HDFS/component\_env*. For example, if you want to set the memory upper limit to 1 GB, refer to the following configuration:

```
CLIENT_GC_OPTS="-Xmx1G"
```

After the modification, run the following command to make the modification take effect:

```
source {Client installation path}/bigdata_env
```

3. When the dynamic policy is used to run the DistCp command, the command exits unexpectedly and the error message "Too many chunks created with splitRatio" is displayed.

The cause of this problem is that the value of **distcp.dynamic.max.chunks.tolerable** (default value: 20,000) is less than the value of **distcp.dynamic.split.ratio** (default value: 2) multiplied by the number of Maps. This problem occurs when the number of Maps exceeds 10,000. You can use the **-m** parameter to reduce the number of Maps to less than 10,000.

```
hadoop distcp -strategy dynamic -m 9500 hdfs://cluster1/source hdfs://cluster2/target
```

Alternatively, you can use the **-D** parameter to set **distcp.dynamic.max.chunks.tolerable** to a large value.

```
hadoop distcp -Ddistcp.dynamic.max.chunks.tolerable=30000 -strategy dynamic hdfs://cluster1/source hdfs://cluster2/target
```

## 7.5 Overview of HDFS File System Directories

This section describes the directory structure in HDFS, as shown in the following table.

**Table 7-5** Directory structure of the HDFS file system

Path	Type	Function	Whether the Directory Can Be Deleted	Deletion Consequence
/tmp/spark2x/sparkhive-scratch	Fixed directory	Stores temporary files of metastore session in Spark2x JDBCServer.	No	Failed to run the task.
/tmp/sparkhive-scratch	Fixed directory	Stores temporary files of metastore sessions that are executed in CLI mode using Spark2x CLI.	No	Failed to run the task.
/tmp/logs/	Fixed directory	Stores container log files.	Yes	Container log files cannot be viewed.
/tmp/carbon/	Fixed directory	Stores the abnormal data in this directory if abnormal CarbonData data exists during data import.	Yes	Error data is lost.
/tmp/Loader- <i>{Job name}_</i> <i>{MR job ID}</i>	Temporary directory	Stores the region information about Loader HBase bulkload jobs. The data is automatically deleted after the job running is completed.	No	Failed to run the Loader HBase Bulkload job.
/tmp/hadoop-omm/yarn/system/rmstore	Fixed directory	Stores the ResourceManager running information.	Yes	Status information is lost after ResourceManager is restarted.
/tmp/archived	Fixed directory	Archives the MR task logs on HDFS.	Yes	MR task logs are lost.
/tmp/hadoop-yarn/staging	Fixed directory	Stores the run logs, summary information, and configuration attributes of ApplicationMaster running jobs.	No	Services are running improperly.

Path	Type	Function	Whether the Directory Can Be Deleted	Deletion Consequence
/tmp/hadoop-yarn/staging/history/done_intermediate	Fixed directory	Stores temporary files in the <b>/tmp/hadoop-yarn/staging</b> directory after all tasks are executed.	No	MR task logs are lost.
/tmp/hadoop-yarn/staging/history/done	Fixed directory	The periodic scanning thread periodically moves the <b>done_intermediate</b> log file to the <b>done</b> directory.	No	MR task logs are lost.
/tmp/mr-history	Fixed directory	Stores the historical record files that are pre-loaded.	No	Historical MR task log data is lost.
/tmp/hive-scratch	Fixed directory	Stores temporary data (such as session information) generated during Hive running.	No	Failed to run the current task.
/user/{user}/.spark Staging	Fixed directory	Stores temporary files of the SparkJDBCServer application.	No	Failed to start the executor.
/user/spark2x/jars	Fixed directory	Stores running dependency packages of the Spark2x executor.	No	Failed to start the executor.
/user/loader	Fixed directory	Stores dirty data of Loader jobs and data of HBase jobs.	No	Failed to execute the HBase job. Or dirty data is lost.
/user/loader/etl_dirty_data_dir				
/user/loader/etl_hbase_pu tlist_tmp				
/user/loader/etl_hbase_tm p				

Path	Type	Function	Whether the Directory Can Be Deleted	Deletion Consequence
/user/oozie	Fixed directory	Stores dependent libraries required for Oozie running, which needs to be manually uploaded.	No	Failed to schedule Oozie.
/user/mapred/hadoop-mapreduce-3.1.1.tar.gz	Fixed files	Stores JAR files used by the distributed MR cache.	No	The MR distributed cache function is unavailable.
/user/hive	Fixed directory	Stores Hive-related data by default, including the depended Spark lib package and default table data storage path.	No	User data is lost.
/user/omm-bulkload	Temporary directory	Stores HBase batch import tools temporarily.	No	Failed to import HBase tasks in batches.
/user/hbase	Temporary directory	Stores HBase batch import tools temporarily.	No	Failed to import HBase tasks in batches.
/spark2xJobHistory2x	Fixed directory	Stores Spark2.x eventlog data.	No	The History Server service is unavailable, and the task fails to be executed.
/flume	Fixed directory	Stores data collected by Flume from HDFS.	No	Flume runs improperly.
/mr-history/tmp	Fixed directory	Stores logs generated by MapReduce jobs.	Yes	Log information is lost.
/mr-history/done	Fixed directory	Stores logs managed by MR JobHistory Server.	Yes	Log information is lost.

Path	Type	Function	Whether the Directory Can Be Deleted	Deletion Consequence
/tenant	Created when a tenant is added.	Directory of a tenant in the HDFS. By default, the system automatically creates a folder in the / <b>tenant</b> directory based on the tenant name. For example, the default HDFS storage directory for <b>ta1</b> is <b>tenant/ta1</b> . When a tenant is created for the first time, the system creates the / <b>tenant</b> directory in the HDFS root directory. You can customize the storage path.	No	The tenant account is unavailable.
/apps{1~5}/	Fixed directory	Stores the Hive package used by WebHCat.	No	Failed to run the WebHCat tasks.
/hbase	Fixed directory	Stores HBase data.	No	HBase user data is lost.
/hbaseFileStream	Fixed directory	Stores HFS files.	No	The HFS file is lost and cannot be restored.

## 7.6 Changing the DataNode Storage Directory

### Scenario

If the storage directory defined by the HDFS DataNode is incorrect or the HDFS storage plan changes, the MRS cluster administrator needs to modify the DataNode storage directory on FusionInsight Manager to ensure that the HDFS works properly. Changing the ZooKeeper storage directory includes the following scenarios:

- Change the storage directory of the DataNode role. In this way, the storage directories of all DataNode instances are changed.
- Change the storage directory of a single DataNode instance. In this way, only the storage directory of this instance is changed, and the storage directories of other instances remain the same.

## Impact on the System

- The HDFS service needs to be stopped and restarted during the process of changing the storage directory of the DataNode role, and the cluster cannot provide services before it is completely started.
- The DataNode instance needs to be stopped and restarted during the process of changing the storage directory of the instance, and the instance at this node cannot provide services before it is started.
- The directory for storing service parameter configurations must also be updated.

## Prerequisites

- New disks have been prepared and installed on each data node, and the disks are formatted.
- New directories have been planned for storing data in the original directories.
- The HDFS client has been installed.
- The MRS cluster administrator user **hdfs** is available.
- When changing the storage directory of a single DataNode instance, ensure that the number of active DataNode instances is greater than the value of **dfs.replication**.

## Procedure

### Check the environment.

**Step 1** Log in to the server where the HDFS client is installed as user **root**, and run the following command to configure environment variables:

```
source Installation directory of the HDFS client/bigdata_env
```

**Step 2** If the cluster is in security mode, run the following command to authenticate the user:

```
kinit hdfs
```

**Step 3** Run the following command on the HDFS client to check whether all directories and files in the HDFS root directory are normal:

```
hdfs fsck /
```

Check the fsck command output.

- If the following information is displayed, no file is lost or damaged. Go to [Step 4](#).  
The filesystem under path '/' is HEALTHY
- If other information is displayed, some files are lost or damaged. Go to [Step 5](#).

**Step 4** Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services**, and check whether **Running Status** of HDFS is **Normal**.

- If yes, go to [Step 6](#).
- If no, the HDFS status is unhealthy. Go to [Step 5](#).

- Step 5** Rectify the HDFS fault.. The task is complete.
- Step 6** Determine whether to change the storage directory of the DataNode role or that of a single DataNode instance:
- To change the storage directory of the DataNode role, go to [Step 7](#).
  - To change the storage directory of a single DataNode instance, go to [Step 12](#).

#### Changing the storage directory of the DataNode role

- Step 7** Choose **Cluster** > *Name of the desired cluster* > **Services** > **HDFS** > **Stop Instance** to stop the HDFS service.

- Step 8** Log in to each data node where the HDFS service is installed as user **root** and perform the following operations:

1. Create a target directory (**data1** and **data2** are original directories in the cluster).

For example, to create a target directory `${BIGDATA_DATA_HOME}/hadoop/data3/dn`, run the following commands:

```
mkdir ${BIGDATA_DATA_HOME}/hadoop/data3 and mkdir $  
{BIGDATA_DATA_HOME}/hadoop/data3/dn
```

2. Mount the target directory to the new disk. For example, mount `${BIGDATA_DATA_HOME}/hadoop/data3` to the new disk.
3. Modify permissions on the new directory.

For example, to create a target directory `${BIGDATA_DATA_HOME}/hadoop/data3/dn`, run the following commands:

```
chmod 700 ${BIGDATA_DATA_HOME}/hadoop/data3/dn -R and chown  
omm:wheel ${BIGDATA_DATA_HOME}/hadoop/data3/dn -R
```

4. Copy the data to the target directory.

For example, if the old directory is `${BIGDATA_DATA_HOME}/hadoop/data1/dn` and the target directory is `${BIGDATA_DATA_HOME}/hadoop/data3/dn`, run the following command:

```
cp -af ${BIGDATA_DATA_HOME}/hadoop/data1/dn/* $  
{BIGDATA_DATA_HOME}/hadoop/data3/dn
```

- Step 9** On FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **HDFS** > **Configurations** > **All Configurations** to go to the HDFS service configuration page.

Change the value of `dfs.datanode.data.dir` from the default value `%{@auto.detect.datapart.dn}` to the new target directory, for example, `${BIGDATA_DATA_HOME}/hadoop/data3/dn`.

For example, the original data storage directories are `/srv/BigData/hadoop/data1`, `/srv/BigData/hadoop/data2`. To migrate data from the `/srv/BigData/hadoop/data1` directory to the newly created `/srv/BigData/hadoop/data3` directory, replace the whole parameter with `/srv/BigData/hadoop/data2`, `/srv/BigData/hadoop/data3`. Separate multiple storage directories with commas (,). In this example, changed directories are `/srv/BigData/hadoop/data2`, `/srv/BigData/hadoop/data3`.

- Step 10** Click **Save**. Choose **Cluster** > *Name of the desired cluster* > **Services**. On the page that is displayed, start the services that have been stopped.

**Step 11** After the HDFS is started, run the following command on the HDFS client to check whether all directories and files in the HDFS root directory are correctly copied:

```
hdfs fsck /
```

Check the fsck command output.

- If the following information is displayed, no file is lost or damaged, and data replication is successful. No further action is required.  
The filesystem under path '/' is HEALTHY
- If other information is displayed, some files are lost or damaged. In this case, check whether [8.4](#) is correct and run the `hdfs fsck Name of the damaged file -delete` command.

### Changing the storage directory of a single DataNode instance

**Step 12** Choose **Cluster** > *Name of the desired cluster* > **Services** > **HDFS** > **Instance**. Select the HDFS instance whose storage directory needs to be modified, and choose **More** > **Stop Instance**.

**Step 13** Log in to the DataNode node as user **root**, and perform the following operations:

1. Create a target directory.

For example, to create a target directory `${BIGDATA_DATA_HOME}/hadoop/data3/dn`, run the following commands:

```
mkdir ${BIGDATA_DATA_HOME}/hadoop/data3 and mkdir $  
{BIGDATA_DATA_HOME}/hadoop/data3/dn
```

2. Mount the target directory to the new disk.

For example, mount `${BIGDATA_DATA_HOME}/hadoop/data3` to the new disk.

3. Modify permissions on the new directory.

For example, to create a target directory `${BIGDATA_DATA_HOME}/hadoop/data3/dn`, run the following commands:

```
chmod 700 ${BIGDATA_DATA_HOME}/hadoop/data3/dn -R and chown  
omm:wheel ${BIGDATA_DATA_HOME}/hadoop/data3/dn -R
```

4. Copy the data to the target directory.

For example, if the old directory is `${BIGDATA_DATA_HOME}/hadoop/data1/dn` and the target directory is `${BIGDATA_DATA_HOME}/hadoop/data3/dn`, run the following command:

```
cp -af ${BIGDATA_DATA_HOME}/hadoop/data1/dn/* $  
{BIGDATA_DATA_HOME}/hadoop/data3/dn
```

**Step 14** On FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Service** > **HDFS** > **Instance**. Click the specified DataNode instance and go to the **Configurations** page.

Change the value of `dfs.datanode.data.dir` from the default value `%{@auto.detect.datapart.dn}` to the new target directory, for example, `${BIGDATA_DATA_HOME}/hadoop/data3/dn`.

For example, the original data storage directories are `/srv/BigData/hadoop/data1`, `/srv/BigData/hadoop/data2`. To migrate data from the `/srv/BigData/hadoop/data1` directory to the newly created `/srv/BigData/hadoop/data3`

directory, replace the whole parameter with `/srv/BigData/hadoop/data2,/srv/BigData/hadoop/data3`.

**Step 15** Click **Save**, and then click **OK**.

**Operation succeeded** is displayed. click **Finish**.

**Step 16** Choose **More > Restart Instance** to restart the DataNode instance.

----End

## 7.7 Configuring HDFS Directory Permission

### Scenario

The permission for some HDFS directories is **777** or **750** by default, which brings potential security risks. You are advised to modify the permission for the HDFS directories after the HDFS is installed to increase user security.

### Procedure

Log in to the HDFS client as the MRS cluster administrator and run the following command to modify the permission for the `/user` directory.

The permission is set to **1777**, that is, **1** is added to the original permission. This indicates that only the user who creates the directory can delete it.

```
hdfs dfs -chmod 1777 /user
```

To ensure security of the system file, you are advised to harden the security for non-temporary directories. The following directories are examples:

- `/user:777`
- `/mr-history:777`
- `/mr-history/tmp:777`
- `/mr-history/done:777`
- `/user/mapred:755`

## 7.8 Configuring NFS

### Scenario

Before deploying a cluster, you can deploy a Network File System (NFS) server based on requirements to store NameNode metadata to enhance data reliability.

If the NFS server has been deployed and NFS services are configured, you can follow operations in this section to configure NFS on the cluster. These operations are optional.

### Procedure

**Step 1** Check the permission of the shared NFS directories on the NFS server to ensure that the server can access NameNode in the MRS cluster.

- Step 2** Log in to the active NameNode as user **root**.
- Step 3** Run the following commands to create a directory and assign it write permissions:
- ```
mkdir ${BIGDATA_DATA_HOME}/namenode-nfs  
chown omm:wheel ${BIGDATA_DATA_HOME}/namenode-nfs  
chmod 750 ${BIGDATA_DATA_HOME}/namenode-nfs
```
- Step 4** Run the following command to mount the NFS to the active NameNode:
- ```
mount -t nfs -o rsize=8192,wsiz=8192,soft,nolock,timeo=3,intr IP address of  
the NFS server.Shared directory ${BIGDATA_DATA_HOME}/namenode-nfs
```
- For example, if the IP address of the NFS server is **192.168.0.11** and the shared directory is **/opt/Hadoop/NameNode**, run the following command:
- ```
mount -t nfs -o rsize=8192,wsiz=8192,soft,nolock,timeo=3,intr  
192.168.0.11:/opt/Hadoop/NameNode ${BIGDATA_DATA_HOME}/namenode-  
nfs
```
- Step 5** Perform [Step 2](#) to [Step 4](#) on the standby NameNode.
-  **NOTE**
- The names of the shared directories (for example, **/opt/Hadoop/NameNode**) created on the NFS server by the active and standby NameNodes must be different.
- Step 6** Log in to FusionInsight Manager, and choose **Cluster > Name of the desired cluster > Service > HDFS > Configuration > All Configurations**.
- Step 7** In the search box, search for **dfs.namenode.name.dir**, add **\${BIGDATA\_DATA\_HOME}/namenode-nfs** to **Value**, and click **Save**. Separate paths with commas (,).
- Step 8** Click **OK**. On the **Dashboard** tab page, choose **More > Restart Service** to restart the service.
- End

## 7.9 Planning HDFS Capacity

In HDFS, DataNode stores user files and directories as blocks, and file objects are generated on the NameNode to map each file, directory, and block on the DataNode.

The file objects on the NameNode require certain memory capacity. The memory consumption linearly increases as more file objects generated. The number of file objects on the NameNode increases and the objects consume more memory when the files and directories stored on the DataNode increase. In this case, the existing hardware may not meet the service requirement and the cluster is difficult to be scaled out.

Capacity planning of the HDFS that stores a large number of files is to plan the capacity specifications of the NameNode and DataNode and to set parameters according to the capacity plans.

## Capacity Specifications

- NameNode capacity specifications

Each file object on the NameNode corresponds to a file, directory, or block on the DataNode.

A file uses at least one block. The default size of a block is **134,217,728**, that is, 128 MB, which can be set in the **dfs.blocksize** parameter. By default, a file whose size is less than 128 MB occupies only one block. If the file size is greater than 128 MB, the number of occupied blocks is the file size divided by 128 MB (Number of occupied blocks = File size/128). The directories do not occupy any blocks.

Based on **dfs.blocksize**, the number of file objects on the NameNode is calculated as follows:

**Table 7-6** Number of NameNode file objects

| Size of a File                 | Number of File Objects                                  |
|--------------------------------|---------------------------------------------------------|
| < 128 MB                       | 1 (File) + 1 (Block) = 2                                |
| > 128 MB (for example, 128 GB) | 1 (File) + 1,024 (128 GB/128 MB = 1,024 blocks) = 1,025 |

The maximum number of file objects supported by the active and standby NameNodes is 300,000,000 (equivalent to 150,000,000 small files).

**dfs.namenode.max.objects** specifies the number of file objects that can be generated in the system. The default value is **0**, which indicates that the number of generated file objects is not limited.

- DataNode capacity specifications

In HDFS, blocks are stored on the DataNode as copies. The default number of copies is **3**, which can be set in the **dfs.replication** parameter.

The number of blocks stored on all DataNode role instances in the cluster can be calculated based on the following formula: Number of HDFS blocks x 3  
Average number of saved blocks = Number of HDFS blocks x 3/Number of DataNodes

**Table 7-7** DataNode specifications

| Item                                                                                                           | Specifications |
|----------------------------------------------------------------------------------------------------------------|----------------|
| Maximum number of block supported by a DataNode instance                                                       | 5,000,000      |
| Maximum number of block supported by a disk on a DataNode instance                                             | 500,000        |
| Minimum number of disks required when the number of block supported by a DataNode instance reaches the maximum | 10             |

**Table 7-8** Number of DataNodes

| Number of HDFS Blocks | Minimum Number of DataNode Roles |
|-----------------------|----------------------------------|
| 10,000,000            | 10,000,000 *3/5,000,000 = 6      |
| 50,000,000            | 50,000,000 *3/5,000,000 = 30     |
| 100,000,000           | 100,000,000 *3/5,000,000 = 60    |

## Setting Memory Parameters

- Configuration rules of the NameNode JVM parameter

Default value of the NameNode JVM parameter **GC\_OPTS**:

-Xms2G -Xmx4G -XX:NewSize=128M -XX:MaxNewSize=256M -  
XX:MetaspaceSize=128M -XX:MaxMetaspaceSize=128M -XX:  
+UseConcMarkSweepGC -XX:+CMSParallelRemarkEnabled -  
XX:CMSInitiatingOccupancyFraction=65 -XX:+PrintGCDetails -  
Dsun.rmi.dgc.client.gcInterval=0x7FFFFFFFFFFFFFFE -  
Dsun.rmi.dgc.server.gcInterval=0x7FFFFFFFFFFFFFFE -XX:-  
OmitStackTraceInFastThrow -XX:+PrintGCDateStamps -XX:  
+UseGCLogFileRotation -XX:NumberOfGCLogFiles=10 -XX:GCLogFileSize=1M -  
Djdk.tls.ephemeralDHKeySize=2048

The number of NameNode files is proportional to the used memory size of the NameNode. When file objects change, you need to change **-Xms2G -Xmx4G -XX:NewSize=128M --XX:MaxNewSize=256M** in the default value. The following table lists the reference values.

**Table 7-9** NameNode JVM configuration

| Number of File Objects | Reference Value                                          |
|------------------------|----------------------------------------------------------|
| 10,000,000             | -Xms6G -Xmx6G -XX:NewSize=512M -<br>XX:MaxNewSize=512M   |
| 20,000,000             | -Xms12G -Xmx12G -XX:NewSize=1G -<br>XX:MaxNewSize=1G     |
| 50,000,000             | -Xms32G -Xmx32G -XX:NewSize=3G -<br>XX:MaxNewSize=3G     |
| 100,000,000            | -Xms64G -Xmx64G -XX:NewSize=6G -<br>XX:MaxNewSize=6G     |
| 200,000,000            | -Xms96G -Xmx96G -XX:NewSize=9G -<br>XX:MaxNewSize=9G     |
| 300,000,000            | -Xms164G -Xmx164G -XX:NewSize=12G -<br>XX:MaxNewSize=12G |

- Configuration rules of the DataNode JVM parameter

Default value of the DataNode JVM parameter **GC\_OPTS**:

```
-Xms2G -Xmx4G -XX:NewSize=128M -XX:MaxNewSize=256M -
XX:MetaspaceSize=128M -XX:MaxMetaspaceSize=128M -XX:
+UseConcMarkSweepGC -XX:+CMSParallelRemarkEnabled -
XX:CMSInitiatingOccupancyFraction=65 -XX:+PrintGCDetails -
Dsun.rmi.dgc.client.gcInterval=0x7FFFFFFFFFFFFFFE -
Dsun.rmi.dgc.server.gcInterval=0x7FFFFFFFFFFFFFFE -XX:-
OmitStackTraceInFastThrow -XX:+PrintGCDateStamps -XX:
+UseGCLogFileRotation -XX:NumberOfGCLogFiles=10 -XX:GCLogFileSize=1M -
Djdk.tls.ephemeralDHKeySize=2048
```

The average number of blocks stored in each DataNode instance in the cluster is: Number of HDFS blocks x 3/Number of DataNodes. If the average number of blocks changes, you need to change **-Xms2G -Xmx4G -XX:NewSize=128M -XX:MaxNewSize=256M** in the default value. The following table lists the reference values.

**Table 7-10** DataNode JVM configuration

| Average Number of Blocks in a DataNode Instance | Reference Value                                    |
|-------------------------------------------------|----------------------------------------------------|
| 2,000,000                                       | -Xms6G -Xmx6G -XX:NewSize=512M -XX:MaxNewSize=512M |
| 5,000,000                                       | -Xms12G -Xmx12G -XX:NewSize=1G -XX:MaxNewSize=1G   |

**Xmx** specifies memory which corresponds to the threshold of the number of DataNode blocks, and each GB memory supports a maximum of 500,000 DataNode blocks. Set the memory as required.

## Viewing the HDFS Capacity Status

- NameNode information  
Log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > HDFS > NameNode(Active)**, and click **Overview** to view information like the number of file objects, files, directories, and blocks in HDFS in **Summary** area.
- DataNode information  
Log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > HDFS > NameNode(Active)**, and click **DataNodes** to view the number of blocks on all DataNodes that report alarms.
- Alarm information  
Check whether the alarms whose IDs are 14007, 14008, and 14009 are generated and change the alarm thresholds as required.

## 7.10 Configuring ulimit for HBase and HDFS

### Symptom

When you open an HDFS file, an error occurs due to the limit on the number of file handles. Information similar to the following is displayed.

```
IOException (Too many open files)
```

### Procedure

You can contact the MRS cluster administrator to add file handles for each user. This is a configuration on the OS instead of HBase or HDFS. It is recommended that the administrator configure the number of file handles based on the service traffic of HBase and HDFS and the rights of each user. If a user performs a large number of operations frequently on the HDFS that has large service traffic, set the number of file handles of this user to a large value.

**Step 1** Log in to the OSs of all nodes or clients in the cluster as user **root**, and go to the **/etc/security** directory.

**Step 2** Run the following command to edit the **limits.conf** file:

```
vi limits.conf
```

Add the following information to the file.

```
hdfs - nofile 32768  
hbase - nofile 32768
```

**hdfs** and **hbase** indicate the usernames of the OSs that are used during the services.

#### NOTE

- Only user **root** has the rights to edit the **limits.conf** file.
- If this modification does not take effect, check whether other nofile values exist in the **/etc/security/limits.d** directory. Such values may overwrite the values set in the **/etc/security/limits.conf** file.
- If a user needs to perform operations on HBase, set the number of file handles of this user to a value greater than **10000**. If a user needs to perform operations on HDFS, set the number of file handles of this user based on the service traffic. It is recommended that the value not be too small. If a user needs to perform operations on both HBase and HDFS, set the number of file handles of this user to a large value, such as **32768**.

**Step 3** Run the following command to check the limit on the number of file handles of a user:

```
su - user_name
```

```
ulimit -n
```

The limit on the number of file handles of this user is displayed as follows.

```
8194
```

```
----End
```


## 7.11 Balancing DataNode Capacity

### Scenario


In the HDFS cluster, unbalanced disk usage among DataNodes may occur, for example, when new DataNodes are added to the cluster. Unbalanced disk usage may result in multiple problems. For example, MapReduce applications cannot make full use of local computing advantages, network bandwidth usage between data nodes cannot be optimal, or node disks cannot be used. Therefore, the MRS cluster administrator needs to periodically check and maintain DataNode data balance.

HDFS provides a capacity balancing program Balancer. By running Balancer, you can balance the HDFS cluster and ensure that the difference between the disk usage of each DataNode and that of the HDFS cluster does not exceed the threshold. DataNode disk usage before and after balancing is shown in [Figure 7-1](#) and [Figure 7-2](#), respectively.

**Figure 7-1** DataNode disk usage before balancing



**Figure 7-2** DataNode disk usage after balancing



The time of the balancing operation is affected by the following two factors:

1. Total amount of data to be migrated:  
The data volume of each DataNode must be greater than  $(\text{Average usage} - \text{Threshold}) \times \text{Average data volume}$  and less than  $(\text{Average usage} + \text{Threshold}) \times \text{Average data volume}$ .

x Average data volume. If the actual data volume is less than the minimum value or greater than the maximum value, imbalance occurs. The system sets the largest deviation volume on all DataNodes as the total data volume to be migrated.

2. Balancer migration is performed in sequence in iteration mode. The amount of data to be migrated in each iteration does not exceed 10 GB, and the usage of each iteration is recalculated.

Therefore, for a cluster, you can estimate the time consumed by each iteration (by observing the time consumed by each iteration recorded in balancer logs) and divide the total data volume by 10 GB to estimate the task execution time.

The balancer can be started or stopped at any time.

## Impact on the System

- The balance operation occupies network bandwidth resources of DataNodes. Perform the operation during maintenance based on service requirements.
- The balance operation may affect the running services if the bandwidth traffic (the default bandwidth control is 20 MB/s) is reset or the data volume is increased.

## Prerequisites

The client has been installed.

## Procedure

- Step 1** Log in to the node where the client is installed as a client installation user. Run the following command to switch to the client installation directory, for example, `/opt/client`:

```
cd /opt/client
```

### NOTE

If the cluster is in normal mode, run the `su - omm` command to switch to user `omm`.

- Step 2** Run the following command to configure environment variables:

```
source bigdata_env
```

- Step 3** If the cluster is in security mode, run the following command to authenticate the HDFS identity:

```
kinit hdfs
```

- Step 4** Determine whether to adjust the bandwidth control.

- If yes, go to [Step 5](#).
- If no, go to [Step 6](#).

- Step 5** Run the following command to change the maximum bandwidth of Balancer, and then go to [Step 6](#).

```
hdfs dfsadmin -setBalancerBandwidth <bandwidth in bytes per second>
```

*<bandwidth in bytes per second>* indicates the bandwidth control value, in bytes. For example, to set the bandwidth control to 20 MB/s (the corresponding value is 20971520), run the following command:

```
hdfs dfsadmin -setBalancerBandwidth 20971520
```

 **NOTE**

- The default bandwidth control is 20 MB/s. This value is applicable to the scenario where the current cluster uses the 10GE network and services are being executed. If the service idle time window is insufficient for balance maintenance, you can increase the value of this parameter to shorten the balance time, for example, to 209715200 (200 MB/s).
- The value of this parameter depends on the networking. If the cluster load is high, you can change the value to 209715200 (200 MB/s). If the cluster is idle, you can change the value to 1073741824 (1 GB/s).
- If the bandwidth of the DataNodes cannot reach the specified maximum bandwidth, modify the HDFS parameter **dfs.datanode.balance.max.concurrent.moves** on FusionInsight Manager, and change the number of threads for balancing on each DataNode to **32** and restart the HDFS service.

**Step 6** Run the following command to start the balance task:

```
bash /opt/client/HDFS/hadoop/sbin/start-balancer.sh -threshold <threshold of balancer>
```

**-threshold** specifies the deviation value of the DataNode disk usage, which is used for determining whether the HDFS data is balanced. When the difference between the disk usage of each DataNode and the average disk usage of the entire HDFS cluster is less than this threshold, the system considers that the HDFS cluster has been balanced and ends the balance task.

For example, to set deviation rate to 5%, run the following command:

```
bash /opt/client/HDFS/hadoop/sbin/start-balancer.sh -threshold 5
```

 **NOTE**

- The preceding command executes the task in the background. You can query related logs in the **hadoop-root-balancer-host name.out log** file in the **/opt/client/HDFS/hadoop/logs** directory of the host.
- To stop the balance task, run the following command:  

```
bash /opt/client/HDFS/hadoop/sbin/stop-balancer.sh
```
- If only data on some nodes needs to be balanced, you can add the **-include** parameter in the script to specify the nodes to be migrated. You can run commands to view the usage of different parameters.
- **/opt/client** is the client installation directory. If the directory is inconsistent, replace it.
- If the command fails to be executed and the error information **Failed to APPEND\_FILE / system/balancer.id** is displayed in the log, run the following command to forcibly delete **/system/balancer.id** and run the **start-balancer.sh** script again:  

```
hdfs dfs -rm -f /system/balancer.id
```

**Step 7** If the following information is displayed, the balancing is complete and the system automatically exits the task:

```
Apr 01, 2016 01:01:01 PM Balancing took 23.3333 minutes
```

After you run the script in **Step 6**, the **hadoop-root-balancer-Host name.out log** file is generated in the client installation directory **/opt/client/HDFS/hadoop/logs**. You can view the following information in the log:

- Time Stamp
- Bytes Already Moved
- Bytes Left To Move
- Bytes Being Moved

----End

## Related Tasks

### Enable automatic execution of the balance task

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Name of the desired cluster > Services > HDFS > Configurations**, select **All Configurations**, search for the following parameters, and change the parameter values.

- **dfs.balancer.auto.enable** indicates whether to enable automatic balance task execution. The default value **false** indicates that automatic balance task execution is disabled. The value **true** indicates that automatic execution is enabled.
- **dfs.balancer.auto.cron.expression** indicates the task execution time. The default value **0 1 \* \* 6** indicates that the task is executed at 01:00 every Saturday. This parameter is valid only when the automatic execution is enabled.

**Table 7-11** describes the expression for modifying this parameter. \* indicates consecutive time segments.

**Table 7-11** Parameters in the execution expression

| Column | Description                                             |
|--------|---------------------------------------------------------|
| 1      | Minute. The value ranges from 0 to 59.                  |
| 2      | Hour. The value ranges from 0 to 23.                    |
| 3      | Date. The value ranges from 1 to 31.                    |
| 4      | Month. The value ranges from 1 to 12.                   |
| 5      | Week. The value ranges from 0 to 6. 0 indicates Sunday. |

- **dfs.balancer.auto.stop.cron.expression** indicates the task ending time. The default value is empty, indicating that the running balance task is not automatically stopped. For example, **0 5 \* \* 6** indicates that the balance task is stopped at 05:00 every Saturday. This parameter is valid only when the automatic execution is enabled.

**Table 7-11** describes the expression for modifying this parameter. \* indicates consecutive time segments.

**Step 3** Running parameters of the balance task that is automatically executed are shown in **Table 7-12**.

**Table 7-12** Running parameters of the automatic balancer

| Parameter                          | Parameter description                                                                                                                                                                                                                                                                                                                                                                               | Default Value                       |
|------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------|
| dfs.balancer.aut.threshold         | Specifies the balancing threshold of the disk capacity percentage. This parameter is valid only when <b>dfs.balancer.auto.enable</b> is set to <b>true</b> .                                                                                                                                                                                                                                        | 10                                  |
| dfs.balancer.aut.exclude.datanodes | Specifies the list of DataNodes on which automatic disk balancing is not required. This parameter is valid only when <b>dfs.balancer.auto.enable</b> is set to <b>true</b> .                                                                                                                                                                                                                        | The value is left blank by default. |
| dfs.balancer.aut.bandwidthPerSec   | Specifies the maximum bandwidth (MB/s) of each DataNode for load balancing.                                                                                                                                                                                                                                                                                                                         | 20                                  |
| dfs.balancer.aut.maxIdleIterations | Specifies the maximum number of consecutive idle iterations of Balancer. An idle iteration is an iteration without moving blocks. When the number of consecutive idle iterations reaches the maximum number, the balance task ends. The value <b>-1</b> indicates infinity.                                                                                                                         | 5                                   |
| dfs.balancer.aut.maxDataNodesNum   | Controls the number of DataNodes that perform automatic balance tasks. Assume that the value of this parameter is <i>N</i> . If <i>N</i> is greater than 0, data is balanced between <i>N</i> DataNodes with the highest percentage of remaining space and <i>N</i> DataNodes with the lowest percentage of remaining space. If <i>N</i> is 0, data is balanced among all DataNodes in the cluster. | 5                                   |

**Step 4** Click **Save** to make configurations take effect. You do not need to restart the HDFS service.

Go to the `/var/log/Bigdata/hdfs/nn/hadoop-omm-balancer-Host name.log` file to view the task execution logs saved in the active NameNode.

----End

## 7.12 Configuring Replica Replacement Policy for Heterogeneous Capacity Among DataNodes

### Scenario

By default, NameNode randomly selects a DataNode to write files. If the disk capacity of some DataNodes in a cluster is inconsistent (the total disk capacity of some nodes is large and of some nodes is small), the nodes with small disk capacity will be fully written. To resolve this problem, change the default disk selection policy for data written to DataNode to the available space block policy. This policy increases the probability of writing data blocks to the node with large available disk space. This ensures that the node usage is balanced when disk capacity of DataNodes is inconsistent.

### Impact on the System

The disk selection policy is changed to **org.apache.hadoop.hdfs.server.blockmanagement.AvailableSpaceBlockPlacementPolicy**. It is proven that the HDFS file write performance optimizes by 3% after the modification.

#### NOTE

**The default replica storage policy of the NameNode is as follows:**

1. First replica: stored on the node where the client resides.
2. Second replica: stored on DataNodes of the remote rack.
3. Third replica: stored on different nodes of the same rack for the node where the client resides.

If there are more replicas, randomly store them on other DataNodes.

The replica selection mechanism (**org.apache.hadoop.hdfs.server.blockmanagement.AvailableSpaceBlockPlacementPolicy**) is as follows:

1. First replica: stored on the DataNode where the client resides (the same as the default storage policy).
2. Second replica:
  - When selecting a storage node, select two data nodes that meet the requirements.
  - Compare the disk usages of the two DataNodes. If the difference is smaller than 5%, store the replicas to the first node.
  - If the difference exceeds 5%, there is a 60% probability (specified by **dfs.namenode.available-space-block-placement-policy.balanced-space-preference-fraction** and default value is **0.6**) that the replica is written to the node whose disk space usage is low.
3. As for the storage of the third replica and subsequent replicas, refer to that of the second replica.

### Prerequisites

The total disk capacity deviation of DataNodes in the cluster cannot exceed 100%.

## Procedure

- Step 1** Go to the **All Configurations** page of HDFS by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** Modify the disk selection policy parameters when HDFS writes data. Search for the **dfs.block.replicator.classname** parameter and change its value to **org.apache.hadoop.hdfs.server.blockmanagement.AvailableSpaceBlockPlacementPolicy**.
- Step 3** Save the modified configuration. Restart the expired service or instance for the configuration to take effect.

----End

## 7.13 Configuring the Number of Files in a Single HDFS Directory

### Scenario

Generally, multiple services are deployed in a cluster, and the storage of most services depends on the HDFS file system. Different components such as Spark and Yarn or clients are constantly writing files to the same HDFS directory when the cluster is running. However, the number of files in a single directory in HDFS is limited. Users must plan to prevent excessive files in a single directory and task failure.

You can set the number of files in a single directory using the **dfs.namenode.fs-limits.max-directory-items** parameter in HDFS.

### Procedure

- Step 1** Go to the **All Configurations** page of HDFS by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** Search for the configuration item **dfs.namenode.fs-limits.max-directory-items**.

**Table 7-13** Parameter description

| Parameter                                  | Description                                                           | Default Value |
|--------------------------------------------|-----------------------------------------------------------------------|---------------|
| dfs.namenode.fs-limits.max-directory-items | Maximum number of items in a directory<br>Value range: 1 to 6,400,000 | 1048576       |

- Step 3** Set the maximum number of files that can be stored in a single HDFS directory. Save the modified configuration. Restart the expired service or instance for the configuration to take effect.

 NOTE

Plan data storage in advance based on time and service type categories to prevent excessive files in a single directory. You are advised to use the default value, which is about 1 million pieces of data in a single directory.

----End

## 7.14 Configuring the Recycle Bin Mechanism

### Scenario

On HDFS, deleted files are moved to the recycle bin (trash can) so that the data deleted by mistake can be restored.

You can set the time threshold for storing files in the recycle bin. Once the file storage duration exceeds the threshold, it is permanently deleted from the recycle bin. If the recycle bin is cleared, all files in the recycle bin are permanently deleted.

### Configuration Description

If a file is deleted from HDFS, the file is saved in the trash space rather than cleared immediately. After the aging time is due, the deleted file becomes an aging file and will be cleared based on the system mechanism or manually cleared by users.

#### Parameter portal:

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-14** Parameter description

| Parameter         | Description                                                                                                                             | Default Value |
|-------------------|-----------------------------------------------------------------------------------------------------------------------------------------|---------------|
| fs.trash.interval | Trash collection time, in minutes. If data in the trash station exceeds the time, the data will be deleted. Value range: 1440 to 259200 | 2880          |

| Parameter                    | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      | Default Value |
|------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| fs.trash.checkpoint.interval | <p>Interval between trash checkpoints, in minutes. The value must be less than or equal to the value of <b>fs.trash.interval</b>. The checkpoint program creates a checkpoint every time it runs and removes the checkpoint created <b>fs.trash.interval</b> minutes ago. For example, the system checks whether aging files exist every 10 minutes and deletes aging files if any. Files that are not aging are stored in the checkpoint list waiting for the next check.</p> <p>If this parameter is set to 0, the system does not check aging files and all aging files are saved in the system.</p> <p>Value range: 0 to <i>fs.trash.interval</i></p> <p><b>NOTE</b><br/>It is not recommended to set this parameter to 0 because aging files will use up the disk space of the cluster.</p> | 60            |

## 7.15 Setting Permissions on Files and Directories

### Scenario

HDFS allows users to modify the default permissions of files and directories. The default mask provided by the HDFS for creating file and directory permissions is **022**. If you have special requirements for the default permissions, you can set configuration items to change the default permissions.

### Configuration Description

#### Parameter portal:

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-15** Parameter description

| Parameter                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  | Default Value |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| fs.permissions.umask-mode | <p>This <b>umask</b> value (user mask) is used when the user creates files and directories in the HDFS on the clients. This parameter is similar to the file permission mask on Linux.</p> <p>The parameter value can be in octal or in symbolic, for example, <b>022</b> (octal, the same as <b>u=rwx,g=r-x,o=r-x</b> in symbolic), or <b>u=rwx,g=rwx,o=</b> (symbolic, the same as <b>007</b> in octal).</p> <p><b>NOTE</b><br/>The octal mask is opposite to the actual permission value. You are advised to use the symbol notation to make the description clearer.</p> | 022           |

## 7.16 Setting the Maximum Lifetime and Renewal Interval of a Token

### Scenario

In security mode, users can flexibly set the maximum token lifetime and token renewal interval in HDFS based on cluster requirements.

### Configuration Description

#### Navigation path for setting parameters:

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-16** Parameter description

| Parameter                                    | Description                                                                                                                                             | Default Value |
|----------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| dfs.namenode.delegation.token.max-lifetime   | This parameter is a server parameter. It specifies the maximum lifetime of a token. Unit: milliseconds. Value range: 10,000 to 10,000,000,000,000       | 604,800,000   |
| dfs.namenode.delegation.token.renew-interval | This parameter is a server parameter. It specifies the maximum lifetime to renew a token. Unit: milliseconds. Value range: 10,000 to 10,000,000,000,000 | 86,400,000    |

## 7.17 Configuring the Damaged Disk Volume

### Scenario

In the open source version, if multiple data storage volumes are configured for a DataNode, the DataNode stops providing services by default if one of the volumes is damaged. You can change the value of **dfs.datanode.failed.volumes.tolerated** to specify the number of damaged disk volumes that are allowed. If the number of damaged volumes does not exceed the threshold, DataNode continues to provide services.

### Configuration Description

**Navigation path for setting parameters:**

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-17** Parameter description

| Parameter                             | Description                                                                                                                                                                                                                                                                                                                                            | Default Value |
|---------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| dfs.datanode.failed.volumes.tolerated | Specifies the number of damaged volumes that are allowed before the DataNode stops providing services. By default, there must be at least one valid volume. The value <b>-1</b> indicates that the minimum value of a valid volume is <b>1</b> . The value greater than or equal to <b>0</b> indicates the number of damaged volumes that are allowed. | -1            |

## 7.18 Configuring Encrypted Channels

### Scenario

Encrypted channel is an encryption protocol of remote procedure call (RPC) in HDFS. When a user invokes RPC, the user's login name will be transmitted to RPC through RPC head. Then RPC uses Simple Authentication and Security Layer (SASL) to determine an authorization protocol (Kerberos and DIGEST-MD5) to complete RPC authorization. When users deploy security clusters, they need to use encrypted channels and configure the following parameters. For details about the secure Hadoop RPC, visit [https://hadoop.apache.org/docs/r3.1.1/hadoop-project-dist/hadoop-common/SecureMode.html#Data\\_Encryption\\_on\\_RPC](https://hadoop.apache.org/docs/r3.1.1/hadoop-project-dist/hadoop-common/SecureMode.html#Data_Encryption_on_RPC).

### Configuration Description

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-18** Parameter description

| Parameter             | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               | Default Value                                                                                                 |
|-----------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------|
| hadoop.rpc.protection | <p><b>NOTICE</b></p> <ul style="list-style-type: none"> <li>The setting takes effect only after the service is restarted. Rolling restart is not supported.</li> <li>After the setting, you need to download the client configuration again. Otherwise, the HDFS cannot provide the read and write services.</li> </ul> <p>Whether the RPC channels of each module in Hadoop are encrypted. The channels include:</p> <ul style="list-style-type: none"> <li>RPC channels for clients to access HDFS</li> <li>RPC channels between modules in HDFS, for example, RPC channels between DataNode and NameNode</li> <li>RPC channels for clients to access Yarn</li> <li>RPC channels between NodeManager and ResourceManager</li> <li>RPC channels for Spark to access Yarn and HDFS</li> <li>RPC channels for MapReduce to access Yarn and HDFS</li> <li>RPC channels for HBase to access HDFS</li> </ul> <p><b>NOTE</b></p> <p>You can set this parameter on the HDFS component configuration page. The parameter setting takes effect globally, that is, the setting of whether the RPC channel is encrypted takes effect on all modules in Hadoop.</p> <p>There are three encryption modes.</p> <ul style="list-style-type: none"> <li><b>authentication:</b> This is the default value in normal mode. In this mode, data is directly transmitted without encryption after being authenticated. This mode ensures performance but has security risks.</li> <li><b>integrity:</b> Data is transmitted without encryption or authentication. To ensure data security, exercise caution when using this mode.</li> <li><b>privacy:</b> This is the default value in security mode, indicating that data is transmitted after authentication and encryption. This mode reduces the performance.</li> </ul> | <ul style="list-style-type: none"> <li>Security mode: privacy</li> <li>Normal mode: authentication</li> </ul> |

## 7.19 Reducing the Probability of Abnormal Client Application Operation When the Network Is Not Stable

### Scenario

Clients probably encounter running errors when the network is not stable. Users can adjust the following parameter values to improve the running efficiency.

### Configuration Description

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-19** Parameter description

| Parameter                                  | Description                                                                                                                                                                                                                                                  | Default Value |
|--------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| ha.health-monitor.rpc-timeout.ms           | Timeout interval during the NameNode health check performed by ZKFC. Increasing this value can prevent dual active NameNodes and reduce the probability of application running exceptions on clients.<br>Unit: millisecond. Value range: 30,000 to 3,600,000 | 180,000       |
| ipc.client.connect.max.retries.on.timeouts | Number of retry times when the socket connection between a server and a client times out.<br>Value range: 1 to 256                                                                                                                                           | 45            |
| ipc.client.connect.timeout                 | Timeout interval of the socket connection between a client and a server. Increasing the value of this parameter increases the timeout interval for setting up a connection.<br>Unit: millisecond. Value range: 1 to 3,600,000                                | 20,000        |

## 7.20 Configuring the NameNode Blacklist

### Scenario

In the existing default DFSclient failover proxy provider, if a NameNode in a process is faulty, all HDFS client instances in the same process attempt to connect to the NameNode again. As a result, the application waits for a long time and timeout occurs.

When clients in the same JVM process connect to the NameNode that cannot be accessed, the system is overloaded. The NameNode blacklist is equipped with the MRS cluster to avoid this problem.

In the new Blacklisting DFSClient failover provider, the faulty NameNode is recorded in a list. The DFSClient then uses the information to prevent the client from connecting to such NameNodes again. This function is called NameNode blacklisting.

For example, there is a cluster with the following configurations:

```
namenode: nn1, nn2
```

```
dfs.client.failover.connection.retries: 20
```

```
Processes in a single JVM: 10 clients
```


In the preceding cluster, if the active **nn1** cannot be accessed, client1 will retry the connection for 20 times. Then, a failover occurs, and client1 will connect to **nn2**. In the same way, other clients also connect to **nn2** when the failover occurs after retrying the connection to **nn1** for 20 times. Such process prolongs the fault recovery of NameNode.

In this case, the NameNode blacklisting adds **nn1** to the blacklist when client1 attempts to connect to the active **nn1** which is already faulty. Therefore, other clients will avoid trying to connect to **nn1** but choose **nn2** directly.

#### NOTE

If, at any time, all NameNodes are added to the blacklist, the content in the blacklist will be cleared, and the client attempts to connect to the NameNodes based on the initial NameNode list. If any fault occurs again, the NameNode is still added to the blacklist.

**Figure 7-3** NameNode blacklisting working principle



### Configuration Description

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-20** NameNode blacklisting parameters

| Parameter                                               | Description                                                                                                                                                                                                                                                                                | Default Value                                                           |
|---------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------|
| dfs.client.failover.proxy.provider.<br>[nameservice ID] | Client Failover proxy provider class which creates the NameNode proxy using the authenticated protocol.<br>Set this parameter to <b>org.apache.hadoop.hdfs.server.namenode.ha.BlackListingFailoverProxyProvider</b> .<br>You can configure the observer NameNode to process read requests. | org.apache.hadoop.hdfs.server.namenode.ha.AdaptiveFailoverProxyProvider |


## 7.21 Optimizing HDFS NameNode RPC QoS

### Scenarios

Several finished Hadoop clusters are faulty because the NameNode is overloaded and unresponsive.


Such problem is caused by the initial design of Hadoop: In Hadoop, the NameNode functions as an independent part and in its namespace coordinates various HDFS operations, including obtaining the data block location, listing directories, and creating files. The NameNode receives HDFS operations, regards them as RPC calls, and places them in the FIFO call queue for read threads to process. Requests in FIFO call queue are served first-in first-out. However, users who perform more I/O operations are served more time than those performing fewer I/O operations. In this case, the FIFO is unfair and causes the delay.

**Figure 7-4** NameNode request processing based on the FIFO call queue



The unfair problem and delaying mentioned before can be improved by replacing the FIFO queue with a new type of queue called FairCallQueue. In this way, FAIR queues assign incoming RPC calls to multiple queues based on the scale of the caller's call. The scheduling module tracks the latest calls and assigns a higher priority to users with a smaller number of calls.

**Figure 7-5** NameNode request processing based on FAIRCallQueue



### Configuration Description

- FairCallQueue ensures quality of service (QoS) by internally adjusting the order in which RPCs are invoked.

This queue consists of the following parts:

- a. DecayRpcScheduler: used to provide priority values from 0 to N (the value 0 indicates the highest priority).
- b. Multi-level queues (located in the FairCallQueue): used to ensure that queues are invoked in order of priority.
- c. Multi-channel converters (provided with Weighted Round Robin Multiplexer): used to provide logic control for queue selection.

After the FairCallQueue is configured, the control module determines the sub-queue to which the received invoking is allocated. The current scheduling module is DecayRpcScheduler, which only continuously tracks the priority numbers of various calls and periodically reduces these numbers.

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-21** FairCallQueue parameters

| Parameter                 | Description                                                                                                                                 | Default Value                            |
|---------------------------|---------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------|
| ipc.<port>.callqueue.impl | Specifies the queue implementation class. You need to run the <b>org.apache.hadoop.ipc.FairCallQueue</b> command to enable the QoS feature. | java.util.concurrent.LinkedBlockingQueue |

- RPC BackOff

Backoff is one of the FairCallQueue functions. It requires the client to retry operations (such as creating, deleting, and opening a file) after a period of time. When the backoff occurs, the RCP server throws RetriableException. The FairCallQueue performs backoff in either of the following cases:

- The queue is full, that is, there are many client calls in the queue.
- The queue response time is longer than the threshold time (specified by the **ipc.<port>.decay-scheduler.backoff.responsetime.thresholds** parameter).

**Table 7-22** RPC Backoff configuration

| Parameter                                                                      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               | Default Value           |
|--------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------|
| <code>ipc.&lt;port&gt;.backoff.enable</code>                                   | Specifies whether to enable the backoff. When the current application contains a large number of user callings, the RPC request is blocked if the connection limit of the operating system is not reached. Alternatively, when the RPC or NameNode is heavily loaded, some explicit exceptions can be thrown back to the client based on certain policies. The client can understand these exceptions and perform exponential rollback, which is another implementation of the <code>RetryInvocationHandler</code> class. | false                   |
| <code>ipc.&lt;port&gt;.decay-scheduler.backoff.response-time.enable</code>     | Indicate whether to enable the backoff based on the average queue response time.                                                                                                                                                                                                                                                                                                                                                                                                                                          | false                   |
| <code>ipc.&lt;port&gt;.decay-scheduler.backoff.response-time.thresholds</code> | Configure the response time threshold for each queue. The response time threshold must match the number of priorities (the value of <code>ipc.&lt;port&gt;.faircallqueue.priority-levels</code> ). Unit: millisecond                                                                                                                                                                                                                                                                                                      | 10000,20000,30000,40000 |

 **NOTE**

- `<port>` indicates the RPC port configured on the NameNode.
- The backoff function based on the response time takes effect only when `ipc.<port>.backoff.enable` is set to **true**.

## 7.22 Optimizing HDFS DataNode RPC QoS

### Scenario

When the speed at which the client writes data to the HDFS is greater than the disk bandwidth of the DataNode, the disk bandwidth is fully occupied. As a result, the DataNode does not respond. The client can back off only by canceling or restoring the channel, which results in write failures and unnecessary channel recovery operations.

### Configuration

The new configuration parameter **dfs.pipeline.ecn** is introduced. When this configuration is enabled, the DataNode sends a signal from the write channel when the write channel is overloaded. The client may perform backoff based on the blocking signal to prevent the system from being overloaded. This configuration parameter is introduced to make the channel more stable and reduce unnecessary cancellation or recovery operations. After receiving the signal, the client backs off for a period of time (5,000 ms), and then adjusts the backoff time based on the related filter (the maximum backoff time is 50,000 ms).

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-23** DN ECN configuration

| Parameter        | Description                                                                      | Default Value |
|------------------|----------------------------------------------------------------------------------|---------------|
| dfs.pipeline.ecn | After configuration, the DataNode can send blocking notifications to the client. | false         |

## 7.23 Configuring Reserved Percentage of Disk Usage on DataNodes

### Scenario

When the Yarn local directory and DataNode directory are on the same disk, the disk with larger capacity can run more tasks. Therefore, more intermediate data is stored in the Yarn local directory.

Currently, you can set **dfs.datanode.du.reserved** to configure the absolute value of the reserved disk space on DataNodes. A small value cannot meet the requirements of a disk with large capacity. However, configuring a large value for a disk with same capacity wastes a lot of disk space.

To avoid this problem, a new parameter **dfs.datanode.du.reserved.percentage** is introduced to configure the reserved percentage of the disk space.

 NOTE

- If `dfs.datanode.du.reserved.percentage` and `dfs.datanode.du.reserved` are configured at the same time, the larger value of the reserved disk space calculated using the two parameters is used as the reserved space of the data nodes.
- You are advised to set `dfs.datanode.du.reserved` or `dfs.datanode.du.reserved.percentage` based on the actual disk space.

## Configuration Description

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-24** Parameter description

| Parameter                                        | Description                                                                                                                                                                                            | Default Value |
|--------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| <code>dfs.datanode.du.reserved.percentage</code> | Indicates the percentage of the reserved disk space on DataNodes. The DataNode permanently reserves the disk space calculated using this percentage.<br>The value is an integer ranging from 0 to 100. | 10            |

## 7.24 Configuring HDFS NodeLabel

### Scenario

You need to configure the nodes for storing HDFS file data blocks based on data features. You can configure a label expression to an HDFS directory or file and assign one or more labels to a DataNode so that file data blocks can be stored on specified DataNodes.

If the label-based data block placement policy is used for selecting DataNodes to store the specified files, the DataNode range is specified based on the label expression. Then proper nodes are selected from the specified range.

- Scenario 1: DataNodes partitioning scenario

Scenario description:

When different application data is required to run on different nodes for separate management, label expressions can be used to achieve separation of different services, storing specified services on corresponding nodes.

By configuring the NodeLabel feature, you can perform the following operations:

- Store data in `/HBase` to DN1, DN2, DN3, and DN4.
- Store data in `/Spark` to DN5, DN6, DN7, and DN8.

Figure 7-6 DataNode partitioning scenario



NOTE

- Run the `hdfs nodelabel -setLabelExpression -expression 'LabelA[fallback=NONE]' -path /Hbase` command to set an expression for the **Hbase** directory. As shown in [Figure 7-6](#), the data block replicas of files in the **/Hbase** directory are placed on the nodes labeled with the **LabelA**, that is, DN1, DN2, DN3, and DN4. Similarly, run the `hdfs nodelabel -setLabelExpression -expression 'LabelB[fallback=NONE]' -path /Spark` command to set an expression for the **Spark** directory. Data block replicas of files in the **/Spark** directory can be placed only on nodes labeled with **LabelB**, that is, DN5, DN6, DN7, and DN8.
- For details about how to set labels for a data node, see [Configuration Description](#).
- If multiple racks are available in one cluster, it is recommended that DataNodes of these racks should be available under each label, to ensure reliability of data block placement.


• Scenario 2: Specifying replica location when there are multiple racks

Scenario description:

In a heterogeneous cluster, customers need to allocate certain nodes with high availability to store important commercial data. Label expressions can be used to specify replica location so that the replica can be placed on a high reliable node.

Data blocks in the **/data** directory have three replicas by default. In this case, at least one replica is stored on a node of RACK1 or RACK2 (nodes of RACK1 and RACK2 are high reliable), and the other two are stored separately on the nodes of RACK3 and RACK4.

Figure 7-7 Scenario example



**NOTE**

Run the `hdfs nodelabel -setLabelExpression -expression 'LabelA|| LabelB[fallback=NONE],LabelC,LabelD' -path /data` command to set an expression for the `/data` directory.

When data is to be written to the `/data` directory, at least one data block replica is stored on a node labeled with the LabelA or LabelB, and the other two data block replicas are stored separately on the nodes labeled with the LabelC and LabelD.

### Configuration Description

- DataNode label configuration

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

Table 7-25 Parameter description

| Parameter                      | Description                                                                                                                                                                                     | Default Value                                                                    |
|--------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------|
| dfs.block.replicator.classname | Used to configure the DataNode policy of HDFS. To enable the NodeLabel function, set this parameter to <b>org.apache.hadoop.hdfs.server.blockmanagement.BlockPlacementPolicyWithNodeLabel</b> . | org.apache.hadoop.hdfs.server.blockmanagement.AvailableSpaceBlockPlacementPolicy |

| Parameter | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     | Default Value |
|-----------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| host2tags | Used to configure a mapping between a DataNode host and a label.<br><br>The host name can be configured with an IP address extension expression (for example, <b>192.168.1.[1-128]</b> or <b>192.168.[2-3].[1-128]</b> ) or a regular expression (for example, <b>/datanode-[123]/</b> or <b>/datanode-\d{2}/</b> ) starting and ending with a slash (/). The label configuration name cannot contain the following characters: = / \ <b>Note:</b> The IP address must be a service IP address. | -             |

 NOTE

- The **host2tags** configuration item is described as follows:  
Assume there are 20 DataNodes which range from dn-1 to dn-20 in a cluster and the IP addresses of clusters range from 10.1.120.1 to 10.1.120.20. The value of **host2tags** can be represented in either of the following methods:  
**Regular expression of the host name**  
**/dn-\d/ = label-1** indicates that the labels corresponding to dn-1 to dn-9 are label-1, that is, dn-1 = label-1, dn-2 = label-1, ..., dn-9 = label-1.  
**/dn-((1[0-9]\$)|(20\$))/ = label-2** indicates that the labels corresponding to dn-10 to dn-20 are label-2, that is, dn-10 = label-2, dn-11 = label-2, ...dn-20 = label-2.  
**IP address range expression**  
**10.1.120.[1-9] = label-1** indicates that the labels corresponding to 10.1.120.1 to 10.1.120.9 are label-1, that is, 10.1.120.1 = label-1, 10.1.120.2 = label-1, ..., and 10.1.120.9 = label-1.  
**10.1.120.[10-20] = label-2** indicates that the labels corresponding to 10.1.120.10 to 10.1.120.20 are label-2, that is, 10.1.120.10 = label-2, 10.1.120.11 = label-2, ..., and 10.1.120.20 = label-2.
- Label-based data block placement policies are applicable to capacity expansion and reduction scenarios.  
A newly added DataNode will be assigned a label if the IP address of the DataNode is within the IP address range in the **host2tags** configuration item or the host name of the DataNode matches the host name regular expression in the **host2tags** configuration item.  
For example, the value of **host2tags** is **10.1.120.[1-9] = label-1**, but the current cluster has only three DataNodes: 10.1.120.1 to 10.1.120.3. If DataNode 10.1.120.4 is added for capacity expansion, the DataNode is labeled as label-1. If the 10.1.120.3 DataNode is deleted or out of the service, no data block will be allocated to the node.
- Set label expressions for directories or files.
  - On the HDFS parameter configuration page, configure **path2expression** to configure the mapping between HDFS directories and labels. If the configured HDFS directory does not exist, the configuration can succeed. When a directory with the same name as the HDFS directory is created manually, the configured label mapping relationship will be inherited by the directory within 30 minutes. After a labeled directory is deleted, a

- new directory with the same name as the deleted one will inherit its mapping within 30 minutes.
- For details about configuring items using commands, see the **hdfs nodelabel -setLabelExpression** command.
- To set label expressions using the Java API, invoke the **setLabelExpression(String src, String labelExpression)** method using the instantiated object `NodeLabelFileSystem`. *src* indicates a directory or file path on HDFS, and **labelExpression** indicates the label expression.
- After the NodeLabel is enabled, you can run the **hdfs nodelabel -listNodeLabels** command to view the label information of each DataNode.

## Block Replica Location Selection

Nodelabel supports different placement policies for replicas. The expression **label-1,label-2,label-3** indicates that three replicas are respectively placed in DataNodes containing label-1, label-2, and label-3. Different replica policies are separated by commas (,).

If you want to place two replicas in DataNode with label-1, set the expression as follows: **label-1 [replica=2],label-2,label-3**. In this case, if the default number of replicas is 3, two nodes with label-1 and one node with label-2 are selected. If the default number of replicas is 4, two nodes with label-1, one node with label-2, and one node with label-3 are selected. Note that the number of replicas is the same as that of each replica policy from left to right. However, the number of replicas sometimes exceeds the expressions. If the default number of replicas is 5, the extra replica is placed on the last node, that is, the node labeled with label-3.

When the ACLs function is enabled and the user does not have the permission to access the labels used in the expression, the DataNode with the label is not selected for the replica.

## Deletion of Redundant Block Replicas

If the number of block replicas exceeds the value of **dfs.replication** (number of file replicas specified by the user), HDFS will delete redundant block replicas to ensure cluster resource usage.

The deletion rules are as follows:

- Preferentially delete replicas that do not meet any expression.

For example: The default number of file replicas is **3**.

The label expression of **/test** is **LA[replica=1],LB[replica=1],LC[replica=1]**.

The file replicas of **/test** are distributed on four nodes (D1 to D4), corresponding to labels (LA to LD).

```
D1:LA  
D2:LB  
D3:LC  
D4:LD
```

Then, block replicas on node D4 will be deleted.

- If all replicas meet the expressions, delete the redundant replicas which are beyond the number specified by the expression.

For example: The default number of file replicas is **3**.

The label expression of **/test** is **LA[replica=1],LB[replica=1],LC[replica=1]**.

The file replicas of **/test** are distributed on the following four nodes, corresponding to the following labels.

```
D1:LA
D2:LA
D3:LB
D4:LC
```

Then, block replicas on node D1 or D2 will be deleted.

- If a file owner or group of a file owner cannot access a label, preferentially delete the replica from the DataNode mapped to the label.

## Example of label-based block placement policy

Assume that there are six DataNodes, namely, dn-1, dn-2, dn-3, dn-4, dn-5, and dn-6 in a cluster and the corresponding IP address range is 10.1.120.[1-6]. Six directories must be configured with label expressions. The default number of block replicas is **3**.

- The following provides three expressions of the DataNode label in **host2labels** file. The three expressions have the same function.
  - Regular expression of the host name

```
/dn-[1456]/ = label-1,label-2
/dn-[26]/ = label-1,label-3
/dn-[3456]/ = label-1,label-4
/dn-5/ = label-5
```
  - IP address range expression

```
10.1.120.[1-6] = label-1
10.1.120.1 = label-2
10.1.120.2 = label-3
10.1.120.[3-6] = label-4
10.1.120.[4-6] = label-2
10.1.120.5 = label-5
10.1.120.6 = label-3
```
  - Common host name expression

```
/dn-1/ = label-1, label-2
/dn-2/ = label-1, label-3
/dn-3/ = label-1, label-4
/dn-4/ = label-1, label-2, label-4
/dn-5/ = label-1, label-2, label-4, label-5
/dn-6/ = label-1, label-2, label-3, label-4
```
- The label expressions of the directories are set as follows:

```
/dir1 = label-1
/dir2 = label-1 && label-3
/dir3 = label-2 || label-4[replica=2]
/dir4 = (label-2 || label-3) && label-4
/dir5 = !label-1
/sdir2.txt = label-1 && label-3[replica=3,fallback=NONE]
/dir6 = label-4[replica=2],label-2
```

### NOTE

For details about the label expression configuration, see the **hdfs nodelabel - setLabelExpression** command.

The file data block storage locations are as follows:

- Data blocks of files in the **/dir1** directory can be stored on any of the following nodes: dn-1, dn-2, dn-3, dn-4, dn-5, and dn-6.
- Data blocks of files in the **/dir2** directory can be stored on the dn-2 and dn-6 nodes. The default number of block replicas is **3**. The expression

matches only two DataNodes. The third replica will be stored on one of the remaining nodes in the cluster.

- Data blocks of files in the **/dir3** directory can be stored on any three of the following nodes: dn-1, dn-3, dn-4, dn-5, and dn-6.
- Data blocks of files in the **/dir4** directory can be stored on the dn-4, dn-5, and dn-6 nodes.
- Data blocks of files in the **/dir5** directory do not match any DataNode and will be stored on any three nodes in the cluster, which is the same as the default block selection policy.
- For the data blocks of the **/sdir2.txt** file, two replicas are stored on the dn-2 and dn-6 nodes. The left one is not stored in the node because **fallback=NONE** is enabled.
- Data blocks of the files in the **/dir6** directory are stored on the two nodes with label-4 selected from dn-3, dn-4, dn-5, and dn-6 and another node with label-2. If the specified number of file replicas in the **/dir6** directory is more than 3, the extra replicas will be stored on a node with label-2.

## Restrictions

In configuration files, **key** and **value** are separated by equation signs (=), colons (:), and whitespace. Therefore, the host name of the **key** cannot contain these characters because these characters may be considered as separators.

## 7.25 Configuring HDFS DiskBalancer

### Scenario

DiskBalancer is an online disk balancer that balances disk data on running DataNodes based on various indicators. It works in the similar way of the HDFS Balancer. The difference is that HDFS Balancer balances data between DataNodes, while HDFS DiskBalancer balances data among disks on a single DataNode.

Data among disks may be unevenly distributed if a large number of files have been deleted from a cluster running for a long time, or disk capacity expansion is performed on a node in the cluster. Uneven data distribution may deteriorate the concurrent read/write performance of the HDFS, or cause service failure due to inappropriate HDFS write policies. In this case, the data density among disks on a node needs to be balanced to prevent heterogeneous small disks from becoming the performance bottleneck of the node.

### Configuration Description

Go to the **All Configurations** page of HDFS and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 7-26** Parameter description

| Parameter                                       | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    | Default Value |
|-------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| dfs.disk.balancer.auto.enabled                  | Indicates whether to enable the HDFS DiskBalancer function. The default value is <b>false</b> , indicating that this function is disabled.                                                                                                                                                                                                                                                                                                                                                     | false         |
| dfs.disk.balancer.auto.cron.expression          | CRON expression of the HDFS disk balancing operation, which is used to control the start time of the balancing operation. This parameter is valid only when <b>dfs.disk.balancer.auto.enabled</b> is set to <b>true</b> . The default value is <b>0 1 * * 6</b> , indicating that tasks are executed at 01:00 every Saturday. For details about cron expression, see <a href="#">Table 7-27</a> . The default value indicates that the DiskBalancer check is executed at 01:00 every Saturday. | 0 1 * * 6     |
| dfs.disk.balancer.max.disk.throughputInMBperSec | Specifies the maximum disk bandwidth that can be used for disk data balancing. The unit is MB/s, and the default value is <b>10</b> . Set this parameter based on the actual disk conditions of the cluster.                                                                                                                                                                                                                                                                                   | 10            |
| dfs.disk.balancer.max.disk.errors               | Specifies the maximum number of errors that are allowed in a specified movement process. If the value exceeds this threshold, the movement fails.                                                                                                                                                                                                                                                                                                                                              | 5             |
| dfs.disk.balancer.block.tolerance.percent       | Specifies the difference threshold between the data storage capacity and perfect status of each disk during data balancing among disks. For example, the ideal data storage capacity of each disk is 1 TB, and this parameter is set to <b>10</b> . When the data storage capacity of the target disk reaches 900 GB, the storage status of the disk is considered as perfect. Value range: 1 to 100.                                                                                          | 10            |
| dfs.disk.balancer.plan.threshold.percent        | Specifies the data density difference that is allowed between two disks during disk data balancing. If the absolute value of the data density difference between any two disks exceeds the threshold, data balancing is required. Value range: 1 to 100.                                                                                                                                                                                                                                       | 10            |
| dfs.disk.balancer.top.nodes.number              | Specifies the top <i>N</i> nodes whose disk data needs to be balanced in the cluster.                                                                                                                                                                                                                                                                                                                                                                                                          | 5             |

To use this function, set **dfs.disk.balancer.auto.enabled** to **true** and configure a proper CRON expression. Set other parameters based on the cluster status.

**Table 7-27** CRON expressions

| Column | Description                                                    |
|--------|----------------------------------------------------------------|
| 1      | Minute. The value ranges from 0 to 59.                         |
| 2      | Hour. The value ranges from 0 to 23.                           |
| 3      | Date. The value ranges from 1 to 31.                           |
| 4      | Month. The value ranges from 1 to 12.                          |
| 5      | Week. The value ranges from 0 to 6. <b>0</b> indicates Sunday. |

## Use Restrictions

1. Data can only be moved between disks of the same type. For example, data can only be moved between SSDs or between DISKS.
2. Enabling this function occupies disk I/O resources and network bandwidth resources of involved nodes. Enable this function in off-peak hours.
3. The DataNodes specified by the **dfs.disk.balancer.top.nodes.number** parameter is frequently calculated. Therefore, set the parameter to a small value.
4. Commands for using the DiskBalancer function on the HDFS client are as follows:

**Table 7-28** DiskBalancer commands

| Syntax                                                                          | Description                                                                                                                                                                                                                                                        |
|---------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>hdfs diskbalancer -report -top &lt;N&gt;</code>                           | Set <i>N</i> to an integer greater than 0. This command can be used to query the top <i>N</i> nodes that require disk data balancing in the cluster.                                                                                                               |
| <code>hdfs diskbalancer -plan &lt;Hostname  IP Address&gt;</code>               | This command can be used to generate a JSON file based on the DataNode. The file contains information about the source disk, target disk, and blocks to be moved. In addition, this command can be used to specify other parameters such as the network bandwidth. |
| <code>hdfs diskbalancer -query &lt;Hostname: \$dfs.datanode.ipc.port&gt;</code> | The default port number of the cluster is 9867. This command is used to query the running status of the DiskBalancer task on the current node.                                                                                                                     |

| Syntax                                                   | Description                                                                                                      |
|----------------------------------------------------------|------------------------------------------------------------------------------------------------------------------|
| <code>hdfs diskbalancer -execute &lt;planfile&gt;</code> | In this command, <b>planfile</b> indicates the JSON file generated in the second command. Use the absolute path. |
| <code>hdfs diskbalancer -cancel &lt;planfile&gt;</code>  | This command is used to cancel the running planfile. Use the absolute path.                                      |

 **NOTE**

- Users running this command on the client must have the **supergroup** permission. You can use the system user **hdfs** of the HDFS service. Alternatively, you can create a user with the **supergroup** permission in the cluster and then run the command.
- Only formats and usage of commands are provided in [Table 7-28](#). For more parameters to be configured for each command, run the **hdfs diskbalancer -help <command>** command to view detailed information.
- When you troubleshoot performance problems during the cluster O&M, check whether the HDFS disk balancing occurs in the event information of the cluster. If yes, check whether DiskBalancer is enabled in the cluster.
- After the automatic DiskBalancer function is enabled, the ongoing task stops only after the current data balancing is complete. The task cannot be canceled during the balancing.
- You can manually specify certain nodes for data balancing on the client.

## 7.26 Performing Concurrent Operations on HDFS Files

### Scenario

Performing this operation can concurrently modify file and directory permissions and access control tools in a cluster.

### Impact on the System

Performing concurrent file modification operations in a cluster has adverse impacts on the cluster performance. Therefore, you are advised to do so when the cluster is idle.

### Prerequisites

- The HDFS client or clients including HDFS has been installed. For example, the installation directory is **/opt/client**.
- Service component users are created by the MRS cluster administrator as required. In security mode, machine-machine users need to download the keytab file. A human-machine user needs to change the password upon the first login. (This operation is not required in normal mode.)

## Procedure

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to go to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** If the cluster is in security mode, the user executing the DistCp command must belong to the **supergroup** group and run the following command to perform user authentication. In normal mode, user authentication is not required.

```
kinit Component service user
```

**Step 5** Increase the JVM size of the client to prevent out of memory (OOM). (32 GB is recommended for 100 million files.)

### NOTE

The HDFS client exits abnormally and the error message "java.lang.OutOfMemoryError" is displayed after the HDFS client command is executed.

This problem occurs because the memory required for running the HDFS client exceeds the preset upper limit (128 MB by default). You can change the memory upper limit of the client by modifying **CLIENT\_GC\_OPTS** in *<Client installation path>/HDFS/component\_env*. For example, if you want to set the upper limit to 1 GB, run the following command:

```
CLIENT_GC_OPTS="-Xmx1G"
```

After the modification, run the following command to make the modification take effect:

```
source <Client installation path>/bigdata_env
```

**Step 6** Run the concurrent commands shown in the following table.

| Command                                                                               | Description                                                                                                                                                                                                                                                                                                                                   | Function                                                                   |
|---------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------|
| hdfs quickcmds [-t threadsNumber] [-p principal] [-k keytab] -setrep <rep> <path> ... | <p><b>threadsNumber</b> indicates the number of concurrent threads. The default value is the number of vCPUs of the local host.</p> <p><b>principal</b> indicates the Kerberos user.</p> <p><b>keytab</b> indicates the Keytab file.</p> <p><b>rep</b> indicates the number of replicas.</p> <p><b>path</b> indicates the HDFS directory.</p> | Used to concurrently set the number of copies of all files in a directory. |

| Command                                                                                                                                      | Description                                                                                                                                                                                                                                                                                                                                                                                           | Function                                                                |
|----------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------|
| hdfs quickcmds [-t threadsNumber] [-p principal] [-k keytab] -chown [owner][: [group]] <path> ...                                            | <p><b>threadsNumber</b> indicates the number of concurrent threads. The default value is the number of vCPUs of the local host.</p> <p><b>principal</b> indicates the Kerberos user.</p> <p><b>keytab</b> indicates the Keytab file.</p> <p><b>owner</b> indicates the owner.</p> <p><b>group</b> indicates the group to which the user belongs.</p> <p><b>path</b> indicates the HDFS directory.</p> | Used to concurrently set the owner group of all files in the directory. |
| hdfs quickcmds [-t threadsNumber] [-p principal] [-k keytab] -chmod <mode> <path> ...                                                        | <p><b>threadsNumber</b> indicates the number of concurrent threads. The default value is the number of vCPUs of the local host.</p> <p><b>principal</b> indicates the Kerberos user.</p> <p><b>keytab</b> indicates the Keytab file.</p> <p><b>mode</b> indicates the permission (for example, 754).</p> <p><b>path</b> indicates the HDFS directory.</p>                                             | Used to concurrently set permissions for all files in a directory.      |
| hdfs quickcmds [-t threadsNumber] [-p principal] [-k keytab] -setfacl [{-b -k} {-m -x} <acl_spec>] <path> ...] [--set <acl_spec> <path> ...] | <p><b>threadsNumber</b> indicates the number of concurrent threads. The default value is the number of vCPUs of the local host.</p> <p><b>principal</b> indicates the Kerberos user.</p> <p><b>keytab</b> indicates the Keytab file.</p> <p><b>acl_spec</b> indicates the ACL list separated by commas (,).</p> <p><b>path</b> indicates the HDFS directory.</p>                                      | Used to concurrently set ACL information for all files in a directory.  |

----End

## 7.27 Introduction to HDFS Logs

### Log Description

**Log path:** The default path of HDFS logs is `/var/log/Bigdata/hdfs/Role name`.

- NameNode: `/var/log/Bigdata/hdfs/nn` (run logs) and `/var/log/Bigdata/audit/hdfs/nn` (audit logs)

- DataNode: `/var/log/Bigdata/hdfs/dn` (run logs) and `/var/log/Bigdata/audit/hdfs/dn` (audit logs)
- ZKFC: `/var/log/Bigdata/hdfs/zkfc` (run logs) and `/var/log/Bigdata/audit/hdfs/zkfc` (audit logs)
- JournalNode: `/var/log/Bigdata/hdfs/jn` (run logs) and `/var/log/Bigdata/audit/hdfs/jn` (audit logs)
- Router: `/var/log/Bigdata/hdfs/router` (run logs) and `/var/log/Bigdata/audit/hdfs/router` (audit logs)
- HttpFS: `/var/log/Bigdata/hdfs/httpfs` (run logs) and `/var/log/Bigdata/audit/hdfs/httpfs` (audit logs)

**Log archive rule:** The automatic HDFS log compression function is enabled. By default, when the size of logs exceeds 100 MB, logs are automatically compressed into a log file named in the following format: `<Original log file name>-<yyyy-mm-dd_hh-mm-ss.[ID].log.zip`. A maximum of 100 latest compressed files are reserved. The number of compressed files can be configured on Manager.

**Table 7-29** HDFS log list

| Type    | Name                                            | Description                                                                                                                                             |
|---------|-------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| Run log | hadoop-<SSH_USER>-<process_name>-<hostname>.log | HDFS system log, which records most of the logs generated when the HDFS system is running.                                                              |
|         | hadoop-<SSH_USER>-<process_name>-<hostname>.out | Log that records the HDFS running environment information.                                                                                              |
|         | hadoop.log                                      | Log that records the operation of the Hadoop client.                                                                                                    |
|         | hdfs-period-check.log                           | Log that records scripts that are executed periodically, including automatic balancing, data migration, and JournalNode data synchronization detection. |
|         | <process_name>-<SSH_USER>-<DATE>-<PID>-gc.log   | Garbage collection log file                                                                                                                             |
|         | postinstallDetail.log                           | Work log before the HDFS service startup and after the installation.                                                                                    |

| Type | Name                        | Description                                                                               |
|------|-----------------------------|-------------------------------------------------------------------------------------------|
|      | hdfs-service-check.log      | Log that records whether the HDFS service starts successfully.                            |
|      | hdfs-set-storage-policy.log | Log that records the HDFS data storage policies.                                          |
|      | cleanupDetail.log           | Log that records the cleanup logs about the uninstallation of the HDFS service.           |
|      | prestartDetail.log          | Log that records cluster operations before the HDFS service startup.                      |
|      | hdfs-recover-fsimage.log    | Recovery log of the NameNode metadata.                                                    |
|      | datanode-disk-check.log     | Log that records the disk status check during the cluster installation and use.           |
|      | hdfs-availability-check.log | Log that check whether the HDFS service is available.                                     |
|      | hdfs-backup-fsimage.log     | Backup log of the NameNode metadata.                                                      |
|      | startDetail.log             | Detailed log that records the HDFS service startup.                                       |
|      | hdfs-blockplacement.log     | Log that records the placement policy of HDFS blocks.                                     |
|      | upgradeDetail.log           | Upgrade logs.                                                                             |
|      | hdfs-clean-acls-java.log    | Log that records the clearing of deleted roles' ACL information by HDFS.                  |
|      | hdfs-haCheck.log            | Run log that checks whether the NameNode in active or standby state has obtained scripts. |
|      | <process_name>-jvmpause.log | Log that records JVM pauses during process running.                                       |

| Type        | Name                                                                                                                                                                   | Description                                                                                            |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------|
|             | hadoop-<SSH_USER>-balancer-<hostname>.log                                                                                                                              | Run log of HDFS automatic balancing.                                                                   |
|             | hadoop-<SSH_USER>-balancer-<hostname>.out                                                                                                                              | Log that records information of the environment where HDFS executes automatic balancing.               |
|             | hdfs-switch-namenode.log                                                                                                                                               | Run log that records the HDFS active/standby switchover.                                               |
|             | hdfs-router-admin.log                                                                                                                                                  | Run log of the mount table management operation                                                        |
| Tomcat logs | hadoop-omm-host1.out, httpfs-catalina.<DATE>.log, httpfs-host-manager.<DATE>.log, httpfs-localhost.<DATE>.log, httpfs-manager.<DATE>.log, localhost_access_web_log.log | Tomcat run log                                                                                         |
| Audit log   | hdfs-audit-<process_name>.log<br>ranger-plugin-audit.log                                                                                                               | Audit log that records the HDFS operations (such as creating, deleting, modifying and querying files). |
|             | SecurityAuth.audit                                                                                                                                                     | HDFS security audit log.                                                                               |

## Log Level

**Table 7-30** lists the log levels supported by HDFS. The log levels include FATAL, ERROR, WARN, INFO, and DEBUG. Logs of which the levels are higher than or equal to the set level will be printed by programs. The higher the log level is set, the fewer the logs are recorded.

**Table 7-30** Log levels

| Level | Description                                                    |
|-------|----------------------------------------------------------------|
| FATAL | Indicates the critical error information about system running. |
| ERROR | Indicates the error information about system running.          |

| Level | Description                                                    |
|-------|----------------------------------------------------------------|
| WARN  | Indicates that the current event processing exists exceptions. |
| INFO  | Indicates that the system and events are running properly.     |
| DEBUG | Indicates the system and system debugging information.         |

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of HDFS by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** On the left menu bar, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Save the configuration. In the displayed dialog box, click **OK** to make the configurations take effect.

 **NOTE**

The configurations take effect immediately without restarting the service.

----End

## Log Formats

The following table lists the HDFS log formats.

**Table 7-31** Log formats

| Type    | Format                                                                                                                                                                            | Example                                                                                                                                                                |
|---------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Run log | <i>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt; &lt;Log level&gt; &lt;Name of the thread that generates the log&gt; &lt;Message in the log&gt; &lt;Location where the log event occurs&gt;</i> | 2015-01-26 18:43:42,840   INFO   IPC Server handler 40 on 8020   Rolling edit logs   org.apache.hadoop.hdfs.server.namenode.FSEditLog.rollEditLog(FSEditLog.java:1096) |

| Type      | Format                                                                                                                                                                            | Example                                                                                                                                                                                                                                                                                                                                                                             |
|-----------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Audit log | <i>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt; &lt;Log level&gt; &lt;Name of the thread that generates the log&gt; &lt;Message in the log&gt; &lt;Location where the log event occurs&gt;</i> | 2015-01-26 18:44:42,607   INFO   IPC Server handler 32 on 8020   allowed=true ugi=hbase (auth:SIMPLE) ip=/10.177.112.145 cmd=getfileinfo src=/hbase/WALs/hghoulaslx410,16020,1421743096083/hghoulaslx410%2C16020%2C1421743096083.1422268722795 dst=null perm=null   org.apache.hadoop.hdfs.server.namenode.FSNameSystem\$DefaultAuditLogger.logAuditMessage(FSNamesystem.java:7950) |

## 7.28 HDFS Performance Tuning

### 7.28.1 Improving Write Performance

#### Scenario

Improve the HDFS write performance by modifying the HDFS attributes.

#### Procedure

Navigation path for setting parameters:

On FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **HDFS** > **Configurations** and select **All Configurations**. Enter a parameter name in the search box.

**Table 7-32** Parameters for improving HDFS write performance

| Parameter                            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | Default Value |
|--------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| dfs.datanode.drop.cache.behind.reads | <p>Specifies whether to enable a DataNode to automatically clear all data in the cache after the data in the cache is transferred to the client.</p> <p>If it is set to <b>true</b>, the cached data is discarded. The parameter needs to be configured on the DataNode.</p> <p>You are advised to set it to <b>true</b> if data is repeatedly read only a few times, so that the cache can be used by other operations. You are advised to set it to <b>false</b> if data is repeatedly read many times to enhance the reading speed.</p> | false         |
| dfs.client-write-packet-size         | <p>Specifies the size of the client write packet. When the HDFS client writes data to the DataNode, the data will be accumulated until a packet is generated. Then, the packet is transmitted over the network. This parameter specifies the size (unit: byte) of the data packet to be transmitted, which can be specified by each job.</p> <p>In the 10-Gigabit network, you can increase the value of this parameter to enhance the transmission throughput.</p>                                                                        | 262144        |

## 7.28.2 Improving Read Performance Using Client Metadata Cache

### Scenario

Improve the HDFS read performance by using the client to cache the metadata for block locations.

#### NOTE

This function is recommended only for reading files that are not modified frequently. Because the data modification done on the server side by some other client is invisible to the cache client, which may cause the metadata obtained from the cache to be outdated.

### Procedure

**Navigation path for setting parameters:**

On FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **HDFS** > **Configurations**, select **All Configurations**, and enter the parameter name in the search box.

**Table 7-33** Parameter configuration

| Parameter                             | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  | Default Value |
|---------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| dfs.client.metadata.cache.enabled     | Enables or disables the client to cache the metadata for block locations. Set this parameter to <b>true</b> and use it along with the <b>dfs.client.metadata.cache.pattern</b> parameter to enable the cache.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                | false         |
| dfs.client.metadata.cache.pattern     | Indicates the regular expression pattern of the path of the file to be cached. Only the metadata for block locations of these files is cached until the metadata expires. This parameter is valid only when <b>dfs.client.metadata.cache.enabled</b> is set to <b>true</b> .<br>Example: <b>/test.*</b> indicates that all files whose paths start with <b>/test</b> are read.<br><b>NOTE</b> <ul style="list-style-type: none"> <li>To ensure consistency, configure a specific mode to cache only files that are not frequently modified by other clients.</li> <li>The regular expression pattern verifies only the path of the URI, but not the schema and authority in the case of the Fully Qualified path.</li> </ul> | -             |
| dfs.client.metadata.cache.expiry.sec  | Indicates the duration for caching metadata. The cache entry becomes invalid after its caching time exceeds this duration. Even metadata that is frequently used during the caching process can become invalid.<br>Time suffixes <b>s/m/h</b> can be used to indicate second, minute, and hour, respectively.<br><b>NOTE</b><br>If this parameter is set to <b>0s</b> , the cache function is disabled.                                                                                                                                                                                                                                                                                                                      | 60s           |
| dfs.client.metadata.cache.max.entries | Indicates the maximum number of non-expired data items that can be cached at a time.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         | 65536         |

 NOTE

Call `DFSClient#clearLocatedBlockCache()` to completely clear the client cache before it expires.

The sample usage is as follows:

```
FileSystem fs = FileSystem.get(conf);
DistributedFileSystem dfs = (DistributedFileSystem) fs;
DFSClient dfsClient = dfs.getClient();
dfsClient.clearLocatedBlockCache();
```

## 7.28.3 Improving the Connection Between the Client and NameNode Using Current Active Cache

### Scenario

When HDFS is deployed in high availability (HA) mode with multiple NameNode instances, the HDFS client needs to connect to each NameNode in sequence to determine which is the active NameNode and use it for client operations.

Once the active NameNode is identified, its details can be cached and shared to all clients running on the client host. In this way, each new client first tries to load the details of the active Name Node from the cache and save the RPC call to the standby NameNode, which can help a lot in abnormal scenarios, for example, when the standby NameNode cannot be connected for a long time.

When a fault occurs and the other NameNode is switched to the active state, the cached details are updated to the information about the current active NameNode.

### Procedure

Navigation path for setting parameters:

On FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **HDFS** > **Configurations**, select **All Configurations**, and enter the parameter name in the search box.

**Table 7-34** Configuration parameters

| Parameter                                               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                        | Default Value                                                           |
|---------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------|
| dfs.client.failover.proxy.provider.<br>[nameservice ID] | Client Failover proxy provider class which creates the NameNode proxy using the authenticated protocol. If this parameter is set to <b>org.apache.hadoop.hdfs.server.namenode.ha.BlackListingFailoverProxyProvider</b> , you can use the NameNode blacklist feature on the HDFS client. If this parameter is set to <b>org.apache.hadoop.hdfs.server.namenode.ha.ObserverReadProxyProvider</b> , you can configure the observer NameNode to process read requests. | org.apache.hadoop.hdfs.server.namenode.ha.AdaptiveFailoverProxyProvider |

| Parameter                                           | Description                                                                                                                                                                                                                                                                           | Default Value |
|-----------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| dfs.client.failover.activeinfo.share.flag           | Specifies whether to enable the cache function and share the detailed information about the current active NameNode with other clients. Set it to <b>true</b> to enable the cache function.                                                                                           | false         |
| dfs.client.failover.activeinfo.share.path           | Specifies the local directory for storing the shared files created by all clients in the host. If a cache area is to be shared by different users, the directory must have required permissions (for example, creating, reading, and writing cache files in the specified directory). | /tmp          |
| dfs.client.failover.activeinfo.share.io.timeout.sec | (Optional) Used to control timeout. The cache file is locked when it is being read or written, and if the file cannot be locked within the specified time, the attempt to read or update the caches will be abandoned. The unit is second.                                            | 5             |

 **NOTE**

The cache files created by the HDFS client are reused by other clients, and thus these files will not be deleted from the local system. If this function is disabled, you may need to manually clear the data.

## 7.29 FAQ

### 7.29.1 NameNode Startup Is Slow

#### Question

The NameNode startup is slow when it is restarted immediately after a large number of files (for example, 1 million files) are deleted.

#### Answer

It takes time for the DataNode to delete the corresponding blocks after files are deleted. When the NameNode is restarted immediately, it checks the block information reported by all DataNodes. If a deleted block is found, the NameNode generates the corresponding INFO log information, as shown below:

```
2015-06-10 19:25:50,215 | INFO | IPC Server handler 36 on 25000 | BLOCK* processReport: blk_1075861877_2121067 on node 10.91.8.218:9866 size 10249 does not belong to any file | org.apache.hadoop.hdfs.server.blockmanagement.BlockManager.processReport(BlockManager.java:1854)
```

A log is generated for each deleted block. A file may contain one or more blocks. Therefore, after startup, the NameNode spends a large amount of time printing

logs when a large number of files are deleted. As a result, the NameNode startup becomes slow.

To address this issue, the following operations can be performed to speed up the startup:

1. After a large number of files are deleted, wait until the DataNode deletes the corresponding blocks and then restart the NameNode.

You can run the *hdfs dfsadmin -report* command to check the disk space and check whether the files have been deleted.

2. If a large number of the preceding logs are generated, you can change the NameNode log level to **ERROR** so that the NameNode stops printing such logs.

After the NameNode is restarted, change the log level back to **INFO**. You do not need to restart the service after changing the log level.

## 7.29.2 Why MapReduce Tasks Fails in the Environment with Multiple NameServices?

### Question

Why MapReduce or Yarn tasks using the viewFS function fail to be executed in the environment with multiple NameServices?

### Answer

When viewFS is used, only directories mounted to viewFS can be accessed. Therefore, the most possible reason is that the configured path is not on the mount point of viewFS. Example:

```
<property>
<name>fs.defaultFS</name>
<value>viewfs://ClusterX</value>
</property>
<property>
<name>fs.viewfs.mounttable.ClusterX.link./folder1</name>
<value>hdfs://NS1/folder1</value>
</property>
<property>
<name>fs.viewfs.mounttable.ClusterX.link./folder2</name>
<value>hdfs://NS2/folder2</value>
</property>
```

In the MR configuration that depends on the HDFS, the mounted directory needs to be used.

#### Incorrect example:

```
<property>
<name>yarn.app.mapreduce.am.staging-dir</name>
<value>/tmp/hadoop-yarn/staging</value>
</property>
```

The root directory (/) cannot be accessed in viewFS.

#### Correct example:

```
<property>
<name>yarn.app.mapreduce.am.staging-dir</name>
```

```
<value>/folder1/tmp/hadoop-yarn/staging</value>  
</property>
```

## 7.29.3 DataNode Is Normal but Cannot Report Data Blocks

### Question

The DataNode is normal, but cannot report data blocks. As a result, the existing data blocks cannot be used.

### Answer

This error may occur when the number of data blocks in a data directory exceeds four times the upper limit (4 x 1 MB). And the DataNode generates the following error logs:

```
2015-11-05 10:26:32,936 | ERROR | DataNode:[[[DISK]file:/srv/BigData/hadoop/data1/dn/]] heartbeating to  
vm-210/10.91.8.210:8020 | Exception in BPOfferService for Block pool  
BP-805114975-10.91.8.210-1446519981645  
(Datanode Uuid bcada350-0231-413b-bac0-8c65e906c1bb) service to vm-210/10.91.8.210:8020 |  
BPServiceActor.java:824  
java.lang.IllegalStateException:com.google.protobuf.InvalidProtocolBufferException:Protocol message was  
too large.May  
be malicious.Use CodedInputStream.setSizeLimit() to increase the size limit. at  
org.apache.hadoop.hdfs.protocol.BlockListAsLongs$BufferDecoder$1.next(BlockListAsLongs.java:369)  
at org.apache.hadoop.hdfs.protocol.BlockListAsLongs$BufferDecoder$1.next(BlockListAsLongs.java:347) at  
org.apache.hadoop.hdfs.  
protocol.BlockListAsLongs$BufferDecoder.getBlockListAsLongs(BlockListAsLongs.java:325) at  
org.apache.hadoop.hdfs.protocolPB.DatanodeProtocolClientSideTranslatorPB.  
blockReport(DatanodeProtocolClientSideTranslatorPB.java:190) at  
org.apache.hadoop.hdfs.server.datanode.BPServiceActor.blockReport(BPServiceActor.java:473)  
at org.apache.hadoop.hdfs.server.datanode.BPServiceActor.offerService(BPServiceActor.java:685) at  
org.apache.hadoop.hdfs.server.datanode.BPServiceActor.run(BPServiceActor.java:822)  
at java.lang.Thread.run(Thread.java:745) Caused  
by:com.google.protobuf.InvalidProtocolBufferException:Protocol message was too large.May be  
malicious.Use CodedInputStream.setSizeLimit()  
to increase the size limit. at  
com.google.protobuf.InvalidProtocolBufferException.sizeLimitExceeded(InvalidProtocolBufferException.java:  
110) at com.google.protobuf.CodedInputStream.refillBuffer(CodedInputStream.java:755)  
at com.google.protobuf.CodedInputStream.readRawByte(CodedInputStream.java:769) at  
com.google.protobuf.CodedInputStream.readRawVarint64(CodedInputStream.java:462) at  
com.google.protobuf.  
CodedInputStream.readInt64(CodedInputStream.java:363) at  
org.apache.hadoop.hdfs.protocol.BlockListAsLongs$BufferDecoder$1.next(BlockListAsLongs.java:363)
```

The number of data blocks in the data directory is displayed as **Metric**. You can monitor its value through **http://<datanode-ip>:<http-port>/jmx**. If the value is greater than four times the upper limit (4 x 1 MB), you are advised to configure multiple drives and restart HDFS.

### Recovery procedure:

1. Configure multiple data directories on the DataNode.

For example, configure multiple directories on the DataNode where only the / **data1/datadir** directory is configured:

```
<property> <name>dfs.datanode.data.dir</name> <value>/data1/datadir</value> </property>
```

Configure as follows:

```
<property> <name>dfs.datanode.data.dir</name> <value>/data1/datadir,/,data2/datadir,/,data3/  
datadir</value> </property>
```

 NOTE

You are advised to configure multiple data directories on multiple disks. Otherwise, performance may be affected.

2. Restart the HDFS.
3. Perform the following operation to move the data to the new data directory:  

```
mv /data1/datadir/current/finalized/subdir1 /data2/datadir/current/finalized/  
subdir1
```
4. Restart the HDFS.

## 7.29.4 HDFS WebUI Cannot Properly Update Information About Damaged Data

### Question

1. When errors occur in the **dfs.datanode.data.dir** directory of DataNode due to the permission or disk damage, HDFS WebUI does not display information about damaged data.
2. After errors are restored, HDFS WebUI does not timely remove related information about damaged data.

### Answer

1. DataNode checks whether the disk is normal only when errors occur in file operations. Therefore, only when a data damage is detected and the error is reported to NameNode, NameNode displays information about the damaged data on HDFS WebUI.
2. After errors are fixed, you need to restart DataNode. During restarting DataNode, all data states are checked and damaged data information is uploaded to NameNode. Therefore, after errors are fixed, damaged data information is not displayed on the HDFS WebUI only by restarting DataNode.

## 7.29.5 Why Does the Distcp Command Fail in the Secure Cluster, Causing an Exception?

### Question

Why distcp command fails in the secure cluster with the following error displayed?

Client side exception

```
Invalid arguments: Unexpected end of file from server
```

Server side exception

```
javax.net.ssl.SSLException: Unrecognized SSL message, plaintext connection?
```

### Answer

The preceding error may occur if **webhdfs://** is used in the distcp command. The reason is that the big data cluster uses the HTTPS mechanism, that is,

**dfs.http.policy** is set to **HTTPS\_ONLY** in **core-site.xml** file. To avoid the error, replace **webhdfs://** with **swebhdfs://** in the file.

For example:

```
./hadoop distcp swwebhdfs://IP:PORT/testfile hdfs://IP:PORT/testfile1
```

## 7.29.6 Why Does DataNode Fail to Start When the Number of Disks Specified by **dfs.datanode.data.dir** Equals **dfs.datanode.failed.volumes.tolerated**?

### Question

If the number of disks specified by **dfs.datanode.data.dir** is equal to the value of **dfs.datanode.failed.volumes.tolerated**, DataNode startup will fail.

### Answer

By default, the failure of a single disk will cause the HDFS DataNode process to shut down, which results in the NameNode scheduling additional replicas for each block that is present on the DataNode. This causes needless replications of blocks that reside on disks that have not failed.

To prevent this, you can configure DataNodes to tolerate the failure of **dfs.data.dir** directories; use the **dfs.datanode.failed.volumes.tolerated** parameter in **hdfs-site.xml**. For example, if the value for this parameter is 3, the DataNode will only shut down after four or more data directories have failed. This value is respected on DataNode startup.

When we are configuring tolerate volumes which should be always less than the configured volumes or else we can keep this as -1 which is equal to n-1 (where n is number of disks) then DataNode will not be shut down.

## 7.29.7 Why Does an Error Occur During DataNode Capacity Calculation When Multiple **data.dir** Are Configured in a Partition?

### Question

DataNode capacity count incorrect if several **data.dir** configured in one disk partition.

### Answer

Currently calculation will be done based on the disk like **df** command in linux. Ideally user should not configure multiple directories for same disk which will be huge impact on performance where all data will go to one disk.

Hence it is always better to configure like below:

For example:

if the machine is having disks like following:

```
host-4:~ # df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/sda1       352G  11G  324G   4%  /
udev            190G  252K  190G   1%  /dev
tmpfs           190G   72K  190G   1%  /dev/shm
/dev/sdb1       2.7T   74G  2.5T   3%  /data1
/dev/sdc1       2.7T   75G  2.5T   3%  /data2
/dev/sdd1       2.7T   73G  2.5T   3%  /data
```

Suggested way of configuration:

```
<property>
<name>dfs.datanode.data.dir</name>
<value>/data1/datadir/,/data2/datadir,/data3/datadir</value>
</property>
```

Following is not recommended:

```
<property>
<name>dfs.datanode.data.dir</name>
<value>/data1/datadir1/,/data2/datadir1,/data3/datadir1,/data1/datadir2/data1/datadir3,/data2/datadir2,/
data2/datadir3,/data3/datadir2,/data3/datadir3</value>
</property>
```

## 7.29.8 Standby NameNode Fails to Be Restarted When the System Is Powered off During Metadata (Namespace) Storage

### Question

When the standby NameNode is powered off during metadata (namespace) storage, it fails to be started and the following error information is displayed.

```
2015-12-04 11:49:12,121 | ERROR | main | Failed to load image from FS
ImageFile(file=/srv/BigData/namenode/current/fsimage_000000000000096
080,
cpkrtTxId=0000000000000096080) | FSImage.java:685
java.io.IOException: Invalid MD5 file /srv/BigData/namenode/current/f
simage_0000000000000096080.md5:
the content " " does not match the expecte
d pattern.
at org.apache.hadoop.hdfs.util.MD5FileUtils.readStoredMd5(MD5FileUtil
s.java:92)
at org.apache.hadoop.hdfs.util.MD5FileUtils.readStoredMd5ForFile(MD5F
ileUtils.java:109)
at org.apache.hadoop.hdfs.server.namenode.FSImage.loadFSImage(FSImage
.java:975)
at org.apache.hadoop.hdfs.server.namenode.FSImage.loadFSImageFile(FSI
mage.java:744)
at org.apache.hadoop.hdfs.server.namenode.FSImage.loadFSImage(FSImage
.java:682)
at org.apache.hadoop.hdfs.server.namenode.FSImage.recoverTransitionRea
d(FSImage.java:300)
at org.apache.hadoop.hdfs.server.namenode.FSNamesystem.loadFSImage(FS
Namesystem.java:968)
at org.apache.hadoop.hdfs.server.namenode.FSNamesystem.loadFromDisk(F
SNamesystem.java:675)
at org.apache.hadoop.hdfs.server.namenode.NameNode.loadNamesystem(Nam
eNode.java:625)
at org.apache.hadoop.hdfs.server.namenode.NameNode.initialize(NameNod
e.java:685)
at org.apache.hadoop.hdfs.server.namenode.NameNode.<init>(NameNode.ja
va:889)
at org.apache.hadoop.hdfs.server.namenode.NameNode.<init>(NameNode.ja
va:872)
at org.apache.hadoop.hdfs.server.namenode.NameNode.createNameNode(Nam
eNode.java:1580)
at org.apache.hadoop.hdfs.server.namenode.NameNode.main(NameNode.java
:1654)
```

## Answer

When the standby NameNode is powered off during metadata (namespace) storage, it fails to be started and the MD5 file is damaged. Remove the damaged fsimage and start the standby NameNode to rectify the fault. After the rectification, the standby NameNode loads the previous fsimage and reproduces all edits.

Recovery procedure:

1. Run the following command to remove the damaged fsimage:  

```
rm -rf ${BIGDATA_DATA_HOME}/namenode/current/
fsimage_0000000000000096
```
2. Start the standby NameNode.

## 7.29.9 Why Data in the Buffer Is Lost If a Power Outage Occurs During Storage of Small Files

### Question

Why data in the buffer is lost if a power outage occurs during storage of small files?

## Answer

Because of a power outage, the blocks in the buffer are not written to the disk immediately after the write operation is completed. To enable synchronization of blocks to the disk, set **dfs.datanode.synconclose** to **true** in the **hdfs-site.xml** file.

By default, **dfs.datanode.synconclose** is set to **false**. This improves the performance but can cause a buffer data loss in the case of a power outage, and therefore, it is recommended that **dfs.datanode.synconclose** be set to **true** even if this may affect the performance. You can determine whether to enable the synchronization function based on your actual situation.

## 7.29.10 Why Does Array Border-crossing Occur During FileInputFormat Split?

### Question

When HDFS calls the FileInputFormat getSplit method, the ArrayIndexOutOfBoundsException: 0 appears in the following log:

```
java.lang.ArrayIndexOutOfBoundsException: 0
at org.apache.hadoop.mapred.FileInputFormat.identifyHosts(FileInputFormat.java:708)
at org.apache.hadoop.mapred.FileInputFormat.getSplitHostsAndCachedHosts(FileInputFormat.java:675)
at org.apache.hadoop.mapred.FileInputFormat.getSplits(FileInputFormat.java:359)
at org.apache.spark.rdd.HadoopRDD.getPartitions(HadoopRDD.scala:210)
at org.apache.spark.rdd.RDD$$anonfun$partitions$2.apply(RDD.scala:239)
at org.apache.spark.rdd.RDD$$anonfun$partitions$2.apply(RDD.scala:237)
at scala.Option.getOrElse(Option.scala:120)
at org.apache.spark.rdd.RDD.partitions(RDD.scala:237)
at org.apache.spark.rdd.MapPartitionsRDD.getPartitions(MapPartitionsRDD.scala:35)
```

### Answer

The elements of each block correspondent frame are as below: /default/rack0/;/ default/rack0/datanodeip:port.

The problem is due to a block damage or loss, making the block correspondent machine ip and port become null. Use **hdfs fsck** to check the file blocks health state when this problem occurs, and remove damaged block or restore the missing block to re-computing the task.

## 7.29.11 Why Is the Storage Type of File Copies DISK When the Tiered Storage Policy Is LAZY\_PERSIST?

### Question

When the storage policy of the file is set to **LAZY\_PERSIST**, the storage type of the first replica should be **RAM\_DISK**, and the storage type of other replicas should be **DISK**.

But why is the storage type of all copies shown as **DISK** actually?

### Answer

When a user writes into a file whose storage policy is **LAZY\_PERSIST**, three replicas are written one by one. The first replica is preferentially written into the

DataNode where the client is located. The storage type of all replicas is **DISK** in the following scenarios:

- If the DataNode where the client is located does not have the RAM disk, the first replica is written into the disk of the DataNode where the client is located, and other replicas are written into the disks of other nodes.
- If the DataNode where the client is located has the RAM disk, and the value of **dfs.datanode.max.locked.memory** is not specified or smaller than the value of **dfs.blocksize**, the first replica is written into the disk of the DataNode where the client is located, and other replicas are written into the disks of other nodes.

## 7.29.12 The HDFS Client Is Unresponsive When the NameNode Is Overloaded for a Long Time

### Question

When the NameNode node is overloaded (100% of the CPU is occupied), the NameNode is unresponsive. The HDFS clients that are connected to the overloaded NameNode fail to run properly. However, the HDFS clients that are newly connected to the NameNode will be switched to a backup NameNode and run properly.

### Answer

The default configuration must be used (as described in [Table 7-35](#)) when the error preceding described occurs: the **keep alive** mechanism is enabled for the RPC connection between the HDFS client and the NameNode. The **keep alive** mechanism will keep the HDFS client waiting for the response from server and prevent the connection from being out timed, causing the unresponsiveness of the HDFS client.

Perform the following operations to the unresponsive HDFS client:

- Leave the HDFS client waiting. Once the CPU usage of the node where NameNode locates drops, the NameNode will obtain CPU resources and the HDFS client will receive a response.
- If you do not want to leave the HDFS client running, restart the application where the HDFS client locates to reconnect the HDFS client to another idle NameNode.

Procedure:

Configure the following parameters in the **core-site.xml** file on the client.

**Table 7-35** Parameter description

Parameter	Description	Default Value
ipc.client.ping	<p>If the <b>ipc.client.ping</b> parameter is configured to <b>true</b>, the HDFS client will wait for the response from the server and periodically send the <b>ping</b> message to avoid disconnection caused by <b>tcp timeout</b>.</p> <p>If the <b>ipc.client.ping</b> parameter is configured to <b>false</b>, the HDFS client will set the value of <b>ipc.ping.interval</b> as the timeout time. If no response is received within that time, timeout occurs.</p> <p>To avoid the unresponsiveness of HDFS when the NameNode is overloaded for a long time, you are advised to set the parameter to <b>false</b>.</p>	true
ipc.ping.interval	<p>If the value of <b>ipc.client.ping</b> is <b>true</b>, <b>ipc.ping.interval</b> indicates the interval between sending the ping messages.</p> <p>If the value of <b>ipc.client.ping</b> is <b>false</b>, <b>ipc.ping.interval</b> indicates the timeout time for connection.</p> <p>To avoid the unresponsiveness of HDFS when the NameNode is overloaded for a long time, you are advised to set the parameter to a large value, for example <b>900000</b> (unit ms) to avoid timeout when the server is busy.</p>	60000

### 7.29.13 Can I Delete or Modify the Data Storage Directory in DataNode?

#### Question

- In DataNode, the storage directory of data blocks is specified by **dfs.datanode.data.dir**. Can I modify **dfs.datanode.data.dir** to modify the data storage directory?
- Can I modify files under the data storage directory?

#### Answer

During the system installation, you need to configure the **dfs.datanode.data.dir** parameter to specify one or more root directories.

- During the system installation, you need to configure the **dfs.datanode.data.dir** parameter to specify one or more root directories.
- Exercise caution when modifying **dfs.datanode.data.dir**. You can configure this parameter to add a new data root directory.
- Do not modify or delete data blocks in the storage directory. Otherwise, the data blocks will lose.

 NOTE

Similarly, do not delete the storage directory, or modify or delete data blocks under the directory using the following parameters:

- `dfs.namenode.edits.dir`
- `dfs.namenode.name.dir`
- `dfs.journalnode.edits.dir`

## 7.29.14 Blocks Miss on the NameNode UI After the Successful Rollback

### Question

Why are some blocks missing on the NameNode UI after the rollback is successful?

### Answer

This problem occurs because blocks with new IDs or genstamps may exist on the DataNode. The block files in the DataNode may have different generation flags and lengths from those in the rollback images of the NameNode. Therefore, the NameNode rejects these blocks in the DataNode and marks the files as damaged.

#### Scenarios:

1. Before an upgrade:  
Client A writes some data to file X. (Assume A bytes are written.)
2. During an upgrade:  
Client A still writes data to file X. (The data in the file is A + B bytes.)
3. After an upgrade:  
Client A completes the file writing. The final data is A + B bytes.
4. Rollback started:  
The status will be rolled back to the status before the upgrade. That is, file X in NameNode will have A bytes, but block files in DataNode will have A + B bytes.

#### Recovery procedure:

1. Obtain the list of damaged files from NameNode web UI or run the following command to obtain:  
**`hdfs fsck <filepath> -list-corruptfileblocks`**
2. Run the following command to delete unnecessary files:  
**`hdfs fsck <corrupt file path> - delete`**

 NOTE

Deleting a file is a high-risk operation. Ensure that the files are no longer needed before performing this operation.

3. For the required files, run the **`fsck`** command to obtain the block list and block sequence.

- In the block sequence table provided, use the block ID to search for the data directory in the DataNode and download the corresponding block from the DataNode.
- Write all such block files in appending mode based on the sequence to construct the original file.

Example:

File 1--> blk\_1, blk\_2, blk\_3

Create a file by combining the contents of all three block files from the same sequence.

- Delete the old file from HDFS and rewrite the new file.

## 7.29.15 Why Is "java.net.SocketException: No buffer space available" Reported When Data Is Written to HDFS

### Question

Why is an "java.net.SocketException: No buffer space available" exception reported when data is written to HDFS?

This problem occurs when files are written to the HDFS. Check the error logs of the client and DataNode.

The client logs are as follows:

Figure 7-8 Client logs

```
2017-07-05 21:58:06.459 INFO [htable-pool3-t11] ipc.AbstractRpcClient: RPC Server Kerberos principal name for service=ClientService is hbase/hadoop.hadoop123.com@HADOOP12
2017-07-05 21:58:06.893 WARN [main] mapreduce.LoadIncrementalHFiles: Skipping non-directory hdfs://hacluster/HBaseTest/bulkload_output/_SUCCESS
2017-07-05 21:59:13.211 WARN [main] hdfs.BlockReaderFactory: I/O error constructing remote block reader.
java.net.SocketException: No buffer space available
    at sun.nio.ch.Net.connect0(Native Method)
    at sun.nio.ch.Net.connect(Net.java:454)
    at sun.nio.ch.SocketChannelImpl.connect(SocketChannelImpl.java:648)
    at org.apache.hadoop.net.SocketIOWithTimeout.connect(SocketIOWithTimeout.java:192)
    at org.apache.hadoop.net.NetUtils.connect(NetUtils.java:531)
    at org.apache.hadoop.hdfs.DFSClient.newConnectedPeer(DFSClient.java:3345)
    at org.apache.hadoop.hdfs.BlockReaderFactory.nextTcpPeer(BlockReaderFactory.java:789)
    at org.apache.hadoop.hdfs.BlockReaderFactory.getRemoteBlockReaderFromTcp(BlockReaderFactory.java:706)
    at org.apache.hadoop.hdfs.BlockReaderFactory.build(BlockReaderFactory.java:369)
    at org.apache.hadoop.hdfs.DFSInputStream.getBlockReader(DFSInputStream.java:713)
    at org.apache.hadoop.hdfs.DFSInputStream.blockSeekTo(DFSInputStream.java:563)
    at org.apache.hadoop.hdfs.DFSInputStream.readWithStrategy(DFSInputStream.java:919)
    at org.apache.hadoop.hdfs.DFSInputStream.read(DFSInputStream.java:973)
    at java.io.DataInputStream.readFully(DataInputStream.java:195)
    at org.apache.hadoop.hbase.io.hfile.FixedFileTrailer.readFromStream(FixedFileTrailer.java:391)
    at org.apache.hadoop.hbase.io.hfile.HFile.isHFileFormat(HFile.java:578)
    at org.apache.hadoop.hbase.io.hfile.HFile.isHFileFormat(HFile.java:560)
    at org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles.visitBulkHFiles(LoadIncrementalHFiles.java:229)
    at org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles.discoverLoadQueue(LoadIncrementalHFiles.java:281)
    at org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles.prepareHFileQueue(LoadIncrementalHFiles.java:452)
    at org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles.doBulkLoad(LoadIncrementalHFiles.java:365)
    at org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles.doBulkLoad(LoadIncrementalHFiles.java:331)
    at org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles.run(LoadIncrementalHFiles.java:1107)
    at org.apache.hadoop.util.ToolRunner.run(ToolRunner.java:70)
    at org.apache.hadoop.hbase.mapreduce.LoadIncrementalHFiles.main(LoadIncrementalHFiles.java:1114)
2017-07-05 21:59:13.215 WARN [main] hdfs.DFSClient: Failed to connect to /192.168.152.128:25009 for block BP-19099348819-192.168.199.5-1497961637591:blk_1107301222_335745
ffer space available
java.net.SocketException: No buffer space available
    at sun.nio.ch.Net.connect0(Native Method)
    at sun.nio.ch.Net.connect(Net.java:454)
    at sun.nio.ch.SocketChannelImpl.connect(SocketChannelImpl.java:648)
    at org.apache.hadoop.net.SocketIOWithTimeout.connect(SocketIOWithTimeout.java:192)
    at org.apache.hadoop.net.NetUtils.connect(NetUtils.java:531)
    at org.apache.hadoop.hdfs.DFSClient.newConnectedPeer(DFSClient.java:3345)
```

DataNode logs are as follows:

```
2017-07-24 20:43:39,269 | ERROR | DataXceiver for client DFSClient_NONMAPREDUCE_996005058_86
at /192.168.164.155:40214 [Receiving block
BP-1287143557-192.168.199.6-1500707719940:blk_1074269754_528941 with io weight 10] |
DataNode{data=FSDataset{dirpath='[/srv/BigData/hadoop/data1/dn/current, /srv/BigData/hadoop/
data2/dn/current, /srv/BigData/hadoop/data3/dn/current, /srv/BigData/hadoop/data4/dn/current, /srv/
BigData/hadoop/data5/dn/current, /srv/BigData/hadoop/data6/dn/current, /srv/BigData/hadoop/data7/dn/
current]'}, localName='192-168-164-155:9866', datanodeUuid='a013e29c-4e72-400c-bc7b-bbbb0799604c',
xmitsInProgress=0}:Exception transferring block
BP-1287143557-192.168.199.6-1500707719940:blk_1074269754_528941 to mirror 192.168.202.99:9866:
java.net.SocketException: No buffer space available | DataXceiver.java:870
```

```

2017-07-24 20:43:39,269 | INFO | DataXceiver for client DFSClient_NONMAPREDUCE_996005058_86
at /192.168.164.155:40214 [Receiving block
BP-1287143557-192.168.199.6-1500707719940:blk_1074269754_528941 with io weight 10] | opWriteBlock
BP-1287143557-192.168.199.6-1500707719940:blk_1074269754_528941 received exception
java.net.SocketException: No buffer space available | DataXceiver.java:933
2017-07-24 20:43:39,270 | ERROR | DataXceiver for client DFSClient_NONMAPREDUCE_996005058_86
at /192.168.164.155:40214 [Receiving block
BP-1287143557-192.168.199.6-1500707719940:blk_1074269754_528941 with io weight 10] |
192-168-164-155:9866:DataXceiver error processing WRITE_BLOCK operation src: /192.168.164.155:40214
dst: /192.168.164.155:9866 | DataXceiver.java:304 java.net.SocketException: No buffer space available
at sun.nio.ch.Net.connect0(Native Method)
at sun.nio.ch.Net.connect(Net.java:454)
at sun.nio.ch.Net.connect(Net.java:446)
at sun.nio.ch.SocketChannelImpl.connect(SocketChannelImpl.java:648)
at org.apache.hadoop.net.SocketIOWithTimeout.connect(SocketIOWithTimeout.java:192)
at org.apache.hadoop.net.NetUtils.connect(NetUtils.java:531)
at org.apache.hadoop.net.NetUtils.connect(NetUtils.java:495)
at org.apache.hadoop.hdfs.server.datanode.DataXceiver.writeBlock(DataXceiver.java:800)
at org.apache.hadoop.hdfs.protocol.datatransfer.Receiver.opWriteBlock(Receiver.java:138)
at org.apache.hadoop.hdfs.protocol.datatransfer.Receiver.processOp(Receiver.java:74)
at org.apache.hadoop.hdfs.server.datanode.DataXceiver.run(DataXceiver.java:265)
at java.lang.Thread.run(Thread.java:748)

```

## Answer

The preceding problem may be caused by network memory exhaustion.

You can increase the threshold of the network device based on the actual scenario.

Example:

```

[root@xxxx ~]# cat /proc/sys/net/ipv4/neigh/default/gc_thresh*
128
512
1024
[root@xxxx ~]# echo 512 > /proc/sys/net/ipv4/neigh/default/gc_thresh1
[root@xxxx ~]# echo 2048 > /proc/sys/net/ipv4/neigh/default/gc_thresh2
[root@xxxx ~]# echo 4096 > /proc/sys/net/ipv4/neigh/default/gc_thresh3
[root@xxxx ~]# cat /proc/sys/net/ipv4/neigh/default/gc_thresh*
512
2048
4096

```

You can also add the following parameters to the `/etc/sysctl.conf` file. The configuration takes effect even if the host is restarted.

```

net.ipv4.neigh.default.gc_thresh1 = 512
net.ipv4.neigh.default.gc_thresh2 = 2048
net.ipv4.neigh.default.gc_thresh3 = 4096

```

## 7.29.16 Why are There Two Standby NameNodes After the active NameNode Is Restarted?

### Question

Why are there two standby NameNodes after the active NameNode is restarted?

When this problem occurs, check the ZooKeeper and ZooKeeper FC logs. You can find that the sessions used for the communication between the ZooKeeper server and client (ZKFC) are inconsistent. The session ID of the ZooKeeper server is **0x164cb2b3e4b36ae4**, and the session ID of the ZooKeeper FC is **0x144cb2b3e4b36ae4**. Such inconsistency means that the data interaction between the ZooKeeper server and ZKFC fails.

Content of the ZooKeeper log is as follows:

```
2015-04-15 21:24:54,257 | INFO | CommitProcessor:22 | Established session 0x164cb2b3e4b36ae4 with negotiated timeout 45000 for client /192.168.0.117:44586 | org.apache.zookeeper.server.ZooKeeperServer.finishSessionInit(ZooKeeperServer.java:623)
2015-04-15 21:24:54,261 | INFO | NIOServerCxn.Factory:192-168-0-114/192.168.0.114:2181 | Successfully authenticated client: authenticationID=hdfs/hadoop@<System domain name>; authorizationID=hdfs/hadoop@<System domain name>. | org.apache.zookeeper.server.auth.SaslServerCallbackHandler.handleAuthorizeCallback(SaslServerCallbackHandler.java:118)
2015-04-15 21:24:54,261 | INFO | NIOServerCxn.Factory:192-168-0-114/192.168.0.114:2181 | Setting authorizedID: hdfs/hadoop@<System domain name> | org.apache.zookeeper.server.auth.SaslServerCallbackHandler.handleAuthorizeCallback(SaslServerCallbackHandler.java:134)
2015-04-15 21:24:54,261 | INFO | NIOServerCxn.Factory:192-168-0-114/192.168.0.114:2181 | adding SASL authorization for authorizationID: hdfs/hadoop@<System domain name> | org.apache.zookeeper.server.ZooKeeperServer.processSasl(ZooKeeperServer.java:1009)
2015-04-15 21:24:54,262 | INFO | ProcessThread(sid:22 cport:-1): | Got user-level KeeperException when processing sessionid:0x164cb2b3e4b36ae4 type:create cxid:0x3 zxid:0x20009fafc txntype:-1 reqpath:n/a Error Path:/hadoop-ha/hacluster/ActiveStandbyElectorLock Error:KeeperErrorCode = NodeExists for /hadoop-ha/hacluster/ActiveStandbyElectorLock | org.apache.zookeeper.server.PrepareRequestProcessor.pRequest(PrepareRequestProcessor.java:648)
```

Content of the ZKFC log is as follows:

```
2015-04-15 21:24:54,237 | INFO | main-SendThread(192-168-0-114:2181) | Socket connection established to 192-168-0-114/192.168.0.114:2181, initiating session | org.apache.zookeeper.ClientCnxn$SendThread.primeConnection(ClientCnxn.java:854)
2015-04-15 21:24:54,257 | INFO | main-SendThread(192-168-0-114:2181) | Session establishment complete on server 192-168-0-114/192.168.0.114:2181, sessionid = 0x144cb2b3e4b36ae4, negotiated timeout = 45000 | org.apache.zookeeper.ClientCnxn$SendThread.onConnected(ClientCnxn.java:1259)
2015-04-15 21:24:54,260 | INFO | main-EventThread | EventThread shut down | org.apache.zookeeper.ClientCnxn$EventThread.run(ClientCnxn.java:512)
2015-04-15 21:24:54,262 | INFO | main-EventThread | Session connected. | org.apache.hadoop.ha.ActiveStandbyElector.processWatchEvent(ActiveStandbyElector.java:547)
2015-04-15 21:24:54,264 | INFO | main-EventThread | Successfully authenticated to ZooKeeper using SASL. | org.apache.hadoop.ha.ActiveStandbyElector.processWatchEvent(ActiveStandbyElector.java:573)
```

## Answer

- Cause Analysis

After the active NameNode restarts, the temporary node **/hadoop-ha/hacluster/ActiveStandbyElectorLock** created on ZooKeeper is deleted. After the standby NameNode receives that information that the **/hadoop-ha/hacluster/ActiveStandbyElectorLock** node is deleted, the standby NameNode creates the **/hadoop-ha/hacluster/ActiveStandbyElectorLock** node in ZooKeeper in order to switch to the active NameNode. However, when the standby NameNode connects with ZooKeeper through the client ZKFC, the session ID of ZKFC differs from that of ZooKeeper due to network issues, overload CPU, or overload clusters. In this case, the watcher of the standby NameNode fails to detect that the temporary node has been successfully created, and fails to consider the standby NameNode as the active NameNode. After the original active NameNode restarts, it detects that the **/hadoop-ha/hacluster/ActiveStandbyElectorLock** already exists and becomes the standby NameNode. Therefore, both NameNodes are standby NameNodes.

- Solution

You are advised to restart two ZKFCs of HDFS on FusionInsight Manager.

## 7.29.17 When Does a Balance Process in HDFS, Shut Down and Fail to be Executed Again?

### Question

After I start a Balance process in HDFS, the process is shut down abnormally. If I attempt to execute the Balance process again, it fails again.

### Answer

After a Balance process is executed in HDFS, another Balance process can be executed only after the **/system/balancer.id** file is automatically released.

However, if a Balance process is shut down abnormally, the **/system/balancer.id** has not been released when the Balance is executed again, which triggers the **append /system/balancer.id** operation.

- If the time spent on releasing the **/system/balancer.id** file exceeds the soft-limit lease period 60 seconds, executing the Balance process again triggers the append operation, which preempts the lease. The last block is in construction or under recovery status, which triggers the block recovery operation. The **/system/balancer.id** file cannot be closed until the block recovery completes. Therefore, the append operation fails.

After the **append /system/balancer.id** operation fails, the exception message **RecoveryInProgressException** is displayed.

```
org.apache.hadoop.ipc.RemoteException(org.apache.hadoop.protocol.RecoveryInProgressException):  
Failed to APPEND_FILE /system/balancer.id for DFSClient because lease recovery is in progress. Try  
again later.
```

- If the time spent on releasing the **/system/balancer.id** file is within 60 seconds, the original client continues to own the lease and the exception **AlreadyBeingCreatedException** occurs and null is returned to the client. The following exception message is displayed on the client:  

```
java.io.IOException: Cannot create any NameNode Connectors.. Exiting...
```

Either of the following methods can be used to solve the problem:

- Execute the Balance process again after the hard-limit lease period expires for 1 hour, when the original client has released the lease.
- Delete the **/system/balancer.id** file before executing the Balance process again.

## 7.29.18 "This page can't be displayed" Is Displayed When Internet Explorer Fails to Access the Native HDFS UI

### Question

Occasionally, internet Explorer 9, Explorer 10, or Explorer 11 fails to access the native HDFS UI.

### Symptom

Internet Explorer 9, Explorer 10, or Explorer 11 fails to access the native HDFS UI, as shown in the following figure.

# This page can't be displayed

Turn on TLS 1.0, TLS 1.1, and TLS 1.2 in Advanced settings and try connecting to

## Cause

Some Internet Explorer 9, Explorer 10, or Explorer 11 versions fail to handle SSL handshake issues, causing access failure.

## Solution

Refresh the page.

## 7.29.19 NameNode Fails to Be Restarted Due to EditLog Discontinuity

### Question

If a JournalNode server is powered off, the data directory disk is fully occupied, and the network is abnormal, the EditLog sequence number on the JournalNode is inconsecutive. In this case, the NameNode restart may fail.

### Symptom

The NameNode fails to be restarted. The following error information is reported in the NameNode run logs:

```
2019-11-08 16:30:28,399 | ERROR | main | Failed to start namenode. | NameNode.java:1732
java.io.IOException: There appears to be a gap in the edit log. We expected txid 13698019, but got txid 13698088.
    at org.apache.hadoop.hdfs.server.namenode.MetaRecoveryContext.editLogLoaderPrompt(MetaRecoveryContext.java:94)
    at org.apache.hadoop.hdfs.server.namenode.FSEditLogLoader.loadEditRecords(FSEditLogLoader.java:278)
    at org.apache.hadoop.hdfs.server.namenode.FSEditLogLoader.loadFSEdits(FSEditLogLoader.java:188)
    at org.apache.hadoop.hdfs.server.namenode.FSImage.loadEdits(FSImage.java:924)
    at org.apache.hadoop.hdfs.server.namenode.FSImage.loadFSImage(FSImage.java:771)
    at org.apache.hadoop.hdfs.server.namenode.FSImage.recoverTransitionRead(FSImage.java:331)
    at org.apache.hadoop.hdfs.server.namenode.FSNamesystem.loadFSImage(FSNamesystem.java:1108)
    at org.apache.hadoop.hdfs.server.namenode.FSNamesystem.loadFromDisk(FSNamesystem.java:727)
    at org.apache.hadoop.hdfs.server.namenode.NameNode.loadNamesystem(NameNode.java:638)
    at org.apache.hadoop.hdfs.server.namenode.NameNode.initialize(NameNode.java:700)
    at org.apache.hadoop.hdfs.server.namenode.NameNode.<init>(NameNode.java:943)
    at org.apache.hadoop.hdfs.server.namenode.NameNode.<init>(NameNode.java:916)
    at org.apache.hadoop.hdfs.server.namenode.NameNode.createNameNode(NameNode.java:1655)
    at org.apache.hadoop.hdfs.server.namenode.NameNode.main(NameNode.java:1725)
```

## Solution

1. Find the active NameNode before the restart, go to its data directory (you can obtain the directory, such as **/srv/BigData/namenode/current** by checking the configuration item **dfs.namenode.name.dir**), and obtain the sequence number of the latest FsImage file, as shown in the following figure:

```

-rw-----, 1 omm wheel      574 Oct  2 01:12 edits_0000000000013259401-0000000000:
-rw-----, 1 omm wheel      575 Oct  2 01:13 edits_0000000000013259409-0000000000:
-rw-----, 1 omm wheel       42 Oct  2 01:13 edits_0000000000013259417-0000000000:
-rw-----, 1 omm wheel 1048576 Nov  8 16:01 edits_inprogress_0000000000013698088
-rw-----, 1 omm wheel 314803 Nov  8 15:53 fsimage_0000000000013698018
-rw-----, 1 omm wheel      62 Nov  8 15:53 fsimage_0000000000013698018.md5
-rw-----, 1 omm wheel 314803 Nov  8 15:56 fsimage_0000000000013698050
-rw-----, 1 omm wheel      62 Nov  8 15:56 fsimage_0000000000013698050.md5
-rw-----, 1 omm wheel 314803 Nov  8 15:59 fsimage_0000000000013698066
-rw-----, 1 omm wheel      62 Nov  8 15:59 fsimage_0000000000013698066.md5
-rw-----, 1 omm wheel      9 Oct  2 01:13 seen_txid
-rw-----, 1 omm wheel     187 Nov  8 15:59 VERSION

```

2. Check the data directory of each JournalNode (you can obtain the directory such as `/srv/BigData/journalnode/hacluster/current` by checking the value of the configuration item `dfs.journalnode.edits.dir`), and check whether the sequence number starting from that obtained in step 1 is consecutive in edits files. That is, you need to check whether the last sequence number of the previous edits file is consecutive with the first sequence number of the next edits file. (As shown in the following figure, `edits_0000000000013259231-0000000000013259237` and `edits_0000000000013259239-0000000000013259246` are not consecutive.)

```

-rw-----, 1 omm wheel      576 Oct  2 00:41 edits_0000000000013259151-0000000000013259158
-rw-----, 1 omm wheel      575 Oct  2 00:43 edits_0000000000013259159-0000000000013259166
-rw-----, 1 omm wheel      576 Oct  2 00:43 edits_0000000000013259167-0000000000013259174
-rw-----, 1 omm wheel      575 Oct  2 00:45 edits_0000000000013259175-0000000000013259182
-rw-----, 1 omm wheel      575 Oct  2 00:45 edits_0000000000013259183-0000000000013259190
-rw-----, 1 omm wheel      576 Oct  2 00:47 edits_0000000000013259191-0000000000013259198
-rw-----, 1 omm wheel      575 Oct  2 00:48 edits_0000000000013259199-0000000000013259206
-rw-----, 1 omm wheel      575 Oct  2 00:49 edits_0000000000013259207-0000000000013259214
-rw-----, 1 omm wheel      575 Oct  2 00:50 edits_0000000000013259215-0000000000013259222
-rw-----, 1 omm wheel      573 Oct  2 00:51 edits_0000000000013259223-0000000000013259230
-rw-----, 1 omm wheel      571 Oct  2 00:52 edits_0000000000013259231-0000000000013259237
-rw-----, 1 omm wheel      576 Oct  2 00:53 edits_0000000000013259239-0000000000013259246
-rw-----, 1 omm wheel      575 Oct  2 00:54 edits_0000000000013259247-0000000000013259254
-rw-----, 1 omm wheel      576 Oct  2 00:55 edits_0000000000013259255-0000000000013259262
-rw-----, 1 omm wheel      42 Oct  2 00:56 edits_0000000000013259263-0000000000013259264
-rw-----, 1 omm wheel     1107 Oct  2 00:57 edits_0000000000013259265-0000000000013259278
-rw-----, 1 omm wheel      42 Oct  2 00:58 edits_0000000000013259279-0000000000013259280
-rw-----, 1 omm wheel     1109 Oct  2 00:59 edits_0000000000013259281-0000000000013259294
-rw-----, 1 omm wheel      42 Oct  2 01:00 edits_0000000000013259295-0000000000013259296
-rw-----, 1 omm wheel     1299 Oct  2 01:01 edits_0000000000013259297-0000000000013259312
-rw-----, 1 omm wheel      260 Oct  2 01:02 edits_0000000000013259313-0000000000013259316
-rw-----, 1 omm wheel      984 Oct  2 01:03 edits_0000000000013259317-0000000000013259328
-rw-----, 1 omm wheel      572 Oct  2 01:04 edits_0000000000013259329-0000000000013259336
-rw-----, 1 omm wheel      575 Oct  2 01:05 edits_0000000000013259337-0000000000013259344
-rw-----, 1 omm wheel      983 Oct  2 01:06 edits_0000000000013259345-0000000000013259356

```

3. If the edits files are not consecutive, check whether the edits files with the related sequence number exist in the data directories of other JournalNodes or NameNode. If the edits files can be found, copy a consecutive segment to the JournalNode.
4. In this way, all inconsecutive edits files are restored.
5. Restart the NameNode and check whether the restart is successful. If the fault persists, contact technical support.

# 8 Using HetuEngine

---

## 8.1 Using HetuEngine from Scratch

This section describes how to use HetuEngine to connect to the Hive data source and query database tables of the Hive data source of the cluster through HetuEngine.

### Prerequisites

- The HetuEngine and Hive services have been installed in the cluster and are running properly.
- If Kerberos authentication has been enabled for the cluster, you need to create a HetuEngine user and grant related permissions to the user in advance. For details, see [Creating a HetuEngine User](#). In addition, you need to configure the permissions to manage the databases, tables, and columns of the data source for the user using Ranger. For details, see [Adding a Ranger Access Permission Policy for HetuEngine](#).
- The cluster client has been installed, for example, in the `/opt/client` directory.

### Procedure

**Step 1** Create and start a HetuEngine compute instance.

1. Log in to FusionInsight Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
2. In the **Basic Information** area on the **Dashboard** tab page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
3. Click **Create Configuration** above the instance list. In the **Configure Instance** dialog box, configure parameters.
  - a. In the **Basic Configuration** area, set **Resource Queue** to the tenant queue associated with the user.
  - b. Configure parameters in the **Coordinator Container Resource Configuration**, **Worker Container Resource Configuration**, and **Advanced Configuration** areas based on the actual resource plan. For details about the parameter configuration, see [Creating HetuEngine Compute Instances](#) or retain the default values.

c. Select **Start Now** and wait until the instance configuration is complete.

**Step 2** Log in to the node where the HetuEngine client is installed and run the following command to switch to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** If the cluster is in security mode, run the following command to perform security authentication. If the cluster is in normal mode, skip this step.

```
kinit HetuEngine operation user
```

Example:

```
kinit hetu_test
```

Enter the password as prompted and change the password upon your first login.

**Step 5** Run the following command to log in to the catalog of the data source:

```
hetu-cli --catalog Data source name
```

For example, run the following command:

```
hetu-cli --catalog hive
```

#### NOTE

The default name of the Hive data source of the cluster is **hive**. If you need to connect to an external data source, configure the external data source on HSConsole by referring to [Configuring Data Sources](#).

```
java -Djava.security.auth.login.config=/opt/client/HetuEngine/hetuserver/conf/jaas.conf -Dzookeeper.sasl.clientconfig=Client -Dzookeeper.auth.type=kerberos -Djava.security.krb5.conf=/opt/client/KrbClient/kerberos/var/krb5kdc/krb5.conf -Djava.util.logging.config.file=/opt/client/HetuEngine/hetuserver/conf/hetuserver-client-logging.properties -jar /opt/client/HetuEngine/hetuserver/jars/hetu-cli-*.executable.jar --catalog hive --deployment-mode on_yarn --server https://10.112.17.189:24002,10.112.17.228:24002,10.112.17.150:24002?serviceDiscoveryMode=zooKeeper&zooKeeperNamespace=hsbroker --krb5-remote-service-name HTTP --krb5-config-path /opt/client/KrbClient/kerberos/var/krb5kdc/krb5.conf hetuengine>
```

**Step 6** Run the following command to view the database information:

```
show schemas;
```

```
Schema
-----
default
information_schema
(2 rows)
Query 20200730_080535_00002_ct2eg, FINISHED, 3 nodes
Splits: 36 total, 36 done (100.00%)
0:02 [2 rows, 35B] [0 rows/s, 15B/s]
```

```
----End
```

## 8.2 HetuEngine Permission Management

## 8.2.1 HetuEngine Permission Management Overview

HetuEngine supports permission control for clusters in security mode. For clusters in non-security mode, permission control is not performed.

In security mode, HetuEngine provides two permission control modes: Ranger and MetaStore. The Ranger mode is used by default.

The following table lists the differences between Ranger and MetaStore. Both Ranger and MetaStore support user, user group, and role authentication.

**Table 8-1** Differences between Ranger and MetaStore

Permission Control Mode	Permission Model	Supported Data Source	Description
Ranger	PBAC	Hive, HBase, Elasticsearch, GaussDB, HetuEngine, and ClickHouse	Row filtering, column masking, and fine-grained permission control are supported.
MetaStore	RBAC	Hive	-

## 8.2.2 Creating a HetuEngine User

### Scenarios

Before using the HetuEngine service in a security cluster, a cluster administrator needs to create a user and grant operation permissions to the user to meet service requirements.

HetuEngine users are classified into administrators and common users. The default HetuEngine administrator group is **hetuadmin**, and the user group of HetuEngine common users is **hetuuser**.

- Users associated with the **hetuadmin** user group can obtain the O&M administrator permissions on the HetuEngine HSConsole web UI and HetuEngine compute instance web UI.
- Users associated with the **hetuuser** user group can obtain the SQL execution permission.

If Ranger authentication is enabled and you need to configure the permissions to manage databases, tables, and columns of data sources for a user after it is created, see [Adding a Ranger Access Permission Policy for HetuEngine](#).

### Prerequisites

Before using the HetuEngine service, ensure that the tenant to be associated with the HetuEngine user has been planned and created. For details about how to create and use a tenant in an MRS cluster.

 NOTE

Common users can only perform operations on and view information about clusters of the tenants associated with them.

## Procedure

### Creating a HetuEngine administrator

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **System > Permission > User > Create**.
- Step 3** Enter a username, for example, **hetu\_admin**.
- Step 4** Set **User Type** to **Human-machine**.
- Step 5** Set **New Password** and **Confirm Password**.
- Step 6** In the **User Group** area, click **Add** to add the **hive**, **hetuadmin**, **hadoop**, **hetuuser**, and **yarnviewgroup** user groups for the user.
- Step 7** In the **Primary Group** drop-down list, select **hive** as the primary group.
- Step 8** In the **Role** area, click **Add** to assign the **default**, **System\_administrator**, and desired tenant role permissions to the user.
- Step 9** Click **OK**.

----End

### Creating a common HetuEngine user

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **System > Permission > User > Create**.
- Step 3** Enter a username, for example, **hetu\_test**.
- Step 4** Set **User Type** to **Human-machine**.
- Step 5** Set **New Password** and **Confirm Password**.
- Step 6** In the **User Group** area, click **Add** to add the **hetuuser** user group for the user.

 NOTE

- Ranger authentication is enabled for the HetuEngine service in the MRS cluster by default. HetuEngine common users only need to be associated with the **hetuuser** user group. If Ranger authentication is disabled, you must associate the user with the **hive** user group and set it as the primary group. Otherwise, the HetuEngine service may be unavailable.
- If Ranger authentication is enabled and you need to configure the permissions to manage databases, tables, and columns of data sources for a user after it is created, see [Adding a Ranger Access Permission Policy for HetuEngine](#).

**Step 7** In the **Role** area, click **Add** to assign the **default** or desired tenant role permissions to the user.

**Step 8** Click **OK**.

----End

## 8.2.3 HetuEngine Ranger-based Permission Control

Newly installed clusters use Ranger for authentication by default. Administrators can use Ranger to configure the permissions to manage databases, tables, and columns of data sources for HetuEngine users. For details, see [Adding a Ranger Access Permission Policy for HetuEngine](#).

If a cluster is upgraded from an earlier version or Ranger authentication is manually disabled for a cluster, enable Ranger authentication again by referring to [Enabling Ranger Authentication](#).

### Enabling Ranger Authentication

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster > Services > HetuEngine > More > Enable Ranger**.
- Step 3** Choose **Cluster > Services > HetuEngine > More > Restart Service**.
- Step 4** Restart the compute instance on HSConsole. For details, see [Managing a HetuEngine Compute Instance](#).

----End

## 8.2.4 HetuEngine MetaStore-based Permission Control

### 8.2.4.1 Overview

Constraints: This parameter applies only to the Hive data source.

When multiple HetuEngine clusters are deployed for collaborative computing, the metadata is centrally managed by the management cluster. Data computing is performed in all clusters. The user permission for accessing HetuEngine clusters must be configured in the management cluster. Users who belong to the Hive user group and share the same name are added to all compute instances.

### MetaStore Permission

Similar to Hive, HetuEngine is a data warehouse framework built on Hadoop, providing storage of structured data like SQL.

Permissions in a cluster must be assigned to roles which are bound to users or user groups. Users can obtain permissions only by binding a role or joining a group that is bound with a role.

### Permission Management

HetuEngine permission management is performed by the permission system to manage users' operations on the database, ensuring that different users can operate databases independently and securely. A user can operate another user's tables and databases only with the corresponding permissions. Otherwise, operations will be rejected.

HetuEngine permission management integrates the functions of Hive permission management. MetaStore service of Hive and the function of granting permissions on the web page are required to enable the HetuEngine permission management.

- Granting permissions on the web page: HetuEngine only supports granting permissions on the web page. On Manager, choose **System > Permission** to add or delete a user, user group, or a role, and to grant permissions or cancel permissions.
- Obtaining and judging a service: When the DDL and DML commands are received from the client, HetuEngine will obtain the client user's permissions on database information from MetaStore, and check whether the required permissions are included. If the required permissions have been obtained, the user's operations are allowed. If the permissions are not obtained, the user's operation will be rejected. After the MetaStore permissions are checked, ACL permission also needs to be checked on HDFS.

## HetuEngine Permission Model

If a user uses HetuEngine to perform SQL query, the user must be granted with permissions of HetuEngine databases and tables (include external tables and views). The complete permission model of HetuEngine consists of the metadata permission and HDFS file permission. Permissions required to use a database or a table are just one type of HetuEngine permission.

- Metadata permissions  
Metadata permissions are controlled at the metadata level. Similar to traditional relational databases, the HetuEngine database contains the CREATE and SELECT permissions. Tables and columns contain the SELECT, INSERT, UPDATE, and DELETE permissions. HetuEngine also supports the permissions of OWNERSHIP and ADMIN.
- Data file permissions (that is, HDFS file permissions)  
HetuEngine database and table files are stored in HDFS. The created databases or tables are saved in the **/user/hive/warehouse** directory of HDFS by default. The system automatically creates subdirectories named after database names and database table names. To access a database or a table, the corresponding file permissions (READ, WRITE, and EXECUTE) on HDFS are required.

To perform various operations on HetuEngine databases or tables, you need to associate the metadata permission and the HDFS file permission. For example, to query HetuEngine data tables, you need to associate the metadata permission SELECT with the READ and EXECUTE permissions on HDFS files.

To use the management function of FusionInsight Manager GUI to manage the permissions of HetuEngine databases and tables, you only need to configure the metadata permission, and the system will automatically associate and configure the HDFS file permission. In this way, operations on the interface are simplified, improving efficiency.

## HetuEngine Application Scenarios and Related Permissions

A user needs to join in the Hive group if a database is created using the HetuEngine service, and role authorization is not required. Users have all

permissions on the databases or tables created by themselves in Hive or HDFS. They can create tables, select, delete, insert, or update data, and grant permissions to other users to allow them to access the tables and corresponding HDFS directories and files.

A user can access the tables or database only with permissions. Permissions required for the user vary depending on different HetuEngine scenarios.

**Table 8-2** Typical HetuEngine scenarios and required permissions

Scenario	Required Permission
Using HetuEngine tables, columns, or databases	Permissions required in different scenarios are as follows: <ul style="list-style-type: none"> <li>• To create a table, the CREATE permission is required.</li> <li>• To query data, the SELECT permission is required.</li> <li>• To insert data, the INSERT permission is required.</li> </ul>

In some special HetuEngine scenarios, other permissions must be configured separately.

**Table 8-3** Typical HetuEngine authentication scenarios and required permissions

Scenario	Required Permission
Creating HetuEngine databases, tables, and foreign tables, or adding partitions to created tables or foreign tables when data files specified by Hive users are saved to other HDFS directories except <b>/user/hive/warehouse</b> .	The directory must exist, the client user must be the owner of the directory, and the user must have the READ, WRITE, and EXECUTE permissions on the directory. The user must have the READ and EXECUTE permissions of all the upper-layer directories of the directory.
Performing operations on all databases and tables in Hive	The user must be added to the <b>supergroup</b> user group, and be assigned the ADMIN permission.

## Enabling MetaStore Authentication

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Services > HetuEngine > More > Disable Ranger**.

**Step 3** Choose **Cluster > Services > HetuEngine > More > Restart Service**.

**Step 4** Restart the compute instance on HSConsole. For details, see [Managing a HetuEngine Compute Instance](#).

----End

### 8.2.4.2 Creating a HetuEngine Role

The system administrator can create and set a HetuEngine role on FusionInsight Manager. The HetuEngine role can be configured with the administrator permission or the permission of performing operations on the table data.

Creating a database with Hive requires users to join in the Hive group, without granting a role. Users have all permissions on the databases or tables created by themselves in Hive or HDFS. They can create tables, select, delete, insert, or update data, and grant permissions to other users to allow them to access the tables and corresponding HDFS directories and files. The created databases or tables are saved in the `/user/hive/warehouse` directory of HDFS by default.

#### Procedure

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **System > Permission > Role**.

**Step 3** Click **Create Role**, and set **Role Name** and **Description**.

**Step 4** In the **Configure Resource Permission** area, choose *Name of the desired cluster* > **Hive** and set role permissions. For details, see [Table 8-4](#).

- **Hive Admin Privilege:** Hive administrator permission.
- **Hive Read Write Privileges:** Hive data table management permission, which is the operation permission to set and manage the data of created tables.

#### NOTE

- Hive role management supports the administrator permission, and the permissions of accessing tables and views, without granting the database permission.
- The permissions of the Hive administrator do not include the permission to manage HDFS.
- If there are too many tables in the database or too many files in tables, the permission granting may last a while. For example, if a table contains 10,000 files, the permission granting lasts about 2 minutes.

**Table 8-4** Setting a role

Scenario	Role Authorization
Setting the permission to query a table of another user in the default database	<ol style="list-style-type: none"> <li>1. In the <b>View Name</b> area, click <b>Hive Read Write Privileges</b>.</li> <li>2. Click the name of the specified database in the database list. Tables in the database are displayed.</li> <li>3. In the <b>Permission</b> column of a specified table, choose <b>Select</b>.</li> </ol>

Scenario	Role Authorization
Setting the permission to import data to a table of another user in the default database	<ol style="list-style-type: none"> <li>1. In the <b>View Name</b> area, click <b>Hive Read Write Privileges</b>.</li> <li>2. Click the name of the specified database in the database list. Tables in the database are displayed.</li> <li>3. In the <b>Permission</b> column of the specified indexes, select <b>Delete</b> and <b>Insert</b>.</li> </ol>

**Step 5** Click **OK**. Return to the **Role** page.

----End

### 8.2.4.3 Configuring Permissions for Tables, Columns, and Databases

If a user needs to access HetuEngine tables or databases created by other users, the user needs to be granted with related permissions. HetuEngine supports permission control based on columns for strict permission control. If a user needs to access some columns in tables created by other users, the user must be granted the permission for columns. The following describes how to grant table, column, and database permissions to users by using the role management function of Manager.

#### Procedure

The operations for granting permissions on HetuEngine tables, columns, and databases are the same as those for Hive.

#### NOTE

- Any permission for a table in the database is automatically associated with the HDFS permission for the database directory to facilitate permission management. When any permission for a table is canceled, the system does not automatically cancel the HDFS permission for the database directory to ensure performance. In this case, users can only log in to the database and view table names.
- When the query permission on a database is added to or deleted from a role, the query permission on tables in the database is automatically added to or deleted from the role. This mechanism is inherited from Hive.
- In HetuEngine, the name of a column of the **struct** type data cannot contain special characters, that is, characters other than letters, digits, and underscores (\_). If the column name of the struct data type contains special characters, the column cannot be displayed on the FusionInsight Manager console when you grant permissions to roles on the **Role** page.

#### Concepts

**Table 8-5** describes the permission requirements when SQL statements are processed in HetuEngine.

**Table 8-5** Using HetuEngine tables, columns, or data

Scenario	Required Permission
DESCRIBE TABLE	Select
ANALYZE TABLE	Select and Insert
SHOW COLUMNS	Select
SHOW TABLE STATUS	Select
SHOW TABLE PROPERTIES	Select
SELECT	Select <b>NOTE</b> To perform the SELECT operation on a view, you must have the <b>Select</b> permission on the view and the tables corresponding to the view.
EXPLAIN	Select
CREATE VIEW	Select, Grant Of Select, and Create
CREATE TABLE	Create
ALTER TABLE ADD PARTITION	Insert
INSERT	Insert
INSERT OVERWRITE	Insert and Delete
ALTER TABLE DROP PARTITION	The table-level Alter and Delete, and column-level Select permissions need to be granted.
ALTER DATABASE	Hive Admin Privilege

## 8.2.5 Permission Principles and Constraints

### General Constraints

- Access data sources in the same cluster using HetuEngine  
 If Ranger authentication is enabled for HetuEngine, the PBAC permission policy of Ranger is used for authentication.  
 If Ranger authentication is disabled for HetuEngine, the RBAC permission policy of MetaStore is used for authentication.
- Access data sources in different clusters using HetuEngine  
 The permission policy is controlled by the permissions of the HetuEngine client and the data source. (In Hive scenarios, it depends on HDFS.)
- HetuEngine users do not support the **supergroup** user group.

- When querying a view, you only need to grant the select permission on the target view. When querying a join table using a view, you need to grant the select permission on the view and table.

 **NOTE**

When the permission control type of HetuEngine is changed, the HetuEngine service, including the HetuEngine compute instance running on Yarn, needs to be restarted.

## 8.3 Creating HetuEngine Compute Instances

### Scenario

This section describes how to create a HetuEngine compute instance. If you want to stop the cluster where compute instances are successfully created, you need to manually stop the compute instances first. If you want to use the compute instances after the cluster is restarted, you need to manually start them.

### Prerequisites

- You have created a user for accessing the HetuEngine web UI. For details, see [Creating a HetuEngine User](#).
- You have created a tenant in the cluster to be operated. For details about how to create a tenant. Ensure that the tenant has sufficient memory and CPUs when modifying the HetuEngine compute instance configuration.

 **NOTE**

You must use a leaf tenant when creating a HetuEngine compute instance. Yarn tasks can be submitted only to the queues of the leaf tenant.

### Procedure

- Step 1** Log in to FusionInsight Manager as a user who can access the HetuEngine web UI and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
- Step 3** Click **Create Configuration** above the instance list. In the **Configure Instance** dialog box, set parameters.
  1. Set parameters in the **Basic Configuration** area. For details about the parameters, see [Table 8-6](#).

**Table 8-6** Basic configuration

Parameter	Description	Example Value
Resource Queue	Resource queue of the instance. Only one compute instance can be created in a resource queue.	Select a queue from the <b>Resource Queue</b> drop-down list.
Instance Deployment Timeout Period (s)	Timeout interval for starting a compute instance by Yarn service deployment. The system starts timing when the compute instance is started. If the compute instance is still in the <b>Creating</b> or <b>Starting</b> state after the time specified by this parameter expires, the compute instance status is displayed as <b>Error</b> and the compute instance that is being created or started on Yarn is stopped.	300 The value ranges from 1 to 2147483647.

- Set parameters in the **Coordinator Container Resource Configuration** area. For details about the parameters, see [Table 8-7](#).

**Table 8-7** Parameters for configuring Coordinator container resources

Parameter	Description	Example Value
Container Memory (MB)	Memory size (MB) allocated by Yarn to a single container of the compute instance Coordinator	Default value: 5120 The value ranges from 1 to 2147483647.
vcore	Number of vCPUs (vCores) allocated by Yarn to a single container of the compute instance Coordinator	Default value: 1 The value ranges from 1 to 2147483647.
Quantity	Number of containers allocated by Yarn to the compute instance Coordinator	Default value: 2 The value ranges from 1 to 3.

Parameter	Description	Example Value
JVM	Log in to FusionInsight Manager and choose <b>Cluster &gt; Services &gt; HetuEngine &gt; Configurations</b> . On the <b>All Configurations</b> tab page, search for <b>extraJavaOptions</b> . The value of this parameter in the <b>coordinator.jvm.config</b> parameter file is the value of the JVM parameter.	-

3. Set parameters in the **Worker Container Resource Configuration** area. For details about the parameters, see [Table 8-8](#).

**Table 8-8** Parameters for configuring Worker container resources

Parameter	Description	Example Value
Container Memory (MB)	Memory size (MB) allocated by Yarn to a single container of the compute instance Worker	Default value: 10240 The value ranges from 1 to 2147483647.
vcore	Number of vCPUs (vCores) allocated by Yarn to a single container of the compute instance Worker	Default value: 1 The value ranges from 1 to 2147483647.
Quantity	Number of containers allocated by Yarn to the compute instance Worker	Default value: 2 The value ranges from 1 to 256.
JVM	Log in to FusionInsight Manager and choose <b>Cluster &gt; Services &gt; HetuEngine &gt; Configurations</b> . On the <b>All Configurations</b> tab page, search for <b>extraJavaOptions</b> . The value of this parameter in the <b>worker.jvm.config</b> parameter file is the value of the JVM parameter.	-

4. Set parameters in the **Advanced Configuration** area. For details about the parameters, see [Table 8-9](#).

**Table 8-9** Advanced configuration parameters

Parameter	Description	Example Value
Ratio of Query Memory	Ratio of the node query memory to the JVM memory. The default value is <b>0</b> . When this parameter is set to <b>0</b> , the calculation function is disabled.	0
Scaling	If auto scaling is enabled, you can increase or decrease the number of Workers without restarting the instance. However, the instance performance may deteriorate. For details about the parameters for enabling dynamic scaling, see <a href="#">Adjusting the Number of Worker Nodes</a> .	OFF

5. Configure **Custom Configuration** parameters. Choose **Advanced Configuration > Custom Configuration** and add custom parameters to the specified parameter file. Select the specified parameter file from the **Parameter File** drop-down list.
  - You can click **Add** to add custom configuration parameters.
  - You can click **Delete** to delete custom configuration parameters.
  - **resource-groups.json** takes effect only in the customized configuration of the Coordinator node. For details about the parameters for configuring resource groups, see [Table 8-10](#).

**Table 8-10** Resource pool group parameters

Parameter	Description	Example Value
resourcegroups	Resource management group configuration of the cluster. Select <b>resource-groups.json</b> from the drop-down list of the parameter file.	<pre>{   "rootGroups": [{     "name": "global",     "softMemoryLimit": "100%",     "hardConcurrencyLimit":     1000,     "maxQueued": 10000   }],   "selectors": [{     "group": "global"   }] }</pre>

 **NOTE**

For the **coordinator.config.properties**, **worker.config.properties**, **log.properties**, and **resource-groups.json** parameter files, if a user-defined parameter name already exists in the specified parameter file, the original parameter values in the parameter file are replaced with the customized parameter value. If the name of the custom parameter does not exist in the specified parameter file, the custom parameter is added to the specified parameter file.

6. Determine whether to start the instance immediately after the configuration is complete.
  - Select **Start Now** to start the instance immediately after the configuration is complete.
  - Deselect **Start Now** and manually start the instance after the configuration is complete.

**Step 4** Click **OK** and wait until the instance configuration is complete.

----End

## 8.4 Configuring Data Sources

### 8.4.1 Before You Start

HetuEngine supports quick joint query of multiple data sources and GUI-based data source configuration and management. You can quickly add a data source on the HSConsole page.

**Table 8-11** lists the data sources supported by HetuEngine of the current version.

**Table 8-11** List for connecting HetuEngine to data sources

HetuEngine Mode	Data Source	Data Source Mode	Supported Data Source Version
Security mode	Hive	Security mode	MRS 3.x, FusionInsight 6.5.1, and Hive in the current cluster
	HBase		MRS 3.x and FusionInsight 6.5.1
	Elasticsearch		Elasticsearch of the current cluster
	HetuEngine		MRS 3.x
	GaussDB		GaussDB 200 and GaussDB A 8.0.0
	Hudi		MRS 3.1.1 or later
	ClickHouse		MRS 3.1.1 or later
Normal mode	Hive	Normal mode	MRS 3.x, FusionInsight 6.5.1, and Hive in the current cluster

HetuEngine Mode	Data Source	Data Source Mode	Supported Data Source Version
	HBase		MRS 3.x and FusionInsight 6.5.1
	Elasticsearch		Elasticsearch of the current cluster
	Hudi		MRS 3.1.1 or later
	ClickHouse		MRS 3.1.1 or later
	GaussDB	Security mode	GaussDB 200 and GaussDB A 8.0.0

Operations such as adding, configuring, and deleting a HetuEngine data source takes effect dynamically without restarting the cluster.

A configured data source takes effect dynamically and you cannot disable this function. By default, the interval for a data source to dynamically take effect is 60 seconds. You can change the interval to a desired one by changing the value of **catalog.scanner-interval** in **coordinator.config.properties** and **worker.config.properties** by referring to [Step 3.5 in Creating HetuEngine Compute Instances](#). See the following example.

```
catalog.scanner-interval =120s
```

 **NOTE**

- The domain name of the data source cluster must be different from that of the HetuEngine cluster. In addition, two data sources with the same domain name cannot be connected to at the same time.
- The data source cluster and the HetuEngine cluster can communicate with each other.

## 8.4.2 Configuring a Hive Data Source

### 8.4.2.1 Configuring a Co-deployed Hive Data Source

#### Scenario

This section describes how to add a Hive data source of the same Hadoop cluster as HetuEngine on HSConsole.

Currently, HetuEngine supports data sources of the following traditional data formats: AVRO, TEXT, RCTEXT, Binary, ORC, Parquet, and SequenceFile.

#### Prerequisites

A HetuEngine compute instance has been created.

 **NOTE**

The HetuEngine service is interconnected to its co-deployed Hive data source by default during its installation. The data source name is **hive** and cannot be deleted. Some default configurations cannot be modified. You need to restart the HetuEngine service to automatically synchronize these unmodifiable configurations once they are updated.

**Procedure**

- Step 1** Log in to FusionInsight Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**.
- Step 2** In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**.
- Step 3** On HSConsole, choose **Data Source**. Locate the row that contains the target Hive data source, click **Edit** in the **Operation** column, and modify the configurations. The following table describes data source configurations that can be modified.

Parameter	Description	Example Value
Description	Description of the data source. The value can contain only letters, digits, commas (,), periods (.), underscores (_), spaces, and line breaks.	-
Enable Data Source Authentication	Whether to use the permission policy of the Hive data source for authentication. If Ranger is disabled for the HetuEngine service, select <b>Yes</b> . If Ranger is enabled, select <b>No</b> .	No
Metastore URL	Value of <b>hive.metastore.uris</b> in <b>hive-site.xml</b> on the data source client. When the Hive MetaStore instance changes, you need to manually update this value.	thrift:// 192.168.1.1:21088, thrift:// 192.168.1.2:21088
Enable Connection Pool	Whether to enable the connection pool when accessing Hive MetaStore. The default value is <b>Yes</b>	Yes
Maximum Connections	Maximum number of connections in the connection pool when accessing Hive MetaStore.	50 (Value range: 0-200)

- Step 4** (Optional) If you need to add **Custom Configuration**, complete the configurations by referring to [Step 6.7](#) and click **OK** to save the configurations.

----End

## 8.4.2.2 Configuring a Traditional Data Source

### Scenario

This section describes how to add a Hive data source on HSConsole.

Currently, HetuEngine supports data sources of the following traditional data formats: AVRO, TEXT, RCTEXT, Binary, ORC, Parquet, and SequenceFile.

### Prerequisites

- The domain name of the cluster where the data source is located must be different from the HetuEngine cluster domain name.
- The cluster where the data source is located and the HetuEngine cluster nodes can communicate with each other.
- A HetuEngine compute instance has been created.

### Procedure

**Step 1** Obtain the **hdfs-site.xml** and **core-site.xml** configuration files of the Hive data source cluster.

1. Log in to FusionInsight Manager of the cluster where the Hive data source is located.
2. Choose **Cluster > Dashboard**.
3. Choose **More > Download Client** and download the client file to the local computer.
4. Decompress the downloaded client file package and obtain the **core-site.xml** and **hdfs-site.xml** files in the **FusionInsight\_Cluster\_1\_Services\_ClientConfig/HDFS/config** directory.
5. Check whether the **core-site.xml** file contains the **fs.trash.interval** configuration item. If not, add the following configuration items:

```
<property>
<name>fs.trash.interval</name>
<value>2880</value>
</property>
```
6. Change the value of **dfs.client.failover.proxy.provider.hacluster** in the **hdfs-site.xml** file to **org.apache.hadoop.hdfs.server.namenode.ha.ConfiguredFailoverProxyProvider**.

```
<property>
<name>dfs.client.failover.proxy.provider.hacluster</name>
<value>org.apache.hadoop.hdfs.server.namenode.ha.ConfiguredFailoverProxyProvider</value>
</property>
```

  - If HDFS has multiple NameServices, change the values of **dfs.client.failover.proxy.provider.NameService name** for multiple NameServices in the **hdfs-site.xml** file to **org.apache.hadoop.hdfs.server.namenode.ha.ConfiguredFailoverProxyProvider**.
  - In addition, if the **hdfs-site.xml** file references the host name of a non-HetuEngine cluster node, you need to add the mapping between the referenced host name and the corresponding IP address to the **/etc/hosts** file of each HetuEngine cluster node. Otherwise, HetuEngine cannot connect to the node that is not in this cluster based on the host name.

---

**NOTICE**

If the Hive data source to be interconnected is in the same Hadoop cluster with HetuEngine, you can log in to the HDFS client and run the following commands to obtain the **hdfs-site.xml** and **core-site.xml** configuration files. For details, see [Using the HDFS Client](#).

```
hdfs dfs -get /user/hetuserver/fiber/restcatalog/hive/core-site.xml
hdfs dfs -get /user/hetuserver/fiber/restcatalog/hive/hdfs-site.xml
```

---

**Step 2** Obtain the **user.keytab** and **krb5.conf** files of the proxy user of the Hive data source.

1. Log in to FusionInsight Manager of the cluster where the Hive data source is located.
2. Choose **System > Permission > User**.
3. Locate the row that contains the target data source user, click **More** in the **Operation** column, and select **Download Authentication Credential**.
4. Decompress the downloaded package to obtain the **user.keytab** and **krb5.conf** files.

 **NOTE**

The proxy user of the Hive data source must be associated with at least the **hive** user group.

**Step 3** Obtain the MetaStore URL and the Principal of the server.

1. Decompress the client package of the cluster where the Hive data source is located and obtain the **hive-site.xml** file from the **FusionInsight\_Cluster\_1\_Services\_ClientConfig/Hive/config** directory.
2. Open the **hive-site.xml** file and search for **hive.metastore.uris**. The value of **hive.metastore.uris** is the value of MetaStore URL. Search for **hive.server2.authentication.kerberos.principal**. The value of **hive.server2.authentication.kerberos.principal** is the value of Principal on the server.

**Step 4** Log in to FusionInsight Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.

**Step 5** In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.

**Step 6** Choose **Data Source** and click **Add Data Source**. Configure parameters on the **Add Data Source** page.

1. Configure parameters in the **Basic Information** area. For details, see [Table 8-12](#).

**Table 8-12** Basic Information

Parameter	Description	Example Value
Name	Name of the data source to be connected. The value can contain only letters, digits, and underscores (_) and must start with a letter.	hive_1
Data Source Type	Type of the data source to be connected. Select <b>Hive</b> .	Hive
Mode	Mode of the current cluster. The default value is <b>Security Mode</b> .	-
Description	Description of the data source. The value can contain only letters, digits, commas (,), periods (.), underscores (_), spaces, and line breaks.	-

2. Configure parameters in the **Hive Configuration** area. For details, see [Table 8-13](#).

**Table 8-13** Hive Configuration

Parameter	Description	Example Value
Driver	The default value is <b>fi-hive-hadoop</b> .	fi-hive-hadoop
hdfs-site File	Select the <b>hdfs-site.xml</b> configuration file obtained in <a href="#">Step 1</a> . The file name is fixed.	-
core-site File	Select the <b>core-site.xml</b> configuration file obtained in <a href="#">Step 1</a> . The file name is fixed.	-
krb5 File	Configure this parameter when the security mode is enabled.  It is the configuration file used for Kerberos authentication. Select the <b>krb5.conf</b> file obtained in <a href="#">Step 2</a> .	krb5.conf

Parameter	Description	Example Value
Enable Data Source Authentication	Whether to use the permission policy of the Hive data source for authentication.  If Ranger is disabled for the HetuEngine service, select <b>Yes</b> . If Ranger is enabled, select <b>No</b> .	No

3. Configure parameters in the **MetaStore Configuration** area. For details, see [Table 8-14](#).

**Table 8-14** MetaStore Configuration

Parameter	Description	Example Value
Metastore URL	URL of the MetaStore of the data source. For details, see <a href="#">Step 3</a> .	thrift:// 10.92.8.42:21088,thrift:// 10.92.8.43:21088,thrift:// 10.92.8.44:21088
Security Authentication Mechanism	After the security mode is enabled, the default value is <b>KERBEROS</b> .	KERBEROS
Server Principal	Configure this parameter when the security mode is enabled.  It specifies the username with domain name used by meta to access MetaStore. For details, see <a href="#">Step 3</a> .	hive/ hadoop.hadoop.com@H ADOOP.COM

Parameter	Description	Example Value
Client Principal	<p>Configure this parameter when the security mode is enabled.</p> <p>The parameter format is as follows: <i>Username for accessing MetaStore@domain name (uppercase).COM</i>. <i>Username for accessing MetaStore</i> is the user to which the <b>user.keytab</b> file obtained in <a href="#">Step 2</a> belongs.</p>	admintest@HADOOP.COM
Keytab File	<p>Configure this parameter when the security mode is enabled.</p> <p>It specifies the keytab credential file of the MetaStore user name. The file name is fixed. Select the <b>user.keytab</b> file obtained in <a href="#">Step 2</a>.</p>	user.keytab

4. Configure parameters in the **Connection Pool Configuration** area. For details, see [Table 8-15](#).

**Table 8-15** Connection Pool Configuration

Parameter	Description	Example Value
Enable Connection Pool	Whether to enable the connection pool when accessing Hive MetaStore.	Yes/No
Maximum Connections	Maximum number of connections in the connection pool when accessing Hive MetaStore.	50

5. Configure parameters in **Hive User Information Configuration**. For details, see [Table 8-16](#).

**Hive User Information Configuration** and **HetuEngine-Hive User Mapping Configuration** must be used together. When HetuEngine is connected to the Hive data source, user mapping enables HetuEngine users to have the same

permissions of the mapped Hive data source user. Multiple HetuEngine users can correspond to one Hive user.

**Table 8-16** Hive User Information Configuration

Parameter	Description	Example Value
Data Source User	Data source user information. The value can contain only letters, digits, underscores (_), hyphens (-), and periods (.), and must start with a letter or underscore (_). The minimum length is 2 characters and the maximum length is 100 characters.	If the data source user is set to <b>hiveuser1</b> , a HetuEngine user mapped to <b>hiveuser1</b> must exist. For example, create <b>hetuuser1</b> and map it to <b>hiveuser1</b> .
Keytab File	Obtain the authentication credential of the user corresponding to the data source.	hiveuser1.keytab

6. Configure parameters in the **HetuEngine-Hive User Mapping Configuration** area. For details, see [Table 8-17](#).

**Table 8-17** HetuEngine-Hive User Mapping Configuration

Parameter	Description	Example Value
HetuEngine User	HetuEngine user information. The value can contain only letters, digits, underscores (_), hyphens (-), and periods (.), and must start with a letter or underscore (_). The minimum length is 2 characters and the maximum length is 100 characters.	hetuuser1

Parameter	Description	Example Value
Data Source User	Data source user information. The value can contain only letters, digits, underscores (_), hyphens (-), and periods (.), and must start with a letter or underscore (_). The minimum length is 2 characters and the maximum length is 100 characters.	<b>hiveuser1</b> (data source user configured in <a href="#">Table 8-16</a> )

7. Modify custom configurations.
  - You can click **Add** to add custom configuration parameters by referring to [Table 8-18](#).

**Table 8-18** Custom parameters

Parameter	Description	Example Value
hive.metastore.connection.pool.maxTotal	Maximum number of connections in the connection pool.	50 (Value range: 0-200)
hive.metastore.connection.pool.maxIdle	Maximum number of idle threads in the connection pool. When the number of idle threads reaches the maximum number, new threads are not released. Default value: <b>10</b> .	10 (The value ranges from 0 to 200 and cannot exceed the maximum number of connections.)
hive.metastore.connection.pool.minIdle	Minimum number of idle threads in the connection pool. When the number of idle threads reaches the minimum number, the thread pool does not create new threads. Default value: <b>10</b> .	10 (The value ranges from 0 to 200 and cannot exceed the value of <b>hive.metastore.connection.pool.maxIdle</b> .)

- You can click **Delete** to delete custom configuration parameters.

 NOTE

- You can add prefixes **coordinator.** and **worker.** to the preceding custom configuration items to configure coordinators and workers, respectively. For example, if **worker.hive.metastore.connection.pool.maxTotal** is set to **50**, a maximum number of 50 connections are allowed for workers to access Hive MetaStore. If no prefix is added, the configuration item is valid for both coordinators and workers.
- By default, the maximum number of connections for coordinators to access Hive MetaStore is 5 and the maximum and minimum numbers of idle data source connections are both 10. The maximum number of connections for workers to access Hive MetaStore is 20, the maximum and minimum numbers of idle data source connections are both 0.

8. Click **OK**.

**Step 7** Log in to the node where the cluster client is located and run the following commands to switch to the client installation directory and authenticate the user:

```
cd /opt/client
```

```
source bigdata_env
```

```
kinit User performing HetuEngine operations (If the cluster is in normal mode, skip this step.)
```

**Step 8** Run the following command to log in to the catalog of the data source:

```
hetu-cli --catalog Data source name --schema default
```

For example, run the following command:

```
hetu-cli --catalog hive_1 --schema default
```

**Step 9** Run the following command to view the database table:

```
show tables;
```

```
Table
-----
hivetb
(1 rows)

Query 20210730_084524_00023_u3sri@default@HetuEngine, FINISHED, 3 nodes
Splits: 36 total, 36 done (100.00%)
0:00 [2 rows, 47B] [7 rows/s, 167B/s]
```

```
----End
```

### 8.4.2.3 Configuring a Hudi Data Source

#### Scenario

HetuEngine can be connected to the Hudi data source of the cluster of MRS 3.1.1 or later.

 NOTE

HetuEngine does not support the reading of Hudi bootstrap tables.

## Prerequisites

- You have created the proxy user of the Hudi data source. The proxy user is a human-machine user and must belong to the **hive** group.
- You have created a HetuEngine administrator by referring to [Creating a HetuEngine User](#).

## Procedure

- Step 1** Perform [Step 1](#) to [Step 6.7](#) to configure a traditional data source by referring to [Configuring a Traditional Data Source](#).
- Step 2** In the **Custom Configuration** area, add a custom parameter, as listed in [Table 8-19](#).

**Table 8-19** Custom configuration parameter for Hudi data

Custom Parameter Name	Value
hive.parquet.use-column-names	true

- Step 3** Click **OK**.
- End

## 8.4.3 Configuring an HBase Data Source

### Scenario

This section describes how to add an HBase data source on HSConsole.

### Prerequisites

- The domain name of the cluster where the data source is located must be different from the HetuEngine cluster domain name.
- The cluster where the data source is located and the HetuEngine cluster nodes can communicate with each other.
- A HetuEngine compute instance has been created.
- The SSL communication encryption configuration of ZooKeeper in the cluster where the data source is located must be the same as that of ZooKeeper in the cluster where HetuEngine is located.

#### NOTE

To check whether SSL communication encryption is enabled, log in to FusionInsight Manager, choose **Cluster > Services > ZooKeeper > Configurations > All Configurations**, and enter **ssl.enabled** in the search box. If the value of **ssl.enabled** is **true**, SSL communication encryption is enabled. If the value is **false**, SSL communication encryption is disabled.

## Procedure

**Step 1** Obtain the **hbase-site.xml**, **hdfs-site.xml**, and **core-site.xml** configuration files of the HBase data source.

1. Log in to FusionInsight Manager of the cluster where the HBase data source is located.
2. Choose **Cluster > Dashboard**.
3. Choose **More > Download Client** and download the client file as prompted.
4. Decompress the downloaded client file package and obtain the **hbase-site.xml**, **core-site.xml**, and **hdfs-site.xml** files in the **FusionInsight\_Cluster\_1\_Services\_ClientConfig/HBase/config** directory.
5. If **hbase.rpc.client.impl** exists in the **hbase-site.xml** file, change the value of **hbase.rpc.client.impl** to **org.apache.hadoop.hbase.ipc.RpcClientImpl**.

```
<property>  
<name>hbase.rpc.client.impl</name>  
<value>org.apache.hadoop.hbase.ipc.RpcClientImpl</value>  
</property>
```

### NOTE

In addition, if the **hdfs-site.xml** and **hbase-site.xml** files reference the host name of a non-HetuEngine cluster node, you need to add the mapping between the referenced host name and the corresponding IP address to the **/etc/hosts** file of each node in the HetuEngine cluster. Otherwise, HetuEngine cannot connect to the node that is not in this cluster based on the host name.

**Step 2** Obtain the **user.keytab** and **krb5.conf** files of the proxy user of the HBase data source.

1. Log in to FusionInsight Manager of the cluster where the HBase data source is located.
2. Choose **System > Permission > User**.
3. Locate the row that contains the target data source user, click **More** in the **Operation** column, and select **Download Authentication Credential**.
4. Decompress the downloaded package to obtain the **user.keytab** and **krb5.conf** files.

### NOTE

The proxy user of the data source must have the permission to perform HBase operations.

**Step 3** Log in to FusionInsight Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.

**Step 4** In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.

**Step 5** Choose **Data Source**.

**Step 6** Click **Add Data Source**. Configure parameters on the **Add Data Source** page.

1. Configure **Basic Information**. For details, see [Table 8-20](#).

**Table 8-20** Basic Information

Parameter	Description	Example Value
Name	Name of the data source to be connected. The value can contain only letters, digits, and underscores (_) and must start with a letter.	hbase_1
Data Source Type	Type of the data source to be connected. Select <b>HBase</b> .	HBase
Description	Description of the data source. The value can contain only letters, digits, commas (,), periods (.), underscores (_), spaces, and line breaks.	-

2. Configure parameters in the **HBase Configuration** area. For details, see [Table 8-21](#).

**Table 8-21** HBase Configuration

Parameter	Description	Example Value
Driver	The default value is <b>hbase-connector</b> .	hbase-connector

Parameter	Description	Example Value
ZooKeeper Quorum Address	<p>Service IP addresses of all quorumpeer instances of the ZooKeeper service for the data source. If the ZooKeeper service of the data source uses IPv6, you need to specify the client port number in the ZooKeeper Quorum address.</p> <p>Log in to FusionInsight Manager, choose <b>Cluster &gt; Services &gt; ZooKeeper &gt; Instance</b>, and view the IP addresses of all the hosts housing the quorumpeer instances.</p>	<ul style="list-style-type: none"> <li>- IPv4: 10.0.136.132,10.0.136.133,10.0.136.134</li> <li>- IPv6: [0.0.0.0.0.0.0.0]:24002</li> </ul>
ZooKeeper Client Port Number	<p>Port number of the ZooKeeper client.</p> <p>Log in to FusionInsight Manager and choose <b>Cluster &gt; Service &gt; ZooKeeper</b>. On the <b>Configurations</b> tab page, check the value of <b>clientPort</b>.</p>	2181
HBase RPC Communication Protection	<p>Set this parameter based on the value of <b>hbase.rpc.protection</b> in the <b>hbase-site.xml</b> file obtained in <a href="#">Step 1</a>.</p> <ul style="list-style-type: none"> <li>- If the value is <b>authentication</b>, set this parameter to <b>No</b>.</li> <li>- If the value is <b>privacy</b>, set this parameter to <b>Yes</b>.</li> </ul>	No
Security Authentication Mechanism	<p>After the security mode is enabled, the default value is <b>KERBEROS</b>.</p>	KERBEROS

Parameter	Description	Example Value
Principal	Configure this parameter when the security authentication mechanism is enabled. Set the parameter to the user to whom the <b>user.keytab</b> file obtained in <a href="#">Step 2</a> belongs.	user_hbase@HADOOP2.COM
Keytab File	Configure this parameter when the security mode is enabled. It specifies the security authentication key. Select the <b>user.keytab</b> file obtained in <a href="#">Step 2</a> .	user.keytab
krb5 File	Configure this parameter when the security mode is enabled. It is the configuration file used for Kerberos authentication. Select the <b>krb5.conf</b> file obtained in <a href="#">Step 2</a> .	krb5.conf
hbase-site File	Configure this parameter when the security mode is enabled. It is the configuration file required for connecting to HDFS. Select the <b>hbase-site.xml</b> file obtained in <a href="#">Step 1</a> .	hbase-site.xml
core-site File	Configure this parameter when the security mode is enabled. This file is required for connecting to HDFS. Select the <b>core-site.xml</b> file obtained in <a href="#">Step 1</a> .	core-site.xml

Parameter	Description	Example Value
hdfs-site File	Configure this parameter when the security mode is enabled. This file is required for connecting to HDFS. Select the <b>hdfs-site.xml</b> file obtained in <a href="#">Step 1</a> .	hdfs-site.xml

3. Modify custom configurations.
  - You can click **Add** to add custom configuration parameters.
  - You can click **Delete** to delete custom configuration parameters.
4. Click **OK**.

**Step 7** Log in to the node where the cluster client is located and run the following commands to switch to the client installation directory and authenticate the user:

```
cd /opt/client
```

```
source bigdata_env
```

**kinit** *User performing HetuEngine operations* (If the cluster is in normal mode, skip this step.)

**Step 8** Run the following command to log in to the catalog of the data source:

```
hetu-cli --catalog Data source name --schema default
```

For example, run the following command:

```
hetu-cli --catalog hbase_1 --schema default
```

```
----End
```

## 8.4.4 Configuring a GaussDB Data Source

### Scenario

This section describes how to add a GaussDB JDBC data source on the HSConsole page.

### Prerequisites

- The domain name of the cluster where the data source is located must be different from the HetuEngine cluster domain name.
- The cluster where the data source is located and the HetuEngine cluster nodes can communicate with each other.
- A HetuEngine compute instance has been created.

## Procedure

- Step 1** Log in to FusionInsight Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
- Step 3** Choose **Data Source**.
- Step 4** Click **Add Data Source**. Configure parameters on the **Add Data Source** page.
  1. Configure **Basic Information**. For details, see [Table 8-22](#).

**Table 8-22** Basic Information

Parameter	Description	Example Value
Name	Name of the data source to be connected. The value can contain only letters, digits, and underscores (_) and must start with a letter.	gaussdb_1
Data Source Type	Type of the data source to be connected. Choose <b>JDBC &gt; GAUSSDB-A</b> .	GAUSSDB-A
Description	Description of the data source. The value can contain only letters, digits, commas (,), periods (.), underscores (_), spaces, and line breaks.	-

2. Configure parameters in the **GAUSSDB-A Configuration** area. For details, see [Table 8-23](#).

**Table 8-23** GAUSSDB-A Configuration

Parameter	Description	Example Value
Driver	The default value is <b>gaussdba</b> .	gaussdba

Parameter	Description	Example Value
JDBC URL	JDBC URL for connecting to GaussDB A. The format is as follows: <b>jdbc:postgresql://CN service IP address:Port number/Database name</b>	jdbc:postgresql://10.0.136.1:25308/postgres
Username	Username for connecting to the GaussDB data source.	Change the value based on the username being connected with the data source.
Password	Password for connecting to the GaussDB data source.	Change the value based on the username and password for connecting to the data source.
GaussDB User Information Configuration	Configure multiple GaussDB usernames and passwords in the format of <b>dataSourceUser</b> and <b>password</b> key-value pairs.	-
HetuEngine-GaussDB User Mapping Configuration	Multiple HetuEngine accounts are configured in the format of <b>hetuUser</b> and <b>dataSourceUser</b> key-value pairs, corresponding to one of the users configured in the <b>GaussDB User Information Configuration</b> area. When different HetuEngine users are used to access GaussDB, different GaussDB usernames and passwords can be used.	-

3. Configure the GaussDB data source user information. For details, see [Table 8-24](#).

**GaussDB User Information Configuration** and **HetuEngine-GaussDB User Mapping Configuration** must be used together. When HetuEngine is

connected to the GaussDB data source, HetuEngine users can have the same permissions of the mapped GaussDB data source user through mapping. Multiple HetuEngine users can correspond to one GaussDB user.

**Table 8-24** GaussDB User Information Configuration

Parameter	Description	Example Value
Data Source User	Data Source User The value can contain only letters, digits, underscores (_), hyphens (-), and periods (.), and must start with a letter or underscore (_). The minimum length is 2 characters and the maximum length is 100 characters.	If the data source user is set to <b>gaussuser1</b> , a HetuEngine user mapped to <b>gaussuser1</b> must exist. For example, create <b>hetuuser1</b> and map it to <b>gaussuser1</b> .
Password	User authentication password of the corresponding data source.	-

4. Configure the HetuEngine-GaussDB user mapping. For details, see [Table 8-25](#).

**Table 8-25** HetuEngine-GaussDB User Mapping Configuration

Parameter	Description	Example Value
HetuEngine User	HetuEngine username. The value can contain only letters, digits, underscores (_), hyphens (-), and periods (.), and must start with a letter or underscore (_). The minimum length is 2 characters and the maximum length is 100 characters.	hetuuser1
Data Source User	Data source user. The value can contain only letters, digits, underscores (_), hyphens (-), and periods (.), and must start with a letter or underscore (_). The minimum length is 2 characters and the maximum length is 100 characters.	<b>gaussuser1</b> (data source user configured in <a href="#">Table 8-24</a> )

5. Modify custom configurations.
  - You can click **Add** to add custom configuration parameters. Configure custom parameters of the GaussDB data source. For details, see [Table 8-26](#).

**Table 8-26** Custom parameters of the GaussDB data source

Parameter	Description	Example Value
use-connection-pool	Whether to use the JDBC connection pool.	true
jdbc.connection.pool.maxTotal	Maximum number of connections in the JDBC connection pool.	8
jdbc.connection.pool.maxIdle	Maximum number of idle connections in the JDBC connection pool.	8
jdbc.connection.pool.minIdle	Minimum number of idle connections in the JDBC connection pool.	0
jdbc.pushdown-enabled	<p><b>true:</b> SQL statements can be pushed down to the data source for execution.</p> <p><b>false:</b> SQL statements are not pushed down to the data source for execution. As a result, more network and computing resources are consumed.</p>	true

Parameter	Description	Example Value
jdbc.pushdown-module	<p>The push-down function should be enabled in advance.</p> <ul style="list-style-type: none"> <li>▪ <b>DEFAULT:</b> No operator is pushed down.</li> <li>▪ <b>BASE_PUSHDOWN:</b> Only operators such as Filter, Aggregation, Limit, TopN, and Projection are pushed down.</li> <li>▪ <b>FULL_PUSHDOWN:</b> All supported operators are pushed down.</li> </ul>	DEFAULT
source-encoding	GaussDB data source encoding mode.	UTF-8
multiple-cnn-enabled	<p>Whether to use the GaussDB multi-CN configuration. To use it, ensure that the JDBC connection pool is disabled and the JDBC URL format is as follows:</p> <pre>jdbc:postgresql:// host:port/ database,jdbc:postgresql://host:port/ database,jdbc:postgresql://host:port/ database.</pre>	false

Parameter	Description	Example Value
parallel-read-enabled	<p>Whether to use the parallel data read function.</p> <p>If the parallel data read function is enabled, the actual number of splits is determined based on the node distribution and the value of <b>max-splits</b>.</p> <p>Multiple connections to the data source will be created for parallel read operations. The dependent data source should support the load.</p>	false
split-type	<p>Type of the parallel data read function.</p> <ul style="list-style-type: none"> <li>▪ <b>NODE</b>: The degree of parallelism (DOP) is categorized based on the GaussDB data source DataNodes.</li> <li>▪ <b>PARTITION</b>: The DOP is categorized based on table partitions.</li> <li>▪ <b>INDEX</b>: The DOP is categorized based on table indexes.</li> </ul>	NODE
max-splits	Maximum degree of parallelism.	5
use-copymanager-for-insert	Whether to use CopyManager for batch import.	false

Parameter	Description	Example Value
unsupported-type-handling	<p>If the connector does not support the data of a certain type, convert it to VARCHAR.</p> <ul style="list-style-type: none"> <li>▪ After the <b>CONVERT_TO_VARCHAR</b> parameter is configured, the data of BIT, VARYING, CIDR, MACADDR, INET, OID, REGTYPE, REGCONFIG and POINT types are converted to the varchar type during query and data of these types can only be read.</li> <li>▪ The default value is IGNORE, indicating that unsupported types will be not displayed in the result.</li> </ul>	CONVERT_TO_VARCHAR
max-bytes-in-a-batch-for-copymanager-in-mb	Maximum volume of data imported by CopyManager in a batch, in MB.	10

- You can click **Delete** to delete custom configuration parameters.
6. Click **OK**.

#### NOTICE

- The UPDATE and DELETE syntaxes do not support filtering clauses containing cross-catalog conditions, for example, **UPDATE mppdb.table SET column1=value WHERE column2 IN (SELECT column2 from hive.table)**.
- To use the DELETE syntax, set **jdbc.pushdown-enabled** to **true** and **unsupported-type-handling** to **CONVERT\_TO\_VARCHAR**.
- The DELETE syntax does not support filtering clauses containing subqueries, for example, **DELETE FROM mppdb.table WHERE column IN (SELECT column FROM mppdb.table1)**.
- HetuEngine supports a maximum precision of 38 digits for GaussDB data sources of the NUMBER data type

----End

## 8.4.5 Configuring a HetuEngine Data Source

### Scenario

This section describes how to add another HetuEngine data source on the HSConsole page for a cluster in security mode.

Currently, the following data sources are supported: boolean, tinyint, smallint, int, bigint, real, double, decimal, varchar, char, date, timestamp, array, map, time with timezone, timestamp with time zone, and Time.

### Procedure

- Step 1** Obtain the **user.keytab** file of the proxy user of the HetuEngine cluster in a remote domain.
  1. Log in to FusionInsight Manager of the HetuEngine cluster in the remote domain.
  2. Choose **System > Permission > User**.
  3. Locate the row that contains the target data source user, click **More** in the **Operation** column, and select **Download Authentication Credential**.
  4. The **user.keytab** file extracted from the downloaded file is the user credential file.
- Step 2** Log in to FusionInsight Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
- Step 3** In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
- Step 4** Choose **Data Source** and click **Add Data Source**. Configure parameters on the **Add Data Source** page.
  1. Configure **Basic Information**. For details, see [Table 8-27](#).

**Table 8-27** Basic Information

Parameter	Description	Example Value
Name	Name of the data source to be connected. The value can contain only letters, digits, and underscores (_) and must start with a letter. If the data source name contains uppercase letters, the background automatically converts the uppercase letters to lowercase letters during storage.	hetu_1
Data Source Type	Type of the data source to be connected. Select <b>HetuEngine</b> .	HetuEngine
Mode	Mode of the current cluster. The security mode is used by default.	Security Mode
Description	Description of the data source. The value can contain only letters, digits, commas (,), periods (.), underscores (_), spaces, and line breaks.	-

2. Configure parameters in the **HetuEngine Configuration** area. For details, see [Table 8-28](#).

**Table 8-28** HetuEngine Configuration

Parameter	Description	Example Value
Driver	The default value is <b>hsfabric-initial</b> .	hsfabric-initial
Username	Configure this parameter when the security mode is enabled. It specifies the user who accesses the remote HetuEngine. Set the parameter to the user to whom the <b>user.keytab</b> file obtained in <a href="#">Step 1</a> belongs.	hetu_test
Keytab File	Configure this parameter when the security mode is enabled. This is the Keytab file of the user who accesses the remote DataCenter. Select the <b>user.keytab</b> file obtained in <a href="#">Step 1</a> .	user.keytab

Parameter	Description	Example Value
Two Way Transmission	<p>This parameter indicates whether to enable bidirectional transmission for cross-domain data transmission. The default value is <b>Yes</b>.</p> <ul style="list-style-type: none"> <li>- <b>Yes:</b> Two-way transmission: Requests are forwarded to the remote HSFabric through the local HSFabric. If two-way transmission is enabled, the local HSFabric address must be configured.</li> <li>- <b>No:</b> Unidirectional transmission: Requests are directly sent to the remote HSFabric.</li> </ul>	Yes
Local Configuration	<p>Host IP address and port number of the HSFabric instance that is responsible for external communication of the HetuEngine service in the local MRS cluster.</p> <ol style="list-style-type: none"> <li>1. Log in to FusionInsight Manager of the local cluster, choose <b>Cluster &gt; Services &gt; HetuEngine &gt; Instance</b>, and check the service IP address of the HSFabric.</li> <li>2. Click <b>HSFabric</b>, choose <b>Instance Configuration</b>, and check the value of <b>server.port</b>. The default value is <b>29900</b>.</li> </ol>	192.162.157.32:29900
Remote Address	<p>Host IP address and port number of the HSFabric instance that is responsible for external communication of the HetuEngine service in the remote MRS cluster.</p> <ol style="list-style-type: none"> <li>1. Log in to FusionInsight Manager of the remote cluster, choose <b>Cluster &gt; Services &gt; HetuEngine &gt; Instance</b>, and check the service IP address of the HSFabric.</li> <li>2. Click <b>HSFabric</b>, choose <b>Instance Configuration</b>, and check the value of <b>server.port</b>. The default value is <b>29900</b>.</li> </ol>	192.168.1.1:29900
Region	<p>Region to which the current request initiator belongs. The value can contain only digits and underscores (_).</p>	0755_01

Parameter	Description	Example Value
Receiving Data Timeout (s)	Timeout interval for receiving data, in seconds.	60
Total Task Timeout (s)	Total timeout duration for executing a cross-domain task, in seconds.	300
Tasks Used by Worker Nodes	Number of tasks used by each worker node to receive data.	5
Data Compression	<ul style="list-style-type: none"> <li>- <b>Yes</b>: Data compression is enabled.</li> <li>- <b>No</b>: Data compression is disabled.</li> </ul>	Yes

3. Modify custom configurations.
  - You can click **Add** to add custom configuration parameters. Configure custom parameters of the HetuEngine data source. For details, see [Table 8-29](#).

**Table 8-29** Custom parameters of the HetuEngine data source

Parameter	Description	Example Value
hsfabric.health.check.time	Interval for checking the HSFabric instance status, in seconds.	60
hsfabric.subquery.pushdown	Whether to enable cross-domain query pushdown. The function is enabled by default. <ul style="list-style-type: none"> <li>▪ <b>true</b>: enables cross-domain query pushdown.</li> <li>▪ <b>false</b>: disables cross-domain query pushdown.</li> </ul>	true

- You can click **Delete** to delete custom configuration parameters.
4. Click **OK**.

----End

## 8.4.6 Configuring a ClickHouse Data Source

### Scenarios

- Currently, HetuEngine supports the interconnection with the ClickHouse data source in the cluster of MRS 3.1.1 or later.
- The HetuEngine cluster in security mode supports the interconnection with the ClickHouse data source in the cluster of MRS 3.1.1 or later in security mode.

- The HetuEngine cluster in normal mode supports the interconnection with the ClickHouse data source in the cluster of MRS 3.1.1 or later in normal mode.
- In the ClickHouse data source, tables with the same name but in different cases, for example, **cktable** (lowercase), **CKTABLE** (uppercase), and **CKtable** (uppercase and lowercase), cannot co-exist in the same schema or database. Otherwise, tables in the schema or database cannot be used by HetuEngine.

## Prerequisites

You have created a HetuEngine administrator by referring to [Creating a HetuEngine User](#).

## Procedure

- Step 1** Log in to FusionInsight Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** tab page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
- Step 3** Choose **Data Source**.
- Step 4** Click **Add Data Source**. On the **Add Data Source** page that is displayed, configure parameters.
  1. Configure parameters in the **Basic Configuration** area. For details about the parameters, see [Table 8-30](#).

**Table 8-30** Basic Information

Parameter	Description	Example Value
Name	Name of the data source to be connected. The value can contain only letters, digits, and underscores (_) and must start with a letter.	clickhouse_1
Data Source Type	Type of the data source to be connected. Choose <b>JDBC &gt; ClickHouse</b> .	ClickHouse
Description	Description of the data source. The value can contain only letters, digits, commas (,), periods (.), underscores (_), spaces, and line breaks.	-

2. Configure parameters in the **ClickHouse Configuration** area. For details, see [Table 8-31](#).

**Table 8-31** ClickHouse Configuration

Parameter	Description	Example Value
Driver	The default value is <b>clickhouse</b> .	clickhouse
JDBC URL	<p>JDBC URL of the ClickHouse data source.</p> <ul style="list-style-type: none"> <li>- If the ClickHouse data source uses IPv4, the format is <b>jdbc:clickhouse://&lt;host&gt;:&lt;port&gt;</b>.</li> <li>- If the ClickHouse data source uses IPv6, the format is <b>jdbc:clickhouse://[&lt;host&gt;]:&lt;port&gt;</b>.</li> <li>- To obtain the value of <b>&lt;host&gt;</b>, log in to Manager of the cluster where the ClickHouse data source is located, choose <b>Cluster &gt; Services &gt; ClickHouse &gt; Instance</b>, and view the ClickHouseBalancer service IP address.</li> <li>- To obtain the value of <b>&lt;port&gt;</b>, log in to Manager of the cluster where the ClickHouse data source is located, and choose <b>Cluster &gt; Services &gt; ClickHouse &gt; Configurations &gt; All Configurations</b>. If the ClickHouse data source is in security mode, check the HTTPS port number of the ClickHouseBalancer instance, that is, the value of <b>lb_https_port</b>. If the ClickHouse data source is in normal mode, check the HTTP port number of the ClickHouseBalancer instance, that is, the value of <b>lb_http_port</b>.</li> </ul>	<p><b>jdbc:clickhouse://10.162.156.243:21426</b>, <b>jdbc:clickhouse://10.162.156.243:21425</b>, or <b>jdbc:clickhouse://[fec0::d916:8:5:164:200]:21426</b></p>

Parameter	Description	Example Value
Username	Username used for connecting to the ClickHouse data source.	Change the value based on the username being connected with the data source.
Password	User password used for connecting to the ClickHouse data source.	Change the value based on the user password for connecting to the data source.
Case-sensitive Table/Schema Name	<p>Whether to support case-sensitive names or schemas of the data source.</p> <p>HetuEngine supports case-sensitive names or schemas of the data source.</p> <ul style="list-style-type: none"> <li>- <b>No:</b> If multiple table names exist in the same schema of a data source, for example, <b>cktable</b> (lowercase), <b>CKTABLE</b> (uppercase), and <b>CKtable</b> (lowercase and uppercase), only <b>cktable</b> (lowercase) can be used by HetuEngine.</li> <li>- <b>Yes:</b> Only one table name can exist in the same schema of the data source, for example, <b>cktable</b> (lowercase), <b>CKTABLE</b> (uppercase), or <b>CKtable</b> (lowercase and uppercase). Otherwise, all tables in the schema cannot be used by HetuEngine.</li> </ul>	-

3. (Optional) Customize the configuration.

You can click **Add** to add custom configuration parameters. Configure custom parameters of the ClickHouse data source. For details, see [Table 8-32](#).

**Table 8-32** Custom parameters of the ClickHouse data source

Parameter	Description	Example Value
use-connection-pool	Whether to use the JDBC connection pool.	true
jdbc.connection.pool.maxTotal	Maximum number of connections in the JDBC connection pool.	8
jdbc.connection.pool.maxIdle	Maximum number of idle connections in the JDBC connection pool.	8
jdbc.connection.pool.minIdle	Minimum number of idle connections in the JDBC connection pool.	0
jdbc.connection.pool.testOnBorrow	Whether to check the connection validity when using a connection obtained from the JDBC connection pool.	false
jdbc.pushdown-enabled	Whether to enable the pushdown function. Default value: <b>true</b>	true
jdbc.pushdown-module	Pushdown type. <ul style="list-style-type: none"> <li>- <b>DEFAULT</b>: No operator is pushed down.</li> <li>- <b>BASE_PUSHDOWN</b>: Only operators such as Filter, Aggregation, Limit, TopN, and Projection are pushed down.</li> <li>- <b>FULL_PUSHDOWN</b>: All supported operators are pushed down.</li> </ul>	-
clickhouse.map-string-as-varchar	Whether to convert the ClickHouse data source of the String and FixedString types to the Varchar type. Default value: <b>true</b>	true
clickhouse.socket-timeout	Timeout interval for connecting to the ClickHouse data source. Unit: millisecond Default value: <b>120000</b>	120000

Parameter	Description	Example Value
case-insensitive-name-matching.cache-ttl	Timeout interval for caching case-sensitive names of schemas or tables of the data sources. Unit: minute Default value: 1	1

You can click **Delete** to delete custom configuration parameters.

4. Click **OK**.

----End

## Operation Guide

- **Table 8-33** lists the ClickHouse data types supported by HetuEngine.

**Table 8-33** ClickHouse data types supported by HetuEngine

Name	ClickHouse Data Type	
ClickHouse data types supported by HetuEngine	UInt8	Decimal128(S)
	UInt16	Boolean
	UInt32	String
	UInt64	Fixedstring(N)
	Int8	UUID
	Int16	Date
	Int32	DateTime([timezone])
	Int64	Enum
	Float32	LowCardinality(data_type)
	Float64	Nullable(typename)
	Decimal(P, S)	IPv4
	Decimal32(S)	IPv6
	Decimal64(S)	-

- **Table 8-34** lists the tables and views that support the interconnection between HetuEngine and ClickHouse.

**Table 8-34** Supported tables and views

Name	Supported Table and View
Tables that support the interconnection between HetuEngine and ClickHouse	Local table (MergeTree)
	Replicated table (ReplicatedReplacingMergeTree)
	Distributed table
Views that support the interconnection between HetuEngine and ClickHouse	Normal view
	Materialized view

## 8.5 Managing Data Sources

### 8.5.1 Managing an External Data Source

#### Scenarios

On the HetuEngine web UI, you can view, edit, and delete an added data source.

#### Prerequisites

You have created a HetuEngine administrator for accessing the HetuEngine web UI. For details, see [Creating a HetuEngine User](#).

#### Viewing Data Source Information

- Step 1** Log in to Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The HetuEngine service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** tab page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
- Step 3** Click **Data Source**. In the data source list, view the data source name, description, type, and creation time.

----End

#### Editing a Data Source

- Step 1** Log in to Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The HetuEngine service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** tab page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.

- Step 3** Click **Data Source**, locate the row that contains the data source to be modified, click **Edit** in the **Operation** column, modify related information by referring to [Configuring Data Sources](#), and click **OK**.

----End

## Deleting a Data Source

- Step 1** Log in to Manager as a HetuEngine administrator and choose **Cluster > Services > HetuEngine**. The HetuEngine service page is displayed.

- Step 2** In the **Basic Information** area on the **Dashboard** tab page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.

- Step 3** Click **Data Source**, locate the row that contains the data source to be deleted, and click **Delete** in the **Operation** column. In the displayed dialog box, select **Deleted data sources cannot be restored. Exercise caution when performing this operation** and click **OK**.

----End

## 8.6 Managing Compute Instances

### 8.6.1 Configuring Resource Groups

#### Resource Group Introduction

The resource group mechanism controls the overall query load of the instance from the perspective of resource allocation and implements queuing policies for queries. Multiple resource groups can be created under a compute instance resource, and each submitted query is assigned to a specific resource group for execution. Before a resource group executes a new query, it checks whether the resource load of the current resource group exceeds the amount of resources allocated to it by the instance. If it is exceeded, new incoming queries are blocked, placed in a queue, or even rejected directly. However, the resource component does not cause the running query to fail.

#### Application Scenarios of Resource Groups

Resource groups are used to manage resources in compute instances. Different resource groups are allocated to different users and queries to isolate resources. This prevents a single user or query from exclusively occupying resources in the compute instance. In addition, the weight and priority of resource components can be configured to ensure that important tasks are executed first. [Table 8-35](#) describes the typical application scenarios of resource groups.

**Table 8-35** Typical application scenarios of resource groups

Typical Scenarios	Solution
As the number of business teams using the compute instance increases, there is no resource when a team's task becomes more important and does not want to execute a query.	Allocate a specified resource group to each team. Important tasks are assigned to resource groups with more resources. When the sum of the proportions of sub-resource groups is less than or equal to 100%, the resources of a queue cannot be preempted by other resource groups. This is similar to static resource allocation.
When the instance resource load is high, two users submit a query at the same time. At the beginning, both queries are queuing. When there are idle resources, the query of a specific user can be scheduled to obtain resources first.	Two users are allocated with different resource groups. Important tasks can be allocated to resource groups with higher weights or priorities. The scheduling policy is configured by schedulingPolicy. Different scheduling policies have different resource allocation sequences.
For ad hoc queries and batch queries, resources can be allocated more properly based on different SQL types.	You can match different resource groups for different query types, such as EXPLAIN, INSERT, SELECT, and DATA_DEFINITION, and allocate different resources to execute the query.

## Enabling a Resource Group

When creating a compute instance, add custom configuration parameters to the **resource-groups.json** file. For details, see [Step 3.5](#) in [Creating HetuEngine Compute Instances](#).

## Resource Group Properties

For details about how to configure resource group attributes, see [Table 8-36](#).

**Table 8-36** Resource group properties

Configuration Item	Man datory	Description
name	Yes	Resource group name
maxQueued	Yes	Maximum number of queued queries. When this threshold is reached, new queries will be rejected.

Configuration Item	Mandatory	Description
hardConcurrencyLimit	Yes	Maximum number of running queries.
softMemoryLimit	No	Maximum memory usage of a resource group. When the memory usage reaches this threshold, new tasks are queued. The value can be an absolute value (for example, 10 GB) or a percentage (for example, 10% of the cluster memory).
softCpuLimit	No	The CPU time that can be used in a period (see the <b>cpuQuotaPeriod</b> parameter in <a href="#">Global Attributes</a> ). You must also specify the <b>hardCpuLimit</b> parameter. When the threshold is reached, the CPU resources occupied by the query that occupies the maximum CPU resources in the resource group are reduced.
hardCpuLimit	No	Maximum CPU time that can be used in a period.
schedulingPolicy	No	<p>The scheduling policy for a specific query from the queuing state to the running state</p> <ul style="list-style-type: none"> <li>• fair (default)</li> </ul> <p>When multiple sub-resource groups in a resource group have queuing queries, the sub-resource groups obtain resources in turn based on the defined sequence. The query of the same sub-resource group obtains resources based on the first-come-first-executed rule.</p> <ul style="list-style-type: none"> <li>• weighted_fair</li> </ul> <p>The <b>schedulingWeight</b> attribute is configured for each resource group that uses this policy. Each sub-resource group calculates a ratio: <i>Number of queried sub-resource groups/Scheduling weight</i>. A sub-resource group with a smaller ratio obtains resources first.</p> <ul style="list-style-type: none"> <li>• weighted</li> </ul> <p>The default value is <b>1</b>. A larger value of <b>schedulingWeight</b> indicates that resources are obtained earlier.</p> <ul style="list-style-type: none"> <li>• query_priority</li> </ul> <p>All sub-resource groups must be set with <b>query_priority</b>. Resources are obtained in the sequence specified by <b>query_priority</b>.</p>
schedulingWeight	No	Weight of the group. For details, see <b>schedulingPolicy</b> . The default value is <b>1</b> .

Configuration Item	Mandatory	Description
jmxExport	No	If this parameter is set to <b>true</b> , group statistics are exported to the JMX for monitoring. The default value is <b>false</b> .
subGroups	No	Subgroup list

## Selector Rules

The selector matches resource groups in sequence. The first matched resource group is used. Generally, you are advised to configure a default resource group. If no default resource group is configured and other resource group selector conditions are not met, the query will be rejected. For details about how to set selector rule parameters, see [Table 8-37](#).

**Table 8-37** Selector rules

Configuration Item	Mandatory	Description
user	No	Regular expression for matching the user name.
source	No	Data source to be matched with, such as JDBC, HBase, and Hive. For details, see the value of <b>--source</b> in <a href="#">Configuration of Selector Attributes</a> .
queryType	No	Task types: <ul style="list-style-type: none"> <li>• <b>DATA_DEFINITION</b>: indicates that you can modify, create, or delete the metadata of schemas, tables, and views, and manage the query of prepared statements, permissions, sessions, and transactions.</li> <li>• <b>DELETE</b>: indicates the DELETE queries.</li> <li>• <b>DESCRIBE</b>: indicates the DESCRIBE, DESCRIBE INPUT, DESCRIBE OUTPUT, and SHOW queries.</li> <li>• <b>EXPLAIN</b>: indicates the EXPLAIN queries.</li> <li>• <b>INSERT</b>: indicates the INSERT and CREATE TABLE AS queries.</li> <li>• <b>SELECT</b>: indicates the SELECT queries.</li> </ul>
clientTags	No	Match client tag to be matched with. Each tag must be in the tag list of the task submitted by the user. For details, see the value of <b>--client-tags</b> in <a href="#">Configuration of Selector Attributes</a> .
group	Yes	The resource group with running queries

## Global Attributes

For details about how to configure global attributes, see [Table 8-38](#).

**Table 8-38** Global attributes

Configuration Item	Mandatory	Description
cpuQuotaPeriod	No	Time range during which the CPU quota takes effect. This parameter is used together with <b>softCpuLimit</b> and <b>hardCpuLimit</b> in <a href="#">Resource Group Properties</a> .

## Configuration of Selector Attributes

The data source name (**source**) can be set as follows:


- **CLI:** Use the **--source** option.
- **JDBC:** Set the ApplicationName client information property on the Connection instance.

The client tag (**clientTags**) can be configured as follows:

- **CLI:** Use the **--client-tags** option.
- **JDBC:** Set the **ClientTags client info** property on the Connection instance.

## Configuration Example

**Figure 8-1** Configuration example



As shown in [Figure 8-1](#).

- For the **global** resource group, a maximum of 100 queries can be executed at the same time. 1000 queries are in the queuing state. The **global** resource group has three sub-resource groups: **data\_definition**, **adhoc**, and **pipeline**.
- Each user in the **pipeline** resource group can run a maximum of five queries at the same time, which occupy 50% of the memory resources of the pipeline resource group. By default, the **fair** scheduling policy is used in the **pipeline** resource group. Therefore, the query is executed in the sequence of "first come, first served".
- To make full use of instance resources, the total memory quota of all child resource groups can be greater than that of the parent resource group. For example, the sum of the memory quota of the **global** resource group (80%) and that of the **admin** resource group (100%) is 180%, which is greater than 100%.

In the following example configuration, there are multiple resource groups, some of which are templates. Administrators can use templates to dynamically build a resource group tree. For example, in the **pipeline\_** $\{USER\}$  group,  $\{USER\}$  is the name of the user who submits a query.  $\{SOURCE\}$  is also supported, which will be the source where a query is submitted later. You can also use custom variables in **source** expressions and **user** regular expressions.

The following is an example of a resource group selector:

```
"selectors": [{
  "user": "bob",
  "group": "admin"
},
{
  "source": ".*pipeline.*",
  "queryType": "DATA_DEFINITION",
  "group": "global.data_definition"
},
{
  "source": ".*pipeline.*",
  "group": "global.pipeline.pipeline_{$USER}"
},
{
  "source": "jdbc#(?<toolname>.*)",
  "clientTags": ["hipri"],
  "group": "global.adhoc.bi-{$toolname}.{$USER}"
},
{
  "group": "global.adhoc.other.{$USER}"
}
]
```

There are four selectors that define which resource group to run the query:

- The first selector matches queries from **bob** and places them in the **admin** group.
- The second selector matches all data definition language (DDL) queries from the source name that includes the **pipeline** and places them in the **global.data\_definition** group. This helps reduce the queuing time of such queries.
- The third selector matches queries from sources that include the **pipeline** and places them in a single-user pipe group that is dynamically created under the **global.pipeline** group.
- The fourth selector matches queries from BI tools whose sources match the regular expression **jdbc#(?<toolname>.\*)**, and the tags provided by the client are the superset of **hi-pri**. These files are placed in the subgroups that are

dynamically created under the **global.pipeline.tools** group. Dynamic subgroups are created based on the naming variable **toolname**, which is extracted from the **source** regular expression. Consider queries that use the query containing the source **jdbc#powerfulbi**, user **kayla**, and client tags, **hipri** and **fast**. This query will be routed to the **global.pipeline.bi-powerfulbi.kayla** resource group.

- The last selector is a default selector that puts all the unmatched queries into the resource group.

These selectors work together to implement the following policies:

- Administrator **bob** can run 50 queries at the same time. The query will run according to the user-supplied priority.
- For the remaining users:
  - The total number of concurrent queries cannot exceed 100.
  - You can use the source pipeline to run a maximum of five concurrent DDL queries. The query is performed in the FIFO sequence.
  - Non-DDL queries are executed in the **global.pipeline** group. The total number of concurrent queries is 45, and each user can run 5 queries concurrently. The query is performed in the FIFO sequence.
  - Each BI tool can run a maximum of 10 concurrent queries, and each user can run a maximum of three concurrent queries. If the total number of concurrent queries exceeds 10, the user who runs the least queries gets the next concurrency slot. This policy makes it fairer to compete for resources.
  - All the remaining queries are placed in each of the user groups under **global.adhoc.other**.

The description of the query match selector is as follows:

- Each pair of braces represents a selector that matches the resource group. Five selectors are configured to match the five resource groups.

```
admin  
global.data_definition  
global.pipeline.pipeline_${USER}  
global.adhoc.bi-${toolname}.${USER}  
global.adhoc.other.${USER}
```

- Only when all the conditions of the selector are met, the task can be put into the current queue for execution. For example, if user **amy** submits a query request in JDBC mode and **clientTags** is not configured, the query request cannot be allocated to the resource group **global.adhoc.bi-\${toolname}.\${USER}**.
- When a query can meet the conditions of two selectors at the same time, the first selector that meets the requirements is matched. For example, if the **bob** user submits a DATA\_DEFINITION job whose source is **pipeline**, only the resource corresponding to the resource group **admin** is matched, not the resource corresponding to **global.data\_definition**.
- If none of the four selectors is matched, resources in the resource group **global.adhoc.other.\${USER}** specified by the last selector are used. This resource group functions as a default resource group. If the default resource group is not set and does not meet the conditions of other resource group selectors, the resource group will be rejected.

The following is a complete example:

```
{
  "rootGroups": [{
    "name": "global",
    "softMemoryLimit": "80%",
    "hardConcurrencyLimit": 100,
    "maxQueued": 1000,
    "schedulingPolicy": "weighted",
    "jmxExport": true,
    "subGroups": [{
      "name": "data_definition",
      "softMemoryLimit": "10%",
      "hardConcurrencyLimit": 5,
      "maxQueued": 100,
      "schedulingWeight": 1
    }],
  },
  {
    "name": "adhoc",
    "softMemoryLimit": "10%",
    "hardConcurrencyLimit": 50,
    "maxQueued": 1,
    "schedulingWeight": 10,
    "subGroups": [{
      "name": "other",
      "softMemoryLimit": "10%",
      "hardConcurrencyLimit": 2,
      "maxQueued": 1,
      "schedulingWeight": 10,
      "schedulingPolicy": "weighted_fair",
      "subGroups": [{
        "name": "${USER}",
        "softMemoryLimit": "10%",
        "hardConcurrencyLimit": 1,
        "maxQueued": 100
      }]
    }],
  },
  {
    "name": "bi-${toolname}",
    "softMemoryLimit": "10%",
    "hardConcurrencyLimit": 10,
    "maxQueued": 100,
    "schedulingWeight": 10,
    "schedulingPolicy": "weighted_fair",
    "subGroups": [{
      "name": "${USER}",
      "softMemoryLimit": "10%",
      "hardConcurrencyLimit": 3,
      "maxQueued": 10
    }],
  }],
  {
    "name": "pipeline",
    "softMemoryLimit": "80%",
    "hardConcurrencyLimit": 45,
    "maxQueued": 100,
    "schedulingWeight": 1,
    "jmxExport": true,
    "subGroups": [{
      "name": "pipeline_${USER}",
      "softMemoryLimit": "50%",
      "hardConcurrencyLimit": 5,
      "maxQueued": 100
    }],
  }],
  {
    "name": "admin",
    "softMemoryLimit": "100%",
    "hardConcurrencyLimit": 50,
```

```
    "maxQueued": 100,  
    "schedulingPolicy": "query_priority",  
    "jmxExport": true  
  }],  
  "selectors": [{  
    "user": "bob",  
    "group": "admin"  
  }],  
  {  
    "source": ".*pipeline.*",  
    "queryType": "DATA_DEFINITION",  
    "group": "global.data_definition"  
  },  
  {  
    "source": ".*pipeline.*",  
    "group": "global.pipeline.pipeline_${USER}"  
  },  
  {  
    "source": "jdbc#(?<toolname>.*)",  
    "clientTags": ["hipri"],  
    "group": "global.adhoc.bi-${toolname}.${USER}"  
  },  
  {  
    "group": "global.adhoc.other.${USER}"  
  }  
],  
  "cpuQuotaPeriod": "1h"  
}
```

## 8.6.2 Adjusting the Number of Worker Nodes

### Scenarios

On the HetuEngine web UI, you can adjust the number of worker nodes for a compute instance. In this way, resources can be expanded for the compute instance when resources are insufficient and released when the resources are idle. The number of workers can be adjusted manually or automatically.

### Prerequisites

You have created a user for accessing the HetuEngine web UI. For details, see [Creating a HetuEngine User](#).

#### NOTE

- When an instance is being scaled in or out, the original services are not affected and the instance can still be used.
- Instance scale-in/out is delayed to implement smooth adjustment of resource consumption within a long period of time. It cannot respond to the requirements of running SQL tasks for available resources in real time.
- After the instance scale-in/out function is enabled, restarting the HSBroker and Yarn services affects the scale-in/out function. If you need to restart the services, you are advised to disable the instance scale-in/out function first.
- Before scaling out a compute instance, ensure that the current queue has sufficient resources. Otherwise, the scale-out cannot reach the expected result and subsequent scale-in operations will be affected.
- To perform manual scale-in/out, log in to Manager, choose **HetuEngine > Configurations > All Configurations**, search for **application.customized.properties**, and add the **yarn.hetuserver.engine.flex.timeout.sec** parameter. The default value is **300** (in seconds).

## Procedure

- Step 1** Log in to FusionInsight Manager as a user who can access the HetuEngine web UI and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** tab page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
- Step 3** Click **Compute Instance**.
- Step 4** Locate the row that contains the target instance, and click **Configure** in the **Operation** column.
- Step 5** If manual scale-in/out is required, change the number of workers on the configuration page and click **OK**. The compute instance enters the **SCALING OUT** or **SCALING IN** state. After the scale-in/out is complete, the compute instance status changes to **RUNNING**.
- Step 6** If automatic scale-in/out is required, choose **Configure Instance > Advanced Configuration** and click the **Scaling** switch.
- **OFF**: Disable dynamic scale-in/out.
  - **ON**: Enable dynamic scale-in/out. For details, see [Table 8-39](#). [Figure 8-2](#) shows the configuration page.

**Table 8-39** Parameters for dynamic scale-in/out

Parameter	Description	Example Value
Scale-out Threshold	When the average value of the instance resource usage in the scale-in/out decision-making period exceeds the threshold, the instance starts to scale out.	0.9
Scale-out Size	Number of Workers to be added each time when the instance starts to scale out.	1
Scale-out Decision Period	Interval for determining whether to scale out an instance. Unit: second	200
Scale-in Threshold	When the average value of the instance resource usage in the scale-in/out decision-making period exceeds the threshold, the instance starts to scale in.	0.1

Parameter	Description	Example Value
Scale-in Size	Number of Workers to be reduced each time when the instance starts to scale in.	1
Scale-in Decision Period	Interval for determining whether to scale in an instance. Unit: second	300
Load Collection Period	Interval for collecting instance load information. Unit: second	10
Scale-out Timeout Period	Timeout period of the scale-out operation. Unit: second	400
Scale-in Timeout Period	Timeout period of the scale-in operation. Unit: second	600

**Figure 8-2** Scaling out/in an instance



----End

## 8.6.3 Managing a HetuEngine Compute Instance

### Scenario

On the HetuEngine web UI, you can start, stop, delete, and roll-restart a single compute instance or compute instances in batches.

## NOTICE

- Restarting HetuEngine  
During the restart or rolling restart of HetuEngine, do not create, start, stop, or delete HetuEngine compute instances on HSConsole.
- Restarting HetuEngine compute instances
  - During the restart or rolling restart of HetuEngine compute instances, do not perform any change operations on the data sources on the HetuEngine and HetuEngine web UI, including restarting HetuEngine and changing its configurations.
  - If a compute instance has only one coordinator or worker, do not roll-restart the instance.
  - If the number of workers is greater than 10, the rolling restart may take more than 200 minutes. During this period, do not perform other O&M operations.
  - During the rolling restart of compute instances, HetuEngine releases Yarn resources and applies for them again. Ensure that the CPU and memory of Yarn are sufficient for starting 20% workers and Yarn resources are not preempted by other jobs. Otherwise, the rolling restart will fail.

Viewing Yarn resources: Log in to FusionInsight Manager and choose **Tenant Resources**. On the navigation pane on the left, choose **Tenant Resources Management** to view the available queue resources of Yarn in the **Resource Quota** area.

Viewing the CPU and memory of a worker container: Log in to FusionInsight Manager as a user who can access the HetuEngine WebUI and choose **Cluster > Services > HetuEngine**. In the **Basic Information** area, click the link next to **HSConsole WebUI** to go to the HSConsole page. Click **Operation** in the row where the target instance is located and click **Configure**.

- During the rolling restart, ensure that Application Manager of coordinators or workers in the Yarn queue runs stably.

### Troubleshooting

- If Application Manager of coordinators or workers in the Yarn queues is restarted during the rolling restart, the compute instances may be abnormal. In this case, you need to stop the compute instances and then start the compute instance for recovery.
- Compute instances are in the subhealthy state if they fail to be roll-restarted, which may lead to inconsistent configuration or number of coordinators or workers. In this case, the subhealth state of the instances will not be automatically restored. You need to manually check the instance status or restore the instance to healthy by performing the rolling restart again or stopping the compute instances.

## Prerequisites

You have created an administrator for accessing the HetuEngine web UI. For details, see [Creating a HetuEngine User](#).

 **NOTE**

- Users in the **hetuadmin** user group are administrators. Administrators have the permission to start, stop, and delete instances, and common users have only the permission to query instances.
- To modify the configuration of the current compute instance, you need to delete the instance on the HSConsole page.

## Procedure

- Step 1** Log in to FusionInsight Manager as an administrator who can access the HetuEngine web UI and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
- Step 3** In the **Operation** column of the instance, you can perform the following operations on a single job:
- To start an instance, click **Start**.
  - To stop an instance, click **Stop**.
  - To delete an instance that is no longer used, click **Delete**. The configuration information of the instance is also deleted.
  - To roll-restart an instance, click **Rolling Restart**.
- Step 4** In the upper part of the instance list, you can perform the following operations on jobs:
- To start instances in batches, select the target instances in the instance list and click **Start**.
  - To stop instances in batches, select the target instances in the instance list and click **Stop**.
  - To delete instances in batches, select the target instances in the instance list and click **Delete**.
  - To roll-restart instances in batches, select the target instances in the instance list and click **Rolling Restart**.

----End

## 8.6.4 Importing and Exporting Compute Instance Configurations

### Scenarios

On the HetuEngine web UI, you can import or export the instance configuration file and download the instance configuration template.

### Prerequisites

You have created a user for accessing the HetuEngine web UI. For details, see [Creating a HetuEngine User](#).

## Procedure

- Step 1** Log in to FusionInsight Manager as a user who can access the HetuEngine web UI and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** tab page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
  - Importing an instance configuration file: Click **Import** above the instance list, select an instance configuration file in JSON format from the local PC, and click **Open**.

---

### NOTICE

The instance configuration file must be named **uploadConfig.json** so that it can be imported.

- Exporting an instance configuration file: Click **Export** above the instance list to export the current instance configuration file to the local PC.

----End

## 8.6.5 Viewing the Instance Monitoring Page

### Scenarios

On the HetuEngine web UI, you can view the detailed information about a specified service, including the execution status of each SQL statement. If the current cluster uses dual planes, a Windows host that can connect to the cluster service plane is required.

#### NOTE

You cannot view the compute instance task monitoring page using Internet Explorer.


### Prerequisites

You have created an administrator for accessing the HetuEngine web UI. For details, see [Creating a HetuEngine User](#).

## Procedure

- Step 1** Log in to FusionInsight Manager as an administrator who can access the HetuEngine web UI and choose **Cluster > Name of the desired cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
- Step 2** In the **Basic Information** area on the **Dashboard** tab page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
- Step 3** Locate the row of the target **Instance ID**, and click **LINK** in the **WebUI** column of the row. The compute instance task monitoring page is displayed on a new page. The **Query History** page is displayed for the first access. Click **Metrics** to view the compute instance task monitoring page.

**Figure 8-3** Compute instance task monitoring page




**Table 8-40** Metric description

Metric	Description
Cluster CPU Usage	Indicates the CPU usage of the current instance.
Cluster Free Memory	Indicates the free memory of the current instance.
Average Cluster CPU Usage	Indicates the average CPU usage of the current instance.
Used Query Memory	Indicates the memory used by the current instance.
Running Queries	Indicates the number of tasks concurrently executed on the current instance.
Queued Queries	Indicates the number of tasks to be executed in the waiting queue on the current instance.
Blocked Queries	Indicates the number of blocked tasks on the current instance.
Active Workers	Indicates the number of valid Workers on the current instance.
Avg Running Tasks	Indicates the average number of running tasks in the current instance.
Avg CPU cycles per worker	Indicates the average CPU cycles of each Worker on the current instance.

**Step 4** Filter query tasks by **State** on the page.

**Figure 8-4** Filtering tasks by State




**Table 8-41** State description


State	Description
Select All	Views tasks of all statuses.
Queued	Views the tasks to be executed in the waiting queue.
Waiting For Resources	Views the tasks that wait for resources.
Dispatching	Views the tasks that are being dispatched.
Planning	Views the tasks that are being planned.
Starting	Views the tasks that start running.
Running	Views running tasks.
Finishing	Views the tasks that are being finished.
Finished	Views the finished tasks.
Failed	Views failed tasks, which can be filtered by failure cause.

**Step 5** Click a task ID to view the basic information, resource usage, and tasks. For a failed task, you can view related logs on the detail query page.


**Figure 8-5** Viewing task details



**Figure 8-6** Task resource utilization summary




**Figure 8-7** Stages



**Table 8-42** Stages monitoring information

Monitoring Item	Description
SCHEDULED TIME SKEW	Indicates the scheduled time of the concurrent tasks on a node in the current stage.
CPU TIME SKEW	Indicates whether concurrent tasks have computing skew in any stage phase.

**Figure 8-8** Tasks




**Table 8-43** Tasks monitoring items

Monitoring Item	Description
ID	Indicates the ID of the task that is concurrently executed in multiple phases. The format is <i>Stage ID.Task ID</i> .
Host	Indicates the Worker node where the current task is being executed.
State	Indicates the task execution status, including <b>PLANNED</b> , <b>RUNNING</b> , <b>FINISHED</b> , <b>CANCELED</b> , <b>ABORTED</b> , and <b>FAILED</b> .
Rows	Indicates the total number of data records read by a task. The unit is thousand (k) or million (M). By analyzing the number of data records read by different tasks in the same stage, you can quickly determine whether data skew occurs in the current task.
Rows/s	Indicates the number of data records read by a task per second. By analyzing the number of data records read by different tasks in the same stage, you can quickly determine whether the network bandwidth of the node is different and whether the node NIC is faulty.
Bytes	Indicates the data volume read by a task.
Bytes/s	Indicates the data volume read by a task per second.
Elapsed	Indicates the task execution duration.
CPU Time	Indicates the CPU time used by a task.
Buffered	Indicates the buffer size of a task.

**Step 6** Click the "Host" link to view the task resource usage of each node.

**Figure 8-9** Resource usage of the Task node



**Table 8-44** Monitoring metrics of node resources

Name	Description
Node ID	Indicates the host ID.
Heap Memory	Indicates the maximum heap memory size.
Processors	Indicates the number of processors.
Uptime	Indicates the running duration.
External Address	Indicates the external IP address.
Internal Address	Indicates the internal IP address.
Process CPU Utilization	Indicates the physical CPU utilization.
System CPU Utilization	Indicates the system CPU utilization.
Heap Utilization	Indicates the heap memory utilization.
Non-Heap Memory Used	Indicates the non-Heap memory size.
Memory Pools	Indicates the memory pool size of the current Worker node.

----End

## 8.6.6 Viewing Coordinator and Worker Logs

### Scenario

On the HetuEngine web UI, you can view Coordinator and Worker logs on the Yarn web UI.

## Prerequisites

You have created a user for accessing the HetuEngine web UI. For details, see [Creating a HetuEngine User](#).

## Procedure

- Step 1** Log in to FusionInsight Manager as a user who can access the HetuEngine web UI and choose **Cluster > Services > HetuEngine**. The **HetuEngine** service page is displayed.
  - Step 2** In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
  - Step 3** Click **Coordinator** or **Worker** in the **LogUI** column of the row where the target instance is located. Coordinator and Worker logs are displayed on the Yarn web UI.
- End

## 8.6.7 Using Resource Labels to Specify on Which Node Coordinators Should Run

By default, coordinator and worker nodes randomly start on Yarn NodeManager nodes, and you have to open all ports on all NodeManager nodes. Using resource labels of Yarn, HetuEngine allows you to specify NodeManager nodes to run coordinators.

## Prerequisites

You have created a user for accessing the HetuEngine web UI. For details, see [Creating a HetuEngine User](#).

## Procedure

- Step 1** Log in to FusionInsight Manager as a user who can access the HetuEngine web UI.
- Step 2** Set Yarn parameters to specify the scheduler to handle PlacementConstraints.
  1. Choose **Cluster > Services > Yarn**. Click the **Configurations** tab and then **All Configurations**. On the displayed page, search for **yarn.resourcemanager.placement-constraints.handler**, set **Value** to **scheduler**, and click **Save**.
  2. Click the **Instance** tab, select the active and standby ResourceManager instances, click **More**, and select **Restart Instance** to restart the ResourceManager instances of Yarn. Then wait until they are restarted successfully.
- Step 3** Configure resource labels.
  1. Choose **Tenant Resources > Resource Pool**. On the displayed page, click **Add Resource Pool**.
  2. Select a cluster, and enter a resource pool name and a resource label name, for example, **pool1**. Select the desired hosts, click **>>** to add the selected hosts to the new resource pool, and click **OK**.

- Step 4** Set HetuEngine parameters to enable the coordinator placement policy and enter the node resource label.
1. Choose **Cluster > Service > HetuEngine**. Click the **Configurations** tab and then **All Configurations**. On the displayed page, set parameters and click **Save**.

**Table 8-45** Setting HetuEngine parameters

Parameter	Setting
yarn.hetuserver.engine.coordinator.placement.enabled	true
yarn.hetuserver.engine.coordinator.placement.label	Node resource label created in <b>Step 3</b> , for example, <b>pool1</b>

2. Click **Dashboard**, click **More**, and select **Service Rolling Restart**. Wait until the HetuEngine service is restarted successfully.

**Step 5** Restart the HetuEngine compute instance.

1. In the **Basic Information** area on the **Dashboard** page, click the link next to **HSConsole WebUI**. The HSConsole page is displayed.
2. Locate the row that contains the target instance and click **Start** in the **Operation** column.

**Step 6** Check the node on which the coordinator is running.

1. Return to FusionInsight Manager.
2. Choose **Cluster > Services > Yarn**. In the **Basic Information** area on the **Dashboard** page, click the link next to **ResourceManager WebUI**.
3. In the navigation pane on the left, choose **Cluster > Nodes**. You can view that the coordinator has been started on the node in the resource pool created in **Step 3**.

pool1	/default/rack0	RUNNING			Mon Sep 13 15:34:23 +0800	1	coordinator(1)	5 GB	11 GB	1	7	0
-------	----------------	---------	--	--	---------------------------	---	----------------	------	-------	---	---	---

----End

## 8.7 Using the HetuEngine Client

### Scenario

If a compute instance is not created or started, you can log in to the HetuEngine client to create or start the compute instance. This section describes how to manage a compute instance on the client in the O&M or service scenario.

### Prerequisites

- The cluster client has been installed. For example, the installation directory is **/opt/client**.

- You have created a common HetuEngine user, for example, **hetu\_test** who has the permissions of the Hive (with Ranger disabled), **hetuuser**, and **default** queues.

For details about how to create a user, see [Creating a HetuEngine User](#).

## Procedure

**Step 1** Log in to the node where the HetuEngine client resides as the user who installs the client, and switch to the client installation directory.

```
cd /opt/client
```

**Step 2** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 3** Log in to the HetuEngine client based on the cluster authentication mode.

- In security mode, run the following command to complete user authentication and log in to the HetuEngine client:

```
kinit hetu_test
```

```
hetu-cli --catalog hive --tenant default --schema default
```

- In normal mode, run the following command to log in to the HetuEngine client:

```
hetu-cli --catalog hive --tenant default --schema default --user hetu_test
```

### NOTE

**hetu\_test** is a service user who has at least the tenant role specified by **--tenant** and cannot be an OS user.

Parameter description:

- **--catalog:** (Optional) Specifies the name of the specified data source.
- **--tenant:** (Optional) Specifies the tenant resource queue started by the cluster. Do not specify it as the default queue of a tenant. When this parameter is used, the service user must have the role permission of the tenant.
- **--schema:** (Optional) Specifies the name of the schema of the data source to be accessed.
- **--user:** (Mandatory in normal mode) Specifies the name of the user who logs in to the client to execute services. The user must have at least the role of the queue specified by **--tenant**.

### NOTE

- When you log in to the client for the first time, you need to start the HetuEngine cluster on the server. The client page is displayed 40 seconds later.
- The client supports SQL syntax and is compatible with the SQL syntax of the open-source openLookeng 1.2.0.

----End


## 8.8 Using the HetuEngine Cross-Source Function

## 8.8.1 Introduction to HetuEngine Cross-Source Function

Enterprises usually store massive data, such as from various databases and warehouses, for management and information collection. However, diversified data sources, hybrid dataset structures, and scattered data storage rise the development cost for cross-source query and prolong the cross-source query duration.

HetuEngine provides unified standard SQL statements to implement cross-source collaborative analysis, simplifying cross-source analysis operations.

**Figure 8-10** HetuEngine cross-source function



### Key Technologies and Advantages of the HetuEngine Cross-Source Function

- Computing pushdown: When HetuEngine is used for cross-source collaborative analysis, HetuEngine enhances the computing pushdown capability from the dimensions listed in the following table to improve access efficiency.

**Table 8-46** Dimensions of HetuEngine computing pushdown

Type	Content
Basic Pushed Down	Predicate
	Projection
	Sub-query
	Limit
Aggregation Pushed Down	Group by

Type	Content
	Order by
	Count
	Sum
	Min
	Max
Operator Pushed Down	<, >
	Like
	Or

- Multi-source heterogeneous data: Collaborative analysis supports both structured data sources such as Hive and GaussDB and unstructured data sources such as HBase and Elasticsearch.
- Global metadata: A mapping table is provided to map unstructured schemas to structured schemas, enabling HetuEngine to access HBase using SQL statements. Global management for data source information is provided.
- Global permission control: Data source permissions can be opened to Ranger through HetuEngine for centralized management and control.

## 8.8.2 Usage Guide of HetuEngine Cross-Source Function

**Step 1** Register the data source by referring to [Configuring a HetuEngine Data Source](#).

**Step 2** If the HBase data source is used, you need to create a structured mapping table.

- The format of the statement for creating a mapping table is as follows:

```
CREATE TABLE schemaName.tableName (
  rowId VARCHAR,
  qualifier1 TINYINT,
  qualifier2 SMALLINT,
  qualifier3 INTEGER,
  qualifier4 BIGINT,
  qualifier5 DOUBLE,
  qualifier6 BOOLEAN,
  qualifier7 TIME,
  qualifier8 DATE,
  qualifier9 TIMESTAMP
)
WITH (
  column_mapping =
  'qualifier1:f1:q1,qualifier2:f1:q2,qualifier3:f2:q3,qualifier4:f2:q4,qualifier5:f2:q5,qualifier6:f3:q1,qualifier7
:f3:q2,qualifier8:f3:q3,qualifier9:f3:q4',
  row_id = 'rowId',
  hbase_table_name = 'hbaseNamespace:hbaseTable',
  external = true
);
-- Note: The value of schemaName must be the same as the value of hbaseNamespace in
hbase_table_name. Otherwise, the table fails to be created.
```

- Supported mapping tables: Mapping tables can be directly associated with tables in the HBase data source or created and associated with new tables that do not exist in the HBase data source.

- Supported data types in a mapping table: VARCHAR, TINYINT, SMALLINT, INTEGER, BIGINT, DOUBLE, BOOLEAN, TIME, DATE, and TIMESTAMP
- The following table describes the keywords in the statements for creating mapping tables.

**Table 8-47** Keywords in the statements for creating mapping tables

Keyword	Type	Mandatory	Default Value	Remarks
column_mapping	String	No	All columns belong to the same Family column family.	Specify the mapping between columns in the mapping table and column families in the HBase data source table. If a table in the HBase data source needs to be associated, the value of <b>column_mapping</b> must be the same as that in the HBase data source. If you create a table that does not exist in the HBase data source, you need to specify <b>column_mapping</b> .
row_id	String	No	First column in the mapping table	Column name corresponding to the rowkey table in the HBase data source

Keyword	Type	Mandatory	Default Value	Remarks
hbase_table_name	String	No	Null	Tablespace and table name of the HBase data source to be associated. Use a colon (:) to separate them. The default tablespace is <b>default</b> . If a new table that does not exist in the HBase data source is created, <b>hbase_table_name</b> does not need to be specified.
external	Boolean	No	true	If <b>external</b> is set to <b>true</b> , the table is a mapping table in the HBase data source and the original table in the HBase data source cannot be deleted. If <b>external</b> is set to false, the table in the HBase data source is deleted when the <b>Hetu-HBase</b> table is deleted.

**Step 3** Use cross-source collaborative analysis.

```
// 1. Register three types of data sources, including Hive, Elasticsearch, and GaussDB A.
hetuengine> show catalogs;
Catalog
-----
dws
es
hive
hive_dg
system
systemremote
(6 rows)

// 2. Compile SQL statements for cross-source collaborative analysis.
select * from hive_dg.schema1.table1 t1 join es.schema3.table3 t2 join dws.schema02.table4 t3 on t1.name
= t2.item and t2.id = t3.cardNo;


----End
```

## 8.9 Using HetuEngine Cross-Domain Function

### 8.9.1 Introduction to HetuEngine Cross-Source Function

HetuEngine provide unified standard SQL to implement efficient access to multiple data sources distributed in multiple regions (or data centers), shields data differences in the structure, storage, and region, and decouples data and applications.

Figure 8-11 HetuEngine cross-region functions



### Key Technologies and Advantages of HetuEngine Cross-Domain Function

- No single-point failure bottleneck: HSFabric supports horizontal scale-out and multi-channel parallel transmission, maximizing the transmission rate. Cross-domain latency is no longer a bottleneck.
- Better computing resource utilization: Data compression and serialization tasks are delivered to Worker for parallel computing.
- Efficient serialization: The data serialization format is optimized to reduce the amount of data to be transmitted at the same data volume level.
- Streaming transmission: Based on HTTP 2.0 stream, ensure the universality of the HTTP protocol and reduce the repeated invoking of RPC during the transmission of a large amount of data.

- Resumable transmission: A large amount of data is prevented from being retransmitted after the connection is interrupted abnormally during data transmission.
- Traffic control: The network bandwidth occupied by data transmission can be limited by region to prevent other services from being affected due to exclusive traffic occupation in cross-region limited bandwidth scenarios.

## 8.9.2 HetuEngine Cross-Domain Function Usage

**Step 1** Open the data source in the local domain. You can create a virtual schema to shield the real schema information and instance information of the physical data source in the local domain from remote access requests. The remote end can use the virtual schema name to access the data source in the local domain.

```
CREATE VIRTUAL SCHEMA hive01.vschem01 WITH (  
  catalog = 'hive01',  
  schema = 'ins1'  
);
```

**Step 2** Register the data source of the HetuEngine type on the remote HetuEngine and add the local domain HetuEngine by referring to [Configuring a HetuEngine Data Source](#).

**Step 3** Use cross-domain collaborative analysis.

```
// 1. Open the hive1.ins2 data source on the remote HetuEngine.
```

```
CREATE VIRTUAL SCHEMA hive1.vins2 WITH (  
  catalog = 'hive1',  
  schema = 'ins2'  
);
```

```
// 2. Register three types of data sources, including Hive, GaussDB A, and HetuEngine, on HetuEngine in the local domain.
```

```
hetuengine> show catalogs;
```

```
  Catalog  
-----  
dws  
hetuengine_dc  
hive  
hive_dg  
system  
systemremote  
(6 rows)
```

```
// 3. Perform cross-source collaborative analysis on HetuEngine in the local domain.
```

```
select * from hive_dg.schema1.table1 t1 join hetuengine_dc.vins2.table3 t2 join dws.schema02.table4 t3 on  
t1.name = t2.item and t2.id = t3.cardNo;
```

----End

## 8.9.3 HetuEngine Cross-Domain Rate Limit Function

**Step 1** Configure the **ratelimit.xml** configuration file for the HSFabric rate limit policy on the local host. The configuration template is as follows:

```
<?xml version="1.0" encoding="UTF-8" standalone="yes"?>  
<ratelimit>  
  <current-domain>0755</current-domain><!-- city a Name of zone to which the local domain data  
source belongs -->  
  <default-bandwidth>5120</default-bandwidth><!-- The default data volume limit is 50 MB -->  
  <domain-list>  
    <domain>  
      <domainName>0769</domainName><!--Name of zone to which the target domain data source  
belongs -->  
      <bandwidth>102400</bandwidth><!-- The data volume (in KB) sent from the current domain (for
```

```

exampel, city a) to the target domain (for example, city b) is 100 /MB -->
  <cluster-list>
  <hsfabric><!-- One HSFabric Cluster -->
    <clusterName>hsfabric01</clusterName><!-- Cluster description -->
    <hsfabric-node>
      <hsfabricHostPort>10.10.10.10:29900</hsfabricHostPort><!-- Host IP address of the
HSFabric instance -->
    </hsfabric-node>
  </hsfabric>
</cluster-list>
</domain>
<domain>
  <domainName>0770</domainName>
  <bandwidth>20480</bandwidth><!-- The data volume (in KB) sent from the current domain (for
exampel, city a) to the target domain (for example, city b) is 20 MB -->
  <cluster-list>
    <hsfabric><!-- One HSFabric Cluster -->
      <clusterName>hsfabric02</clusterName>
      <hsfabric-node>
        <hsfabricHostPort>10.10.10.10:29900</hsfabricHostPort>
      </hsfabric-node>
    </hsfabric>
  </cluster-list>
</domain>
</domain-list>
</ratelimit>

```

**Table 8-48** Parameters in the `ratelimit.xml` file

Parameter	Description	Example Value
current-domain	Name of zone to which the local domain data source belongs	0755
default-bandwidth	Default data volume limit, in KB	5120
domainName	Name of zone to which the target domain data source belongs	0769
bandwidth	Data volume from the current zone (for example, city a) to the target zone (for example, city b), in KB	102400
clusterName	Description of the cluster in the target domain	hsfabric01
hsfabricHostPort	Service IP address and port number of HSFabric in the target domain	10.10.10.10:29900

- Step 2** Log in to Manager where the target domain cluster locates as an administrator who can access the HetuEngine WebUI.
- Step 3** Choose **Cluster > Services > HetuEngine**. On the displayed page, click **Configurations** and then **All Configurations**.
- Step 4** Choose **HSFabric(role) > Rate Limit** and click **Upload File** to upload the `ratelimit.xml` file prepared in [Step 1](#).

- Step 5** Click **Instance**, select the **HSFabric** instance, choose **More > Restart Instance**, and enter the password to restart the HSFabric instance.

----End

## 8.10 Using a Third-Party Visualization Tool to Access HetuEngine

### 8.10.1 Usage Instruction

To access the dual-plane environment, the cluster service plane must be able to communicate with the local Windows environment.

### 8.10.2 Using DBeaver to Access HetuEngine

This section uses DBeaver 6.3.5 as an example to describe how to perform operations on HetuEngine.

#### Prerequisites

- The DBeaver has been installed properly. Download the DBeaver software from <https://dbeaver.io/files/6.3.5/>.

 **NOTE**

Currently, DBeaver 5.x and 6.x are supported.

- A human-machine user has been created in the cluster. For details about how to create a user, see [Creating a HetuEngine User](#).

#### Procedure

Method 1: Using ZooKeeper to access HetuEngine

- Step 1** Download the HetuEngine client.

1. Log in to FusionInsight Manager.
2. Choose **Cluster > Services > HetuEngine > Dashboard**.
3. In the upper right corner of the page, choose **More > Download Client** and download the **Complete Client** to the local PC as prompted.
4. Decompress the HetuEngine client package **FusionInsight\_Cluster\_Cluster ID\_HetuEngine\_Client.tar** to obtain the JDBC file and save it to a local directory, for example, **D:\test**.

 **NOTE**

Obtaining the JDBC file:

Obtain the **hetu-jdbc-\*.jar** file from the **FusionInsight\_Cluster\_Cluster ID\_HetuEngine\_ClientConfig\HetuEngine\xxx\** directory.

Note: **xxx** can be **arm** or **x86**.

- Step 2** Download the Kerberos authentication file of the HetuEngine user.

1. Log in to FusionInsight Manager.

2. Choose **System > Permission > User**.
3. Locate the row that contains the target HetuEngine user, click **More** in the **Operation** column, and select **Download Authentication Credential**.
4. Decompress the downloaded package to obtain the **user.keytab** and **krb5.conf** files.

**Step 3** Log in to the node where the HSBroker role is deployed in the cluster as user **omm**, go to the `#{BIGDATA_HOME}/FusionInsight_Hetu_8.1.2.2/xxx_HSBroker/etc/` directory, and download the **jaas-zk.conf** and **hetuserver.jks** files to the local PC.

 **NOTE**

The version 8.1.2.2 is used as an example. Replace it with the actual version number.

Modify the **jaas-zk.conf** file as follows. **keyTab** is the keytab file path of the user who accesses HetuEngine, and **principal** is *Username for accessing HetuEngine@Domain name in uppercase.COM*.

```
Client {  
com.sun.security.auth.module.Krb5LoginModule required  
useKeyTab=true  
keyTab="D:\\tmp\\user.keytab"  
principal="admintest@HADOOP.COM"  
useTicketCache=false  
storeKey=true  
debug=true;  
};
```

**Step 4** Add the host mapping to the local **hosts** file. The content format is as follows:

*Host IP address Host name*

Example: 192.168.23.221 192-168-23-221

 **NOTE**

The local **hosts** file in a Windows environment is stored in, for example, **C:\Windows\System32\drivers\etc**.

**Step 5** Configure the DBeaver startup file **dbeaver.ini**.

1. Add the Java path to the file.
2. Set the ZooKeeper and Kerberos parameters by referring to the following parameters. Replace the file paths with the actual paths.

```
-VM  
C:\Program Files\Java\jdk1.8.0_131\bin  
  
-Dsun.security.krb5.debug=true  
-Djava.security.auth.login.config=D:\tmp\jaas-zk.conf  
-Dzookeeper.sasl.clientconfig=Client  
-Dzookeeper.auth.type=kerberos  
-Djava.security.krb5.conf=D:\tmp\krb5.conf
```

 **NOTE**

- The Greenwich Mean Time (GMT) is not supported. If the current time zone is GMT+, add **-Duser.timezone=UTC** to the **dbeaver.ini** file to change the time zone to UTC.
- If DBeaver is started, restart the DBeaver software for the new configuration items in the **dbeaver.ini** file to take effect.

**Step 6** Start the DBeaver, right-click **Database Navigator**, and click **Create New Connection**.

- Step 7** Search for **Presto** in the search box and double-click the Presto icon.
- Step 8** Click **Edit Driver Settings**.
- Step 9** Set **Class Name** to **io.prestosql.jdbc.PrestoDriver**.
- Step 10** Enter the URL of HetuEngine in the **URL Template** text box.  
 URL format: `jdbc:presto://IP address of node 1 where the ZooKeeper service resides:2181,IP address of node 2 where the ZooKeeper service resides:2181,IP address of node 3 where the ZooKeeper service resides:2181/hive/default?serviceDiscoveryMode=zooKeeper&zooKeeperNamespace=hsbroker&zooKeeperServerPrincipal=zookeeper/hadoop.hadoop.com`  
 Example: `jdbc:presto://192.168.8.37:2181,192.168.8.38:2181,192.168.8.39:2181/hive/default?serviceDiscoveryMode=zooKeeper&zooKeeperNamespace=hsbroker&zooKeeperServerPrincipal=zookeeper/hadoop.hadoop.com`
- Step 11** Click **Add File** and select the obtained JDBC file obtained in [Step 1.4](#).
- Step 12** Click **Connection properties**. On the **Connection properties** tab page, right-click and select **Add new property**. Set parameters by referring to [Table 8-49](#).


**Table 8-49** Property information

Parameter	Example Value
KerberosPrincipal	zhangsan <b>NOTE</b> Human-machine user created in the cluster. For details, see <a href="#">Creating a HetuEngine User</a> .
KerberosKeytabPath	D:\\user.keytab <b>NOTE</b> You need to configure this parameter when using the keytab mode for access.
KerberosRemoteServiceName	HTTP
SSL	true
deploymentMode	on_yarn
tenant	default <b>NOTE</b> The tenant to which the user belongs needs to be configured in the cluster.
user	zhangsan <b>NOTE</b> Human-machine user created in the cluster. For details, see <a href="#">Creating a HetuEngine User</a> .

Parameter	Example Value
password	zhangsan@##65331853 <b>NOTE</b> <ul style="list-style-type: none"> <li>• Password set when a human-machine user is created in the cluster. For details, see <a href="#">Creating a HetuEngine User</a>.</li> <li>• You need to configure this parameter when using username and password for access.</li> </ul>
KerberosConfigPath	D:\\krb5.conf
SSLTrustStorePath	D:\\hetuserver.jks

Figure 8-12 shows an example of the parameter settings.

Figure 8-12 Example of parameter settings



**Step 13** Click **OK**.

**Step 14** Click **Finish**. The HetuEngine is successfully connected.

 **NOTE**

If a message is displayed indicating that you do not have the permission to view the table, configure the permission by referring to [Configuring Permissions for Tables, Columns, and Databases](#).

----End

Method 2: Using HSBroker to access HetuEngine


- Step 1** Obtain the JDBC JAR file by referring to [Step 1](#).
- Step 2** Open DBeaver, choose **Database > New Database Connection**, search for PrestoSQL, and open it.
- Step 3** Click **Edit Driver Settings** and set parameters by referring to the following table.

**Table 8-50** Driver settings

Parameter	Value	Remarks
Class Name	io.prestosql.jdbc.PrestoDriver	/
URL Template	URL of HetuEngine	URL format: jdbc:presto:// <HSBrokerIP1:port1>,<HSBroke rIP2:port2>,<HSBrokerIP3:port3 >/hive/default?serviceDiscover- yMode=hsbroker


- Step 4** Click **Add File** and upload the JDBC driver package obtained in [Step 1](#).
- Step 5** Click **Find Class**. The driver class is automatically obtained. Click **OK** to complete the driver setting, as shown in [Figure 8-13](#).

**Figure 8-13** Driver settings




**Step 6** On the **Main** tab page for creating a connection, enter the user name and password, and click **Test Connection**. After the connection is successful, click **OK**, and then click **Finish**.

Figure 8-14 Creating a connection



Step 7 After the connection is successful, the page shown in Figure 8-15 is displayed.

Figure 8-15 Successful connection



----End


### 8.10.3 Using Tableau to Access HetuEngine

#### Prerequisites

- Tableau has been installed.
- The JDBC JAR file has been obtained. For details, see [Step 1](#).
- A human-machine user has been created in the cluster. For details about how to create a user, see [Creating a HetuEngine User](#).

## Procedure

- Step 1** Place the obtained JAR file to the Tableau installation directory, for example, **C:\Program Files\Tableau\Drivers**.
- Step 2** Open Tableau, select **Other databases (JDBC)**, enter the URL and the username and password of the created human-machine user, and click **Sign In**.



URL format:

```
jdbc:presto://<HSBrokerIP1:port1>,<HSBrokerIP2:port2>,<HSBrokerIP3:port3>/hive/default?serviceDiscoveryMode=hsbroker
```

Example:

```
jdbc:presto://192.168.8.37:29860,192.168.8.38:29860,192.168.8.39:29860/hive/default?serviceDiscoveryMode=hsbroker
```

Obtain the HSBroker node and port number:

1. Log in to FusionInsight Manager.
2. Choose **Cluster > Services > HetuEngine > Role > HSBroker** to obtain the service IP addresses of all HSBroker instances.
3. Choose **Cluster > Services > HetuEngine > Configurations > All Configurations** and search for **server.port** on the right to obtain the port number of HSBroker.

### NOTE

- You can select one or more normal brokers for the HSBroker node and port number.
- If the connection fails, disable the proxy and try again.

**Step 3** After the login is successful, drag the data table to be operated to the operation window on the right and refresh data.

----End

## 8.10.4 Using PowerBI to Access HetuEngine


### Prerequisites

- PowerBI has been installed.
- The JDBC JAR file has been obtained. For details, see [Step 1](#).
- A human-machine user has been created in the cluster. For details about how to create a user, see [Creating a HetuEngine User](#).

### Procedure

**Step 1** Use the default configuration to install **hetu-odbc-win64.msi**. Download link: <https://openlookeng.io/en/download/>.

**Figure 8-16** Downloading the driver



**Step 2** Configure data source driver.

1. Run the following commands in the local command prompt to stop the ODBC service that is automatically started.

```
cd C:\Program Files\openLookEng\openLookEng ODBC Driver 64-bit  
\odbc_gateway\mycat\bin
```

```
mycat.bat stop
```

```
C:\Program Files\openLookEng\openLookEng ODBC Driver 64-bit\odbc_gateway\mycat\bin>mycat.bat stop  
wrapper | Stopping the Mycat-server service...  
wrapper | Mycat-server stopped.
```

2. Replace the JDBC driver.

Copy the JDBC JAR file obtained in [Step 1](#) to the **C:\Program Files\openLookEng\openLookEng ODBC Driver 64-bit\odbc\_gateway\mycat\lib** directory and delete the original **hetu-jdbc-1.0.1.jar** file from the directory.

3. Edit the protocol prefix of the ODBC **server.xml** file.

Change the property value of **server.xml** in the **C:\Program Files\openLookEng\openLookEng ODBC Driver 64-bit\odbc\_gateway\mycat\conf** directory from `<property name="jdbcUrlPrefix">jdbc:lk://</property>` to

```
<property name="jdbcUrlPrefix">jdbc:presto://</property>
```

4. Configure the connection mode of using the user name and password.

Create a **jdbc\_param.properties** file in a user-defined path, for example, **C:\hetu**, and add the following content to the file:

```
user=adminitest  
password=adminitest@##65331853
```

 **NOTE**

**user:** indicates the username of the created human-machine user, for example, **adminitest**.

**password:** indicates the password of the created human-machine user, for example, **adminitest@##65331853**.

5. Run the following commands to restart the ODBC service:

```
cd C:\Program Files\openLookeng\openLookeng ODBC Driver 64-bit  
\odbc_gateway\mycat\bin  
mycat.bat restart
```


 **NOTE**

The ODBC service must be stopped each time the configuration is modified. After the modification is complete, restart the ODBC service.


- Step 3** On the Windows **Control Panel**, enter **odbc** to search for the ODBC management program.




- Step 4** Choose **Add > openLookeng ODBC 1.1 Driver > Finish**.





**Step 5** Enter the name and description as shown in the following figure and click **Next**.




**Step 6** Configure parameters by referring to the following figure. Obtain `<HSBrokerIP1:port1>,<HSBrokerIP2:port2>,<HSBrokerIP3:port3>/hive/default?serviceDiscoveryMode=hsbroker` for **Connect URL** by referring to [Step 2](#). Select the `jdbc_param.properties` file prepared in [Step 2.4](#) for **Connect Config**. Set **User name** to the user name that is used to download the credential.




**Step 7** Click **Test DSN** to test the connection. If the connection is successful and both **Catalog** and **Schema** contain content, the connection is successful. Click **Next**.



**Step 8** Click **Finish**.




**Step 9** To use PowerBI for interconnection, choose **Get data > All > ODBC > Connect**.




**Step 10** Select the data source to be added and click **OK**.

**Figure 8-17** Adding a data source




**Step 11** (Optional) Enter **User name** and **Password** of the user who downloads the credential, and click **Connect**.

**Figure 8-18** Entering the database username and password



**Step 12** After the connection is successful, all table information is displayed, as shown in [Figure 8-19](#).

Figure 8-19 Successful connection



----End


## 8.10.5 Using Yonghong BI to Access HetuEngine

### Prerequisites

- Yonghong BI has been installed.
- The JDBC JAR file has been obtained. For details, see [Step 1](#).
- A human-machine user has been created in the cluster. For details about how to create a user, see [Creating a HetuEngine User](#).

### Procedure

**Step 1** Open Yonghong Desktop and choose **Create Connection > presto**.



**Step 2** On the data source configuration page, set parameters by referring to [Figure 8-20](#). **User** and **Password** are the username and password of the created human-machine user. After the configuration is complete, click **Test Connection**.


**Figure 8-20** Configuring the data source

- **Driver:** Choose **Custom** > **Select Custom Driver**. Click , edit the driver name, click **Upload File** to upload the obtained JDBC JAR file, and click **OK**.


- **URL:** For details, see "URL format" in [Step 2](#).
- **Server Login:** Select **Username and Password** and enter the username and password.

**Step 3** Click **New Data Set**. On the displayed page, change the save path by referring to [Figure 8-21](#) and click **OK**.


Figure 8-21 Changing a path



**Step 4** In the connection area, select **hetu > hive > default > Views**. In the **New Data Set** area on the right, select **SQL Data Set**.



**Step 5** In the **Connection** area, select the new data set created in **Step 3**. All table information is displayed. Select a table, for example, **test**, and click **Refresh Data**. All table information is displayed in the **Data Details** area on the right.



----End

## 8.11 Function & UDF Development and Application

### 8.11.1 HetuEngine Function Plugin Development and Application

You can customize functions to extend SQL statements to meet personalized requirements. These functions are called UDFs.

This section describes how to develop and apply HetuEngine function plugins.

#### Developing Function Plugins

This sample implements two function plugins described in the following table.

**Table 8-51** HetuEngine function plugins

Parameter	Description	Type
add_two	Adds 2 to the input integer and returns the result.	ScalarFunction
avg_double	Aggregates and calculates the average value of a specified column. The field type of the column is <b>double</b> .	AggregationFunction

**Step 1** Create a Maven project. Set **groupId** to **com.test.udf** and **artifactId** to **udf-test**. The two values can be customized based on the site requirements.

**Step 2** Modify the **pom.xml** file as follows:

```
<project xmlns="http://maven.apache.org/POM/4.0.0" xmlns:xsi="http://www.w3.org/2001/XMLSchema-
instance" xsi:schemaLocation="http://maven.apache.org/POM/4.0.0 http://maven.apache.org/xsd/
maven-4.0.0.xsd">
  <modelVersion>4.0.0</modelVersion>
  <groupId>com.test.udf</groupId>
  <artifactId>udf-test</artifactId>
  <version>0.0.1-SNAPSHOT</version>

  <packaging>hetu-plugin</packaging>

  <dependencies>
    <dependency>
      <groupId>com.google.guava</groupId>
      <artifactId>guava</artifactId>
      <version>26.0-jre</version>
    </dependency>

    <dependency>
      <groupId>io.hetu.core</groupId>
      <artifactId>presto-spi</artifactId>
      <version>1.2.0</version>
      <scope>provided</scope>
    </dependency>
  </dependencies>

  <build>
    <plugins>
      <plugin>
        <groupId>org.apache.maven.plugins</groupId>
        <artifactId>maven-assembly-plugin</artifactId>
        <version>2.4.1</version>
        <configuration>
          <encoding>UTF-8</encoding>
        </configuration>
      </plugin>
      <plugin>
        <groupId>io.hetu</groupId>
        <artifactId>presto-maven-plugin</artifactId>
        <version>9</version>
        <extensions>true</extensions>
      </plugin>
    </plugins>
  </build>
</project>
```

**Step 3** Create the implementation class of the function plugin.

1. Create the function plugin implementation class **com.hadoop.other.TestUDF4**.

The code is as follows:

```
public class TestUDF4 {
    @ScalarFunction("add_two")
    @SqlType(StandardTypes.INTEGER)
    public static long add2(@SqlNullable @SqlType(StandardTypes.INTEGER) Long i)    {
        return i+2;
    }
}
```

2. Create the function plugin implementation class **com.hadoop.other.AverageAggregation**. The code is as follows:

```
@AggregationFunction("avg_double")
public class AverageAggregation
{
    @InputFunction
    public static void input(
        LongAndDoubleState state,
        @SqlType(StandardTypes.DOUBLE) double value)
    {
```

```
        state.setLong(state.getLong() + 1);
        state.setDouble(state.getDouble() + value);
    }

    @CombineFunction
    public static void combine(
        LongAndDoubleState state,
        LongAndDoubleState otherState)
    {
        state.setLong(state.getLong() + otherState.getLong());
        state.setDouble(state.getDouble() + otherState.getDouble());
    }

    @OutputFunction(StandardTypes.DOUBLE)
    public static void output(LongAndDoubleState state, BlockBuilder out)
    {
        long count = state.getLong();
        if (count == 0) {
            out.appendNull();
        }
        else {
            double value = state.getDouble();
            DOUBLE.writeDouble(out, value / count);
        }
    }
}
```

**Step 4** Create the **com.hadoop.other.LongAndDoubleState** API on which **AverageAggregation** depends.

```
public interface LongAndDoubleState extends AccumulatorState {
    long getLong();

    void setLong(long value);

    double getDouble();


    void setDouble(double value);
}
```

**Step 5** Create the function plugin registration class **com.hadoop.other.RegisterFunctionTestPlugin**. The code is as follows:

```
public class RegisterFunctionTestPlugin implements Plugin {

    @Override
    public Set<Class<?>> getFunctions() {
        return ImmutableSet.<Class<?>>builder()
            .add(TestUDF4.class)
            .add(AverageAggregation.class)
            .build();
    }
}
```

**Step 6** Pack the Maven project and obtain the **udf-test-0.0.1-SNAPSHOT** directory in the **target** directory. The following figure shows the overall structure of the project.



----End

## Deploying Function Plugins

Before the deployment, ensure that:

- The HetuEngine service is normal.
- The HDFS and HetuEngine client have been installed on the cluster node, for example, in the **/opt/client** directory.
- A HetuEngine user has been created. For details about how to create a user, see [Creating a HetuEngine User](#).

**Step 1** Upload the **udf-test-0.0.1-SNAPSHOT** directory obtained in packing the Maven project to any directory on the node where the client is installed.

**Step 2** Upload the **udf-test-0.0.1-SNAPSHOT** directory to HDFS.

1. Log in to the node where the client is installed and perform security authentication.

**cd /opt/client**

```
source bigdata_env
```

```
kinit HetuEngine user
```

Enter the password as prompted and change the password upon the first authentication.

2. Create the following paths in HDFS. If the paths already exist, skip this step.

```
hdfs dfs -mkdir -p /user/hetuserver/udf/data/externalFunctionsPlugin
```

3. Upload the **udf-test-0.0.1-SNAPSHOT** directory to HDFS.

```
hdfs dfs -put udf-test-0.0.1-SNAPSHOT /user/hetuserver/udf/data/  
externalFunctionsPlugin
```

4. Change the directory owner and owner group.

```
hdfs dfs -chown -R hetuserver:hadoop /user/hetuserver/udf/data
```

**Step 3** Restart the HetuEngine compute instance.

----End

## Verifying Function Plugins

**Step 1** Log in to the node where the client is installed and perform security authentication.

```
cd /opt/client
```

```
source bigdata_env
```

```
kinit HetuEngine user
```

```
hetu-cli --catalog hive --schema default
```

**Step 2** Verify function plugins.

1. Query a table.

```
select * from test1;
```

```
select * from test1;  
name | price  
-----|-----  
apple | 17.8  
orange | 25.0  
(2 rows)
```

2. Return the average value.

```
select avg_double(price) from test1;
```

```
select avg_double(price) from test1;  
_col0  
-----  
21.4  
(1 row)
```

3. Return the value of the input integer plus 2.

```
select add_two(4);
```

```
select add_two(4);  
_col0  
-----  
6  
(1 row)
```

----End

## 8.11.2 Hive UDF Development and Application

You can customize functions to extend SQL statements to meet personalized requirements. These functions are called UDFs.

This section describes how to develop and apply Hive UDFs.

### Developing Hive UDFs

This sample implements one Hive UDF described in the following table.

**Table 8-52** Hive UDF

Parameter	Description
AutoAddOne	Adds 1 to the input value and returns the result.

#### NOTE

- A common Hive UDF must be inherited from **org.apache.hadoop.hive.ql.exec.UDF**.
- A common Hive UDF must implement at least one **evaluate()**. The **evaluate** function supports overloading.
- Currently, only the following data types are supported:
  - boolean, byte, short, int, long, float, and double
  - Boolean, Byte, Short, Int, Long, Float, and Double
  - List and Map

UDFs, UDAFs, and UDTFs currently do not support complex data types other than the preceding ones.
- Currently, Hive UDFs supports only less than or equal to five input parameters. UDFs with more than five input parameters will fail to be registered.
- If the input parameter of a Hive UDF is **null**, the call returns **null** directly without parsing the Hive UDF logic. As a result, the UDF execution result may be inconsistent with the Hive execution result.
- To add the **hive-exec-3.1.1** dependency package to the Maven project, you can obtain the package from the Hive installation directory.
- (Optional) If the Hive UDF depends on a configuration file, you are advised to save the configuration file as a resource file in the **resources** directory so that it can be packed into the Hive UDF function package.

**Step 1** Create a Maven project. Set **groupId** to **com.test.udf** and **artifactId** to **udf-test**. The two values can be customized based on the site requirements.

**Step 2** Modify the **pom.xml** file as follows:

```
<project xmlns="http://maven.apache.org/POM/4.0.0" xmlns:xsi="http://www.w3.org/2001/XMLSchema-
instance" xsi:schemaLocation="http://maven.apache.org/POM/4.0.0 http://maven.apache.org/xsd/
maven-4.0.0.xsd">
  <modelVersion>4.0.0</modelVersion>
  <groupId>com.test.udf</groupId>
  <artifactId>udf-test</artifactId>
  <version>0.0.1-SNAPSHOT</version>

  <dependencies>
    <dependency>
```

```

    <groupId>org.apache.hive</groupId>
    <artifactId>hive-exec</artifactId>
    <version>3.1.1</version>
  </dependency>
</dependencies>

<build>
  <plugins>
    <plugin>
      <artifactId>maven-shade-plugin</artifactId>
      <executions>
        <execution>
          <phase>package</phase>
          <goals>
            <goal>shade</goal>
          </goals>
        </execution>
      </executions>
    </plugin>
    <plugin>
      <artifactId>maven-resources-plugin</artifactId>
      <executions>
        <execution>
          <id>copy-resources</id>
          <phase>package</phase>
          <goals>
            <goal>copy-resources</goal>
          </goals>
          <configuration>
            <outputDirectory>${project.build.directory}</outputDirectory>
            <resources>
              <resource>
                <directory>src/main/resources</directory>
                <filtering>>false</filtering>
              </resource>
            </resources>
          </configuration>
        </execution>
      </executions>
    </plugin>
  </plugins>
</build>
</project>

```

**Step 3** Create the implementation class of the Hive UDF.

```

import org.apache.hadoop.hive.ql.exec.UDF;

/**
 * AutoAddOne
 *
 * @since 2020-08-24
 */
public class AutoAddOne extends UDF {
    public int evaluate(int data) {
        return data + 1;
    }
}

```

**Step 4** Package the Maven project. The **udf-test-0.0.1-SNAPSHOT.jar** file in the **target** directory is the Hive UDF function package.

----End

## Configuring Hive UDFs

In configuration file **udf.properties**, add registration information in the "Function\_name Class\_path" format to each line.

The following provides an example of registering four Hive UDFs in configuration file **udf.properties**:

```
booleanudf io.hetu.core.hive.dynamicfunctions.examples.udf.BooleanUDF
shortudf io.hetu.core.hive.dynamicfunctions.examples.udf.ShortUDF
byteudf io.hetu.core.hive.dynamicfunctions.examples.udf.ByteUDF
intudf io.hetu.core.hive.dynamicfunctions.examples.udf.IntUDF
```

 **NOTE**

- If the added Hive UDF registration information is incorrect, for example, the format is incorrect or the class path does not exist, the system ignores the incorrect registration information and prints the corresponding logs.
- If duplicate Hive UDFs are registered, the system will only register once and ignore the duplicate registrations.
- If the Hive UDF to be registered is the same as that already registered in the system, the system throws an exception and cannot be started properly. To solve this problem, you need to delete the Hive UDF registration information.

## Deploying Hive UDFs

To use an existing Hive UDF in HetuEngine, you need to upload the UDF function package, **udf.properties** file, and configuration file on which the UDF depends to the specified HDFS directory, for example, **/user/hetuserver/udf/**, and restart the HetuEngine compute instance.

**Step 1** Create the **/user/hetuserver/udf/data/externalFunctions** directory, save the **udf.properties** file in the **/user/hetuserver/udf** directory, save the UDF function package in the **/user/hetuserver/udf/data/externalFunctions** directory, and save the configuration files on which the UDF depends in the **/user/hetuserver/udf/data** directory.

- Upload the files on the HDFS page:
  - a. Log in to FusionInsight Manager using the HetuEngine username and choose **Cluster > Services > HDFS**.
  - b. In the **Basic Information** area on the **Dashboard** page, click the link next to **NameNode WebUI**.
  - c. Choose **Utilities > Browse the file system** and click  to create the **/user/hetuserver/udf/data/externalFunctions** directory.
  - d. Go to **/user/hetuserver/udf** and click  to upload the **udf.properties** file.
  - e. Go to the **/user/hetuserver/udf/data/** directory and click  to upload the configuration file on which the UDF depends.
  - f. Go to the **/user/hetuserver/udf/data/externalFunctions** directory and click  to upload the UDF function package.
- Use the HDFS CLI to upload the files.
  - a. Log in to the node where the HDFS service client is located and switch to the client installation directory, for example, **/opt/client**.  
**cd /opt/client**

- b. Run the following command to configure environment variables:  
**source bigdata\_env**
- c. If the cluster is in security mode, run the following command to authenticate the user. In normal mode, skip user authentication.  
**kinit HetuEngine username**  
Enter the password as prompted.
- d. Run the following commands to create directories and upload the prepared UDF function package, **udf.properties** file, and configuration file on which the UDF depends to the target directories:  
**hdfs dfs -mkdir /user/hetuserver/udf/data/externalFunctions**  
**hdfs dfs -put ./Configuration files on which the UDF depends /user/hetuserver/udf/data**  
**hdfs dfs -put ./udf.properties /user/hetuserver/udf**  
**hdfs dfs -put ./UDF function package /user/hetuserver/udf/data/externalFunctions**

**Step 2** Restart the HetuEngine compute instance.

----End

## Using Hive UDFs

Use a client to access a Hive UDF:

1. Log in to the HetuEngine client. For details, see [Using the HetuEngine Client](#).
2. Run the following command to use a Hive UDF:

```
select AutoAddOne(1);
```

```
select AutoAddOne(1);
_col0
-----
      2
(1 row)
```

### 8.11.3 HetuEngine UDF Development and Application

You can customize functions to extend SQL statements to meet personalized requirements. These functions are called UDFs.

This section describes how to develop and apply HetuEngine UDFs.

#### Developing HetuEngine UDFs

This sample implements one HetuEngine UDF described in the following table.

**Table 8-53** HetuEngine UDF

Parameter	Description
AddTwo	Adds 2 to the input value and returns the result.

**Step 1** Create a Maven project. Set **groupId** to **com.test.udf** and **artifactId** to **udf-test**. The two values can be customized based on the site requirements.

**Step 2** Modify the **pom.xml** file as follows:

```
<project xmlns="http://maven.apache.org/POM/4.0.0" xmlns:xsi="http://www.w3.org/2001/XMLSchema-
instance" xsi:schemaLocation="http://maven.apache.org/POM/4.0.0 http://maven.apache.org/xsd/
maven-4.0.0.xsd">
  <modelVersion>4.0.0</modelVersion>
  <groupId>com.test.udf</groupId>
  <artifactId>udf-test</artifactId>
  <version>0.0.1-SNAPSHOT</version>

  <build>
    <plugins>
      <plugin>
        <artifactId>maven-shade-plugin</artifactId>
        <executions>
          <execution>
            <phase>package</phase>
            <goals>
              <goal>shade</goal>
            </goals>
          </execution>
        </executions>
      </plugin>
      <plugin>
        <artifactId>maven-resources-plugin</artifactId>
        <executions>
          <execution>
            <id>copy-resources</id>
            <phase>package</phase>
            <goals>
              <goal>copy-resources</goal>
            </goals>
            <configuration>
              <outputDirectory>${project.build.directory}</outputDirectory>
              <resources>
                <resource>
                  <directory>src/main/resources</directory>
                  <filtering>>false</filtering>
                </resource>
              </resources>
            </configuration>
          </execution>
        </executions>
      </plugin>
    </plugins>
  </build>
</project>
```

**Step 3** Create the implementation class of the HetuEngine UDF.

```
package com.xxx.bigdata.hetuengine.functions;

public class AddTwo {
    public Integer evaluate(Integer num) {
        return num + 2;
    }
}
```

**Step 4** Package the Maven project. The **udf-test-0.0.1-SNAPSHOT.jar** file in the **target** directory is the HetuEngine UDF function package.

----End

 NOTE

- A common HetuEngine UDF must implement at least one **evaluate()**. The **evaluate** function supports overloading.
- Currently, HetuEngine UDFs supports only less than or equal to five input parameters. HetuEngine UDFs with more than five input parameters will fail to be registered.
- (Optional) If the HetuEngine UDF depends on a configuration file, you are advised to save the configuration file as a resource file in the **resources** directory so that it can be packed into the HetuEngine UDF function package.

## Deploying HetuEngine UDFs

To use the HetuEngine UDF in HetuEngine, you need to upload the corresponding UDF function package to a specified HDFS directory, for example, **/udf/hetuserver**. The directory can be customized based on the site requirements.

Create the **/udf/hetuserver** directory and save the UDF function package to it.

- Upload the files on the HDFS page:
  - a. Log in to FusionInsight Manager using the HetuEngine username and choose **Cluster > Services > HDFS**.
  - b. In the **Basic Information** area on the **Dashboard** page, click the link next to **NameNode WebUI**.
  - c. Choose **Utilities > Browse the file system** and click  to create the **/udf/hetuserver** directory.
  - d. Go to the **/udf/hetuserver** directory and click  to upload UDF function package.
- Use the HDFS CLI to upload the files.
  - a. Log in to the node where the HDFS service client is located and switch to the client installation directory, for example, **/opt/client**.  
**cd /opt/client**
  - b. Run the following command to configure environment variables:  
**source bigdata\_env**
  - c. If the cluster is in security mode, run the following command to authenticate the user. In normal mode, skip user authentication.  
**kinitHetuEngineusername**  
Enter the password as prompted.
  - d. Run the following commands to create a directory and upload the prepared UDF function package to the target directory:  
**hdfs dfs -mkdir /udf/hetuserver**  
**hdfs dfs -put ./UDF function package /udf/hetuserver.**
  - e. Run the following command to change the permission of the UDF function package:  
**hdfs dfs -chmod 644 /udf/hetuserver/UDF function package**

### NOTICE

- When uploading a UDF JAR file to a user-defined HDFS directory, ensure that the user has the read permission on the JAR file. You are advised to use **chmod 644** to set the permission. In addition, if you want the UDF JAR file to be deleted during the HetuEngine service uninstallation, you can create a user-defined directory in the **/user/hetuserver/** directory.
- Currently, HetuEngine supports the UDF JAR file to be stored only in **hdfs://Resource URI** in HDFS.
- If the JAR file is re-uploaded due to function modification or addition, HetuEngine caches the classloader for 5 minutes by default. The JAR file does not take effect immediately, instead, it is updated and reloaded 5 minutes later.

## Using HetuEngine UDFs

Use a client to access a HetuEngine UDF.

1. Log in to the HetuEngine client. For details, see [Using the HetuEngine Client](#).
2. Create a HetuEngine UDF.

```
CREATE FUNCTION example.namespace01.add_two (
  num integer
)
RETURNS integer
LANGUAGE JAVA
DETERMINISTIC
SYMBOL "com.xxx.bigdata.hetuengine.functions.AddTwo"
URI "hdfs://hacluster/udf/hetuserver/udf-test-0.0.1-SNAPSHOT.jar";
```

3. Use the HetuEngine UDF.

```
select example.namespace01.add_two(2);
_col0
-----
  4
(1 row)
```

### NOTE

Overloading is used to distinguish functions with the same name in the implementation classes. Therefore, you need to specify different function names when creating a HetuEngine UDF.

## 8.12 Introduction to HetuEngine Logs

### Log Description

#### Log paths:

The HetuEngine logs are stored in **/var/log/Bigdata/hetuengine/** and **/var/log/Bigdata/audit/hetuengine/**.

#### Log archiving rules:

Log archiving rules use the FixedWindowRollingPolicy policy. The maximum size of a single file and the maximum number of log archive files can be configured. The rules are as follows:

- When the size of a single file exceeds the default maximum value, a new compressed archive file is generated. The naming rule of the compressed archive log file is as follows: *<Original log name>.[ID].log.gz*.
- When the number of log archive files reaches the maximum value, the earliest log file is deleted.

By default, the maximum size of an audit log file is 30 MB, and the maximum number of log archive files is 20.

By default, the maximum size of a run log file is 100 MB, and the maximum number of log archive files is 20.

To change the maximum size of a single run log file or audit log file or change the maximum number of log archive files of an instance, perform the following operations:

**Step 1** Log in to Manager.

**Step 2** Choose **Cluster > Services > HetuEngine > Configurations > All Configurations**.

**Step 3** In the parameter list of log levels, search for **logback.xml** to view the current run log and audit log configurations of HSBroker, HSConsole, and HSFabric.

**Step 4** Select the configuration item to be modified and modify it.

**Step 5** Click **Save**, and then click **OK**. The configuration automatically takes effect after about 30 seconds.

----End

**Table 8-54** Log list

Type	Name	Description
Installation, startup and stopping log	/var/log/Bigdata/hetuengine/hsbroker/prestart.log	HSBroker pre-processing script logs before startup
	/var/log/Bigdata/hetuengine/hsbroker/start.log	HSBroker Spring Boot startup logs
	/var/log/Bigdata/hetuengine/hsbroker/stop.log	HSBroker stop logs
	/var/log/Bigdata/hetuengine/hsbroker/postinstall.log	HSBroker post-installation logs
	/var/log/Bigdata/hetuengine/hsconsole/prestart.log	HSConsole pre-processing script logs before startup
	/var/log/Bigdata/hetuengine/hsconsole/start.log	HSConsole Spring Boot startup logs
	/var/log/Bigdata/hetuengine/hsconsole/stop.log	HSConsole stop logs
	/var/log/Bigdata/hetuengine/hsconsole/postinstall.log	HSConsole post-installation logs

Type	Name	Description
	/var/log/Bigdata/hetuengine/hsfabric/prestart.log	HSFabric preprocessing script logs before startup
	/var/log/Bigdata/hetuengine/hsfabric/start.log	HSFabric startup logs
	/var/log/Bigdata/hetuengine/hsfabric/stop.log	HSFabric stop logs
	/var/log/Bigdata/hetuengine/hsfabric/postinstall.log	HSFabric post-installation logs
Run log	/var/log/Bigdata/hetuengine/hsbroker/hsbroker.log	HSBroker run logs
	/var/log/Bigdata/hetuengine/hsconsole/hsconsole.log	HSConsole run logs
	/var/log/Bigdata/hetuengine/hsfabric/hsfabric.log	HSFabric run logs
	hdfs://hacluster/hetuserverhistory/ <i>Tenant/Coordinator or worker</i> /application_ID/container_ID/yyyyMMdd/server.log	Run logs of the HetuEngine compute instance
Status check log	/var/log/Bigdata/hetuengine/hsbroker/service_check.log	HSBroker health check logs
	/var/log/Bigdata/hetuengine/hsbroker/service_getstate.log	HSBroker status check logs
	/var/log/Bigdata/hetuengine/availability-check.log	Status check logs indicating whether the HetuEngine service is available
	/var/log/Bigdata/hetuengine/hsconsole/service_getstate.log	HSConsole status check logs
	/var/log/Bigdata/hetuengine/hsfabric/service_getstate.log	HSFabric status check logs
Audit log	/var/log/Bigdata/audit/hetuengine/hsbroker/hsbroker-audit.log	HSBroker audit logs
	/var/log/Bigdata/audit/hetuengine/hsconsole/hsconsole-audit.log	HSConsole audit logs
	hdfs://hacluster/hetuserverhistory/ <i>Tenant/coordinator/application_ID</i> /container_ID/yyyyMMdd/hetuserver-engine-audit.log	Audit logs of the HetuEngine compute instance
	/var/log/Bigdata/audit/hetuengine/hsfabric/hsfabric-audit.log	HSFabric audit logs

Type	Name	Description
Clean log	/var/log/Bigdata/hetuengine/hsbroker/cleanup.log	HSBroker cleanup script logs
	/var/log/Bigdata/hetuengine/hconsole/cleanup.log	HSConsole cleanup script logs
	/var/log/Bigdata/hetuengine/hsfabric/cleanup.log	HSFabric cleanup script logs
Initialization log	/var/log/Bigdata/hetuengine/hsbroker/hetupg.log	HSBroker metadata initialization logs
	/var/log/Bigdata/hetuengine/hconsole/hetupg.log	HSConsole connection metadata logs.
	/var/log/Bigdata/hetuengine/ranger-presto-plugin-enable.log	Operation logs generated when the Ranger plug-in is integrated into the HetuEngine kernel.

## Log Level

**Table 8-55** describes the log levels provided by HetuEngine. The priorities of log levels are OFF, ERROR, WARN, INFO, and DEBUG in descending order. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 8-55** Log levels

Level	Description
OFF	Logs of this level record no logs.
ERROR	Logs of this level record error information about the current event processing.
WARN	Logs of this level record exception information about the current event processing.
INFO	Logs of this level record normal running status information about the system and events.
DEBUG	Logs of this level record the system information and system debugging information.

To change the run log or audit log level of an instance, perform the following steps:

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Services > HetuEngine > Configurations > All Configurations**.

**Step 3** In the parameter list of log levels, search for **logback.xml** to view the current run log and audit log levels of HSBroker, HSConsole, and HSFabric.

**Step 4** Select a desired log level.

**Step 5** Click **Save**, and then click **OK**. The configuration automatically takes effect after about 30 seconds.

----End

To change the HetuEngine Coordinator/Worker log level, perform the following steps:

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Services > HetuEngine > Configurations > All Configurations**.

**Step 3** In the parameter list of log levels, search for **log.properties** to view the current log levels.

**Step 4** Select a desired log level.

**Step 5** Click **Save**, and then click **OK**. Wait until the operation is successful.

**Step 6** Choose **Cluster > Services > HetuEngine > Instance**, click the HSBroker instance in the role list, and choose **More > Restart Instance**.

**Step 7** After the HSBroker instance is restarted, choose **Cluster > Services > HetuEngine**. On the overview page, click the link next to **HSConsole WebUI** to go to the compute instance page.

**Step 8** Select a compute instance and click **Stop**. After the instance is stopped, click **Start** to restart it.

----End

## 8.13 HetuEngine Performance Tuning

### 8.13.1 Adjusting the Yarn Service Configuration

#### Scenario

HetuEngine depends on the resource allocation and control capabilities provided by Yarn. You need to adjust the Yarn service configuration based on the actual service and cluster server configuration to achieve the optimal performance.

#### Procedure

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Services > Yarn > Configurations > All Configurations** and set Yarn service parameters by referring to [Table 8-56](#).

**Table 8-56** Yarn configuration parameters

Parameter	Default Value	Recommended Value
yarn.nodemanager.resource.memory-mb	16384	To achieve the optimal performance, set this parameter to 90% of the minimum physical memory of the node in the cluster.
yarn.nodemanager.resource.cpu-vcores	8	To achieve the optimal performance, set this parameter to the minimum number of vCores of the node in the cluster.
yarn.scheduler.maximum-allocation-mb	65536	To achieve the optimal performance, set this parameter to 90% of the minimum physical memory of the node in the cluster.
yarn.scheduler.maximum-allocation-vcores	32	To achieve the optimal performance, set this parameter to the minimum number of vCores of the node in the cluster.

**Step 3** Click **Save**.

**Step 4** Choose **Cluster > Services > Yarn > More > Restart Service** to restart the Yarn service for the parameters to take effect.

----End

## 8.13.2 Adjusting Cluster Node Resource Configurations

### Scenario

The default memory size and disk overflow path of HetuEngine are not the best. You need to adjust node resources in the cluster based on the actual service and server configuration of the cluster to achieve the optimal performance.

### Procedure

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Services > HetuEngine > Configurations > All Configurations** and adjust the cluster node resource parameters by referring to [Table 8-57](#).

**Table 8-57** Parameters for configuring cluster node resources

Parameter	Default Value	Recommended Value	Description	Parameter File
yarn.hetuserver.engine.coordinator.memory	5120	At least 2 GB less than that of <b>yarn.scheduler.maximum-allocation-mb</b>	Memory size used by a Coordinator node	application.properties
yarn.hetuserver.engine.coordinator.number-of-containers	2	2	Number of Coordinator nodes	application.properties
yarn.hetuserver.engine.coordinator.number-of-cpus	1	At least two vCores less than <b>yarn.scheduler.maximum-allocation-vcores</b>	CPU vCores used by a Coordinator node	application.properties
yarn.hetuserver.engine.worker.memory	10240	At least 2 GB less than that of <b>yarn.scheduler.maximum-allocation-mb</b>	Memory size used by a worker node	application.properties
yarn.hetuserver.engine.worker.number-of-containers	2	Adjusted based on application requirements	Number of worker nodes	application.properties
yarn.hetuserver.engine.worker.number-of-cpus	1	At least two vCores less than <b>yarn.scheduler.maximum-allocation-vcores</b>	CPU vCores used by a Worker node	application.properties

Parameter	Default Value	Recommended Value	Description	Parameter File
<b>Xmx</b> size in the <b>extraJavaOptions</b> parameter	8GB	Max ( <i>Memory size used by a Worker node</i> – 30 GB, <i>Memory size used by a Worker node</i> x 0.7)	Maximum available memory of the worker JVM process	worker.jvm.config
query.max-memory-per-node	5GB	Worker JVM x 0.7	Maximum available memory of a Query node	worker.config.properties
query.max-total-memory-per-node	5GB	Worker JVM x 0.7	Maximum available memory of a Query + System node	worker.config.properties
memory.heap-headroom-per-node	3 GB	Worker JVM x 0.3	Maximum available memory of a system heap node	worker.config.properties
<b>Xmx</b> size in the <b>extraJavaOptions</b> parameter	4GB	Max ( <i>Memory size used by a Coordinator node</i> – 30 GB, <i>Memory size used by a Coordinator node</i> x 0.7)	Maximum available memory of the Coordinator JVM process	coordinator.jvm.config
query.max-memory-per-node	3GB	Coordinator JVM x 0.7	Maximum memory that can be used for node query	coordinator.config.properties
query.max-total-memory-per-node	3GB	Coordinator JVM x 0.7	Maximum available memory of a Query + System node	coordinator.config.properties
memory.heap-headroom-per-node	1GB	Coordinator JVM x 0.3	Maximum available memory of a system heap node	coordinator.config.properties

Parameter	Default Value	Recommended Value	Description	Parameter File
query.max-memory	7GB	Sum(query.max-memory-per-node) x 0.7	Maximum available memory of a Query cluster	worker.config.properties/coordinator.config.properties
experimental.spiller-spill-path	CONTAINER_ROOT_PATH/tmp/hetuserver/hetuserver-sqlengine/	One or more independent SSDs	Disk output file path	worker.config.properties/coordinator.config.properties
experimental.max-spill-per-node	10 GB	Sum(Available space of each node) x 50%	Available disk space for storing output files of all queries on a node	worker.config.properties/coordinator.config.properties
experimental.query-max-spill-per-node	10 GB	80% of the available disk space on a node	Available disk space for storing output files of a query on a node	worker.config.properties/coordinator.config.properties

**Step 3** Click **Save**.

**Step 4** Choose **Cluster > Services > HetuEngine > More > Restart Service** to restart the HetuEngine service for the parameters to take effect.

----End

### 8.13.3 Adjusting Execution Plan Cache

#### Scenario

HetuEngine provides the execution plan cache function. For the same query that needs to be executed for multiple times, this function reduces the time required for generating the execution plans for the same query.

#### Procedure

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Services > HetuEngine > Configurations > All Configurations** and adjust the execution plan cache parameters by referring to [Table 8-58](#).

**Table 8-58** Execution plan cache parameters

Parameter	Default Value	Recommended Value	Description	Parameter File
hetu.executionplan.cache.enabled	false	true	Indicates whether to enable the global execution plan cache.	<b>coordinator.config.properties</b> and <b>worker.config.properties</b>
hetu.executionplan.cache.limit	20000	Adjust the value based on application requirements.	Indicates the maximum number of execution plans that can be cached.	<b>coordinator.config.properties</b> and <b>worker.config.properties</b>
hetu.executionplan.cache.timeout	86400000	Adjust the value based on application requirements.	Indicates the timeout interval of the cached execution plan since the last access, in milliseconds.	<b>coordinator.config.properties</b> and <b>worker.config.properties</b>

**Step 3** Click **Save**.

**Step 4** Choose **Cluster > Services > HetuEngine > More > Restart Service** to restart the HetuEngine service for the parameters to take effect.

----End

## 8.13.4 Adjusting Metadata Cache

### Scenario

When HetuEngine accesses the Hive data source, it needs to access the Hive metastore to obtain the metadata information. HetuEngine provides the metadata cache function. When the database or table of the Hive data source is accessed for the first time, the metadata information (database name, table name, table field, partition information, and permission information) of the database or table is cached, the Hive metastore does not need to be accessed again during subsequent access. If the table data of the Hive data source does not change frequently, the query performance can be improved to some extent.

### Procedure

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Services > HetuEngine > Configurations > All Configurations** and adjust the metadata cache parameters by referring to [Table 8-59](#).

**Table 8-59** Metadata cache parameters

Parameter	Description	Default Value	Parameter File
hive.metastore-cache-ttl	Cache duration of the metadata of the co-deployed Hive data source.	0s	hive.properties
hive.metastore-cache-maximum-size	Maximum cache size of the metadata of the co-deployed Hive data source.	10000	hive.properties
hive.metastore-refresh-interval	Interval for refreshing the metadata of the co-deployed Hive data source.	1s	hive.properties
hive.per-transaction-metastore-cache-maximum-size	Maximum cache size of the metadata for each transaction of the co-deployed Hive data source.	1000	hive.properties

**Step 3** Click **Save**.

**Step 4** Choose **Cluster > Services > HetuEngine > More > Restart Service** to restart the HetuEngine service for the parameters to take effect.

----End

## 8.13.5 Modifying the CTE Configuration

### Scenario

If a table or common table expression (CTE) contained in a query appears multiple times and has the same projection and filter, you can enable the CTE reuse function to cache data in memory. In this way, you do not need to read data from disks for multiple times, reducing the time required for query execution.

### Procedure

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster > Services > HetuEngine > Configurations > All Configurations** and configure related parameters by referring to [Table 8-60](#).

**Table 8-60** CTE configuration parameters

Parameter	Description	Recommended Value	Default Value	Parameter File
optimizer.reuse-table-scan	Whether to enable the CTE table data reuse function.	true	false	<b>coordinator.config.properties</b> and <b>worker.config.properties</b>
experimental.spill-reuse-tablescan	Whether to enable the function of spilling memory to disks during tablescan reuse.	true	false	<b>coordinator.config.properties</b> and <b>worker.config.properties</b>
optimizer.cte-reuse-enabled	Whether to enable CTE reuse. If this function is enabled, CTE is executed only once irrespective of the number of times the same CTE is being used in the main query.	true	false	<b>coordinator.config.properties</b> and <b>worker.config.properties</b>
dynamic-filtering-max-per-driver-size	Maximum volume of data that can be collected by each driver when dynamic filtering starts.	100 MB	1MB	<b>coordinator.config.properties</b> and <b>worker.config.properties</b>

**Step 3** Click **Save**.

**Step 4** Choose **Cluster > Services > HetuEngine > More > Restart Service** and enter the password to restart the HetuEngine service for the parameters to take effect.

----End

## 8.14 Common Issues About HetuEngine

## 8.14.1 How Do I Perform Operations After the Domain Name Is Changed?

### Question

After the domain name is changed, the installed client configuration and data source configuration become invalid, and the created cluster is unavailable. When data sources in different domains are interconnected, HetuEngine automatically combines the **krb5.conf** file. After the domain name is changed, the domain name for Kerberos authentication changes. As a result, the information about the interconnected data source becomes invalid.

### Answer

- You need to reinstall the cluster client.
- Delete the old data source information on HSConsole by referring to [Managing Data Sources](#) and configure the data source information on the HSConsole again by referring to [Configuring Data Sources](#).

## 8.14.2 What Do I Do If Starting a Cluster on the Client Times Out?

### Question

If the cluster startup on the client takes a long time, the waiting times out and the waiting page exits.

### Answer

If the cluster startup times out, the waiting page automatically exits. You can log in to the cluster again until the cluster is successfully started. Additionally, you can also view the cluster running status on the HSConsole page. When the cluster is in the running state, log in to the cluster again. If the cluster fails to be started, you can locate the fault based on the startup logs. For details, see [Log Description](#).

## 8.14.3 How Do I Handle Data Source Loss?

### Question

Why is the data source lost when I log in to the client to check the data source connected to the HSConsole page?

### Answer

The possible cause of data source loss is that the DBService active/standby switchover occurs or the database connection usage exceeds the threshold. You can log in to FusionInsight Manager to view the alarm information and clear the DBService alarm based on the alarm guide.

## 8.14.4 How Do I Handle HetuEngine Alarms?

### Question

Log in to FusionInsight Manager and HetuEngine alarms are generated for the cluster.

### Answer

Log in to FusionInsight Manager, go to the O&M page, and view alarm details. You can click the drop-down button of an alarm to view the alarm details. For most alarms, you can locate and handle them based on the alarm causes in the alarm details. You can also view the online help information about an alarm by using the alarm help function. If the alarm is not automatically cleared, you can manually clear it after troubleshooting.

1. Log in to FusionInsight Manager.
2. Choose **O&M > Alarm > Alarms**.
3. View alarm details in the alarm list.
4. Locate the row that contains the alarm and click **View Help** in the **Operation** column to obtain more help information.
5. Locate the fault based on the possible causes provided in the online help and clear the HetuEngine alarms based on the handling procedure provided in the online help.

## 8.14.5 How Do I Do If Coordinators and Workers Cannot Be Started on the New Node?

### Question

A new host is added to the cluster in security mode, the NodeManager instance is added, and the parameters of the HetuEngine compute instance are adjusted. After the HetuEngine compute instance is restarted, the Coordinators and Workers of the HetuEngine compute instance cannot be started on the new host.

### Answer

In security mode, the internal communication between nodes of HetuEngine compute instances uses the Simple and Protected GSS API Negotiation Mechanism (SPNEGO) authentication. The JKS certificate is required. It contains information about all nodes in the compute instance. The information about the newly added nodes is not contained in the original certificate. You need to restart all HetuEngine HSBroker instances to generate a new certificate, and then restart the HetuEngine compute instance.

# 9 Using Hive

## 9.1 Using Hive from Scratch

Hive is a data warehouse framework built on Hadoop. It maps structured data files to a database table and provides SQL-like functions to analyze and process data. It also allows you to quickly perform simple MapReduce statistics using SQL-like statements without the need of developing a specific MapReduce application. It is suitable for statistical analysis of data warehouses.

### Background

Suppose a user develops an application to manage users who use service A in an enterprise. The procedure of operating service A on the Hive client is as follows:

#### Operations on common tables:

- Create the **user\_info** table.
- Add users' educational backgrounds and professional titles to the table.
- Query user names and addresses by user ID.
- Delete the user information table after service A ends.

**Table 9-1** User information

ID	Name	Gender	Age	Address
12005000201	A	Male	19	City A
12005000202	B	Female	23	City B
12005000203	C	Male	26	City C
12005000204	D	Male	18	City D
12005000205	E	Female	21	City E
12005000206	F	Male	32	City F
12005000207	G	Female	29	City G

ID	Name	Gender	Age	Address
12005000208	H	Female	30	City H
12005000209	I	Male	26	City I
12005000210	J	Female	25	City J

## Procedure

**Step 1** Download the client configuration file.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Dashboard** > **More** > **Download Client**.
3. Download the cluster client.
4. Set **Select Client Type** to **Configuration Files Only**, select a platform type, and click **OK** to generate the client configuration file which is then saved in the `/tmp/FusionInsight-Client/` directory on the active management node by default.

**Step 2** Log in to the active management node of Manager.

1. Log in to any node where Manager is deployed as user **root**.
2. Run the following command to identify the active and standby nodes:

```
sh ${BIGDATA_HOME}/om-server/om/sbin/status-oms.sh
```

In the command output, the value of **HAActive** for the active management node is **active**, and that for the standby management node is **standby**. In the following example, **node-master1** is the active management node, and **node-master2** is the standby management node.

```
HAMode
double
NodeName      HostName      HAVersion      StartTime      HAActive
HAAllResOK    HARunPhase
192-168-0-30  node-master1  V100R001C01    2020-05-01 23:43:02  active
normal        Activated
192-168-0-24  node-master2  V100R001C01    2020-05-01 07:14:02  standby
normal        Deactivated
```

3. Log in to the primary management node as user **root** and run the following command to switch to user **omm**:

```
sudo su - omm
```

**Step 3** Run the following command to go to the client installation directory:

```
cd /opt/client
```

The cluster client has been installed in advance. The following client installation directory is used as an example. Change it based on the site requirements.

**Step 4** Run the following command to update the client configuration for the active management node.

```
sh refreshConfig.sh /opt/client Full path of the client configuration file package
```

For example, run the following command:

```
sh refreshConfig.sh /opt/client /tmp/FusionInsight-Client/  
FusionInsight_Cluster_1_Services_Client.tar
```

If the following information is displayed, the configurations have been updated successfully.

```
ReFresh components client config is complete.  
Succeed to refresh components client config.
```

 **NOTE**

You can refer to Method 2 in to perform operations in steps [Step 1](#) to [Step 4](#).

**Step 5** Use the client on a Master node.

1. On the active management node, for example, **192-168-0-30**, run the following command to switch to the client directory, for example, **/opt/client**.

```
cd /opt/client
```

2. Run the following command to configure environment variables:

```
source bigdata_env
```

3. If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the current user:

```
kinit MRS cluster user
```

Example: user **kinit hiveuser**

The current user must have the permission to create Hive tables. To create a role with the permission, refer to . To bind the role to the current user, refer to . If Kerberos authentication is disabled, skip this step.

4. Run the client command of the Hive component directly.

```
beeline
```

**Step 6** Run the Hive client command to implement service A.

**Operations on internal tables:**

1. Create the **user\_info** user information table according to [Table 9-1](#) and add data to it.

```
create table user_info(id string,name string,gender string,age int,addr  
string);
```

```
insert into table user_info(id,name,gender,age,addr)  
values("12005000201","A","Male",19,"City A");
```

2. Add users' educational backgrounds and professional titles to the **user\_info** table.

For example, to add educational background and title information about user 12005000201, run the following command:

```
alter table user_info add columns(education string,technical string);
```

3. Query user names and addresses by user ID.

For example, to query the name and address of user 12005000201, run the following command:

```
select name,addr from user_info where id='12005000201';
```

4. Delete the user information table.

```
drop table user_info;
```

#### Operations on external partition tables:

Create an external partition table and import data.

1. Create a path for storing external table data.

```
hdfs dfs -mkdir /hive/user_info
```

2. Create a table.

```
create external table user_info(id string,name string,gender string,age  
int,addr string) partitioned by(year string) row format delimited fields  
terminated by ' ' lines terminated by '\n' stored as textfile location '/hive/  
user_info';
```

#### NOTE

**fields terminated** indicates delimiters, for example, spaces.

**lines terminated** indicates line breaks, for example, \n.

**/hive/user\_info** indicates the path of the data file.

3. Import data.

- a. Execute the insert statement to insert data.

```
insert into user_info partition(year="2018") values  
("12005000201","A","Male",19,"City A");
```

- b. Run the **load data** command to import file data.

- i. Create a file based on the data in [Table 9-1](#). For example, the file name is **txt.log**. Fields are separated by space, and the line feed characters are used as the line breaks.

- ii. Upload the file to HDFS.

```
hdfs dfs -put txt.log /tmp
```

- iii. Load data to the table.

```
load data inpath '/tmp/txt.log' into table user_info partition  
(year='2011');
```

4. Query the imported data.

```
select * from user_info;
```

5. Delete the user information table.

```
drop table user_info;
```

----End

## 9.2 Configuring Hive Parameters

### Navigation Path

Go to the Hive configurations page by referring to [Modifying Cluster Service Configuration Parameters](#).

## Parameter Description

**Table 9-2** Hive parameter description

Parameter	Description	Default Value
hive.auto.convert.join	Whether Hive converts common <b>join</b> to <b>mapjoin</b> based on the input file size.  When Hive is used to query a join table, whatever the table size is (if the data in the join table is less than 24 MB, it is a small one), set this parameter to <b>false</b> . If this parameter is set to <b>true</b> , new <b>mapjoin</b> cannot be generated when you query a join table.	Possible values are as follows: <ul style="list-style-type: none"> <li>• true</li> <li>• false</li> </ul> The default value is <b>true</b> .
hive.default.fileformat	Indicates the default file format used by Hive.	RCFile
hive.exec.reducers.max	Indicates the maximum number of reducers in a MapReduce job submitted by Hive.	999
hive.server2.thrift.max.worker.threads	Indicates the maximum number of threads that can be started in the HiveServer internal thread pool.	1,000
hive.server2.thrift.min.worker.threads	Indicates the number of threads started during initialization in the HiveServer internal thread pool.	5
hive.hbase.delete.mode.enabled	Indicates whether to enable the function of deleting HBase records from Hive. If this function is enabled, you can use <b>remove table xx where xxx</b> to delete HBase records from Hive.	true
hive.metastore.server.min.threads	Indicates the number of threads started by MetaStore for processing connections. If the number of threads is more than the set value, MetaStore always maintains a number of threads that is not lower than the set value, that is, the number of resident threads in the MetaStore thread pool is always higher than the set value.	200

Parameter	Description	Default Value
hive.server2.enable.doAs	Indicates whether to simulate client users during sessions between HiveServer2 and other services (such as Yarn and HDFS). If you change the configuration item from <b>false</b> to <b>true</b> , users with only the column permission lose the permissions to access corresponding tables.	true

### 9.3 Hive SQL

Hive SQL supports all features of Hive-3.1.0. For details, see <https://cwiki.apache.org/confluence/display/hive/languagemanual>.

**Table 9-3** describes the extended Hive statements provided by .

**Table 9-3** Extended Hive statements

Extended Syntax	Syntax Description	Syntax Example	Example Description
<pre>CREATE [TEMPORARY] [EXTERNAL] TABLE [IF NOT EXISTS] [db_name.]table_ name (col_name data_type [COMMENT col_comment], ...) [ROW FORMAT row_format] [STORED AS file_format]   STORED BY 'storage.handler.cl ass.name' [WITH SERDEPROPERTIE S (...) ] ..... [TBLPROPERTIES ("groupId"=" group1 ","locatorId"="loc ator1")] ...;</pre>	<p>The statement is used to create a Hive table and specify locators on which table data files locate. For details, see <a href="#">Using HDFS Colocation to Store Hive Tables</a>.</p>	<pre>CREATE TABLE tab1 (id INT, name STRING) row format delimited fields terminated by '\t' stored as RCFILE TBLPROPERTIES(" groupId"=" group1 ","locatorId"="loc ator1");</pre>	<p>The statement is used to create table <b>tab1</b> and specify locator1 on which the table data of <b>tab1</b> locates.</p>

Extended Syntax	Syntax Description	Syntax Example	Example Description
<pre>CREATE [TEMPORARY] [EXTERNAL] TABLE [IF NOT EXISTS] [db_name.]table_name (col_name data_type [COMMENT col_comment], ...) [ROW FORMAT row_format] [STORED AS file_format]   STORED BY 'storage.handler.class.name' [WITH SERDEPROPERTIES (...)] ... [TBLPROPERTIES ('column.encode.columns'='col_name1,col_name2'  'column.encode.indices'='col_id1,col_id2', 'column.encode.classname'='encode_classname')]...;</pre>	<p>The statement is used to create a hive table and specify the table encryption column and encryption algorithm. For details, see <a href="#">Using the Hive Column Encryption Function</a>.</p>	<pre>create table encode_test(id INT, name STRING, phone STRING, address STRING) ROW FORMAT SERDE 'org.apache.hadoop p.hive.serde2.lazy. LazySimpleSerDe' WITH SERDEPROPERTIES S ('column.encode.i ndices'='2,3', 'column.encode.cl assname'='org.apa che.hadoop.hive.s erde2.SMS4Rewrit er') STORED AS TEXTFILE;</pre>	<p>The statement is used to create table <b>encode_test</b> and specify that column 2 and column 3 will be encrypted using the <b>org.apache.hadoop.hive.serde2.SMS4Rewriter</b> encryption algorithm class during data insertion.</p>
<pre>REMOVE TABLE hbase_tablename [WHERE where_condition];</pre>	<p>The statement is used to delete data that meets criteria from the Hive on HBase table. For details, see <a href="#">Deleting Single-Row Records from Hive on HBase</a>.</p>	<pre>remove table hbase_table1 where id = 1;</pre>	<p>The statement is used to delete data that meets the criterion of "id = 1" from the table.</p>

Extended Syntax	Syntax Description	Syntax Example	Example Description
<pre>CREATE [TEMPORARY] [EXTERNAL] TABLE [IF NOT EXISTS] [db_name.]table_ name (col_name data_type [COMMENT col_comment], ...) [ROW FORMAT row_format] <b>STORED AS inputformat 'org.apache.hado op.hive.contrib.fil eformat.Specifie dDelimiterInput- Format' outputformat 'org.apache.hadoo p.hive ql.io.HiveIg noreKeyTextOutpu tFormat';</b></pre>	<p>The statement is used to create a hive table and specify that the table supports customized row delimiters. For details, see <a href="#">Customizing Row Separators</a>.</p>	<pre>create table blu(time string, num string, msg string) row format delimited fields terminated by ',' <b>stored as inputformat 'org.apache.hado op.hive.contrib.fil eformat.Specifie dDelimiterInput- Format' outputformat 'org.apache.hadoo p.hive ql.io.HiveIg noreKeyTextOutpu tFormat';</b></pre>	<p>The statement is used to create table <b>blu</b> and set <b>inputformat</b> to <b>SpecifiedDelimiterInputFormat</b> so that the query row delimiter can be specified during the query.</p>

## 9.4 Permission Management

### 9.4.1 Hive Permission

Hive is a data warehouse framework built on Hadoop. It provides basic data analysis services using the Hive query language (HQL), a language like the structured query language (SQL).

MRS supports users, user groups, and roles. Permissions must be assigned to roles and then roles are bound to users or user groups. Users can obtain permissions only by binding a role or joining a group that is bound with a role. For details about Hive authorization, visit <https://cwiki.apache.org/confluence/display/Hive/LanguageManual+Authorization>.

#### NOTE

- Hive permissions in security mode need to be managed whereas those in normal mode do not.
- If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. For details, see [Adding a Ranger Access Permission Policy for Hive](#).

## Hive Permission Model

To use the Hive component, users must have permissions on Hive databases and tables (including external tables and views). In MRS, the complete Hive permission model is composed of Hive metadata permission and HDFS file permission. The Hive permission model also includes the permission to use databases or tables.

- Hive metadata permission

Similar to traditional relational databases, the Hive database of MRS supports the **CREATE** and **SELECT** permission, and the Hive tables and columns support the **SELECT**, **INSERT**, and **DELETE** permissions. Hive also supports the permissions of **OWNERSHIP** and **Hive Admin Privilege**.

- Hive data file permission, also known as HDFS file permission

Hive database and table files are stored in the HDFS. The created databases or tables are saved in the **/user/hive/warehouse** directory of the HDFS by default. The system automatically creates subdirectories named after database names and database table names. To access a database or a table, the corresponding file permissions (read, write, and execute) on the HDFS are required.

To perform various operations on Hive databases or tables, you need to associate the metadata permission with the HDFS file permission. For example, to query Hive data tables, you need to associate the metadata permission **SELECT** and the HDFS file permissions **Read** and **Write**.

To use the role management function of Manager GUI to manage the permissions of Hive databases and tables, you only need to configure the metadata permission, and the system will automatically associate and configure the HDFS file permission. In this way, operations on the interface are simplified, and the efficiency is improved.

## Hive Users

MRS provides users and roles to use Hive, such as creating tables, inserting data into tables, and querying tables. Hive defines the **USER** class, corresponding to user instances. Hive defines the **GROUP** class, corresponding to role instances.

You can use Manager to set permissions for Hive users. This method only supports permission setting in roles. A user or user group can obtain the permissions only after a role is bound to the user or user group. Hive users can be granted administrator permissions and permissions to access databases, tables, and columns.

## Hive Usage Scenarios and Related Permissions

Creating a database with Hive requires users to join in the **hive** group, without granting a role. Users have all permissions on the databases or tables created by themselves in Hive or HDFS. They can create tables, select, delete, insert, or update data, and grant permissions to other users to allow them to access the tables and corresponding HDFS directories and files.

A user can access the tables or database only with permissions. The permission required by users varies according to Hive usage scenarios.

**Table 9-4** Hive usage scenarios

Typical Scenario	Permission
Using Hive tables, columns, or databases	<p>Permissions required in different scenarios are as follows:</p> <ul style="list-style-type: none"> <li>• To create tables, the <b>CREATE</b> permission is required.</li> <li>• To query data, the <b>SELECT</b> permission is required.</li> <li>• To insert data, the <b>INSERT</b> permission is required.</li> <li>• To delete data, the <b>DELETE</b> permission is required.</li> </ul>
Associating and using other components	<p>In addition to Hive permissions, permissions of other components are required in some scenarios, for example:</p> <ul style="list-style-type: none"> <li>• Yarn permissions are required when some HQL statements, such as <b>insert, count, distinct, group by, order by, sort by,</b> and <b>join,</b> are run. You are advised to grant Yarn permissions to the role of each Hive user.</li> <li>• HBase permission is required when Hive over HBase is used, for example, querying HBase table data in Hive.</li> </ul>

In some special Hive usage scenarios, you need to configure other types of permission.

**Table 9-5** Hive authorization precautions

Scenario	Permission
Creating Hive databases, tables, and external tables, or adding partitions to created Hive tables or external tables when data files specified by Hive users are saved to other HDFS directories except <b>/user/hive/warehouse</b>	<p>The directory must already exist, the Hive user must be the owner of the directory, and the Hive user must have the read, write, and execute permissions on the directory. The user must have the <b>read</b> and <b>write</b> permissions of all the upper-layer directories of the directory. After an administrator grants the Hive permission to the role, the HDFS permission is automatically granted.</p>

Scenario	Permission
<p>Using <b>load</b> to load data from all the files or specified files in a specified directory to Hive tables as a Hive user</p>	<ul style="list-style-type: none"> <li>• The data source is a Linux local disk, the specified directory exists, and the system user <b>omm</b> has read and execute permission of the directory and all its upper-layer directories. The specified file exists, and user <b>omm</b> has read permission of the file and has the read and execute permission of all the upper-layer directories of the file.</li> <li>• The data source is HDFS, the specified directory exists, and the Hive user is the owner of the directory and has read, write, and execute permission on the directory and its subdirectories, and has read and write permission on all its upper-layer directories. The specified file exists, and the Hive user is the owner of the file and has read, write, and execute permission, and has read and execute permission on the file and all its upper-layer directories.</li> </ul> <p><b>NOTE</b> When <b>load</b> is used to import data to a Linux local disk, files must be loaded to the HiveServer on which the command is run and the permission must be modified. You are advised to run the command on a client. The HiveServer to which the client is connected can be found. For example, if the Hive client displays <b>0:</b> <b>jdbc:hive2://10.172.0.43:21066/&gt;</b>, the IP address of the connected HiveServer is 10.172.0.43.</p>
<p>Creating or deleting functions or modifying any database</p>	<p>The <b>Hive Admin Privilege</b> is required.</p>
<p>Performing operations on all databases and tables in Hive</p>	<p>The user must be added to the <b>supergroup</b> user group and granted <b>Hive Admin Privilege</b>.</p>

## 9.4.2 Creating a Hive Role

### Scenario

This section describes how to create and configure a Hive role on Manager as the system administrator. The Hive role can be granted the permissions of the Hive administrator and the permissions to operate Hive table data.

Creating a database with Hive requires users to join in the **hive** group, without granting a role. Users have all permissions on the databases or tables created by themselves in Hive or HDFS. They can create tables, select, delete, insert, or update data, and grant permissions to other users to allow them to access the tables and corresponding HDFS directories and files. The created databases or tables are saved in the **/user/hive/warehouse** directory of the HDFS by default.

 **NOTE**

- A Hive role can be created only in security mode.
- If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. For details, see [Adding a Ranger Access Permission Policy for Hive](#).

## Prerequisites

- The system administrator has understood the service requirements.
- Log in to FusionInsight Manager.
- The Hive client has been installed.

## Procedure

**Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).

**Step 2** Choose **System > Permission > Role**.

**Step 3** Click **Create Role**, and set **Role Name** and **Description**.

**Step 4** Set **Configure Resource Permission**. For details, see [Table 9-6](#).

- **Hive Admin Privilege:** Hive administrator permission.
- **Hive Read Write Privileges:** Hive data table management permission, which is the operation permission to set and manage the data of created tables.

 **NOTE**

- Hive role management supports the administrator permissions and the permission of accessing databases, tables, and views.
- The permissions of the Hive administrator do not include the permission to manage HDFS.
- If there are too many tables in the database or too many files in tables, the permission granting may last a while. For example, if a table contains 10,000 files, the permission granting lasts about 2 minutes.

**Table 9-6** Setting a role

Task	Role Authorization
Setting the Hive administrator permission	<p>In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Hive</b> and select <b>Hive Admin Privilege</b>.</p> <p><b>NOTE</b> After being bound to the Hive administrator role, perform the following operations during each maintenance operation:</p> <ol style="list-style-type: none"> <li>1. Log in to the node where the Hive client is installed as the client installation user.</li> <li>2. Run the following command to configure environment variables: For example, if the Hive client installation directory is <code>/opt/hiveclient</code>, run <code>source /opt/hiveclient/bigdata_env</code>.</li> <li>3. Run the following command to authenticate the user: <code>kinit Hive service user</code></li> <li>4. Run the following command to log in to the client tool: <code>beeline</code></li> <li>5. Run the following command to update the administrator permissions: <code>set role admin;</code></li> </ol>
Setting the permission to query a table of another user in the default database	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Hive</b> &gt; <b>Hive Read Write Privileges</b>.</li> <li>2. Click the name of the specified database in the database list. Tables in the database are displayed.</li> <li>3. In the <b>Rights</b> column of the specified table, choose <b>Select</b>.</li> </ol>
Setting the permission to query a table of another user in the default database	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Hive</b> &gt; <b>Hive Read Write Privileges</b>.</li> <li>2. Click the name of the specified database in the database list. Tables in the database are displayed.</li> <li>3. In the <b>Permission</b> column of the specified table, select <b>INSERT</b>.</li> </ol>

Task	Role Authorization
Setting the permission to import data to a table of another user in the default database	<ol style="list-style-type: none"> <li>In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Hive</b> &gt; <b>Hive Read Write Privileges</b>.</li> <li>Click the name of the specified database in the database list. Tables in the database are displayed.</li> <li>In the <b>Permission</b> column of the specified indexes, select <b>DELETE</b> and <b>INSERT</b>.</li> </ol>
Setting the permission to submit HQL commands to Yarn for execution	<p>The HQL commands used by some services are converted into MapReduce tasks and submitted to Yarn for execution. You need to set the Yarn permissions. For example, the HQL statements to be run use statements, such as <b>insert</b>, <b>count</b>, <b>distinct</b>, <b>group by</b>, <b>order by</b>, <b>sort by</b>, or <b>join</b>.</p> <ol style="list-style-type: none"> <li>In the <b>Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Yarn</b> &gt; <b>Scheduling Queue</b> &gt; <b>root</b>.</li> <li>In the <b>Permission</b> column of the <b>default</b> queue, select <b>Submit</b>.</li> </ol>

**Step 5** Click **OK**, and return to the **Role** page.

----End

### 9.4.3 Configuring Permissions for Hive Tables, Columns, or Databases

#### Scenario

You can configure related permissions if you need to access tables or databases created by other users. Hive supports column-based permission control. If a user needs to access some columns in tables created by other users, the user must be granted the permission for columns. The following describes how to grant table, column, and database permissions to users by using the role management function of MRS Manager.

 **NOTE**

- You can configure permissions for Hive tables, columns, or databases only in security mode.
- If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. For details, see [Adding a Ranger Access Permission Policy for Hive](#).

## Prerequisites

- You have obtained a user account with the administrator permissions, such as **admin**.
- You have created a role, for example, **hrole**, on Manager by referring to instructions in [Creating a Hive Role](#). You do not need to set the Hive permission but need to set the permission to submit the HQL command to Yarn for execution.
- You have created two Hive human-machine users, such as **huser1** and **huser2**, on Manager and added them to the **hive** group. **huser2** has been bound to **hrole**. The **hdb** database has created by user **huser1** and the **htable** table has been created in the database.

## Procedure

- Granting Table Permissions  
Users have complete permission on the tables created by themselves in Hive and the HDFS. To access the tables created by others, they need to be granted the permission. After the Hive metadata permission is granted, the HDFS permission is automatically granted. The procedure for granting a role the permission of querying, inserting, and deleting **htable** data is as follows:
  - a. On FusionInsight Manager, choose **System > Permission > Role**.
  - b. Locate the row that contains **hrole**, and click **Modify**.
  - c. Choose *Name of the desired cluster* > **Hive > Hive Read Write Privileges**.
  - d. Click the name of the specified database **hdb** in the database list. Table **htable** in the database is displayed.
  - e. In the **Permission** column of the **htable** table, select **SELECT, INSERT, and DELETE**.
  - f. Click **OK**.

### NOTE

In role management, the procedure for granting a role the permission of querying, inserting, and deleting Hive external table data is the same. After the metadata permission is granted, the HDFS permission is automatically granted.

- Granting Column Permissions  
Users have all permissions for the tables created by themselves in Hive and HDFS. Users do not have the permission to access the tables created by others. If a user needs to access some columns in tables created by other users, the user must be granted the permission for columns. After the Hive metadata permission is granted, the HDFS permission is automatically granted. The procedure for granting a role the permission of querying and inserting data in **hcol** of **htable** is as follows:
  - a. On FusionInsight Manager, choose **System > Permission > Role**.
  - b. Locate the row that contains **hrole**, and click **Modify**.
  - c. Choose *Name of the desired cluster* > **Hive > Hive Read Write Privileges**.
  - d. In the database list, click the specified database **hdb** to display the **htable** table in the database. Click the **htable** table to display the **hcol** column in the table.

- e. In the **Permission** column of the **hcol** column, select **SELECT** and **INSERT**.
- f. Click **OK**.

 **NOTE**

In role management, after the metadata permission is granted, the HDFS permission is automatically granted. Therefore, after the column permission is granted, the HDFS ACL permission for all files of the table is automatically granted.

- **Granting Database Permissions**

Users have complete permission on the databases created by themselves in Hive and the HDFS. To access the databases created by others, they need to be granted the permission. After the Hive metadata permission is granted, the HDFS permission is automatically granted. The procedure for granting a role the permission of querying data and creating tables in database **hdb** is as follows. Other types of database operation permission are not supported.

- a. On FusionInsight Manager, choose **System > Permission > Role**.
- b. Locate the row that contains **hrole**, and click **Modify**.
- c. Choose *Name of the desired cluster* > **Hive > Hive Read Write Privileges**.
- d. In the **Permission** column of the **hdb** database, select **SELECT** and **CREATE**.
- e. Click **OK**.

 **NOTE**

- Any permission for a table in the database is automatically associated with the HDFS permission for the database directory to facilitate permission management. When any permission for a table is canceled, the system does not automatically cancel the HDFS permission for the database directory to ensure performance. In this case, users can only log in to the database and view table names.
- When the query permission on a database is added to or deleted from a role, the query permission on tables in the database is automatically added to or deleted from the role.

## Concepts

**Table 9-7** Scenarios of using Hive tables, columns, or databases

Scenario	Required Permission
DESCRIBE TABLE	SELECT
SHOW PARTITIONS	SELECT
ANALYZE TABLE	SELECT and INSERT
SHOW COLUMNS	SELECT
SHOW TABLE STATUS	SELECT
SHOW TABLE PROPERTIES	SELECT
SELECT	SELECT

Scenario	Required Permission
EXPLAIN	SELECT
CREATE VIEW	SELECT, Grant Of Select, and CREATE
SHOW CREATE TABLE	SELECT and Grant Of Select
CREATE TABLE	CREATE
ALTER TABLE ADD PARTITION	INSERT
INSERT	INSERT
INSERT OVERWRITE	INSERT and DELETE
LOAD	INSERT and DELETE
ALTER TABLE DROP PARTITION	DELETE
CREATE FUNCTION	Hive Admin Privilege
DROP FUNCTION	Hive Admin Privilege
ALTER DATABASE	Hive Admin Privilege

## 9.4.4 Configuring Permissions to Use Other Components for Hive

### Scenario

Hive may need to be associated with other components. For example, Yarn permissions are required in the scenario of using HQL statements to trigger MapReduce jobs, and HBase permissions are required in the Hive over HBase scenario. The following describes the operations in the two scenarios.

#### NOTE

- In security mode, Yarn and HBase permission management is enabled by default. Therefore, Yarn and HBase permissions need to be configured by default.
- In common mode, Yarn and HBase permission management is disabled by default. That is, any user has permissions. Therefore, YARN and HBase permissions does not need to be configured by default. If a user enables the permission management by modifying the Yarn or HBase configurations, the Yarn and HBase permissions then need to be configured.
- If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. For details, see [Adding a Ranger Access Permission Policy for Hive](#).

### Prerequisites

- The Hive client has been installed.. For example, the installation directory is `/opt/client`.
- You have obtained a user account with the administrator permissions, such as `admin`.

## Procedure

### Association with Yarn

Yarn permissions are required when HQL statements, such as **insert**, **count**, **distinct**, **group by**, **order by**, **sort by**, and **join**, are used to trigger MapReduce jobs. The following uses the procedure for assigning a role the permissions to run the **count** statements in the **thc** table as an example.

- Step 1** Create a role on FusionInsight Manager.
- Step 2** In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **Yarn** > **Scheduler Queue** > **root**.
- Step 3** In the **Permission** column of the **default** queue, select **Submit** and click **OK**.
- Step 4** In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **Hive** > **Hive Read Write Privileges** > **default**. Select **SELECT** for table **thc**, and click **OK**.

----End

### Hive over HBase Authorization

After the permissions are assigned, you can use HQL statements that are similar to SQL statements to access HBase tables from Hive. The following uses the procedure for assigning a user the rights to query HBase tables as an example.

- Step 1** On the role management page of FusionInsight Manager, create an HBase role, for example, **hive\_hbase\_create**, and grant the permission to create HBase tables.

In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **HBase** > **HBase Scope** > **global**. Select **Create** of the namespace **default**, and click **OK**.

- Step 2** On FusionInsight Manager, create a human-machine user, for example, **hbase\_creates\_user**, add the user to the **hive** group, and bind the **hive\_hbase\_create** role to the user so that the user can create Hive and HBase tables.

- Step 3** Log in to the node where the client is installed as the client installation user.

- Step 4** Run the following command to configure environment variables:

```
source /opt/client/bigdata_env
```

- Step 5** Run the following command to authenticate the user:

```
kinit hbase_creates_user
```

- Step 6** Run the following command to go to the shell environment of the Hive client:

```
beeline
```

- Step 7** Run the following command to create a table in Hive and HBase, for example, the **thh** table.

```
CREATE TABLE thh(id int, name string, country string) STORED BY  
'org.apache.hadoop.hive.hbase.HBaseStorageHandler' WITH  
SERDEPROPERTIES("hbase.columns.mapping" = "cf1:id,cf1:name,;key")  
TBLPROPERTIES ("hbase.table.name" = "thh");
```

The created Hive table and the HBase table are stored in the Hive database **default** and the HBase namespace **default**, respectively.

**Step 8** On the role management page of FusionInsight Manager, create a role, for example, **hive\_hbase\_select**, and assign the role the permission to query the Hive table **thh** and the HBase table **thh**.

1. In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **HBase** > **HBase Scope** > **global** > **default**. Select **read** of the **thh** table, and click **OK** to grant the table query permission to the HBase role.
2. Edit the role. In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **HBase** > **HBase Scope** > **global** > **hbase**, select **Execute** for **hbase:meta**, and click **OK**.
3. Edit the role. In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **Hive** > **Hive Read Write Privileges** > **default**. Select **SELECT** for the **thh** table, and click **OK**.

**Step 9** On FusionInsight Manager, create a human-machine user, for example, **hbase\_select\_user**, add the user to the **hive** group, and bind the **hive\_hbase\_select** role to the user so that the user can query Hive and HBase tables.

**Step 10** Run the following command to configure environment variables:

```
source /opt/client/bigdata_env
```

**Step 11** Run the following command to authenticate users:

```
kinit hbase_select_user
```

**Step 12** Run the following command to go to the shell environment of the Hive client:

```
beeline
```

**Step 13** Run the following command to use an HQL statement to query HBase table data:

```
select * from thh;
```

```
----End
```

## 9.5 Using a Hive Client

### Scenario

This section guides users to use a Hive client in an O&M or service scenario.

### Prerequisites

- The client has been installed. For example, the client is installed in the **/opt/hadoopclient** directory. The client directory in the following operations is only an example. Change it to the actual installation directory.
- Service component users are created by the administrator as required. In security mode, machine-machine users need to download the keytab file. A human-machine user must change the password upon the first login.

## Using the Hive Client

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to go to the client installation directory:

```
cd /opt/hadoopclient
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** Log in to the Hive client based on the cluster authentication mode.

- In security mode, run the following command to complete user authentication and log in to the Hive client:

```
kinit Component service user
```

```
beeline
```

- In common mode, run the following command to log in to the Hive client. If no component service user is specified, the current OS user is used to log in to the Hive client.

```
beeline -n component service user
```

**Step 5** Run the following command to execute the HCatalog client command:

```
hcat -e "cmd"
```

*cmd* must be a Hive DDL statement, for example, **hcat -e "show tables"**.

### NOTE

- To use the HCatalog client, choose **More > Download Client** on the service page to download the clients of all services. This restriction does not apply to the beeline client.
- Due to permission model incompatibility, tables created using the HCatalog client cannot be accessed on the HiveServer client. However, the tables can be accessed on the WebHCat client.
- If you use the HCatalog client in Normal mode, the system performs DDL commands using the current user who has logged in to the operating system.
- Exit the beeline client by running the **!q** command instead of by pressing **Ctrl + C**. Otherwise, the temporary files generated by the connection cannot be deleted and a large number of junk files will be generated as a result.
- If multiple statements need to be entered during the use of beeline clients, separate the statements from each other using semicolons (;) and set the value of **entireLineAsCommand** to **false**.

Setting method: If beeline has not been started, run the **beeline --entireLineAsCommand=false** command. If the beeline has been started, run the **!set entireLineAsCommand false** command.

After the setting, if a statement contains semicolons (;) that do not indicate the end of the statement, escape characters must be added, for example, **select concat\_ws('\;', collect\_set(col1)) from tbl**.

----End

## Common Hive Client Commands

The following table lists common Hive Beeline commands.

For more commands, see <https://cwiki.apache.org/confluence/display/Hive/HiveServer2+Clients#HiveServer2Clients-BeelineCommands>.

**Table 9-8** Common Hive Beeline commands

Command	Description
set <key>=<value>	Sets the value of a specific configuration variable (key). <b>NOTE</b> If the variable name is incorrectly spelled, the Beeline does not display an error.
set	Prints the list of configuration variables overwritten by users or Hive.
set -v	Prints all configuration variables of Hadoop and Hive.
add FILE[S] <filepath> <filepath>*add JAR[S] <filepath> <filepath>*add ARCHIVE[S] <filepath> <filepath>*	Adds one or more files, JAR files, or ARCHIVE files to the resource list of the distributed cache.
add FILE[S] <ivyurl> <ivyurl>* add JAR[S] <ivyurl> <ivyurl>* add ARCHIVE[S] <ivyurl> <ivyurl>*	Adds one or more files, JAR files, or ARCHIVE files to the resource list of the distributed cache using the Ivy URL in the <b>ivy://goup:module:version?query_string</b> format.
list FILE[S]list JAR[S]list ARCHIVE[S]	Lists the resources that have been added to the distributed cache.
list FILE[S] <filepath>*list JAR[S] <filepath>*list ARCHIVE[S] <filepath>*	Checks whether given resources have been added to the distributed cache.
delete FILE[S] <filepath>*delete JAR[S] <filepath>*delete ARCHIVE[S] <filepath>*	Deletes resources from the distributed cache.
delete FILE[S] <ivyurl> <ivyurl>* delete JAR[S] <ivyurl> <ivyurl>* delete ARCHIVE[S] <ivyurl> <ivyurl>*	Delete the resource added using <ivyurl> from the distributed cache.

Command	Description
reload	Enable HiveServer2 to discover the change of the JAR file <b>hive.reloadable.aux.jars.path</b> in the specified path. (You do not need to restart HiveServer2.) Change actions include adding, deleting, or updating JAR files.
dfs <dfs command>	Runs the <b>dfs</b> command.
<query string>	Executes the Hive query and prints the result to the standard output.

## 9.6 Using HDFS Colocation to Store Hive Tables

### Scenario

HDFS Colocation is the data location control function provided by HDFS. The HDFS Colocation API stores associated data or data on which associated operations are performed on the same storage node. Hive supports the HDFS Colocation function. When Hive tables are created, after the locator information is set for table files, data files of related tables are stored on the same storage node when data is inserted into tables using the insert statement (other data import modes are not supported). This ensures convenient and efficient data computing among associated tables. The supported table formats are only TextFile and RCFile.

### Procedure

- Step 1** Log in to the node where the client is installed as a client installation user.
- Step 2** Run the following command to switch to the client installation directory, for example, **opt/client**:  
**cd /opt/client**
- Step 3** Run the following command to configure environment variables:  
**source bigdata\_env**
- Step 4** If the cluster is in security mode, run the following command to authenticate the user:  
**kinit MRS username**
- Step 5** Create the *groupid* through the HDFS API.  
**hdfs colocationadmin -createGroup -groupId <groupid> -locatorIds <locatorid1>,<locatorid2>,<locatorid3>**

 NOTE

In the preceding command, *<groupid>* indicates the name of the created group. The group created in this example contains three locators. You can define the number of locators as required.

For details about group ID creation and HDFS Colocation, see HDFS description.

**Step 6** Run the following command to log in to the Hive client:

**beeline**

**Step 7** Enable Hive to use colocation.

Assume that **table\_name1** and **table\_name2** are associated with each other. Run the following statements to create them:

```
CREATE TABLE <[db_name.]table_name1>[(col_name data_type , ...)] [ROW  
FORMAT <row_format>] [STORED AS <file_format>]  
TBLPROPERTIES("groupid"=" <group> ","locatorId"=" <locator1>");
```

```
CREATE TABLE <[db_name.]table_name2> [(col_name data_type , ...)] [ROW  
FORMAT <row_format>] [STORED AS <file_format>]  
TBLPROPERTIES("groupid"=" <group> ","locatorId"=" <locator1>");
```

After data is inserted into **table\_name1** and **table\_name2** using the insert statement, data files of **table\_name1** and **table\_name2** are distributed to the same storage position in the HDFS, facilitating associated operations among the two tables.

----End

## 9.7 Using the Hive Column Encryption Function

### Scenario

Hive supports encryption of one or more columns in a table. When creating a Hive table, you can specify the columns to be encrypted and encryption algorithm. When data is inserted into the table using the insert statement, the related columns are encrypted. Column encryption can be performed in HDFS tables of only the TextFile and SequenceFile file formats. Hive column encryption does not support the view and Hive over HBase scenarios.

Hive supports two column encryption algorithms, which can be specified during table creation:

- AES (the encryption class is org.apache.hadoop.hive.serde2.AESRewriter)
- SMS4 (the encryption class is org.apache.hadoop.hive.serde2.SMS4Rewriter)

 NOTE

*When you import data from a common Hive table into a Hive column encryption table, you are advised to delete the original data from the common Hive table as long as doing this does not affect other services. The reason is that retaining an unencrypted table is a security risk.*

## Operation Procedure

- Step 1** Specify the column to be encrypted and encryption algorithm when creating a table.

```
create table <[db_name.]table_name> (<col_name1>
<data_type> ,<col_name2> <data_type>,<col_name3>
<data_type>,<col_name4> <data_type>) ROW FORMAT SERDE
'org.apache.hadoop.hive.serde2.lazy.LazySimpleSerDe' WITH
SERDEPROPERTIES ('column.encode.columns'='<col_name2>,<col_name3>',
'column.encode.classname'='org.apache.hadoop.hive.serde2.AESRewriter')STO
RED AS TEXTFILE;
```

Alternatively, use the following statement:

```
create table <[db_name.]table_name> (<col_name1>
<data_type> ,<col_name2> <data_type>,<col_name3>
<data_type>,<col_name4> <data_type>) ROW FORMAT SERDE
'org.apache.hadoop.hive.serde2.lazy.LazySimpleSerDe' WITH
SERDEPROPERTIES ('column.encode.indices'='1,2',
'column.encode.classname'='org.apache.hadoop.hive.serde2.SMS4Rewriter')
STORED AS TEXTFILE;
```

### NOTE

- The numbers used to specify encryption columns start from 0. 0 indicates column 1, 1 indicates column 2, and so on.
- When creating a table with encrypted columns, ensure that the directory where the table resides is empty.

- Step 2** Insert data into the table using the insert statement.

Assume that the test table exists and contains data.

```
insert into table <table_name> select <col_list> from test;
```

----End

## 9.8 Customizing Row Separators

### Scenario

In most cases, a carriage return character is used as the row delimiter in Hive tables stored in text files, that is, the carriage return character is used as the terminator of a row during queries. However, some data files are delimited by special characters, and not a carriage return character.

MRS Hive allows you to use different characters or character combinations to delimit rows of Hive text data. When creating a table, set **inputformat** to **SpecifiedDelimiterInputFormat**, and set the following parameter before search each time. Then the table data is queried by the specified delimiter.

```
set hive.textinput.record.delimiter="";
```

 NOTE

The Hue component of the current version does not support the configuration of multiple separators when files are imported to a Hive table.

## Procedure

**Step 1** Specify **inputFormat** and **outputFormat** when creating a table.

```
CREATE [TEMPORARY] [EXTERNAL] TABLE [IF NOT EXISTS]
[db_name.]table_name [(col_name data_type [COMMENT col_comment], ...)]
[ROW FORMAT row_format] STORED AS inputformat
'org.apache.hadoop.hive.contrib.fileformat.SpecifiedDelimiterInputFormat'
outputformat 'org.apache.hadoop.hive ql.io.HiveIgnoreKeyTextOutputFormat'
```

**Step 2** Specify the delimiter before search.

```
set hive.textinput.record.delimiter='!@!'
```

Hive will use '!@!' as the row delimiter.

----End

## 9.9 Deleting Single-Row Records from Hive on HBase

### Scenario

Due to the limitations of underlying storage systems, Hive does not support the ability to delete a single piece of table data. In Hive on HBase, MRS Hive supports the ability to delete a single piece of HBase table data. Using a specific syntax, Hive can delete one or more pieces of data from an HBase table.

**Table 9-9** Permissions required for deleting single-row records from the Hive on HBase table

Cluster Authentication Mode	Required Permission
Security mode	SELECT, INSERT, and DELETE
Common mode	None

### Procedure

**Step 1** To delete some data from an HBase table, run the following HQL statement:

```
remove table <table_name> where <expression>;
```

In the preceding information, *<expression>* specifies the filter condition of the data to be deleted. *<table\_name>* indicates the Hive on HBase table from which data is to be deleted.

----End

## 9.10 Configuring HTTPS/HTTP-based REST APIs

### Scenario

WebHCat provides external REST APIs for Hive. By default, the open-source community version uses the HTTP protocol.

MRS Hive supports the HTTPS protocol that is more secure, and enables switchover between the HTTP protocol and the HTTPS protocol.

#### NOTE

The security mode supports HTTPS and HTTP, and the common mode supports only HTTP.

### Procedure

**Step 1** Modify the Hive configuration.

Choose **WebHCat > Security**. On the page that is displayed, select **HTTPS** or **HTTP**. After the modification, restart the Hive service to use the corresponding protocol.

----End

## 9.11 Enabling or Disabling the Transform Function

### Scenario

The Transform function is not allowed by Hive of the open source version.

MRS Hive supports the configuration of the Transform function. The function is disabled by default, which is the same as that of the open-source community version.

Users can modify configurations of the Transform function to enable the function. However, security risks exist when the Transform function is enabled.

#### NOTE

The Transform function can be disabled only in security mode.

### Procedure

**Step 1** Enter the parameter name in the search box, search for **hive.security.transform.disallow**, change the parameter value to **true** or **false**, and restart all HiveServer instances.

 NOTE

- If this parameter is set to **true**, the Transform function is disabled, which is the same as that in the open-source community version.
- If this parameter is set to **false**, the Transform function is enabled, which poses security risks.

----End

## 9.12 Access Control of a Dynamic Table View on Hive

### Scenario

This section describes how to create a view on Hive when MRS is configured in security mode, authorize access permissions to different users, and specify that different users access different data.

In the view, Hive can obtain the built-in function **current\_user()** of the users who submit tasks on the client and filter the users. This way, authorized users can only access specific data in the view.

 NOTE

In normal mode, the **current\_user()** function cannot distinguish users who submit tasks on the client. Therefore, the access control function takes effect only for Hive in security mode. If the **current\_user()** function is used in the actual service logic, the possible risks must be fully evaluated during the conversion between the security mode and normal mode.

### Operation Example

- If the **current\_user** function is not used, different views need to be created for different users to access different data.
  - Authorize the view **v1** permission to user **hiveuser1**. The user **hiveuser1** can access data with **type** set to **hiveuser1** in **table1**.  
**create view v1 as select \* from table1 where type='hiveuser1'**
  - Authorize the view **v2** permission to user **hiveuser2**. The user **hiveuser2** can access data with **type** set to **hiveuser2** in **table1**.  
**create view v2 as select \* from table1 where type='hiveuser2'**
- If the **current\_user** function is used, only one view needs to be created. Authorize the view **v** permission to users **hiveuser1** and **hiveuser2**. When user **hiveuser1** queries view **v**, the **current\_user()** function is automatically converted to **hiveuser1**. When user **hiveuser2** queries view **v**, the **current\_user()** function is automatically converted to **hiveuser2**.  
**create view v as select \* from table1 where type=current\_user()**

## 9.13 Specifying Whether the ADMIN Permissions Is Required for Creating Temporary Functions

### Scenario

You must have **ADMIN** permission when creating temporary functions on Hive of the open source community version.

MRS Hive supports the configuration of the function for creating temporary functions with **ADMIN** permission. The function is disabled by default, which is the same as that of the open-source community version.

You can modify configurations of this function. After the function is enabled, you can create temporary functions without **ADMIN** permission. If this parameter is set to **false**, security risks exist.

#### NOTE

The security mode supports the configuration of whether the ADMIN permission is required for creating temporary functions, but the common mode does not support this function.

### Procedure

**Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.

**Step 2** Enter the parameter name in the search box, search for **hive.security.temporary.function.need.admin**, change the parameter value to **true** or **false**, and restart all HiveServer instances.

#### NOTE

- If this parameter is set to **true**, the ADMIN permission is required for creating temporary functions, which is the same as that in the open source community.
- If this parameter is set to **false**, the ADMIN permission is not required for creating temporary functions.

----End

## 9.14 Using Hive to Read Data in a Relational Database

### Scenario

Hive allows users to create external tables to associate with other relational databases. External tables read data from associated relational databases and support Join operations with other tables in Hive.

Currently, the following relational databases can use Hive to read data:

- DB2
- Oracle

## Prerequisites

The Hive client has been installed.

## Procedure

**Step 1** Log in to the node where the Hive client is installed as the Hive client installation user .

**Step 2** Run the following command to go to the client installation directory:

```
cd Client installation directory
```

For example, if the client installation directory is **/opt/client**, run the following command:

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** Check whether the cluster authentication mode is Security.

- If yes, run the following command to authenticate the user:  

```
kinit Hive service user
```
- If no, go to [Step 5](#).

**Step 5** Run the following command to upload the driver JAR package of the relational database to be associated to an HDFS directory.

```
hdfs dfs -put directory where the JAR package is located HDFS directory to which the JAR is uploaded
```

For example, to upload the Oracle driver JAR package in **/opt** to the **/tmp** directory in HDFS, run the following command:

```
hdfs dfs -put /opt/ojdbc6.jar /tmp
```

**Step 6** Create an external table on the Hive client to associate with the relational database, as shown in the following example.

 **NOTE**

If the security mode is used, the user who creates the table must have the **ADMIN** permission. The **ADD JAR** path is subject to the actual path.

```
-- Example of associating with an Oracle Linux 6 database
-- In security mode, set the admin permission.
set role admin;
-- Upload the driver JAR package of the relational database to be associated. The driver JAR packages
vary according to databases.
ADD JAR hdfs:///tmp/ojdbc6.jar;

CREATE EXTERNAL TABLE ora_test
-- The Hive table must have one more column than the database return result. This column is used for
paging query.
(id STRING,rownum string)
STORED BY 'com.qubitproducts.hive.storage.jdbc.JdbcStorageHandler'
TBLPROPERTIES (
-- Relational database table type
"qubit.sql.database.type" = "ORACLE",
-- Connect to the URL of the relational database through JDBC. (The URL formats vary according to
databases.)
"qubit.sql.jdbc.url" = "jdbc:oracle:thin:@//10.163.0.1:1521/mydb",
-- Relational database driver class type
"qubit.sql.jdbc.driver" = "oracle.jdbc.OracleDriver",
-- SQL statement queried in the relational database. The result is returned to the Hive table.
"qubit.sql.query" = "select name from aaa",
-- (Optional) Match the Hive table columns to the relational database table columns.
"qubit.sql.column.mapping" = "id=name",
-- Relational database user
"qubit.sql.dbcp.username" = "test",
-- Relational database password
"qubit.sql.dbcp.password" = "123456");
```

----End

## 9.15 Supporting Traditional Relational Database Syntax in Hive

### Overview

Hive supports the following types of traditional relational database syntax:

- Grouping
- EXCEPT and INTERSECT

### Grouping

Syntax description:

- Grouping takes effect only when the Group by statement contains ROLLUP or CUBE.
- The result set generated by CUBE contains all the combinations of values in the selected columns.
- The result set generated by ROLLUP contains the combinations of a certain layer structure in the selected columns.
- Grouping: If a row is added by using the CUBE or ROLLUP operator, the output value of the added row is 1. If the row is not added by using the CUBE or ROLLUP operator, the output value of the added row is 0.

For example, the **table\_test** table exists in Hive and the table structure is as follows:

```
+-----+-----+
| table_test.id | table_test.value |
+-----+-----+
| 1             | 10                |
| 1             | 15                |
| 2             | 20                |
| 2             | 5                 |
| 2             | 13                |
+-----+-----+
```

Run the following statement:

**select id,grouping(id),sum(value) from table\_test group by id with rollup;**

The result is as follows:

```
+-----+-----+-----+
| id | groupingresult | sum |
+-----+-----+-----+
| 1  | 0              | 25  |
| NULL | 1              | 63  |
| 2  | 0              | 38  |
+-----+-----+-----+
```

## EXCEPT and INTERSECT

Syntax description:

- EXCEPT returns the difference of two result sets (that is, non-duplicated values return only one query).
- INTERSECT returns the intersection of two result sets (that is, non-duplicated values return by both queries).

For example, two tables **test\_table1** and **test\_table2** exist in Hive.

The table structure of **test\_table1** is as follows:

```
+-----+
| test_table1.id |
+-----+
| 1              |
| 2              |
| 3              |
| 4              |
+-----+
```

The table structure of **test\_table2** is as follows:

```
+-----+
| test_table2.id |
+-----+
| 2              |
| 3              |
| 4              |
| 5              |
+-----+
```

- Run the following EXCEPT statement:

**select id from test\_table1 except select id from test\_table2;**

The result is as follows:

```
+-----+
| _alias_0.id |
+-----+
```

```
+-----+--+  
| 1      |  
+-----+--+
```

- Run the following INTERSECT statement:  
**select id from test\_table1 intersect select id from test\_table2;**

The result is as follows:

```
+-----+--+  
|_alias_0.id |  
+-----+--+  
| 2          |  
| 3          |  
| 4          |  
+-----+--+
```

## 9.16 Creating User-Defined Hive Functions

When built-in functions of Hive cannot meet requirements, you can compile user-defined functions (UDFs) and use them for query.

According to implementation methods, UDFs are classified as follows:

- Common UDFs: used to perform operations on a single data row and export a single data row.
- User-defined aggregating functions (UDAFs): used to input multiple data rows and export a single data row.
- User-defined table-generating functions (UDTFs): used to perform operations on a single data row and export multiple data rows.

According to use methods, UDFs are classified as follows:

- Temporary functions: used only in the current session and must be recreated after a session restarts.
- Permanent functions: used in multiple sessions. You do not need to create them every time a session restarts.

### NOTE

You need to properly control the memory and thread usage of variables in UDFs. Improper control may cause memory overflow or high CPU usage.

The following uses AddDoublesUDF as an example to describe how to compile and use UDFs.

## Function

AddDoublesUDF is used to add two or more floating point numbers. In this example, you can learn how to write and use UDFs.

### NOTE

- A common UDF must be inherited from **org.apache.hadoop.hive.ql.exec.UDF**.
- A common UDF must implement at least one **evaluate()**. The evaluate function supports overloading.
- To develop a customized function, you need to add the **hive-exec-3.1.0.jar** dependency package to the project. The package can be obtained from the Hive installation directory.

## Sample Code

The following is a UDF code example:

In the preceding command, xxx indicates the name of the organization that develops the program.

```
package com.xxx.bigdata.hive.example.udf;
import org.apache.hadoop.hive.ql.exec.UDF;

public class AddDoublesUDF extends UDF {
    public Double evaluate(Double... a) {
        Double total = 0.0;
        // Processing logic
        for (int i = 0; i < a.length; i++)
            if (a[i] != null)
                total += a[i];
        return total;
    }
}
```

## How to Use

**Step 1** Packing programs as **AddDoublesUDF.jar** on the client node, and upload the package to a specified directory in HDFS, for example, **/user/hive\_examples\_jars**.

Both the user who creates the function and the user who uses the function must have the read permission on the file.

The following are example statements:

```
hdfs dfs -put ./hive_examples_jars /user/hive_examples_jars
```

```
hdfs dfs -chmod 777 /user/hive_examples_jars
```

**Step 2** Check the cluster authentication mode.

- In security mode, log in to the beeline client as a user with the Hive management permission and run the following commands:

```
kinit Hive service user
```

```
beeline
```

```
set role admin;
```

- In common mode, run the following command:

```
beeline -n Hive service user
```

**Step 3** Define the function in HiveServer. Run the following SQL statement to create a permanent function:

```
CREATE FUNCTION addDoubles AS  
'com.xxx.bigdata.hive.example.udf.AddDoublesUDF' using jar 'hdfs://hacluster/  
user/hive_examples_jars/AddDoublesUDF.jar';
```

*addDoubles* indicates the function alias that is used for SELECT query; *xxx* indicates the name of the organization that develops the program..

Run the following statement to create a temporary function:

```
CREATE TEMPORARY FUNCTION addDoubles AS  
'com.xxx.bigdata.hive.example.udf.AddDoublesUDF' using jar 'hdfs://hacluster/  
user/hive_examples_jars/AddDoublesUDF.jar';
```

- *addDoubles* indicates the function alias that is used for SELECT query.
- **TEMPORARY** indicates that the function is used only in the current session with the HiveServer.

**Step 4** Run the following SQL statement to use the function on the HiveServer:

```
SELECT addDoubles(1,2,3);
```

 **NOTE**

If an [Error 10011] error is displayed when you log in to the client again, run the **reload function;** command and then use this function.

**Step 5** Run the following SQL statement to delete the function from the HiveServer:

```
DROP FUNCTION addDoubles;
```

```
----End
```

## Extended Applications

None

## 9.17 Enhancing beeline Reliability

### Scenario

- When the beeline client is disconnected due to network exceptions during the execution of a batch processing task, tasks submitted before beeline is disconnected can be properly executed in Hive. When you start the batch processing task again, the submitted tasks are not executed and tasks that are not executed are executed in sequence.
- When the HiveServer service breaks down due to some reasons during the execution of a batch processing task, Hive enables that the tasks that have been successfully executed are not executed again when the same batch processing task is started again. The execution starts from the task that has not been executed from the time when HiveServer2 breaks down.

### Example

1. Beeline is reconnected after being disconnection.

Example:

```
beeline -e "${SQL}" --hivevar batchid=xxxxx
```

2. Beeline kills the running tasks.

Example:

```
beeline -e "" --hivevar batchid=xxxxx --hivevar kill=true
```

3. Log in to the beeline client and start the mechanism of reconnection after disconnection.

Log in to the beeline client and run the **set hivevar:batchid=xxxx** command.

 **NOTE**

Instructions:

- `xxxx` indicates the batch ID of tasks submitted in the same batch using the beeline client. Batch IDs can be used to identify the task submission batch. If the batch ID is not contained when a task is submitted, this feature is not enabled.
- If the running SQL script depends on the data timeliness, you are advised not to enable the breakpoint reconnection mechanism. You can use a new batch ID to submit tasks. During reexecution of the scripts, some SQL statements have been executed and are not executed again. As a result, expired data is obtained.
- If some built-in time functions are used in the SQL script, it is recommended that you do not enable the breakpoint reconnection mechanism or the use of a new batch ID for each execution. The reason is the same as above.
- A SQL script contains one or more subtasks. If the logic for deleting and creating temporary tables exist in the SQL script, it is recommended that the logic for deleting temporary tables be placed at the end of the script. If the subtasks executed after the temporary table deletion task fail to be executed and the temporary table is used in the subtasks before the temporary table deletion task, when the SQL script is executed using the same batch ID for the next time, the compilation of the subtasks (excluding the task for creating the temporary table because the creation has been completed and is not executed again, and only compilation is allowed) executed before the temporary table deletion task fails because the temporary table has been deleted. In this case, you are advised to use a new batch ID to execute the script.

Parameter description:

- **zk.cleanup.finished.job.interval**: indicates the interval for executing the cleanup task. The default interval is 60 seconds.
- **zk.cleanup.finished.job.outdated.threshold**: indicates the threshold of the node validity period. A node is generated for tasks in the same batch. The threshold is calculated from the end time of the execution of the current batch task. If the time exceeds 60 minutes, the node is deleted.
- **batch.job.max.retry.count**: indicates the maximum number of retry times of a batch task. If the number of retry times of a batch task exceeds the value of this parameter, the task execution record is deleted. The task will be executed from the first task when the task is started next time. The default value is **10**.
- **beeline.reconnect.zk.path**: indicates the root node for storing task execution progress. The default value for the Hive service is **/beeline**.

## 9.18 Viewing Table Structures Using the show create Statement as Users with the select Permission

### Scenario

This function is applicable to Hive and Spark2x in.

With this function enabled, if the select permission is granted to a user during Hive table creation, the user can run the **show create table** command to view the table structure.

### Procedure

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.

**Step 2** Choose **HiveServer(Role) > Customization**, add a customized parameter to the **hive-site.xml** parameter file, set **Name** to **hive.allow.show.create.table.in.select.nogrant**, and set **Value** to **true**. Restart all Hive instances after the modification.

**Step 3** Determine whether to enable this function on the Spark2x client.

- If yes, download and install the Spark2x client again.
- If no, no further action is required.

----End

## 9.19 Writing a Directory into Hive with the Old Data Removed to the Recycle Bin

### Scenario

This function applies to Hive.

After this function is enabled, run the following command to write a directory into Hive: **insert overwrite directory "/path1" ....** After the operation is successfully performed, the old data is removed to the recycle bin, and the directory cannot be an existing database path in the Hive metastore.

**Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.

**Step 2** Choose **HiveServer(Role) > Customization**, add a customized parameter to the **hive-site.xml** parameter file, set **Name** to **hive.overwrite.directory.move.trash**, and set **Value** to **true**. Restart all Hive instances after the modification.

----End

## 9.20 Inserting Data to a Directory That Does Not Exist

### Scenario

This function applies to Hive.

With this function enabled, run the **insert overwrite directory /path1/path2/path3...** command to write a subdirectory. The permission of the **/path1/path2** directory is 700, and the owner is the current user. If the **/path3** directory does not exist, it is automatically created and data is written successfully.

This function is supported when **hive.server2.enable.doAs** is set to **true** in earlier versions. This version supports the function when **hive.server2.enable.doAs** is set to **false**.

#### NOTE

The parameter adjustment of this function is the same as that of the custom parameters added in [Writing a Directory into Hive with the Old Data Removed to the Recycle Bin](#).

## Procedure

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.
- Step 2** Choose **HiveServer(Role) > Customization**, add a customized parameter to the **hive-site.xml** parameter file, set **Name** to **hive.override.directory.move.trash**, and set **Value** to **true**. Restart all Hive instances after the modification.

----End

## 9.21 Creating Databases and Creating Tables in the Default Database Only as the Hive Administrator

### Scenario

This function is applicable to Hive and Spark2x.

After this function is enabled, only the Hive administrator can create databases and tables in the default database. Other users can use the databases only after being authorized by the Hive administrator.

#### NOTE

- After this function is enabled, common users are not allowed to create a database or create a table in the default database. Based on the actual application scenario, determine whether to enable this function.
- Permissions of common users are restricted. In the scenario where common users have been used to perform operations, such as database creation, table script migration, and metadata recreation in an earlier version of database, the users can perform such operations on the database in the condition that this function is disabled temporarily after the database is migrated or after the cluster is upgraded.

## Procedure

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.
- Step 2** Choose **HiveServer(Role) > Customization**, add a customized parameter to the **hive-site.xml** parameter file, set **Name** to **hive.allow.only.admin.create**, and set **Value** to **true**. Restart all Hive instances after the modification.
- Step 3** Determine whether to enable this function on the Spark2x client.
  - If yes, download and install the Spark2x client again.
  - If no, no further action is required.

----End

## 9.22 Disabling of Specifying the location Keyword When Creating an Internal Hive Table

### Scenario

This function is applicable to Hive and Spark2x.

After this function is enabled, the **location** keyword cannot be specified when a Hive internal table is created. Specifically, after a table is created, the table path following the location keyword is created in the default **\warehouse** directory and cannot be specified to another directory. If the location is specified when the internal table is created, the creation fails.

#### NOTE

After this function is enabled, the location keyword cannot be specified during the creation of a Hive internal table. The table creation statement is restricted. If a table that has been created in the database is not stored in the default directory **/warehouse**, the **location** keyword can still be specified when the database creation, table script migration, or metadata recreation operation is performed by disabling this function temporarily.

### Procedure

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.
- Step 2** Choose **HiveServer(Role) > Customization**, add a customized parameter to the **hive-site.xml** parameter file, set **Name** to **hive.internaltable.notallowlocation**, and set **Value** to **true**. Restart all Hive instances after the modification.
- Step 3** Determine whether to enable this function on the Spark2x client.
  - If yes, download and install the Spark2x client again.
  - If no, no further action is required.

----End

## 9.23 Enabling the Function of Creating a Foreign Table in a Directory That Can Only Be Read

### Scenario

This function is applicable to Hive and Spark2x.

After this function is enabled, the user or user group that has the read and execute permissions on a directory can create foreign tables in the directory without checking whether the current user is the owner of the directory. In addition, the directory of a foreign table cannot be stored in the default directory **\warehouse**. In addition, do not change the permission of the directory during foreign table authorization.

 NOTE

After this function is enabled, the function of the foreign table changes greatly. Based on the actual application scenario, determine whether to enable this function.

## Procedure

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.
- Step 2** Choose **HiveServer(Role) > Customization**, add a customized parameter to the **hive-site.xml** parameter file, set **Name** to **hive.restrict.create.grant.external.table**, and set **Value** to **true**.
- Step 3** Choose **MetaStore(Role) > Customization**, add a customized parameter to the **hivemetastore-site.xml** parameter file, set **Name** to **hive.restrict.create.grant.external.table**, and set **Value** to **true**. Restart all Hive instances after the modification.
- Step 4** Determine whether to enable this function on the Spark2x client.
  - If yes, download and install the Spark2x client again.
  - If no, no further action is required.

----End

## 9.24 Authorizing Over 32 Roles in Hive

### Scenario

This function applies to Hive.

The number of OS user groups is limited, and the number of roles that can be created in Hive cannot exceed 32. After this function is enabled, more than 32 roles can be created in Hive.

 NOTE

- After this function is enabled and the table or database is authorized, roles that have the same permission on the table or database will be combined using vertical bars (|). When the ACL permission is queried, the combined result is displayed, which is different from that before the function is enabled. This operation is irreversible. Determine whether to make adjustment based on the actual application scenario.
- If the current component uses Ranger for permission control, you need to configure related policies based on Ranger for permission management. For details, see [Adding a Ranger Access Permission Policy for Hive](#).
- After this function is enabled, a maximum of 512 roles (including **owner**) are supported by default. The number is controlled by the user-defined parameter **hive.supports.roles.max** of MetaStore. You can change the value based on the actual application scenario.

## Procedure

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.
- Step 2** Choose **MetaStore(Role) > Customization**, add a customized parameter to the **hivemetastore-site.xml** parameter file, set **Name** to **hive.supports.over.32.roles**, and set **Value** to **true**. Restart all Hive instances after the modification.  
----End

## 9.25 Restricting the Maximum Number of Maps for Hive Tasks

### Scenario

- This function applies to Hive.
- This function is used to limit the maximum number of maps for Hive tasks on the server to avoid performance deterioration caused by overload of the HiveServer service.

### Procedure

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Hive > Configurations > All Configurations**.
- Step 2** Choose **MetaStore(Role) > Customization**, add a customized parameter to the **hivemetastore-site.xml** parameter file, set **Name** to **hive.mapreduce.per.task.max.splits**, and set the parameter to a large value. Restart all Hive instances after the modification.  
----End

## 9.26 HiveServer Lease Isolation

### Scenario

- This function applies to Hive.
- This function can be enabled to specify specific users to access HiveServer services on specific nodes, achieving HiveServer resource isolation.

### Procedure

This section describes how to set lease isolation for user **hiveuser** for existing HiveServer instances.

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).

**Step 2** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Hive** > **HiveServer**.

**Step 3** In the HiveServer list, select the HiveServer for which lease isolation is configured and choose **HiveServer** > **Instance Configurations** > **All Configurations**.

**Step 4** In the upper right corner of the **All Configurations** page, search for **hive.server2.zookeeper.namespace** and specify its value, for example, **hiveserver2\_zk**.

**Step 5** Click **Save**. In the dialog box that is displayed, click **OK**.

**Step 6** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Hive**, choose **More** > **Restart Service**, and enter the password to restart the service.

**Step 7** Run the **beeline -u** command to log in to the client and run the following command:

```
beeline -u
"jdbc:hive2://10.5.159.13:2181/;serviceDiscoveryMode=zooKeeper;zooKeeperNameSpace=hiveserver2_zk;sasl.qop=auth-conf;auth=KERBEROS;principal=hive/hadoop.<System domain name>@<System domain name>"
```

In the command, **10.5.159.13** is replaced with the IP address of any ZooKeeper instance, which can be viewed through **Cluster** > *Name of the desired cluster* > **Services** > **ZooKeeper** > **Instance**.

**hiveserver2\_zk** following **zooKeeperNameSpace=** is set to the value of **hive.server2.zookeeper.namespace** in [Step 4](#).

As a result, only the HiveServer whose lease isolation is configured can be logged in.

#### NOTE

- After this function is enabled, you must run the preceding command during login to access the HiveServer for which lease isolation is configured. If you run the **beeline** command to log in to the client, only the HiveServer that is not isolated by the lease is accessed.
- You can log in to FusionInsight Manager, choose **System** > **Permission** > **Domain and Mutual Trust**, and view the value of **Local Domain**, which is the current system domain name. **hive/hadoop.<system domain name>** is the username. All letters in the system domain name contained in the username are lowercase letters.

----End

## 9.27 Hive Supporting Transactions

### Scenario

Hive supports transactions at the table and partition levels. When the transaction mode is enabled, transaction tables can be incrementally updated, deleted, and read, implementing atomicity, isolation, consistency, and durability of operations on transaction tables.

### Introduction to Transaction Features

A transaction is a group of unitized operations. These operations are either executed together or not executed together. A transaction is an inseparable unit of

work. The four basic elements of a transaction are usually called ACID features, which are as follows:

- **Atomicity:** A transaction is an inseparable unit of work. All operations in a transaction occur or do not occur together.
- **Consistency:** The database integrity constraints are not damaged before and after a transaction starts.
- **Isolation:** When multiple transactions are concurrently accessed, the transactions are isolated from each other. A transaction does not affect the running of other transactions. The impacts between transactions are as follows: dirty read, non-repeatable read, phantom read, and lost update.
- **Durability:** After a transaction is complete, changes made by the transaction lock to the database are permanently stored in the database.

Characteristics of transaction execution:

- A statement can be written to multiple partitions or tables. If the operation fails, the user cannot see partial write or insert. Even if data is frequently changed, operations can still be quickly performed.
- Hive can automatically compress ACID transaction files without affecting concurrent queries. When querying many small partition files, automatic compression can improve query performance and metadata occupation.
- Read semantics include snapshot isolation. When the read operation starts, the Hive data warehouse is logically locked. The read operation is not affected by any changes that occur during the operation.

## Lock Mechanism

Transactions implement the ACID feature through the following two aspects:

- Write-ahead logging ensures atomicity and durability.
- Locking ensures isolation.

Operation	Type of Held Locks
Insert overwrite	If <b>hive.txn.lock.iow</b> is set to <b>true</b> , the exclusive lock is held. If <b>hive.txn.lock.iow</b> is set to <b>false</b> , the semi-shared lock is held.
Insert	Shared lock. When performing this operation, you can perform read and write operations on the current table or partition.
Update/delete	Semi-shared lock. When this operation is performed, an operation of holding a shared lock can be performed, but an operation of holding an exclusive lock or a semi-shared lock cannot be performed.
Drop	Exclusive lock. You cannot perform any other operations on the current table or partition when performing this operation.

 NOTE

If a conflict caused by the lock mechanism exists in the write operation, the operation that preferentially holds the lock succeeds, and other operations fail.

## Procedure

### Starting a Transaction

**Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster** > *Name of the desired cluster* > **Services** > **Hive** > **Configurations** > **All Configurations** > **MetaStore(Role)** > **Transaction**.

**Step 2** Set **metastore.compactor.initiator.on** to **true**.

**Step 3** Set **metastore.compactor.worker.threads** to a positive integer.

 NOTE

**metastore.compactor.worker.threads**: Specifies the number of working threads for running the compression program on MetaStore. Set this parameter based on the actual requirements. If the value is too small, the transaction compression task is executed slowly. If the value is too large, the MetaStore execution performance deteriorates.

**Step 4** Log in to the Hive client and run the following command to enable the following parameters. For details, see [Using a Hive Client](#).

```
set hive.support.concurrency=true;
```

```
set hive.exec.dynamic.partition.mode=nonstrict;
```

```
set hive.txn.manager=org.apache.hadoop.hive.ql.lockmgr.DbTxnManager;
```

Create a transaction table.

**Step 5** Run the following command to create a transaction table:

```
CREATE TABLE [IF NOT EXISTS] [db_name.]table_name (col_name data_type  
[COMMENT col_comment], ...) [ROW FORMAT row_format] STORED AS orc .....  
TBLPROPERTIES ('transactional'='true'[, 'groupId'='group1' ... ] );
```

For example:

```
CREATE TABLE acidTbl (a int, b int) STORED AS ORC TBLPROPERTIES  
('transactional'='true');
```

 NOTE

- Currently, the transactions support only the ORC format.
- External tables are not supported.
- Sorted tables are not supported.
- To create a transaction table, you must add the table attribute **transactional'='true'**.
- The transaction table can be read and written only in transaction mode.

**Use the transaction table.**

**Step 6** Run commands to use the transaction table. The following uses the **acidTbl** table as an example:

- Insert data into an existing transaction table:

**INSERT INTO acidTbl VALUES(1,1);**

- Update an existing transaction table:

**UPDATE acidTbl SET b = 10 where a = 1;**

The content of **acidTbl** is changed to:

```
+-----+-----+
| acidtbl.a | acidtbl.b |
+-----+-----+
| 1         | 10        |
+-----+-----+
1 row selected (0.775 seconds)
```

- Merge the old and new transaction tables:

The **acidTbl\_update** table contains the following data:

```
+-----+-----+
| acidtbl_update.a | acidtbl_update.b |
+-----+-----+
| 1                 | 20                |
| 2                 | 10                |
+-----+-----+
2 rows selected (0.537 seconds)
```

**MERGE INTO acidTbl AS a  
USING acidTbl\_update AS b ON a.a = b.a  
WHEN MATCHED THEN UPDATE SET b = b.b  
WHEN NOT MATCHED THEN INSERT VALUES (b.a, b.b);**

The content of **acidTbl** is changed to:

```
+-----+-----+
| acidtbl.a | acidtbl.b |
+-----+-----+
| 1         | 20        |
| 2         | 10        |
+-----+-----+
2 rows selected (0.666 seconds)
```

 **NOTE**

If "Error evaluating cardinality\_violation" is displayed when you run the **merge** command, check whether duplicate connection keys exist or run the **set hive.merge.cardinality.check=false** command to avoid this exception.

- Delete records from the transaction table.

**DELETE FROM acidTbl where a = 2;**

```
+-----+-----+
| acidtbl.a | acidtbl.b |
+-----+-----+
| 1         | 20        |
+-----+-----+
1 row selected (1.253 seconds)
```

### Checking the Transaction Execution Status

**Step 7** Run the following command to check the transaction execution status:

- Check the lock:  
**show locks;**
- Check the compression task:  
**show compactions;**
- Check the task execution status:  
**show transactions;**

- Interrupt a transaction:  
**abort transactions** *TransactionId*;  
  
----End

## Configuring the Compression Function

HDFS does not support in-place file changing. For the new content, HDFS does not provide read consistency either. To provide these features on HDFS, we follow the standard approach used in other data warehouse tools: table or partition data is stored in a set of base files, and new, updated, as well as deleted records are stored in incremental files. Each transaction creates a new set of incremental files to change the table or partition. When read, the base files and the incremental files are merged and the changes of the update or deletion are applied.

Writing a transaction table generates some small files in HDFS. Hive provides major and minor compression policies for combining these small files.

## Procedure of Automatic Compression

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster** > *Name of the desired cluster* > **Services** > **Hive** > **Configurations** > **All Configurations** > **MetaStore(Role)** > **Transaction**.
- Step 2** Set the following parameters as required:

**Table 9-10** Parameter description

Parameter	Description
hive.compactor.check.interval	Interval of executing compression threads. Unit: second. Default value: <b>300</b>
hive.compactor.cleaner.run.interval	Interval of executing cleaning threads. Unit: millisecond. Default value: <b>5,000</b> .
hive.compactor.delta.num.threshold	Threshold of the number of incremental files that trigger minor compression. Default value: <b>10</b>
hive.compactor.delta.pct.threshold	Ratio threshold of the total size of incremental files (delta) that trigger Major compression to the size of base files. The value <b>0.1</b> indicates that Major compression is triggered when the ratio of the total size of delta files to the size of base files is 10%. Default value: <b>0.1</b>
hive.compactor.max.num.delta	Maximum number of incremental files that the compressor will attempt to process in a single job. Default value: <b>500</b>
metastore.compactor.initiator.on	Indicates whether to run the startup program thread and cleanup program thread on the MetaStore instance. The value must be <b>true</b> . Default value: <b>false</b> .

Parameter	Description
metastore.compactor.worker.threads	Number of compression program work threads running on MetaStore. If this parameter is set to <b>0</b> , no compression is performed. To use a transaction, you must set this parameter to a positive number on one or more instances of the MetaStore service. Unit: second Default value: <b>0</b>

**Step 3** Log in to the Hive client and perform compression. For details, see [Using a Hive Client](#).

```
CREATE TABLE table_name (
  id int, name string
)
CLUSTERED BY (id) INTO 2 BUCKETS STORED AS ORC
TBLPROPERTIES ("transactional"="true",
  "compactor.mapreduce.map.memory.mb"="2048",          -- Specify the properties of a compression
  "compactor.hive.compactor.delta.num.threshold"="4", -- If there are more than four incremental
  "compactor.hive.compactor.delta.pct.threshold"="0.5" -- If the ratio of the incremental file size to
  "tblprops.orc.compress.size"="8192");
);
```

or

```
ALTER TABLE table_name COMPACT 'minor' WITH OVERWRITE TBLPROPERTIES
("compactor.mapreduce.map.memory.mb"="3072"); -- Specify the properties of a compression map job.
ALTER TABLE table_name COMPACT 'major' WITH OVERWRITE TBLPROPERTIES
("tblprops.orc.compress.size"="8192"); -- Modify any other Hive table attributes.
```

 **NOTE**

After compression, small files are not deleted immediately. After the cleaner thread performs cleaning, the files are deleted in batches.

----End

## 9.28 Switching the Hive Execution Engine to Tez

### Scenario

Hive can use the Tez engine to process data computing tasks. Before executing a task, you can manually switch the execution engine to Tez.

### Prerequisites

The TimelineServer role of the Yarn service has been installed in the cluster and is running properly.

### Switching the Execution Engine on the Client to Tez

**Step 1** Install and log in to the Hive client. For details, see [Using a Hive Client](#).

**Step 2** Run the following commands to switch the engine and enable the `yarn.timeline-service.enabled` parameter:

```
set hive.execution.engine=tez;
```

```
set yarn.timeline-service.enabled=true;
```

 NOTE

- After **yarn.timeline-service.enabled** is enabled, you can view the details about the tasks executed by the Tez engine on TezUI. After this function is enabled, task information will be reported to TimelineServer. If the TimelineServer instance is faulty, the task will fail.
- Tez uses the ApplicationMaster buffer pool. Therefore, **yarn.timeline-service.enabled** must be enabled before Tez tasks are submitted. Otherwise, this parameter cannot take effect and you need to log in to the client again to configure it.
- When the execution engine needs to be switched to another engine, you need to run the **set yarn.timeline-service.enabled=false** command on the client to disable the **yarn.timeline-service.enabled** parameter.
- To specify a Yarn running queue, run the **set tez.queue.name=default** command on the client.

**Step 3** Submit and execute the Tez tasks.

**Step 4** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Name of the desired cluster > Services > Tez > TezUI (host name)** to view the task execution status on the TezUI page.

----End

## Switching the Default Execution Engine of Hive to Tez

**Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Name of the desired cluster > Services > Hive > Configurations > All Configurations > HiveServer(Role)**, and search for **hive.execution.engine**.

**Step 2** Set **hive.execution.engine** to **tez**.

**Step 3** Choose **Hive(Service) > Customization** and search for **yarn.site.customized.configs**.

**Step 4** Add a customized parameter **yarn.timeline-service.enabled** next to **yarn.site.customized.configs** and set its value to **true**.

 NOTE

- After **yarn.timeline-service.enabled** is enabled, you can view the details about the tasks executed by the Tez engine on TezUI. After this function is enabled, task information will be reported to TimelineServer. If the TimelineServer instance is faulty, the task will fail.
- Tez uses the ApplicationMaster buffer pool. Therefore, **yarn.timeline-service.enabled** must be enabled before Tez tasks are submitted. Otherwise, this parameter cannot take effect and you need to log in to the client again to configure it.
- When the execution engine needs to be switched to another one, you need to set the value of parameter **yarn.timeline-service.enabled** to **false**.

**Step 5** Click **Save**. In the displayed confirmation dialog box, click **OK**.

**Step 6** Choose **Dashboard > More > Restart Service** to restart the Hive service. Enter the password to restart the service.

**Step 7** Install and log in to the Hive client. For details, see [Using a Hive Client](#).

**Step 8** Submit and execute the Tez tasks.

**Step 9** Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **Tez** > **TezUI** (*host name*). On the displayed TezUI page, view the task execution status.

----End

## 9.29 Connecting Hive with External RDS

### NOTE

- RDS indicates the relational database in this section. This section describes how to connect Hive with the open-source MySQL and Postgres databases.
- After an external metadata database is deployed in a cluster with Hive data, the original metadata table will not be automatically synchronized. Therefore, before installing Hive, you need to check whether the metadata is external RDS or built-in DBService. If the metadata is external RDS, you need to configure the metadata to external RDS when installing Hive or when there is no Hive data. After the installation, the metadata cannot be modified. Otherwise, the original metadata will be lost.

**Hive supports access to open source MySQL and Postgres metabases.**

**Step 1** Install the open source MySQL or Postgres database.

### NOTE

The node where the database is installed must be in the same network segment as the cluster, so that they can access each other.

**Step 2** Upload the driver package.

- Postgres: Use the open source Postgres driver package to replace the existing one of the cluster. Upload the Postgres driver package **postgresql-42.2.5.jar** to the `/${BIGDATA_HOME}/third_lib/Hive` directory on all MetaStore instance nodes. To download the open-source driver package, visit <https://repo1.maven.org/maven2/org/postgresql/postgresql/42.2.5/>.
- MySQL: Go to the MySQL official website (<https://www.mysql.com/>), select **Downloads** > **Community** > **MySQL Connectors** > **Connector/J** to download the driver package of the corresponding version, and upload the driver package to the `/${BIGDATA_HOME}/third_lib/Hive` directory on all RDSMetastore nodes.

**Step 3** Create a database in RDS as the specified database of Hive metadata.

Run the following command in Postgres or MySQL:

```
create database databasename;
```

### NOTE

In the preceding command, *databasename* indicates the database name.

**Step 4** Import the SQL statements for creating metadata tables.

- Path of the Postgres SQL file: `/${BIGDATA_HOME}/FusionInsight_HD_8.1.2.2/install/FusionInsight-Hive-3.1.0/hive-3.1.0/scripts/metastore/upgrade/postgres/hive-schema-3.1.0.postgres.sql`

Run the following command to import the SQL file to Postgres:

```
./bin/psql -U username -d databasename -f hive-schema-3.1.0.postgres.sql
```

Specifically:

**./bin/psql** is in the Postgres installation directory.

**username** indicates the username for logging in to Postgres.

**databasename** indicates the database name.

- Path of the MySQL file: **`\${BIGDATA\_HOME}/FusionInsight\_HD\_8.1.2.2/install/FusionInsight-Hive-3.1.0/hive-3.1.0/scripts/metastore/upgrade/mysql/hive-schema-3.1.0.mysql.sql**

Run the following command to import the SQL file to the MySQL database:

```
./bin/mysql -u username -ppassword -Ddatabasename<hive-schema-3.1.0.mysql.sql
```

Specifically:

**./bin/mysql** is in the MySQL installation directory.

**username** indicates the user name for logging in to MySQL.

**databasename** indicates the database name.

- Step 5** To connect Hive to the open-source database, log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Name of the desired cluster > Services > Hive > Configurations > All Configurations > Hive(Service) > MetaDB**, modify the following parameters, and click **Save**.

**Table 9-11** Parameter description

Parameter	Default Value	Description
javax.jdo.option.ConnectionDriverName	org.postgresql.Driver	<p>Driver class for connecting metadata on MetaStore</p> <ul style="list-style-type: none"> <li>• If an external MySQL database is used, the value is: <b>com.mysql.jdbc.Driver</b></li> <li>• If an external Postgres database is used, the value is: <b>org.postgresql.Driver</b></li> </ul>

Parameter	Default Value	Description
javax.jdo.option.ConnectionURL	jdbc:postgresql://% {DBSERVICE_FLOAT_IP}% {DBServer}:% {DBSERVICE_CPORT}/ hivemeta? socketTimeout=60	URL of the JDBC link of the MetaStore metadata <ul style="list-style-type: none"> <li>If an external MySQL database is used, the value is: <b>jdbc:mysql://MySQL IP address.MySQL port number/test? useSSL=false</b></li> <li>If an external Postgres database is used, the value is: <b>jdbc:postgresql:// Postgres IP address.Postgres port number/test</b></li> </ul>
javax.jdo.option.ConnectionUserName	hive\${SERVICE_INDEX}\$ {SERVICE_INDEX}	Username for connecting to the metadata database on Metastore

**Step 6** Change the Postgres database password in MetaStore. Choose **Cluster > Name of the desired cluster > Services > Hive > Configurations > All Configurations > MetaStore(Role) > MetaDB**, modify the following parameters, and click **Save**.

**Table 9-12** Parameter description

Parameter	Default Value	Description
javax.jdo.option.extend.ConnectionPassword	*****	User password for connecting to the external metadata database on Metastore. The password is encrypted in the background.

**Step 7** Log in to each MetaStore background node and check whether the local directory **/opt/Bigdata/tmp** exists.

- If yes, go to **Step 8**.
- If no, run the following commands to create one:

```
mkdir -p /opt/Bigdata/tmp
chmod 755 /opt/Bigdata/tmp
```

**Step 8** Save the configuration. Choose **Dashboard > More > Restart Service**, and enter the password to restart the Hive service.

----End

## 9.30 Redis-based CacheStore of HiveMetaStore

### Scenario

The MetaStore service of Hive can cache the metadata of some tables in Redis.

### Prerequisites

The Redis service has been installed in a cluster.

### Configure Parameters Related to Metastore

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster** > *Name of the desired cluster* > **Services** > **Hive** > **Configurations** > **All Configurations** > **MetaStore(Role)** > **Customization**. Modify the following parameters to interconnect the cache of MetaStore to the Redis service.

**Table 9-13** Parameters

Parameter	Value	Description
hive.metastore.rawstore.impl	org.apache.hadoop.hive.metastore.cache.redis.RedisCachedStore	(Mandatory) Implementation class of CachedStore. Use the customized RedisCachedStore.
redis.cluster.host.and.port	xxx.xxx.xxx.xxx:22400;xxx.xxx.xxx.xxx.xxx:22401	(Mandatory) IP address and port number of any node in the Redis cluster. The format is <i>ip:port</i> . <i>ip:port</i> . The value cannot end with a semicolon (;).
metastore.cached.rawstore.cached.object.whitelist	catalog.database.table,catalog.database.table	(Optional) Cache table whitelist. The configured tables are cached to Redis. Multiple tables are separated by commas (,). The default separator is <i>.*</i> , that is, all tables are cached. <b>NOTE</b> The table name consists of <b>catalog.database.table</b> . The default catalog is <b>hive</b> .

Parameter	Value	Description
metastore.cached.rastore.cached.object.blacklist	catalog.database.table,catalog.database.table	(Optional) Cache table blacklist. Tables that are not configured in the blacklist are not cached in Redis. Multiple tables are separated by commas (.). By default, this parameter is left blank. <b>NOTE</b> The table name consists of <b>catalog.database.table</b> . The default catalog is <b>hive</b> .
redis.cache.prewarm.cron	cronTab expression, for example, 0 0 16 * *?	(Optional) Periodically execute the cron expression of prewarm to update the data cached in the metastore to redisCache for synchronization.
metastore.cached.rastore.catalogs	hive	(Optional) Catalog to be cached. The default value is <b>hive</b> .
jedis.pool.max.wait.mills	30,000	(Optional) Obtain the Redis connection timeout interval. In security mode, the timeout interval can be longer. The unit is ms. The default value is 30,000 ms.
jedis.pool.max.idle	200	(Optional) Maximum number of idle connections in the Jedis connection pool. You are advised to set this parameter to the value of <b>max.total</b> . The default value is 200.
jedis.pool.max.total	200	(Optional) Maximum number of connections in the Jedis connection pool. The default value is 200.
redis.security.enabled	true or false	(Optional) Whether to enable the Redis cache security mode. The default value is <b>true</b> , indicating that the security mode is enabled.

 NOTE

If the cluster is installed in non-security mode, choose **Cluster** > *Name of the desired cluster* > **Services** > **Redis** > **Configurations** > **All Configurations** > **Redis** > **Security** and check whether the value of **REDIS\_SECURITY\_ENABLED** is **false**. If not, change it to **false**. Otherwise, the Redis service does not comply with the non-security mode of the current Metastore.

**Step 2** Save the configuration and choose **Dashboard** > **More** > **Restart Service** to restart the Hive service.

----End

## Precautions

If Redis is switched back to the native non-cache mode and then switched back after a period of time, the added, deleted, or modified metadata cannot be synchronized to the Redis when the database is used. Therefore, before switching back, you must clear the cache table in the Redis and synchronize the metadata again in either of the following two clearing modes:

- Log in to the Redis client and run the **flushall** command on all Redis nodes.
- Log in to the Redis client and run the following commands to change the two Redis identifiers. *{hiveServiceName}* is the value of **HIVE\_DEFAULT\_GROUP** in the Metastore configuration file **ENV\_VARS**. The default value is **hive**.

```
set {hiveServiceName}-hive-isRedisAvailable false
del {hiveServiceName}-hive-isCanPrewarm
```

## 9.31 Hive Materialized View

### Introduction

A Hive materialized view is a special table obtained based on the query results of Hive internal tables. A materialized view can be considered as an intermediate table that stores actual data and occupies physical space. The tables on which a materialized view depends are called the base tables of the materialized view.

Materialized views are used to pre-compute and save the results of time-consuming operations such as table joining or aggregation. When executing a query, you can rewrite the query statement based on the base tables to the query statement based on materialized views. In this way, you do not need to perform time-consuming operations such as join and group by, thereby quickly obtaining the query result.

 NOTE

- A materialized view is a special table that stores actual data and occupies physical space.
- Before deleting a base table, you must delete the materialized view created based on the base table.
- The materialized view creation statement is atomic, which means that other users cannot see the materialized view until all query results are populated.
- A materialized view cannot be created based on the query results of another materialized view.
- A materialized view cannot be created based on the results of a tableless query.
- You cannot insert, update, delete, load, or merge materialized views.
- You can perform complex query operations on materialized views, because they are special tables in nature.
- When the data of a base table is updated, you need to manually update the materialized view. Otherwise, the materialized view will retain the old data. That is, the materialized view expires.
- You can use the describe syntax to check whether the materialized view created based on ACID tables has expired.
- The describe statement cannot be used to check whether a materialized view created based on non-ACID tables has expired.

## Creating a Materialized View

### Syntax

```
CREATE MATERIALIZED VIEW [IF NOT EXISTS] [db_name.]materialized_view_name
[COMMENT materialized_view_comment]
DISABLE REWRITE
[ROW FORMAT row_format]
[STORED AS file_format]
| STORED BY 'storage.handler.class.name' [WITH SERDEPROPERTIES (...)]
]
[LOCATION hdfs_path]
[TBLPROPERTIES (property_name=property_value, ...)]
AS
<query>;
```

 NOTE

- Currently, the following materialized view file formats are supported: PARQUET, TextFile, SequenceFile, RCfile, and ORC. If **STORED AS** is not specified in the creation statement, the default file format is ORC.
- Names of materialized views must be unique in the same database. Otherwise, you cannot create a new materialized view, and data files of the original materialized view will be overwritten by the data files queried based on the base table in the new one. As a result, data may be tampered with. (After being tampered with, the materialized view can be restored by re-creating the materialized view.)

### Cases

**Step 1** Log in to the Hive client and run the following command to enable the following parameters. For details, see [Using a Hive Client](#).

```
set hive.support.concurrency=true;
```

```
set hive.exec.dynamic.partition.mode=nonstrict;
```

```
set hive.txn.manager=org.apache.hadoop.hive.ql.lockmgr.DbTxnManager;
```

### Step 2 Create a base table and insert data.

```
create table tb_emp(  
empno int,ename string,job string,mgr int,hiredate TIMESTAMP,sal float,comm float,deptno int  
)stored as orc  
tblproperties('transactional'='true');  
  
insert into tb_emp values(7369, 'SMITH', 'CLERK',7902, '1980-12-17 08:30:09',800.00,NULL,20),  
(7499, 'ALLEN', 'SALESMAN',7698, '1981-02-20 17:12:00',1600.00,300.00,30),  
(7521, 'WARD', 'SALESMAN',7698, '1981-02-22 09:05:34',1250.00,500.00,30),  
(7566, 'JONES', 'MANAGER', 7839, '1981-04-02 10:14:13',2975.00,NULL,20),  
(7654, 'MARTIN', 'SALESMAN',7698, '1981-09-28 08:36:17',1250.00,1400.00,30),  
(7698, 'BLAKE', 'MANAGER',7839, '1981-05-01 11:12:55',2850.00,NULL,30),  
(7782, 'CLARK', 'MANAGER',7839, '1981-06-09 15:45:28',2450.00,NULL,10),  
(7788, 'SCOTT', 'ANALYST',7566, '1987-04-19 14:05:34',3000.00,NULL,20),  
(7839, 'KING', 'PRESIDENT',NULL, '1981-11-17 10:18:25',5000.00,NULL,10),  
(7844, 'TURNER', 'SALESMAN',7698, '1981-09-08 09:05:34',1500.00,0.00,30),  
(7876, 'ADAMS', 'CLERK',7788, '1987-05-23 15:07:44',1100.00,NULL,20),  
(7900, 'JAMES', 'CLERK',7698, '1981-12-03 16:23:56',950.00,NULL,30),  
(7902, 'FORD', 'ANALYST',7566, '1981-12-03 08:48:17',3000.00,NULL,20),  
(7934, 'MILLER', 'CLERK',7782, '1982-01-23 11:45:29',1300.00,NULL,10);
```

### Step 3 Create a materialized view based on the results of the **tb\_emp** query.

```
create materialized view group_mv disable rewrite  
row format serde 'org.apache.hadoop.hive.serde2.JsonSerDe'  
stored as textfile  
tblproperties('mv_content'='Total compensation of each department')  
as select deptno,sum(sal) sum_sal from tb_emp group by deptno;
```

----End

## Applying a Materialized View

Rewrite the query statement based on base tables to the query statement based on materialized views to improve the query efficiency.

### Cases

Execute the following query statement:

```
select deptno,sum(sal) from tb_emp group by deptno having sum(sal)>10000;
```

Based on the created materialized view, rewrite the query statement:

```
select deptno, sum_sal from group_mv where sum_sal>10000;
```

## Checking a Materialized View

### Syntax

```
SHOW MATERIALIZED VIEWS [IN database_name]  
['identifier_with_wildcards'];
```

```
DESCRIBE [EXTENDED | FORMATTED] [db_name.]materialized_view_name;
```

### Cases

```
show materialized views;
```

```
describe formatted group_mv;
```

## Deleting a Materialized View

### Syntax

```
DROP MATERIALIZED VIEW [db_name.]materialized_view_name;
```

**Cases**

```
drop materialized view group_mv;
```

## Rebuilding a Materialized View

When a materialized view is created, the base table data is filled in the materialized view. However, the data that is added, deleted, or modified in the base table is not automatically synchronized to the materialized view. Therefore, you need to manually rebuild the view after updating the data.

**Syntax**

```
ALTER MATERIALIZED VIEW [db_name.]materialized_view_name REBUILD;
```

**Cases**

```
alter materialized view group_mv rebuild;
```

 **NOTE**

When the base table data is updated but the materialized view data is not updated, the materialized view is in the expired state by default.

The describe statement can be used to check whether a materialized view created based on transaction tables has expired. If the value of **Outdated for Rewriting** is **Yes**, the license has expired. If the value of **Outdated for Rewriting** is **No**, the license has not expired.

## 9.32 Hive Supporting Reading Hudi Tables

### Hive External Tables Corresponding to Hudi Tables

A Hudi source table corresponds to a copy of HDFS data. The Hudi table data can be mapped to a Hive external table through the Spark component, Flink component, or Hudi client. Based on the external table, Hive can easily perform real-time query, read-optimized view query, and incremental view query.

 NOTE

- Different view queries are provided for different types of Hudi source tables:
  - When the Hudi source table is a Copy-On-Write (COW) table, it can be mapped to a Hive external table. The table supports real-time query and incremental view query.
  - When the Hudi source table is a Merge-On-Read (MOR) table, it can be mapped to two Hive external tables (RO table and RT table). The RO table supports read-optimized view query, and the RT table supports real-time view query and incremental view query.
- Hive external tables cannot be added, deleted, or modified (including **insert**, **update**, **delete**, **load**, **merge**, **alter** and **msck**). Only the query operation (**select**) is supported.
- Granting table permissions: The update, alter, write, and all permissions cannot be modified.
- Backup and restoration: The RO and RT tables are mapped from the same Hudi source table. When one table is backed up, the other table is also backed up. The same applies to restoration. Therefore, only one table needs to be backed up.
- Hudi bootstrap tables: The storage mode of bootstrap tables is different from that of common Hudi tables. Therefore, you need to configure **hive.user.aux.jars.path** for the Tez query engine. Log in to FusionInsight Manager, choose **Cluster > Services > Hive > Configurations > All Configurations**, and add the following paths to the value of **hive.user.aux.jars.path** (use commas (,) as separators):
  - `${BIGDATA_HOME}/FusionInsight_HD_8.1.2.2/install/FusionInsight-Hive-3.1.0/hive-3.1.0/lib/hbase-shaded-miscellaneous-xxx.jar`
  - `${BIGDATA_HOME}/FusionInsight_HD_8.1.2.2/install/FusionInsight-Hive-3.1.0/hive-3.1.0/lib/hbase-metrics-api-xxx.jar`
  - `${BIGDATA_HOME}/FusionInsight_HD_8.1.2.2/install/FusionInsight-Hive-3.1.0/hive-3.1.0/lib/hbase-metrics-xxx.jar`
  - `${BIGDATA_HOME}/FusionInsight_HD_8.1.2.2/install/FusionInsight-Hive-3.1.0/hive-3.1.0/lib/hbase-protocol-shaded-xxx.jar`
  - `${BIGDATA_HOME}/FusionInsight_HD_8.1.2.2/install/FusionInsight-Hive-3.1.0/hive-3.1.0/lib/hbase-shaded-protobuf-xxx.jar`
  - `${BIGDATA_HOME}/FusionInsight_HD_8.1.2.2/install/FusionInsight-Hive-3.1.0/hive-3.1.0/lib/htrace-core4-4.2.0-incubating-xxx.jar`

Replace *xxx* with the actual version in the path of the HiveServer node. For example, if the name of **hbase-shaded-miscellaneous-xxx.jar** in the actual environment is **hbase-shaded-miscellaneous-3.3.0.jar**, replace *xxx* with **3.3.0**.
- Component versions:
  - Hive: FusionInsight\_HD\_8.1.2.2; Hive kernel version 3.1.0.
  - Spark2x: FusionInsight\_Spark2x\_8.1.2.2; Hudi kernel version: 0.9.0.

## Creating Hive External Tables Corresponding to Hudi Tables

Generally, Hudi table data is synchronized to Hive external tables when the data is imported to the lake. In this case, you can directly query the corresponding Hive external tables in Beeline. If the data is not synchronized to the Hive external tables, you can use the Hudi client tool **run\_hive\_sync\_tool.sh** to synchronize data manually.

## Querying Hive External Tables Corresponding to Hudi Tables

### Prerequisites

Set **hive.input.format** before using Hive to query a Hudi table.

In addition, you need to set another three parameters for incremental query. The three parameters are table-level parameters. Each Hudi source table corresponds to three parameters, where **hoodie.hudisourcetablename** indicates the name of the Hudi source table (not the name of the Hive external table).

**Table 9-14** Parameter description

Parameter	Default Value	Description
hoodie.hudisourcetable-name.consume.mode	None	Query mode of the Hudi table. <ul style="list-style-type: none"> <li>Incremental query: Set it to <b>INCREMENTAL</b>.</li> <li>Non-incremental query: Do not set this parameter or set it to <b>SNAPSHOT</b>.</li> </ul>
hoodie.hudisourcetable-name.consume.start.timestamp	None	Start time of the incremental query on the Hudi table. <ul style="list-style-type: none"> <li>Incremental query: start time of the incremental query.</li> <li>Non-incremental query: Do not set this parameter.</li> </ul>
hoodie.hudisourcetable-name.consume.max.commits	None	The incremental query on the Hudi table is based on the number of commits after <b>hoodie.hudisourcetable-name.consume.start.timestamp</b> . <ul style="list-style-type: none"> <li>Incremental query: number of commits. For example, if this parameter is set to <b>3</b>, data after three commits from the specified start time is queried. If this parameter is set to <b>-1</b>, all data committed after the specified start time is queried.</li> <li>Non-incremental query: Do not set this parameter.</li> </ul>

### Querying a Hudi COW Table

For example, the name of a Hudi source table of the COW type is **hudicow**, and the name of the mapped Hive external table is **hudicow**.

- Real-time view query on the COW table: After **hive.input.format** is set, query the COW table as a common Hive table.  
**set hive.input.format= org.apache.hadoop.hive.ql.io.HiveInputFormat;**  
**Select \* from hudicow;**
- Incremental query on the COW table: In addition to **hive.input.format**, you need to set three incremental query parameters based on the name of the Hudi source table. The **where** clause of the incremental query statements

must contain ``_hoodie_commit_time`>'xxx'`, where `xxx` indicates the value of `hoodie.hudisourcetable.consume.start.timestamp`.

```
set hive.input.format= org.apache.hadoop.hive.ql.io.HiveInputFormat;
set hoodie.hudicow.consume.mode= INCREMENTAL;
set hoodie.hudicow.consume.max.commits=3;
set hoodie.hudicow.consume.start.timestamp= 20200427114546;
select count(*) from hudicow where
`_hoodie_commit_time`>'20200427114546';
```

### Querying a Hudi MOR Table

For example, the name of a Hudi source table of the MOR type is `hudimor`, and the two mapped Hive external tables are `hudimor_ro` (RO table) and `hudimor_rt` (RT table).

- Read-optimized view query on the RO table: After `hive.input.format` is set, query the COW table as a common Hive table.  

```
set hive.input.format= org.apache.hadoop.hive.ql.io.HiveInputFormat;
Select * from hudicow_ro;
```
- Real-time view query on the RT table: After `hive.input.format` is set, the latest data of the Hudi source table can be queried.  

```
set hive.input.format= org.apache.hadoop.hive.ql.io.HiveInputFormat;
Select * from hudicow_rt;
```
- Incremental query on the RT table: In addition to `hive.input.format`, you need to set three incremental query parameters based on the name of the Hudi source table. The `where` clause of the incremental query statements must contain ``_hoodie_commit_time`>'xxx'`, where `xxx` indicates the value of `hoodie.hudisourcetable.consume.start.timestamp`.

```
set
hive.input.format=org.apache.hudi.hadoop.hive.HoodieCombineHiveInputFormat;
set hoodie.hudimor.consume.mode=INCREMENTAL;
set hoodie.hudimor.consume.max.commits=-1;
set hoodie.hudimor.consume.start.timestamp=20210207144611;
select * from hudimor_rt where
`_hoodie_commit_time`>'20210207144611';
```

#### NOTE

- `set hive.input.format=org.apache.hudi.hadoop.hive.HoodieCombineHiveInputFormat`; is used only for the incremental query on the RT table and cannot be used for other tables. Therefore, after the incremental query on the RT table is complete, run `set hive.input.format=org.apache.hadoop.hive.ql.io.HiveInputFormat`. Alternatively, run `set hive.input.format=org.apache.hadoop.hive.ql.io.CombineHiveInputFormat`; to change the value to the default value for the queries on other tables.
- `set hoodie.hudisourcetable.consume.mode=INCREMENTAL`; is used only for the incremental query on the table. To switch to another query mode, run `set hoodie.hudisourcetable.consume.mode=SNAPSHOT`;

## 9.33 Hive Supporting Cold and Hot Storage of Partitioned Metadata

### Cold and Hot Storage of Partitioned Metadata

- The metadata that have not been used for a long time is moved to a backup table to reduce the pressure on metadata databases. This process is called partitioned data freezing. The partitions in which data is moved are cold partitions, partitions that are not frozen are hot partitions. A table with a cold partition is a frozen table. Moving the frozen data back to the original metadata table is called partitioned data unfreezing.
- When a partition is changed from a hot partition to a cold partition, only metadata is identified. The partition path and data file content on the HDFS service side do not change.

### Freezing a Partition

The user who creates the table can freeze one or more partitions based on filter criteria. The format is **freeze partitions Database name Table name where Filter criteria**.

Example:

```
freeze partitions testdb.test where year <= 2021;  
freeze partitions testdb.test where year<=2021 and month <= 5;  
freeze partitions testdb.test where year<=2021 and month <= 5 and day <= 27;
```

### Unfreezing a Partition

The user who creates the table can unfreeze one or more partitions based on filter criteria. The format is **unfreeze partitions Database name Table name where Filter criteria**. Example:

```
unfreeze partitions testdb.test where year <= 2021;  
unfreeze partitions testdb.test where year<=2021 and month <= 5;  
unfreeze partitions testdb.test where year<=2021 and month <= 5 and day <= 27;
```

### Querying Tables with Frozen Data

- Querying all frozen tables in the current database  
**show frozen tables;**
- Querying all frozen tables in the **dbname** database  
**show frozen tables in dbname;**

### Querying Frozen Partitions of a Frozen Table

Querying frozen partitions

**show frozen partitions table;**

 NOTE

- By default, only partitions of the int, string, varchar, date, or timestamp type can be frozen in the metadata database.
- For external metadata databases, only the Postgres database is supported, and only partitions of the int, string, varchar, or timestamp type can be frozen.
- You need to unfreeze data to restore the metadata of a frozen table using MSCK. If a frozen table has been backed up, you can run **msck repair** to restore the table, and you can only run this command to unfreeze the table.
- You need to unfreeze data before renaming a frozen partition. Otherwise, a message indicating that the partition does not exist is displayed.
- When a table that contains frozen data is deleted, the frozen data is also deleted.
- When a partition that contains frozen data is deleted, information about the frozen partition and HDFS service data are not deleted.
- When you run the **select** command to query data, the criteria for filtering the data in cold partitions is automatically added. The query result does not contain the data in cold partitions.
- When you run the **show partitions table** command to query the partitioned data in the table, the query result does not contain the data in cold partitions. You can run the **show frozen partitions table** command to query frozen partitions.

## 9.34 Hive Supporting ZSTD Compression Formats

Zstandard (ZSTD) is an open-source lossless data compression algorithm. Its compression performance and compression ratio are better than those of other compression algorithms supported by Hadoop. Hive with this feature supports tables in ZSTD compression formats. The ZSTD compression formats supported by Hive include ORC, RCFile, TextFile, JsonFile, Parquet, Sequence, and CSV.

You can create a table in ZSTD compression format as follows:

- To create a table in ORC format, specify **TBLPROPERTIES("orc.compress"="zstd")**.  
**create table tab\_1(...) stored as orc  
TBLPROPERTIES("orc.compress"="zstd");**
- To create a table in Parquet format, specify **TBLPROPERTIES("parquet.compression"="zstd")**.  
**create table tab\_2(...) stored as parquet  
TBLPROPERTIES("parquet.compression"="zstd");**
- To create a table in other formats or common formats, run the following commands to set the **mapreduce.map.output.compress.codec** and **mapreduce.output.fileoutputformat.compress.codec** parameters to **org.apache.hadoop.io.compress.ZStandardCode**.  
**set hive.exec.compress.output=true;**  
**set mapreduce.map.output.compress=true;**  
**set  
mapreduce.map.output.compress.codec=org.apache.hadoop.io.compress.Z  
StandardCodec;**  
**set mapreduce.output.fileoutputformat.compress=true;**

```

set
mapreduce.output.fileoutputformat.compress.codec=org.apache.hadoop.i
o.compress.ZStandardCodec;
set hive.exec.compress.intermediate=true;
create table tab_3(...) stored as textfile;
    
```

 NOTE

The SQL operations on a table compressed using ZSTD are the same as those on a common compressed table. A table compressed using ZSTD supports addition, deletion, query, and aggregation SQL operations.

## 9.35 Hive Log Overview

### Log Description

**Log path:** The default save path of Hive logs is `/var/log/Bigdata/hive/role name`, the default save path of Hive1 logs is `/var/log/Bigdata/hive1/role name`, and the others follow the same rule.

- HiveServer: `/var/log/Bigdata/hive/hiveserver` (run log) and `var/log/Bigdata/audit/hive/hiveserver` (audit log)
- MetaStore: `/var/log/Bigdata/hive/metastore` (run log) and `/var/log/Bigdata/audit/hive/metastore` (audit log)
- WebHCat: `/var/log/Bigdata/hive/webhcat` (run log) and `/var/log/Bigdata/audit/hive/webhcat` (audit log)

**Log archive rule:** The automatic compression and archiving function of Hive is enabled. By default, when the size of a log file exceeds 20 MB (which is adjustable), the log file is automatically compressed. The naming rule of a compressed log file is as follows: `<Original log name>-<yyyy-mm-dd_hh-mm-ss>.[ID].log.zip`. A maximum of 20 latest compressed files are reserved. The number of compressed files and compression threshold can be configured.

**Table 9-15** Hive log list

Log Type	Log File Name	Description
Run log	<code>/hiveserver/hiveserver.out</code>	Log file that records HiveServer running environment information.
	<code>/hiveserver/hive.log</code>	Run log file of the HiveServer process.
	<code>/hiveserver/hive-omm-&lt;Date&gt;-&lt;PID&gt;-gc.log.&lt;No.&gt;</code>	GC log file of the HiveServer process.
	<code>/hiveserver/prestartDetail.log</code>	Work log file before the HiveServer startup.

Log Type	Log File Name	Description
	/hiveserver/check-serviceDetail.log	Log file that records whether the Hive service starts successfully
	/hiveserver/cleanupDetail.log	Cleanup log file about the HiveServer uninstallation
	/hiveserver/startDetail.log	Startup log file of the HiveServer process.
	/hiveserver/stopDetail.log	Shutdown log file of the HiveServer process.
	/hiveserver/localtasklog/omm_<Date>_<Task ID>.log	Run log file of the local Hive task.
	/hiveserver/localtasklog/omm_<Date>_<Task ID>-gc.log.<No.>	GC log file of the local Hive task.
	/metastore/metastore.log	Run log file of the MetaStore process.
	/metastore/hive-omm-<Date> <PID>-gc.log.<No.>	GC log file of the MetaStore process.
	/metastore/postinstallDetail.log	Work log file after the MetaStore installation.
	/metastore/prestartDetail.log	Work log file before the MetaStore startup
	/metastore/cleanupDetail.log	Cleanup log file of the MetaStore uninstallation
	/metastore/startDetail.log	Startup log file of the MetaStore process.
	/metastore/stopDetail.log	Shutdown log file of the MetaStore process.
	/metastore/metastore.out	Log file that records MetaStore running environment information.
	/webhcat/webhcat-console.out	Log file that records the normal start and stop of the WebHCat process.
	/webhcat/webhcat-console-error.out	Log file that records the start and stop exceptions of the WebHCat process.

Log Type	Log File Name	Description
	/webhcat/ prestartDetail.log	Work log file before the WebHCat startup.
	/webhcat/ cleanupDetail.log	Cleanup logs generated during WebHCat uninstallation or before WebHCat installation
	/webhcat/hive-omm- <Date>-<PID>- gc.log.<No.>	GC log file of the WebHCat process.
	/webhcat/webhcat.log	Run log file of the WebHCat process
Audit log	hive-audit.log hive-rangeraudit.log	HiveServer audit log file
	metastore-audit.log	MetaStore audit log file.
	webhcat-audit.log	WebHCat audit log file.
	jetty-<Date>.request.log	Request logs of the jetty service.

## Log Levels

**Table 9-16** describes the log levels supported by Hive.

Levels of run logs are ERROR, WARN, INFO, and DEBUG from the highest to the lowest priority. Run logs of equal or higher levels are recorded. The higher the specified log level, the fewer the logs recorded.

**Table 9-16** Log levels

Level	Description
ERROR	Logs of this level record error information about system running.
WARN	Logs of this level record exception information about the current event processing.
INFO	Logs of this level record normal running status information about the system and events.
DEBUG	Logs of this level record the system information and system debugging information.

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of the Yarn service by referring to **Modifying Cluster Service Configuration Parameters**.
- Step 2** On the menu bar on the left, select the log menu of the target role.
- Step 3** Select a desired log level and save the configuration.

 **NOTE**

The Hive log level takes effect immediately after being configured. You do not need to restart the service.

----End

## Log Formats

The following table lists the Hive log formats:

**Table 9-17** Log formats

Log Type	Format	Example
Run log	<yyyy-MM-dd HH:mm:ss,SSS> <LogLevel> <Thread that generates the log> <Message in the log> <Location of the log event>	2014-11-05 09:45:01,242   INFO   main   Starting hive metastore on port 21088   org.apache.hadoop.hive.metastore.HiveMetaStore.main(HiveMetaStore.java:5198)
Audit log	<yyyy-MM-dd HH:mm:ss,SSS> <LogLevel> <Thread that generates the log> <UserName><User IP><Time><Operation><Resource><Result><Detail > <Location of the log event >	2018-12-24 12:16:25,319   INFO   HiveServer2-Handler-Pool: Thread-185   UserName=hive UserIP=10.153.2.204 Time=2018/12/24 12:16:25 Operation=CloseSession Result=SUCCESS Detail=   org.apache.hive.service.cli.thrift.ThriftCLIService.logAuditEvent(ThriftCLIService.java:434)

## 9.36 Hive Performance Tuning

### 9.36.1 Creating Table Partitions

#### Scenario

During the Select query, Hive generally scans the entire table, which is time-consuming. To improve query efficiency, create table partitions based on service requirements and query dimensions.

## Procedure

**Step 1** Log in to the node where the Hive client has been installed as user **root**.

**Step 2** Run the following command to go to the client installation directory, for example, **/opt/client**.

```
cd /opt/client
```

**Step 3** Run the **source bigdata\_env** command to configure environment variables for the client.

**Step 4** Run the following command on the client for login:

```
kinit Username
```

**Step 5** Run the following command to log in to the client tool:

```
beeline
```

**Step 6** Select the static or dynamic partition.

- Static partition:  
Manually enter a partition name, and use the keyword **PARTITIONED BY** to specify partition column name and data type when creating a table. During application development, use the **ALTER TABLE ADD PARTITION** statement to add a partition and use the **LOAD DATA INTO PARTITION** statement to load data to the partition, which supports only static partitions.
- Dynamic partition: Use a query command to insert results to a partition of a table. The partition can be a dynamic partition.

The dynamic partition can be enabled on the client tool by running the following command:

```
set hive.exec.dynamic.partition=true;
```

The default mode of the dynamic partition is strict. That is, at least a column must be specified as a static partition, under which dynamic sub-partitions can be created. You can run the following command to enable a completely dynamic partition:

```
set hive.exec.dynamic.partition.mode=nonstrict;
```

### NOTE

- The dynamic partition may cause a DML statement to create a large number of partitions and new mapping folders, which deteriorates system performance.
- If there are a large number of files, it takes a long time to run a SQL statement. You can run the **set mapreduce.input.fileinputformat.list-status.num-threads = 100;** statement before running a SQL statement to shorten the time. The parameter **mapreduce.input.fileinputformat.list-status.num-threads** can be set only after being added to the Hive whitelist.

----End

## 9.36.2 Optimizing Join

### Scenario

When the Join statement is used, the command execution speed and query speed may be slow in case of large data volume. To resolve this problem, you can optimize Join.

Join optimization can be classified into the following modes:

- Map Join
- Sort Merge Bucket Map Join
- Optimizing Join Sequences

### Map Join

Hive Map Join applies to small tables (the table size is less than 25 MB) that can be stored in the memory. The table size can be defined using **hive.mapjoin.smalltable.filesize**, and the default table size is 25 MB.

Map Join has two methods:

- Use `/*+ MAPJOIN(join_table) */`.
- Set the following parameter before running the statement. The default value is true in the current version.

```
set hive.auto.convert.join=true;
```

There is no Reduce task when Map Join is used. Instead, a MapReduce Local Task is created before the Map job. The task uses TableScan to read small table data to the local computer, saves and writes the data in HashTable mode to a hard disk on the local computer, upload the data to DFS, and saves the data in distributed cache. The small table data that the map task reads from the local disk or distributed cache is the output together with the large table join result.

When using Map Join, make sure that the size of small tables cannot be too large. If small tables use up memory, the system performance will deteriorate and even memory leakage occurs.

### Sort Merge Bucket Map Join

The following conditions must be met before using Sort Merge Bucket Map Join:

- The two Join tables are large and cannot be stored in the memory.
- The two tables are bucketed (clustered by (column)) and sorted (sorted by(column)) according to the join key, and the buckets counts of the two tables are in integral multiple relationship.

Set the following parameters to enable Sort Merge Bucket Map Join:

```
set hive.optimize.bucketmapjoin=true;
```

```
set hive.optimize.bucketmapjoin.sortedmerge=true;
```

This type of Map Join does not have Reduce tasks too. A MapReduce Local Task is started before the Map job to read small table data by bucket to the local

computer. The local computer saves the HashTable backup of multiple buckets and writes the backup into HDFS. The backup is also saved in the distributed cache. The small table data that the map task reads from the local disk or distributed cache by bucket is the output after mapping with the large table.

## Optimizing Join Sequences

If the Join operation is to be performed on three or more tables and different Join sequences are used, the execution time will be greatly different. Using an appropriate Join sequence can shorten the time for task execution.

Rules of a Join sequence:

- A table with small data volume or a combination with fewer results generated after a Join operation is executed first.
- A table with large data volume or a combination with more results generated after a Join operation is executed later.

For example, the **customer** table has the largest data volume, and fewer results will be generated if a Join operation is performed on the **orders** and **lineitem** tables first.

The original Join statement is as follows.

```
select
  l_orderkey,
  sum(l_extendedprice * (1 - l_discount)) as revenue,
  o_orderdate,
  o_shippriority
from
  customer,
  orders,
  lineitem
where
  c_mktsegment = 'BUILDING'
  and c_custkey = o_custkey
  and l_orderkey = o_orderkey
  and o_orderdate < '1995-03-22'
  and l_shipdate > '1995-03-22'
limit 10;
```

After the sequence is optimized, the Join statements are as follows:

```
select
  l_orderkey,
  sum(l_extendedprice * (1 - l_discount)) as revenue,
  o_orderdate,
  o_shippriority
from
  orders,
  lineitem,
  customer
where
  c_mktsegment = 'BUILDING'
  and c_custkey = o_custkey
  and l_orderkey = o_orderkey
  and o_orderdate < '1995-03-22'
  and l_shipdate > '1995-03-22'
limit 10;
```

## Precautions

### Join Data Skew Problem

Data skew refers to the symptom that the task progress is 99% for a long time.

Data skew often exists because the data volume of a few Reduce tasks is much larger than that of others. Most Reduce tasks are complete while a few Reduce tasks are not complete.

To resolve the data skew problem, set **hive.optimize.skewjoin=true** and adjust the value of **hive.skewjoin.key**. **hive.skewjoin.key** specifies the maximum number of keys received by a Reduce task. If the number reaches the maximum, the keys are atomically distributed to other Reduce tasks.

### 9.36.3 Optimizing Group By

#### Scenario

Optimize the Group by statement to accelerate the command execution and query speed.

During the Group by operation, Map performs grouping and distributes the groups to Reduce; Reduce then performs grouping again. Group by optimization can be performed by enabling Map aggregation to reduce Map output data volume.

#### Procedure

On a Hive client, set the following parameter:

```
set hive.map.aggr=true
```

#### Precautions

##### Group By Data Skew

Group by have data skew problems. When **hive.groupby.skewindata** is set to true, the created query plan has two MapReduce jobs. The Map output result of the first job is randomly distributed to Reduce tasks, and each Reduce task performs aggregation operations and generates output result. Such processing may distribute the same Group By Key to different Reduce tasks for load balancing purpose. According to the preprocessing result, the second Job distributes Group By Key to Reduce to complete the final aggregation operation.

##### Count Distinct Aggregation Problem

When the aggregation function count distinct is used in deduplication counting, serious Reduce data skew occurs if the processed value is empty. The empty value can be processed independently. If count distinct is used, exclude the empty value using the where statement and increase the last count distinct result by 1. If there are other computing operations, process the empty value independently and then combine the value with other computing results.

### 9.36.4 Optimizing Data Storage

#### Scenario

**ORC** is an efficient column storage format and has higher compression ratio and reading efficiency than other file formats.

You are advised to use **ORC** as the default Hive table storage format.

## Prerequisites

You have logged in to the Hive client. For details, see [Using a Hive Client](#).

## Procedure

- Recommended: **SNAPPY** compression, which applies to scenarios with even compression ratio and reading efficiency requirements.  
**Create table *xx* (*col\_name data\_type*) stored as orc tblproperties ("orc.compress"="SNAPPY");**
- Available: **ZLIB** compression, which applies to scenarios with high compression ratio requirements.  
**Create table *xx* (*col\_name data\_type*) stored as orc tblproperties ("orc.compress"="ZLIB");**

### NOTE

*xx* indicates the specific Hive table name.

## 9.36.5 Optimizing SQL Statements

### Scenario

When SQL statements are executed on Hive, if the **(a&b) or (a&c)** logic exists in the statements, you are advised to change the logic to **a & (b or c)**.

### Example

If condition a is **p\_partkey = l\_partkey**, the statements before optimization are as follows:

```
select
  sum(l_extendedprice* (1 - l_discount)) as revenue
from
  lineitem,
  part
where
  (
    p_partkey = l_partkey
    and p_brand = 'Brand#32'
    and p_container in ('SM CASE', 'SM BOX', 'SM PACK', 'SM PKG')
    and l_quantity >= 7 and l_quantity <= 7 + 10
    and p_size between 1 and 5
    and l_shipmode in ('AIR', 'AIR REG')
    and l_shipinstruct = 'DELIVER IN PERSON'
  )
  or
  (
    p_partkey = l_partkey
    and p_brand = 'Brand#35'
    and p_container in ('MED BAG', 'MED BOX', 'MED PKG', 'MED PACK')
    and l_quantity >= 15 and l_quantity <= 15 + 10
    and p_size between 1 and 10
    and l_shipmode in ('AIR', 'AIR REG')
    and l_shipinstruct = 'DELIVER IN PERSON'
  )
  or
  (
    p_partkey = l_partkey
    and p_brand = 'Brand#24'
```

```

and p_container in ('LG CASE', 'LG BOX', 'LG PACK', 'LG PKG')
and l_quantity >= 26 and l_quantity <= 26 + 10
and p_size between 1 and 15
and l_shipmode in ('AIR', 'AIR REG')
and l_shipinstruct = 'DELIVER IN PERSON'
)

```

The statements after optimization are as follows:

```

select
  sum(l_extendedprice* (1 - l_discount)) as revenue
from
  lineitem,
  part
where p_partkey = l_partkey and
  ((
    p_brand = 'Brand#32'
    and p_container in ('SM CASE', 'SM BOX', 'SM PACK', 'SM PKG')
    and l_quantity >= 7 and l_quantity <= 7 + 10
    and p_size between 1 and 5
    and l_shipmode in ('AIR', 'AIR REG')
    and l_shipinstruct = 'DELIVER IN PERSON'
  )
  or
  (
    p_brand = 'Brand#35'
    and p_container in ('MED BAG', 'MED BOX', 'MED PKG', 'MED PACK')
    and l_quantity >= 15 and l_quantity <= 15 + 10
    and p_size between 1 and 10
    and l_shipmode in ('AIR', 'AIR REG')
    and l_shipinstruct = 'DELIVER IN PERSON'
  )
  or
  (
    p_brand = 'Brand#24'
    and p_container in ('LG CASE', 'LG BOX', 'LG PACK', 'LG PKG')
    and l_quantity >= 26 and l_quantity <= 26 + 10
    and p_size between 1 and 15
    and l_shipmode in ('AIR', 'AIR REG')
    and l_shipinstruct = 'DELIVER IN PERSON'
  ))

```

## 9.36.6 Optimizing the Query Function Using Hive CBO

### Scenario

When joining multiple tables in Hive, Hive supports Cost-Based Optimization (CBO). The system automatically selects the optimal plan based on the table statistics, such as the data volume and number of files, to improve the efficiency of joining multiple tables. Hive needs to collect table statistics before CBO optimization.

#### NOTE

- The CBO optimizes the joining sequence based on statistics and search criteria. However, the joining sequence may fail to be optimized in some special scenarios, such as data skew occurs and query condition values are not in the table.
- When column statistics collection is enabled, Reduce operations must be performed for aggregation. For insert tasks without the Reduce phase, Reduce operations will be performed to collect statistics.

### Prerequisites

You have logged in to the Hive client. For details, see [Using a Hive Client](#).

## Procedure

**Step 1** On the Manager UI, search for the **hive.cbo.enable** parameter in the service configuration of the Hive component, and select **true** to enable the function permanently.

**Step 2** Collect statistics about the existing data in Hive tables manually.

Run the following command to manually collect statistics: Statistics about only one table can be collected. If statistics about multiple tables need to be collected, the command needs to be executed repeatedly.

```
ANALYZE TABLE [db_name.]tablename [PARTITION(partcol1[=val1],  
partcol2[=val2], ...)]
```

```
COMPUTE STATISTICS
```

```
[FOR COLUMNS]
```

```
[NOSCAN];
```

 **NOTE**

- When **FOR COLUMNS** is specified, column-level statistics are collected.
- When **NOSCAN** is specified, statistics about the file size and number of files will be collected, but specific files will not be scanned.

For example:

```
analyze table table_name compute statistics;
```

```
analyze table table_name compute statistics for columns;
```

**Step 3** Configure the automatic statistics collection function of Hive. After the function is enabled, new statistics will be collected only when you insert data by running the **insert overwrite/into** command.

- Run the following commands on the Hive client to enable the statistics collection function temporarily:

```
set hive.stats.autogather = true; enables the automatic collection of table/  
partition-level statistics.
```

```
set hive.stats.column.autogather = true; enables the automatic collection of  
column-level statistics.
```

 **NOTE**

- The column-level statistics collection does not support complex data types, such as Map and Struct.
- The automatic table-level statistics collection does not support Hive on HBase tables.
- On the Manager UI, search for the **hive.stats.autogather** and **hive.stats.column.autogather** parameters in the service configuration of Hive, and select **true** to enable the collection function permanently.

**Step 4** Run the following command to view statistics:

```
DESCRIBE FORMATTED table_name[.column_name] PARTITION  
partition_spec;
```

For example:

```
desc formatted table_name;
```

```
desc formatted table_name.id;
```

```
desc formatted table_name.id partition(time='2016-05-27');
```

 NOTE

Partition tables only support partition-level statistics collection, so you must specify partitions to query statistics for partition tables.

----End

## 9.37 Common Issues About Hive

### 9.37.1 How Do I Delete UDFs on Multiple HiveServers at the Same Time?

#### Question

How can I delete permanent user-defined functions (UDFs) on multiple HiveServers at the same time?

#### Answer

Multiple HiveServers share one MetaStore database. Therefore, there is a delay in the data synchronization between the MetaStore database and the HiveServer memory. If a permanent UDF is deleted from one HiveServer, the operation result cannot be synchronized to the other HiveServers promptly.

In this case, you need to log in to the Hive client to connect to each HiveServer and delete permanent UDFs on the HiveServers one by one. The operations are as follows:

**Step 1** Log in to the node where the Hive client is installed as the Hive client installation user.

**Step 2** Run the following command to go to the client installation directory:

```
cd Client installation directory
```

For example, if the client installation directory is **/opt/client**, run the following command:

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** Run the following command to authenticate the user:

```
kinit Hive service user
```

 NOTE

The login user must have the Hive admin rights.

**Step 5** Run the following command to connect to the specified HiveServer:

```
beeline -u "jdbc:hive2://10.39.151.74:21066/default;sasl.qop=auth-  
conf;auth=KERBEROS;principal=hive/hadoop.<system domain name>@<system  
domain name>"
```

 NOTE

- *10.39.151.74* is the IP address of the node where the HiveServer is located.
- *21066* is the port number of the HiveServer. The HiveServer port number ranges from 21066 to 21070 by default. Use the actual port number.
- *hive* is the username. For example, if the Hive1 instance is used, the username is **hive1**.
- You can log in to FusionInsight Manager, choose **System > Permission > Domain and Mutual Trust**, and view the value of **Local Domain**, which is the current system domain name.
- **hive/hadoop.<system domain name>** is the username. All letters in the system domain name contained in the username are lowercase letters.

**Step 6** Run the following command to enable the Hive admin rights:

```
set role admin;
```

**Step 7** Run the following command to delete the permanent UDF:

```
drop function function_name;
```

 NOTE

- *function\_name* indicates the name of the permanent function.
- If the permanent UDF is created in Spark, the permanent UDF needs to be deleted from Spark and then from HiveServer by running the preceding command.

**Step 8** Check whether the permanent UDFs are deleted from all HiveServers.

- If yes, no further action is required.
- If no, go to [Step 5](#).

----End

## 9.37.2 Why Cannot the DROP operation Be Performed on a Backed-up Hive Table?

### Question

Why cannot the **DROP** operation be performed for a backed up Hive table?

### Answer

Snapshots have been created for an HDFS directory mapping to the backed up Hive table, so the HDFS directory cannot be deleted. As a result, the Hive table cannot be deleted.

When a Hive table is being backed up, snapshots are created for the HDFS directory mapping to the table. The snapshot mechanism of HDFS has the

following limitation: If snapshots have been created for an HDFS directory, the directory cannot be deleted or renamed unless the snapshots are deleted. When the **DROP** operation is performed for a Hive table (except the EXTERNAL table), the system attempts to delete the HDFS directory mapping to the table. If the directory fails to be deleted, the system displays a message indicating that the table fails to be deleted.

If you need to delete this table, manually delete all backup tasks related to this table.

### 9.37.3 How to Perform Operations on Local Files with Hive User-Defined Functions

#### Question

How to perform operations on local files (such as reading the content of a file) with Hive user-defined functions?

#### Answer

By default, you can perform operations on local files with their relative paths in UDF. The following are sample codes:

```
public String evaluate(String text) {  
    // some logic  
    File file = new File("foo.txt");  
    // some logic  
    // do return here  
}
```

In Hive, upload the file **foo.txt** used in UDF to HDFS, such as **hdfs://hacluster/tmp/foo.txt**. You can perform operations on the **foo.txt** file by creating UDF with the following sentences:

```
create function testFunc as 'some.class' using jar 'hdfs://hacluster/  
somejar.jar', file 'hdfs://hacluster/tmp/foo.txt';
```

In abnormal cases, if the value of **hive.fetch.task.conversion** is **more**, you can perform operations on local files in UDF by using absolute path instead of relative path. In addition, you must ensure that the file exists on all HiveServer nodes and NodeManager nodes and **omm** user have corresponding operation rights.

### 9.37.4 How Do I Forcibly Stop MapReduce Jobs Executed by Hive?

#### Question

How do I stop a MapReduce task manually if the task is suspended for a long time?

#### Answer

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Yarn**.

**Step 3** On the left pane, click **ResourceManager(Host name, Active)**, and log in to Yarn.

**Step 4** Click the button corresponding to the task ID. On the task page that is displayed, click **Kill Application** in the upper left corner and click **OK** in the displayed dialog box to stop the task.

----End

## 9.37.5 How Do I Monitor the Hive Table Size?

### Question

How do I monitor the Hive table size?

### Answer

The HDFS refined monitoring function allows you to monitor the size of a specified table directory.

### Prerequisites

- The Hive and HDFS components are running properly.
- The HDFS refined monitoring function is normal.

### Procedure

**Step 1** Log in to FusionInsight Manager.

**Step 2** Choose **Cluster** > *Name of the desired cluster* > **Services** > **HDFS** > **Resource**.

**Step 3** Click the first icon in the upper left corner of **Resource Usage (by Directory)**, as shown in the following figure.

Resource Usage (by Directory) 

**Step 4** In the displayed sub page for configuring space monitoring, click **Add**.

**Step 5** In the displayed **Add a Monitoring Directory** dialog box, set **Name** to the name or the user-defined alias of the table to be monitored and **Path** to the path of the monitored table. Click **OK**. In the monitoring result, the horizontal coordinate indicates the time, and the vertical coordinate indicates the size of the monitored directory.

----End

## 9.37.6 How Do I Prevent Key Directories from Data Loss Caused by Misoperations of the insert overwrite Statement?

### Question

How do I prevent key directories from data loss caused by misoperations of the **insert overwrite** statement?

### Answer

During monitoring of key Hive databases, tables, or directories, to prevent data loss caused by misoperations of the **insert overwrite** statement, configure **hive.local.dir.confblacklist** in Hive to protect directories.

This configuration item has been configured for directories such as **/opt/** and **/user/hive/warehouse** by default.

### Prerequisites

The Hive and HDFS components are running properly.

### Procedure

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster > Name of the desired cluster > Services > Hive > Configurations > All Configurations**, and search for the **hive.local.dir.confblacklist** configuration item.
- Step 3** Add paths of databases, tables, or directories to be protected in the parameter value.
- Step 4** Click **Save** to save the settings.

----End

## 9.37.7 Why Is Hive on Spark Task Freezing When HBase Is Not Installed?

### Scenario

This function applies to Hive.

Perform the following operations to configure parameters. When Hive on Spark tasks are executed in the environment where the HBase is not installed, freezing of tasks can be prevented.

 NOTE

The Spark kernel version of Hive on Spark tasks has been upgraded to Spark2x. Hive on Spark tasks can be executed if Spark2x is not installed. If HBase is not installed, when Spark tasks are executed, the system attempts to connect to the ZooKeeper to access HBase until timeout occurs by default. As a result, task freezing occurs.

If HBase is not installed, perform the following operations to execute Hive on Spark tasks. If HBase is upgraded from an earlier version, you do not need to configure parameters after the upgrade.

## Procedure

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Hive** > **Configurations** > **All Configurations**.
- Step 3** Choose **HiveServer(Role)** > **Customization**. Add a customized parameter to the **spark-defaults.conf** parameter file. Set **Name** to **spark.security.credentials.hbase.enabled**, and set **Value** to **false**.
- Step 4** Click **Save**. In the dialog box that is displayed, click **OK**.
- Step 5** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Hive** > **Instance**, select all Hive instances, choose **More** > **Restart Instance**, enter the password, and click **OK**.

----End

## 9.37.8 Error Reported When the WHERE Condition Is Used to Query Tables with Excessive Partitions in FusionInsight Hive

### Question

When a table with more than 32,000 partitions is created in Hive, an exception occurs during the query with the WHERE partition. In addition, the exception information printed in **metastore.log** contains the following information:

```
Caused by: java.io.IOException: Tried to send an out-of-range integer as a 2-byte value: 32970
    at org.postgresql.core.PGStream.SendInteger2(PGStream.java:199)
    at org.postgresql.core.v3.QueryExecutorImpl.sendParse(QueryExecutorImpl.java:1330)
    at org.postgresql.core.v3.QueryExecutorImpl.sendOneQuery(QueryExecutorImpl.java:1601)
    at org.postgresql.core.v3.QueryExecutorImpl.sendParse(QueryExecutorImpl.java:1191)
    at org.postgresql.core.v3.QueryExecutorImpl.execute(QueryExecutorImpl.java:346)
```

### Answer

During a query with partition conditions, HiveServer optimizes the partitions to avoid full table scanning. All partitions whose metadata meets the conditions need to be queried. However, the **sendOneQuery** interface provided by GaussDB limits the parameter value to **32767** in the **sendParse** method. If the number of partition conditions exceeds **32767**, an exception occurs.

## 9.37.9 Why Cannot I Connect to HiveServer When I Use IBM JDK to Access the Beeline Client?

### Scenario

When users check the JDK version used by the client, if the JDK version is IBM JDK, the Beeline client needs to be reconstructed. Otherwise, the client will fail to connect to HiveServer.

### Procedure

- Step 1** Log in to FusionInsight Manager and choose **System > Permission > User**. In the **Operation** column of the target user, choose **More > Download Authentication Credential**, select the cluster information, and click **OK** to download the keytab file.
- Step 2** Decompress the keytab file and use WinSCP to upload the decompressed **user.keytab** file to the Hive client installation directory on the node to be operated, for example, **/opt/client**.
- Step 3** Run the following command to open the **Hive/component\_env** configuration file in the Hive client directory:

```
vi Hive client installation directory/Hive/component_env
```

Add the following content to the end of the line where **export CLIENT\_HIVE\_URI** is located:

```
\; user.principal=Username@HADOOP.COM\;user.keytab=user.keytab file path/user.keytab
```

----End

## 9.37.10 Description of Hive Table Location (Either Be an OBS or HDFS Path)

### Question

Does a Hive Table Can Be Stored Either in OBS or HDFS?

### Answer

- The location of a common Hive table stored on OBS can be set to an HDFS path.
- In the same Hive service, you can create tables stored in OBS and HDFS, respectively.
- For a Hive partitioned table stored on OBS, the location of the partition cannot be set to an HDFS path. (For a partitioned table stored on HDFS, the location of the partition cannot be changed to OBS.)

### 9.37.11 Why Cannot Data Be Queried After the MapReduce Engine Is Switched After the Tez Engine Is Used to Execute Union-related Statements?

#### Question

Hive uses the Tez engine to execute union-related statements to write data. After Hive is switched to the MapReduce engine for query, no data is found.

#### Answer

When Hive uses the Tez engine to execute the union-related statement, the generated output file is stored in the **HIVE\_UNION\_SUBDIR** directory. After Hive is switched back to the MapReduce engine, files in the directory are not read by default. Therefore, data in the **HIVE\_UNION\_SUBDIR** directory is not read.

In this case, you can set **mapreduce.input.fileinputformat.input.dir.recursive** to **true** to enable union optimization and determine whether to read data in the directory.

### 9.37.12 Why Does Hive Not Support Concurrent Data Writing to the Same Table or Partition?

#### Question

Why Does Data Inconsistency Occur When Data Is Concurrently Written to a Hive Table Through an API?

#### Answer

Hive does not support concurrent data insertion for the same table or partition. As a result, multiple tasks perform operations on the same temporary data directory, and one task moves the data of another task, causing task data exception. The service logic is modified so that data is inserted to the same table or partition in single thread mode.

### 9.37.13 Why Does Hive Not Support Vectorized Query?

#### Question

When the vectorized parameter **hive.vectorized.execution.enabled** is set to **true**, why do some null pointers or type conversion exceptions occur occasionally when Hive on Tez/MapReduce/Spark is executed?

#### Answer

Currently, Hive does not support vectorized execution. Many community issues are introduced during vectorized execution and are not resolved stably. The default value of **hive.vectorized.execution.enabled** is **false**. You are advised not to set this parameter to **true**.

## 9.37.14 Hive Configuration Problems

- The error message "java.lang.OutOfMemoryError: Java heap space." is displayed during Hive SQL execution.  
Solution:
  - For MapReduce tasks, increase the values of the following parameters:  
**set mapreduce.map.memory.mb=8192;**  
**set mapreduce.map.java.opts=-Xmx6554M;**  
**set mapreduce.reduce.memory.mb=8192;**  
**set mapreduce.reduce.java.opts=-Xmx6554M;**
  - For Tez tasks, increase the value of the following parameter:  
**set hive.tez.container.size=8192;**
- After a column name is changed to a new one using the Hive SQL **as** statement, the error message "Invalid table alias or column reference 'xxx'." is displayed when the original column name is used for compilation.  
Solution: Run the **set hive.cbo.enable=true;** statement.
- The error message "Unsupported SubQuery Expression 'xxx': Only SubQuery expressions that are top level conjuncts are allowed." is displayed during Hive SQL subquery compilation.  
Solution: Run the **set hive.cbo.enable=true;** statement.
- The error message "CalciteSubquerySemanticException [Error 10249]: Unsupported SubQuery Expression Currently SubQuery expressions are only allowed as Where and Having Clause predicates." is displayed during Hive SQL subquery compilation.  
Solution: Run the **set hive.cbo.enable=true;** statement.
- The error message "Error running query: java.lang.AssertionError: Cannot add expression of different type to set." is displayed during Hive SQL compilation.  
Solution: Run the **set hive.cbo.enable=false;** statement.
- The error message "java.lang.NullPointerException at org.apache.hadoop.hive.ql.udf.generic.GenericUDAFComputeStats \$GenericUDAFNumericStatsEvaluator.init." is displayed during Hive SQL execution.  
Solution: Run the **set hive.map.aggr=false;** statement.
- When **hive.auto.convert.join** is set to **true** (enabled by default) and **hive.optimize.skewjoin** is set to **true**, the error message "ClassCastException org.apache.hadoop.hive.ql.plan.ConditionalWork cannot be cast to org.apache.hadoop.hive.ql.plan.MapredWork" is displayed.  
Solution: Run the **set hive.optimize.skewjoin=false;** statement.
- When **hive.auto.convert.join** is set to **true** (enabled by default), **hive.optimize.skewjoin** is set to **true**, and **hive.exec.parallel** is set to **true**, the error message "java.io.FileNotFoundException: File does not exist:xxx/reduce.xml" is displayed.  
Solution:
  - Method 1: Switch the execution engine to Tez. For details, see [Switching the Hive Execution Engine to Tez](#).

- Method 2: Run the **set hive.exec.parallel=false;** statement.
- Method 3: Run the **set hive.auto.convert.join=false;** statement.

# 10 Using Hudi

---

## 10.1 Quick Start

### Scenario

This section describes capabilities of Hudi using spark-shell. Using the Spark data source, this section describes how to insert and update a Hudi dataset of the default storage mode Copy-on Write (COW) tables based on code snippets. After each write operation, you will be introduced how to read snapshot and incremental data.

### Prerequisites

- You have downloaded and installed the Hudi client. Currently, Hudi is integrated in Spark2x. You only need to download the Spark2x client on Manager. For example, the client installation directory is **/opt/client**.
- You have created a user and added the user to user groups **hadoop** and **hive** on Manager.

### Procedure

**Step 1** Download and install the Hudi client. For details, see [Using an MRS Client](#).

 **NOTE**

Currently, Hudi is integrated in Spark2x. You only need to download the Spark2x client on Manager. For example, the client installation directory is **/opt/client**.

**Step 2** Log in to the node where the client is installed as user **root** and run the following command:

```
cd /opt/client
```

**Step 3** Run the following commands to load environment variables:

```
source bigdata_env
```

```
source Hudi/component_env
```

**kinit** *Created user*

 **NOTE**

- You need to change the password of the created user, and then run the **kinit** command to log in to the system again.
- In normal mode, you do not need to run the **kinit** command.

**Step 4** Use **spark-shell --master yarn-client** to import Hudi packages to generate test data:

```
// Import required packages.
import org.apache.hudi.QuickstartUtils._
import scala.collection.JavaConversions._
import org.apache.spark.sql.SaveMode._
import org.apache.hudi.DataSourceReadOptions._
import org.apache.hudi.DataSourceWriteOptions._
import org.apache.hudi.config.HoodieWriteConfig._
// Define the storage path and generate the test data.
val tableName = "hudi_cow_table"
val basePath = "hdfs://hacluster/tmp/hudi_cow_table"
val dataGen = new DataGenerator
val inserts = convertToStringList(dataGen.generateInserts(10))
val df = spark.read.json(spark.sparkContext.parallelize(inserts, 2))
```

**Step 5** Write data to the Hudi table in overwrite mode.

```
df.write.format("org.apache.hudi").
options(getQuickstartWriteConfigs).
option(PRECOMBINE_FIELD_OPT_KEY, "ts").
option(RECORDKEY_FIELD_OPT_KEY, "uuid").
option(PARTITIONPATH_FIELD_OPT_KEY, "partitionpath").
option(TABLE_NAME, tableName).
mode(Overwrite).
save(basePath)
```

**Step 6** Query the Hudi table.

Register a temporary table and query the table.

```
val roViewDF = spark.
read.
format("org.apache.hudi").
load(basePath + "/*/*/*/*")
roViewDF.createOrReplaceTempView("hudi_ro_table")
spark.sql("select fare, begin_lon, begin_lat, ts from hudi_ro_table where fare > 20.0").show()
```

**Step 7** Generate new data and update the Hudi table in append mode.

```
val updates = convertToStringList(dataGen.generateUpdates(10))
val df = spark.read.json(spark.sparkContext.parallelize(updates, 1))
```

```
df.write.format("org.apache.hudi").  
options(getQuickstartWriteConfigs).  
option(PRECOMBINE_FIELD_OPT_KEY, "ts").  
option(RECORDKEY_FIELD_OPT_KEY, "uuid").  
option(PARTITIONPATH_FIELD_OPT_KEY, "partitionpath").  
option(TABLE_NAME, tableName).  
mode(Append).  
save(basePath)
```

**Step 8** Query incremental data in the Hudi table.

- Reload data.  
spark.  
read.  
format("org.apache.hudi").  
load(basePath + "/\*/\*/\*/\*").  
createOrReplaceTempView("hudi\_ro\_table")
- Perform the incremental query.  
val commits = spark.sql("select distinct( \_hoodie\_commit\_time) as  
commitTime from hudi\_ro\_table order by commitTime").map(k =>  
k.getString(0)).take(50)  
val beginTime = commits(commits.length - 2)  
val incViewDF = spark.  
read.  
format("org.apache.hudi").  
option(VIEW\_TYPE\_OPT\_KEY, VIEW\_TYPE\_INCREMENTAL\_OPT\_VAL).  
option(BEGIN\_INSTANTTIME\_OPT\_KEY, beginTime).  
load(basePath);  
incViewDF.registerTempTable("hudi\_incr\_table")  
spark.sql("select ` \_hoodie\_commit\_time`, fare, begin\_lon, begin\_lat, ts  
from hudi\_incr\_table where fare > 20.0").show()

**Step 9** Perform the point-in-time query.

```
val beginTime = "000"  
val endTime = commits(commits.length - 2)  
val incViewDF = spark.read.format("org.apache.hudi").  
option(VIEW_TYPE_OPT_KEY, VIEW_TYPE_INCREMENTAL_OPT_VAL).  
option(BEGIN_INSTANTTIME_OPT_KEY, beginTime).  
option(END_INSTANTTIME_OPT_KEY, endTime).  
load(basePath);
```

```
incViewDF.registerTempTable("hudi_incr_table")

spark.sql("select ` _hoodie_commit_time`, fare, begin_lon, begin_lat, ts from
hudi_incr_table where fare > 20.0").show()
```

**Step 10** Delete data.

- Prepare the data to be deleted.
 

```
val df = spark.sql("select uuid, partitionpath from hudi_ro_table limit 2")
val deletes = dataGen.generateDeletes(df.collectAsList())
```
- Execute the deletion.
 

```
val df = spark.read.json(spark.sparkContext.parallelize(deletes, 2));
df.write.format("org.apache.hudi").
options(getQuickstartWriteConfigs).
option(OPERATION_OPT_KEY,"delete").
option(PRECOMBINE_FIELD_OPT_KEY, "ts").
option(RECORDKEY_FIELD_OPT_KEY, "uuid").
option(PARTITIONPATH_FIELD_OPT_KEY, "partitionpath").
option(TABLE_NAME, tableName).
mode(Append).
save(basePath);
```
- Query data again.
 

```
val roViewDFAfterDelete = spark.
read.
format("org.apache.hudi").
load(basePath + "/*/*/*/*")
roViewDFAfterDelete.createOrReplaceTempView("hudi_ro_table")
spark.sql("select uuid, partitionPath from hudi_ro_table").show()
```

----End

## 10.2 Basic Operations

### 10.2.1 Hudi Table Schema

When writing data, Hudi generates a Hudi table based on attributes such as the storage path, table name, and partition structure.

Hudi table data files can be stored in the OS file system or distributed file system such as HDFS. To ensure analysis performance and data reliability, HDFS is generally used for storage. Using HDFS as an example, Hudi table storage files are classified into two types.

<input type="checkbox"/>	 Permission	 Owner	 Group	 Size	 Last Modified	 Replication	 Block Size	 Name
<input type="checkbox"/>	<a href="#">drwxr-xr-x</a>	<a href="#">testcz</a>	<a href="#">hadoop</a>	0 B	Apr 25 15:32	<a href="#">0</a>	0 B	<a href="#">.hoodie</a>
<input type="checkbox"/>	<a href="#">drwxr-xr-x</a>	<a href="#">testcz</a>	<a href="#">hadoop</a>	0 B	Apr 25 15:30	<a href="#">0</a>	0 B	<a href="#">americas</a>
<input type="checkbox"/>	<a href="#">drwxr-xr-x</a>	<a href="#">testcz</a>	<a href="#">hadoop</a>	0 B	Apr 25 15:30	<a href="#">0</a>	0 B	<a href="#">asia</a>

- The **.hoodie** folder stores the log files related to file merging.

<a href="#">drwxr-xr-x</a>	<a href="#">admintest</a>	<a href="#">hadoop</a>	0 B	Mar 30 09:44	0	0 B	<a href="#">.aux</a>
<a href="#">drwxr-xr-x</a>	<a href="#">admintest</a>	<a href="#">hadoop</a>	0 B	Mar 30 11:45	0	0 B	<a href="#">.temp</a>
<a href="#">-rw-r--r--</a>	<a href="#">admintest</a>	<a href="#">hadoop</a>	4.58 KB	Mar 30 09:44	3	128 MB	<a href="#">20210330094435.deltacommith</a>
<a href="#">-rw-r--r--</a>	<a href="#">admintest</a>	<a href="#">hadoop</a>	0 B	Mar 30 09:44	3	128 MB	<a href="#">20210330094435.deltacommith.inflight</a>
<a href="#">-rw-r--r--</a>	<a href="#">admintest</a>	<a href="#">hadoop</a>	0 B	Mar 30 09:44	3	128 MB	<a href="#">20210330094435.deltacommith.requested</a>

- The path containing **\_partition\_key** stores actual data files and metadata by partition.

Hudi data files of are stored in Parquet base files and Avro log files.

<a href="#">-rw-r--r--</a>	<a href="#">admintest</a>	<a href="#">hadoop</a>	93 B	Mar 30 09:44	3	128 MB	<a href="#">.hoodie_partition_metadata</a>
<a href="#">-rw-r--r--</a>	<a href="#">admintest</a>	<a href="#">hadoop</a>	441.77 KB	Mar 30 09:46	3	128 MB	<a href="#">2b4d098e-4dc8-4633-a22a-dc22f87c57d9-1_0-13-22_20210330094613.parquet</a>
<a href="#">-rw-r--r--</a>	<a href="#">admintest</a>	<a href="#">hadoop</a>	445.28 KB	Mar 30 09:44	3	128 MB	<a href="#">4010e8a8-1b20-4be7-8442-4e30af401e84-0_1-4-8_20210330094435.parquet</a>

## 10.2.2 Write

Currently, Spark and Flink can be used as write engines for Hudi. The capability of Flink of the current version is weak and not recommended. It will be enhanced in later versions.

### 10.2.2.1 Batch Write

Hudi provides multiple write modes. For details, see the configuration item **hoodie.datasource.write.operation**. This section describes **upsert**, **insert**, and **bulk\_insert**.

- **insert**: The operation process is similar to **upsert**. The query on updated file partitions is not based on indexes. Therefore, **insert** is faster than **upsert**. This operation is recommended for data sources that do not contain updated data. If the data source contains updated data, duplicate data will exist in the data lake.
- **bulk\_insert** (insert in batches): It is used for initial dataset loading. This operation sorts primary keys and then inserts data into a Hudi table by writing data to a common Parquet table. It has the best performance but cannot control small files. The **upsert** and **insert** operations can control small files by using heuristics.
- **upsert** (insert and update): It is the default operation type. Hudi determines whether historical data exists based on the primary key. Historical data is updated, and other data is inserted. This operation is recommended for data sources, such as change data capture (CDC), that include updated data.

#### NOTE

- Primary keys are not sorted during **insert**. Therefore, you are not advised to use **insert** during dataset initialization.
- You are advised to use **insert** if data is new, use **upsert** if data needs to be updated, and use **bulk\_insert** if datasets need to be initialized.

Example:

```
df.write.format("hudi").
  option(PRECOMBINE_FIELD_OPT_KEY, "col4").// Specify the pre-combined field, which must be
  sortable.
```

```

option(RECORDKEY_FIELD_OPT_KEY, "primary_key"). // Specify the primary key of the Hudi table. The
primary key must be unique.
option(PARTITIONPATH_FIELD_OPT_KEY, "col0").// Specify a partition.
option(OPERATION_OPT_KEY, "bulk_insert").// Specify that the operation is bulk_insert.
option("hoodie.bulkinsert.shuffle.parallelism", par.toString).// Specify the concurrency of the
bulk_insert operation.
option(HIVE_SYNC_ENABLED_OPT_KEY, "true").// Specify the synchronization of the Hudi table to
Hive.
option(HIVE_PARTITION_FIELDS_OPT_KEY, "col0").// Specify the Hive partition column name.
option(HIVE_PARTITION_EXTRACTOR_CLASS_OPT_KEY,
"org.apache.hudi.hive.MultiPartKeyValueExtractor").
option(HIVE_DATABASE_OPT_KEY, db).
option(HIVE_TABLE_OPT_KEY, tableName).
option(HIVE_USE_JDBC_OPT_KEY, "false").// Specify whether to use JDBC for Hive synchronization.
The default value is true.
option(TABLE_NAME, tableName). // Specify the table name.
mode(Overwrite). // Specify the write mode.
save(s"/tmp/${db}/${tableName}")// Specify the storage path of the Hudi table.

```

**NOTE**

- If the Spark DataSource API is used to update the MOR table, small files of the updated data may be merged when a small volume of data is upserted. As a result, some updated data can be found in the read-optimized view of the MOR table.
- If the base file of the data to be updated is a small file, the data to be inserted and new data for update are merged with the base file to generate a new base file instead of being written to logs.

## Configuring Partitions

Hudi supports multiple partitioning modes, such as multi-level partitioning, non-partitioning, single-level partitioning, and partitioning by date. You can select a proper partitioning mode as required. The following describes how to configure different partitioning modes for Hudi.

- Multi-level partitioning

Multi-level partitioning indicates that multiple fields are specified as partition keys. Pay attention to the following configuration items:

Configuration Item	Description
hoodie.datasource.write.partitionpath.field	Configure multiple partition fields, for example, <b>p1</b> , <b>p2</b> , and <b>p3</b> .
hoodie.datasource.hive_sync.partition_fields	Set this parameter to <b>p1</b> , <b>p2</b> , and <b>p3</b> . The values must be the same as the partition fields of <b>hoodie.datasource.write.partitionpath.field</b> .
hoodie.datasource.write.keygenerator.class	Set this parameter to <b>org.apache.hudi.keygen.ComplexKeyGenerator</b> .
hoodie.datasource.hive_sync.partition_extractor_class	Set this parameter to <b>org.apache.hudi.hive.MultiPartKeyValueExtractor</b> .

- Non-partitioning

Hudi supports non-partitioned tables. Pay attention to the following configuration items:

Configuration Item	Description
hoodie.datasource.write.partitionpath.field	Leave this parameter blank.
hoodie.datasource.hive_sync.partition_fields	Leave this parameter blank.
hoodie.datasource.write.keygenerator.class	Set this parameter to <b>org.apache.hudi.keygen.NonpartitionedKeyGenerator</b> .
hoodie.datasource.hive_sync.partition_extractor_class	Set this parameter to <b>org.apache.hudi.hive.NonPartitionedExtractor</b> .

- Single-level partitioning

It is similar to multi-level partitioning. Pay attention to the following configuration items:

Configuration Item	Description
hoodie.datasource.write.partitionpath.field	Set this parameter to one field, for example, <b>p</b> .
hoodie.datasource.hive_sync.partition_fields	Set this parameter to <b>p</b> . The value must be the same as the partition field of <b>hoodie.datasource.write.partitionpath.field</b>
hoodie.datasource.write.keygenerator.class	(Optional) The default value is <b>org.apache.hudi.keygen.SimpleKeyGenerator</b> .
hoodie.datasource.hive_sync.partition_extractor_class	Set this parameter to <b>org.apache.hudi.hive.MultiPartKeyValueExtractor</b> .

- Partitioning by date

The **date** field is specified as the partition field. Pay attention to the following configuration items:

Configuration Item	Description
hoodie.datasource.write.partitionpath.field	Set this parameter to the <b>date</b> field, for example, <b>operationTime</b> .

Configuration Item	Description
hoodie.datasource.hive_sync.partition_fields	Set this parameter to <b>operationTime</b> . The value must be the same as the preceding partition field.
hoodie.datasource.write.keygenerator.class	(Optional) The default value is <b>org.apache.hudi.keygen.SimpleKeyGenerator</b> .
hoodie.datasource.hive_sync.partition_extractor_class	Set this parameter to <b>org.apache.hudi.hive.SlashEncodedDayPartitionValueExtractor</b> .

 **NOTE**

Date format for **SlashEncodedDayPartitionValueExtractor** must be *yyyy/mm/dd*.

- Partition sorting

Configuration Item	Description
hoodie.bulkinsert.user.defined.partition_sorter.class	Specifies the partition sorting class. You can customize a sorting method. For details, see the sample code.

 **NOTE**

By default, **bulk\_insert** sorts data by character and applies only to primary keys of StringType.

### 10.2.2.2 Stream Write

The HoodieDeltaStreamer tool provided by Hudi supports stream write. You can also use SparkStreaming to write data in microbatch mode. HoodieDeltaStreamer provides the following functions:

- Supports multiple data sources, such as Kafka and DFS.
- Manages checkpoints, rollback, and recovery to ensure exactly-once semantics.
- Supports user-defined transformations.

Example:

Prepare the configuration file **kafka-source.properties**.

```
#Hudi configuration
hoodie.datasource.write.recordkey.field=id
hoodie.datasource.write.partitionpath.field=age
hoodie.upsert.shuffle.parallelism=100
#hive config
hoodie.datasource.hive_sync.table=hudimor_deltastreamer_partition
hoodie.datasource.hive_sync.partition_fields=age
```

```
hoodie.datasource.hive_sync.partition_extractor_class=org.apache.hudi.hive.MultiPartKeyValueExtractor
hoodie.datasource.hive_sync.use_jdbc=false
hoodie.datasource.hive_sync.support_timestamp=true
# Kafka Source topic
hoodie.deltastreamer.source.kafka.topic=hudimor_deltastreamer_partition
#checkpoint
hoodie.deltastreamer.checkpoint.provider.path=hdfs://hacluster/tmp/huditest/
hudimor_deltastreamer_partition
# Kafka props
# The kafka cluster we want to ingest from
bootstrap.servers= xx.xx.xx.xx:xx
auto.offset.reset=earliest
#auto.offset.reset=latest
group.id=hoodie-delta-streamer
offset.rang.limit=10000
```

Run the following commands to specify the HoodieDeltaStreamer execution parameters (for details about the parameter configuration, visit the official website <https://hudi.apache.org/>):

**spark-submit --master yarn**

**--jars /opt/hudi-java-examples-1.0.jar** // Specify the Hudi jars directory required for Spark running.

**--driver-memory 1g**

**--executor-memory 1g --executor-cores 1 --num-executors 2 --conf spark.kryoserializer.buffer.max=128m**

**--driver-class-path /opt/client/Hudi/hudi/conf:/opt/client/Hudi/hudi/lib/\*:/opt/client/Spark2x/spark/jars/\*:/opt/hudi-examples-0.6.1-SNAPSHOT.jar:/opt/hudi-examples-0.6.1-SNAPSHOT-tests.jar** // Specify the Hudi jars directory required by the Spark driver.

**--class org.apache.hudi.utilities.deltastreamer.HoodieDeltaStreamer spark-internal**

**--props file:///opt/kafka-source.properties** // Specify the configuration file. You need to set the configuration file path to the HDFS path when submitting tasks in yarn-cluster mode.

**--target-base-path /tmp/huditest/hudimor1\_deltastreamer\_partition** // Specify the path of the Hudi table.

**--table-type MERGE\_ON\_READ** // Specify the type of the Hudi table to be written.

**--target-table hudimor\_deltastreamer\_partition** // Specify the Hudi table name.

**--source-ordering-field name** // Specify the columns to be pre-combined in the Hudi table.

**--source-class org.apache.hudi.utilities.sources.JsonKafkaSource** // Set the consumed data source to **JsonKafkaSource**. Different source classes are specified based on different data sources.

**--schemaprovider-class**

**com.xxx.bigdata.hudi.examples.DataSchemaProviderExample** // Specify the schema required by the Hudi table.

**--transformer-class com.xxx.bigdata.hudi.examples.TransformerExample** // Specify how to process the data obtained from the data source. Set this parameter based on service requirements.

**--enable-hive-sync** // Enable Hive synchronization to synchronize the Hudi table to Hive.

**--continuous** // Set the stream processing mode to **continuous**.

### 10.2.2.3 Bootstrapping

The bootstrapping function provided by Hudi converts historical tables into Hudi tables without any change by generating Hoodie management files based on historical Parquet tables.

The following shows an example of converting a Hive table in the **hdfs://hacluster/user/hive/warehouse/pq1** directory on HDFS to a Hudi table and save it in the **hdfs://hacluster/tmp/hudi\_bootstrap\_test** directory.

#### NOTE

- Bootstrapping and write operations cannot be executed concurrently. Bootstrapping is used only to create new Hudi tables rather than to execute existing Hudi tables.
- Bootstrapping supports only the write operations on COW tables.

```
spark-shell

import collection.JavaConverters._
import org.apache.hadoop.fs.FileSystem
import org.apache.hudi.bootstrap.SparkParquetBootstrapDataProvider
import org.apache.hudi.client.bootstrap.selector.FullRecordBootstrapModeSelector
import org.apache.hudi.{DataSourceReadOptions, DataSourceWriteOptions, HoodieDataSourceHelpers}
import org.apache.hudi.common.fs.FSUtils
import org.apache.hudi.common.table.timeline.HoodieTimeline
import org.apache.hudi.config.{HoodieBootstrapConfig, HoodieCompactionConfig, HoodieWriteConfig}
import org.apache.hudi.keygen.SimpleKeyGenerator
import org.apache.spark.api.java.JavaSparkContext
import org.apache.spark.sql.functions.{col, lit}
import org.apache.spark.sql.{SaveMode, SparkSession}
import org.apache.hudi.QuickstartUtils._
import scala.collection.JavaConversions._
import org.apache.spark.sql.SaveMode._
import org.apache.hudi.DataSourceReadOptions._
import org.apache.hudi.DataSourceWriteOptions._
import org.apache.hudi.config.HoodieWriteConfig._
import java.time._
import java.util.Collections

val timestamp = Instant.now.toEpochMilli
val jsc = JavaSparkContext.fromSparkContext(spark.sparkContext)
val numRecords: Int = 100
val srcPath = "hdfs://hacluster/user/hive/warehouse/pq1"
val basePath = "hdfs://hacluster/tmp/hudi_bootstrap_test"

// Hudi configuration information
val commonOpts: Map[String, String] = Map(
  HoodieWriteConfig.INSERT_PARALLELISM -> "4",
  HoodieWriteConfig.UPSERT_PARALLELISM -> "4",
  HoodieWriteConfig.DELETE_PARALLELISM -> "4",
  HoodieWriteConfig.BULKINSERT_PARALLELISM -> "4",
  HoodieWriteConfig.FINALIZE_WRITE_PARALLELISM -> "4",
  HoodieBootstrapConfig.BOOTSTRAP_PARALLELISM -> "4",
  DataSourceWriteOptions.RECORDKEY_FIELD_OPT_KEY -> "col1",
  DataSourceWriteOptions.PARTITIONPATH_FIELD_OPT_KEY -> "partition",
  DataSourceWriteOptions.PRECOMBINE_FIELD_OPT_KEY -> "timestamp",
```

```
HoodieWriteConfig.TABLE_NAME -> "hoodie_test"
)
// Bootstrapping
val bootstrapDF = spark.emptyDataFrame
bootstrapDF.write
  format("hudi").
  options(commonOpts).
  option(DataSourceWriteOptions.OPERATION_OPT_KEY,
DataSourceWriteOptions.BOOTSTRAP_OPERATION_OPT_VAL).
  option(DataSourceWriteOptions.TABLE_TYPE_OPT_KEY,
DataSourceWriteOptions.COW_TABLE_TYPE_OPT_VAL).
  option(HoodieBootstrapConfig.BOOTSTRAP_BASE_PATH_PROP, srcPath).
  option(HoodieBootstrapConfig.BOOTSTRAP_KEYGEN_CLASS, classOf[SimpleKeyGenerator].getName).
  mode(SaveMode.Overwrite).
  save(basePath)

// Query data after bootstrapping.
var hoodieROViewDF1 = spark.read.format("hudi").load(basePath + "/*")
hoodieROViewDF1.show
```

### 10.2.2.4 Synchronizing Hudi Table Data to Hive

You can run `run_hive_sync_tool.sh` to synchronize data in the Hudi table to Hive.

For example, run the following command to synchronize the Hudi table in the `hdfs://hacluster/tmp/huditest/hudimor1_deltastreamer_partition` directory on HDFS to the Hive table `table hive_sync_test3` with `unite`, `country`, and `state` as partition keys:

```
run_hive_sync_tool.sh --partitioned-by unite,country,state --base-path hdfs://hacluster/tmp/huditest/
hudimor1_deltastreamer_partition --table hive_sync_test3 --partition-value-extractor
org.apache.hudi.hive.MultiPartKeyValueExtractor --support-timestamp
```

**Table 10-1** Parameter description

Command	Description	Mandatory or Not (Yes or No)	Default Value
<code>--database</code>	Specifies the Hive database name.	No	default
<code>--table</code>	Specifies the Hive table name.	Yes	-
<code>--base-file-format</code>	Specifies the file format ( <b>PARQUET</b> or <b>HFILE</b> ).	No	PARQUET
<code>--user</code>	Specifies the Hive username.	No	-
<code>--pass</code>	Specifies the Hive password.	No	-
<code>--jdbc-url</code>	Specifies the Hive JDBC connection URL.	No	-
<code>--base-path</code>	Specifies the storage path of the Hudi table to be synchronized.	Yes	-

Command	Description	Mandatory or Not (Yes or No)	Default Value
--partitioned-by	Specifies the partition key.	No	-
--partition-value-extractor	Specifies the partition class. PartitionValueExtractor needs to be implemented. The partition value can be extracted from the HDFS path.	No	SlashEncodedDayPartitionValueExtractor
--assume-date-partitioning	Creates partitions in yyyy/mm/dd format to support backward compatibility.	No	false
--use-pre-apache-input-format	Use InputFormat in the <b>com.uber.hoodie</b> package to replace the one in the <b>org.apache.hudi</b> package. Do not use this command except for migrating projects from <b>com.uber.hoodie</b> to <b>org.apache.hudi</b> .	No	false
--use-jdbc	Uses Hive JDBC connection.	No	true
--auto-create-database	Specifies whether to automatically create a Hive database.	No	true
--skip-ro-suffix	Specifies whether to skip the read-optimized view with the <b>_ro</b> suffix during registration.	No	false
--use-file-listing-from-metadata	Specifies whether to obtain the file list from the Hudi metadata.	No	false
--verify-metadata-file-listing	Specifies whether to verify the file list in the Hudi metadata based on the file system.	No	false
--help/-h	Specifies whether to display help information.	No	false

Command	Description	Mandatory or Not (Yes or No)	Default Value
--support-timestamp	Specifies whether to convert <b>TIMESTAMP_MICROS</b> of INT64 to Hive timestamp.	No	false
--decode-partition	Specifies whether to decode the partition value if the partition is encoded during the write process.	No	false
--batch-sync-num	Specifies the number of Hive partitions to be synchronized in each batch.	No	1000

 **NOTE**

During Hive synchronization, if the table does not exist, an external table is created and partitions are added. If the table exists, check whether table schemas are different. If they are different, replace the table. Check whether new partitions exist. If new partitions exist, partitions are added accordingly.

Therefore, there are the following restrictions when Hive synchronization is used:

- Fields can only be added to the schema and cannot be modified or deleted.
- Partition directories can only be added but cannot be deleted.
- **Overwrite** can only overwrite the Hudi table. The Hive table cannot be overwritten synchronously.
- Do not use the timestamp type as the partition column when synchronizing a Hudi table to Hive.
- When this script is used for synchronization, JDBC must be used for security purposes. That is, **--use-jdbc** must be set to **true**.

### 10.2.3 Read

The read operation of Hudi applies to three views of Hudi. You can select a proper view for query based on requirements.

Hudi supports multiple query engines, including Spark, Hive, and HetuEngine. For details, see [Table 10-2](#) and [Table 10-3](#).

**Table 10-2** COW tables

Query Engine	Real-time View/Read-optimized View	Incremental View
Hive	Y	Y
Spark (SparkSQL)	Y	Y

Query Engine	Real-time View/Read-optimized View	Incremental View
Spark (SparkDataSource API)	Y	Y
HetuEngine	Y	N

**Table 10-3** MOR tables

Query Engine	Real-time View	Incremental View	Read-optimized View
Hive	Y	Y	Y
Spark (SparkSQL)	Y	Y	Y
Spark (SparkDataSource API)	Y	Y	Y
HetuEngine	Y	N	Y

 **CAUTION**

- Currently, the partition deduction capability is not supported when Hudi uses the Spark DataSource API to read data. For example, when the DataSource API is used to query a bootstrap table, the partition field may not be displayed or may be displayed as null.
- For an incremental view, set **hoodie.hudicow.consume.mode** to **INCREMENTAL**. This parameter applies only to queries on the incremental view and cannot be used for queries on other types of Hudi tables or queries on other tables. You can set **hoodie.hudicow.consume.mode** to **SNAPSHOT** or any value to restore the configuration.

### 10.2.3.1 Reading COW Table Views

- Reading the real-time view (using Hive and SparkSQL as an example):  
Directly read the Hudi table stored in Hive.
- Reading the real-time view (using the Spark DataSource API as an example):  
This is similar to reading a common DataSource table.

**QUERY\_TYPE\_OPT\_KEY** must be set to **QUERY\_TYPE\_SNAPSHOT\_OPT\_VAL**.

```
spark.read.format("hudi")
.option(QUERY_TYPE_OPT_KEY, QUERY_TYPE_SNAPSHOT_OPT_VAL) // Set the query type to the real-time view.
.load("/tmp/default/cow_bugx/**/**") // Set the path of the Hudi table to be read. The current table has three levels of partitions.
.createTempView("mycall")
spark.sql("select * from mycall").show(100)
```

- Reading the incremental view (using Hive and SparkSQL as an example):  

```
set hoodie.test.consume.mode=INCREMENTAL; // Specify the incremental reading mode.
set hoodie.test.consume.max.commits=3; // Specify the maximum number of commits to be consumed.
set hoodie.test.consume.start.timestamp=20201227153030; // Specify the initial incremental pull commit.
select count(*) from default.test where `_hoodie_commit_time`>'20201227153030'; // This filtering condition must be added, and the value is the initial incremental pull commit.
```

- Reading the incremental view (using the Spark DataSource API as an example):

**QUERY\_TYPE\_OPT\_KEY** must be set to **QUERY\_TYPE\_INCREMENTAL\_OPT\_VAL**.

```
spark.read.format("hudi")
.option(QUERY_TYPE_OPT_KEY, QUERY_TYPE_INCREMENTAL_OPT_VAL) // Set the query type to the incremental mode.
.option(BEGIN_INSTANTTIME_OPT_KEY, "20210308212004") // Specify the initial incremental pull commit.
.option(END_INSTANTTIME_OPT_KEY, "20210308212318") //: Specify the end commit of the incremental pull.
.load("/tmp/default/cow_bugx/*/*/*") // Set the path of the Hudi table to be read. The current table has three levels of partitions.
.createTempView("mycall") // Register as a Spark temporary table.
spark.sql("select * from mycall where `_hoodie_commit_time`>'20210308211131'")// Start the query. The statement is the same as the Hive incremental query statement.
.show(100, false)
```

- Reading the read-optimized view: The read-optimized view of COW tables is equivalent to the real-time view.

### 10.2.3.2 Reading MOR Table Views

After the MOR table is synchronized to Hive, the following two tables are synchronized to Hive: *Table name\_rt* and *Table name\_ro*. The table suffixed with **rt** indicates the real-time view, and the table suffixed with **ro** indicates the read-optimized view. For example, the name of the Hudi table to be synchronized to Hive is **test**. After the table is synchronized to Hive, two more tables **test\_rt** and **test\_ro** are generated in the Hive table.

- Reading the real-time view (using Hive and SparkSQL as an example):  
Directly read the Hudi table with suffix **\_rt** stored in Hive.  

```
select count(*) from test_rt;
```
- Reading the real-time view (using the Spark DataSource API as an example):  
The operations are the same as those for the COW table. For details, see the operations for the COW table.
- Reading the incremental view (using Hive and SparkSQL as an example):  

```
set hive.input.format=org.apache.hudi.hadoop.hive.HoodieCombineHiveInputFormat; // This parameter does not need to be specified for SparkSQL.
set hoodie.test.consume.mode=INCREMENTAL;
set hoodie.test.consume.max.commits=3;
set hoodie.test.consume.start.timestamp=20201227153030;
select count(*) from default.test_rt where `_hoodie_commit_time`>'20201227153030';
```
- Incremental view (using the Spark DataSource API as an example):  
The operations are the same as those for the COW table. For details, see the operations for the COW table.
- Reading the read-optimized view (using Hive and SparkSQL as an example):  
Directly read the Hudi table with suffix **\_ro** stored in Hive.  

```
select count(*) from test_ro;
```
- Reading the read-optimized view (using the Spark DataSource API as an example):  
This is similar to reading a common DataSource table.

**QUERY\_TYPE\_OPT\_KEY** must be set to  
**QUERY\_TYPE\_READ\_OPTIMIZED\_OPT\_VAL**.

```
spark.read.format("hudi")  
.option(QUERY_TYPE_OPT_KEY, QUERY_TYPE_READ_OPTIMIZED_OPT_VAL) // Set the query type to  
the read-optimized view.  
.load("/tmp/default/mor_bugx/**/**/**") // Set the path of the Hudi table to be read. The current table  
has three levels of partitions.  
.createTempView("mycall")  
spark.sql("select * from mycall").show(100)
```

Note:  
Spark SQL cannot query the incremental view of the datasource table but can query Hive tables and  
dataSource APIs.

## 10.2.4 Data Management and Maintenance

### 10.2.4.1 Metadata Table

- **Introduction**

A metadata table is a special Hudi metadata table, which is hidden from users. The table stores metadata of a common Hudi table.

The metadata table is included in a common Hudi table and has a one-to-one mapping relationship with the Hudi table.

- **Functions**

Listing massive table partition files in HDFS consumes a large number of RPC requests, reducing HDFS throughput and affecting performance. This problem is more serious for object storage such as OBS. However, a query engine must go through the preceding step before a query.

Generally, partition information of the current partitioned table is stored in Hive MetaStore. If the partition size of a partitioned table reaches a certain level, the query engine performance deteriorates significantly when querying the partition information of the current table.

- **Mechanism**

A metadata table stores the partition information of the current Hudi table and the file information in the partition directory as the metadata information in a special Hudi table. In this way, when a query engine lists partition files of the table, the engine only needs access the metadata table. The RPC pressure of HDFS during query can be greatly reduced with a small volume of metadata information.

A metadata table is implemented using a Hudi MOR table. Therefore, it can be compacted, cleaned up, and incrementally updated. Unlike similar implementations in other projects, the file listing information is indexed as HFiles, which offers point-lookup performance to obtain partition file listings.

- **How to Use**

For Hive query, run **set hoodie.metadata.enable=true**.

For Spark SQL query, set **--conf spark.hadoop.hoodie.metadata.enable to true** when starting Spark SQL.

When using Spark to write data, set **hoodie.metadata.enable** in the **option** parameter to **true**.

For details about more parameters, see [Configuration Reference](#) or visit Hudi official website <http://hudi.apache.org/docs/configurations.html#metadata-config>.

- **Performance improvement**

In the test on a large table with 250,000 partition files, the metadata table delivers two to three times speedup over parallelized listing done by Spark.

---

 **CAUTION**

1. Do not manually operate a metadata table. Otherwise, data security may be affected.
  2. To use metadata, you must enable metadata for each write operation to ensure data integrity.
  3. When compaction and rollback are performed on tables of Hudi 0.8, data cannot be synchronized to the metadata table.
  4. When metadata is enabled during the clean operation, the metadata table can be updated.
  5. When the number of commits reaches a specified value, compaction, clean, and archive operations are automatically triggered. Therefore, the operation in [a](#) is unnecessary.
- 

## 10.2.4.2 Clustering

### Introduction

Clustering reorganizes data layout to improve query performance without affecting the ingestion speed.


### Architecture

Hudi provides different operations, such as **insert**, **upsert**, and **bulk\_insert**, through its write client API to write data to a Hudi table. To weight between file size and speed of importing data into the data lake, Hudi provides **hoodie.parquet.small.file.limit** to configure the minimum file size. You can set it to **0** to force new data to be written to new file groups, or to a higher value to ensure that new data is "padded" to existing small file groups until it reaches the specified size, but this increases ingestion latency.

To support fast ingestion without affecting query performance, the clustering service is introduced to rewrite data to optimize the layout of Hudi data lake files.

The clustering service can run asynchronously or synchronously. It adds a new operation type called **REPLACE**, which will mark the clustering operation in the Hudi metadata timeline.

Clustering service is based on the MVCC design of Hudi to allow new data to be inserted. Clustering operations run in the background to reformat data layout, ensuring snapshot isolation between concurrent readers and writers.



Clustering is divided into two parts:

- Scheduling clustering: Create a clustering plan using a pluggable clustering strategy.
  - a. Identify files that are eligible for clustering: Depending on the selected clustering strategy, the scheduling logic will identify the files eligible for clustering.
  - b. Group files that are eligible for clustering based on specific criteria. The data size of each group must be a multiple of **targetFileSize**. Grouping is a part of the strategy defined in the plan. Additionally, there is an option to control group size to improve parallelism and avoid shuffling large volumes of data.
  - c. Save the clustering plan to the timeline in Avro metadata format.
- Execute clustering: Process the plan using an execution strategy to create new files and replace old files.
  - a. Read the clustering plan and get **clusteringGroups** that marks the file groups to be clustered.
  - b. Instantiate appropriate strategy class for each group using **strategyParams** (for example, **sortColumns**) and apply the strategy to rewrite data.
  - c. Create a **REPLACE** commit and update the metadata in HoodieReplaceCommitMetadata.

## How to Execute Clustering

1. Executing clustering synchronously
 

```
df.write.format("org.apache.hudi").
options(getQuickstartWriteConfigs).
option(PRECOMBINE_FIELD_OPT_KEY, "ts").
option(RECORDKEY_FIELD_OPT_KEY, "uuid").
option(PARTITIONPATH_FIELD_OPT_KEY, "partitionpath").
```

```
option(TABLE_NAME, "tableName").  
option("hoodie.parquet.small.file.limit", "0").  
option("hoodie.clustering.inline", "true").  
option("hoodie.clustering.inline.max.commits", "4").  
option("hoodie.clustering.plan.strategy.target.file.max.bytes",  
"1073741824").  
option("hoodie.clustering.plan.strategy.small.file.limit", "629145600").  
option("hoodie.clustering.plan.strategy.sort.columns",  
"column1,column2"). mode(Append).save("dfs://location");
```

2. Executing clustering asynchronously

```
spark-submit --master yarn --class  
org.apache.hudi.utilities.HoodieClusteringJob /opt/client/Hudi/hudi/lib/  
hudi-utilities*.jar --schedule --base-path <table_path> --table-name  
<table_name> --props /tmp/clusteringjob.properties --spark-memory 1g  
spark-submit --master yarn --driver-memory 16G --executor-memory 12G  
--executor-cores 4 --num-executors 4 --class  
org.apache.hudi.utilities.HoodieClusteringJob /opt/client/Hudi/hudi/lib/  
hudi-utilities*.jar --base-path <table_path> --instant-time  
20210605112954 --table-name <table_name> --props /tmp/  
clusteringjob.properties --spark-memory 12g
```

 NOTE

`clusteringjob.properties` contains custom clustering configurations.

Example:

```
hoodie.clustering.plan.strategy.target.file.max.bytes=1073741824  
hoodie.clustering.inline.max.commits=4
```

For details, see [Configuration Reference](#).

---

 CAUTION

1. By default, only the two partitions with the largest size are clustered. The clustering of other partitions depends on the custom strategy.
  2. The sorting column of clustering cannot be null. This is restricted by Spark RDD.
  3. If the value of **target.file.max.bytes** is large, increase the value of **--spark-memory** to execute clustering. Otherwise, the executor memory overflow occurs.
  4. Currently, the clean mechanism cannot be used to delete junk files generated after the clustering fails.
  5. After the clustering, sizes of new files may be different, causing data skew.
  6. Clustering and upsert operations cannot be performed at the same time.
- 

### 10.2.4.3 Cleaning

Cleaning is used to delete data of versions that are no longer required.

Hudi uses the cleaner working in the background to continuously delete unnecessary data of old versions. You can configure **hoodie.cleaner.policy** and

**hoodie.cleaner.commits.retained** to use different cleaning policies and determine the number of saved commits.

You can use either of the following methods to perform cleaning:

- Using Hudi CLI  
**cleans run --sparkMaster yarn --hoodieConfigs 'hoodie.cleaner.policy=KEEP\_LATEST\_COMMITS,hoodie.cleaner.commits.retained=1,hoodie.cleaner.incremental.mode=false,hoodie.keep.max.commits=3,hoodie.keep.min.commits=2'**
- Using APIs  
**spark-submit --master yarn --jars /opt/client/Hudi/hudi/lib/hudi-client-common-xxx.jar --class org.apache.hudi.utilities.HoodieCleaner /opt/client/Hudi/hudi/lib/hudi-utilities\_xxx.jar --target-base-path /tmp/default/tb\_test\_mor**

For details about more cleaning parameters, see [Configuration Reference](#).

### 10.2.4.4 Compaction

A compaction merges base and log files of MOR tables.

For MOR tables, data is stored in columnar Parquet files and row-based Avro files, updates are recorded in incremental files, and then a synchronous or asynchronous compaction is performed to generate new versions of columnar files. MOR tables can reduce data ingestion latency, so an asynchronous compaction that does not block ingestion is useful.

An asynchronous compaction is performed in the following two steps:

1. Scheduling a compaction: A compaction is completed by the job of importing data into the data lake. In this step, Hudi scans partitions and selects the file slices to be compacted. A compaction plan is finally written to the Hudi timeline.
2. Executing a compaction: A separate process or thread reads the compaction plan and performs the compaction of file slices.

Compaction can be synchronous or asynchronous.

#### Synchronization modes

- When HoodieDeltaStreamer is used to write upstream data (Kafka/DFS) to a Hudi dataset, the default value of **--disable-compaction** is **false**, indicating that a compaction is automatically executed.
- Using DataSource to specify parameters when writing data  
**option("hoodie.compact.inline", "true").**  
**option("hoodie.compact.inline.max.delta.commits", "2").**

#### Asynchronous modes

- Using Hudi CLI  
Scheduling a compaction:  
**compaction schedule --hoodieConfigs 'hoodie.compaction.strategy=org.apache.hudi.table.action.compact.strate**

```
gy.BoundedIOCompactionStrategy,hoodie.compaction.target.io=1,hoodie.c  
ompact.inline.max.delta.commits=1'
```

Executing a compaction:

```
compaction run --parallelism 100 --sparkMemory 1g --retry 1 --  
compactionInstant 20210602101315 --hoodieConfigs  
'hoodie.compaction.strategy=org.apache.hudi.table.action.compact.strate  
gy.BoundedIOCompactionStrategy,hoodie.compaction.target.io=1,hoodie.c  
ompact.inline.max.delta.commits=1' --propsFilePath hdfs://  
hacluster/tmp/default/tb_test_mor/.hoodie/hoodie.properties --  
schemaFilePath /tmp/default/tb_test_mor/.hoodie/compact_tb_base.json
```

- Using APIs

Scheduling a compaction:

```
spark-submit --master yarn --jars /opt/client/Hudi/hudi/lib/hudi-client-  
common-xxx.jar --class org.apache.hudi.utilities.HoodieCompactor /opt/  
client/Hudi/hudi/lib/hudi-utilities_xxx.jar --base-path /tmp/default/  
tb_test_mor --table-name tb_test_mor --parallelism 100 --spark-memory  
1G --schema-file /tmp/default/tb_test_mor/.hoodie/compact_tb_base.json  
--instant-time 20210602141810 --schedule --strategy  
org.apache.hudi.table.action.compact.strategy.UnBoundedCompactionStra  
tegy
```

Executing a compaction:

```
spark-submit --master yarn --jars /opt/client/Hudi/hudi/lib/hudi-client-  
common-xxx.jar --class org.apache.hudi.utilities.HoodieCompactor /opt/  
client/Hudi/hudi/lib/hudi-utilities_xxx.jar --base-path /tmp/default/  
tb_test_mor --table-name tb_test_mor --parallelism 100 --spark-memory  
1G --schema-file /tmp/default/tb_test_mor/.hoodie/compact_tb_base.json  
--instant-time 20210602141810
```

#### NOTE

- When using Hudi CLI to schedule a compaction, you do not need to specify **instant-time**, which is automatically generated and returned by the system after the scheduling is successful. You only need to pass this parameter during execution.
- For **schema-file**, you need to manually edit the schema file of the current Hudi table and upload it to the server. You can use the schema in the latest **.commit** file.
- Compaction and write operations cannot be performed at the same time.

### 10.2.4.5 Savepoint

Savepoints are used to save and restore data of the customized version.

Savepoints provided by Hudi can save different commits so that the cleaner program does not delete them. You can use rollback to restore them later.

Using Hudi CLI to manage savepoints includes:

- Creating a savepoint  
**savepoint create --commit <commit\_time>**
- Rolling back a savepoint  
**savepoint rollback --savepoint <savepoint\_time>**

- Refreshing savepoints  
**savepoints refresh**
- Viewing all existing savepoints  
**savepoints show**


 NOTE

MOR tables do not support savepoints.

### 10.2.4.6 Single-Table Concurrent Write

#### Hudi Single-Table Concurrent Write Solution

1. Uses an external service (ZooKeeper or Hive MetaStore) as the distributed mutex lock service.
2. Files can be concurrently written, but commits cannot be concurrent. The commit operation is encapsulated in a transaction.
3. When the commit operation is performed, the system performs conflict check. If the modified file list in the current commit operation overlaps with the file list in the commit operation after the instance time, the commit operation fails and the write operation is invalid.



#### Precautions for Using the Concurrency Mechanism

1. For **insert** and **bulk\_insert** operations, the current Hudi concurrency mechanism cannot ensure that the primary key of the table is unique after data is written. You need to ensure that the primary key is unique.
2. For incremental queries, data consumption and checkpoints may be out of order. As a result, multiple concurrent write operations are completed at different time points.
3. Concurrent write is supported only after this feature is enabled.

## How to Use the Concurrency Mechanism

1. Enable the concurrent write mechanism.  
**hoodie.write.concurrency.mode=optimistic\_concurrency\_control**  
**hoodie.cleaner.policy.failed.writes=LAZY**
2. Sets the concurrent lock mode.  
Hive MetaStore:  
**hoodie.write.lock.provider=org.apache.hudi.hive.HiveMetastoreBasedLockProvider**  
**hoodie.write.lock.hivemetastore.database=<database\_name>**  
**hoodie.write.lock.hivemetastore.table=<table\_name>**  
ZooKeeper:  
**hoodie.write.lock.provider=org.apache.hudi.client.transaction.lock.ZookeeperBasedLockProvider**  
**hoodie.write.lock.zookeeper.url=<zookeeper\_url>**  
**hoodie.write.lock.zookeeper.port=<zookeeper\_port>**  
**hoodie.write.lock.zookeeper.lock\_key=<table\_name>**  
**hoodie.write.lock.zookeeper.base\_path=<table\_path>**

For details about more parameters, see [Configuration Reference](#).

---

### CAUTION

If **cleaner policy** is set to **Lazy**, the system can only check whether the written files expire but cannot check and clear junk files generated by historical writes. That is, junk files cannot be automatically cleared in concurrent scenarios.

---

## 10.2.5 Using the Hudi Client

### 10.2.5.1 Operating a Hudi Table Using `hudi-cli.sh`

#### Prerequisites

- You have created a user and added the user to user groups **hadoop** and **hive** on Manager.
- The Hudi client has been downloaded and installed.

#### Basic Operations


1. Log in to the client node as user **root** and run the following commands:  
**cd *Client installation directory***  
**source bigdata\_env**  
**cd *Client installation directory*****Hudi**  
**source component\_env**  
**kinit *Created user***

2. Run the **hudi-cli.sh** command to access the Hudi client.

**cd** *Client installation directory***Hudi**

**hudi-cli.sh**

```
[root@kwephisprad4948 bin]# hudi-cli.sh
Running : java -cp /opt/prober/client/Hudi/hudi/conf:/opt/prober/client/Hudi/hudi/lib/*:/opt/prober/client/Spark2x/spark/jars/* -
Djava.security.krb5.conf=/opt/prober/client/Krbclient/Kerberos/var/krb5de/krb5.conf -Dzookeeper.server.principal=zookeeper/hadoo
p.hadooptest.com -Djava.security.auth.login.config=/opt/prober/client/Hudi/hudi/conf/jaas.conf -Dzookeeper.kinit=/opt/prober/clie
nt/Krbclient/kerberos/bin/kinit -DSPARK_CONF_DIR=/opt/prober/client/Hudi/hudi/conf -DHADOOP_CONF_DIR=/opt/prober/client/Hudi/hudi
/conf org.springframework.shell.Bootstrap
2021-09-17 15:24:08,035 | INFO | main | Loading XML bean definitions from URL [jar:file:/opt/prober/client/Hudi/hudi/lib/hudi-cl
i-0.9.0-hw-ei-312001-SNAPSHOT.jar!/META-INF/spring/spring-shell-plugin.xml] | org.springframework.beans.factory.xml.XmlBeanDefini
tionReader.loadBeanDefinitions(XmlBeanDefinitionReader.java:317)
2021-09-17 15:24:08,627 | INFO | main | Refreshing org.springframework.context.support.GenericApplicationContext@59906517: start
up date [Fri Sep 17 15:24:08 CST 2021]; root of context hierarchy | org.springframework.context.support.GenericApplicationContext
.prepareRefresh(ApplicationContext.java:578)
2021-09-17 15:24:08,827 | INFO | main | JSR-330 'javax.inject.Inject' annotation found and supported for autowiring | org.spring
framework.beans.factory.annotation.AutowiredAnnotationBeanPostProcessor.<init>(AutowiredAnnotationBeanPostProcessor.java:153)
Table command getting loaded
HoodieSplashScreen loaded
```



```
Welcome to Apache Hudi CLI. Please type help if you are looking for help.
```

3. Run the following example commands as required. For details about all commands, visit the [Hudi official website](#).

- Viewing help information

**help** // View all Hudi CLI commands.

**help 'command'** // View the help information and parameter list of a certain command.

- Connecting to a table

**connect --path** *'/tmp/huditest/test\_table'*

- Viewing table information

**desc**

- Viewing compaction plans

**compactions show all**

- Viewing cleaning plans

**cleans show**

- Performing the cleaning operation

**cleans run**

- Viewing commit information

**commits show**

- Viewing the partition where the commit is written to

**commit showpartitions --commit** *20210127153356*

 **NOTE**

*20210127153356* indicates the commit timestamp.

- Viewing the file where the commit is written to

**commit showfiles --commit** *20210127153356*

- Comparing the commit information of two tables

**commits compare --path** */tmp/hudimor/mytest100*

- Rolling back a commit (Only the last commit can be rolled back.)

- commit rollback --commit 20210127164905**

  - Scheduling a compaction
 

**compaction schedule --hoodieConfigs**  
*'hoodie.compaction.strategy=org.apache.hudi.table.action.compact.strategy.BoundedIOCompactionStrategy,hoodie.compaction.target.io=1,hoodie.compact.inline.max.delta.commits=1'*
  - Performing a compaction
 

**compaction run --parallelism 100 --sparkMemory 1g --retry 1 --compactionInstant 20210602101315 --hoodieConfigs**  
*'hoodie.compaction.strategy=org.apache.hudi.table.action.compact.strategy.BoundedIOCompactionStrategy,hoodie.compaction.target.io=1,hoodie.compact.inline.max.delta.commits=1' --propsFilePath hdfs://hacluster/tmp/default/tb\_test\_mor/.hoodie/hoodie.properties --schemaFilePath /tmp/default/tb\_test\_mor/.hoodie/compact\_tb\_base.json*
  - Creating a savepoint
 

**savepoint create --commit 20210318155750**
  - Rolling back a specified savepoint
 

**savepoint rollback --savepoint 20210318155750**

---

 CAUTION

1. If the commit operation causes metadata conflicts, you can run the **commit rollback** and **savepoint rollback** commands to roll back data, but the Hive metadata cannot be rolled back. In this case, you can delete the Hive table and manually synchronize data.
  2. The **commit rollback** command rolls back only the latest commit, and the **savepoint rollback** command rolls back only the latest savepoint. You cannot specify a commit or savepoint to roll back.
- 

## 10.2.6 Configuration Reference

This section describes important Hudi configurations. For details, visit the Hudi official website <https://hudi.apache.org/docs/configurations.html>.

### 10.2.6.1 Write Configuration

**Table 10-4** Write configuration

Parameter	Description	Default Value
hoodie.datasource.write.table.name	Specifies the name of the Hudi table to be written.	None

Parameter	Description	Default Value
hoodie.datasource.write.operation	<p>Specifies the operation type of writing the Hudi table. Currently, <b>upsert</b>, <b>delete</b>, <b>insert</b>, <b>bulk_insert</b>, and <b>bootstrap</b> are supported.</p> <ul style="list-style-type: none"> <li>• <b>upsert</b>: updates and inserts data.</li> <li>• <b>delete</b>: deletes data.</li> <li>• <b>insert</b>: inserts data.</li> <li>• <b>bulk_insert</b>: imports data during initial table creation. Do not <b>upsert</b> or <b>insert</b> during initial table creation.</li> <li>• <b>bootstrap</b>: directly transforms a Parquet table into a Hudi table.</li> <li>• <b>insert_overwrite</b>: performs insert and overwrite operations on static partitions.</li> <li>• <b>insert_overwrite_table</b>: performs insert and overwrite operations on dynamic partitions. It does not immediately delete the entire table or overwrite the table. Instead, it overwrites the metadata of the Hudi table logically, and Hudi deletes useless data through the clean mechanism. Its efficiency is higher than that of the combination of <b>bulk_insert</b> and <b>overwrite</b>.</li> </ul>	upsert
hoodie.datasource.write.table.type	<p>Specifies the Hudi table type. Once the table type is specified, this parameter cannot be modified. The value can be <b>MERGE_ON_READ</b>.</p>	COPY_ON_WRITE
hoodie.datasource.write.precombine.field	<p>Merges and reduplicates rows with the same key before write.</p>	ts

Parameter	Description	Default Value
hoodie.datasource.write.payload.class	Specifies the class used to merge the records to be updated and the updated records during update. This parameter can be customized. You can compile it yourself to implement your merge logic.	org.apache.hudi.OverwriteWithLatestAvroPayload
hoodie.datasource.write.recordkey.field	Specifies the primary key of the Hudi table. The Hudi table must have a unique primary key.	uuid
hoodie.datasource.write.partitionpath.field	Specifies the partition key. This parameter is used together with <b>hoodie.datasource.write.keygenerator.class</b> to meet the requirements of different partition scenarios.	partitionpath
hoodie.datasource.write.hive_style_partitioning	Specifies whether the partition mode is the same as that of Hive. You are advised to set this parameter to <b>true</b> .	false
hoodie.datasource.write.keygenerator.class	Generates the primary key and partition mode when used together with <b>hoodie.datasource.write.partitionpath.field</b> and <b>hoodie.datasource.write.recordkey.field</b> .	org.apache.hudi.keygen.SimpleKeyGenerator

### 10.2.6.2 Configuration of Hive Table Synchronization

Parameter	Description	Default Value
hoodie.datasource.hive_sync.enable	Specifies whether to synchronize the Hudi table information to Hive MetaStore. <b>CAUTION</b> You are advised to set this parameter to <b>true</b> to use Hive to manage the Hudi table.	false
hoodie.datasource.hive_sync.database	Specifies the name of the database to be synchronized to Hive.	default

Parameter	Description	Default Value
hoodie.datasource.hive_sync.table	Specifies the name of the table to be synchronized to Hive. You are advised to set this parameter to the value of <b>hoodie.datasource.write.table.name</b> .	None
hoodie.datasource.hive_sync.username	Specifies the username used for Hive synchronization.	hive
hoodie.datasource.hive_sync.password	Specifies the password used for Hive synchronization.	hive
hoodie.datasource.hive_sync.jdbcurl	Specifies the Hive JDBC URL for connection.	jdbc:hive2://localhost:10000
hoodie.datasource.hive_sync.use_jdbc	Specifies whether to use Hive JDBC to connect to Hive for the Hudi table information synchronization. You are advised to set this parameter to <b>false</b> , which indicates that the JDBC connection configuration is invalid.	true
hoodie.datasource.hive_sync.partition_fields	Specifies the Hive partition columns.	` `
hoodie.datasource.hive_sync.partition_extractor_class	Specifies the class used to extract Hudi partition field values and convert them into Hive partition columns.	org.apache.hudi.hive.SlashEncodedDayPartitionValueExtractor
hoodie.datasource.hive_sync.support_timestamp	If the Hudi table contains a field of the timestamp type, set this parameter to <b>true</b> to synchronize the timestamp type to the Hive metadata. The default value is <b>false</b> , indicating that the timestamp type is converted to bigint during synchronization by default. In this case, an error may occur when you query a Hudi table that contains a field of the timestamp type using SQL statements.	true

### 10.2.6.3 Index Configuration

Parameter	Description	Default Value
hoodie.index.class	Specifies the full path of user-defined index class. It must be a subclass of HoodieIndex and takes precedence over the <b>hoodie.index.type</b> configuration if specified.	""
hoodie.index.type	Specifies the type of index to be used. The Bloom filter is used by default. The possible option is [ <b>BLOOM</b>   <b>HBASE</b>   <b>GLOBAL_BLOOM</b>   <b>SIMPLE</b>   <b>GLOBAL_SIMPLE</b> ]. The Bloom filter eliminates the dependency on an external system and is stored in the footer of a Parquet data file.	BLOOM
hoodie.index.bloom.num_entries	Specifies the number of entries to be stored in the Bloom filter. If the <b>maxParquetFileSize</b> is 128 MB and <b>averageRecordSize</b> is 1,024 bytes, a total of 130 KB records exist in a file. The default value (60000) is about half of this approximate value. <b>CAUTION</b> If the value is too low, a large number of false positives will occur, and index lookup will have to scan more files than it needs. If the value is too high, the size every data file will be increased linearly (about 4 KB for every 50000 entries).	60000
hoodie.index.bloom.fpp	Specifies the allowed error rate based on the number of entries. This is used to calculate how many bits should be assigned for the Bloom filter and the number of hash functions. Generally, it is set to a small value (0.000000001 by default). You need to balance the disk space to reduce the false positive rate.	0.000000001

Parameter	Description	Default Value
hoodie.bloom.index.parallelism	Specifies the parallelism for index lookup, which involves Spark Shuffle. By default, this is automatically computed based on input workload characteristics.	0
hoodie.bloom.index.prune.by.ranges	If this parameter is set to <b>true</b> , information is ranged from files to speed up index lookups. It is particularly useful if the key has a monotonously increasing prefix, such as timestamp.	true
hoodie.bloom.index.use.caching	If this parameter is set to <b>true</b> , the input RDD is cached to speed up index lookups by reducing I/O for computing parallelism or affected partitions.	true
hoodie.bloom.index.use.treebased.filter	If this parameter is set to <b>true</b> , the file pruning optimization based on interval tree is enabled. This mode speeds up file pruning based on key ranges compared with the brute-force mode.	true
hoodie.bloom.index.bucketized.checking	If this parameter is set to <b>true</b> , the bucketized Bloom filtering is enabled. This reduces skew in the sort-based Bloom index lookup.	true
hoodie.bloom.index.keys.per.bucket	This parameter is applicable only when <b>bloomIndexBucketizedChecking</b> is enabled and the index type is <b>BLOOM</b> . This parameter controls the "bucket" size which tracks the number of record-key checks made against a single file and is the unit of work allocated to each partition performing the Bloom filter lookup. A higher value would amortize the fixed cost of reading the Bloom filter to memory.	10000000

Parameter	Description	Default Value
hoodie.bloom.index.update.partition.path	This parameter is applicable only when the index type is <b>GLOBAL_BLOOM</b> . If this parameter is set to <b>true</b> , an update including the partition path of a record that already exists will result in the insertion of the incoming record into the new partition and the deletion of the original record in the old partition. If this parameter is set to <b>false</b> , the original record will only be updated in the old partition.	false
hoodie.index.hbase.zk.quorum	This parameter is applicable only when the index type is <b>HBASE</b> . HBase ZooKeeper quorum URL to be connected.	Mandatory
hoodie.index.hbase.zk.port	This parameter is applicable only when the index type is <b>HBASE</b> . HBase ZooKeeper quorum port to be connected.	Mandatory
hoodie.index.hbase.zk.node.path	This parameter is applicable only when the index type is <b>HBASE</b> . It is the root znode that will contain all the znodes created and used by HBase.	Mandatory
hoodie.index.hbase.table	This parameter is applicable only when the index type is <b>HBASE</b> . HBase table name to be used as an index. Hudi stores the <b>row_key</b> and <b>[partition_path, fileId, commitTime]</b> mapping in the table.	Mandatory

### 10.2.6.4 Storage Configuration

Parameter	Description	Default Value
hoodie.parquet.max.file.size	Specifies the target size for Parquet files generated in Hudi write phases. For DFS, this parameter needs to be aligned with the underlying file system block size for optimal performance.	120 x 1024 x 1024 bytes
hoodie.parquet.block.size	Specifies the Parquet page size. Page is the unit of read in a Parquet file. In a block, pages are compressed separately.	120 x 1024 x 1024 bytes
hoodie.parquet.compression.ratio	Specifies the expected compression ratio of Parquet data when Hudi attempts to adjust the size of a new Parquet file. If the size of the file generated by <b>bulk_insert</b> is smaller than the expected size, increase the value.	0.1
hoodie.parquet.compression.codec	Specifies the name of the Parquet compression encoding or decoding mode. The default value is <b>gzip</b> . Possible options are <b>[gzip   snappy   uncompressed   lzo]</b> .	gzip
hoodie.logfile.max.size	Specifies the maximum size of LogFile. It is the maximum size allowed for a log file before it is rolled over to the next version.	1GB
hoodie.logfile.data.block.max.size	Specifies the maximum size of a LogFile data block. It is the maximum size allowed for a single data block to be appended to a log file. It helps to ensure that the data appended to the log file is broken up into sizable blocks to prevent OOM errors. The size should be greater than the JVM memory.	256MB

Parameter	Description	Default Value
hoodie.logfile.to.parquet.compression.ratio	Specifies the expected additional compression when records move from log files to Parquet files. It is used for MOR tables to send inserted content into log files and control the size of compacted Parquet files.	0.35
hoodie.parquet.compression.codec	Specifies the compression encoding and decoding mode for Parquet files.	gzip

### 10.2.6.5 Compaction and Cleaning Configurations

Parameter	Description	Default Value
hoodie.cleaner.policy	Specifies the cleaning policy to be used. Hudi will delete the Parquet file of an old version to reclaim space. Any query or computation referring to this version of the file will fail. You are advised to ensure that the data retention time exceeds the maximum query execution time.	KEEP_LATEST_COMMITS
hoodie.cleaner.commits.retained	Specifies the number of commits to retain. Data will be retained for <b>num_of_commits * time_between_commits</b> (scheduled). This also directly translates into the number of datasets can be incrementally pulled.	10
hoodie.keep.min.commits, hoodie.keep.max.commits	Each commit is a small file in the <b>.hoodie</b> directory. DFS typically does not support a large number of small files, so Hudi archives older commits into a sequential log. A commit is published atomically by renaming the commit file.	20

Parameter	Description	Default Value
hoodie.commits.archival.batch	This parameter controls the number of commit instants read in memory as a batch and archived together.	10
hoodie.parquet.small.file.limit	The value must be smaller than that of <b>maxFileSize</b> . If <b>maxFileSize</b> is set to <b>0</b> , this function is disabled. Small files always exist because of the large number of insert records in a partition of batch processing. Hudi provides an option to solve the problem of small files by masking inserts into this partition as updates to existing small files. The size here is the minimum file size that is considered as a "small file size".	104857600 byte
hoodie.copyonwrite.insert.split.size	Specifies the parallelism for inserting and writing data. It is the number of inserts grouped for a single partition. Writing out 100 MB files with at least 1 KB records means 100 KB records exist in each file. Overprovision to 500 KB by default. To improve insert latency, adjust the value to match the number of records in a single file. If it is set to a smaller value, the file size will shrink (especially when <b>compactionSmallFileSize</b> is set to <b>0</b> ).	500000
hoodie.copyonwrite.insert.auto.split	Specifies whether Hudi dynamically computes <b>insertSplitSize</b> based on the last 24 commit metadata. This function is disabled by default.	true

Parameter	Description	Default Value
hoodie.copyonwrite.record.size.estimate	Specifies the average record size. If specified, Hudi will use this parameter and not compute dynamically based on the last 24 commit metadata. There is no default value. This is critical in computing the insert parallelism and packing inserts into small files.	1024
hoodie.compact.inline	If this parameter is set to <b>true</b> , compaction is triggered by the ingestion itself right after a commit or delta commit action as part of <b>insert</b> , <b>upsert</b> , or <b>bulk_insert</b> .	false
hoodie.compact.inline.max.delta.commits	Specifies the maximum number of delta commits to be retained before inline compression is triggered.	5
hoodie.compaction.lazylazy.block.read	When <b>CompactedLogScanner</b> merges all log files, this parameter helps to choose whether the logblocks should be read lazily. Set it to <b>true</b> to use I/O-intensive lazy block read (low memory usage) or <b>false</b> to use memory-intensive immediate block read (high memory usage).	false
hoodie.compaction.reverse.log.read	<b>HoodieLogFormatReader</b> reads a log file in the forward direction from <b>pos=0</b> to <b>pos=file_length</b> . If this parameter is set to <b>true</b> , Reader reads a log file in reverse direction from <b>pos=file_length</b> to <b>pos=0</b> .	false
hoodie.cleaner.parallelism	Increase this parameter if cleaning becomes slow.	200
hoodie.compaction.strategy	Determines which file groups are selected for compaction during each compaction run. By default, Hudi selects the log file with most accumulated unmerged data.	org.apache.hudi.table.action.compact.strategy. LogFileSizeBasedCompactionStrategy

Parameter	Description	Default Value
hoodie.compaction.target.io	Specifies the number of MBs to spend during compaction run for <b>LogFileBasedCompactionStrategy</b> . This parameter can limit ingestion latency when compaction is run in inline mode.	500 * 1024 MB
hoodie.compaction.daybased.target	Used by <b>org.apache.hudi.io.compact.strategy.DayBasedCompactionStrategy</b> to denote the number of latest partitions to compact during a compaction run.	10
hoodie.compaction.payload.class	It needs to be same as class used during insert or upsert. Similar to writing, compaction also uses the record payload class to merge records in the log against each other, merge again with the base file, and produce the final record to be written after compaction.	org.apache.hudi.common.model.OverwriteWithLatestAvroPayload

### 10.2.6.6 Metadata Table Configuration

Parameter	Description	Default Value
hoodie.metadata.enable	Specifies whether to enable the metadata table.	false
hoodie.metadata.rollback.enable	Specifies whether to enable rollback.	true
hoodie.metadata.insert.parallelism	Specifies the parallelism of insertion.	1
hoodie.metadata.compact.max.delta.commits	Specifies the number of commits to trigger metadata table compaction.	maxNumDeltaCommitsBeforeCompaction = 24
hoodie.metadata.keep.min.commits hoodie.metadata.keep.max.commits	Specifies the maximum and minimum number of commits reserved for compaction.	minToKeep = 20 maxToKeep = 30

### 10.2.6.7 Single-Table Concurrent Write Configuration

Parameter	Description	Default Value
hoodie.write.lock.provider	Specifies the lock provider. You are advised to set the parameter to <b>org.apache.hudi.hive.HiveMetastoreBasedLockProvider</b> .	org.apache.hudi.client.transaction.lock.ZookeeperBasedLockProvider
hoodie.write.lock.hive.metastore.database	Specifies the Hive database.	-
hoodie.write.lock.hive.metastore.table	Specifies the Hive table name.	-
hoodie.write.lock.client.num_retries	Specifies the retry times.	0
hoodie.write.lock.client.wait_time_ms_between_retry	Specifies the retry interval.	10000
hoodie.write.lock.conflict.resolution.strategy	Specifies the lock provider class, which must be a subclass of <b>ConflictResolutionStrategy</b> .	org.apache.hudi.client.transaction.SimpleConcurrentFileWritesConflictResolutionStrategy
hoodie.write.lock.zookeeper.base_path	Path for storing ZNodes. The parameter must be the same for all concurrent write configurations of the same table.	-
hoodie.write.lock.zookeeper.lock_key	ZNode name. It is recommended that the ZNode name be the same as the Hudi table name.	-
hoodie.write.lock.zookeeper.connection_timeout_ms	ZooKeeper connection timeout period.	15000
hoodie.write.lock.zookeeper.port	ZooKeeper port number.	-
hoodie.write.lock.zookeeper.url	URL of the ZooKeeper.	-
hoodie.write.lock.zookeeper.session_timeout_ms	Session expiration time of ZooKeeper.	60000

## 10.3 Hudi Performance Tuning

### 10.3.1 Performance Tuning Methods

In the current version, Spark is recommended for Hudi write operations. Therefore, the tuning methods of Hudi are similar to those of Spark. For details, see [Spark2x Performance Tuning](#).

### 10.3.2 Recommended Resource Configuration

- For MOR tables:  
The essence of MOR tables is to write incremental files, so the tuning is based on the data size (dataSize) of Hudi.  
If dataSize is only several GBs, you are advised to run Spark in single-node mode or run Spark in Yarn mode with only one container allocated.  
Parallelism (**p**) of programs for importing data to the lake:  $p = \text{dataSize} / 128 \text{ MB}$ . The number of cores allocated to programs must be the same as the value of **p**. It is recommended that the ratio of the memory size to the number of cores be greater than 1.5:1. That is, a core is configured with 1.5 GB memory. For off-heap memory, it is recommended that the ratio of the memory size to the number of cores be greater than 0.5:1.
- For COW tables:  
The principle of COW tables is to rewrite the original data. Therefore, dataSize and the number of rewritten files must be considered during tuning. Generally, more cores lead to better performance. The number of cores is directly related to the number of rewritten files. The settings of parallelism (**p**) and memory size are similar to those of MOR tables.

## 10.4 Hudi SQL Syntax Reference

### 10.4.1 Constraints

Hudi 0.9.0 adds Spark SQL DDL and DML statements for using Hudi, making it easier for all users (including non-engineers or analysts) to access and operate Hudi.

#### Constraints

- You can use Spark SQL to operate Hudi on the Hudi client.
- You can use Spark SQL to operate Hudi in JDBCServer of Spark2x.
- You cannot use Spark SQL to operate Hudi on the Spark2x client.
- You cannot operate Hudi in the Hive or Hetu engine.
- The default value of **KeyGenerator** in SQL is **org.apache.hudi.keygen.ComplexKeyGenerator**. Therefore, you need to set the **KeyGenerator** value to that of SQL when data is written in DataSource mode.

- If you run the **Show Partitions** command for the first time, you need to run the **msck repair** command as prompted.
- Spark SQL does not support incremental view query.
- Spark SQL does not support ALTER CHANGE DATA TYPE.
- To write data incrementally using SQL into a COW table created using DataSource, you need to run the **ALTER TABLE *table\_name* SET SERDEPROPERTIES(primaryKey='xx',preCombineField='xx')** statement in SQL to reset two properties of the table. To write data incrementally using SQL into an MOR table created using DataSource, you need to specify a path to the one set for creating this MOR table.

## 10.4.2 DDL

### 10.4.2.1 CREATE TABLE

#### Function

This command is used to create a Hudi table by specifying the list of fields along with the table options.

#### Syntax

```
CREATE TABLE [ IF NOT EXISTS] [database_name.]table_name
[ (columnTypeList)]
USING hudi
[ COMMENT table_comment ]
[ LOCATION location_path ]
[ OPTIONS (options_list) ]
```

#### Parameter Description

Table 10-5 Parameters

Parameter	Description
database_name	Database name that contains letters, digits, and underscores (_).
table_name	Database table name that contains letters, digits, and underscores (_).
columnTypeList	List of comma-separated columns with data types. The column name contains letters, digits, and underscores (_).
using	Uses <b>hudi</b> to define and create a Hudi table.
table_comment	Description of the table.

Parameter	Description
location_path	HDFS path. If this parameter is set, the Hudi table will be created as an external table.
options_list	List of Hudi table options.

**Table 10-6** Table options

Parameter	Description
primaryKey	Name of the primary key with fields separated by commas (,).
type	Type of the table. ' <b>cow</b> ' indicates a copy-on-write (COW) table, and ' <b>mor</b> ' indicates a merge-on-read (MOR) table. If this parameter is not specified, the default value is ' <b>cow</b> '.
preCombineField	Pre-Combine field in the table.
payloadClass	Payload classes for data filtering, including default <b>OverwriteWithLatestAvroPayload</b> and multiple preset payloads, such as <b>OverwriteNonDefaultsWithLatestAvroPayload</b> , <b>DefaultHoodieRecordPayload</b> , and <b>EmptyHoodieRecordPayload</b> .

## Examples

- **Create a non-partitioned table.**

```
-- Create an internal COW table.
create table if not exists hudi_table0 (
  id int,
  name string,
  price double
) using hudi
options (
  type = 'cow',
  primaryKey = 'id'
);
-- Create an external MOR table.
create table if not exists hudi_table1 (
  id int,
  name string,
  price double,
  ts bigint
) using hudi
location '/tmp/hudi/hudi_table1'
options (
  type = 'mor',
  primaryKey = 'id,name',
  preCombineField = 'ts'
);
-- Create a table without primary keys.
create table if not exists hudi_table2(
  id int,
  name string,
  price double
```

```
) using hudi  
options (  
type = 'cow'  
);
```

- **Create a partitioned table.**

```
create table if not exists hudi_table_p0 (  
id bigint,  
name string,  
ts bigint,  
dt string,  
hh string  
) using hudi  
location '/tmp/hudi/hudi_table_p0'  
options (  
type = 'cow',  
primaryKey = 'id',  
preCombineField = 'ts'  
)  
partitioned by (dt, hh);
```

- **Create an external table for the Hudi table created using spark-shell or deltalake before Hudi 0.9.0.**

```
create table h_p1  
using hudi  
options (  
primaryKey = 'id',  
preCombineField = 'ts'  
)  
partitioned by (dt)  
location '/path/to/hudi';
```

- **Create a table and specify table options.**

```
create table if not exists h3(  
id bigint,  
name string,  
price double  
) using hudi  
options (  
primaryKey = 'id',  
type = 'mor',  
hoodie.cleaner.fileversions.retained = '20',  
hoodie.keep.max.commits = '20'  
);
```

## Precautions

Currently, Hudi does not support the CHAR, VARCHAR, TINYINT, and SMALLINT data types. You are advised to use the string or INT data type.

## System Response

The table is successfully created, and the success message is logged in the system.

### 10.4.2.2 CREATE TABLE AS SELECT

#### Function

This command is used to create a Hudi table by specifying the list of fields along with the table options.

#### Syntax

```
CREATE TABLE [ IF NOT EXISTS] [database_name.]table_name
```

**USING hudi**

*[ COMMENT table\_comment ]*

*[ LOCATION location\_path ]*

*[ OPTIONS (options\_list) ]*

*[ AS query\_statement ]*

**Parameter Description**

**Table 10-7** Parameters

Parameter	Description
database_name	Database name that contains letters, digits, and underscores (_).
table_name	Database table name that contains letters, digits, and underscores (_).
using	Uses <b>hudi</b> to define and create a Hudi table.
table_comment	Description of the table.
location_path	HDFS path. If this parameter is set, the Hudi table will be created as an external table.
options_list	List of Hudi table options.
query_statement	SELECT statement

**Examples**

- **Create a partitioned table.**

```
create table h2 using hudi
options (type = 'cow', primaryKey = 'id')
partitioned by (dt)
as
select 1 as id, 'a1' as name, 10 as price, 1000 as dt;
```
- **Create a non-partitioned table.**

```
create table h3 using hudi
as
select 1 as id, 'a1' as name, 10 as price;
```

Load data from a parquet table to the Hudi table.

```
# Create a parquet table.
create table parquet_mngd using parquet options(path='hdfs://tmp/parquet_dataset/*.parquet');
```

# Create a Hudi table by Creating a Table from Query Results (CTAS).

```
create table hudi_tbl using hudi location 'hdfs://tmp/hudi/hudi_tbl/' options (
type = 'cow',
primaryKey = 'id',
preCombineField = 'ts'
)
partitioned by (datestr) as select * from parquet_mngd;
```

## Precautions

For better data loading performance, CTAS uses **bulk insert** to write data.

## System Response

The table is successfully created, and the success message is logged in the system.

### 10.4.2.3 DROP TABLE

## Function

This command is used to delete an existing table.

## Syntax

```
DROP TABLE [IF EXISTS] [db_name.]table_name;
```

## Parameter Description

**Table 10-8** Parameters

Parameter	Description
db_name	Database name. If this parameter is not specified, the current database is selected.
table_name	Name of the table to be deleted.

## Precautions

In this command, **IF EXISTS** and **db\_name** are optional.

## Examples

```
DROP TABLE IF EXISTS hudidb.h1;
```

## System Response

The table will be deleted.

### 10.4.2.4 SHOW TABLE

## Function

This command is used to display all tables in current database or all tables in a specific database.

## Syntax

```
SHOW TABLES [IN db_name];
```

## Parameter Description

**Table 10-9** Parameters

Parameter	Description
IN db_name	Name of the specific database whose tables need to be all displayed.

## Precautions

**IN db\_Name** is optional. It is required only when you need to display all tables of a specific database.

## Examples

```
SHOW TABLES IN hudidb;
```

## System Response

All tables are listed.

### 10.4.2.5 ALTER RENAME TABLE

## Function

This command is used to rename an existing table.

## Syntax

```
ALTER TABLE oldTableName RENAME TO newTableName
```

## Parameter Description

**Table 10-10** Parameters

Parameter	Description
oldTableName	Current name of the table
new_table_name	New name of the table

## Examples

```
alter table h0 rename to h0_1;
```

## System Response

The table name is changed. You can run the **SHOW TABLES** command to display the new table name.

### 10.4.2.6 ALTER ADD COLUMNS

#### Function

This command is used to add columns to an existing table.

#### Syntax

```
ALTER TABLE tableIdentifier ADD COLUMNS (colAndType (,colAndType)*)
```

#### Parameter Description

**Table 10-11** Parameters

Parameter	Description
<i>tableIdentifier</i>	Table name.
<i>colAndType</i>	Name of a comma-separated column with data types. A column name consists of letters, digits, and underscores (_).

#### Examples

```
alter table h0_1 add columns(ext0 string);
```

## System Response

The columns are added to the table. You can run the **DESCRIBE** command to display the columns.

### 10.4.2.7 TRUNCATE TABLE

#### Function

This command is used to clear all data in a specific table.

#### Syntax

```
TRUNCATE TABLE tableIdentifier
```

## Parameter Description

**Table 10-12** Parameters

Parameter	Description
tableIdentifier	Table name.

## Examples

```
truncate table h0_1;
```

## System Response

Data in the table is cleared. You can run the **QUERY** statement to check whether data in the table has been deleted.

## 10.4.3 DML

### 10.4.3.1 INSERT INTO

## Function

This command is used to insert the output of the **SELECT** statement to a Hudi table.

## Syntax

```
INSERT INTO tableIdentifier select query;
```

## Parameter Description

**Table 10-13** Parameters

Parameter	Description
tableIdentifier	Name of the Hudi table.
select query	SELECT statement.

## Precautions

- Insert mode: Hudi supports three insert modes for tables with primary keys. You can set a parameter to specify the insert mode. The default value is **upsert**.
  - a. In strict mode, the INSERT statement retains the primary key constraint of COW tables and is not allowed to insert duplicate records. If a record already exists during data insertion, HoodieDuplicateKeyException is

thrown for COW tables. For MOR tables, the behavior in this mode is the same as that in upsert mode.

- b. In non-strict mode, records are inserted to primary key tables.
- c. In upsert mode, duplicate values in the primary key table are updated.
- You can set **hoodie.sql.bulk.insert.enable** to **true** to enable the bulk insert statement as the write mode of the insert statement. Bulkinsert cannot be performed on the primary key table.

## Examples

```
insert into h0 select 1, 'a1', 20;

-- insert static partition
insert into h_p0 partition(dt = '2021-01-02') select 1, 'a1';

-- insert dynamic partition
insert into h_p0 select 1, 'a1', dt;

-- insert dynamic partition
insert into h_p1 select 1 as id, 'a1', '2021-01-03' as dt, '19' as hh;

-- insert overwrite table
insert overwrite table h0 select 1, 'a1', 20;

-- insert overwrite table with static partition
insert overwrite h_p0 partition(dt = '2021-01-02') select 1, 'a1';

-- insert overwrite table with dynamic partition
insert overwrite table h_p1 select 2 as id, 'a2', '2021-01-03' as dt, '19' as hh;
```

## System Response

You can view the result in driver logs.

### 10.4.3.2 MERGE INTO

#### Function

This command is used to query another table based on the join condition of a table or subquery. If **UPDATE** or **DELETE** is executed for the table matching the join condition, and **INSERT** is executed if the join condition is not met. This command completes the synchronization requiring only one full table scan, delivering higher efficiency than **INSERT** plus **UPDATE**.

#### Syntax

```
MERGE INTO tableIdentifier AS target_alias
USING (sub_query | tableIdentifier) AS source_alias
ON <merge_condition>
[ WHEN MATCHED [ AND <condition> ] THEN <matched_action> ]
[ WHEN MATCHED [ AND <condition> ] THEN <matched_action> ]
[ WHEN NOT MATCHED [ AND <condition> ] THEN <not_matched_action> ]
```

```

<merge_condition> =A equal bool condition
<matched_action> =
DELETE |
UPDATE SET * |
UPDATE SET column1 = expression1 [, column2 = expression2 ...]
<not_matched_action> =
INSERT * |
INSERT (column1 [, column2 ...]) VALUES (value1 [, value2 ...])
    
```

## Parameter Description

**Table 10-14** Parameters

Parameter	Description
tableIdentifier	Name of the Hudi table.
target_alias	Alias of the target table.
sub_query	Subquery.
source_alias	Alias of the source table or source expression.
merge_condition	Condition for associating the source table or expression with the target table.
condition	Filtering condition. This parameter is optional.
matched_action	DELETE or UPDATE operation to be performed when conditions are met.
not_matched_action	INSERT operation to be performed when conditions are not met.

## Precautions

1. The merge-on condition supports only primary key columns currently.
2. Currently, only some fields in COW tables can be updated. The following is an example:

```

merge into h0 using s0
on h0.id = s0.id
when matched then update set price = s0.price * 2
    
```
3. Currently, only when COW tables are updated, fields in the target table can appear in the right of the UPDATE expression. The following is an example:

```

merge into h0 using s0
on h0.id = s0.id
when matched then update set id = s0.id,
name = h0.name,
price = s0.price + h0.price
    
```

## Examples

```
merge into h0 as target
using (
select id, name, price, flag from s
) source
on target.id = source.id
when matched then update set *
when not matched then insert *;

merge into h0
using (
select id, name, price, flag from s
) source
on h0.id = source.id
when matched and flag != 'delete' then update set id = source.id, name = source.name, price = source.price
* 2
when matched and flag = 'delete' then delete
when not matched then insert (id,name,price) values(source.id, source.name, source.price);

merge into t0 as target
using s0 source
on target.id = source.id
when matched then update set *
when not matched then insert *;
```

## System Response

You can view the result in driver logs or on the client.

### 10.4.3.3 UPDATE

## Function

This command is used to update the Hudi table based on the column expression and optional filtering conditions.

## Syntax

```
UPDATE tableIdentifier SET column = EXPRESSION(column = EXPRESSION)
[ WHERE boolExpression ]
```

## Parameter Description

**Table 10-15** Parameters

Parameter	Description
tableIdentifier	Name of the Hudi table to be updated.
column	Target column to be updated.
EXPRESSION	Expression of the source table column to be updated in the target table.
boolExpression	Filtering condition expression.

## Examples

```
update h0 set price = price + 20 where id = 1;  
update h0 set price = price *2, name = 'a2' where id = 2;
```

## System Response

You can view the result in driver logs or on the client.

### 10.4.3.4 DELETE

## Function

This command is used to delete records from a Hudi table.

## Syntax

```
DELETE from tableIdentifier [ WHERE boolExpression ]
```

## Parameter Description

**Table 10-16** Parameters

Parameter	Description
tableIdentifier	Name of the Hudi table to delete records.
boolExpression	Filtering conditions for deleting records.

## Examples

- Example 1:  
delete from h0 where column1 = 'country';
- Example 2:  
delete from h0 where column1 IN ('country1', 'country2');
- Example 3:  
delete from h0 where column1 IN (select column11 from sourceTable2);
- Example 4:  
delete from h0 where column1 IN (select column11 from sourceTable2 where column1 = 'USA');
- Example 5:  
delete from h0;

## System Response

You can view the result in driver logs or on the client.

### 10.4.3.5 COMPACTION

## Function

This command is used to convert row-based log files in MOR tables into column-based data files in parquet tables to accelerate record search.

## Syntax

**SCHEDULE COMPACTION** on *tableIdentifier* |tablelocation;

**SHOW COMPACTION** on *tableIdentifier* |tablelocation;

**RUN COMPACTION** on *tableIdentifier* |tablelocation [at instant-time];

## Parameter Description

**Table 10-17** Parameters

Parameter	Description
tableIdentifier	Name of the Hudi table to convert log files.
tablelocation	The storage path of the Hudi table.
instant-time	Time to run the command. You can run the <b>show compaction</b> command to view the <b>instant-time</b> value.

## Examples

```
schedule compaction on h1;  
show compaction on h1;  
run compaction on h1 at 20210915170758;  
  
schedule compaction on '/tmp/hudi/h1';  
run compaction on '/tmp/hudi/h1';
```

## Precautions

You need to set **hoodie.payload.ordering.field** to the value of **preCombineField** when you use the Hudi CLI or API to trigger compaction for the Hudi table created by SQL.

## System Response

You can view the result in driver logs or on the client.

### 10.4.3.6 SET/RESET

## Function

This command is used to dynamically add, update, display, or reset Hudi parameters without restarting the driver.

## Syntax

- Add or update a parameter value:  
**SET** *parameter\_name=parameter\_value*  
This command is used to add or update the value of **parameter\_name**.
- Display a parameter value:

**SET** *parameter\_name*

This command is used to display the value of **parameter\_name**.

- Display session parameters:

**SET**

This command is used to display all supported session parameters.

- Display session parameters along with usage details:

**SET -v**

This command is used to display all supported session parameters and their usage details.

- Reset parameter values:

**RESET**

This command is used to reset all session parameters.

## Parameter Description

**Table 10-18** Parameters

Parameter	Description
parameter_name	Name of the parameter to be dynamically added, updated, or displayed.
parameter_value	New value to be set for <b>parameter_name</b> .

## Precautions

The following table lists the properties to be used in the **SET** or **RESET** commands.

**Table 10-19** Properties

Property	Description
hoodie.insert.shuffle.parallelism	Degree of parallelism (DOP) of Spark shuffle for writing data in insert mode.
hoodie.upsert.shuffle.parallelism	DOP of Spark shuffle for writing data in upsert mode.
hoodie.delete.shuffle.parallelism	DOP of Spark shuffle for deleting data in delete mode.
hoodie.sql.insert.mode	Insert mode. The value can be strict, non-strict, or upsert.
hoodie.sql.bulk.insert.enable	Whether to enable bulk insert.

Property	Description
spark.sql.hive.convertMetastoreParquet	Converts the parquet table into a data source table for reading. If the provider of Hudi is Hive and Spark SQL or Spark Beeline is used to read data, set this parameter to <b>false</b> .

## Examples

- Add or Update command:  
set hoodie.insert.shuffle.parallelism = 100;  
set hoodie.upsert.shuffle.parallelism = 100;  
set hoodie.delete.shuffle.parallelism = 100;
- Reset command:  
RESET

## System Response

- You can view the success result in driver logs.
- You can view the failure result on the UI.

# 10.5 Common Issues About Hudi

## 10.5.1 Data Write

### 10.5.1.1 Parquet/Avro schema Is Reported When Updated Data Is Written

#### Question

The following error is reported when data is written:

```
org.apache.parquet.io.InvalidRecordException: Parquet/Avro schema mismatch: Avro field 'col1' not found
```

#### Answer

You are advised to evolve schemas in backward compatible mode while using Hudi. This error usually occurs when you delete some columns, such as **col1**, in backward incompatible mode and then update **col1** written with the old schema in the Parquet file. In this case, the Parquet file attempts to search for all the current fields in the input record, if **col1** does not exist, the preceding exception is thrown.

To solve this problem, create an uber schema using all the schema versions evolved and use this uber schema as the target schema. You can obtain a schema from Hive MetaStore and merge it with the current schema.

### 10.5.1.2 UnsupportedOperationException Is Reported When Updated Data Is Written

#### Question

The following error is reported when data is written:

```
java.lang.UnsupportedOperationException: org.apache.parquet.avro.AvroConverters$FieldIntegerConverter
```

#### Answer

This error will occur again because schema evolutions are in non-backwards compatible mode. Basically, there is some update U for a record R which is already written to the Hudi dataset in the Parquet file. R contains field F which includes certain data type, that is long. U has the same field F with the int data type. Parquet FS does not support incompatible data type conversions.

For such errors, perform valid data type conversions in the data source where you collect data.

### 10.5.1.3 SchemaCompatabilityException Is Reported When Updated Data Is Written

#### Question

The following error is reported when data is written:

```
org.apache.hudi.exception.SchemaCompatabilityException: Unable to validate the rewritten record <record> against schema <schema>at org.apache.hudi.common.util.HoodieAvroUtils.rewrite(HoodieAvroUtils.java:215)
```

#### Answer

This error may occur if a schema contains some **non-nullable** field whose value is not present or is null.

You are advised to evolve schemas in backward compatible mode. Essentially, this means either you need to set each newly added field to null or to default values. In Hudi 0.5.1 and later versions, the troubleshooting is invalid if fields rely on default values.

### 10.5.1.4 What Should I Do If Hudi Consumes Much Space in a Temporary Folder During Upsert?

#### Question

Hudi consumes much space in a temporary folder during upsert.

#### Answer

Hudi will spill part of input data to disk if the maximum memory for merge is reached when much input data is upserted.

If the memory is sufficient, increase the memory of the Spark executor and add the `hoodie.memory.merge.fraction` option, for example, `option("hoodie.memory.merge.fraction", "0.8")`.

## 10.5.2 Data Collection

### 10.5.2.1 IllegalArgumentException Is Reported When Kafka Is Used to Collect Data

#### Question

The error "org.apache.kafka.common.KafkaException: Failed to construct kafka consumer" is reported in the **main** thread, and the following error is reported.

```
java.lang.IllegalArgumentException: Could not find a 'KafkaClient' entry in the JAAS configuration. System property 'java.security.auth.login.config' is not set
```

#### Answer

This error may occur when you try to collect data from the Kafka source with SSL enabled and the installation program cannot read the `jaas.conf` file and its properties.

To solve this problem, pass the required property as part of the command submitted through Spark. Example: `--files jaas.conf,failed_tables.json --conf 'spark.driver.extraJavaOptions=-Djava.security.auth.login.config=jaas.conf' --conf 'spark.executor.extraJavaOptions=-Djava.security.auth.login.config=jaas.conf'`

### 10.5.2.2 HoodieException Is Reported When Data Is Collected

#### Question

The following error is reported when data is collected:

```
com.uber.hoodie.exception.HoodieException: created_at(Part -created_at) field not found in record.  
Acceptable fields were :[col1, col2, col3, id, name, dob, created_at, updated_at]
```

#### Answer

This error usually occurs when a field marked as recordKey or partitionKey is not present in the input record. Cross verify the input record.

### 10.5.2.3 HoodieKeyException Is Reported When Data Is Collected

#### Question

Is it possible to use a nullable field that contains null records as a primary key when creating a Hudi table?

#### Answer

No. HoodieKeyException will be thrown.

```
Caused by: org.apache.hudi.exception.HoodieKeyException: recordKey value: "null" for field: "name" cannot be null or empty.  
at org.apache.hudi.keygen.SimpleKeyGenerator.getKey(SimpleKeyGenerator.java:58)  
at org.apache.hudi.HoodieSparkSqlWriter$$anonfun$1.apply(HoodieSparkSqlWriter.scala:104)  
at org.apache.hudi.HoodieSparkSqlWriter$$anonfun$1.apply(HoodieSparkSqlWriter.scala:100)
```

## 10.5.3 Hive Synchronization

### 10.5.3.1 SQLException Is Reported During Hive Data Synchronization

#### Question

The following error is reported during Hive data synchronization:

```
Caused by: java.sql.SQLException: Error while processing statement: FAILED: Execution Error, return code 1 from org.apache.hadoop.hive.ql.exec.DDLTask. Unable to alter table. The following columns have types incompatible with the existing columns in their respective positions :  
__col1,__col2
```

#### Answer

This error usually occurs when you try to add a new column to an existing Hive table using the **HiveSyncTool.java** class. Databases usually do not allow the modification of a column data type from a higher order to lower order or cases where the data types may conflict with the data that is already stored or will be stored in the table. To solve this problem,

set **hive.metastore.disallow.incompatible.col.type.changes** to **false**.

### 10.5.3.2 HoodieHiveSyncException Is Reported During Hive Data Synchronization

#### Question

The following error is reported during Hive data synchronization:

```
com.uber.hoodie.hive.HoodieHiveSyncException: Could not convert field Type from <type1> to <type2> for field col1
```

#### Answer

This error occurs because HiveSyncTool currently supports only few compatible data type conversions. The exception is thrown if any other incompatible changes are made.

Check the data type evolution for the related field and verify if it indeed can be considered as a valid data type conversion based on the Hudi code base.

### 10.5.3.3 SemanticException Is Reported During Hive Data Synchronization

#### Question

The following error is reported during Hive data synchronization:

```
org.apache.hadoop.hive.ql.parse.SemanticException: Database does not exist: test_db
```

## Answer

This error usually occurs when Hive synchronization is performed on the Hudi dataset but the configured **hive\_sync** database does not exist.

Create the corresponding database on your Hive cluster and try again.

# 11 Using Hue

---

## 11.1 Using Hue from Scratch

Hue aggregates interfaces which interact with most Apache Hadoop components and enables you to use Hadoop components with ease on a web UI. You can operate components such as HDFS, Hive, HBase, Yarn, MapReduce, Oozie and Spark SQL on the Hue web UI.

### Prerequisites

You have installed Hue, and the Kerberos authentication cluster is in the running state.

### Procedure

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** In the navigation tree on the left, click the editor icon  and choose **Hive**.

**Step 3** Select a Hive database from the **Database** drop-down list box. The default database is **default**.

The system displays all available tables. You can enter a keyword of the table name to search for the desired table.

**Step 4** Click the desired table name. All columns in the table are displayed.

**Step 5** Enter the HiveQL statements in the area for editing.

```
create table hue_table(id int,name string,company string) row format  
delimited fields terminated by ',' stored as textfile;
```

**Step 6** Click  to execute the HiveQL statements.

**Step 7** In the command text box, enter **show tables;** and click . Check whether the **hue\_table** table created in [Step 5](#) exists in the **Result**.

----End

## 11.2 Accessing the Hue Web UI

### Scenario

After Hue is installed in an MRS cluster, users can use Hadoop-related components on the Hue web UI.

This section describes how to open the Hue web UI on the MRS cluster.

#### NOTE

To access the Hue web UI, you are advised to use a browser that is compatible with the Hue WebUI, for example, Google Chrome 50. The Internet Explorer may be incompatible with the Hue web UI.

### Impact on the System

Site trust must be added to the browser when you access Manager and Hue web UI for the first time. Otherwise, the Hue web UI cannot be accessed.

### Prerequisites

When Kerberos authentication is enabled, the MRS cluster administrator has assigned the permission for using Hive to the user. For details, see . For example, create a human-machine user named **hueuser**, add the user to user groups **hive** (the primary group), **hadoop**, **supergroup**, and **System\_administrator**, and assign the **System\_administrator** role.

This user is used to log in to Manager.

### Procedure

**Step 1** Log in to the service page.

Log in to FusionInsight Manager (for details, see [Accessing FusionInsight Manager](#)) and choose **Cluster > Services > Hue**.

**Step 2** On the right of **Hue WebUI**, click the link to open the Hue web UI.

Hue WebUI provides the following functions:

- Click  to execute query statements of Hive and SparkSQL as well as Notebook code. Make sure that Hive and Spark2x have been installed in the MRS cluster before this operation.
- Click  to submit workflow tasks, scheduled tasks, and bundle tasks.
- Click  to view, import, and export tasks on the Hue web UI, such as workflow tasks, scheduled tasks, and bundle tasks.
- Click  to manage metadata in Hive and SparkSQL. Make sure that Hive and Spark2x have been installed in the MRS cluster before this operation.

- Click  to view the directories and files in HDFS. Make sure that HDFS has been installed in the MRS cluster before this operation.
- Click  to view all jobs in the MRS cluster. Make sure that Yarn has been installed in the MRS cluster before this operation.
- Use  to create or query HBase tables. Make sure that the HBase component has been installed in the MRS cluster and the Thrift1Server instance has been added before this operation.
- Use  to import data that is in the CSV or TXT format.

 **NOTE**

- When you log in to the Hue web UI as user **hueuser** for the first time, you need to change the password.
- After obtaining the URL for accessing the Hue web UI, you can give the URL to other users who cannot access MRS Manager for accessing the Hue web UI.
- If you perform operations on the Hue WebUI only but not on Manager, you must enter the password of the current login user when accessing Manager again.

----End

## 11.3 Hue Common Parameters

### Page Access

Go to the **All Configurations** page of the Hue service by referring to [Modifying Cluster Service Configuration Parameters](#).

### Parameter Description

For details about Hue common parameters, see [Table 11-1](#).

**Table 11-1** Hue common parameters

Configuration	Description	Default Value	Value Range
HANDLER_ACCESSLOG_LEVEL	Hue access log level.	DEBUG	<ul style="list-style-type: none"> <li>• ERROR</li> <li>• WARN</li> <li>• INFO</li> <li>• DEBUG</li> </ul>
HANDLER_AUDITLOG_LEVEL	Hue audit log level.	DEBUG	<ul style="list-style-type: none"> <li>• ERROR</li> <li>• WARN</li> <li>• INFO</li> <li>• DEBUG</li> </ul>

Configuration	Description	Default Value	Value Range
HANDLER_ERRORLOG_LEVEL	Hue error log level.	ERROR	<ul style="list-style-type: none"> <li>• ERROR</li> <li>• WARN</li> <li>• INFO</li> <li>• DEBUG</li> </ul>
HANDLER_LOGFILE_LEVEL	Hue run log level.	INFO	<ul style="list-style-type: none"> <li>• ERROR</li> <li>• WARN</li> <li>• INFO</li> <li>• DEBUG</li> </ul>
HANDLER_LOGFILE_MAXBACKUPINDEX	Maximum number of Hue log files.	20	1 to 999
HANDLER_LOGFILE_SIZE	Maximum size of a Hue log file.	5 MB	-

For details about Hue custom parameters, see [Table 11-2](#).

**Table 11-2** Hue custom parameters

Configuration	Description
dfs.customized.configs	Custom configuration item added to the global configuration file <b>hdfs-site.xml</b> .
hbase.customized.configs	Custom configuration item added to the global configuration file <b>hbase-site.xml</b> .
hive.customized.configs	Custom configuration item added to the global configuration file <b>hive-site.xml</b> .

## 11.4 Using HiveQL Editor on the Hue Web UI

### Scenario

Users can use the Hue web UI to execute HiveQL statements in an MRS cluster.

### Access Editor

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** In the navigation tree on the left, click  and choose **Hive**. The **Hive** page is displayed.

**Hive** supports the following functions:

- Executes and manages HiveQL statements.
- Views the HiveQL statements saved by the current user in **Saved Queries**.
- Queries HiveQL statements executed by the current user in **Query History**.

----End

## Executing HiveQL Statements

**Step 1** Select a Hive database from the **Database** drop-down list box. The default database is **default**.

The system displays all available tables. You can enter a keyword of the table name to search for the desired table.

**Step 2** Click the desired table name. All columns in the table are displayed.

Move the cursor to the row where the table or column is located and click . Column details are displayed.

**Step 3** Enter the query statements in the area for editing HiveQL statements.

**Step 4** Click  to execute the HiveQL statements.

### NOTE

- If you want to use the entered HiveQL statements again, click  to save them.
- Advanced query configuration:

Click  in the upper right corner to configure information such as files, functions, and settings.

- Viewing the information of shortcut keys:

Click  in the upper right corner to view the syntax and keyboard shortcut information.

- To delete an entered HiveQL statement, click the triangle next to  and select **Clear**.

- Viewing history:

Click **Query History** to view the HiveQL running status. You can view the history of all the statements or only the saved statements. If many historical records exist, you can enter keywords in the text box to search for desired records.

----End

## Viewing Execution Results

**Step 1** View the execution results below the execution area on **Hive**. The **Query History** tab page is displayed by default.

**Step 2** Click a result to view the execution result of the executed statement.

----End

## Managing Query Statements

**Step 1** Click **Saved Queries**.

**Step 2** Click a saved statement. The system automatically adds the statement to the editing area.

----End

## Modifying the Session Configuration of the Hue Editor

**Step 1** On the editor page, click .

**Step 2** Click  on the right of **Files**, and then click  to select files.

You can click  next to **Files** to add a file resource.

**Step 3** In the **Functions**  area, enter a user-defined name and the class name of the function.

You can click  next to **Functions** to add a customized function.

**Step 4** In the **Settings**  area, enter the Hive parameter name in the **Key**, and value in **Value**. The current Hive session connects to Hive based on the customized configuration.

You can click  to add a parameter.

----End

# 11.5 Using the Metadata Browser on the Hue Web UI

## Scenario

Users can use the Hue web UI to manage Hive metadata in an MRS cluster.

## Using Metadata Manager

Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

- Viewing metadata of Hive tables

Click  in the navigation tree on the left and click a table name. The metadata of the Hive table is displayed.

- Managing metadata of Hive tables

On the metadata information page of a Hive table:

- Click **Import** in the upper right corner to import data.

- Click **Overview** to view the location of the table file in the **PROPERTIES** field.
- Click **Sample** to browse data.
- Managing Hive metadata tables
  - Click **+** in the left list to create a table based on the uploaded file in the database. You can also manually create a table.

---

 **CAUTION**

The Hue page is used to view and analyze data such as files and tables. Do not perform high-risk management operations such as deleting objects on the page. If an operation is required, you are advised to perform the operation on each component after confirming that the operation has no impact on services. For example, you can use the HDFS client to perform operations on HDFS files and use the Hive client to perform operations on Hive tables.

---

## 11.6 Using File Browser on the Hue Web UI

### Scenario

Users can use the Hue web UI to manage files in HDFS.

---

 **CAUTION**

The Hue page is used to view and analyze data such as files and tables. Do not perform high-risk management operations such as deleting objects on the page. If an operation is required, you are advised to perform the operation on each component after confirming that the operation has no impact on services. For example, you can use the HDFS client to perform operations on HDFS files and use the Hive client to perform operations on Hive tables.

---

### Accessing File Browser

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** In the left navigation pane, click . The **File Browser** page is displayed.

By default, the homepage of **File Browser** is the home directory of the current login user. On the displayed page, the following information about subdirectories for files in the directory is displayed:

**Table 11-3** HDFS file attributes

Attribute	Description
Name	Name of a directory or file

Attribute	Description
Size	File size
User	Owner of a directory or file
Group	Group of a directory or file
Permission	Permission of a directory or file
Date	Time when a directory or file is created

**Step 3** In the search box, enter a keyword. The system automatically searches directories or files in the current directory.

**Step 4** Clear the search criteria. The system displays all directories or files.

----End

## Performing Actions

**Step 1** On the **File Browser** page, select one or more directories or files.

**Step 2** Click **Actions**. On the menu that is displayed, select an operation.

- **Rename**: renames a directory or file.
- **Move**: moves a file. In **Move to**, select a new directory and click **Move**.
- **Copy**: copies the selected files or directories.
- **Change permissions**: changes permission to access the selected directory or file.
  - You can grant the owner, the group, or other users with the **Read**, **Write**, and **Execute** permissions.
  - **Sticky**: indicates that only HDFS administrators, directory owners, and file owners can move files in the directory.
  - **Recursive**: indicates that permission is granted to subdirectories recursively.
- **Storage policies**: indicates the policies for storing files or directories in HDFS.
- **Summary**: indicates that the HDFS storage information about the selected file or directory can be viewed.

----End

## Uploading User Files

**Step 1** On the **File Browser** page, click **Upload**.

**Step 2** In the displayed dialog box for uploading files, click **Select files** or drag the file to the dialog box.

----End

## Creating a New File or Directory

**Step 1** On the **File Browser** page, click **New**.

**Step 2** Select an operation.

- **File:** creates a file. Enter a file name and click **Create**.
- **Directory:** creates a directory. Enter a directory name and click **Create**.

----End

## Storage Policy Definition and Usage

### NOTE

If the value of Hue parameter `fs_defaultFS` is set to `viewfs://ClusterX`, the big data storage policy cannot be enabled.

**Step 1** Log in to FusionInsight Manager.

**Step 2** On FusionInsight Manager, choose **System > Permission > Manage Role > Create Role**.

1. Set **Role Name**.
2. In the **Configure Resource Permission** area, choose *Name of the desired cluster* > **Hue**, select **Storage Policy Admin**, and click **OK**. Then, grant the permission to the role.

**Step 3** Choose **System > Permission > User Group > Create User Group**. Set **Group Name** and click **Select and Add Role** next to **Role**. On the displayed page, select the role created in [Step 2](#) and click **OK** to add the role to the group.

**Step 4** Choose **System > Permission > User > Create**.

1. **Username:** Enter the name of the user to be added.
2. Set **User Type** to **Human-machine**.
3. Set **Password** and **Confirm Password** for logging in to the Hue web UI.
4. Click **Add** next to **User Group**. On the page that is displayed, select the user group created in [Step 3](#), **supergroup**, **hadoop**, and **hive**, and click **OK**.
5. Set **Primary Group** to **hive**.
6. Click **Add** on the right of **Role**. On the page that is displayed, select the role created in [Step 2](#) and **System\_administrator** role, and click **OK**.
7. Click **OK**. The user is added successfully.

**Step 5** Access the Hue web UI as the created user. For details, see [Accessing the Hue Web UI](#).

**Step 6** In the left navigation tree, click . The **File Browser** page is displayed.

**Step 7** Select the check box of the directory and click **Actions** on the top of the page. Choose **Storage policies**.

**Step 8** In the dialog box that is displayed, set a new storage policy and click **OK**.

----End

## 11.7 Using Job Browser on the Hue Web UI

### Scenario

Users can use the Hue web UI to query all jobs in an MRS cluster.

### Accessing Job Browser

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** Click .

View the jobs in the current cluster.

#### NOTE

The number on **Job Browser** indicates the total number of jobs in the cluster.

**Job Browser** displays the following job information:

**Table 11-4** MRS job attributes

Attribute	Description
Name	Job name
User	User who starts a job
Type	Job type
Status	Job status, including <b>Succeeded</b> , <b>Running</b> , and <b>Failed</b> .
Progress	Job running progress
Group	Group to which a job belongs
Start	Start time of a job
Duration	Job running duration
Id	Job ID, which is generated by the system automatically.

#### NOTE

If the MRS cluster has Spark, the **Spark-JDBCServer** job is started by default to execute tasks.

----End

### Searching for Jobs

**Step 1** In the search box of **Job Browser**, enter the specified character. The system automatically searches for all jobs that contain the keyword by ID, name, or user.

**Step 2** Clear the search criteria. The system displays all jobs.

----End

## Querying Job Details

**Step 1** In the job list on the **Job Browser** page, click the row that contains the desired job to view details.

**Step 2** On the **Metadata** tab page, you can view the metadata of the job.

 **NOTE**

You can click **Log** to open the job running log.

----End

# 11.8 Using HBase on the Hue Web UI

## Scenario

You can use Hue to create or query HBase tables in a cluster and run tasks on the Hue web UI.

## Accessing Job Browser

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** Click HBase . The **HBase Browser** page is displayed.

----End

## Creating an HBase Table

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** Click HBase . The **HBase Browser** page is displayed.

**Step 3** Click **New Table** on the right, enter the table name and column family parameters, and click **Submit**.

----End

## Querying Data in an HBase Table

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** Click HBase . The **HBase Browser** page is displayed.

**Step 3** Click the HBase table to be queried. Then, click the key value next to search box in the upper part, and query the HBase table.

----End

## 11.9 Typical Scenarios

### 11.9.1 HDFS on Hue

Hue provides the file browser function for users to use HDFS in GUI mode.

---

**CAUTION**

The Hue page is used to view and analyze data such as files and tables. Do not perform high-risk management operations such as deleting objects on the page. If an operation is required, you are advised to perform the operation on each component after confirming that the operation has no impact on services. For example, you can use the HDFS client to perform operations on HDFS files and use the Hive client to perform operations on Hive tables.

---

#### How to Use File Browser

Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).



Click . The **File Browser** page is displayed. You can perform the following operations:

- Viewing files or directories  
By default, the directory and files in the directory of the login user are displayed. You can view **Name**, **Size**, **User**, **Group**, **Permission**, and **Date**.  
Click a file name to view the text information or binary data in the text file. The file content can be edited.  
If there are a large number of files and directories, you can enter keywords in the search text box to search for specific files or directories.
- Creating files or directories  
Click **New** in the upper right corner. Choose **File** to create the file. Choose **Directory** to create a directory.
- Managing files or directories  
Select the check box of a file or director, and click **Actions**. In the displayed menu, choose **Rename**, **Move**, **Copy**, and **Change permissions** to rename, move, copy, or change the file or directory permissions.
- Uploading files  
Click **Upload** in the upper right corner and click **Select files** or drag the file to the window.

#### How to Use Storage Policies

 **NOTE**

If the value of Hue parameter **fs\_defaultFS** is set to **viewfs://ClusterX**, the big data storage policy cannot be enabled.

**Storage policies on the Hue web UI are classified into the following two types:**

- **Static Storage Policies**
  - a. **Current storage policy**  
According to the access frequency and importance of documents in HDFS, specify a storage policy for an HDFS directory, such as ONE\_SSD or ALL\_SSD. The files in this directory can be migrated to the storage media.
  - b. **Current EC policy**  
Specify EC policies for HDFS directories, such as RS-10-4-1024k and RS-3-2-1024k. .
- **Dynamic Storage Policies**  
Set rules for an HDFS directory. The system can automatically change the storage policy, the number of file copies, migrate the file directory.  
Before configuring a dynamic storage policy on the Hue WebUI, you must set the CRON expressions for cold and hot data migration and start automatic cold and hot data migration on Manager.

Operations:

Change the value of **dfs.auto.data.mover.cron.expression** for NameNode of the HDFS service. For details, see [Modifying Cluster Service Configuration Parameters](#).

 **NOTE**

- **dfs.auto.data.mover.cron.expression** indicates the CRON expression for checking whether HDFS data meets the dynamic storage policy rule. It is used to control the start time of data migration. The default value is **0 \* \* \* \***, indicating that the detection is performed on the hour. When the dynamic storage policy rule is met, cold and hot data migration tasks are executed on the hour.
- The default value of **dfs.auto.data.mover.enable** is **false**. This parameter value is valid only when **dfs.auto.data.mover.enable** is set to **true**.

**Table 11-5** describes the expression for modifying this parameter. \* indicates consecutive time segments.

**Table 11-5** Parameters in the execution expression

Column	Description
1	Minute. The value ranges from 0 to 59.
2	Hour. The value ranges from 0 to 23.
3	Date. The value ranges from 1 to 31.
4	Month. The value ranges from 1 to 12.
5	Week. The value ranges from 0 to 6. 0 indicates Sunday.

**To set storage policies on the web UI, perform the following operations:**

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).

**Step 2** On FusionInsight Manager, choose **System > Permission > Role > Create Role**.

1. Set **Role Name**.
2. In the **Configure Resource Permission** area, choose *Name of the desired cluster* > **Hue**, select **Storage Policy Admin**, and click **OK**. Then, grant the permission to the role.

**Step 3** Choose **System > Permission > User Group > Create User Group**. Set **Group Name**, and click **Add** next to **Role**. On the displayed page, select the created role, click **OK** to add the role to the group, and click **OK**.

**Step 4** Choose **System > Permission > User > Create**.

1. **Username**: Enter the name of the user to be added.
2. Set **User Type** to **Human-machine**.
3. Set **Password** and **Confirm Password** for logging in to the Hue web UI.
4. Click **Add** next to **User Group**. On the page that is displayed, select the created user group in [Step 3](#), **supergroup**, **hadoop**, and **hive**, and click **OK**.
5. Set **Primary Group** to **hive**.
6. Click **Add** next to **Role**. On the page that is displayed, select the created role in [Step 2](#) and the **System\_administrator** role, and click **OK**.
7. Click **OK**. The user is added successfully.

**Step 5** Access the Hue web UI as the created user. For details, see [Accessing the Hue Web UI](#).

**Step 6** In the left navigation pane, click . The **File Browser** page is displayed.

**Step 7** Select the check box of a directory and choose **Action** on the top of the page. Choose **Storage policies**.

**Step 8** In the dialog box that is displayed, set a new storage policy and click **OK**.

- On the **Static Storage Policy** tab page, select a policy from the **New EC Policy** drop-down list box and click **Save**.
- On the **Dynamic Storage Policy** tab page, you can create, delete, or modify a dynamic storage policy. [Table 11-6](#) describes the parameters.

**Table 11-6** Parameters of the dynamic storage policy

Category	Parameter	Description
Rule	Last Access to File	Indicates the time when the file is last accessed.
	Last File Modification	Indicates the time when the file is last modified.
Operation	Change Number of Copies	Indicates the number of file copies.

Category	Parameter	Description
	Modify Storage Policy	Indicates that you can modify storage policies to the following: HOT, WARM, COLD, ONE_SSD, and ALL_SSD.
	Move to Directory	Indicates that you can move the file to another directory.

 **NOTE**

- You need to consider whether the rules conflict with each other and whether the rules damage the system when setting rules.
- When a directory is configured with multiple rules and operations, the rule that is triggered first is located at the bottom of the rule/operation list, and the rules that are triggered later are placed from bottom to top to prevent repeated operations.
- The system checks whether the files under the directory specified by the dynamic storage policy meet the rules on an hourly basis. If the files meet the rules, the execution is triggered. Execution logs are recorded in the `/var/log/Bigdata/hdfs/nn/hadoop.log` directory of the active NameNode.

----End

## Typical Scenarios

On the Hue page, view and edit HDFS files in text or binary mode as follows:

### Viewing a File

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** In the left navigation pane, click . The **File Browser** page is displayed.

**Step 3** Click the name of the file to be viewed.

**Step 4** Click **View as binary** to switch from the text mode to the binary mode. Click **View as file** to switch from the binary mode to the text mode.

### Editing a file

**Step 5** Click **Edit File**. The file content can be edited.

**Step 6** Click **Save** or **Save As** to save the file.

----End

## 11.9.2 Hive on Hue

Hue provides the Hive GUI management function so that users can query Hive data in GUI mode.

### How to Use Query Editor

Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

In the navigation tree on the left, click  and choose **Hive**. The **Hive** page is displayed.

- Running Hive HQL statements

Select the target database on the left. You can also click **default**  in the upper right corner and enter the target database name to search for the target database.

Enter a Hive HQL statement in the text box and click  or press **Ctrl+Enter** to run the HQL statement. The execution result is displayed on the **Result** tab page.

- Analyzing Hive HQL statements

Select the target database on the left, enter the Hive HQL statement in the text box, and click  to compile the HQL statement and check whether the statement is correct. The execution result is displayed under the text editing box.

- Saving HQL statements

Enter the Hive HQL statement in the text box, click  in the upper right corner, and enter the name and description. You can view the saved statements on the **Saved Queries** tab page.

- Viewing historical records

Click **Query History** to view the HQL running status. You can view the history of all the statements or only the saved statements. If many historical records exist, you can enter keywords in the text box to search for desired records.

- Configuring advanced query

Click  in the upper right corner to configure the file, function, and settings.

- Viewing the information of shortcut keys

Click  in the upper right corner to view information about all shortcut keys.

## How to Use Metadata Browser

Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

- Viewing metadata of Hive tables

Click  in the navigation tree on the left and click a table name. The metadata of the Hive table is displayed.

- Managing metadata of Hive tables

On the metadata information page of a Hive table:

- Click **Import** in the upper right corner to import data.
- Click **Overview** to view the location of the table file in the **PROPERTIES** field.

You can view the field information in each column of the Hive table and manually add the description. Note that the added description is not the field comment information in the Hive table.

- Click **Sample** to browse data.

- Managing Hive metadata tables  
Click  in the left list to create a table based on the uploaded file in the database. You can also manually create a table.

---

 **CAUTION**

The Hue page is used to view and analyze data such as files and tables. Do not perform high-risk management operations such as deleting objects on the page. If an operation is required, you are advised to perform the operation on each component after confirming that the operation has no impact on services. For example, you can use the HDFS client to perform operations on HDFS files and use the Hive client to perform operations on Hive tables.

---

## Typical Scenarios

On the Hue page, create a Hive table as follows:

**Step 1** Click  at the upper left corner of Hue web UI and select the Hive instance to be operated to enter the Hive command execution page.

**Step 2** Enter an HQL statement in the command input box, for example:

```
create table hue_table(id int,name string,company string) row format  
delimited fields terminated by ',' stored as textfile;
```

Click  to execute the HQL statements.

**Step 3** Enter the following command in the command input box:

```
show tables;
```

Click  to view the created table **hue\_table** in **Result**.

----End

## 11.9.3 Oozie on Hue

Hue provides the Oozie job manager function, in this case, you can use Oozie in GUI mode.

---

 **CAUTION**

The Hue page is used to view and analyze data such as files and tables. Do not perform high-risk management operations such as deleting objects on the page. If an operation is required, you are advised to perform the operation on each component after confirming that the operation has no impact on services. For example, you can use the HDFS client to perform operations on HDFS files and use the Hive client to perform operations on Hive tables.

---

## How to Use Oozie Job Designer

Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

In the navigation tree on the left, click  and choose **Workflow**.


The job designer allows users to create MapReduce, Java, Streaming, Fs, SSH, Shell and DistCp jobs.

## How to Use Dashboard

Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

Click **Jobs** in the upper right corner. The **Job Browser** page is displayed.

View the running status of the Workflow, Coordinator, and Bundles jobs.



## How to Use Editor

Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

In the navigation tree on the left, click  and choose **Workflow**.

Workflows, Schedule, and Bundle tasks can be created. Existing applications can be submitted for running, shared, copied, and exported.

- Each Workflow can contain one or more jobs to form a complete workflow for a specified service.  
When creating a Workflow, you can design jobs in the Hue editor and add the jobs to the Workflow.
- Each Schedule can define a time trigger to periodically execute a specified Workflow. One time trigger cannot execute multiple Workflows.
- Each Bundles can define a set to execute multiple Schedules so that different Workflows can be executed in batches.

## 11.10 Hue Log Overview

### Log Description

**Log paths:** The default paths of Hue logs are `/var/log/Bigdata/hue` (for storing run logs) and `/var/log/Bigdata/audit/hue` (for storing audit logs).

**Log archive rules:** The automatic compression and archiving function of the Hue logs is enabled. By default, when the size of a log file (**access.log**, **error.log**, **runcpserver.log**, or **hue-audits.log**) exceeds 5 MB, logs are automatically compressed. A maximum of 20 latest compressed files are reserved. The number of compressed files and compression threshold can be configured.

**Table 11-7** Hue log list

Type	Log File Name	Description
Run log	access.log	Access log file
	error.log	Error log file
	gsdb_check.log	Log file of the GaussDB check information
	kt_renewer.log	Log file of Kerberos authentication
	kt_renewer.out.log	Log file of the abnormal Kerberos authentication logs
	runcpserver.log	Log file of operation records
	runcpserver.out.log	Log file of process running exceptions
	supervisor.log	Log file of process startup
	supervisor.out.log	Log file of process startup exceptions
	dbDetail.log	Log file of database initialization
	initSecurityDetail.log	Download initialization log file of the Keytab file
	postinstallDetail.log	Work log file generated after the Hue service is installed
	prestartDetail.log	Prestart log file
	statusDetail.log	Log file of the Hue health status
	startDetail.log	Startup log
	get-hue-ha.log	Log file of the Hue HA status
	hue-ha-status.log	Log file of the Hue HA status monitoring
	get-hue-health.log	Log file of the Hue health status
	hue-health-check.log	Log file of the Hue health check
	hue-refresh-config.log	Log file of the Hue configuration update
	hue-script-log.log	Log file of the Hue operations on the Manager console
hue-service-check.log	Log file of the Hue service status monitoring	

Type	Log File Name	Description
	db_pwd.log	Log that records the changes of the password for Hue to connect to the DBService database
	modifyDBPwd_Date.log	-
	watch_config_update.log	Parameter update log file
Audit log	hue-audits.log	Audit log file

## Log Level

**Table 11-8** describes the log levels supported by Hue.

Levels of logs are ERROR, WARN, INFO, and DEBUG from the highest to the lowest priority. Run logs of equal or higher levels are recorded. The higher the specified log level, the fewer the logs recorded.

**Table 11-8** Log levels

Level	Description
ERROR	Logs of this level record error information about system running.
WARN	Logs of this level record exception information about the current event processing.
INFO	Logs of this level record normal running status information about the system and events.
DEBUG	Logs of this level record the system information and system debugging information.

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of the Hue service by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** In the navigation tree on the left, select **Log** corresponding to the role to be modified.
- Step 3** Select the log level to be changed on the right.
- Step 4** Save the configuration. In the displayed dialog box, click **OK** to make the configurations take effect.
- Step 5** Restart the service or instance whose configuration has expired for the configuration to take effect.

----End

## Log Format

The following table lists the Hue log formats:

**Table 11-9** Log formats

Type	Format	Example
Run log	<i>&lt;dd-MM-yy HH:mm:ss,SSS&gt;&lt;Location where the log event occurs&gt;&lt;Log level&gt;&lt;Message in the log&gt;</i>	[03/Nov/2014 11:57:19 ] middleware   INFO   Unloading MimeTypeJSFileFixStreamingMiddleware.
	<i>&lt;Log level&gt;&lt;Time format&gt;&lt;yyyy-MM-dd HH:mm:ss,SSS&gt;&lt;Location where the log event occurs&gt;&lt;Message in the log&gt;</i>	INFO : CST 2014-11-06 11:22:52 hue-ha- status.sh : update 4 <= 15:myHostName=10.0.0. 250 ACTIVE=10.0.0.250
Audit log	<i>&lt;UserName&gt;&lt;yyyy-MM-dd HH:mm:ss,SSS&gt;&lt; Audit operation description&gt; &lt;Resource parameter&gt; &lt;URL&gt; &lt;Whether to allow&gt; &lt;Audit operation&gt; &lt;IP address&gt;</i>	{"username": "admin", "eventTime": "2014-11-06 10:28:34", "operationText": "Successful login for user: admin", "service": "accounts", "url": "/" accounts/login/", "allowed": true, "operation": "USER_LOGIN", "ipAddress": "10.0.0.250"}

## 11.11 Common Issues About Hue

### 11.11.1 How Do I Solve the Problem that HQL Fails to Be Executed in Hue Using Internet Explorer?

#### Question

What do I do if all HQL statements fail to be executed when I use Internet Explorer to access Hive Editor in Hue and the message "There was an error with your query" is displayed?

## Answer

Internet Explorer does not support processing of AJAX POST requests containing form data in 307 redirection. You are advised to use a compatible browser, for example, Google Chrome.

## 11.11.2 Why Does the use database Statement Become Invalid When Hive Is Used?

### Question

When Hive is used, the **use database** statement is entered in the text box to switch the database, and other statements are also entered, why does the database fail to be switched?


### Answer

Using Hive on Hue is different from using Hive on the Hive client. There is an option to select a database on the Hue interface, and the database where the current SQL is executed is the one that is displayed on the interface. You are advised to use functions on the Hue interface instead of using statements to perform session-level and one-off operations, for example, setting parameters. If you must enter specific statements to perform an operation, ensure that all statements you enter are in one text box.

## 11.11.3 What Can I Do If HDFS Files Fail to Be Accessed Using Hue WebUI?

### Question

What can I do if an error message shown in the following figure is displayed, indicating that the HDFS file cannot be accessed when I use Hue web UI to access the HDFS file?



### Answer

1. Check whether the user who logs in to the Hue web UI has the permissions of the **hadoop** user group.
2. Check whether the HttpFS instance has been installed for the HDFS service and is running properly. If the HttpFS instance is not installed, manually install and restart the Hue service.

## 11.11.4 What Should I Do If a Large File Fails to Be Uploaded on the Hue Page?

### Question

A large file fails to be uploaded on the Hue page.

### Answer

1. You are not advised to use the Hue browser to upload large files. You are advised to use the client to upload large files using commands.
2. If Hue is required, perform the following steps to modify Httpd parameters:
  - a. Log in to the active management node as user **omm**.
  - b. Run the following command to edit the **httpd.conf** configuration file:  
**vi \$BIGDATA\_HOME/om-server/Apache-httpd-2.4.39/conf/httpd.conf**
  - c. Search for 21201 and add **RequestReadTimeout handshake=0 header=0 body=0** to the `</VirtualHost>` configuration.

```
...
<VirtualHost *:21201>
  ServerName https://10.112.16.93:21201
  AllowEncodedSlashes On
  SSLProxyEngine On
  ProxyRequests Off
  TraceEnable off
  ProxyTimeout 1200
  RewriteEngine on
  RewriteMap proxylist dbm:${BIGDATA_ROOT_HOME}/om-server_XXX/Apache-httpd-2.4.39/
  conf/proxylist.dbm

  RewriteRule ^(\.*)$ ${proxylist:/Hue/Hue/21201}$1 [E=TARGET_PATH:$1,L,P]

  Header edit Location ^(!https://100.112.16.93:20009|https://100.112.16.93:21201)http[s]?://
  [^/]*(.*)$ https://10.112.16.93:21201$1

  ProxyPassReverseCookiePath / / interpolate

  SSLEngine On
  SSLProxyProtocol All +TLSv1.2 -SSLv2 -SSLv3 -TLSv1 -TLSv1.1
  SSLProtocol ALL +TLSv1.2 -SSLv2 -SSLv3 -TLSv1 -TLSv1.1
  SSLCipherSuite ECDHE-RSA-AES256-GCM-SHA384:ECDHE-ECDSA-AES256-GCM-
  SHA384:ECDHE-RSA-AES128-GCM-SHA256:ECDHE-ECDSA-AES128-GCM-SHA256:DHE-DSS-
  AES256-GCM-SHA384:DHE-RSA-AES256-GCM-SHA384:DHE-DSS-AES128-GCM-SHA256:DHE-
  RSA-AES128-GCM-SHA256
  SSLProxyCheckPeerName off
  SSLProxyCheckPeerCN off
  SSLCertificateFile "${BIGDATA_ROOT_HOME}/om-server_8.0.2.1/Apache-httpd-2.4.39/conf/
  security/proxy_ssl.cert"
  SSLCertificateKeyFile "${BIGDATA_ROOT_HOME}/om-server_8.0.2.1/Apache-httpd-2.4.39/
  conf/security/server.key"
  SSLProxyCACertificateFile ${BIGDATA_ROOT_HOME}/om-server_8.0.2.1/apache-
  tomcat-8.5.57/conf/security/tomcat.crt
  SSLCertificateChainFile "${BIGDATA_ROOT_HOME}/om-server_8.0.2.1/Apache-httpd-2.4.39/
  conf/security/proxy_chain.cert"
  RequestReadTimeout handshake=0 header=0 body=0
</VirtualHost>
...
```

- d. Run the **ps -ef|grep httpd|grep -v grep|xargs kill -9** command to restart the httpd.

## 11.11.5 Hue Page Cannot Be Displayed When the Hive Service Is Not Installed in a Cluster

### Question

If the Hive service is not installed in the cluster, the native Hue service page is blank.

### Answer

In the current version, Hue depends on the Hive component. If this occurs, check whether the Hive component is installed in the current cluster. If not, install the Hive component.

# 12 Using Kafka

---

## 12.1 Using Kafka from Scratch

### Scenario

You can create, query, and delete topics on a cluster client.

### Prerequisites

The client has been installed. For example, the client is installed in the `/opt/hadoopclient` directory. The client directory in the following operations is only an example. Change it to the actual installation directory.

### Using the Kafka Client

**Step 1** Access the ZooKeeper instance page.

Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster** > *Name of the desired cluster* > **Services** > **ZooKeeper** > **Instance**.

**Step 2** View the IP addresses of the ZooKeeper role instance.

Record any IP address of the ZooKeeper instance.

**Step 3** Log in to the node where the client is installed.

**Step 4** Run the following command to switch to the client directory, for example, `/opt/hadoopclient/Kafka/kafka/bin`.

```
cd /opt/hadoopclient/Kafka/kafka/bin
```

**Step 5** Run the following command to configure environment variables:

```
source /opt/hadoopclient/bigdata_env
```

**Step 6** If Kerberos authentication is enabled for the current cluster, run the following command to authenticate the current user. If Kerberos authentication is disabled for the current cluster, skip this step.

**kinit** *Kafka user*

**Step 7** Create a topic.

```
sh kafka-topics.sh --create --topic Topic name --partitions Number of partitions occupied by the topic --replication-factor Number of replicas of the topic --zookeeper IP address of the node where the ZooKeeper instance resides:clientPort/kafka
```

**Step 8** Run the following command to view the topic information in the cluster:

```
sh kafka-topics.sh --list --zookeeper IP address of the node where the ZooKeeper instance resides:clientPort/kafka
```

**Step 9** Delete the topic created in [Step 7](#).

```
sh kafka-topics.sh --delete --topic Topic name --zookeeper IP address of the node where the ZooKeeper instance resides:clientPort/kafka
```

Type **y** and press **Enter**.

----End

## 12.2 Managing Kafka Topics

### Scenario

You can manage Kafka topics on a cluster client based on service requirements. Management permission is required for clusters with Kerberos authentication enabled.

### Prerequisites

You have installed the Kafka client.

### Procedure

**Step 1** View the IP addresses of the ZooKeeper role instance.

Record any IP address of the ZooKeeper instance.

**Step 2** Prepare the client based on service requirements. Log in to the node where the client is installed.

Log in to the node where the client is installed. For details, see .

**Step 3** Run the following command to switch to the client directory, for example, **/opt/client/Kafka/kafka/bin**.

```
cd /opt/client/Kafka/kafka/bin
```

**Step 4** Run the following command to configure environment variables:

```
source /opt/client/bigdata_env
```

**Step 5** Run the following command to perform user authentication (skip this step in normal mode):

**kinit** *Component service user*

**Step 6** Use **kafka-topics.sh** to manage Kafka topics.

- Creating a topic:

By default, partitions of a topic are distributed based on the number of partitions on the node and disk. To distribute partitions based on the disk capacity, set **log.partition.strategy** to **capacity** for the Kafka service.

- **./kafka-topics.sh --create --topic** *topic name* **--partitions** *number of partitions occupied by the topic* **--replication-factor** *number of replicas of the topic* **--zookeeper** *IP address of any ZooKeeper node:clientPort/kafka*

- **./kafka-topics.sh --create --topic** *topic name* **--partitions** *number of partitions occupied by the topic* **--replication-factor** *number of replicas of the topic* **--bootstrap-server** *IP address of the Kafka cluster:21007* **--command-config** *../config/client.properties*

- List of topics:

- **./kafka-topics.sh --list --zookeeper** *service IP address of any ZooKeeper node:clientPort/kafka*

- **./kafka-topics.sh --list --bootstrap-server** *IP address of the Kafka cluster:21007* **--command-config** *../config/client.properties*

- Viewing the topic:

- **./kafka-topics.sh --describe --zookeeper** *service IP address of any ZooKeeper node:clientPort/kafka* **--topic** *topic name*

- **./kafka-topics.sh --describe --bootstrap-server** *IP address of the Kafka cluster:21007* **--command-config** *../config/client.properties* **--topic** *topic name*

- Modifying a topic:

- **./kafka-topics.sh --alter --topic** *topic name* **--config** *configuration item=configuration value* **--zookeeper** *service IP address of any ZooKeeper node:clientPort/kafka*

- Expanding partitions:

- **./kafka-topics.sh --alter --topic** *topic name* **--zookeeper** *service IP address of any ZooKeeper node:clientPort/kafka* **--command-config** *Kafka/kafka/config/client.properties* **--partitions** *number of partitions after the expansion*

- **./kafka-topics.sh --alter --topic** *topic name* **--bootstrap-server** *IP address of the Kafka cluster:21007* **--command-config** *Kafka/kafka/config/client.properties* **--partitions** *number of partitions after the expansion*

- Deleting a topic

- **./kafka-topics.sh --delete --topic** *topic name* **--zookeeper** *Service IP address of any ZooKeeper node:clientPort/kafka*

- **./kafka-topics.sh --delete --topic** *topic name* **--bootstrap-server** *IP address of the Kafka cluster:21007* **--command-config** *../config/client.properties*

----End

## 12.3 Querying Kafka Topics

### Scenario

You can query existing Kafka topics on MRS.

### Procedure

**Step 1** Click **KafkaTopicMonitor**.

All topics are displayed in the list by default. You can view the number of partitions and replicas of the topics.

**Step 2** Click the desired topic in the list to view its details.

----End

## 12.4 Managing Kafka User Permissions

### Scenario

For clusters with Kerberos authentication enabled, using Kafka requires relevant permissions. MRS clusters can grant the use permission of Kafka to different users.

**Table 12-1** lists the default Kafka user groups.

#### NOTE

Kafka supports two types of authentication plug-ins: Kafka open-source authentication plug-in and Ranger authentication plug-in.

This section describes the user permission management based on the Kafka open source authentication plug-in. For details about how to use the Ranger authentication plug-in, see [Adding a Ranger Access Permission Policy for Kafka](#).

**Table 12-1** Default Kafka user groups

User Group	Description
kafkaadmin	Kafka administrator group. Users in this group have the permissions to create, delete, read, and write all topics, and authorize other users.
kafkasuperuser	Kafka super user group. Users in this group have the permissions to read and write all topics.
kafka	Kafka common user group. Users in this group can access a topic only when they are granted with the read and write permissions of the topic by a user in the <b>kafkaadmin</b> group.

## Prerequisites

- You have installed the Kafka client.
- A user in the **kafkaadmin** group, for example **admin**, has been prepared.

## Procedure

**Step 1** View the IP addresses of the ZooKeeper role instance.

Record the IP address of any ZooKeeper instance.

**Step 2** Prepare the client based on service requirements. Log in to the node where the client is installed.

Log in to the node where the client is installed. For details, see .

**Step 3** Run the following command to switch to the client directory, for example, **/opt/client/Kafka/kafka/bin**.

```
cd /opt/client/Kafka/kafka/bin
```

**Step 4** Run the following command to configure environment variables:

```
source /opt/client/bigdata_env
```

**Step 5** Run the following command to authenticate the user (skip this step in normal mode):

```
kinit Component service user
```

**Step 6** The following table lists the common commands used for user authorization when **kafka-acl.sh** is used.

- View the permission control list of a topic:

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --list --topic <topicname>
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --command-config ../config/client.properties --list --topic <topic name>
```

- Add the Producer permission for a user:

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --add --allow-principal User:<username> --producer --topic <topic name>
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --command-config ../config/client.properties --add --allow-principal User:<username> --producer --topic <topic name>
```

- Assign the Producer permission to a user in batches.

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --add --allow-principal User:<username> --producer --topic <topic name> --resource-pattern-type prefixed
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --command-config ../config/client.properties --add --allow-principal User:<username> --producer --topic <topic name> --resource-pattern-type prefixed
```

- Remove the Producer permission from a user:  

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --remove --allow-principal User:<username> --producer --topic <topic name>
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --command-config ../config/client.properties --remove --allow-principal User:<username> --producer --topic <topic name>
```
- Delete the Producer permission of a user in batches:  

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --remove --allow-principal User:<username> --producer --topic <topic name> --resource-pattern-type prefixed
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --command-config ../config/client.properties --remove --allow-principal User:<username> --producer --topic <topic name>--resource-pattern-type prefixed
```
- Add the Consumer permission for a user:  

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --add --allow-principal User:<user name> --consumer --topic <topic name> --group <consumer group name>
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --command-config ../config/client.properties --add --allow-principal User:<username> --consumer --topic <topicname> --group <consumer group name>
```
- Add consumer permissions to a user in batches:  

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --add --allow-principal User:<username> --consumer --topic <topic name> --group <consumer group name> --resource-pattern-type prefixed
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --command-config ../config/client.properties --add --allow-principal User:<username> --consumer --topic <topicname> --group <consumer group name> --resource-pattern-type prefixed
```
- Remove the consumer permission from a user:  

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --remove --allow-principal User:<username> --consumer --topic <topic name> --group <consumer group name>
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --command-config ../config/client.properties --remove --allow-principal User:<username> --consumer --topic <topic name> --group <consumer group name>
```
- Delete the consumer permission of a user in batches:  

```
./kafka-acls.sh --authorizer-properties zookeeper.connect=<service IP address of any ZooKeeper node:2181/kafka > --remove --allow-principal User:<username> --consumer --topic <topic name> --group <consumer group name> --resource-pattern-type prefixed
```

```
./kafka-acls.sh --bootstrap-server <IP address of the Kafkacluster:21007> --  
command-config ../config/client.properties --remove --allow-principal  
User:<username> --consumer --topic <topicname> --group <consumer  
group name> --resource-pattern-type prefixed
```

----End

## 12.5 Managing Messages in Kafka Topics

### Scenario

You can produce or consume messages in Kafka topics using the MRS cluster client. For clusters with Kerberos authentication enabled, you must have the permission to perform these operations.

### Prerequisites

You have installed the Kafka client.

### Procedure

**Step 1** Click **instance**. Query the IP addresses of the Kafka instances.

Record the IP address of any Kafka instance.

**Step 2** Prepare the client based on service requirements. Log in to the node where the client is installed.

Log in to the node where the client is installed. For details, see .

**Step 3** Run the following command to switch to the client directory, for example, **/opt/client/Kafka/kafka/bin**.

```
cd /opt/client/Kafka/kafka/bin
```

**Step 4** Run the following command to configure environment variables:

```
source /opt/client/bigdata_env
```

**Step 5** For clusters with Kerberos authentication enabled, run the following command to authenticate the user. For clusters with Kerberos authentication disabled, skip this step.

```
kinit Kafka user
```

Example:

```
kinit admin
```

**Step 6** Manage messages in Kafka topics using the following commands:

- Producing messages

```
sh kafka-console-producer.sh --broker-list IP address of the node where the  
Kafka instance resides:9092 --topic Topic name --producer.config /opt/  
client/Kafka/kafka/config/producer.properties
```

You can input specified information as the messages produced by the producer and then press **Enter** to send the messages. To end message producing, press **Ctrl + C** to exit.

- Consuming messages

```
sh kafka-console-consumer.sh --topic Topic name --bootstrap-server IP address of the node where the Kafka instance resides:9092 --consumer.config /opt/client/Kafka/kafka/config/consumer.properties
```

In the configuration file, **group.id** (indicating the consumer group) is set to **example-group1** by default. Users can change the value as required. The value takes effect each time consumption occurs.

By default, the system reads unprocessed messages in the current consumer group when the command is executed. If a new consumer group is specified in the configuration file and the **--from-beginning** parameter is added to the command, the system reads all messages that have not been automatically deleted in Kafka.

 NOTE

----End

## 12.6 Creating a Kafka Role

### Scenario

This section describes how to create and configure a Kafka role.

 NOTE

Users can create Kafka roles only in security mode.

If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. For details, see [Adding a Ranger Access Permission Policy for Kafka](#).

### Prerequisites

The system administrator has understood the service requirements.

### Procedure

- Step 1** Log in to FusionInsight Manager and choose **System > Permission > Role**.
- Step 2** On the displayed page, click **Create Role** and enter a **Role Name** and **Description**.
- Step 3** On the **Configure Resource Permission** page, choose *Name of the desired cluster* > **Kafka**.
- Step 4** Select permissions based on service requirements. For details about configuration items, see [Table 12-2](#).

**Table 12-2** Description

Scenario	Role Authorization
Setting the Kafka administrator permissions	In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> > <b>Kafka</b> > <b>Kafka Manager Privileges</b> . <b>NOTE</b> This permission allows you to create and delete topics, but does not allow you to produce or consume any topics.
Setting the production permission of a user on a topic	1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> > <b>Kafka</b> > <b>Kafka Topic Producer And Consumer Privileges</b> . 2. In the <b>Permission</b> column of the specified topic, select <b>Kafka Producer Permission</b> .
Setting the consumption permission of a user on a topic	1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> > <b>Kafka</b> > <b>Kafka Topic Producer And Consumer Privileges</b> . 2. In the <b>Permission</b> column of the specified topic, select <b>Kafka Consumer Privileges</b> .

**Step 5** Click **OK**, and return to the **Role** page.

----End

## 12.7 Kafka Common Parameters

Navigation path for setting parameters:

For details about how to set parameters, see [Modifying Cluster Service Configuration Parameters](#).

### Common Parameters

**Table 12-3** Parameter description

Parameter	Description	Default Value
log.dirs	List of Kafka data storage directories. Use commas (,) to separate multiple directories.	% {@auto.detect.datapart.b k.log.logs}

Parameter	Description	Default Value
KAFKA_HEAP_OPTS	Specifies the JVM option used for Kafka to start broker. It is recommended that you set this parameter based on service requirements.	-Xmx6G -Xms6G
auto.create.topics.enable	Indicates whether a topic is automatically created. If this parameter is set to <b>false</b> , you need to run a command to create a topic before sending a message.	true
default.replication.factor	Default number of replicas of a topic is automatically created.	2
monitor.preInitDelay	Delay of the first health check after the server is started. If the startup takes a long time, increase the value of the parameter. Unit: millisecond	600,000

## Timeout Parameters

**Table 12-4** Broker-related timeout parameters

Parameter	Description	Default Value	Impact
controller.socket.timeout.ms	Specifies the timeout for connecting controller to broker. Unit: millisecond	30,000	Generally, retain the default value of this parameter.
group.max.session.timeout.ms	Specifies the maximum session timeout during the consumer registration. Unit: millisecond	180000	The configured value must be less than the value of this parameter.
group.min.session.timeout.ms	Specifies the minimum session timeout during the consumer registration. Unit: millisecond	6000	The configured value must be greater than the value of this parameter.

Parameter	Description	Default Value	Impact
offsets.commit.timeout.ms	Specifies the timeout for the Offset to submit requests. Unit: millisecond	5,000	This parameter specifies the maximum delay for processing an Offset request.
replica.socket.timeout.ms	Specifies the timeout of the request for synchronizing replica data. Its value must be greater than or equal to that of the <b>replica.fetch.wait.max.ms</b> parameter. Unit: millisecond	30,000	Specifies the maximum timeout for establishing a channel before the synchronization thread sends a synchronization request. The value must be greater than that of the <b>replica.fetch.wait.max.ms</b> parameter.
request.timeout.ms	Specifies the timeout for waiting for a response after the client sends a connection request. If no response is received within the timeout, the client resends the request. A request failure is returned after the maximum retry times is reached. Unit: millisecond	30,000	This parameter is configured when the networkclient connection is transferred in the controller and replica threads on the broker node.
transaction.max.timeout.ms	Specifies the maximum timeout allowed by the transaction. If the client request time exceeds the value of this parameter, broker returns an error in InitProducerIdRequest. This prevents a long client request timeout, ensuring that consumer can receive topics. Unit: millisecond	900,000	Specifies the maximum timeout for transactions.

Parameter	Description	Default Value	Impact
user.group.cache.timeout.seconds	Specifies the time when the user group information is stored in the cache. Unit: second	300	Specifies the time for caching the mapping between users and user groups. If time exceeds the threshold, the system automatically runs the <b>id -Gn</b> command to query the user information. During this period, the mapping in the cache is used.
zookeeper.connection.timeout.ms	Specifies the timeout for connecting to ZooKeeper. Unit: millisecond	45,000	This parameter specifies the duration for connecting the ZooKeeper and zkclient for the first time. If the duration exceeds the value of this parameter, the zkclient automatically disconnects the connection.

Parameter	Description	Default Value	Impact
zookeeper.session.timeout.ms	Specifies the ZooKeeper session timeout duration. During this period, ZooKeeper disconnects the connection if broker does not report its heartbeats to ZooKeeper. Unit: millisecond	45,000	ZooKeeper session timeout has the following functions: 1) Based on value of this parameter and the number of ZooKeeper URLs in ZKURL, if the connection duration exceeds the node timeout value (sessionTimeout/ Number of transferred ZooKeeper URLs), the connection fails and the system attempts to connect to the next node. 2) After the connection is established, a session (for example, the temporary BrokerId node registered on the ZooKeeper) is cleared by the ZooKeeper a session timeout later if the broker is stopped.

**Table 12-5** Producer-related timeout parameters

Parameter	Description	Default Value	Impact
request.timeout.ms	Specifies the timeout of a message request.	30,000	If a network fault occurs, increase the value of this parameter. If the value is too small, the Batch Expire occurs.

**Table 12-6** Consumer-related timeout parameters

Parameter	Description	Default Value	Impact
connections.max.idle.ms	Specifies the maximum retention period for idle connections.	600,000	If the idle connection time is greater than this parameter value, this connection is disconnected. If necessary, a new connection is created.
request.timeout.ms	Specifies the timeout for consumer requests.	30,000	If the request times out, the request will fail and be sent again.

## 12.8 Safety Instructions on Using Kafka

### Brief Introduction to Kafka APIs

- **Producer API**  
Indicates the API defined in **org.apache.kafka.clients.producer.KafkaProducer**. When **kafka-console-producer.sh** is used, the API is used by default.
- **Consumer API**  
Indicates the API defined in **org.apache.kafka.clients.consumer.KafkaConsumer**. When **kafka-console-consumer.sh** is used, the API is used by default.

 **NOTE**

Kafka does not support old Producer APIs and old Consumer APIs.

### Protocol Description for Accessing Kafka

The protocols used to access Kafka are as follows: PLAINTEXT, SSL, SASL\_PLAINTEXT, and SASL\_SSL.

When Kafka service is started, the listeners using the PLAINTEXT and SASL\_PLAINTEXT protocols are started. You can set **ssl.mode.enable** to **true** in Kafka service configuration to start listeners using SSL and SASL\_SSL protocols. The following table describes the four protocols:

Protocol	Description	Default Port
PLAINTEXT	Supports plaintext access without authentication.	9092

Protocol	Description	Default Port
SASL_PLAINTEXT	Supports plaintext access with Kerberos authentication.	21007
SSL	Supports SSL-encrypted access without authentication.	9093
SASL_SSL	Supports SSL-encrypted access with Kerberos authentication.	21009

## ACL Settings for a Topic

To view and set topic permission information, run the `kafka-acls.sh` script on the Linux client. For details, see [Managing Kafka User Permissions](#).

## Use of Kafka APIs in Different Scenarios

- Scenario 1: accessing the topic with an ACL

Used API	User Group	Client Parameter	Server Parameter	Accessed Port
API	Users need to meet one of the following conditions: <ul style="list-style-type: none"> <li>In the administrator group</li> <li>In the <b>kafkaadmin</b> group</li> <li>In the <b>kafkasuperuser</b> group</li> <li>In the <b>kafka</b> group and be authorized</li> </ul>	security.inter.broker.protocol=SASL_PLAINTEXT sasl.kerberos.service.name = kafka	-	sasl.port (The default number is 21007.)
		security.protocol=SASL_SSL sasl.kerberos.service.name = kafka	Set <b>ssl.mode.enabled</b> to <b>true</b> .	sasl-ssl.port (The default number is 21009.)

- Scenario 2: accessing the topic without an ACL

Used API	User Group	Client Parameter	Server Parameter	Accessed Port
API	<p>Users need to meet one of the following conditions:</p> <ul style="list-style-type: none"> <li>• In the administrator group</li> <li>• In the <b>kafkaadmin</b> group</li> <li>• In the <b>kafkasuperuser</b> group</li> </ul>	<p>security.protocol=SASL_PLAINTEXT sasl.kerberos.service.name = kafka</p>	-	<p>sasl.port (The default number is 21007.)</p>
	<p>Users are in the <b>kafka</b> group.</p>		<p>Set <b>allow.everyone.if.no.acl.found</b> to <b>true</b>.</p> <p><b>NOTE</b> In normal mode, the server parameter <b>allow.everyone.if.no.acl.found</b> does not need to be modified.</p>	<p>sasl.port (The default number is 21007.)</p>
	<p>Users need to meet one of the following conditions:</p> <ul style="list-style-type: none"> <li>• In the administrator group</li> <li>• In the <b>kafkaadmin</b> group</li> <li>• In the <b>kafkasuperuser</b> group</li> </ul>	<p>security.protocol=SASL_SSL sasl.kerberos.service.name = kafka</p>	<p>Set <b>ssl.mode.enable</b> to <b>true</b>.</p>	<p>sasl-ssl.port (The default number is 21009.)</p>

Used API	User Group	Client Parameter	Server Parameter	Accessed Port
	Users are in the <b>kafka</b> group.		<ol style="list-style-type: none"> <li>1. Set <b>allow.everyone.if.no.acl.found</b> to <b>true</b>.</li> <li>2. Set <b>ssl.mode.enable</b> to <b>true</b>.</li> </ol>	sasl-ssl.port (The default number is 21009.)
	-	security.protocol=PLAINTEXT	Set <b>allow.everyone.if.no.acl.found</b> to <b>true</b> .	port (The default number is 9092.)
	-	security.protocol=SSL	<ol style="list-style-type: none"> <li>1. Set <b>allow.everyone.if.no.acl.found</b> to <b>true</b>.</li> <li>2. Set <b>ssl.mode.enable</b> to <b>true</b>.</li> </ol>	ssl.port (The default number is 9063.)

## 12.9 Kafka Specifications

### Upper Limit of Topics

The maximum number of topics depends on the number of file handles (mainly used by data and index files on site) opened in the process.

1. Run the **ulimit -n** command to view the maximum number of file handles that can be opened in the process.
2. Run the **lsof -p <Kafka PID>** command to view the file handles (which may keep increasing) that are opened in the Kafka process on the current single node.
3. Determine whether the maximum number of file handles will be reached and whether the running of Kafka is affected after required topics are created, and estimate the maximum size of data that each partition folder can store and the number of data (\*.log file, whose default size is 1 GB and can be adjusted by modifying **log.segment.bytes**) and index (\*.index file, whose default size is 10 MB and can be adjusted by modifying **log.index.size.max.bytes**) files that will be produced after required topics are created.

## Number of Concurrent Consumers

In an application, it is recommended that the number of concurrent consumers in a group be the same as the number of partitions in a topic, ensuring that a consumer consumes data in only a specified partition. If the number of concurrent consumers is more than the number of partitions, the redundant consumers have no data to consume.

## Relationship Between Topic and Partition

- If  $K$  Kafka nodes are deployed in the cluster, each node is configured with  $N$  disks, the size of each disk is  $M$ , the cluster contains  $n$  topics (named as  $T_1, T_2, \dots, T_n$ ), the data input traffic per second of the  $m$  topic is  $X(T_m)$  MB/s, the number of configured replicas is  $R(T_m)$ , and the configured data retention time is  $Y(T_m)$  hour, the following requirement must be met:

$$M \times N \times K > \sum_{i=T_1}^{T_n} (X(i)R(i)Y(i) \times 3600)$$

- If the size of a disk is  $M$ , the disk has  $n$  partitions (named as  $P_0, P_1, \dots, P_n$ ), the data write traffic per second of the  $m$  partition is  $Q(P_m)$  MB/s (calculation method: data traffic of the topic to which the  $m$  partition belongs divided by the number of partitions), and the data retention time is  $T(P_m)$  hours, the following requirement must be met for the disk:

$$M > \sum_{i=P_0}^{P_n} (Q(i)T(i) \times 3600)$$

- Based on the throughput, if the throughput that can be reached by the producer is  $P$ , the throughput that can be reached by the consumer is  $C$ , and the expected throughput of Kafka is  $T$ , it is recommended that the number of partitions of the topic be set to  $\text{Max}(T/P, T/C)$ .

### NOTE

- In a Kafka cluster, more partitions mean higher throughput. However, too many partitions also pose potential impacts, such as a file handle increase, unavailability increase (for example, if a node is faulty, the time window becomes large after the leader is reselected in some partitions), and end-to-end latency increase.
- Suggestion: The disk usage of a partition is smaller than or equal to 100 GB; the number of partitions on a node is smaller than or equal to 3,000; the number of partitions in the entire cluster is smaller than or equal to 10,000.

## 12.10 Using the Kafka Client

### Scenario

This section guides users to use a Kafka client in an O&M or service scenario.

### Prerequisites

- The client has been installed. For example, the installation directory is **/opt/client**.

- Service component users are created by the administrator as required. Machine-machine users need to download the keytab file. A human-machine user must change the password upon the first login. (Not involved in normal mode)
- After changing the domain name of a cluster, redownload the client to ensure that the **kerberos.domain.name** value in the configuration file of the client is set to the correct server domain name.

## Procedure

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to go to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** Run the following command to perform user authentication (skip this step in normal mode):

```
kinit Component service user
```

**Step 5** Run the following command to switch to the Kafka client installation directory:

```
cd Kafka/kafka/bin
```

**Step 6** Run the following command to use the client tool to view and use the help information:

- **./kafka-console-consumer.sh**: Kafka message reading tool
- **./kafka-console-producer.sh**: Kafka message publishing tool
- **./kafka-topics.sh**: Kafka topic management tool

----End

## 12.11 Configuring Kafka HA and High Reliability Parameters

### Scenario

For the Kafka message transmission assurance mechanism, different parameters are available for meeting different performance and reliability requirements. This section describes how to configure Kafka high availability (HA) and high reliability parameters.

### Impact on the System

- Impact of HA and high performance configurations:

**NOTICE**

After HA and high performance are configured, the data reliability decreases. Specifically, data may be lost if disks or nodes are faulty.

- Impact of high reliability configurations:
  - Deteriorated performance  
If **ack** is set to **-1**, data written is considered as successful only when data is written to multiple replicas. As a result, the delay of a single message increases and the client processing capability decreases. The impact is subject to the actual test data.
  - Reduced availability  
A replica that is not in the ISR list cannot be elected as a leader. If the leader goes offline and other replicas are not in the ISR list, the partition remains unavailable until the leader node recovers. When the node where a replica of a partition is located is faulty, the minimum number of successful replicas cannot be met. As a result, service writing fails.
- If parameters are at the service level, Kafka needs to be restarted. You are advised to modify the service-level configuration in the change window.

### Parameter Description

- If services require high availability and high performance, set the parameters listed in [Table 12-7](#) on the server. For details about the parameter configuration entry, see [Modifying Cluster Service Configuration Parameters](#).

**Table 12-7** Server HA and high performance parameters

Parameter	Default Value	Description
unclean.leader.election.enable	true	Specifies whether a replica that is not in the ISR can be selected as the leader. If this parameter is set to <b>true</b> , data may be lost.
auto.leader.rebalance.enable	true	Specifies whether the leader automated balancing function is used. If this parameter is set to <b>true</b> , the controller periodically balances the leader of each partition on all nodes and assigns the leader to a replica with a higher priority.
min.insync.replicas	1	Specifies the minimum number of replicas to which data is written when <b>acks</b> is set to <b>-1</b> for the Producer.

Set the parameters listed in [Table 12-8](#) in the client configuration file **producer.properties**. The path for storing **producer.properties** is **/opt/client/Kafka/kafka/config/producer.properties**, where **/opt/client** indicates the installation directory of the Kafka client.

**Table 12-8** Client HA and high performance parameters

Parameter	Default Value	Description
acks	1	<p>The leader needs to check whether the message has been received and determine whether the required operation has been processed. This parameter affects message reliability and performance.</p> <ul style="list-style-type: none"> <li>• If this parameter is set to <b>0</b>, the producer does not wait for any response from the server, and the message is considered successful.</li> <li>• If this parameter is set to <b>1</b>, when the leader of the replica verifies that data has been written into the cluster, the leader returns a response without waiting for data to be written to all replicas. In this case, if the leader is abnormal when the leader makes the confirmation but replica synchronization is not complete, data will be lost.</li> <li>• If this parameter is set to <b>-1</b>, the message is considered to be successfully received only when all synchronized replicas are confirmed. If the <b>min.insync.replicas</b></li> </ul>

Parameter	Default Value	Description
		parameter is also configured, data can be written into multiple replicas. In this case, records will not be lost as long as one replica remains active.

- To ensure high data reliability for services, set the parameters listed in [Table 12-9](#) on the server. For details about the parameter configuration entry, see [Modifying Cluster Service Configuration Parameters](#).

**Table 12-9** Server HA parameters

Parameter	Recommended Value	Description
unclean.leader.election.enable	false	A replica that is not in the ISR list cannot be elected as a leader.
min.insync.replicas	2	Specifies the minimum number of replicas to which data is written when <b>acks</b> is set to <b>-1</b> for the Producer. Ensure that the value of <b>min.insync.replicas</b> is equal to or less than that of <b>replication.factor</b> .

Set the parameters listed in [Table 12-10](#) in the client configuration file **producer.properties**. The path for storing **producer.properties** is **/opt/client/Kafka/kafka/config/producer.properties**, where **/opt/client** indicates the installation directory of the Kafka client.

**Table 12-10** Server HA parameters

Parameter	Recommended Value	Description
acks	-1	<p>The leader needs to check whether the message has been received and determine whether the required operation has been processed.</p> <p>If this parameter is set to <b>-1</b>, the message is considered to be successfully received only when all replicas in the ISR list have confirmed to receive the message. This parameter is used along with <b>min.insync.replicas</b> to ensure that multiple copies are successfully written. As long as one copy is active, the record will not be lost. If this parameter is set to <b>-1</b>, the production performance deteriorates. Therefore, you need to set this parameter based on the actual situation.</p>

## Configuration Suggestions

Configure parameters based on requirements on reliability and performance in the following service scenarios:

- For valued data, you are advised to configure RAID1 or RAID5 for Kafka data directory disks to improve data reliability when a single disk is faulty.
- For parameters that can be modified at the topic level, the service level configurations are used by default.

These parameters can be separately configured based on topic reliability requirements. For example, log in to the Kafka client as user **root**, and run the following command to configure the reliability parameter with topic named test in the client installation directory:

```
cd Kafka/kafka/bin
```

```
kafka-topics.sh --zookeeper 192.168.1.205:2181/kafka --alter --topic test  
--config unclean.leader.election.enable=false --config  
min.insync.replicas=2
```

**192.168.1.205** indicates the ZooKeeper service IP address.

- If parameters are at the service level, Kafka needs to be restarted. You are advised to modify the service-level configuration in the change window.

## 12.12 Changing the Broker Storage Directory

### Scenario

When a broker storage directory is added, the system administrator needs to change the broker storage directory on FusionInsight Manager, to ensure that the Kafka can work properly. The new topic partition will be generated in the directory that has fewest partitions. Changing the ZooKeeper storage directory includes the following scenarios:

#### NOTE

Because Kafka does not detect disk capacity, ensure that the disk quantity and capacity configured for each Broker instance are the same.

- Change the storage directory of the Broker role. In this way, the storage directories of all Broker instances are changed.
- Change the storage directory of a single Broker instance. In this way, only the storage directory of this Broker instance is changed, and the storage directories of other Broker instances remain the same.

### Impact on the System

- Changing the Broker role storage directory requires the restart of services. The services cannot be accessed during the restart.
- The storage directory of a single Broker instance can be changed only after the instance is restarted. The instance cannot provide services during the restart.
- The directory for storing service parameter configurations must also be updated.

### Prerequisites

- New disks have been prepared and installed on each data node, and the disks are formatted.
- The Kafka client has been installed.
- When you change the storage directory of a single Broker instance, the number of active Broker instances must be greater than the number of backups specified during topic creation.

### Procedure

#### Changing the storage directory of the Kafka role

**Step 1** Log in as user **root** to each node on which the Kafka service is installed, and perform the following operations:

1. Create a target directory.

For example, to create the target directory `${BIGDATA_DATA_HOME}/kafka/data2`, run the following command:

```
mkdir ${BIGDATA_DATA_HOME}/kafka/data2
```

2. Mount the directory to the new disk. For example, mount `${BIGDATA_DATA_HOME}/kafka/data2` to the new disk.
3. Modify permissions on the new directory.

For example, to modify permissions on the `${BIGDATA_DATA_HOME}/kafka/data2` directory, run the following commands:

```
chmod 700 ${BIGDATA_DATA_HOME}/kafka/data2 -R and chown omm:wheel ${BIGDATA_DATA_HOME}/kafka/data2 -R
```

**Step 2** Log in to FusionInsight Manager and choose **Cluster > Services > Kafka > Configurations**.

**Step 3** Add a new directory to the end of the default value of **log.dirs**.

Enter **log.dirs** in the search box and add the new directory to the end of the default value of the **log.dirs** configuration item. Use commas (,) to separate multiple directories. For example:

```
${BIGDATA_DATA_HOME}/kafka/data1/kafka-logs,${BIGDATA_DATA_HOME}/kafka/data2/kafka-logs
```

**Step 4** Click **Save**, and then click **OK**. When **Operation succeeded** is displayed, click **Finish**.

**Step 5** Choose **Cluster > Services > Kafka**. In the upper right corner, choose **More > Restart Service** to restart the Kafka service.

### Changing the storage directory of a single Kafka instance

**Step 6** Log in to the Broker node as user **root** and perform the following operations:

1. Create a target directory.

For example, to create the target directory `${BIGDATA_DATA_HOME}/kafka/data2`, run the following command:

```
mkdir ${BIGDATA_DATA_HOME}/kafka/data2
```

2. Mount the directory to the new disk. For example, mount `${BIGDATA_DATA_HOME}/kafka/data2` to the new disk.
3. Modify permissions on the new directory.

For example, to modify permissions on the `${BIGDATA_DATA_HOME}/kafka/data2` directory, run the following commands:

```
chmod 700 ${BIGDATA_DATA_HOME}/kafka/data2 -R and chown omm:wheel ${BIGDATA_DATA_HOME}/kafka/data2 -R
```

**Step 7** Log in to FusionInsight Manager and choose **Cluster > Services > Kafka > Instance**.

**Step 8** Click the specified broker instance and switch to **Instance Configurations**.

Enter **log.dirs** in the search box and add the new directory to the end of the default value of the **log.dirs** configuration item. Use commas (,) to separate multiple directories, for example, `${BIGDATA_DATA_HOME}/kafka/data1/kafka-logs,${BIGDATA_DATA_HOME}/kafka/data2/kafka-logs`.

- Step 9** Click **Save**, and then click **OK**. A message is displayed, indicating that the operation is successful. Click **Finish**.
- Step 10** On the Broker instance page, choose **More > Restart Instance** to restart the Broker instance.
- End

## 12.13 Checking the Consumption Status of Consumer Group

### Scenario

This section describes how to view the current expenditure on the client based on service requirements.

### Prerequisites

- The system administrator has understood service requirements and prepared a system user.
- The Kafka client has been installed.

### Procedure

- Step 1** Log in as a client installation user to the node on which the Kafka client is installed.
- Step 2** Switch to the Kafka client installation directory, for example, **/opt/kafkaclient**.
- ```
cd /opt/kafkaclient
```
- Step 3** Run the following command to configure environment variables:
- ```
source bigdata_env
```
- Step 4** Run the following command to perform user authentication (skip this step in normal mode):
- ```
kinit Component service user
```
- Step 5** Run the following command to switch to the Kafka client installation directory:
- ```
cd Kafka/kafka/bin
```
- Step 6** Run the **kafka-consumer-groups.sh** command to check the current consumption status.
- Check the Consumer Group list on Kafka saved by Offset:  

```
./kafka-consumer-groups.sh --list --bootstrap-server <Service IP address of any broker node:21007> --command-config ../config/consumer.properties
```

  
eg: 

```
./kafka-consumer-groups.sh --bootstrap-server 192.168.1.1:21007 --list --command-config ../config/consumer.properties
```
  - Check the consumption status of Consumer Group on Kafka saved by Offset:

```
./kafka-consumer-groups.sh --describe --bootstrap-server <Service IP  
address of any broker node:21007> --group Consumer group name --  
command-config ../config/consumer.properties  
eg:./kafka-consumer-groups.sh --describe --bootstrap-server  
192.168.1.1:21007 --group example-group --command-config ../config/  
consumer.properties
```

---

**NOTICE**

1. Ensure that the current consumer is online and consumes data.
2. Configure the **group.id** in the **consumer.properties** configuration file and **--group** in the command to the group to be queried.
3. The Kafka cluster's IP port number is 21007 in security mode and 9092 in normal mode.

---

----End

## 12.14 Kafka Balancing Tool Instructions

### Scenario

This section describes how to use the Kafka balancing tool on a client to balance the load of the Kafka cluster based on service requirements in scenarios such as node decommissioning, node recommissioning, and load balancing.

### Prerequisites

- The system administrator has understood service requirements and prepared a Kafka administrator (belonging to the **kafkaadmin** group. It is not required for the normal mode.).
- The Kafka client has been installed.

### Procedure

- Step 1** Log in as a client installation user to the node on which the Kafka client is installed.
- Step 2** Switch to the Kafka client installation directory, for example, **/opt/kafkaclient**.
- Step 3** Run the following command to configure environment variables:  
**source bigdata\_env**
- Step 4** Run the following command to authenticate the user (skip this step in normal mode):  
**kinit Component service user**
- Step 5** Run the following command to switch to the Kafka client installation directory:  
**cd Kafka/kafka**

**Step 6** Run the **kafka-balancer.sh** command to balance user cluster. The commonly used commands are:

- Run the **--run** command to perform cluster balancing:

```
./bin/kafka-balancer.sh --run --zookeeper <ZooKeeper service IP address of any ZooKeeper node:zkPort/kafka> --bootstrap-server <Kafka cluster IP:port> --throttle 1000000 --consumer-config config/consumer.properties --show-details
```

This command consists of generation and execution of the balancing solution. **--show-details** is optional, indicating whether to print the solution details. **--throttle** indicates the bandwidth limit during the execution of the balancing solution. The unit is bytes per second (bytes/sec).

- Run the **--run** command to decommission a node:

```
./bin/kafka-balancer.sh --run --zookeeper <Service IP address of any ZooKeeper node:zkPort/kafka> --bootstrap-server <Kafka cluster IP address:port> --throttle 1000000 --consumer-config config/consumer.properties --remove-brokers <BrokerId list> --force
```

In the command, **--remove-brokers** indicates the list of broker IDs to be deleted. Multiple broker IDs are separated by commas (.). **--force** is optional, indicating that the disk usage alarm is ignored and the migration solution is forcibly generated.

- Run the following command to view the execution status:

```
./bin/kafka-balancer.sh --status --zookeeper <Service IP address of any ZooKeeper node:zkPort/kafka>
```

- Run the following command to generate a balancing solution:

```
./bin/kafka-balancer.sh --generate --zookeeper <Service IP address of any ZooKeeper node:zkPort/kafka> --bootstrap-server <Kafka cluster IP address:port> --consumer-config config/consumer.properties
```

This command is used to generate a migration solution based on the current cluster status and print the solution to the console.

- Clearing the intermediate status

```
./bin/kafka-balancer.sh --clean --zookeeper <Service IP address of any ZooKeeper node:zkPort/kafka>
```

This command is used to clear the intermediate status information on the ZooKeeper when the migration is not complete.

---

#### NOTICE

The port number of the Kafka cluster's IP address is 21007 in security mode and 9092 in normal mode.

---

----End

## Troubleshooting

During partition migration using the Kafka balancing tool, if the execution progress of the balancing tool is blocked due to a Broker fault in the cluster, you need to manually rectify the fault. The scenarios are as follows:

- The Broker is faulty because the disk usage reaches 100%.
  - a. Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Kafka** > **Instance**, stop the Broker instance in the **Restoring** state, and record the management IP address of the node where the instance resides and the corresponding **broker.id**. You can click the role name to view the value, on the **Instance Configurations** page, select **All Configurations** and search for the **broker.id** parameter.
  - b. Log in to the recorded management IP address as user **root**, and run the **df -lh** command to view the mounted directory whose disk usage is 100%, for example, `/${BIGDATA_DATA_HOME}/kafka/data1`.
  - c. Go to the directory, run the **du -sh \*** command to view the size of each file in the directory, Check whether files other than files in the **kafka-logs** directory exist, and determine whether these files can be deleted or migrated.
    - If yes, delete or migrate the related data and go to **8**.
    - If no, go to **4**.
  - d. Go to the **kafka-logs** directory, run the **du -sh \*** command, select a partition folder to be moved. The naming rule is **Topic name-Partition ID**. Record the topic and partition.
  - e. Modify the **recovery-point-offset-checkpoint** and **replication-offset-checkpoint** files in the **kafka-logs** directory in the same way.
    - i. Decrease the number in the second line in the file. (To remove multiple directories, the number deducted is equal to the number of files to be removed.
    - ii. Delete the line of the to-be-removed partition. (The line structure is "*Topic name Partition ID Offset*". Save the data before deletion. Subsequently, the content must be added to the file of the same name in the destination directory.)
  - f. Modify the **recovery-point-offset-checkpoint** and **replication-offset-checkpoint** files in the destination data directory (for example, `/${BIGDATA_DATA_HOME}/kafka/data2/kafka-logs`) in the same way.
    - Increase the number in the second line in the file. (To move multiple directories, the number added is equal to the number of files to be moved.
    - Add the to-be moved partition to the end of the file. (The line structure is "*Topic name Partition ID Offset*". You can copy the line data saved in **5**.)
  - g. Move the partition to the destination directory. After the partition is moved, run the **chown omm:wheel -R Partition directory** command to modify the directory owner group for the partition.
  - h. Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **Kafka** > **Instance** to start the stopped Broker instance.
  - i. Wait for 5 to 10 minutes and check whether the health status of the Broker instance is **Good**.

- If yes, resolve the disk capacity insufficiency problem according to the handling method of "ALM-38001 Insufficient Kafka Disk Capacity" after the alarm is cleared.
- If no, contact O&M support.

After the faulty Broker is recovered, the blocked balancing task continues. You can run the **--status** command to view the task execution progress.

- The Broker fault occurs because of other causes, the fault scenario is clear, and the fault can be rectified within a short period of time.
  - a. Restore the faulty Broker according to the root cause.
  - b. After the faulty Broker is recovered, the blocked balancing task continues. You can run the **--status** command to view the task execution progress.
- The Broker fault occurs because of other causes, the fault scenario is complex, and the fault cannot be rectified within a short period of time.
  - a. Run the **kinit *Kafka administrator account*** command (skip this step in normal mode).
  - b. Run the **zkCli.sh -server <ZooKeeper cluster service IP address.zkPort/ kafka>** command to log in to ZooKeeper Shell.
  - c. Run the **addauth krbgroup** command (skip this step in normal mode).
  - d. Delete the **/admin/reassign\_partitions** and **/controller** directories.
  - e. Perform the preceding steps to forcibly stop the migration. After the cluster recovers, run the **kafka-reassign-partitions.sh** command to delete redundant copies generated during the intermediate process.

## 12.15 Kafka Token Authentication Mechanism Tool Usage

### Scenario

Operations need to be performed on tokens when the token authentication mechanism is used.

### Prerequisites

- The system administrator has understood service requirements and prepared a system user.
- The Kafka client has been installed.

### Procedure

- Step 1** Log in as a client installation user to the node on which the Kafka client is installed.
- Step 2** Switch to the Kafka client installation directory, for example, **/opt/kafkaclient**.  
**cd /opt/kafkaclient**
- Step 3** Run the following command to configure environment variables:

**source bigdata\_env**

**Step 4** Run the following command to perform user authentication (skip this step in normal mode):

**kinit** *Component service user*

**Step 5** Run the following command to switch to the Kafka client installation directory:

**cd** Kafka/kafka/bin

**Step 6** Use **kafka-delegation-tokens.sh** to perform operations on tokens.

- Generate a token for a user.

```
./kafka-delegation-tokens.sh --create --bootstrap-server <IP1:PORT, IP2:PORT,...> --max-life-time-period <Long: max life period in milliseconds> --command-config <config file> --renewer-principal User:<user name>
```

Example: **./kafka-delegation-tokens.sh --create --bootstrap-server 192.168.1.1:21007,192.168.1.2:21007,192.168.1.3:21007 --command-config ../config/producer.properties --max-life-time-period -1 --renewer-principal User:username**

- List information about all tokens of a specified user.

```
./kafka-delegation-tokens.sh --describe --bootstrap-server <IP1:PORT, IP2:PORT,...> --command-config <config file> --owner-principal User:<user name>
```

Example: **./kafka-delegation-tokens.sh --describe --bootstrap-server 192.168.1.1:21007,192.168.1.2:21007,192.168.1.3:21007 --command-config ../config/producer.properties --owner-principal User:username**

- Update the token validity period.

```
./kafka-delegation-tokens.sh --renew --bootstrap-server <IP1:PORT, IP2:PORT,...> --renew-time-period <Long: renew time period in milliseconds> --command-config <config file> --hmac <String: HMAC of the delegation token>
```

Example: **./kafka-delegation-tokens.sh --renew --bootstrap-server 192.168.1.1:21007,192.168.1.2:21007,192.168.1.3:21007 --renew-time-period -1 --command-config ../config/producer.properties --hmac ABCDEFG**

- Destroy a token.

```
./kafka-delegation-tokens.sh --expire --bootstrap-server <IP1:PORT, IP2:PORT,...> --expiry-time-period <Long: expiry time period in milliseconds> --command-config <config file> --hmac <String: HMAC of the delegation token>
```

Example: **./kafka-delegation-tokens.sh --expire --bootstrap-server 192.168.1.1:21007,192.168.1.2:21007,192.168.1.3:21007 --expiry-time-period -1 --command-config ../config/producer.properties --hmac ABCDEFG**

----End

## 12.16 Kafka Feature Description

### Kafka Idempotent Feature

Feature description: The function of creating idempotent producers is introduced in Kafka 0.11.0.0. After this function is enabled, producers are automatically upgraded to idempotent producers. When producers send messages with the same field values, brokers automatically detect whether the messages are duplicate to avoid duplicate data. Note that this feature can only ensure idempotence in a single partition. That is, an idempotent producer can ensure that no duplicate messages exist in a partition of a topic. Only idempotence on a single session can be implemented. The session refers to the running of the producer process. That is, idempotence cannot be ensured after the producer process is restarted.

Method for enabling this feature:

1. Add **props.put("enable.idempotence", true)** to the secondary development code.
2. Add **enable.idempotence = true** to the client configuration file.

### Kafka Transaction Feature

Feature description: Kafka 0.11 introduces the transaction feature. The Kafka transaction feature indicates that a series of producer message production and consumer offset submission operations are in the same transaction, or are regarded as an atomic operation. Message production and offset submission succeed or fail at the same time. This feature provides transactions at the Read Committed isolation level to ensure that multiple messages are written to the target partition atomically and that the consumer can view only the transaction messages that are successfully submitted. The transaction feature of Kafka is used in the following scenarios:

1. Multiple pieces of data sent by a producer can be encapsulated in a transaction to form an atomic operation. All messages are successfully sent or fail to be sent.
2. read-process-write mode: Message consumption and production are encapsulated in a transaction to form an atomic operation. In a streaming application, a service usually needs to receive messages from the upstream system, process the messages, and then send the processed messages to the downstream system. This corresponds to message consumption and production.

Example of secondary development code:

```
// Initialize the configuration and enable the transaction feature.
Properties props = new Properties();
props.put("enable.idempotence", true);
props.put("transactional.id", "transaction1");
...
KafkaProducer producer = new KafkaProducer<String, String>(props);

// init transaction
producer.initTransactions();
try {
```

```
// Start a transaction.  
producer.beginTransaction();  
producer.send(record1);  
producer.send(record2);  
// Stop a transaction.  
producer.commitTransaction();  
} catch (KafkaException e) {  
    // Abort a transaction.  
    producer.abortTransaction();  
}
```

## Ranger Unified Authentication

Feature description: In versions earlier than Kafka 2.4.0, Kafka supports only the SimpleAclAuthorizer authentication plugin provided by the community. In Kafka 2.4.0 and later versions, MRS Kafka supports both the Ranger authentication plugin and the authentication plugin provided by the community. Ranger authentication is used by default. Based on the Ranger authentication plugin, fine-grained Kafka ACL management can be performed.

### NOTE

If the Ranger authentication plugin is used on the server and **allow.everyone.if.no.acl.found** is set to **true**, all actions are allowed when a non-secure port is used for access. You are advised to disable **allow.everyone.if.no.acl.found** for security clusters that use the Ranger authentication plugin.

## 12.17 Using Kafka UI

### 12.17.1 Accessing Kafka UI

#### Scenario

After the Kafka component is installed in an MRS cluster, you can use Kafka UI to query cluster information, node status, topic partitions, and data production and consumption details. Kafka UI provides a GUI for users to create and delete topics, modify configurations, as well as add and migrate partitions, simplifying user operations and improving O&M efficiency.

#### Prerequisites

You have created a user who has the permission to access Kafka UI. To perform related operations on the page, for example, creating a topic, you need to grant related permissions to the user. For details, see [Managing Kafka User Permissions](#).

#### Impact on the System

Site trust must be added to the browser when you access Manager and Kafka UI for the first time. Otherwise, Kafka UI cannot be accessed.

## Procedure

**Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Kafka**.

**Step 2** On the right of **KafkaManager WebUI**, click the URL to access Kafka UI.

You can perform the following operations on Kafka UI:

- Redistribute partitions in the cluster.
- Create, view, and delete topics.
- Add partitions to existing topics and modify configurations.
- View produced data in a topic.
- View broker information.
- View the consumption information about the consumer group.

----End

## 12.17.2 Kafka UI Overview

### Scenario

After logging in to Kafka UI, you can view the basic information about the existing topics, brokers, and consumer groups in the current cluster on the home page. You can also create and delete topics, modify configurations, and add and migrate partitions in the cluster.

### Procedure

#### Cluster Summary

**Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).

**Step 2** In the **Cluster Summary** area, view the number of existing topics, brokers, and consumer groups in the current cluster.



- Step 3** Click the number under **Brokers**. The **Brokers** page is displayed. For details about the operations on this page, see [Viewing Brokers on Kafka UI](#).
- Click the number under **Topics**. The **Topics** page is displayed. For details about the operations on this page, see [Managing Topics on Kafka UI](#).
- Click the number under **Consumer Group**. The **Consumers** page is displayed. For details about the operations on this page, see [Viewing a Consumer Group on Kafka UI](#).

----End

#### Cluster Action

- Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).
- Step 2** In the **Cluster Action** area, create topics and migrate partitions. For details, see [Creating a Topic on Kafka UI](#) and [Migrating a Partition on Kafka UI](#).

----End

#### Topic Rank

- Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).
- Step 2** In the **Topic Rank** column, view top 10 topics by the number of topic logs, data volume, incoming data volume, and outgoing data volume in the current cluster.

Topic Rank

Topic Logsize Top 10				Topic Capacity Top 10			
RankID	TopicName	Logsize	Default Topic	RankID	TopicName	Capacity	Default Topic
1	test1	142171968	false	1	test1	15.9GB	false
2	__consumer_offsets	16174	true	2	__default_metrics	12.0MB	true
3	__default_metrics	14148	true	3	__consumer_offsets	2.9MB	true
4	__KafkaMetricReport	3477	true	4	__KafkaMetricReport	679.5KB	true
5	cdi-connect-configs	20	false	5	cdi-connect-configs	3.8KB	false
6	test2	5	false	6	test2	225.0B	false
7	test2	3	false	7	test2	147.0B	false
8	cdi-connect-offsets	0	false	8	cdi-connect-offsets	0.0B	false
9	cdi-connect-status	0	false	9	cdi-connect-status	0.0B	false
10				10			

**Step 3** Click a topic name in the **TopicName** column to go to the topic details page. For details about operations on the page, see [Managing Topics on Kafka UI](#).

----End

### 12.17.3 Creating a Topic on Kafka UI

#### Scenario

Create a topic on Kafka UI.

#### Creating a Topic

- Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).
- Step 2** Click **Create Topic**. On the displayed page, configure parameters by referring to [Table 12-11](#) and click **Create**.

**Table 12-11** Topic information

Parameter	Description	Remarks
Topic	Topic name, which can contain a maximum of 249 characters. Only letters, digits, hyphens (-), and underscores (_) are allowed.	Example: <b>kafka_ui</b>
Partitions	Number of topic partitions. The value must be greater than or equal to 1. The default value is <b>3</b> .	-
Replication Factor	Replication factor of a topic. The value ranges from 1 to <i>N</i> . <i>N</i> indicates the number of brokers in the current cluster. The default value is <b>2</b> .	-

 NOTE

- You can click **Advanced Options** to set advanced topic parameters based on service requirements. Generally, retain the default values.
- In a cluster in security mode, the user who creates a topic must belong to the **kafkaadmin** user group. Otherwise, the topic cannot be created due to authentication failure.
- In a cluster in non-security mode, no authentication is required for creating a topic. That is, any user can create a topic.

----End

## 12.17.4 Migrating a Partition on Kafka UI

### Scenario

Migrate a partition on Kafka UI.

 NOTE

- In security mode, the user who migrates a partition must belong to the **kafkaadmin** user group. Otherwise, the operation fails due to authentication failure.
- In non-security mode, Kafka UI does not authenticate any operation.

### Migrating a Partition

- Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#). Click **Generate assignment**. The **Generate Partition Assignments** page is displayed.
- Step 2** In the **Brokers** area, select brokers to which the topic is to be re-assigned.
- Step 3** Click **Generate Partition Assignments** to generate a partition migration solution.

**Generate Partition Assignments**

Choose brokers to reassign topic to:

\* Brokers:

Select All  
 1       2       3

Current Assignments

Partition	Replicas
__KafkaMetricReport-0	[3, 2]
__KafkaMetricReport-1	[1, 3]
cdl-connect-configs-0	[3, 1, 2]
cdl-connect-status-0	[1, 3, 2]
cdl-connect-status-1	[2, 1, 3]
cdl-connect-status-2	[3, 2, 1]
cdl-connect-status-3	[1, 2, 3]
cdl-connect-status-4	[2, 3, 1]
cdl-connect-offsets-0	[1, 3, 2]

**Step 4** Click **Run assignment** to migrate a partition.

----End

## 12.17.5 Managing Topics on Kafka UI

### Scenario

On Kafka UI, you can view topic details, modify topic configurations, add topic partitions, delete topics, and view the number of data records produced in different time segments in real time.

#### NOTE

- In security mode, Kafka UI does not authenticate the operation of viewing topic details. That is, any user can query topic information. To modify topic configurations, add topic partitions, or delete topics, ensure that the Kafka UI login user belongs to the **kafkaadmin** user group or grant the corresponding operation permissions to the user. Otherwise, the authentication fails.
- In non-security mode, Kafka UI does not authenticate any operation.

### Viewing Topic Details

**Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).

**Step 2** Click **Topics**. The topic management page is displayed.

**Step 3** In the **Topic List** area, you can view the names, status, number of partitions, creation time, and number of replicas of topics created in the current cluster.

Name	Status	Partitions Num	Replication Num	Created Time	Operation
<a href="#">__KafkaMetricReport</a>	ACTIVE	2	2	2021-06-18 18:54:02	Action ▾
<a href="#">__consumer_offsets</a>	ACTIVE	50	3	2021-06-18 18:54:02	Action ▾
<a href="#">__default_metrics</a>	ACTIVE	12	3	2021-06-18 18:54:03	Action ▾
<a href="#">cdl-connect-configs</a>	ACTIVE	1	3	2021-06-18 20:03:04	Action ▾
<a href="#">cdl-connect-offsets</a>	ACTIVE	25	3	2021-06-18 20:03:02	Action ▾
<a href="#">cdl-connect-status</a>	ACTIVE	5	3	2021-06-18 20:03:03	Action ▾


Producer Message

**Step 4** Click a topic name to view details about the topic and partition.

Partition Summary

Partition Id	Leader	Replicas	In Sync Replicas	Logsize ⓘ	Start Offset	End Offset
0	1	[1, 2, 3]	[1, 2, 3]	0.0B	0	0
1	2	[2, 3, 1]	[2, 3, 1]	0.0B	0	0
2	3	[3, 1, 2]	[3, 1, 2]	0.0B	0	0
3	1	[1, 3, 2]	[1, 3, 2]	0.0B	0	0
4	2	[2, 1, 3]	[2, 1, 3]	0.0B	0	0
5	3	[3, 2, 1]	[3, 2, 1]	3.0MB	0	14583
6	1	[1, 2, 3]	[1, 2, 3]	0.0B	0	0
7	2	[2, 3, 1]	[2, 3, 1]	0.0B	0	0
8	3	[3, 1, 2]	[3, 1, 2]	0.0B	0	0
9	1	[1, 3, 2]	[1, 3, 2]	0.0B	0	0

**Step 5** In the **Producer Message** area, you can select **Day**, **Week**, or **Month** based on service requirements to view the number of data records produced in the topic.



----End

## Modifying the Topic Configuration

**Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).

**Step 2** Click **Topics**. The topic management page is displayed.

**Step 3** In the **Operation** column of the item to be modified, choose **Action > Config**. On the displayed page, change the values of **Key** and **Value** of the topic. To add multiple items, click **+**.

**Step 4** Click **OK**.

----End

## Searching for a Topic

**Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).

**Step 2** Click **Topics**. The topic management page is displayed.

**Step 3** In the upper right corner of the page, enter a topic name to search for the topic.

----End

## Adding a Partition

**Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).

**Step 2** Click **Topics**. The topic management page is displayed.

**Step 3** In the **Operation** column of the item to be modified, choose **Action > Alter**. On the displayed page, modify the topic partition.

### NOTE

Currently, you can only add partitions to a cluster. That is, the number of partitions after modification must be greater than the number of original partitions.

**Step 4** Click **OK**.

----End

## Deleting a Topic

**Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).

**Step 2** Click **Topics**. The topic management page is displayed.

**Step 3** In the **Operation** column of the item to be modified, choose **Action > Delete**.

**Step 4** In the confirmation dialog box that is displayed, click **OK**.

### NOTE

The default built-in topics cannot be deleted.


----End

## Viewing the Number of Data Records Produced

**Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).

**Step 2** Click **Topics**. The topic management page is displayed.

**Step 3** In the **Producer Message** area, you can select **Day**, **Week**, or **Month** to view the number of data records produced in different time segments in the current cluster.



----End

## 12.17.6 Viewing Brokers on Kafka UI

### Scenario

On Kafka UI, you can view broker details and JMX metrics of the broker node data traffic.

### Viewing a Broker

**Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).

**Step 2** Click **Brokers**. The broker details page is displayed.

**Step 3** In the **Broker Summary** area, you can view **Broker ID**, **Host**, **Rack**, **Disk(Used|Total)**, and **Memory(Used|Total)** of brokers.

Broker ID	Host	Rack	Disk(Used Total)	Memory(Used Total)
1	10.112.17.150	/default/rack0	40.2MB   9.1GB	4.4G   6G
2	10.112.17.189	/default/rack0	40.2MB   9.1GB	4.4G   6G
3	10.112.17.228	/default/rack0	41.3MB   9.1GB	4.4G   6G

**Step 4** In the **Brokers Metrics** area, you can view the JMX metrics of the broker node data traffic, including the average number of incoming messages per second, number of bytes of incoming messages per second, number of bytes of outgoing messages per second, and number of failed requests per second, total number of requests per second, and number of production requests per second in different time windows.

Brokers Metrics ©

Window	Message in /sec	Bytes in /sec	Bytes out /sec	Failed fetch request /sec	Total fetch request /sec	Total produce request /sec
1 min	60067	6639249	10	0	106415	1339
5 min	16769	1855373	10	0	30536	372
15 min	5937	658534	136	0	11611	132
All time	1850	224273	170077	0	17220	122

----End

## Searching for a Broker

- Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).
- Step 2** Click **Brokers**. The broker details page is displayed.
- Step 3** In the upper right corner of the page, you can enter a host IP address or rack configuration information to search for a broker.

----End

## 12.17.7 Viewing a Consumer Group on Kafka UI

### Scenario

On Kafka UI, you can view the basic information about a consumer group and the consumption status of topics in the group.

### Viewing a Consumer Group

- Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).
- Step 2** Click **Consumers**. On the consumer group details page that is displayed, you can view all consumer groups in the current cluster and the IP address of the node where each consumer group coordinator is located. In the upper right corner of the page, you can enter a consumer group name to search for the specified consumer group.

### Consumer Summary

Q

Group	Topics	Coordinator	Active Topics
<a href="#">example-group11</a>	2	10.244.228.252	0
<a href="#">example-group4</a>	1	10.244.229.85	0
<a href="#">example-group5</a>	1	10.244.229.170	0
<a href="#">example-group6</a>	1	10.244.229.85	0
<a href="#">example-group7</a>	1	10.244.228.252	0
<a href="#">example-group8</a>	1	10.244.229.170	0
<a href="#">__KafkaMetricReportGroup</a>	1	10.244.228.252	0
<a href="#">example-group9</a>	1	10.244.229.85	0
<a href="#">example-group10</a>	1	10.244.228.89	0
<a href="#">example-group1</a>	1	10.244.229.85	0

**Step 3** In the **Consumer Summary** area, you can view the existing consumer groups in the current cluster. You can click a consumer group name to view the topics consumed by the consumer group. Consumed topics can be in the **pending** or **running** state. **pending** indicates that the topic has been consumed but not being consumed. **running** indicates that the topic is being consumed. You can enter a topic name in the upper right corner of the dialog box to filter topics.

### Consumer Topics

Q

test0

Topic	Consumer Status
<a href="#">123456789012345678901234567890123456789...</a>	pending
<a href="#">test0</a>	pending

**Step 4** Click a topic name. On the **Consumer Offsets** page that is displayed, view the topic consumption details.


Consumer Offsets  
example-group11 : aaa

Partition	Log End Offset	Current Offset	Lag	ConsumerID	Host
0	21683	18206	3477	consumer-example-group11-1-7c65fa74-01...	10.244.228.252
1	21498	18155	3343	consumer-example-group11-1-7c65fa74-01...	10.244.228.252

----End

## Viewing the Consumption Lineage Graph

- Step 1** Log in to Kafka UI. For details, see [Accessing Kafka UI](#).
- Step 2** Click **Consumers**. The consumer group details page is displayed. In the **Active Topic** area, view all consumer groups in the current cluster and topics that are being consumed by each consumer group.



**NOTE**

MRS clusters do not support redirection by clicking a consumer group name.

----End

## 12.18 Introduction to Kafka Logs

### Log Description

**Log paths:** The default storage path of Kafka logs is `/var/log/Bigdata/kafka`. The default storage path of audit logs is `/var/log/Bigdata/audit/kafka`.

Broker: `/var/log/Bigdata/kafka/broker` (run logs)

Log archive rule: The automatic Kafka log compression function is enabled. By default, when the size of logs exceeds 30 MB, logs are automatically compressed

into a log file named in the following format: *<Original log file name>-<yyyy-mm-dd\_hh-mm-ss>.[ID].log.zip*. A maximum of 20 latest compressed files are retained by default. You can configure the number of compressed files and the compression threshold.

**Table 12-12** Broker log list

Type	Log File Name	Description
Run log	server.log	Server run log of the broker process
	controller.log	Controller run log of the broker process
	kafka-request.log	Request run log of the broker process
	log-cleaner.log	Cleaner run log of the broker process
	state-change.log	State-change run log of the broker process
	kafkaServer-<SSH_USER>-<DATE>-<PID>-gc.log	GC log of the broker process
	postinstall.log	Work log after broker installation
	prestart.log	Work log before broker startup
	checkService.log	Log that records whether broker starts successfully
	start.log	Startup log of the broker process
	stop.log	Stop log of the broker process
	checkavailable.log	Log that records the health check details of the Kafka service
	checkInstanceHealth.log	Log that records the health check details of broker instances
	kafka-authorizer.log	Broker authorization log
	kafka-root.log	Broker basic log
cleanup.log	Cleanup log of broker uninstallation	

Type	Log File Name	Description
	metadata-backup-recovery.log	Broker backup and recovery log
	ranger-kafka-plugin-enable.log	Log that records the Ranger plug-ins enabled by brokers
	server.out	Broker JVM log
	audit.log	Authentication log of the Ranger authentication plug-in. This log is archived in the <b>/var/log/Bigdata/audit/kafka</b> directory.

## Log Level

**Table 12-13** describes the log levels supported by Kafka.

Levels of run logs are ERROR, WARN, INFO, and DEBUG from the highest to the lowest priority. Run logs of equal or higher levels are recorded. The higher the specified log level, the fewer the logs recorded.

**Table 12-13** Log levels

Level	Description
ERROR	Logs of this level record error information about system running.
WARN	Logs of this level record exception information about the current event processing.
INFO	Logs of this level record normal running status information about the system and events.
DEBUG	Logs of this level record the system information and system debugging information.

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page. See **Modifying Cluster Service Configuration Parameters**.
- Step 2** On the menu bar on the left, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Save the configuration. In the displayed dialog box, click **OK** to make the configurations take effect.

----End

## Log Format

The following table describes the Kafka log format.

**Table 12-14** Log formats

Type	Format	Example
Run log	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> <Thread that generates the log> <Message in the log> <Full name of the log event invocation class>(<Log file>:<Row>)	2015-08-08 11:09:53,483   INFO   [main]   Loading logs.   kafka.log.LogManager (Logging.scala:68)
	<yyyy-MM-dd HH:mm:ss><HostName> <Component name><LogLevel><Message>	2015-08-08 11:09:51 10-165-0-83 Kafka INFO Running kafka-start.sh.

## 12.19 Performance Tuning

### 12.19.1 Kafka Performance Tuning

#### Scenario

You can modify Kafka server parameters to improve Kafka processing capabilities in specific service scenarios.

#### Parameter Tuning

Modify the service configuration parameters. For details, see [Modifying Cluster Service Configuration Parameters](#). For details about the tuning parameters, see [Table 12-15](#).

**Table 12-15** Tuning parameters

Parameter	Default Value	Scenario
num.recovery.threads.per.data.dir	10	During the Kafka startup process, if a large volume of data exists, you can increase the value of this parameter to accelerate the startup.

Parameter	Default Value	Scenario
background.threads	10	Specifies the number of threads processed by a broker background task. If a large volume of data exists, you can increase the value of this parameter to improve broker processing capabilities.
num.replica.fetchers	1	Specifies the number of threads used when a replica requests to the Leader for data synchronization. If the value of this parameter is increased, the replica I/O concurrency increases.
num.io.threads	8	Specifies the number of threads used by the broker to process disk I/O. It is recommended that the number of threads be greater than or equal to the number of disks.
KAFKA_HEAP_OPTS	-Xmx6G -Xms6G	Specifies the Kafka JVM heap memory setting. If the data volume on the broker is large, adjust the heap memory size.

## 12.20 Common Issues About Kafka

### 12.20.1 How Do I Solve the Problem that Kafka Topics Cannot Be Deleted?

#### Question

How do I delete a Kafka topic if it fails to be deleted?

#### Answer

- Possible cause 1: The **delete.topic.enable** configuration item is not set to **true**. The deletion can be performed only when the configuration item is set to **true**.
- Possible cause 2: The **auto.create.topics.enable** configuration parameter is set to **true**, which is used by other applications and is always running in the background.

Solution:

- For cause 1: Set **delete.topic.enable** to **true** on the configuration page.

- For cause 2: Stop the application that uses the topic in the background, or set **auto.create.topics.enable** to **false** (restart the Kafka service), and then delete the topic.

# 13 Using Loader

## 13.1 Common Loader Parameters

### Navigation Path

For details about the how to set parameters, see [Modifying Cluster Service Configuration Parameters](#).

### Parameter Description

Table 13-1 Common Loader parameters

Parameter	Description	Default Value	Value Range
mapreduce.client.submit.file.replication	Number of copies of the job files that the MapReduce task depends on in HDFS. If the number of DataNodes in the cluster is less than the value of this parameter, the number of copies is equal to the number of DataNodes. If the number of DataNodes is greater than or equal to the value of this parameter, the number of copies is the value of this parameter.	10	3 to 256

Parameter	Description	Default Value	Value Range
loader.fault.tolerance.rate	Error tolerance. If the value is greater than 0, the error tolerance mechanism is enabled. When enabling the fault tolerance mechanism, you are advised to set the number of Map jobs to be greater than or equal to 3. It is recommended that this function be used when the job data volume is large.	0	0 to 1.0
loader.input.field.separator	Default input field separator. The parameter value takes effect only when input and output conversion steps are configured. The conversion steps can be left blank. If no separators are configured in job conversion steps, the default separator is used.	,	-
loader.input.line.separator	Default input line separator. The parameter value takes effect only when input and output conversion steps are configured. The conversion steps can be left blank. If no separators are configured in job conversion steps, the default separator is used.	-	-
loader.output.field.separator	Default output field separator. The parameter value takes effect only when input and output conversion steps are configured. The conversion steps can be left blank. If no separators are configured in job conversion steps, the default separator is used.	,	-
loader.output.line.separator	Line separator of data that Loader outputs	-	-

 NOTE

- Because it needs time to calculate the fault tolerance rate, you are recommended to use the **loader.fault.tolerance.rate** parameter when the job runtime is longer than 2 minutes to ensure user experience.
- Default separators are configured for the parameters in the preceding table for Loader. If separators are configured in the conversion steps for the jobs, the separators in the conversion steps will be used. If separators are not configured in the conversion steps, the default separators will be used.

## 13.2 Creating a Loader Role

### Scenario

This section describes how to create and configure a Loader role on FusionInsight Manager. The Loader role can set Loader administrator permissions, job connections, job groups, and Loader job operation and scheduling permissions.

### Prerequisites

- The system administrator has understood the service requirements.
- You have logged in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).

### Procedure

**Step 1** Choose **System > Permission > Role**.

**Step 2** Click **Create Role** and set a role name and enter description.

**Step 3** Set permissions. For details, see [Table 13-2](#).

 NOTE

When setting permissions for a role, you cannot set permissions for multiple resources at the same time. If you need to set permissions for multiple resources, set them one by one.

Loader permissions:

- **Admin:** Loader administrator permission
- **Job Connector:** connection permission of Loader
- **Job Group:** permission to perform operations on Loader job groups. You can set the operation permissions of a specific job in a specified job group, including the **Edit** and **Execute** permissions of the job.
- **Job Scheduler:** permission to schedule Loader jobs

**Table 13-2** Setting Loader roles

Task	Role Authorization
Setting the Loader administrator permission	In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> > <b>Loader</b> and select <b>Admin</b> .
Setting the connection permission of Loader (including the editing, deletion, and reference permissions of Job Connection)	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Loader</b> &gt; <b>Job Connector</b>.</li> <li>2. In the <b>Permission</b> column of the specified job link, select <b>Edit</b>.</li> </ol>
Setting the edit permission for Loader job groups (including modifying the name of a job group, deleting a specified group, creating jobs in a specified group, importing jobs from external systems to a specified group in batches, and migrating jobs from other groups to a specified group)	<ol style="list-style-type: none"> <li>1. In the <b>Permission</b> table, choose <b>Loader</b> &gt; <b>Job Group</b>.</li> <li>2. In the <b>Permission</b> column of the specified job group, select <b>Edit Group</b>.</li> </ol>
Setting the edit permission for all jobs in a Loader job group (including the permission to edit all existing or new jobs in the group)	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Loader</b> &gt; <b>Job Group</b>.</li> <li>2. In the <b>Permission</b> column of the specified job group, select <b>Edit Job</b>.</li> </ol>
Setting the execution permission for all jobs in the Loader job group (including the execution permission on all existing or new jobs in the group)	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Loader</b> &gt; <b>Job Group</b>.</li> <li>2. In the <b>Permission</b> column of the specified job group, select <b>Execute Job</b>.</li> </ol>
Setting the edit permission for Loader jobs (including editing, deleting, copying, and exporting jobs)	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Loader</b> &gt; <b>Job Group</b>.</li> <li>2. Select a job group.</li> <li>3. In the <b>Permission</b> column of the specified job, select <b>Edit</b>.</li> </ol>

Task	Role Authorization
Setting the execution permission for Loader jobs (including permissions to start and stop jobs and view historical records)	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Loader</b> &gt; <b>Job Group</b>.</li> <li>2. Select a job group.</li> <li>3. In the <b>Permission</b> column of the specified job, select <b>Execute</b>.</li> </ol>
Setting the permission for scheduling Loader jobs (including the editing, deletion, and validation permissions of Scheduler)	<ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Loader</b> &gt; <b>Job Scheduling</b>.</li> <li>2. In the <b>Permission</b> column of the specified job scheduling row, select <b>Edit</b>.</li> </ol>

 **NOTE**

1. In addition to **Admin**, the preceding permissions are configured only for inventory resource information.
2. Users without the preceding roles can also create tasks, groups, and connectors, but cannot perform operations on inventory resources.

**Step 4** Click **OK**, and return to the **Role** page.

----End

## 13.3 Managing Loader Links

### Scenarios

You can create, view, edit, and delete links on the Loader page.

### Creating a Connection

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster** > **Services**.
- Step 2** Select **Loader**. On the right of **Loader WebUI**, click the link to open the Loader web UI.
- Step 3** On the Loader page, click **New job**.
- Step 4** Click **Add** next to **Connection** and set connection parameters.  
For details about the parameters, see [Loader Connection Configuration](#).
- Step 5** Click **OK**.

If connection configurations, for example, IP address, port, and access user information, are incorrect, the connection will fail to be verified and saved.

 **NOTE**

You can click **Test** to immediately check whether the connection is available.

----End

## Viewing a Connection

**Step 1** On the Loader page, click **New job**.

**Step 2** Click the drop-down list of **Connection** to view the connections you have created.

----End

## Editing a Connection

**Step 1** On the Loader page, click **New job**.

**Step 2** Select the name of the connection to be edited from the **Connection** drop-down list.

**Step 3** Click **Edit** next to **Connection**.

**Step 4** On the dialog box displayed, modify the connection parameters based on service requirements.

**Step 5** Click **Test**.

- If the test is successful, go to [Step 6](#).
- If the test fails, repeat [Step 4](#).

**Step 6** Click **Save**.

If a Loader job has integrated into a Loader link, editing the link parameters may affect Loader running.

----End

## Deleting a Connection

**Step 1** On the Loader page, click **New job**.

**Step 2** Select the name of the connection to be deleted from the **Connection** drop-down list.

**Step 3** Click **Delete**.

**Step 4** In the displayed dialog box, click **OK**.

If a Loader job has integrated a Loader connection, the connection cannot be deleted.

----End

## Loader Connection Configuration

Loader supports the following connections:

- **generic-jdbc-connector**: For details about parameter settings, see [Table 13-3](#).
- **ftp-connector**: For details about parameter settings, see [Table 13-4](#).
- **sftp-connector**: For details about parameter settings, see [Table 13-5](#).
- **hdfs-connector**: For details about parameter settings, see [Table 13-6](#).
- **oracle-connector**: For details about parameter settings, see [Table 13-7](#).
- **mysql-fastpath-connector**: For details about parameter settings, see [Table 13-9](#).
- **oracle-partition-connector**: For details about parameter settings, see [Table 13-8](#).

**Table 13-3 generic-jdbc-connector configuration**

Parameter	Description
Name	Name of a Loader connection
Connector	Select <b>generic-jdbc-connector</b> .
JDBC Driver Class	JDBC driver classes are as follows: <ul style="list-style-type: none"> <li>• oracle: <b>oracle.jdbc.driver.OracleDriver</b></li> <li>• SQLServer: <b>com.microsoft.jdbc.sqlserver.SQLServerDriver</b></li> <li>• mysql: <b>com.mysql.jdbc.Driver</b></li> <li>• postgresql: <b>org.postgresql.Driver</b></li> <li>• gaussdb200: <b>com.xxx.gauss200.jdbc.Driver</b></li> </ul>
JDBC Connection String	Database access address, which can be an IP address or domain name. Enter the database connection string. In the following examples, <b>10.10.10.10</b> indicates the IP address and <b>test</b> indicates the database name. <ul style="list-style-type: none"> <li>• oracle: <b>jdbc:oracle:thin:@10.10.10.10:1521:orcl</b></li> <li>• SQLServer: <b>jdbc:microsoft:sqlserver://10.10.10.10:1433;DatabaseName=test</b></li> <li>• mysql: <b>jdbc:mysql://10.10.10.10/test?&amp;useUnicode=true&amp;characterEncoding=GBK</b></li> <li>• postgresql: <b>jdbc:postgresql://10.10.10.10:5432/test</b></li> <li>• gaussdb200: <b>jdbc:gaussdb://10.10.10.10:15400/test</b> (15400 is an example port number.)</li> </ul>
Username	Username for accessing the database
Password	Password of the user. Use the actual password.

**Table 13-4 ftp-connector** configuration

Parameter	Description
Name	Name of a Loader connection
Connector	Select <b>ftp-connector</b> .
FTP Mode	Select <b>ACTIVE</b> or <b>PASSIVE</b> .
FTP Protocol	Select: <ul style="list-style-type: none"> <li>• FTP</li> <li>• SSL_EXPLICIT</li> <li>• SSL_IMPLICIT</li> <li>• TLS_EXPLICIT</li> <li>• TLS_IMPLICIT</li> </ul>
File Name Encoding Type	Encoding type of the file name or file path.

**Table 13-5 sftp-connector** configuration

Parameter	Description
Name	Name of a Loader connection
Connector	Select <b>sftp-connector</b> .

**Table 13-6 hdfs-connector** configuration

Parameter	Description
Name	Name of a Loader connection
Connector	Select <b>hdfs-connector</b> .

**Table 13-7 oracle-connector** configuration

Parameter	Description
Name	Name of a Loader connection
Connector	Select <b>oracle-connector</b> .
JDBC Connection String	Connection string used for connecting to the database
Username	Username for accessing the database
Password	Password of the user. Use the actual password.

**Table 13-8 oracle-partition-connector** configuration

Parameter	Description
Name	Name of a Loader connection
Connector	Select <b>oracle-partition-connector</b> .
JDBC Driver Class	Enter <b>com.microsoft.jdbc.sqlserver.SQLServerDriver</b> .
JDBC Connection String	Connection string used for connecting to the database
Username	Username for accessing the database
Password	Password of the user. Use the actual password.

**Table 13-9 mysql-fastpath-connector** configuration

Parameter	Description
Name	Name of a Loader connection
Connector	<p>Select <b>mysql-fastpath-connector</b>.</p> <p><b>NOTICE</b></p> <p>When <b>mysql-fastpath-connector</b> is used, the <b>mysqldump</b> and <b>mysqlimport</b> commands of MySQL must be available on NodeManagers, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, see <a href="http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html">http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html</a>. Install the MySQL client applications and tools.</p> <p>For example, the following RPM packages need to be installed on the RHEL-x86 system (select a version based on the site requirements):</p> <ul style="list-style-type: none"> <li>• mysql-community-client-5.7.23-1.el7.x86_64.rpm</li> <li>• mysql-community-common-5.7.23-1.el7.x86_64.rpm</li> <li>• mysql-community-devel-5.7.23-1.el7.x86_64.rpm</li> <li>• mysql-community-embedded-5.7.23-1.el7.x86_64.rpm</li> <li>• mysql-community-libs-5.7.23-1.el7.x86_64.rpm</li> <li>• mysql-community-libs-compat-5.7.23-1.el7.x86_64.rpm</li> </ul>
JDBC Connection String	Connection string used for connecting to the database
Username	Username for accessing the database
Password	Password of the user. Use the actual password.

## 13.4 Importing Data

### 13.4.1 Overview

#### Description

Loader is an ETL tool that enables MRS to exchange data and files with external data sources, such as relational databases, SFTP servers, and FTP servers. It allows data or files to be imported from relational databases or file systems to MRS.

Loader supports the following data import modes:

- Importing data from a relational database to HDFS or OBS
- Importing data from a relational database to HBase
- Importing data from a relational database to Phoenix tables
- Importing data from a relational database to Hive tables
- Importing data from an SFTP server to HDFS or OBS
- Importing data from an SFTP server to HBase
- Importing data from an SFTP server to Phoenix tables
- Importing data from an SFTP server to Hive tables
- Importing data from an FTP server to HDFS or OBS
- Importing data from an FTP server to HBase
- Importing data from an FTP server to Phoenix tables
- Importing data from an FTP server to Hive tables
- Importing data from HDFS or OBS to HBase in the same cluster

MRS needs to connect to an external data source to exchange data and files with the data source. The following connectors are used to configure connection parameters for different types of data sources:

- `generic-jdbc-connector`: relational database connector
- `ftp-connector`: FTP data source connector
- `hdfs-connector`: HDFS data source connector
- `oracle-connector`: dedicated connector for Oracle databases. **row\_id** serves as partition columns. Compared with `generic-jdbc-connector`, Map jobs are more evenly distributed on `oracle-connector`, and whether indexes have been created for the partition columns does not matter.
- `mysql-fastpath-connector`: dedicated connector for MySQL databases. Data is imported and exported by using the `mysqldump` and `mysqlimport` tools of MySQL. Compared with `generic-jdbc-connector`, `mysql-fastpath-connector` delivers a faster data import and export speed.
- `sftp-connector`: SFTP data source connector
- `oracle-partition-connector`: connector that supports the Oracle partition feature, which is used to optimize the import and export of Oracle partition tables.


 NOTE

- When an FTP data source connector is used, data is not encrypted. This may result in security risks. You are advised to use an SFTP data source connector.
- You are advised to deploy the SFTP server, FTP server, database server, and Loader into separate subnets to ensure secure data import.
- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When mysql-fastpath-connector is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManager nodes, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, install the MySQL client applications and tools following the instructions at <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>.
- When oracle-connector is used, the connection user must be granted the select permission on the following system catalogs or views:  
dba\_tab\_partitions, dba\_constraints, dba\_tables, dba\_segments, v\$version, dba\_objects, v\$instance, SYS\_CONTEXT, dba\_extents, and dba\_tab\_subpartitions
- When oracle-partition-connector is used, the connection user must be granted the select permission on the following system catalogs: dba\_objects and dba\_extents.

## Import Process

You can import data on the Loader web UI. [Figure 13-1](#) shows the data import process.

**Figure 13-1** Import process



You can also use shell scripts to update and run Loader jobs. To use this method, you need to configure the installed Loader client.

## 13.4.2 Importing Data Using Loader

### Scenario

This section describes how to import data from external data sources to MRS.

Generally, you can manually manage data import and export jobs on the Loader UI. To use shell scripts to update and run Loader jobs, you must configure the installed Loader client.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have the permission to access the HDFS or OBS directories, HBase tables, and data involved in job execution.
- You have obtained the username and password used by an external data source (SFTP server or relational database).
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.

- When using Loader to import data from SFTP, FTP, and HDFS/OBS, ensure that the input paths and input path subdirectories of the external data sources and the name of the files in these directories do not contain any of the special characters /'";,;
- If a task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.

## Procedure

**Step 1** Check whether data is imported from MRS to a relational database for the first time.

- If yes, go to [Step 2](#).
- If no, go to [Step 3](#).

**Step 2** Modify the permission on the JAR package of the relational database driver.

1. Log in to the active and standby management nodes of the Loader service, obtain the JAR package of the relational database driver, and save it to the following directory on the active and standby Loader nodes: **\$ {BIGDATA\_HOME}/FusionInsight\_Porter\_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib.**

### NOTE

The version 8.1.2.2 is used as an example. Replace it with the actual version number.

2. Run the following command as user **root** on the active and standby nodes of the Loader service to modify the permission:

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib
```

```
chown omm:wheel JAR package name
```


```
chmod 600 JAR package name
```

3. Log in to FusionInsight Manager. Choose **Cluster > Name of the desired cluster > Services > Loader > More > Restart Service**. Enter the password of the administrator to restart the Loader service.

**Step 3** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster > Name of the desired cluster > Services > Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-2** Loader web UI



- Step 4** Create a Loader data import job. Click **New Job**. Select the required job type in **1. Basic Information**, and click **Next**.
1. Set **Name** to the job name and **Type** to **Import**.
  2. Select a connection for **Connection**. By default, no connection is created. Click **Add** to create a connection, and then click **Test** to test whether the connection is available. Click **OK** when the system displays a message indicates that the test is successful.

Data sources need to be connected when MRS exchanges data and files with external data sources. **Connection** indicates the set of connection parameters for connecting to data sources.

**Table 13-10** Connection configuration parameters

Connector	Parameter	Description
generic-jdbc-connector	JDBC Driver Class	Name of a JDBC driver class
	JDBC Connection String	JDBC connection string
	Username	Username for connecting to the database
	Password	Password for connecting to the database
	JDBC Connection Properties	JDBC connection attribute. Click <b>Add</b> to manually add connection attributes. <ul style="list-style-type: none"> <li>- <b>Name</b>: connection attribute name</li> <li>- <b>Value</b>: connection attribute value</li> </ul>
ftp-connector	FTP Server IP Address	IP address of the FTP server
	FTP Server Port	Port number of the FTP server
	FTP Username	Username for accessing the FTP server
	FTP Password	Password for accessing the FTP server
	FTP Mode	FTP access mode. Possible values are <b>ACTIVE</b> and <b>PASSIVE</b> . If this parameter is not set, FTP access is in passive mode by default.

Connector	Parameter	Description
	FTP Protocol	<p>FTP protocol.</p> <ul style="list-style-type: none"> <li>- <b>FTP</b>: indicates the FTP protocol.</li> <li>- <b>SSL_EXPLICIT</b>: indicates the explicit SSL protocol.</li> <li>- <b>SSL_IMPLICIT</b>: indicates the implicit SSL protocol.</li> <li>- <b>TLS_EXPLICIT</b>: indicates the explicit TLS protocol.</li> <li>- <b>TLS_IMPLICIT</b>: indicates the implicit TLS protocol.</li> </ul> <p>If this parameter is not set, the FTP protocol is used by default.</p>
	File Name Encoding Type	File name and file path encoding format supported by the FTP server. If this parameter is not set, the default format UTF-8 is used.
hdfs-connector	-	-
oracle-connector	JDBC Connection String	Connection string for a user to connect to the database
	Username	Username for connecting to the database
	Password	Password for connecting to the database
	Connection Properties	<p>Connection attributes. Click <b>Add</b> to manually add connection attributes.</p> <ul style="list-style-type: none"> <li>- <b>Name</b>: connection attribute name</li> <li>- <b>Value</b>: connection attribute value</li> </ul>
mysql-fastpath-connector	JDBC Connection String	JDBC connection string
	Username	Username for connecting to the database
	Password	Password for connecting to the database
	Connection Properties	<p>Connection attributes. Click <b>Add</b> to manually add connection attributes.</p> <ul style="list-style-type: none"> <li>- <b>Name</b>: connection attribute name</li> <li>- <b>Value</b>: connection attribute value</li> </ul>
sftp-connector	SFTP Server IP Address	IP address of the SFTP server

Connector	Parameter	Description
	SFTP Server Port	Port number of the SFTP server
	SFTP Username	Username for accessing the SFTP server
	SFTP Password	Password for accessing the SFTP server
	SFTP Public Key	Public key of the SFTP server
oracle-partition-connector	JDBC Driver Class	Name of a JDBC driver class
	JDBC Connection String	JDBC connection string
	Username	Username for connecting to the database
	Password	Password for connecting to the database
	Connection Properties	Connection attributes. Click <b>Add</b> to manually add connection attributes. <ul style="list-style-type: none"> <li>- <b>Name:</b> connection attribute name</li> <li>- <b>Value:</b> connection attribute value</li> </ul>

3. Set **Group** to the group to which the job belongs. By default, there is no created group. Click **Add** to create a group and click **OK**.
4. **Queue** indicates that Loader tasks are executed in a specified Yarn queue. The default value is **root.default**, which indicates that the tasks are executed in the **default** queue.
5. Set **Priority** to the priority of Loader tasks in the specified Yarn queue. The value can be **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, or **VERY\_HIGH**. The default value is **NORMAL**.

**Step 5** In the **2. Input Settings** area, set the data source and click **Next**.

 **NOTE**

- When creating or editing a Loader job, you can use macro definitions when configuring parameters such as the SFTP path, HDFS/OBS path, and Where condition of SQL. For details, see [Using Macro Definitions in Configuration Items](#) .
- Loader supports common field data types, such as Char, VarChar, Boolean, Binary, SmallInt, Int, BigInt, Decimal, Float, Double, Date, Time, TimeStamp, and String. The supported types may vary according to the data source. For details about the supported types, expand the field data type drop-down list of the corresponding input operator (such as Table Input) on the Loader GUI. Some database-specific fields may not be supported. For example, Loader does not support the CLOB, XMLType, and BLOB fields in Oracle.

**Table 13-11** List of input configuration parameters

Source File Type	Parameter	Description
sftp-connector or ftp-connector	Input Path	Input path or name of the source file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple input paths separated with semicolons (;). Ensure that the number of input paths is the same as that of SFTP servers configured for the connector.
	File Split Type	Indicates whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each Map in the MapReduce task for data import. <b>FILE</b> indicates that each Map processes one or more complete source files. The same source file cannot be allocated to different Maps. When the data is saved to the output directory, the directory structure of the input path is retained. <b>SIZE</b> indicates that each Map processes input files of a certain size. A source file can be split into multiple Maps. The number of files saved when data is saved to the output directory is the same as that of Maps. The file name format is <b>import_part_xxxx</b> , where <i>xxxx</i> is a unique random number generated by the system.
	Filter Type	File filtering criterion. <b>WILCARD</b> indicates that a wildcard is used in filtering, and <b>REGEX</b> indicates that a regular expression is used in filtering. This parameter is used together with <b>Path Filter</b> and <b>File Filter</b> . The default value is <b>WILDCARD</b> .
	Path Filter	Wildcard or regular expression for filtering the directories in the input path of the source files. This parameter is used when <b>Filter Type</b> is set. <b>Input Path</b> is not used for filtering. If there are multiple filter conditions, use commas (,) to separate them. If the value is empty, the directories are not filtered.
	File Filter	Wildcard or regular expression for filtering the file names of the source files. This parameter is used when <b>Filter Type</b> is set. If there are multiple filter conditions, use commas (,) to separate them. The value cannot be left blank.

Source File Type	Parameter	Description
	Encoding Type	Source file encoding format, for example, UTF-8. This parameter can be set only in text file import.
	Suffix	File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file.
	Compression	Indicates whether to enable compressed transmission when SFTP is used to export data. <b>true</b> indicates that compression is enabled, and <b>false</b> indicates that compression is disabled.
hdfs-connector	Input Path	Input path of source files in HDFS
	Path Filter	Wildcard for filtering the directories in the input paths of the source files. <b>Input Path</b> is not used for filtering. If there are multiple filter conditions, use commas (,) to separate them. If the value is empty, the directories are not filtered. The regular expression filtering is not supported.
	File Filter	Wildcard for filtering the file names of the source files. If there are multiple filter conditions, use commas (,) to separate them. The value cannot be left blank. The regular expression filtering is not supported.
	Encoding Type	Source file encoding format, for example, UTF-8. This parameter can be set only in text file import.
	Suffix	File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file.
generic-jdbc-connector	Schema Name	Database schema name. This parameter exists in the <b>Table name</b> schema.
	Table Name	Database table name. This parameter exists in the <b>Table name</b> schema.

Source File Type	Parameter	Description
	SQL Statement	SQL statement for the Loader to query data to be imported in <b>Table SQL statement</b> mode. The SQL statement requires the query condition <b>WHERE \${CONDITIONS}</b> . Without this condition, the SQL statement cannot be run properly, for example, <b>select * from TABLE WHERE A&gt;B and \${CONDITIONS}</b> . If <b>Table column names</b> is set, the column specified by <b>Table column names</b> will replace the column queried in the SQL statement. This parameter cannot be set when <b>Schema name</b> or <b>Table name</b> is set.
	Table Column Names	Table columns whose content is to be imported by Loader. Use commas (,) to separate multiple fields.
	Partition Column Name	Database table column based on which to-be-imported data is determined. This parameter is used for partitioning in a Map job. You are advised to configure the primary key field. <b>NOTE</b> <ul style="list-style-type: none"> <li>• A partition column must have an index. If no index exists, do not specify a partition column. If a partition column without an index is specified, the database server disk I/O will be busy, the access of other services to the database will be affected, and the import will take a long period.</li> <li>• In multiple fields with indexes, select the field that has the most discrete value as the partition column. A partition column that is not discrete may result in load imbalance when multiple MapReduce jobs are imported.</li> <li>• The sorting rules of partition columns must be case-sensitive. Otherwise, data may be lost during data import.</li> <li>• You are not advised to select fields of the float or double type for the partition column. Otherwise, the records containing the minimum and maximum values of the partition column may fail to be imported due to precision issues.</li> </ul>
	Nulls in Partition Column	Indicates whether to process records whose values are null in database table columns. If the value is <b>true</b> , the data whose value is null in the partition column is processed. If the value is <b>false</b> , the data whose value is null in the partition column is not processed.

Source File Type	Parameter	Description
	Whether to Specify a Partition Column	Indicates whether to specify a partition column.
oracle-connector	Table Name	Table name.
	Column Name	Column name.
	Query Condition	Query condition in an SQL statement
	Splitting Mode	Data splitting mode. The options are <b>ROWID</b> and <b>PARTITION</b> .
	Table Partition Name	Name of a table partition. Use commas (,) to separate the names of different partitions.
	Data Block Allocation Mode	Allocation method of data after being split.
	Read Size	Amount of data to be read each time.
mysql-fastpath-connector	Schema Name	Database schema name.
	Table Name	Database table name.
	Query Condition	Query condition of a specified table.
	Partition Column Name	Database table column based on which to-be-imported data is determined. This parameter is used for partitioning in a Map job. You are advised to configure the primary key field. <b>NOTE</b> <ul style="list-style-type: none"> <li>• A partition column must have an index. If no index exists, do not specify a partition column. If a partition column without an index is specified, the database server disk I/O will be busy, the access of other services to the database will be affected, and the import will take a long period.</li> <li>• In multiple fields with indexes, select the field that has the most discrete value as the partition column. A partition column that is not discrete may result in load imbalance when multiple MapReduce jobs are imported.</li> <li>• You are not advised to select fields of the float or double type for the partition column. Otherwise, the records containing the minimum and maximum values of the partition column may fail to be imported due to precision issues.</li> </ul>

Source File Type	Parameter	Description
	Nulls in Partition Column	Indicates whether to process records whose values are null in database table columns. If the value is <b>true</b> , the data whose value is null in the partition column is processed. If the value is <b>false</b> , the data whose value is null in the partition column is not processed.
	Whether to Specify a Partition Column	Indicates whether to specify a partition column.
oracle-partition-connector	Schema Name	Database schema name.
	Table Name	Partition table name.
	Query Condition	Query condition in an SQL statement.
	Table Column Names	Table columns whose content is to be imported by Loader. Use commas (,) to separate multiple fields.

**Step 6** In the **3. Convert** area, set the conversion operations during data transmission.

Check whether source data values in the data operation job created by the Loader can be directly used without conversion, including upper and lower case conversion, cutting, merging, and separation.

- If yes, click **Next**.
  - If no, perform [Step 6.1](#) to [Step 6.4](#).
1. No created conversion step exists by default. Drag an example conversion step on the left to the edit box to create a new conversion step.
  2. Conversion step types must be selected based on service requirements. A complete conversion process includes the following types:
    - a. Input type. Only one conversion step can be added. This parameter is mandatory if the task involves HBase or relational databases.
    - b. Conversion type, which is an intermediate conversion step. You can add one or more conversion types or do not add any conversion type.
    - c. Output type. Only one output type can be added in the last conversion step. This parameter is mandatory if the task involves HBase or relational databases.

**Table 13-12** Example list

Type	Description
Input Type	<ul style="list-style-type: none"> <li data-bbox="762 353 1362 454">▪ <b>CSV File Input:</b> CSV file input step for configuring separators to generate multiple fields.</li> <li data-bbox="762 481 1410 582">▪ <b>Fixed-Width File Input:</b> Text file input step for configuring the length of characters or bytes to be truncated to generate multiple fields.</li> <li data-bbox="762 609 1430 710">▪ <b>Table Input:</b> relational data input step for configuring specified columns in the database as input fields.</li> <li data-bbox="762 736 1398 837">▪ <b>HBase Input:</b> HBase table input step for configuring the column definition of an HBase table to a specified field.</li> <li data-bbox="762 864 1406 965">▪ <b>HTML Input:</b> HTML web page data input step for obtaining the target data of the HTML web page file to the specified field.</li> <li data-bbox="762 992 1385 1093">▪ <b>Hive Input:</b> Hive table input step for defining columns in a Hive table to specified fields.</li> <li data-bbox="762 1097 1406 1198">▪ <b>Spark Input:</b> Spark SQL table input step for defining columns in the SparkSQL table to specified fields. Only SparkSQL can access Hive data.</li> </ul>

Type	Description
Conversion Type	<ul style="list-style-type: none"> <li>▪ <b>Long Integer Time Conversion:</b> Configure the conversion between a long integer value and a date.</li> <li>▪ <b>Null Value Conversion:</b> Configure a specified value to replace the null value.</li> <li>▪ <b>Random Value Conversion:</b> Configure new value-added fields as random data fields.</li> <li>▪ <b>Adding a Constant Field:</b> Add a constant to directly generate a constant field.</li> <li>▪ <b>Concatenation and Conversion:</b> Concatenate fields, connect generated fields using connection characters, and convert new fields.</li> <li>▪ <b>Separator Conversion:</b> Configure the generated fields to be separated by separators and convert new fields.</li> <li>▪ <b>Modulo Conversion:</b> Configure the generated fields to be converted into new fields through modulo operation.</li> <li>▪ <b>Cutting Character String:</b> Truncate a generated field based on a specified position to generate a new field.</li> <li>▪ <b>EL Operation Conversion:</b> Calculate field values. Currently, the following operators are supported: md5sum, sha1sum, sha256sum, and sha512sum.</li> <li>▪ <b>Character String Case Conversion:</b> Configure the generated fields to be converted to new fields through case conversion.</li> <li>▪ <b>Reverse String Conversion:</b> Reverse the generated fields to generate new fields.</li> <li>▪ <b>Character String Space Clearing Conversion:</b> Configure the generated fields to clear spaces and convert them to new fields.</li> <li>▪ <b>Row Filtering Conversion:</b> Configure logical conditions to filter out rows that contain triggering conditions.</li> <li>▪ <b>Update Fields:</b> Update the value of a specified field when certain conditions are met.</li> </ul>

Type	Description
Output Type	<ul style="list-style-type: none"> <li>▪ <b>File Output:</b> Configure generated fields to be connected by separators and exported to a file.</li> <li>▪ <b>Table Output:</b> Configure the mapping between output fields and specified columns in the database.</li> <li>▪ <b>HBase Output:</b> Configure the generated fields to the columns of the HBase table.</li> <li>▪ <b>Hive Output:</b> Configure generated fields to a column of a Hive table.</li> <li>▪ <b>Spark Output:</b> Configure generated fields to the columns of SparkSQL tables. Only SparkSQL can access Hive data.</li> </ul>

The edit box allows you to perform the following tasks:

- **Rename:** Rename an example.
- **Edit:** Edit the step conversion by referring to [Step 6.3](#).
- **Delete:** Delete an example.

 **NOTE**

You can also use the shortcut key **Del** to delete the example.

3. Click **Edit** to edit the step conversion information and configure fields and data.

For details about how to set parameters in the step conversion information, see [Operator Help](#).

 **NOTE**

- When sftp-connector or ftp-connector is used to import data, the time type field in the original data must be set to a string during the data conversion so that the time can be accurate to millisecond for data import. The data that has more precise time than millisecond will not be imported.
- When generic-jdbc-connector is used to import data, it is recommended that the data length of the CHAR or VARCHAR type field be set to -1 during data conversion so that all data can be imported. This prevents the data from being truncated when the actual data length is too long.
- When generic-jdbc-connector is used to import data, the time type field in the original data must be set to a time type value during the data conversion so that the time can be accurate to second for data import. The data that has more precise time than second will not be imported.
- When data is imported to a Hive partitioned table, Hive does not scan the newly imported data by default. You need to run the following HQL statement to repair the table so that the newly imported data can be queried:

**MSCK REPAIR TABLE** *table\_name*;

If the conversion step is incorrectly configured, the source data cannot be converted and become dirty data. The dirty data marking rules are as follows:

- In any input type step, all data becomes dirty data if the number of fields contained in the original data is less than that of configured fields, or the field values in the original data do not match the configured field type.
- In the **CSV File Input** step, **Validate input field** checks whether the input field matches the value type. If the input field and value type of a row do not match, the row is skipped and becomes dirty data.
- In the **Fixed Width File Input** step, **Fixed Length** specifies the field splitting length. If the length is greater than the length of the original field value, data splitting fails and the current row becomes dirty data.
- In the **HBase Input** step, if the HBase table name specified by **HBase Table Name** is incorrect, or no primary key column is configured for **Primary Key**, all data becomes dirty data.
- In any conversion step, rows whose conversion fails become dirty data. For example, in the **Split Conversion** step, if the number of generated fields is less than that of configured fields, or the original data cannot be converted to the String type, the current row becomes dirty data.
- In the **Filter Row Conversion** step, rows filtered by filter criteria become dirty data.
- In the **Modulo Conversion** step, if the original field value is **NULL**, the current row becomes dirty data.
- For jobs that import data to Hive/SparkSQL tables, you must configure the Hive conversion step.

4. Click **Next**.

**Step 7** In the **4. Output Settings** area, set the destination location for saving data and click **Save** to save the job or click **Save and Run** to save and run the job.

**Table 13-13** List of output configuration parameters

Storage Type	Parameter	Description
HDFS	File Type	Compression format of files imported to HDFS. Select a format from the drop-down list. If you select <b>NONE</b> or do not set this parameter, data is not compressed.
	Compression Format	Compression format of files imported to HDFS. Select a format from the drop-down list. If you select <b>NONE</b> or do not set this parameter, data is not compressed.
	Output Directory	Directory for storing data imported into HDFS.


Storage Type	Parameter	Description
	Operation	<p>Action during data import. When all data is to be imported from the input path to the destination path, the data is stored in a temporary directory and then copied from the temporary directory to the destination path. After the data is imported successfully, the data is deleted from the temporary directory. One of the following actions can be taken when duplicate file names exist during data transfer:</p> <ul style="list-style-type: none"> <li>• <b>OVERRIDE:</b> overrides the old file.</li> <li>• <b>RENAME:</b> renames as new file. For a file without an extension, a string is added to the file name as the extension; for a file with an extension, a string is added to the extension. The string is unique.</li> <li>• <b>APPEND:</b> adds the content of the new file to the end of the old file. This action only adds content regardless of whether the file can be used. For example, a text file can be used after this operation, while a compressed file cannot.</li> <li>• <b>IGNORE:</b> reserves the old file and does not copy the new file.</li> <li>• <b>ERROR:</b> stops the task and reports an error if duplicate file names exist. Transferred files are imported successfully, while files that have duplicate names and files that are not transferred fail to be imported.</li> </ul>
	Extractors	<p>Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. This parameter cannot be set when <b>Extractor Size</b> is set. The value must be less than or equal to 3000.</p>
	Extractor Size	<p>Size of data processed by Maps that are started in a MapReduce task of a data configuration operation. The unit is MB. The value must be greater than or equal to 100. The recommended value is <b>1000</b>. This parameter cannot be set when <b>Extractors</b> is set. When a relational database connector is used, <b>Extractor Size</b> is unavailable. You need to set <b>Extractors</b>.</p>

Storage Type	Parameter	Description
HBASE_BULKLOAD	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.
	Clear data before import	Indicates whether to clear data in the original table before importing data. The value <b>true</b> indicates that the clearing operation is performed, and the value <b>false</b> indicates that the clearing operation is not performed. If you do not set this parameter, the original table is not cleared by default.
	Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.
	Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .
HBASE_PUTLIST	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.
	Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.
	Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .
HIVE	Output Directory	Directory for storing data imported into Hive.
	Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. This parameter cannot be set when <b>Extractor Size</b> is set. The value must be less than or equal to 3000.

Storage Type	Parameter	Description
	Extractor Size	Size of data processed by Maps that are started in a MapReduce task of a data configuration operation. The unit is MB. The value must be greater than or equal to 100. The recommended value is <b>1000</b> . This parameter cannot be set when <b>Extractors</b> is set. When a relational database connector is used, <b>Extractor Size</b> is unavailable. You need to set <b>Extractors</b> .
SPARK	Output Directory	Only SparkSQL is supported to access Hive data. You can specify the directory for storing data imported to Hive.
	Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. This parameter cannot be set when <b>Extractor Size</b> is set. The value must be less than or equal to 3000.
	Extractor Size	Size of data processed by Maps that are started in a MapReduce task of a data configuration operation. The unit is MB. The value must be greater than or equal to 100. The recommended value is <b>1000</b> . This parameter cannot be set when <b>Extractors</b> is set. When a relational database connector is used, <b>Extractor Size</b> is unavailable. You need to set <b>Extractors</b> .

**Step 8** On the Loader web UI, view, start, stop, copy, delete, edit, or view historical information about created jobs.

**Figure 13-3** Viewing Loader jobs



----End

## 13.4.3 Typical Scenario: Importing Data from an SFTP Server to HDFS or OBS

### Scenario

Use Loader to import data from an SFTP server to HDFS or OBS.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HDFS or OBS directories and data involved in job execution.
- You have obtained the username and password of the SFTP server as well as the read permission for the source files on the SFTP server. If file name extension needs to be added after a source file is imported, the user must have the write permission of the source file.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- When using Loader to import data from the SFTP server, the input paths and input path subdirectories of the SFTP server and the name of the files in these directories do not contain any of the special characters `/'";`.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


### Procedure

#### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-4** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-5 Basic Information**

The screenshot shows a configuration form with the following fields and values:

- Name:** An empty text input field.
- Type:** A dropdown menu with "Import" selected.
- Connection:** An empty dropdown menu with a blue "+ Add" button to its right.
- Group:** A dropdown menu with "Choose..." selected and a blue "+ Add" button to its right.
- Queue:** A dropdown menu with "default" selected.
- Priority:** A dropdown menu with "NORMAL" selected.

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **sftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**. Loader allows multiple SFTP servers to be configured. Click **Add** to add the configuration information of multiple SFTP servers.

**Table 13-14** Connection parameters

Parameter	Description	Example Value
Name	Name of the SFTP server connection	sftpName
SFTP Server IP Address	IP address of the SFTP server	10.16.0.1
SFTP Server Port	Port number of the SFTP server	22
SFTP Username	Username for accessing the SFTP server	root
SFTP Password	Password for accessing the SFTP server	xxxx
SFTP Public Key	Public key of the SFTP server	OdDt/yn...etM

**NOTE**

When multiple SFTP servers are configured, the data in the specified directories of the SFTP servers is imported to the same directory in HDFS or OBS.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-15** Parameter description

Parameter	Description	Example Value
Input Path	<p>Input path or name of the source file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple input paths separated with semicolons (;). Ensure that the number of input paths is the same as that of SFTP servers configured for the connector.</p> <p><b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a>.</p>	/opt/ tempfile;/ opt
File Split Type	<p>Indicates whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each Map in the MapReduce task for data import.</p> <ul style="list-style-type: none"> <li>• <b>FILE</b>: indicates that the source file is split by file. That is, each Map processes one or multiple complete files, the same source file cannot be allocated to different Maps, and the source file directory structure is retained after data import.</li> <li>• <b>SIZE</b>: indicates that the source file is split by size. That is, each Map processes input files of a certain size, and a source file can be divided and processed by multiple Maps. After data is stored in the output directory, the number of saved files is the same as that of Maps. The file name format is <b>import_part_XXXX</b>, where <i>XXXX</i> is a unique random number generated by the system.</li> </ul>	FILE
Filter Type	<p>File filter condition. This parameter is used when <b>Path Filter</b> or <b>File Filter</b> is set.</p> <ul style="list-style-type: none"> <li>• <b>WILDCARD</b>: indicates using a wildcard.</li> <li>• <b>REGEX</b>: indicates using a regular expression.</li> <li>• If the parameter is not set, a wildcard is used by default.</li> </ul>	WILDCARD

Parameter	Description	Example Value
Path Filter	<p>Wildcard or regular expression for filtering the directories in the input path of the source files. This parameter is used when <b>Filter Type</b> is set. <b>Input Path</b> is not used for filtering. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. If this parameter is left empty, directories are not filtered.</p> <ul style="list-style-type: none"> <li>• ? matches a single character.</li> <li>• * indicates multiple characters.</li> <li>• Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	1*,2*;1*
File Filter	<p>Wildcard or regular expression for filtering the file names of the source files. This parameter is used when <b>Filter Type</b> is set. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. This parameter cannot be left blank.</p> <ul style="list-style-type: none"> <li>• ? matches a single character.</li> <li>• * indicates multiple characters.</li> <li>• Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	*.txt,*.csv; *.txt
Encoding Type	Source file encoding format, for example, UTF-8 and GBK. This parameter can be set only in text file import.	UTF-8
Suffix	<p>File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file. This parameter is valid only when the data source is a file system. You are advised to set this parameter in incremental data import.</p> <p>For example, if the parameter is set to <b>.txt</b> and the source file is <b>test-loader.csv</b>, the source file name is <b>test-loader.csv.txt</b> after export.</p>	.log
Compression	<p>Indicates whether to enable compressed transmission when SFTP is used to export data.</p> <ul style="list-style-type: none"> <li>• The value <b>true</b> indicates that compression is enabled.</li> <li>• The value <b>false</b> indicates that compression is disabled.</li> </ul>	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-16](#).

**Table 13-16** Input and output parameters of the operator

Input Type	Output Type
CSV File Input	File Output
HTML Input	File Output
Fixed File Input	File Output

**Figure 13-6** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **HDFS**.

**Table 13-17** Parameter description

Parameter	Description	Example Value
File Type	Type of a file after the file is imported. The options are as follows: <ul style="list-style-type: none"> <li>• <b>TEXT_FILE</b>: imports a text file and stores it as a text file.</li> <li>• <b>SEQUENCE_FILE</b>: imports a text file and stores it as a sequence file.</li> <li>• <b>BINARY_FILE</b>: imports files of any format by using binary streams.</li> </ul>	TEXT_FILE
Compression Format	Compression format of files imported to HDFS or OBS. Select a format from the drop-down list. If you select <b>NONE</b> or do not set this parameter, data is not compressed.	NONE
Output Directory	Directory for storing data imported into HDFS or OBS. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/user/test

Parameter	Description	Example Value
Operation	<p>Action during data import. When all data is to be imported from the input path to the destination path, the data is stored in a temporary directory and then copied from the temporary directory to the destination path. After the data is imported successfully, the data is deleted from the temporary directory. One of the following actions can be taken when duplicate file names exist during data transfer:</p> <ul style="list-style-type: none"> <li>● <b>OVERRIDE</b>: overrides the old file.</li> <li>● <b>RENAME</b>: renames as new file. For a file without an extension, a string is added to the file name as the extension; for a file with an extension, a string is added to the extension. The string is unique.</li> <li>● <b>APPEND</b>: adds the content of the new file to the end of the old file. This action only adds content regardless of whether the file can be used. For example, a text file can be used after this operation, while a compressed file cannot.</li> <li>● <b>IGNORE</b>: reserves the old file and does not copy the new file.</li> <li>● <b>ERROR</b>: stops the task and reports an error if duplicate file names exist. Transferred files are imported successfully, while files that have duplicate names and files that are not transferred fail to be imported.</li> </ul>	OVERRIDE
Extractors	<p>Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. This parameter cannot be set when <b>Extractor Size</b> is set. The value must be less than or equal to 3000. You are advised to set the parameter to the number of CPU cores on the SFTP server.</p> <p><b>NOTE</b> To improve the data import speed, ensure that the following conditions are met:</p> <ul style="list-style-type: none"> <li>● Each Map connection is equivalent to a client connection. Therefore, you must ensure that the maximum number of connections of the SFTP server is greater than the number of Maps.</li> <li>● Ensure that the disk I/O or network bandwidth on the SFTP server does not reach the upper limit.</li> </ul>	20


Parameter	Description	Example Value
Extractor Size	Size of data processed by Maps that are started in a MapReduce task of a data configuration operation. The unit is MB. The value must be greater than or equal to 100. The recommended value is 1000. This parameter cannot be set when <b>Extractors</b> is set.	1000

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-7** Viewing job details



----End

## 13.4.4 Typical Scenario: Importing Data from an SFTP Server to HBase

### Scenario

Use Loader to import data from an SFTP server to HBase.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HBase tables or phoenix tables that are used during job execution.
- You have obtained the username and password of the SFTP server as well as the read permission for the source files on the SFTP server. If file name extension needs to be added after a source file is imported, the user must have the write permission of the source file.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- When using Loader to import data from the SFTP server, the input paths and input path subdirectories of the SFTP server and the name of the files in these directories do not contain any of the special characters `/'";,;`.

- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-8** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-9** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **sftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**. Loader

allows multiple SFTP servers to be configured. Click **Add** to add the configuration information of multiple SFTP servers.

**Table 13-18** Connection parameters

Parameter	Description	Example Value
Name	Name of the SFTP server connection	sftpName
SFTP Server IP Address	IP address of the SFTP server	10.16.0.1
SFTP Server Port	Port number of the SFTP server	22
SFTP Username	Username for accessing the SFTP server	root
SFTP Password	Password for accessing the SFTP server	xxxx
SFTP Public Key	Public key of the SFTP server	OdDt/yn...etM

 **NOTE**

When multiple SFTP servers are configured, the data in the specified directories of the servers is imported to HBase.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-19** Parameter description

Parameter	Description	Example Value
Input Path	<p>Input path or name of the source file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple input paths separated with semicolons (;). Ensure that the number of input paths is the same as that of SFTP servers configured for the connector.</p> <p><b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .</p>	/opt/ tempfile;/op t

Parameter	Description	Example Value
File Split Type	<p>Indicates whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each Map in the MapReduce task for data import.</p> <ul style="list-style-type: none"> <li>● <b>FILE</b>: indicates that the source file is split by file. That is, each Map processes one or multiple complete files, the same source file cannot be allocated to different Maps, and the source file directory structure is retained after data import.</li> <li>● <b>SIZE</b>: indicates that the source file is split by size. That is, each Map processes input files of a certain size, and a source file can be divided and processed by multiple Maps. After data is stored in the output directory, the number of saved files is the same as that of Maps. The file name format is <b>import_part_xxxx</b>, where <b>xxxx</b> is a unique random number generated by the system.</li> </ul>	FILE
Filter Type	<p>File filter condition. This parameter is used when <b>Path Filter</b> or <b>File Filter</b> is set.</p> <ul style="list-style-type: none"> <li>● <b>WILDCARD</b>: indicates using a wildcard.</li> <li>● <b>REGEX</b>: indicates using a regular expression.</li> <li>● If the parameter is not set, a wildcard is used by default.</li> </ul>	WILDCARD
Path Filter	<p>Wildcard or regular expression for filtering the directories in the input path of the source files. This parameter is used when <b>Filter Type</b> is set. <b>Input Path</b> is not used for filtering. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. If this parameter is left empty, directories are not filtered.</p> <ul style="list-style-type: none"> <li>● ? matches a single character.</li> <li>● * indicates multiple characters.</li> <li>● Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	1*,2*;1*

Parameter	Description	Example Value
File Filter	<p>Wildcard or regular expression for filtering the file names of the source files. This parameter is used when <b>Filter Type</b> is set. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. This parameter cannot be left blank.</p> <ul style="list-style-type: none"> <li>• ? matches a single character.</li> <li>• * indicates multiple characters.</li> <li>• Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	*.txt;*.csv;*.txt
Encoding Type	Source file encoding format, for example, UTF-8 and GBK. This parameter can be set only in text file import.	UTF-8
Suffix	<p>File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file. This parameter is valid only when the data source is a file system. You are advised to set this parameter in incremental data import.</p> <p>For example, if the parameter is set to <b>.txt</b> and the source file is <b>test-loader.csv</b>, the source file name is <b>test-loader.csv.txt</b> after export.</p>	.log
Compression	<p>Indicates whether to enable compressed transmission when SFTP is used to export data.</p> <ul style="list-style-type: none"> <li>• The value <b>true</b> indicates that compression is enabled.</li> <li>• The value <b>false</b> indicates that compression is disabled.</li> </ul>	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-20](#).

**Table 13-20** Input and output parameters of the operator

Input Type	Output Type
CSV File Input	HBase Output
HTML Input	HBase Output
Fixed File Input	HBase Output

**Figure 13-10** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **HBASE\_BULKLOAD** or **HBASE\_PUTLIST** based on the actual situation.

**Table 13-21** Parameter description

Storage Type	Applicable Scenario	Parameter	Description	Example Value
HBASE_BULKLOAD	Large data volume	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
		Clear data before import	Indicates whether to clear data in the original table before importing data. The value <b>true</b> indicates that the data is cleared, and the value <b>false</b> indicates that the data is not cleared. If you do not set this parameter, the original table is not cleared by default.	true

Storage Type	Applicable Scenario	Parameter	Description	Example Value
		Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the SFTP server.	20
		Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .	-
HBASE_P UTLIST	Small data volume	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase


Storage Type	Applicable Scenario	Parameter	Description	Example Value
		Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.	20
		Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .	-

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-11** Viewing job details



----End

## 13.4.5 Typical Scenario: Importing Data from an SFTP Server to Hive

### Scenario

Use Loader to import data from an SFTP server to Hive.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.

- You have had the permission to access the Hive table specified in the job.
- You have obtained the username and password of the SFTP server as well as the read permission for the source files on the SFTP server. If file name extension needs to be added after a source file is imported, the user must have the write permission of the source file.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- When using Loader to import data from the SFTP server, the input paths and input path subdirectories of the SFTP server and the name of the files in these directories do not contain any of the special characters /'";.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


## Procedure

### Setting Basic Job Information

#### Step 1 Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-12 Loader web UI



#### Step 2 Click **New Job** to go to the **Basic Information** page and set basic job information.

Figure 13-13 Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.

3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **sftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**. Loader allows multiple SFTP servers to be configured. Click **Add** to add the configuration information of multiple SFTP servers.

**Table 13-22** Connection parameters

Parameter	Description	Example Value
Name	Name of the SFTP server connection	sftpName
SFTP Server IP Address	IP address of the SFTP server	10.16.0.1
SFTP Server Port	Port number of the SFTP server	22
SFTP Username	Username for accessing the SFTP server	root
SFTP Password	Password for accessing the SFTP server	xxxx
SFTP Public Key	Public key of the SFTP server	OdDt/yn...etM

 **NOTE**

When multiple SFTP servers are configured, the data in the specified directories of the servers is imported to Hive.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-23** Parameter description

Parameter	Description	Example Value
Input Path	<p>Input path or name of the source file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple input paths separated with semicolons (;). Ensure that the number of input paths is the same as that of SFTP servers configured for the connector.</p> <p><b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .</p>	/opt/tem file;opt
File Split Type	<p>Indicates whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each Map in the MapReduce task for data import.</p> <ul style="list-style-type: none"> <li>● <b>FILE</b>: indicates that the source file is split by file. That is, each Map processes one or multiple complete files, the same source file cannot be allocated to different Maps, and the source file directory structure is retained after data import.</li> <li>● <b>SIZE</b>: indicates that the source file is split by size. That is, each Map processes input files of a certain size, and a source file can be divided and processed by multiple Maps. After data is stored in the output directory, the number of saved files is the same as that of Maps. The file name format is <b>import_part_xxxx</b>, where <i>xxxx</i> is a unique random number generated by the system.</li> </ul>	FILE
Filter Type	<p>File filter condition. This parameter is used when <b>Path Filter</b> or <b>File Filter</b> is set.</p> <ul style="list-style-type: none"> <li>● <b>WILDCARD</b>: indicates using a wildcard.</li> <li>● <b>REGEX</b>: indicates using a regular expression.</li> <li>● If the parameter is not set, a wildcard is used by default.</li> </ul>	WIL DC AR D

Parameter	Description	Example Value
Path Filter	<p>Wildcard or regular expression for filtering the directories in the input path of the source files. This parameter is used when <b>Filter Type</b> is set. <b>Input Path</b> is not used for filtering. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. If this parameter is left empty, directories are not filtered.</p> <ul style="list-style-type: none"> <li>• ? matches a single character.</li> <li>• * indicates multiple characters.</li> <li>• Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	1*, 2*, 1*
File Filter	<p>Wildcard or regular expression for filtering the file names of the source files. This parameter is used when <b>Filter Type</b> is set. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. This parameter cannot be left blank.</p> <ul style="list-style-type: none"> <li>• ? matches a single character.</li> <li>• * indicates multiple characters.</li> <li>• Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	*.txt ,*.csv; *.txt
Encoding Type	<p>Source file encoding format, for example, UTF-8 and GBK. This parameter can be set only in text file import.</p>	UTF-8
Suffix	<p>File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file. This parameter is valid only when the data source is a file system. You are advised to set this parameter in incremental data import.</p> <p>For example, if the parameter is set to <b>.txt</b> and the source file is <b>test-loader.csv</b>, the source file name is <b>test-loader.csv.txt</b> after export.</p>	.log

Parameter	Description	Example Value
Compression	<p>Indicates whether to enable compressed transmission when SFTP is used to export data.</p> <ul style="list-style-type: none"> <li>The value <b>true</b> indicates that compression is enabled.</li> <li>The value <b>false</b> indicates that compression is disabled.</li> </ul>	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-24](#).

**Table 13-24** Input and output parameters of the operator

Input Type	Output Type
CSV File Input	Hive Output
HTML Input	Hive Output
Fixed File Input	Hive Output

**Figure 13-14** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **HIVE**.

**Table 13-25** Parameter description


Parameter	Description	Example Value
Output Directory	Directory for storing data imported into Hive. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/opt/tempfile
Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the SFTP server.	20
Extractor Size	Hive does not support this parameter. Please set <b>Extractors</b> .	-

**Step 7** Click **Save and run** to save and run the job.

**Checking the Job Execution Result**

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-15** Viewing job details



----End

## 13.4.6 Typical Scenario: Importing Data from an SFTP Server to Spark

### Scenario

Use Loader to import data from an SFTP server to Spark.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the Spark table specified in the job.
- You have obtained the username and password of the SFTP server as well as the read permission for the source files on the SFTP server. If file name extension needs to be added after a source file is imported, the user must have the write permission of the source file.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- When using Loader to import data from the SFTP server, the input paths and input path subdirectories of the SFTP server and the name of the files in these directories do not contain any of the special characters `/'";:`.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


### Procedure

#### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-16** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-17 Basic Information**

The screenshot shows a configuration form with the following fields and values:

- Name:** An empty text input field.
- Type:** A dropdown menu with "Import" selected.
- Connection:** A dropdown menu with an empty field and a "+ Add" button to its right.
- Group:** A dropdown menu with "Choose..." selected and a "+ Add" button to its right.
- Queue:** A dropdown menu with "default" selected.
- Priority:** A dropdown menu with "NORMAL" selected.

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **sftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**. Loader allows multiple SFTP servers to be configured. Click **Add** to add the configuration information of multiple SFTP servers.

**Table 13-26** Connection parameters

Parameter	Description	Example Value
Name	Name of the SFTP server connection	sftpName
SFTP Server IP Address	IP address of the SFTP server	10.16.0.1
SFTP Server Port	Port number of the SFTP server	22
SFTP Username	Username for accessing the SFTP server	root
SFTP Password	Password for accessing the SFTP server	xxxx
SFTP Public Key	Public key of the SFTP server	OdDt/yn...etM

**NOTE**

When multiple SFTP servers are configured, the data in the specified directories of the servers is imported to Spark.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-27** Parameter description

Parameter	Description	Example Value
Input Path	<p>Input path or name of the source file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple input paths separated with semicolons (;). Ensure that the number of input paths is the same as that of SFTP servers configured for the connector.</p> <p><b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a>.</p>	/opt/ tempfile;/opt
File Split Type	<p>Indicates whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each Map in the MapReduce task for data import.</p> <ul style="list-style-type: none"> <li>• <b>FILE</b>: indicates that the source file is split by file. That is, each Map processes one or multiple complete files, the same source file cannot be allocated to different Maps, and the source file directory structure is retained after data import.</li> <li>• <b>SIZE</b>: indicates that the source file is split by size. That is, each Map processes input files of a certain size, and a source file can be divided and processed by multiple Maps. After data is stored in the output directory, the number of saved files is the same as that of Maps. The file name format is <b>import_part_xxxx</b>, where <b>xxxx</b> is a unique random number generated by the system.</li> </ul>	FILE
Filter Type	<p>File filter condition. This parameter is used when <b>Path Filter</b> or <b>File Filter</b> is set.</p> <ul style="list-style-type: none"> <li>• <b>WILDCARD</b>: indicates using a wildcard.</li> <li>• <b>REGEX</b>: indicates using a regular expression.</li> <li>• If the parameter is not set, a wildcard is used by default.</li> </ul>	WILDCARD

Parameter	Description	Example Value
Path Filter	<p>Wildcard or regular expression for filtering the directories in the input path of the source files. This parameter is used when <b>Filter Type</b> is set. <b>Input Path</b> is not used for filtering. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. If this parameter is left empty, directories are not filtered.</p> <ul style="list-style-type: none"> <li>• ? matches a single character.</li> <li>• * indicates multiple characters.</li> <li>• Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	1*,2*;1*
File Filter	<p>Wildcard or regular expression for filtering the file names of the source files. This parameter is used when <b>Filter Type</b> is set. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. This parameter cannot be left blank.</p> <ul style="list-style-type: none"> <li>• ? matches a single character.</li> <li>• * indicates multiple characters.</li> <li>• Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	*.txt,*.csv;*.txt
Encoding Type	Source file encoding format, for example, UTF-8 and GBK. This parameter can be set only in text file import.	UTF-8

Parameter	Description	Example Value
Suffix	File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file. This parameter is valid only when the data source is a file system. You are advised to set this parameter in incremental data import.  For example, if the parameter is set to <b>.txt</b> and the source file is <b>test-loader.csv</b> , the source file name is <b>test-loader.csv.txt</b> after export.	.log
Compression	Indicates whether to enable compressed transmission when SFTP is used to export data. <ul style="list-style-type: none"> <li>The value <b>true</b> indicates that compression is enabled.</li> <li>The value <b>false</b> indicates that compression is disabled.</li> </ul>	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-28](#).

**Table 13-28** Input and output parameters of the operator

Input Type	Output Type
CSV File Input	Spark Output
HTML Input	Spark Output
Fixed File Input	Spark Output

**Figure 13-18** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **SPARK**.

**Table 13-29** Parameter description

Parameter	Description	Example Value
Output Directory	Specifies the directory for storing data imported into Spark. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/opt/tempfile
Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the SFTP server.	20
Extractor Size	Spark does not support this parameter. Please set <b>Extractors</b> .	-

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-19** Viewing job details

Job ID	Name	Description	Start Time	Execute User	Progress	Status	Operation
5	hdfs-sftp-size	Export from HDFS to SF...	2016-03-26 14:45:08	admin	<div style="width: 100%;"></div>	Succeeded	[Icons]
4	hdfs-sftp	Export from HDFS to SF...	2016-03-26 14:43:14	admin	<div style="width: 100%;"></div>	Succeeded	[Icons]
3	sftp-hdfs-1-1	Import from SFTP to HD...	2016-03-26 12:00:36	admin	<div style="width: 100%;"></div>	Succeeded	[Icons]
1	sftp-hdfs	Import from SFTP to HD...	2016-03-26 11:08:09	admin	<div style="width: 100%;"></div>	Succeeded	[Icons]
2	sftp-hdfs-1	Import from SFTP to HD...	2016-03-26 11:07:56	admin	<div style="width: 100%;"></div>	Succeeded	[Icons]

-----End

## 13.4.7 Typical Scenario: Importing Data from an FTP Server to HBase

### Scenario

Use Loader to import data from an FTP server to HBase.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have obtained the username and password of the FTP server and the user has the read permission of the source files on the FTP server. If file name extension needs to be added after a source file is imported, the user must have the write permission of the source file.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- When using Loader to import data from the FTP server, the input paths and input path subdirectories of the FTP server and the name of the files in these directories do not contain any of the special characters /'";,.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.

### Procedure


#### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).

2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-20** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-21** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **ftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**. Loader allows multiple FTP servers to be configured. Click **Add** to add the configuration information of multiple FTP servers.

**Table 13-30** Connection parameters

Parameter	Description	Example Value
FTP Server IP Address	IP address of the FTP server	ftpName
FTP Server Port	Port number of the FTP server	22

Parameter	Description	Example Value
FTP Username	Username for accessing the FTP server	root
FTP Password	Password for accessing the FTP server	xxxx
FTP Mode	FTP access mode. Possible values are <b>ACTIVE</b> and <b>PASSIVE</b> . If this parameter is not set, FTP access is in passive mode by default.	PASSIVE
FTP Protocol	<p>FTP protocol.</p> <ul style="list-style-type: none"> <li>• <b>FTP</b>: indicates the FTP protocol.</li> <li>• <b>SSL_EXPLICIT</b>: indicates the explicit SSL protocol.</li> <li>• <b>SSL_IMPLICIT</b>: indicates the implicit SSL protocol.</li> <li>• <b>TLS_EXPLICIT</b>: indicates the explicit TLS protocol.</li> <li>• <b>TLS_IMPLICIT</b>: indicates the implicit TLS protocol.</li> </ul> <p>If this parameter is not set, the FTP protocol is used by default.</p>	FTP
File Name Encoding Type	File name and file path encoding format supported by the FTP server. If this parameter is not set, the default format UTF-8 is used.	UTF-8

 **NOTE**

When multiple FTP servers are configured, the data in the specified directories of the servers is imported to HBase.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-31** Parameter description

Parameter	Description	Example Value
Input Path	<p>Input path or name of the source file on an FTP server. If multiple FTP server IP addresses are configured for the connector, you can set this parameter to multiple input paths separated with semicolons (;). Ensure that the number of input paths is the same as that of FTP servers configured for the connector.</p> <p><b>NOTE</b>            You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .</p>	/opt/ tempfile;/o pt
File Split Type	<p>Indicates whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each Map in the MapReduce task for data import.</p> <ul style="list-style-type: none"> <li>● <b>FILE</b>: indicates that the source file is split by file. That is, each Map processes one or multiple complete files, the same source file cannot be allocated to different Maps, and the source file directory structure is retained after data import.</li> <li>● <b>SIZE</b>: indicates that the source file is split by size. That is, each Map processes input files of a certain size, and a source file can be divided and processed by multiple Maps. After data is stored in the output directory, the number of saved files is the same as that of Maps. The file name format is <b>import_part_XXXX</b>, where <b>XXXX</b> is a unique random number generated by the system.</li> </ul>	FILE
Filter Type	<p>File filter condition. This parameter is used when <b>Path Filter</b> or <b>File Filter</b> is set.</p> <ul style="list-style-type: none"> <li>● <b>WILDCARD</b>: indicates using a wildcard.</li> <li>● <b>REGEX</b>: indicates using a regular expression.</li> <li>● If the parameter is not set, a wildcard is used by default.</li> </ul>	WILDCARD

Parameter	Description	Example Value
Path Filter	<p>Wildcard or regular expression for filtering the directories in the input path of the source files. This parameter is used when <b>Filter Type</b> is set. <b>Input Path</b> is not used for filtering. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. If this parameter is left empty, directories are not filtered.</p> <ul style="list-style-type: none"> <li>● ? matches a single character.</li> <li>● * indicates multiple characters.</li> <li>● Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	1*,2*;1*
File Filter	<p>Wildcard or regular expression for filtering the file names of the source files. This parameter is used when <b>Filter Type</b> is set. Use semicolons (;) to separate the path filters on multiple servers and use commas (,) to separate the filter conditions of each server. This parameter cannot be left blank.</p> <ul style="list-style-type: none"> <li>● ? matches a single character.</li> <li>● * indicates multiple characters.</li> <li>● Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul> <p>For example, when <b>Filter type</b> is set to <b>WILDCARD</b>, set the parameter to *; when <b>Filter type</b> is set to <b>REGEX</b>, set the parameter to \\.*.</p>	*.txt,*.csv;*.txt
Encoding Type	<p>Source file encoding format, for example, UTF-8 and GBK. This parameter can be set only in text file import.</p>	UTF-8

Parameter	Description	Example Value
Suffix	File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file. This parameter is valid only when the data source is a file system. You are advised to set this parameter in incremental data import.  For example, if the parameter is set to <b>.txt</b> and the source file is <b>test-loader.csv</b> , the source file name is <b>test-loader.csv.txt</b> after export.	.log
Compression	Indicates whether to enable compressed transmission when FTP is used to export data. <ul style="list-style-type: none"> <li>• The value <b>true</b> indicates that compression is enabled.</li> <li>• The value <b>false</b> indicates that compression is disabled.</li> </ul>	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-32](#).

**Table 13-32** Input and output parameters of the operator

Input Type	Output Type
CSV File Input	HBase Output
HTML Input	HBase Output
Fixed File Input	HBase Output

**Figure 13-22** Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **HBASE\_BULKLOAD** or **HBASE\_PUTLIST** based on the actual situation.

**Table 13-33** Parameter description

Storage Type	Applicable Scenario	Parameter	Description	Example Value
HBASE_BULKLOAD	Large data volume	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
		Clear data before import	Indicates whether to clear data in the original table before importing data. <b>True</b> indicates clearing data and <b>False</b> indicates not to clear data. If you do not set this parameter, the original table is not cleared by default.	true


Storage Type	Applicable Scenario	Parameter	Description	Example Value
		Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the FTP server.	20
		Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .	-
HBASE_P UTLIST	Small data volume	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
		Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.	20
		Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .	-

**Step 7** Click **Save and run** to save and run the job.

**Checking the Job Execution Result**

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-23** Viewing job details



----End

## 13.4.8 Typical Scenario: Importing Data from a Relational Database to HDFS or OBS

### Scenario

Use Loader to import data from a relational database to HDFS or OBS.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HDFS or OBS directories and data involved in job execution.
- You have obtained the username and password of the relational database.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes: `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`.
  - b. Run the following command on the active and standby nodes as user **root** to modify the permission:

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/  
FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/  
webapps/loader/WEB-INF/ext-lib  
  
chown omm:wheel JAR package name  
chmod 600 JAR package name
```
  - c. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader** > **More** > **Restart Service**. Enter the password of the administrator to restart the Loader service.


### Procedure

#### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-24 Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

Figure 13-25 Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or a dedicated database connector (oracle-connector, oracle-partition-connector, or mysql-fastpath-connector), set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**.

**NOTE**

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When mysql-fastpath-connector is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManager nodes, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, install the MySQL client applications and tools following the instructions at <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>.

**Table 13-34 generic-jdbc-connector** connection parameters

Parameter	Description	Example Value
Name	Name of a relational database connection	dbName
JDBC Driver Class	Name of a Java database connectivity (JDBC) driver class	oracle.jdbc.driver.OracleDriver
JDBC Connection String	JDBC connection string	jdbc:oracle:thin:@//10.16.0.1:1521/oradb
Username	Username for connecting to the database	omm
Password	Password for connecting to the database	xxxx
JDBC Connection Properties	JDBC connection attribute. Click <b>Add</b> to manually add the attribute. <ul style="list-style-type: none"> <li>Name: connection attribute name</li> <li>Value: connection attribute value</li> </ul>	<ul style="list-style-type: none"> <li>Name: <b>socketTimeout</b></li> <li>Value: <b>20</b></li> </ul>

### Setting Data Source Information

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-35** Parameter description

Parameter	Description	Example Value
Schema Name	Database schema name. This parameter exists in the <b>Table name</b> schema.	public
Table Name	Database table name. This parameter exists in the <b>Table name</b> schema.	test

Parameter	Description	Example Value
SQL Statement	<p>SQL statement for Loader to query data to be imported in <b>Table SQL statement</b> mode. The SQL statement requires the query condition <b>WHERE \${CONDITIONS}</b>. Without this condition, the SQL statement cannot be run properly. An example SQL statement is as follows: <b>select * from TABLE WHERE A&gt;B and \${CONDITIONS}</b>. If <b>Table column names</b> is set, the column specified by <b>Table column names</b> will replace the column queried in the SQL statement. This parameter cannot be set when <b>Schema name</b> or <b>Table name</b> is set.</p> <p><b>NOTE</b> You can use macros to define SQL Where statements. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .</p>	select * from TABLE WHERE A>B and \${CONDITIONS}
Table Column Names	<p>Table columns whose content is to be imported by Loader. Use commas (,) to separate multiple fields.</p> <p>If the parameter is not set, all the columns are imported and the <b>Select *</b> order is used as the column location.</p>	id,name
Partition Column Name	<p>Database table column based on which to-be-imported data is determined. This parameter is used for partitioning in a Map job. You are advised to configure the primary key field.</p> <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>• A partition column must have an index. If no index exists, do not specify a partition column. If a partition column without an index is specified, the database server disk I/O will be busy, the access of other services to the database will be affected, and the import will take a long period.</li> <li>• In multiple fields with indexes, select the field that has the most discrete value as the partition column. A partition column that is not discrete may result in load imbalance when multiple MapReduce jobs are imported.</li> <li>• The sorting rules of partition columns must be case-sensitive. Otherwise, data may be lost during data import.</li> <li>• You are not advised to select fields of the float or double type for the partition column. Otherwise, the records containing the minimum and maximum values of the partition column may fail to be imported due to precision issues.</li> </ul>	id

Parameter	Description	Example Value
Nulls in Partition Column	Indicates whether to process records whose values are null in database table columns. <ul style="list-style-type: none"> <li>• <b>true</b>: Records whose values are null are processed.</li> <li>• <b>false</b>: Records whose values are not null are processed.</li> </ul>	true
Whether to Specify a Partition Column	Indicates whether to specify a partition column.	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-36](#).

**Table 13-36** Input and output parameters of the operator

Input Type	Output Type
Table input	File output

**Figure 13-26** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **HDFS**.

**Table 13-37** Parameter description

Parameter	Description	Example Value
File Type	Type of a file after the file is imported. The options are as follows: <ul style="list-style-type: none"> <li>● <b>TEXT_FILE</b>: imports a text file and stores it as a text file.</li> <li>● <b>SEQUENCE_FILE</b>: imports a text file and stores it as a sequence file.</li> <li>● <b>BINARY_FILE</b>: imports files of any format by using binary streams.</li> </ul>	TEXT_FILE
Compression Format	Compression format of files imported to HDFS. Select a format from the drop-down list. If you select <b>NONE</b> or leave this parameter blank, data is not compressed.	NONE
Output Directory	Directory for storing data imported into HDFS or OBS. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/user/test

Parameter	Description	Example Value
Operation	<p>Action during data import. When all data is to be imported from the input path to the destination path, the data is stored in a temporary directory and then copied from the temporary directory to the destination path. After the data is imported successfully, the data is deleted from the temporary directory. One of the following actions can be taken when duplicate file names exist during data transfer:</p> <ul style="list-style-type: none"> <li>● <b>OVERWRITE</b>: overrides the old file.</li> <li>● <b>RENAME</b>: renames as new file. For a file without an extension, a string is added to the file name as the extension; for a file with an extension, a string is added to the extension. The string is unique.</li> <li>● <b>APPEND</b>: adds the content of the new file to the end of the old file. This action only adds content regardless of whether the file can be used. For example, a text file can be used after this operation, while a compressed file cannot.</li> <li>● <b>IGNORE</b>: reserves the old file and does not copy the new file.</li> <li>● <b>ERROR</b>: stops the task and reports an error if duplicate file names exist. Transferred files are imported successfully, while files that have duplicate names and files that are not transferred fail to be imported.</li> </ul>	OVERWRITE
Extractors	<p>Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. This parameter cannot be set when <b>Extractor Size</b> is set. The value must be less than or equal to 3000.</p>	-
Extractor Size	<p>Size of data processed by Maps that are started in a MapReduce task of a data configuration operation. The unit is MB. The value must be greater than or equal to 100. The recommended value is 1000. This parameter cannot be set when <b>Extractors</b> is set. When a relational database connector is used, <b>Extractor Size</b> is unavailable. You need to set <b>Extractors</b>.</p>	1000

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-27** Viewing job details

Job ID	Name	Description	Start Time	Execute User	Progress	Status	Operation
5	hdfs-sftp-size	Export from HDFS to SF...	2016-03-26 14:45:08	admin	<div style="width: 100%;"></div>	Succeeded	[Action icons]
4	hdfs-sftp	Export from HDFS to SF...	2016-03-26 14:43:14	admin	<div style="width: 100%;"></div>	Succeeded	[Action icons]
3	sftp-hdfs-1-1	Import from SFTP to HD...	2016-03-26 12:00:36	admin	<div style="width: 100%;"></div>	Succeeded	[Action icons]
1	sftp-hdfs	Import from SFTP to HD...	2016-03-26 11:08:09	admin	<div style="width: 100%;"></div>	Succeeded	[Action icons]
2	sftp-hdfs-1	Import from SFTP to HD...	2016-03-26 11:07:56	admin	<div style="width: 100%;"></div>	Succeeded	[Action icons]

----End

## 13.4.9 Typical Scenario: Importing Data from a Relational Database to HBase

### Scenario

Use Loader to import data from a relational database to HBase.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HBase tables or phoenix tables that are used during job execution.
- You have obtained the username and password of the relational database.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes:  `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`.
  - b. Run the following command on the active and standby nodes as user `root` to modify the permission:
 

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/
FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/
webapps/loader/WEB-INF/ext-lib
chown omm:wheel JAR package name
chmod 600 JAR package name
```

- c. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader** > **More** > **Restart Service**. Enter the password of the administrator to restart the Loader service.


## Procedure

### Setting Basic Job Information

#### Step 1 Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-28 Loader web UI



#### Step 2 Click **New Job** to go to the **Basic Information** page and set basic job information.

Figure 13-29 Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

#### Step 3 In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or a dedicated database connector (oracle-connector, oracle-partition-connector, or mysql-fastpath-connector), set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**.

 **NOTE**

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When mysql-fastpath-connector is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManager nodes, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, install the MySQL client applications and tools following the instructions at <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>.

**Table 13-38 generic-jdbc-connector connection parameters**

Parameter	Description	Example Value
Name	Name of a relational database connection	dbName
JDBC Driver Class	Name of a JDBC driver class	oracle.jdbc.driver.OracleDriver
JDBC Connection String	JDBC connection string	jdbc:oracle:thin:@//10.16.0.1:1521/oradb
Username	Username for connecting to the database	omm
Password	Password for connecting to the database	xxxx
JDBC Connection Properties	JDBC connection attribute. Click <b>Add</b> to manually add the attribute. <ul style="list-style-type: none"> <li>• Name: connection attribute name</li> <li>• Value: connection attribute value</li> </ul>	<ul style="list-style-type: none"> <li>• Name: <b>socketTimeout</b></li> <li>• Value: <b>20</b></li> </ul>

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-39** Parameter description

Parameter	Description	Example Value
Schema Name	Database schema name. This parameter exists in the <b>Table name</b> schema.	dbo

Parameter	Description	Example Value
Table Name	Database table name. This parameter exists in the <b>Table name</b> schema.	test
SQL Statement	<p>SQL statement for Loader to query data to be imported in <b>Table SQL statement</b> mode. The SQL statement requires the query condition <b>WHERE \$ {CONDITIONS}</b>. Without this condition, the SQL statement cannot be run properly. An example SQL statement is as follows: <b>select * from TABLE WHERE A&gt;B and \$ {CONDITIONS}</b>. If <b>Table column names</b> is set, the column specified by <b>Table column names</b> will replace the column queried in the SQL statement. This parameter cannot be set when <b>Schema name</b> or <b>Table name</b> is set.</p> <p><b>NOTE</b> You can use macros to define SQL Where statements. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .</p>	select * from test where \$ {CONDITIONS}
Table Column Names	<p>Table columns whose content is to be imported by Loader. Use commas (,) to separate multiple fields.</p> <p>If the parameter is not set, all the columns are imported and the <b>Select *</b> order is used as the column location.</p>	-

Parameter	Description	Example Value
Partition Column Name	<p>Database table column based on which to-be-imported data is determined. This parameter is used for partitioning in a Map job. You are advised to configure the primary key field.</p> <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>• A partition column must have an index. If no index exists, do not specify a partition column. If a partition column without an index is specified, the database server disk I/O will be busy, the access of other services to the database will be affected, and the import will take a long period.</li> <li>• In multiple fields with indexes, select the field that has the most discrete value as the partition column. A partition column that is not discrete may result in load imbalance when multiple MapReduce jobs are imported.</li> <li>• The sorting rules of partition columns must be case-sensitive. Otherwise, data may be lost during data import.</li> <li>• You are not advised to select fields of the float or double type for the partition column. Otherwise, the records containing the minimum and maximum values of the partition column may fail to be imported due to precision issues.</li> </ul>	id
Nulls in Partition Column	<p>Indicates whether to process records whose values are null in database table columns.</p> <ul style="list-style-type: none"> <li>• <b>true</b>: Records whose values are null are processed.</li> <li>• <b>false</b>: Records whose values are not null are processed.</li> </ul>	true
Whether to Specify a Partition Column	Indicates whether to specify a partition column.	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-40](#).

**Table 13-40** Input and output parameters of the operator

Input Type	Output Type
Table input	HBase output

**Figure 13-30** Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **HBASE\_BULKLOAD** or **HBASE\_PUTLIST** based on the actual situation.

**Table 13-41** Parameter description

Storage Type	Applicable Scenario	Parameter	Description	Example Value
HBASE_BULKLOAD	Large data volume	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase

Storage Type	Applicable Scenario	Parameter	Description	Example Value
		Clear data before import	Indicates whether to clear data in the original table before importing data. <b>True</b> indicates clearing data and <b>False</b> indicates not to clear data. If you do not set this parameter, the original table is not cleared by default.	true
		Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.	20
		Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .	-
HBASE_P UTLIST	Small data volume	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
		Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.	true
		Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .	-

**Step 7** Click **Save and run** to save and run the job.

**Checking the Job Execution Result**

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

Figure 13-31 Viewing job details

Job ID	Name	Description	Start Time	Execute User	Progress	Status	Operation
5	hdfs-stfp-size	Export from HDFS to SF...	2016-03-26 14:45:08	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🗑️</a>
4	hdfs-stfp	Export from HDFS to SF...	2016-03-26 14:43:14	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🗑️</a>
3	stfp-hdfs-1-1	Import from SFTP to HD...	2016-03-26 12:00:36	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🗑️</a>
1	stfp-hdfs	Import from SFTP to HD...	2016-03-26 11:08:09	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🗑️</a>
2	stfp-hdfs-1	Import from SFTP to HD...	2016-03-26 11:07:56	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🗑️</a>

----End

## 13.4.10 Typical Scenario: Importing Data from a Relational Database to Hive

### Scenario

Use Loader to import data from a relational database to Hive.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the Hive tables that are used during job execution.
- You have obtained the username and password of the relational database.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes: `$(BIGDATA_HOME)/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`.
  - b. Run the following command on the active and standby nodes as user `root` to modify the permission:
 

```
cd $(BIGDATA_HOME)/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib
chown omm:wheel JAR package name
chmod 600 JAR package name
```
  - c. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader** > **More** > **Restart Service**. Enter the password of the administrator to restart the Loader service.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-32** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-33** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or a dedicated database connector (oracle-connector, oracle-partition-connector, or mysql-fastpath-connector), set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**.

 NOTE

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When mysql-fastpath-connector is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManager nodes, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, install the MySQL client applications and tools following the instructions at <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>.

**Table 13-42 generic-jdbc-connector connection parameters**

Parameter	Description	Example Value
Name	Name of a relational database connection	dbName
JDBC Driver Class	Name of a JDBC driver class	oracle.jdbc.driver.OracleDriver
JDBC Connection String	JDBC connection string	jdbc:oracle:thin:@//10.16.0.1:1521/oradb
Username	Username for connecting to the database	omm
Password	Password for connecting to the database	xxxx
JDBC Connection Properties	<p>JDBC connection attribute. Click <b>Add</b> to manually add the attribute.</p> <ul style="list-style-type: none"> <li>• Name: connection attribute name</li> <li>• Value: connection attribute value</li> </ul> <p><b>NOTICE</b> If a general connector is used to connect to the MySQL database and there a large amount of data, you need to set <b>useCursorFetch=true</b> in the JDBC connection string.</p>	<ul style="list-style-type: none"> <li>• Name: <b>socketTimeout</b></li> <li>• Value: <b>20</b></li> </ul>

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-43** Parameter description

Parameter	Description	Example Value
Schema Name	Database schema name. This parameter exists in the <b>Table name</b> schema.	dbo
Table Name	Database table name. This parameter exists in the <b>Table name</b> schema.	test
SQL Statement	<p>SQL statement for Loader to query data to be imported in <b>Table SQL statement</b> mode. The SQL statement requires the query condition <b>WHERE \$ {CONDITIONS}</b>. Without this condition, the SQL statement cannot be run properly. An example SQL statement is as follows: <b>select * from TABLE WHERE A&gt;B and \$ {CONDITIONS}</b>. If <b>Table column names</b> is set, the column specified by <b>Table column names</b> will replace the column queried in the SQL statement. This parameter cannot be set when <b>Schema name</b> or <b>Table name</b> is set.</p> <p><b>NOTE</b>                      You can use macros to define SQL Where statements. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .</p>	select * from test where \$ {CONDITIONS}
Table Column Names	<p>Table columns whose content is to be imported by Loader. Use commas (,) to separate multiple fields.</p> <p>If the parameter is not set, all the columns are imported and the <b>Select *</b> order is used as the column location.</p>	-

Parameter	Description	Example Value
Partition Column Name	<p>Database table column based on which to-be-imported data is determined. This parameter is used for partitioning in a Map job. You are advised to configure the primary key field.</p> <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>• A partition column must have an index. If no index exists, do not specify a partition column. If a partition column without an index is specified, the database server disk I/O will be busy, the access of other services to the database will be affected, and the import will take a long period.</li> <li>• In multiple fields with indexes, select the field that has the most discrete value as the partition column. A partition column that is not discrete may result in load imbalance when multiple MapReduce jobs are imported.</li> <li>• The sorting rules of partition columns must be case-sensitive. Otherwise, data may be lost during data import.</li> <li>• You are not advised to select fields of the float or double type for the partition column. Otherwise, the records containing the minimum and maximum values of the partition column may fail to be imported due to precision issues.</li> </ul>	id
Nulls in Partition Column	<p>Indicates whether to process records whose values are null in database table columns.</p> <ul style="list-style-type: none"> <li>• <b>true</b>: Records whose values are null are processed.</li> <li>• <b>false</b>: Records whose values are not null are processed.</li> </ul>	true
Whether to Specify a Partition Column	Indicates whether to specify a partition column.	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-44](#).

**Table 13-44** Input and output parameters of the operator

Input Type	Output Type
Table input	Hive output

**Figure 13-34** Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **HIVE**.

**Table 13-45** Parameter description

Parameter	Description	Example Value
Output Directory	Directory for storing data imported into Hive. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/opt/ tempfile
Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the SFTP server.	20
Extractor Size	Hive does not support this parameter. Please set <b>Extractors</b> .	-

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-35** Viewing job details

Job ID	Name	Description	Start Time	Execute User	Progress	Status	Operation
5	hdfs-stp-size	Export from HDFS to SF...	2016-03-26 14:45:08	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🔍</a>
4	hdfs-stp	Export from HDFS to SF...	2016-03-26 14:43:14	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🔍</a>
3	stf-hdfs-1-1	Import from SFTP to HD...	2016-03-26 12:00:36	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🔍</a>
1	stf-hdfs	Import from SFTP to HD...	2016-03-26 11:08:09	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🔍</a>
2	stf-hdfs-1	Import from SFTP to HD...	2016-03-26 11:07:56	admin	<div style="width: 100%;"></div>	Succeeded	<a href="#">▶</a> <a href="#">📄</a> <a href="#">🔍</a>

----End

## 13.4.11 Typical Scenario: Importing Data from a Relational Database to Spark

### Scenario

Use Loader to import data from a relational database to Spark.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the Spark tables that are used during job execution.
- You have obtained the username and password of the relational database.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes:  `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`.
  - b. Run the following command on the active and standby nodes as user `root` to modify the permission:
 

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/  
FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/  
webapps/loader/WEB-INF/ext-lib  
chown omm:wheel JAR package name
```

*chmod 600 JAR package name*

- c. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader** > **More** > **Restart Service**. Enter the password of the administrator to restart the Loader service.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-36** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-37** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or a dedicated database connector (oracle-connector, oracle-partition-connector, or mysql-fastpath-connector), set connection

parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**.

 **NOTE**

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When mysql-fastpath-connector is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManager nodes, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, install the MySQL client applications and tools following the instructions at <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>.

**Table 13-46 generic-jdbc-connector connection parameters**

Parameter	Description	Example Value
Name	Name of a relational database connection	dbName
JDBC Driver Class	Name of a JDBC driver class	oracle.jdbc.driver.OracleDriver
JDBC Connection String	JDBC connection string	jdbc:oracle:thin:@//10.16.0.1:1521/oradb
Username	Username for connecting to the database	omm
Password	Password for connecting to the database	xxxx
JDBC Connection Properties	JDBC connection attribute. Click <b>Add</b> to manually add the attribute. <ul style="list-style-type: none"> <li>• Name: connection attribute name</li> <li>• Value: connection attribute value</li> </ul>	<ul style="list-style-type: none"> <li>• Name: <b>socketTimeout</b></li> <li>• Value: <b>20</b></li> </ul>

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-47** Parameter description

Parameter	Description	Example Value
Schema Name	Database schema name. This parameter exists in the <b>Table name</b> schema.	dbo
Table Name	Database table name. This parameter exists in the <b>Table name</b> schema.	test
SQL Statement	SQL statement for Loader to query data to be imported in <b>Table SQL statement</b> mode. The SQL statement requires the query condition <b>WHERE \$ {CONDITIONS}</b> . Without this condition, the SQL statement cannot be run properly. An example SQL statement is as follows: <b>select * from TABLE WHERE A&gt;B and \$ {CONDITIONS}</b> . If <b>Table column names</b> is set, the column specified by <b>Table column names</b> will replace the column queried in the SQL statement. This parameter cannot be set when <b>Schema name</b> or <b>Table name</b> is set. <b>NOTE</b> You can use macros to define SQL Where statements. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	select * from test where \$ {CONDITIONS}
Table Column Names	Table columns whose content is to be imported by Loader. Use commas (,) to separate multiple fields. If the parameter is not set, all the columns are imported and the <b>Select *</b> order is used as the column location.	-

Parameter	Description	Example Value
Partition Column Name	<p>Database table column based on which to-be-imported data is determined. This parameter is used for partitioning in a Map job. You are advised to configure the primary key field.</p> <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>• A partition column must have an index. If no index exists, do not specify a partition column. If a partition column without an index is specified, the database server disk I/O will be busy, the access of other services to the database will be affected, and the import will take a long period.</li> <li>• In multiple fields with indexes, select the field that has the most discrete value as the partition column. A partition column that is not discrete may result in load imbalance when multiple MapReduce jobs are imported.</li> <li>• The sorting rules of partition columns must be case-sensitive. Otherwise, data may be lost during data import.</li> <li>• You are not advised to select fields of the float or double type for the partition column. Otherwise, the records containing the minimum and maximum values of the partition column may fail to be imported due to precision issues.</li> </ul>	id
Nulls in Partition Column	<p>Indicates whether to process records whose values are null in database table columns.</p> <ul style="list-style-type: none"> <li>• <b>true</b>: Records whose values are null are processed.</li> <li>• <b>false</b>: Records whose values are not null are processed.</li> </ul>	true
Whether to Specify a Partition Column	Indicates whether to specify a partition column.	true


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-48](#).

**Table 13-48** Input and output parameters of the operator

Input Type	Output Type
Table input	Spark output

**Figure 13-38** Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **SPARK**.

**Table 13-49** Parameter description

Parameter	Description	Example Value
Output Directory	Directory for storing data imported into Spark. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/opt/tempfile
Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the SFTP server.	20
Extractor Size	Spark does not support this parameter. Please set <b>Extractors</b> .	-

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-39** Viewing job details

Job ID	Name	Description	Start Time	Execute User	Progress	Status	Operation
5	hdfs-sftp-size	Export from HDFS to SF...	2016-03-26 14:45:08	admin		Succeeded	
4	hdfs-sftp	Export from HDFS to SF...	2016-03-26 14:43:14	admin		Succeeded	
3	sftp-hdfs-1-1	Import from SFTP to HD...	2016-03-26 12:00:36	admin		Succeeded	
1	sftp-hdfs	Import from SFTP to HD...	2016-03-26 11:08:09	admin		Succeeded	
2	sftp-hdfs-1	Import from SFTP to HD...	2016-03-26 11:07:56	admin		Succeeded	

----End

## 13.4.12 Typical Scenario: Importing Data from HDFS or OBS to HBase

### Scenario

Use Loader to import data from HDFS or OBS to HBase.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HDFS or OBS directories and data involved in job execution.
- You have had the permission to access the HBase tables or phoenix tables that are used during job execution.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- When using Loader to import data from HDFS or OBS, the input paths and input path subdirectories of HDFS and the name of the files in these directories do not contain any of the special characters /'";,.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.

### Procedure


#### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).

2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-40** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-41** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **hdfs-connector**, set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**.

#### Setting Data Source Information

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-50** Parameter description

Parameter	Description	Example Value
Input Path	Input path of source files in HDFS or OBS <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/ user/ test
Path Filter	Wildcard for filtering the directories in the input paths of the source files. <b>Input Path</b> is not used for filtering. If there are multiple filter conditions, use commas (,) to separate them. If the parameter is empty, the directories are not filtered. The regular expression filtering is not supported.	*
File Filter	Wildcard for filtering the file names of the source files. If there are multiple filter conditions, use commas (,) to separate them. The value cannot be left blank. The regular expression filtering is not supported.	*
Encoding Type	Source file encoding format, for example, UTF-8. This parameter can be set only in text file import.	UTF-8
Suffix	File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file.	.log


### Setting Data Transformation

- Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-51](#).

**Table 13-51** Input and output parameters of the operator

Input Type	Output Type
CSV File Input	HBase Output
HTML Input	HBase Output
Fixed File Input	HBase Output

Figure 13-42 Operator operation procedure



Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **HBASE\_BULKLOAD** or **HBASE\_PUTLIST** based on the actual situation.

Table 13-52 Parameter description

Storage Type	Applicable Scenario	Parameter	Description	Example Value
HBASE_BULKLOAD	Large data volume	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
		Clear data before import	Indicates whether to clear data in the original table before importing data. <b>True</b> indicates clearing data and <b>False</b> indicates not to clear data. If you do not set this parameter, the original table is not cleared by default.	true
		Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.	20


Storage Type	Applicable Scenario	Parameter	Description	Example Value
		Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .	-
HBASE_PUTLIS T	Small data volume	HBase Instance	HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
		Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.	20
		Extractor Size	HBase does not support this parameter. Please set <b>Extractors</b> .	-

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-43** Viewing job details



----End

## 13.4.13 Typical Scenario: Importing Data from a Relational Database to ClickHouse

### Scenario

This section describes how to use Loader to import data from a relational database to ClickHouse using MySQL as an example.

## Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have created a ClickHouse table, and you have operation permissions on the table during job execution.
- You have obtained the user name and password of the MySQL database.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the MySQL client JAR file (for example, **mysqlclient-5.8.1.jar**) from the MySQL database installation path and save it to the following directory on the active and standby Loader nodes: **`\${BIGDATA\_HOME}/FusionInsight\_Porter\_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`**.
  - b. Obtain the **clickhouse-jdbc-\*.jar** file from the ClickHouse installation directory and save it in the **`\${BIGDATA\_HOME}/FusionInsight\_Porter\_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`** directory on the active and standby Loader nodes.
  - c. Run the following command on the active and standby nodes as user **root** to modify the permission:

```
cd `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/  
FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/  
webapps/loader/WEB-INF/ext-lib  
chown omm:wheel JAR file name  
chmod 600 JAR file name
```
  - d. Log in to FusionInsight Manager, choose **Cluster > Services > Loader > More > Restart Service** and enter the administrator password to restart the Loader service.


## Procedure

### Setting Basic Job Information

#### Step 1 Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster > Name of the desired cluster > Services > Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-44 Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

Figure 13-45 Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or a dedicated database connector (oracle-connector, oracle-partition-connector, or mysql-fastpath-connector), set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**.

**NOTE**

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When mysql-fastpath-connector is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManager nodes, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, install the MySQL client applications and tools following the instructions at <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>.

**Table 13-53** generic-jdbc-connector connection parameters

Parameter	Description	Example
Name	Name of a relational database connection	mysql_test
JDBC Driver Class	Name of a JDBC driver class	com.mysql.jdbc.Driver
JDBC Connection String	JDBC connection string	jdbc:mysql://10.254.144.102:3306/test?useUnicode=true&characterEncoding=UTF-8
Username	Username for connecting to the database	root
Password	Password for connecting to the database	xxxx

### Setting Data Source Information

**Step 4** Click **Next**. On the displayed **From** page, configure the data source information. Currently, only **Table name** is supported.

**Table 13-54** Parameter description

Parameter	Description	Example
Schema name	Schema name of the specified database	public
Table name	Table name	test
Table column names	Names of the columns to be imported	id,name
Need partition column	Currently, only the unspecified partition mode is supported.	false

### Setting Data Transformation


**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-55](#).

**Table 13-55** Input and output parameters of the operator

Input Type	Output Type
MySQL Input	ClickHouse Output


Drag **Table Input** to the grid, double-click **Table Input**, and select **autoRecognition**, as shown in **Figure 13-46**.

**Figure 13-46** Operator input



Drag **ClickHouse Output** to the grid, double-click **Table Output**, and select **associate** or manually edit the table to correspond to the input table, as shown in **Figure 13-47**.

**Figure 13-47** Operator output



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **CLICKHOUSE**.

**Table 13-56** Parameter description

Parameter	Description	Example
Storage type	Select <b>CLICKHOUSE</b> .	-
ClickHouse instance	Select <b>ClickHouse</b> .	-

Parameter	Description	Example
Clear data before import	Select <b>true</b> or <b>false</b> . <b>NOTE</b> ClickHouse distributed tables do not support clearing data before import. You need to manually clear the table.	true

**Step 7** Click **Save and Run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-48** Viewing job details

ID	Table Name	Operation	Start Time	User	Status	Actions
8	mysql_clickhouse-field...	Import from RDB to CL...	2021-06-23 19:53:12	admintest	Succeeded	▶ □ 📄 ▼
7	mysql_clickhouse-field	Import from RDB to CL...	2021-06-23 19:53:11	admintest	Succeeded	▶ □ 📄 ▼
6	mysql_clickhouse	Import from RDB to CL...	2021-06-23 19:16:09	admintest	Succeeded	▶ □ 📄 ▼

**Step 9** On the ClickHouse client, check whether the data in the ClickHouse table is the same as that in the MySQL table.

----End

## 13.4.14 Typical Scenario: Importing Data from HDFS to ClickHouse

### Scenario

Use Loader to import data from HDFS to ClickHouse.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HDFS directories and data involved in job execution.
- You have created a ClickHouse table, and you have operation permissions on the table during job execution.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- When using Loader to import data from HDFS, the input paths and input path subdirectories of HDFS and the name of the files in these directories do not contain any of the special characters `/'":;`.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-49** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-50** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Import**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **hdfs-connector**, set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**.

### Setting Data Source Information

**Step 4** Click **Next**. On the displayed **From** page, set the data source information.

**Table 13-57** Parameter description

Parameter	Description	Example
Input Path	Input path of source files in HDFS <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/user/test
Path Filter	Wildcard for filtering the directories in the input paths of the source files. <b>Input Path</b> is not used for filtering. If there are multiple filter conditions, use commas (,) to separate them. If the parameter is empty, the directories are not filtered. The regular expression filtering is not supported.	*
File Filter	Wildcard for filtering the file names of the source files. If there are multiple filter conditions, use commas (,) to separate them. The value cannot be left blank. The regular expression filtering is not supported.	*
Encoding Type	Source file encoding format, for example, UTF-8. This parameter can be set only in text file import.	UTF-8
Suffix	File name extension added to a source file after the source file is imported. If this parameter is empty, no file name extension is added to the source file.	.log

### Setting Data Transformation

- Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-58](#).

**Table 13-58** Input and output parameters of the operator

Input Type	Output Type
CSV File Input	ClickHouse Output

**Figure 13-51** Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set **Storage type** to **CLICKHOUSE** based on the actual situation.

**Table 13-59** Parameter description

Storage Type	Parameter	Description	Example
CLICKHOUSE	ClickHouse instance	ClickHouse service instance that Loader selects from all available ClickHouse service instances in the cluster. If the selected ClickHouse service instance is not added to the cluster, the ClickHouse job cannot be run properly.	ClickHouse
	Clear data before import	Whether to clear data in the original table before importing data <b>true</b> indicates clearing data and <b>false</b> indicates not to clear data. If you do not set this parameter, the original table is not cleared by default. <b>NOTE</b> ClickHouse distributed tables do not support clearing data before import. You need to manually clear the table.	false
	Extractors	Number of Maps that are started at the same time in a MapReduce task of a data configuration operation. The value must be less than or equal to 3000.	20
	Extractor size	ClickHouse does not support this parameter. Please set <b>Extractors</b> .	-
	Number	Number of Map tasks.	-

**Step 7** Click **Save and Run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the Loader web UI. When **Status** is **Succeeded**, the job is complete.

**Figure 13-52** Viewing job details



ID	Name	Source	Target	Time	User	Status
7	mysql_clickhouse-idea	Import from RDB to CL...	2021-06-23 19:53:11	admintest	Succeeded	
6	mysql_clickhouse	Import from RDB to CL...	2021-06-23 19:16:09	admintest	Succeeded	
2	hdfs_clickhouse	Import from HDFS to C...	2021-06-23 18:38:12	admintest	Succeeded	

**Step 9** On the ClickHouse client, check whether the data in the ClickHouse table is the same as that imported from HDFS.

----End

## 13.5 Exporting Data

### 13.5.1 Overview

#### Description

Loader is an extract, transform, and load (ETL) tool for exchanging data and files between MRS and relational databases and file systems. You can use the Loader to export data or files from MRS to the relational databases or file systems.

Loader supports the following data export modes:

- Exporting data from HDFS/OBS to an SFTP server
- Exporting data from HDFS/OBS to a relational database
- Exporting data from HBase to an SFTP server
- Exporting data from HBase to a relational database
- Exporting data from Phoenix tables to an SFTP server
- Exporting data from Phoenix tables to a relational database
- Exporting data from Hive to an SFTP server
- Exporting Data from Hive to a Relational Database
- Exporting data from HBase to HDFS/OBS in the same cluster

The MRS needs to connect to the data source to exchange data and files with the external data source. The following connectors are used to configure connection parameters for different types of data sources:

- `generic-jdbc-connector`: relational database connector
- `hdfs-connector`: HDFS data source connector
- `oracle-connector`: specifies a dedicated connector for Oracle databases. `row_id` serves as partition columns. Compared with `generic-jdbc-connector`, Map tasks are more evenly distributed on `oracle-connector`, and whether the partition columns have created indexes does not affect `oracle-connector`.
- `mysql-fastpath-connector`: specifies a dedicated connector for MySQL databases. Data is imported and exported by using the `mysqldump` and `mysqlimport` tools of MySQL. Compared with `generic-jdbc-connector`, the data import and export speed is faster.

- `sftp-connector`: SFTP data source connector
- `oracle-partition-connector`: connector that supports the Oracle partition feature, which is used to optimize the import and export of Oracle partition tables.


 **NOTE**

- You are advised to deploy the SFTP server, database server, and Loader into separate subnets to ensure secure data export.
- For connection to relational databases, general database connectors (`generic-jdbc-connector`) or dedicated database connectors (`oracle-connector`, `oracle-partition-connector`, and `mysql-fastpath-connector`) are available. However, compared with general database connectors, dedicated database connectors performs better in data import and export because it is optimized for specific database types.
- When **`mysql-fastpath-connector`** is used, the **`mysqldump`** and **`mysqlimport`** commands of MySQL must be available on NodeManagers, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, see <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>. Install the MySQL client applications and tools.
- When `oracle-connector` is used, the connection user must be granted the select permission on the following system catalogs or views:  
dba\_tab\_partitions, dba\_constraints, dba\_tables, dba\_segments, v\$instance, dba\_objects, v\$instance, dba\_extents, dba\_tab\_partitions and dba\_tab\_subpartitions.
- When `oracle-partition-connector` is used, the connection user must be granted the select permission on the following system catalogs: dba\_objects and dba\_extents.

## Export Process

A data export job can be executed in the Loader WebUI. [Figure 13-53](#) shows the export process.

**Figure 13-53** Export process



Loader jobs can also be updated and executed using shell scripts. In this mode, the Loader client that has been installed needs to be configured.

## 13.5.2 Using Loader to Export Data

### Scenario

This task enables you to export data from MRS to external data sources.

Generally, users can manually manage data import and export jobs on the Loader UI. To use shell scripts to update and run Loader jobs, you must configure the installed Loader client.

### Prerequisites

- You have obtained the service user name and password for creating a Loader job.
- You have had the permission to access the HDFS directories, HBase tables, and data involved in job execution.
- You have obtained the user name and password used by an external data source (SFTP server or relational database).
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.

- When using Loader to export data from HDFS/OBS, the input paths and input path subdirectories of HDFS/OBS data source and the name of the files in these directories do not contain any of the following special characters: `\/\"'";,.`
- If the job requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.

## Procedure

**Step 1** Check whether data is exported from Loader to a relational database for the first time.

- If yes, go to **Step 2**.
- If no, go to **Step 3**.

**Step 2** Modify the permission on the JAR package of the RDS driver.

1. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes:  `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`.
2. Run the following command on the active and standby nodes as user **root** to modify the permission:

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib
```

```
chown omm:wheel JAR package name
```


```
chmod 600 JAR package name
```

3. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Service** > **Loader** > **More** > **Restart**. Enter the password of the administrator to restart the Loader service.

**Step 3** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-54** Loader web UI



**Step 4** Create a Loader data import job. Click **New Job**. Select the required job type in **1. Basic Information** and click **Next**.

1. Set **Name** to the job name and **Type** to **Export**.
2. Select a connection for **Connection**. By default, no connection is created. Click **Add** to create a connection, and then click **Test** to test whether the connection is available. Click **OK** when the system displays a message indicates that the test is successful.

**Table 13-60** Connection configuration parameters

Connector Type	Parameter	Description
generic-jdbc-connector	JDBC Driver Class	Specifies the name of a JDBC driver class.
	JDBC Connection String	Specifies the JDBC connection string.
	Username	Specifies the username for connecting to the database.
	Password	Specifies the password for connecting to the database.
	JDBC Connection Properties	Specifies JDBC connection attributes. Click <b>Add</b> to manually add connection attributes. <ul style="list-style-type: none"> <li>- <b>Name</b>: connection attribute name</li> <li>- <b>Value</b>: connection attribute value</li> </ul>
hdfs-connector	-	-
oracle-connector	JDBC Connection String	Specifies connection string for a user to connect to the database.
	Username	Specifies the username for connecting to the database.
	Password	Specifies the password for connecting to the database.
	Connection Properties	Specifies connection attributes. Click <b>Add</b> to manually add connection attributes. <ul style="list-style-type: none"> <li>- <b>Name</b>: connection attribute name</li> <li>- <b>Value</b>: connection attribute value</li> </ul>
mysql-fastpath-connector	JDBC Connection String	Specifies the JDBC connection string.
	Username	Specifies the username for connecting to the database.

Connector Type	Parameter	Description
	Password	Specifies the password for connecting to the database.
	Connection Properties	Specifies connection attributes. Click <b>Add</b> to manually add connection attributes. <ul style="list-style-type: none"> <li>- <b>Name:</b> connection attribute name</li> <li>- <b>Value:</b> connection attribute value</li> </ul>
sftp-connector	SFTP Server IP	Specifies the IP address of the SFTP server.
	SFTP Server Port	Specifies the port number of the SFTP server.
	SFTP Username	Specifies the username for accessing the SFTP server.
	SFTP Password	Specifies the password for accessing the SFTP server.
	SFTP Public Key	Specifies public key of the SFTP server.
oracle-partition-connector	JDBC Driver Class	Specifies the name of a Java database connectivity (JDBC) driver class.
	JDBC Connection String	Specifies the JDBC connection string.
	Username	Specifies the username for connecting to the database.
	Password	Specifies the password for connecting to the database.
	Connection Properties	Specifies connection attributes. Click <b>Add</b> to manually add connection attributes. <ul style="list-style-type: none"> <li>- <b>Name:</b> connection attribute name</li> <li>- <b>Value:</b> connection attribute value</li> </ul>

3. Set **Group** to the group to which the job belongs. By default, there is no created group. Click **Add** to create a group and click **OK**.
4. **Queue** indicates that Loader tasks are executed in a specified Yarn queue. The default value is **root.default**, which indicates that the tasks are executed in the **default** queue.
5. Set **Priority** to the priority of Loader tasks in the specified Yarn queue. The options can be **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, or **VERY\_HIGH**. The default value is **NORMAL**.

**Step 5** In the **2. Input Settings** area, set the data source and click **Next**.

 NOTE

When creating or editing a Loader job, you can use macro definitions when configuring parameters such as the SFTP path, HDFS/OBS path, and Where condition of SQL. For details, see [Using Macro Definitions in Configuration Items](#) .

**Table 13-61** List of input configuration parameters

Source File Type	Parameter	Description
HDFS/OBS	Input Directory	Specifies the input path when data is exported from HDFS/OBS.
	Path Filter	Specifies the wildcard for filtering the directories in the input paths of the source files. <b>Input Directory</b> is not used in filtering. If there are multiple filter conditions, use commas (,) to separate them. If the value is empty, the directory is not filtered. The regular expression filtering is not supported.
	File Filter	Specifies the wildcard for filtering the file names of the source files. If there are multiple filter conditions, use commas (,) to separate them. The value cannot be left blank. The regular expression filtering is not supported.
	File Type	Specifies the file import type. <ul style="list-style-type: none"> <li>• <b>TEXT_FILE</b>: imports a text file and stores it as a text file.</li> <li>• <b>SEQUENCE_FILE</b>: imports a text file and stores it as a sequence file.</li> <li>• <b>BINARY_FILE</b>: imports files of any format by using binary streams.</li> </ul>
	File Split Type	Specifies whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each map in the MapReduce task for data export.
	Extractors	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. This parameter cannot be set when <b>Extractor Size</b> is set. The value must be less than or equal to 3000.

Source File Type	Parameter	Description
	Extractor size	Specifies the size of data processed by maps that are started in a MapReduce job of a data configuration operation. The unit is MB. The value must be greater than or equal to 100. The recommended value is <b>1000</b> . This parameter cannot be set when <b>Extractors</b> is set. When a relational database connector is used, <b>Extractor size</b> is unavailable. You need to set <b>Extractors</b> .
HBASE	HBase Instance	Specifies the HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.
	Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000.
HIVE	Hive instance	Specifies the Hive service instance that Loader selects from all available Hive service instances in the cluster. If the selected Hive service instance is not added to the cluster, the Hive job cannot run properly.
	Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000.
SPARK	Spark instance	Only SparkSQL can access Hive data. Specifies the SparkSQL service instance that Loader selects from all available SparkSQL service instances in the cluster. If the selected Spark service instance is not added to the cluster, the Spark job cannot be run properly.
	Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000.

**Step 6** In the **3. Convert** area, set the conversion operations during data transmission.

Check whether source data values in the data operation job created by the Loader can be directly used without conversion, including upper and lower case conversion, cutting, merging, and separation.

- If yes, click **Next**.

- If no, perform [Step 6.1](#) to [Step 6.4](#).
1. No created conversion step exists by default. Drag an example conversion step on the left to the edit box to create a new conversion step.
  2. Conversion step types must be selected based on service requirements. A complete conversion process includes the following types:
    - a. Input type. Only one conversion step can be added. This parameter is mandatory if the task involves HBase or relational databases.
    - b. Conversion type, which is an intermediate conversion step. You can add one or more conversion types or do not add any conversion type.
    - c. Output type. Only one output type can be added in the last conversion step. This parameter is mandatory if the task involves HBase or relational databases.

**Table 13-62** Example list

Type	Description
Input Type	<ul style="list-style-type: none"> <li>▪ <b>CSV File Input:</b> CSV file input step for configuring separators to generate multiple fields.</li> <li>▪ <b>Fixed-Width File Input:</b> Text file input step for configuring the length of characters or bytes to be truncated to generate multiple fields.</li> <li>▪ <b>Table Input:</b> relational data input step for configuring specified columns in the database as input fields.</li> <li>▪ <b>HBase Input:</b> HBase table input step for configuring the column definition of an HBase table to a specified field.</li> <li>▪ <b>HTML Input:</b> HTML web page data input step for obtaining the target data of the HTML web page file to the specified field.</li> <li>▪ <b>Hive Input:</b> Hive table input step for defining columns in a Hive table to specified fields.</li> <li>▪ <b>Spark Input:</b> Spark SQL table input step for defining columns in the SparkSQL table to specified fields. Only Hive data can be stored and accessed.</li> </ul>

Type	Description
Conversion type	<ul style="list-style-type: none"> <li data-bbox="762 309 1406 409">▪ <b>Long Integer Time Conversion:</b> Configure the conversion between a long integer value and a date.</li> <li data-bbox="762 434 1390 501">▪ <b>Null Value Conversion:</b> Configure a specified value to replace the null value.</li> <li data-bbox="762 526 1362 593">▪ <b>Random Value Conversion:</b> Configure new value-added fields as random data fields.</li> <li data-bbox="762 618 1374 685">▪ <b>Adding a Constant Field:</b> Add a constant to directly generate a constant field.</li> <li data-bbox="762 710 1426 810">▪ <b>Concatenation and Conversion:</b> Concatenate fields, connect generated fields using connection characters, and convert new fields.</li> <li data-bbox="762 835 1422 936">▪ <b>Separator Conversion:</b> Configure the generated fields to be separated by separators and convert new fields.</li> <li data-bbox="762 960 1390 1061">▪ <b>Modulo Conversion:</b> Configure the generated fields to be converted into new fields through modulo operation.</li> <li data-bbox="762 1086 1422 1187">▪ <b>Cutting Character String:</b> Truncate a generated field based on a specified position to generate a new field.</li> <li data-bbox="762 1211 1410 1346">▪ <b>EL Operation Conversion:</b> Calculate field values. Currently, the following operators are supported: md5sum, sha1sum, sha256sum, and sha512sum.</li> <li data-bbox="762 1370 1394 1471">▪ <b>Character String Case Conversion:</b> Configure the generated fields to be converted to new fields through case conversion.</li> <li data-bbox="762 1496 1315 1574">▪ <b>Reverse String Conversion:</b> Reverse the generated fields to generate new fields.</li> <li data-bbox="762 1599 1394 1700">▪ <b>Character String Space Clearing Conversion:</b> Configure the generated fields to clear spaces and convert them to new fields.</li> <li data-bbox="762 1724 1374 1825">▪ <b>Row Filtering Conversion:</b> Configure logical conditions to filter out rows that contain triggering conditions.</li> <li data-bbox="762 1850 1406 1906">▪ <b>Update Fields:</b> Update the value of a specified field when certain conditions are met.</li> </ul>

Type	Description
Output type	<ul style="list-style-type: none"> <li>▪ <b>File Output:</b> Configure generated fields to be connected by separators and exported to a file.</li> <li>▪ <b>Table Output:</b> Configure the mapping between output fields and specified columns in the database.</li> <li>▪ <b>HBase Output:</b> Configure the generated fields to the columns of the HBase table.</li> <li>▪ <b>Hive Output:</b> Configure generated fields to a column of a Hive table.</li> <li>▪ <b>Spark Output:</b> Configure generated fields to the columns of SparkSQL tables. Only SparkSQL can access Hive data.</li> </ul>

The edit box allows you to perform the following tasks:

- Re-command: Rename an example.
- Edit: Edit the step conversion by referring to [Step 6.3](#).
- Delete: Delete an example.

 **NOTE**

You can also use the shortcut key Del to delete the file.

3. Click **Edit** to edit the step conversion information and configure fields and data.

For details about how to set parameters in the step conversion information, see [Operator Help](#).

If the conversion step is incorrectly configured, the source data cannot be converted and become dirty data. The dirty data marking rules are as follows:

- In any input type step, the number of fields contained in the original data is less than the number of configured fields or the field values in the original data do not match the configured field type.
- In the **CSV File Input** step, **Validate input field** checks whether the input field matches the value type. If the input field and value type of a line do not match, the line is skipped and becomes dirty data.
- In the **Fixed Width File Input** step, **Fixed Length** specifies the field splitting length. If the length is greater than the length of the original field value, data splitting fails and the current line becomes dirty data.
- In the **HBase Input** step, if the HBase table name specified by **HBase Table Name** is incorrect, or no primary key column is configured for Primary Key, all data becomes dirty data.
- In any conversion step, lines whose conversion fails becomes dirty data. For example, in the **Split Conversion** step, the number of generated fields is less than the number of configured fields, or the original data

cannot be converted to the String type, and the current row becomes dirty data.

- In the **Filter Row Conversion** step, rows filtered by filter criteria become dirty data.
- In the **Modulo Conversion** step, if the original field value is NULL, the current row becomes dirty data.

4. Click **Next**.

**Step 7** In the **4. Output Settings** area, set the destination location for saving data and click **Save** to save the job or click **Save and Run** to save and run the job.

**Table 13-63** List of Output Configuration Parameters

Data Connection Type	Parameter	Description
sftp-connector	Output Path	Path or name of the export file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple paths or file names separated with semicolons (;). Ensure that the number of input paths or file names is the same as the number of SFTP servers configured for the connector.


Data Connection Type	Parameter	Description
	Operation	<p>Specifies the action during data import. When all data is to be imported from the input path to the destination path, the data is stored in a temporary directory and then copied from the temporary directory to the destination path. After the data is imported successfully, the data is deleted from the temporary directory. One of the following actions can be taken when duplicate file names exist during data transfer:</p> <ul style="list-style-type: none"> <li>• <b>OVERRIDE:</b> overrides the old file.</li> <li>• <b>RENAME:</b> renames as new file. For a file without an extension, a string is added to the file name as the extension; for a file with an extension, a string is added to the extension. The string is unique.</li> <li>• <b>APPEND:</b> adds the content of the new file to the end of the old file. This action only adds content regardless of whether the file can be used. For example, a text file can be used after this operation, while a compressed file cannot.</li> <li>• <b>IGNORE:</b> reserves the old file and does not copy the new file.</li> <li>• <b>ERROR:</b> stops the task and reports an error if duplicate file names exist. Transferred files are imported successfully, while files that have duplicate names and files that are not transferred fail to be imported.</li> </ul>
	Encode type	Specifies the exported file encoding format, for example, UTF-8. This parameter can be set only in text file export.
	Compression	Indicates whether to enable the compressed transmission function when SFTP is used to export data. <b>true</b> indicates that compression is enabled, and <b>false</b> indicates that compression is disabled.
hdfs-connector	Output Path	Specifies the output directory or file name of the export file in the HDFS/OBS.

Data Connection Type	Parameter	Description
	File Format	Specifies the file export type. <ul style="list-style-type: none"> <li>• <b>TEXT_FILE</b>: imports a text file and stores it as a text file.</li> <li>• <b>SEQUENCE_FILE</b>: imports a text file and stores it as a sequence file.</li> <li>• <b>BINARY_FILE</b>: imports files of any format by using binary streams.</li> </ul>
	Compression codec	Specifies the compression format of files exported to HDFS/OBS. Select a format from the drop-down list. If you select <b>NONE</b> or do not set this parameter, data is not compressed.
	User-defined compression format	Name of a user-defined compression format type.
generic-jdbc-connector	Schema name	Specifies the database schema name.
	Table name	Specifies the name of a database table that is used to save the final data of the transmission.
	Temporary table	Specifies the name of a temporary database table that is used to save temporary data during the transmission. The fields in the table must be the same as those in the database specified by <b>Table name</b> .
oracle-partition-connector	Schema Name	Specifies the database schema name.
	Table Name	Specifies the name of a database table that is used to save the final data of the transmission.
	Temporary Table	Specifies the name of a temporary database table that is used to save temporary data during the transmission. The fields in the table must be the same as those in the database specified by <b>Table name</b> .
oracle-connector	Table Name	Destination table name to store data.
	Column Name	Specifies the name of the column to be written. Columns that are not specified can be set to null or the default value.
mysql-fastpath-connector	Schema Name	Specifies the database schema name.

Data Connection Type	Parameter	Description
	Table Name	Specifies the name of a database table that is used to save the final data of the transmission.
	Temporary Table Name	Name of the temporary table, which is used to store data. After the job is successfully executed, data is transferred to the formal table.

**Step 8** On the Loader WebUI page, you can view, start, stop, copy, delete, edit, and view historical information about created jobs.

**Figure 13-55** Viewing Loader Jobs



----End

### 13.5.3 Typical Scenario: Exporting Data from HDFS/OBS to an SFTP Server

#### Scenario

This section describes how to use Loader to export data from HDFS/OBS to an SFTP server.

#### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HDFS or OBS directories and data involved in job execution.
- You have obtained the username and password of the SFTP server and the user has the write permission of the data export directory on the SFTP server.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- When using Loader to export data from HDFS/OBS, the input paths and input path subdirectories of HDFS/OBS data source and the name of the files in these directories do not contain any of the following special characters: \"/>

- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-56** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-57** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **sftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "**Test Success**" is displayed, click **OK**. Loader

allows multiple SFTP servers to be configured. Click **Add** to add the configuration information of multiple SFTP servers.

**Table 13-64** Connection parameters

Parameter	Description	Example Value
Name	Specifies the name of the SFTP server connection.	sftpName
SFTP Server IP	Specifies the IP address of the SFTP server.	10.16.0.1
SFTP Server Port	Specifies the port number of the SFTP server.	22
SFTP Username	Specifies the user name for accessing the SFTP server.	root
SFTP Password	Specifies the password for accessing the SFTP server.	xxxx
SFTP Public Key	Specifies public key of the SFTP server.	OdDt/yn...etM

 **NOTE**

When multiple SFTP servers are configured, the data of HDFS/OBS will be divided into multiple parts and exported to the SFTP servers randomly.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **HDFS**.

**Table 13-65** Data source parameters

Parameter	Description	Example Value
Input directory	Specifies the input path when data is exported from HDFS/OBS. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/ use r/ test

Parameter	Description	Example Value
Path filter	<p>Specifies the wildcard for filtering the directories in the input paths of the source files. <b>Input directory</b> is not used in filtering. If there are multiple filter conditions, use commas (,) to separate them. If the parameter is empty, the directory is not filtered. The regular expression filtering is not supported.</p> <ul style="list-style-type: none"> <li>● ? matches a single character.</li> <li>● * indicates multiple characters.</li> <li>● Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul>	*
File filter	<p>Specifies the wildcard for filtering the file names of the source files. If there are multiple filter conditions, use commas (,) to separate them. The value cannot be left blank. The regular expression filtering is not supported.</p> <ul style="list-style-type: none"> <li>● ? matches a single character.</li> <li>● * indicates multiple characters.</li> <li>● Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul>	*
File Type	<p>Specifies the file import type.</p> <ul style="list-style-type: none"> <li>● <b>TEXT_FILE</b>: imports a text file and stores it as a text file.</li> <li>● <b>SEQUENCE_FILE</b>: imports a text file and stores it as a <b>sequence file</b>.</li> <li>● <b>BINARY_FILE</b>: imports files of any format by using binary streams but not to process the files.</li> </ul> <p><b>NOTE</b> When the file import type to <b>TEXT_FILE</b> or <b>SEQUENCE_FILE</b>, Loader automatically selects a decompression method based on the file name extension to decompress a file.</p>	TEXT_FILE

Parameter	Description	Example Value
File Split Type	<p>Indicates whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each map in the MapReduce task for data export.</p> <ul style="list-style-type: none"> <li>● <b>FILE</b>: indicates that the source file is split by file. That is, each map processes one or multiple complete files, the same source file cannot be allocated to different maps, and the source file directory structure is retained after data import.</li> <li>● <b>SIZE</b>: indicates that the source file is split by size. That is, each map processes input files of a certain size, and a source file can be divided and processed by multiple maps. After data is stored in the output directory, the number of saved files is the same as the number of maps. The file name format is <b>import_part_xxxx</b>, where <b>xxxx</b> is a unique random number generated by the system.</li> </ul>	FILE
Extractors	<p>Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. This parameter cannot be set when <b>Extractor Size</b> is set. The value must be less than or equal to 3000. You are advised to set the parameter to the number of CPU cores on the SFTP server.</p> <p><b>NOTE</b> To improve the data import speed, ensure that the following conditions are met:</p> <ul style="list-style-type: none"> <li>● Each map connection is equivalent to a client connection. Therefore, you must ensure that the maximum number of connections of the SFTP server is greater than the number of maps.</li> <li>● Ensure that the disk I/O or network bandwidth on the SFTP server does not reach the upper limit.</li> </ul>	20
Extractor size	<p>Specifies the size of data processed by maps that are started in a MapReduce job of a data configuration operation. The unit is MB. The value must be greater than or equal to 100. The recommended value is 1000. This parameter cannot be set when <b>Extractors</b> is set.</p>	-


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-66](#).

**Table 13-66** Setting the input and output parameters of the operator

Input Type	Export Type
CSV file input	File output
HTML input	File output
Fixed-width file input	File output

**Figure 13-58** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

**Table 13-67** Parameter description

Parameter	Description	Example Value
Output path	<p>Specifies the path or file name of the exported file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple paths or file names separated with semicolons (;). Ensure that the number of paths or file names is the same as the number of SFTP servers configured for the connector.</p> <p><b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .</p>	/opt/tempfile
Operation	<p>Specifies the action during data import. When all data is to be imported from the input path to the destination path, the data is stored in a temporary directory and then copied from the temporary directory to the destination path. After the data is imported successfully, the data is deleted from the temporary directory. One of the following actions can be taken when duplicate file names exist during data transfer:</p> <ul style="list-style-type: none"> <li>● <b>OVERWRITE</b>: overrides the old file.</li> <li>● <b>RENAME</b>: renames as new file. For a file without an extension, a string is added to the file name as the extension; for a file with an extension, a string is added to the extension. The string is unique.</li> <li>● <b>APPEND</b>: adds the content of the new file to the end of the old file. This action only adds content regardless of whether the file can be used. For example, a text file can be used after this operation, while a compressed file cannot.</li> <li>● <b>IGNORE</b>: reserves the old file and does not copy the new file.</li> <li>● <b>ERROR</b>: stops the task and reports an error if duplicate file names exist. Transferred files are imported successfully, while files that have duplicate names and files that are not transferred fail to be imported.</li> </ul>	OVER RIDE
Encode type	Specifies the exported file encoding format, for example, UTF-8. This parameter can be set only in text file export.	UTF-8


Parameter	Description	Example Value
Compression	<p>Indicates whether to enable the compressed transmission function when SFTP is used to export data.</p> <ul style="list-style-type: none"> <li>The value <b>true</b> indicates that compression is enabled.</li> <li>The value <b>false</b> indicates that compression is disabled.</li> </ul>	true

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

**Figure 13-59** Viewing a job



----End

## 13.5.4 Typical Scenario: Exporting Data from HBase to an SFTP Server

### Scenario

Use Loader to export data from HBase to an SFTP server.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HBase tables or phoenix tables that are used during job execution.
- You have obtained the username and password of the SFTP server and the user has the write permission of the data export directory on the SFTP server.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.

- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-60** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-61** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **sftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "**Test Success**" is displayed, click **OK**. Loader allows multiple SFTP servers to be configured. Click **Add** to add the configuration information of multiple SFTP servers.

**Table 13-68** Connection parameters

Parameter	Description	Example Value
Name	Specifies the name of the SFTP server connection.	sftpName
SFTP server IP	Specifies the IP address of the SFTP server.	10.16.0.1
SFTP server port	Specifies the port number of the SFTP server.	22
SFTP username	Specifies the user name for accessing the SFTP server.	root
SFTP password	Specifies the password for accessing the SFTP server.	xxxx
SFTP public key	Specifies public key of the SFTP server.	OdDt/yn...etM

 **NOTE**

When multiple SFTP servers are configured, the data of HBase tables or phoenix tables will be divided into multiple parts and saved to the SFTP servers randomly.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **HBASE**.

**Table 13-69** Data source parameters

Parameter	Description	Example Value
HBase instance	Specifies the HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the SFTP server.	20


**Setting Data Transformation**

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-70](#).

**Table 13-70** Setting the input and output parameters of the operator

Input Type	Export Type
HBase input	File output

**Figure 13-62** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

**Table 13-71** Parameter description

Parameter	Description	Example Value
Output path	Specifies the path or file name of the exported file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple paths or file names separated with semicolons (;). Ensure that the number of paths or file names is the same as the number of SFTP servers configured for the connector.  <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/opt/tem pfile

Parameter	Description	Example Value
Operation	<p>Specifies the action during data import. When all data is to be imported from the input path to the destination path, the data is stored in a temporary directory and then copied from the temporary directory to the destination path. After the data is imported successfully, the data is deleted from the temporary directory. One of the following actions can be taken when duplicate file names exist during data transfer:</p> <ul style="list-style-type: none"> <li>● <b>OVERRIDE</b>: overrides the old file.</li> <li>● <b>RENAME</b>: renames as new file. For a file without an extension, a string is added to the file name as the extension; for a file with an extension, a string is added to the extension. The string is unique.</li> <li>● <b>APPEND</b>: adds the content of the new file to the end of the old file. This action only adds content regardless of whether the file can be used. For example, a text file can be used after this operation, while a compressed file cannot.</li> <li>● <b>IGNORE</b>: reserves the old file and does not copy the new file.</li> <li>● <b>ERROR</b>: stops the task and reports an error if duplicate file names exist. Transferred files are imported successfully, while files that have duplicate names and files that are not transferred fail to be imported.</li> </ul>	OVERRIDE
Encode type	Specifies the exported file encoding format, for example, UTF-8. This parameter can be set only in text file export.	UTF-8
Compression	<p>Indicates whether to enable the compressed transmission function when SFTP is used to export data.</p> <ul style="list-style-type: none"> <li>● The value <b>true</b> indicates that compression is enabled.</li> <li>● The value <b>false</b> indicates that compression is disabled.</li> </ul>	true

**Step 7** Click **Save and run** to save and run the job.

#### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

Figure 13-63 Viewing a job

Job ID	Name	Description	Start Time	Execute User	Progress	Status	Operation
5	hdfs-sftp-size	Export from HDFS to SF...	2016-03-26 14:45:08	admin		Succeeded	
4	hdfs-sftp	Export from HDFS to SF...	2016-03-26 14:43:14	admin		Succeeded	
3	sftp-hdfs-1-1	Import from SFTP to HD...	2016-03-26 12:00:36	admin		Succeeded	
1	sftp-hdfs	Import from SFTP to HD...	2016-03-26 11:08:09	admin		Succeeded	
2	sftp-hdfs-1	Import from SFTP to HD...	2016-03-26 11:07:56	admin		Succeeded	

----End

## 13.5.5 Typical Scenario: Exporting Data from Hive to an SFTP Server

### Scenario

Use Loader to export data from Hive to an SFTP server.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the Hive table specified in the job.
- You have obtained the username and password of the SFTP server and the user has the write permission of the data export directory on the SFTP server.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.

### Procedure

#### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.
  - a. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-64 Loader web UI

**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-65 Basic Information**

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **sftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "**Test Success**" is displayed, click **OK**. Loader allows multiple SFTP servers to be configured. Click **Add** to add the configuration information of multiple SFTP servers.

**Table 13-72** Connection parameters

Parameter	Description	Example Value
<b>Name</b>	Specifies the name of the SFTP server connection.	sftpName
SFTP server IP	Specifies the IP address of the SFTP server.	10.16.0.1
SFTP server port	Specifies the port number of the SFTP server.	22
SFTP username	Specifies the user name for accessing the SFTP server.	root
SFTP password	Specifies the password for accessing the SFTP server.	xxxx
SFTP public key	Specifies public key of the SFTP server.	OdDt/yn...etM

 **NOTE**

When multiple SFTP servers are configured, the data of Hive tables will be divided into multiple parts and saved to the SFTP servers randomly.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **HIVE**.

**Table 13-73** Data source parameters

Parameter	Description	Example Value
Hive instance	Specifies the Hive service instance that Loader selects from all available Hive service instances in the cluster. If the selected Hive service instance is not added to the cluster, the Hive job cannot run properly.	hive
Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the SFTP server.	20


**Setting Data Transformation**

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-74](#).

**Table 13-74** Setting the input and output parameters of the operator

Input Type	Export Type
Hive input	File output

**Figure 13-66** Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

**Table 13-75** Parameter description

Parameter	Description	Example Value
Output path	Specifies the path or file name of the exported file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple paths or file names separated with semicolons (;). Ensure that the number of paths or file names is the same as the number of SFTP servers configured for the connector. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/opt/tem pfile

Parameter	Description	Example Value
Operation	<p>Specifies the action during data import. When all data is to be imported from the input path to the destination path, the data is stored in a temporary directory and then copied from the temporary directory to the destination path. After the data is imported successfully, the data is deleted from the temporary directory. One of the following actions can be taken when duplicate file names exist during data transfer:</p> <ul style="list-style-type: none"> <li>● <b>OVERRIDE</b>: overrides the old file.</li> <li>● <b>RENAME</b>: renames as new file. For a file without an extension, a string is added to the file name as the extension; for a file with an extension, a string is added to the extension. The string is unique.</li> <li>● <b>APPEND</b>: adds the content of the new file to the end of the old file. This action only adds content regardless of whether the file can be used. For example, a text file can be used after this operation, while a compressed file cannot.</li> <li>● <b>IGNORE</b>: reserves the old file and does not copy the new file.</li> <li>● <b>ERROR</b>: stops the task and reports an error if duplicate file names exist. Transferred files are imported successfully, while files that have duplicate names and files that are not transferred fail to be imported.</li> </ul>	OVERRIDE
Encode type	Specifies the exported file encoding format, for example, UTF-8. This parameter can be set only in text file export.	UTF-8
Compression	<p>Indicates whether to enable the compressed transmission function when SFTP is used to export data.</p> <ul style="list-style-type: none"> <li>● The value <b>true</b> indicates that compression is enabled.</li> <li>● The value <b>false</b> indicates that compression is disabled.</li> </ul>	true

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

**Figure 13-67** Viewing a job

Job ID	Name	Description	Start Time	Execute User	Progress	Status	Operation
5	hdfs-sftp-size	Export from HDFS to SF...	2016-03-26 14:45:08	admin		Succeeded	
4	hdfs-sftp	Export from HDFS to SF...	2016-03-26 14:43:14	admin		Succeeded	
3	sftp-hdfs-1-1	Import from SFTP to HD...	2016-03-26 12:00:36	admin		Succeeded	
1	sftp-hdfs	Import from SFTP to HD...	2016-03-26 11:08:09	admin		Succeeded	
2	sftp-hdfs-1	Import from SFTP to HD...	2016-03-26 11:07:56	admin		Succeeded	

----End

## 13.5.6 Typical Scenario: Exporting Data from Spark to an SFTP Server

### Scenario

This section describes how to use Loader to export data from Spark to an SFTP server.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the Spark table specified in the job.
- You have obtained the username and password of the SFTP server and the user has the write permission of the data export directory on the SFTP server.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


### Procedure

#### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-68** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-69 Basic Information**

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **sftp-connector**, click **Add**, set connection parameters, and click **Test** to verify whether the connection is available. When "**Test Success**" is displayed, click **OK**. Loader allows multiple SFTP servers to be configured. Click **Add** to add the configuration information of multiple SFTP servers.

**Table 13-76** Connection parameters

Parameter	Description	Example Value
<b>Name</b>	Specifies the name of the SFTP server connection.	sftpName
SFTP server IP	Specifies the IP address of the SFTP server.	10.16.0.1
SFTP server port	Specifies the port number of the SFTP server.	22
SFTP username	Specifies the user name for accessing the SFTP server.	root
SFTP password	Specifies the password for accessing the SFTP server.	xxxx
SFTP public key	Specifies public key of the SFTP server.	OdDt/yn...etM

 **NOTE**

When multiple SFTP servers are configured, the data of Spark tables will be divided into multiple parts and saved to the SFTP servers randomly.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **SPARK**.

**Table 13-77** Data source parameters

Parameter	Description	Example Value
Spark instance	Specifies the Spark service instance that Loader selects from all available Spark service instances in the cluster. If the selected Spark service instance is not added to the cluster, the Spark job cannot be run properly.	spark
Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000. You are advised to set the parameter to the maximum number of connections on the SFTP server.	20


**Setting Data Transformation**

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-78](#).

**Table 13-78** Setting the input and output parameters of the operator

Input Type	Export Type
Spark Input	File output

**Figure 13-70** Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

**Table 13-79** Parameter description

Parameter	Description	Example Value
Output path	Specifies the path or file name of the exported file on an SFTP server. If multiple SFTP server IP addresses are configured for the connector, you can set this parameter to multiple paths or file names separated with semicolons (;). Ensure that the number of paths or file names is the same as the number of SFTP servers configured for the connector. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/opt/tem pfile

Parameter	Description	Example Value
Operation	<p>Specifies the action during data import. When all data is to be imported from the input path to the destination path, the data is stored in a temporary directory and then copied from the temporary directory to the destination path. After the data is imported successfully, the data is deleted from the temporary directory. One of the following actions can be taken when duplicate file names exist during data transfer:</p> <ul style="list-style-type: none"> <li>● <b>OVERRIDE</b>: overrides the old file.</li> <li>● <b>RENAME</b>: renames as new file. For a file without an extension, a string is added to the file name as the extension; for a file with an extension, a string is added to the extension. The string is unique.</li> <li>● <b>APPEND</b>: adds the content of the new file to the end of the old file. This action only adds content regardless of whether the file can be used. For example, a text file can be used after this operation, while a compressed file cannot.</li> <li>● <b>IGNORE</b>: reserves the old file and does not copy the new file.</li> <li>● <b>ERROR</b>: stops the task and reports an error if duplicate file names exist. Transferred files are imported successfully, while files that have duplicate names and files that are not transferred fail to be imported.</li> </ul>	OVERRIDE
Encode type	Specifies the exported file encoding format, for example, UTF-8. This parameter can be set only in text file export.	UTF-8
Compression	<p>Indicates whether to enable the compressed transmission function when SFTP is used to export data.</p> <ul style="list-style-type: none"> <li>● The value <b>true</b> indicates that compression is enabled.</li> <li>● The value <b>false</b> indicates that compression is disabled.</li> </ul>	true

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

Figure 13-71 Viewing a job

Job ID	Name	Description	Start Time	Execute User	Progress	Status	Operation
5	hdfs-sftp-size	Export from HDFS to SF...	2016-03-26 14:45:08	admin	<div style="width: 100%; background-color: green;"></div>	Succeeded	[Action icons]
4	hdfs-sftp	Export from HDFS to SF...	2016-03-26 14:43:14	admin	<div style="width: 100%; background-color: green;"></div>	Succeeded	[Action icons]
3	sftp-hdfs-1-1	Import from SFTP to HD...	2016-03-26 12:00:36	admin	<div style="width: 100%; background-color: green;"></div>	Succeeded	[Action icons]
1	sftp-hdfs	Import from SFTP to HD...	2016-03-26 11:08:09	admin	<div style="width: 100%; background-color: green;"></div>	Succeeded	[Action icons]
2	sftp-hdfs-1	Import from SFTP to HD...	2016-03-26 11:07:56	admin	<div style="width: 100%; background-color: green;"></div>	Succeeded	[Action icons]

----End

## 13.5.7 Typical Scenario: Exporting Data from HDFS/OBS to a Relational Database

### Scenario

This section describes how to use Loader to export data from HDFS/OBS to a relational database.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HDFS or OBS directories and data involved in job execution.
- You have obtained the username and password of the relational database.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes: `$ {BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`.
  - b. Run the following command on the active and standby nodes as user root to modify the permission:
 

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/
FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/
webapps/loader/WEB-INF/ext-lib
chown omm:wheel JAR package name
chmod 600 JAR package name
```
  - c. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Service** > **Loader** > **More** > **Restart**. Enter the password of the administrator to restart the Loader service.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-72** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-73** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or dedicated database connector (oracle-connector, oracle-partition-connector or mysql-fastpath-connector), set connection parameters, and click **Test** to verify whether the connection is available. When "**Test Success**" is displayed, click **OK**.

 **NOTE**

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When **mysql-fastpath-connector** is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManagers, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, see <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>. Install the MySQL client applications and tools.

**Table 13-80 generic-jdbc-connector connection parameters**

Parameter	Description	Example Value
Name	Specifies the name of a relational database connection.	dbName
JDBC Driver Class	Specifies the name of a Java database connectivity (JDBC) driver class.	oracle.jdbc.driver.OracleDriver
JDBC Connection String	Specifies the JDBC connection string.	jdbc:oracle:thin:@//10.16.0.1:1521/oradb
Username	Specifies the username for connecting to the database.	omm
Password	Specifies the password for connecting to the database.	xxxx
JDBC Connection Properties	JDBC connection attribute. Click <b>Add</b> to manually add the attribute. <ul style="list-style-type: none"> <li>• Name: connection attribute name</li> <li>• Value: connection attribute value</li> </ul>	<ul style="list-style-type: none"> <li>• Name: socketTimeout</li> <li>• Value: 20</li> </ul>

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **HDFS**.

**Table 13-81** Data source parameters

Parameter	Description	Example Value
Input directory	Specifies the input path when data is exported from HDFS/OBS. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/ user/ test
Path filter	Specifies the wildcard for filtering the directories in the input paths of the source files. <b>Input directory</b> is not used in filtering. If there are multiple filter conditions, use commas (,) to separate them. If the parameter is empty, the directory is not filtered. The regular expression filtering is not supported. <ul style="list-style-type: none"> <li>● ? matches a single character.</li> <li>● * indicates multiple characters.</li> <li>● Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul>	*
File filter	Specifies the wildcard for filtering the file names of the source files. If there are multiple filter conditions, use commas (,) to separate them. The value cannot be left blank. The regular expression filtering is not supported. <ul style="list-style-type: none"> <li>● ? matches a single character.</li> <li>● * indicates multiple characters.</li> <li>● Adding ^ before the condition indicates negated filtering, that is, file filtering.</li> </ul>	*
File Type	Specifies the file import type. <ul style="list-style-type: none"> <li>● <b>TEXT_FILE</b>: imports a text file and stores it as a text file.</li> <li>● <b>SEQUENCE_FILE</b>: imports a text file and stores it as a sequence file.</li> <li>● <b>BINARY_FILE</b>: imports files of any format by using binary streams but not to process the files.</li> </ul> <b>NOTE</b> When the file import type to <b>TEXT_FILE</b> or <b>SEQUENCE_FILE</b> , Loader automatically selects a decompression method based on the file name extension to decompress a file.	TEXT_FILE

Parameter	Description	Example Value
File split type	<p>Indicates whether to split source files by file name or size. The files obtained after the splitting are used as the input files of each map in the MapReduce task for data export.</p> <ul style="list-style-type: none"> <li>● <b>FILE</b>: indicates that the source file is split by file. That is, each map processes one or multiple complete files, the same source file cannot be allocated to different maps, and the source file directory structure is retained after data import.</li> <li>● <b>SIZE</b>: indicates that the source file is split by size. That is, each map processes input files of a certain size, and a source file can be divided and processed by multiple maps. After data is stored in the output directory, the number of saved files is the same as the number of maps. The file name format is <b>import_part_xxxx</b>, where <b>xxxx</b> is a unique random number generated by the system.</li> </ul>	FILE
Extractors	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. This parameter cannot be set when <b>Extractor size</b> is set. The value must be less than or equal to 3000.	20
Extractor size	Specifies the size of data processed by maps that are started in a MapReduce job of a data configuration operation. The unit is MB. The value must be greater than or equal to 100. The recommended value is 1000. This parameter cannot be set when <b>Extractors</b> is set. When a relational database connector is used, <b>Extractor size</b> is unavailable. You need to set <b>Extractors</b> .	-

### Setting Data Transformation


**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-82](#).

**Table 13-82** Setting the input and output parameters of the operator

Input Type	Export Type
CSV file input	Table output

Input Type	Export Type
HTML Input	Table output
Fixed-width file input	Table output

Figure 13-74 Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

Table 13-83 Parameter description

Parameter	Description	Example Value
Schema name	Specifies the database schema name.	dbo
Table Name	Specifies the name of a database table that is used to save the final data of the transmission. <b>NOTE</b> Table names can be defined using macros. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	test


Parameter	Description	Example Value
Temporary table	<p>Specifies the name of a temporary database table that is used to save temporary data during the transmission. The fields in the table must be the same as those in the database specified by <b>Table name</b>.</p> <p><b>NOTE</b> A temporary table is used to prevent dirty data from being generated in the destination table when data is exported to the database. Data is migrated from the temporary table to the destination table only after all data is successfully written to the temporary table. Using temporary tables increases the job execution time.</p>	tmp_test

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

**Figure 13-75** Viewing a job



----End

## 13.5.8 Typical Scenario: Exporting Data from HBase to a Relational Database

### Scenario

Use Loader to export data from HBase to a relational database.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the HBase tables or phoenix tables that are used during job execution.
- You have obtained the username and password of the relational database.

- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes: `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`.
  - b. Run the following command on the active and standby nodes as user root to modify the permission:

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/  
FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/  
webapps/loader/WEB-INF/ext-lib  
chown omm:wheel JAR package name  
chmod 600 JAR package name
```
  - c. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Service** > **Loader** > **More** > **Restart**. Enter the password of the administrator to restart the Loader service.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-76** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-77 Basic Information**

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or dedicated database connector (oracle-connector, oracle-partition-connector or mysql-fastpath-connector), set connection parameters, and click **Test** to verify whether the connection is available. When "**Test Success**" is displayed, click **OK**.

**NOTE**

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When **mysql-fastpath-connector** is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManagers, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, see <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>. Install the MySQL client applications and tools.

**Table 13-84 generic-jdbc-connector connection parameters**

Parameter	Description	Example Value
<b>Name</b>	Specifies the name of a relational database connection.	dbName
JDBC Driver Class	Specifies the name of a Java database connectivity (JDBC) driver class.	oracle.jdbc.driver.OracleDriver

Parameter	Description	Example Value
JDBC Connection String	Specifies the JDBC connection string.	jdbc:oracle:thin:@//10.16.0.1:1521/oradb
Username	Specifies the username for connecting to the database.	omm
Password	Specifies the password for connecting to the database.	xxxx
JDBC Connection Properties	JDBC connection attribute. Click <b>Add</b> to manually add the attribute. <ul style="list-style-type: none"> <li>Name: connection attribute name</li> <li>Value: connection attribute value</li> </ul>	<ul style="list-style-type: none"> <li>Name: socketTimeout</li> <li>Value: 20</li> </ul>

### Setting Data Source Information

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **HBASE**.

**Table 13-85** Data source parameters

Parameter	Description	Example Value
HBase instance	Specifies the HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000.	20


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-86](#).

**Table 13-86** Setting the input and output parameters of the operator

Input Type	Export Type
HBase input	Table output

**Figure 13-78** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

**Table 13-87** Parameter description

Parameter	Description	Example Value
Schema name	Specifies the database schema name.	dbo
Table name	Specifies the name of a database table that is used to save the final data of the transmission. <b>NOTE</b> Table names can be defined using macros. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	test


Parameter	Description	Example Value
Temporary table	<p>Specifies the name of a temporary database table that is used to save temporary data during the transmission. The fields in the table must be the same as those in the database specified by <b>Table name</b>.</p> <p><b>NOTE</b> A temporary table is used to prevent dirty data from being generated in the destination table when data is exported to the database. Data is migrated from the temporary table to the destination table only after all data is successfully written to the temporary table. Using temporary tables increases the job execution time.</p>	tm p_ t est

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

**Figure 13-79** Viewing a job



----End

## 13.5.9 Typical Scenario: Exporting Data from Hive to a Relational Database

### Scenario

Use Loader to export data from Hive to a relational database.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the Hive tables that are used during job execution.
- You have obtained the username and password of the relational database.

- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes: `${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`.
  - b. Run the following command on the active and standby nodes as user root to modify the permission:

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/  
FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/  
webapps/loader/WEB-INF/ext-lib  
chown omm:wheel JAR package name  
chmod 600 JAR package name
```
  - c. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Service** > **Loader** > **More** > **Restart**. Enter the password of the administrator to restart the Loader service.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-80** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-81 Basic Information**

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or dedicated database connector (oracle-connector, oracle-partition-connector or mysql-fastpath-connector), set connection parameters, and click **Test** to verify whether the connection is available. When "**Test Success**" is displayed, click **OK**.

**NOTE**

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When **mysql-fastpath-connector** is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManagers, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, see <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>. Install the MySQL client applications and tools.

**Table 13-88 generic-jdbc-connector connection parameters**

Parameter	Description	Example Value
Name	Specifies the name of a relational database connection.	dbName
JDBC Driver Class	Specifies the name of a Java database connectivity (JDBC) driver class.	oracle.jdbc.driver.OracleDriver

Parameter	Description	Example Value
JDBC Connection String	Specifies the JDBC connection string.	jdbc:oracle:thin:@//10.16.0.1:1521/oradb
Username	Specifies the username for connecting to the database.	omm
Password	Specifies the password for connecting to the database.	xxxx
JDBC Connection Properties	JDBC connection attribute. Click <b>Add</b> to manually add the attribute. <ul style="list-style-type: none"> <li>Name: connection attribute name</li> <li>Value: connection attribute value</li> </ul>	<ul style="list-style-type: none"> <li>Name: socketTimeout</li> <li>Value: 20</li> </ul>

### Setting Data Source Information

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **HIVE**.

**Table 13-89** Data source parameters

Parameter	Description	Example Value
Hive instance	Specifies the Hive service instance that Loader selects from all available Hive service instances in the cluster. If the selected Hive service instance is not added to the cluster, the Hive job cannot run properly.	hive
Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000.	20


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-90](#).

**Table 13-90** Setting the input and output parameters of the operator

Input Type	Export Type
Hive input	Table output

**Figure 13-82** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

**Table 13-91** Parameter description

Parameter	Description	Example Value
Schema name	Specifies the database schema name.	dbo
Table name	Specifies the name of a database table that is used to save the final data of the transmission. <b>NOTE</b> Table names can be defined using macros. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	test


Parameter	Description	Example Value
Temporary table	<p>Specifies the name of a temporary database table that is used to save temporary data during the transmission. The fields in the table must be the same as those in the database specified by <b>Table name</b>.</p> <p><b>NOTE</b> A temporary table is used to prevent dirty data from being generated in the destination table when data is exported to the database. Data is migrated from the temporary table to the destination table only after all data is successfully written to the temporary table. Using temporary tables increases the job execution time.</p>	tmp_test

**Step 7** Click **Save and run** to save and run the job.

### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

**Figure 13-83** Viewing a job



----End

## 13.5.10 Typical Scenario: Exporting Data from Spark to a Relational Database

### Scenario

This section describes how to use Loader to export data from Spark to a relational database.

### Prerequisites

- You have obtained the service username and password for creating a Loader job.
- You have had the permission to access the Spark tables that are used during job execution.

- You have obtained the username and password of the relational database.
- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.
- Before the operation, perform the following steps:
  - a. Obtain the JAR package of the relational database driver and save it to the following directory on the active and standby Loader nodes: **`${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/webapps/loader/WEB-INF/ext-lib`**.
  - b. Run the following command on the active and standby nodes as user root to modify the permission:

```
cd ${BIGDATA_HOME}/FusionInsight_Porter_8.1.2.2/install/  
FusionInsight-Sqoop-1.99.3/FusionInsight-Sqoop-1.99.3/server/  
webapps/loader/WEB-INF/ext-lib  
chown omm:wheel JAR package name  
chmod 600 JAR package name
```
  - c. Log in to FusionInsight Manager. Choose **Cluster** > *Name of the desired cluster* > **Service** > **Loader** > **More** > **Restart**. Enter the password of the administrator to restart the Loader service.


## Procedure

### Setting Basic Job Information

#### Step 1 Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-84 Loader web UI



#### Step 2 Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-85 Basic Information**

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **generic-jdbc-connector** or dedicated database connector (oracle-connector, oracle-partition-connector or mysql-fastpath-connector), set connection parameters, and click **Test** to verify whether the connection is available. When "**Test Success**" is displayed, click **OK**.

**NOTE**

- For connection to relational databases, general database connectors (generic-jdbc-connector) or dedicated database connectors (oracle-connector, oracle-partition-connector, and mysql-fastpath-connector) are available. However, compared with general database connectors, dedicated database connectors perform better in data import and export because they are optimized for specific database types.
- When **mysql-fastpath-connector** is used, the **mysqldump** and **mysqlimport** commands of MySQL must be available on NodeManagers, and the MySQL client version to which the two commands belong must be compatible with the MySQL server version. If the two commands are unavailable or the versions are incompatible, see <http://dev.mysql.com/doc/refman/5.7/en/linux-installation-rpm.html>. Install the MySQL client applications and tools.

**Table 13-92 generic-jdbc-connector connection parameters**

Parameter	Description	Example Value
Name	Specifies the name of a relational database connection.	dbName
JDBC Driver Class	Specifies the name of a Java database connectivity (JDBC) driver class.	oracle.jdbc.driver.OracleDriver

Parameter	Description	Example Value
JDBC Connection String	Specifies the JDBC connection string.	jdbc:oracle:thin:@//10.16.0.1:1521/oradb
Username	Specifies the username for connecting to the database.	omm
Password	Specifies the password for connecting to the database.	xxxx
JDBC Connection Properties	JDBC connection attribute. Click <b>Add</b> to manually add the attribute. <ul style="list-style-type: none"> <li>Name: connection attribute name</li> <li>Value: connection attribute value</li> </ul>	<ul style="list-style-type: none"> <li>Name: socketTimeout</li> <li>Value: 20</li> </ul>

### Setting Data Source Information

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **SPARK**.

**Table 13-93** Data source parameters

Parameter	Description	Example Value
Spark instance	Specifies the Spark service instance that Loader selects from all available Spark service instances in the cluster. If the selected Spark service instance is not added to the cluster, the Spark job cannot be run properly.	spark
Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000.	20


### Setting Data Transformation

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-94](#).

**Table 13-94** Setting the input and output parameters of the operator

Input Type	Export Type
Spark Input	Table output

**Figure 13-86** Operator operation procedure



**Setting Data Storage Information and Executing the Job**

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

**Table 13-95** Parameter description

Parameter	Description	Example Value
Schema name	Specifies the database schema name.	dbo
Table name	Specifies the name of a database table that is used to save the final data of the transmission. <b>NOTE</b> Table names can be defined using macros. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	test


Parameter	Description	Example Value
Temporary table	<p>Specifies the name of a temporary database table that is used to save temporary data during the transmission. The fields in the table must be the same as those in the database specified by <b>Table name</b>.</p> <p><b>NOTE</b> A temporary table is used to prevent dirty data from being generated in the destination table when data is exported to the database. Data is migrated from the temporary table to the destination table only after all data is successfully written to the temporary table. Using temporary tables increases the job execution time.</p>	tmp_test

**Step 7** Click **Save and run** to save and run the job.

#### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

**Figure 13-87** Viewing a job



----End

## 13.5.11 Typical Scenario: Importing Data from HBase to HDFS/OBS

### Scenario

This section describes how to use Loader to export data from HBase to HDFS/OBS.

### Prerequisites

- You have obtained the service user name and password for creating a Loader job.
- You have had the permission to access the HDFS/OBS directories and data involved in job execution.
- You have had the permission to access the HBase tables or phoenix tables that are used during job execution.

- No disk space alarm is reported, and the available disk space is sufficient for importing and exporting data.
- If a configured task requires the Yarn queue function, the user must be authorized with related Yarn queue permission.
- The user who configures a task must obtain execution permission on the task and obtain usage permission on the related connection of the task.


## Procedure

### Setting Basic Job Information

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-88** Loader web UI



**Step 2** Click **New Job** to go to the **Basic Information** page and set basic job information.

**Figure 13-89** Basic Information

1. Set **Name** to the name of the job.
2. Set **Type** to **Export**.
3. Set **Group** to the group to which the job belongs. No group is created by default. You need to click **Add** to create a group and click **OK** to save the created group.
4. Set **Queue** to the Yarn queue that executes the job. The default value is **root.default**.
5. Set **Priority** to the priority of the Yarn queue that executes the job. The default value is **NORMAL**. The options are **VERY\_LOW**, **LOW**, **NORMAL**, **HIGH**, and **VERY\_HIGH**.

**Step 3** In the **Connection** area, click **Add** to create a connection, set **Connector** to **hdfs-connector**, set connection parameters, and click **Test** to verify whether the connection is available. When "Test Success" is displayed, click **OK**.

**Setting Data Source Information**

**Step 4** Click **Next**. On the displayed **From** page, set **Source type** to **HBASE**.

**Table 13-96** Parameter description

Parameter	Description	Example
HBase instance	Specifies the HBase service instance that Loader selects from all available HBase service instances in the cluster. If the selected HBase service instance is not added to the cluster, the HBase job cannot be run properly.	HBase
Quantity	Specifies the number of maps that are started at the same time in a MapReduce job of a data configuration operation. The value must be less than or equal to 3000.	20


**Setting Data Transformation**

**Step 5** Click **Next**. On the displayed **Transform** page, set the transformation operations in the data transformation process. For details about how to select operators and set parameters, see [Operator Help](#) and [Table 13-97](#).

**Table 13-97** Setting the input and output parameters of the operator

Input Type	Export Type
HBase input	File output

**Figure 13-90** Operator operation procedure



### Setting Data Storage Information and Executing the Job

**Step 6** Click **Next**. On the displayed **To** page, set the data storage mode.

**Table 13-98** Parameter description


Parameter	Description	Example
Output path	Specifies the output directory or file name of the export file in the HDFS/OBS. <b>NOTE</b> You can use macros to define path parameters. For details, see <a href="#">Using Macro Definitions in Configuration Items</a> .	/user/test
File Format	Specifies the file export type. <ul style="list-style-type: none"> <li>• <b>TEXT_FILE</b>: imports a text file and stores it as a text file.</li> <li>• <b>SEQUENCE_FILE</b>: imports a text file and stores it as a <b>sequence file</b>.</li> <li>• <b>BINARY_FILE</b>: imports files of any format by using binary streams.</li> </ul>	TEXT_FILE
Compression codec	Specifies the compression format of files exported to HDFS/OBS. Select a format from the drop-down list. If you select <b>NONE</b> or do not set this parameter, data is not compressed.	NONE

**Step 7** Click **Save and run** to save and run the job.

#### Checking the Job Execution Result

**Step 8** Go to the **Loader WebUI**. When **Status** is **Succeeded**, the job is complete.

**Figure 13-91** Viewing a job



----End

## 13.6 Job Management

## 13.6.1 Migrating Loader Jobs in Batches

### Scenario

Loader allows jobs to be migrated in batches from a group (source group) to another group (target group).

### Prerequisites


- The source group and target group exist.
- The current user has the **Group Edit** permission for the source group and target group.
- The current user has the **Jobs Edit** permission for the source group or the **Edit** permission for the jobs to be migrated.

### Procedure

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-92** Loader web UI



**Step 2** Click **Change Group**. The Job Migration page is displayed.

**Step 3** In **Source group**, select the group to which the jobs to be migrated belong; in **target group**, select the group to which the jobs are to be migrated.

**Step 4** Set **Select Change Type** to a migration type.

- **All**: migrates all the jobs in the source group to the target group.
- **Specify Job**: migrates the specified jobs in the source group to the target group. Select **Specify Job**. In the job list, select the jobs to be migrated.

**Step 5** Click **OK** to start job migration. In the displayed dialog box, if the progress bar is 100%, the job migration is complete.

----End

## 13.6.2 Deleting Loader Jobs in Batches

### Scenario

Loader allows existing jobs to be deleted in batches.

### Prerequisites


The current user has the **Edit** permission for the jobs to be deleted or the **Jobs Edit** permission for the group to which the jobs belong.

### Procedure

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-93 Loader web UI



**Step 2** Click **Batch Delete**. The Batch Delete page is displayed.

**Step 3** Set **Batch Delete** to a job deletion type.

- **ALL**: deletes all jobs.
- **Specify Job**: deletes specified jobs. Select **Specify Job**. In the job list, select the jobs to be deleted.

**Step 4** Click **OK** to start the job deletion. In the displayed dialog box, if the progress bar is 100%, the job deletion is complete.

----End

## 13.6.3 Importing Loader Jobs in Batches

### Scenario

Loader allows all jobs of a configuration file to be imported in batches.

## Prerequisites

The current user has the **Jobs Edit** permission of the group to which the jobs to be imported belong.

### NOTE


If the group to which the jobs to be imported belong does not exist, the group is automatically created first. The current user is the creator of the group and has the **Jobs Edit** permission of the group.

## Procedure

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-94** Loader web UI



**Step 2** Click **Import**. The Export Job page is displayed.

**Step 3** On the **Import** page, specify the path of the configuration file whose jobs are to be imported.

**Step 4** Click **Upload** to start the job import. In the displayed dialog box, if the progress bar is 100%, the job import is complete.

----End

## 13.6.4 Exporting Loader Jobs in Batches

### Scenario

Loader allows existing jobs to be exported in batches.

### Prerequisites


The current user has the **Edit** permission for the jobs to be exported or the **Jobs Edit** permission of the group to which the jobs belong.

## Procedure

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-95** Loader web UI



**Step 2** Click **Export**. The job export page is displayed.

**Step 3** Set **Batch Delete** to a job export type.

- **ALL**: exports all jobs.
- **Specify Job**: exports specified jobs. Select **Specify Job**. In the job list, select the jobs to be exported.
- **Specify Group**: exports all the jobs in a specified group. Select **Specify Group**. In the group list, select the group whose jobs are to be exported.

**Export Password**: exports the connector password. If this parameter is selected, the password is exported as an encrypted string.

**Step 4** Click **OK** to start the job export. In the displayed dialog box, if the progress bar is 100%, the job import is complete.

----End

## 13.6.5 Viewing Historical Job Information

### Scenario

Query the execution status and execution duration of a Loader job during routine maintenance. You can perform the following operations on the job:

- **Dirty Data**: Query data that fails to be processed or data that is filtered out during job execution, and check which source data does not meet transformation or cleaning rules.
- **Logs**: Query log information about job execution in MapReduce.

### Prerequisites


You have obtained the username and password for logging in to the Loader WebUI.

## Procedure

### Step 1 Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-96 Loader web UI



### Step 2 Query historical records of a Loader job.

1. Locate the row that contains the job to be viewed.
2. As shown in the following figure, click **History** to view the job execution history.

Figure 13-97 Viewing historical records



Table 13-99 Parameters

Name	Description
Rows/Files Read	Indicates the number of rows (files) read from the input source.
Rows/Files Written	Number of rows (files) written to the output source.
Rows/Files Overridden	<ul style="list-style-type: none"> <li>– Indicates the number of bad rows (files) recorded during transformation. The input format is incorrect, so transformation cannot be performed.</li> <li>– Number of rows that are skipped after filtering conditions are configured during conversion.</li> </ul>

----End

## 13.7 Operator Help

### 13.7.1 Overview

#### Conversion Process

Loader reads data at the source end, uses an input operator to convert data into fields by certain rules, use a conversion operator to clean or convert the fields, and finally use an output operator to process the fields and export the output result to the target end.

- A job for performing data conversion can have only one input operator and one output operator.
- Data that does not meet conversion rules will become dirty data and be skipped.

#### NOTE

- For the data import from a relational database to HDFS/OBS, data conversion does not need to be configured and the data is separated using commas (,) and saved to HDFS/OBS.
- For the data import from HDFS/OBS to a relational database, data conversion does not need to be configured and the data is separated using commas (,) and saved to the relational database.

#### Operator Description

Loader operators have three types:

- **Input Operators**  
First step of data conversion. This type of operator converts data into fields. Only one input operator can be used in each conversion. The input operator is mandatory in HBase or Hive data import and export.
- **Conversion Operators**  
Intermediate conversion step of data conversion. This type of operator is optional. The conversion operators can be used together in any combination. Conversion operators can process only fields. Therefore, an input operator must be used first to convert data into fields.
- **Output Operators**  
Last step of data conversion. Only one output operator can be used in each conversion for exporting processed fields. The output operator is mandatory in HBase or Hive data import and export.

**Table 13-100** List of operator types

Node Type	Description
Input:	<ul style="list-style-type: none"><li>• CSV file input: Each line in the file is converted into multiple input fields based on the specified delimiter.</li><li>• Fixed-width file input: Each line of the file is converted into multiple input fields based on the characters or bytes with configurable length.</li><li>• Table input: converts specified columns in a relational database table into input fields of the same quantity.</li><li>• HBase input: converts specified columns in an HBase table into input fields of the same quantity.</li><li>• HTML input: converts elements in an HTML file into input fields.</li><li>• Hive input: converts specified columns in a Hive table into input fields of the same quantity.</li></ul>

Node Type	Description
Convert	<ul style="list-style-type: none"> <li>● Long integer to time conversion: Implements the conversion between long integer values and date types.</li> <li>● Null value conversion: Replaces a null value with a specified value.</li> <li>● Constant field adding: Generates a constant field.</li> <li>● Random value conversion: generates a random number field.</li> <li>● Concatenation and conversion: concatenates existing fields to generate new fields.</li> <li>● Delimiter conversion: separates existing fields with specified separators to generate new fields.</li> <li>● Modulo conversion: performs modulo operation on an existing field to generate a new field.</li> <li>● Character string cutting: cuts existing string fields by the specified start position and end position to generate new fields.</li> <li>● EL operation conversion: specifies a calculator to calculate field values. Currently, the following operators are supported: md5sum, sha1sum, sha256sum, and sha512sum.</li> <li>● Character string case conversion: converts the upper and lower cases of existing fields to generate new fields.</li> <li>● Character string reverse conversion: reverses existing character string fields to generate new fields.</li> <li>● Character string space clearing and conversion: clears the spaces on the left and right of the existing character string fields to generate new fields.</li> <li>● Row filtering conversion: filters rows that contain triggering conditions by configuring logic conditions.</li> <li>● Domain update: updates fields values when certain conditions are met.</li> </ul>
Output:	<ul style="list-style-type: none"> <li>● Hive Output: exports existing fields to a Hive table.</li> <li>● Table output: exports existing fields to a relational database table.</li> <li>● File output: uses delimiters to concatenate existing fields and exports new fields to a file.</li> <li>● HBase Output: exports existing fields to an HBase table.</li> </ul>

## Field Description

Fields in the job configuration are data items defined by Loader based on service requirements to match user data. Fields have specific types and the fields types must be consistent with the actual user data types.

## 13.7.2 Input Operators

### 13.7.2.1 CSV File Input

#### Overview

The **CSV File Input** operator imports all files that can be opened by using a text editor.

#### Input and Output

- Input: test files
- Output: fields

#### Parameter Description

**Table 13-101** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Delimiter	Delimiter in a CSV file for separating data lines.	string	Yes	,
Line Delimiter	Line delimiter, which can be any string specified by users based on the actual situation. The OS line delimiter is used by default.	string	No	\n
Filename as field	User-defined field whose value is the name of the file that stores the current data.	string	No	None
Absolute path	Indicates whether the file name used as the value of <b>Filename as field</b> contains an absolute path. Selecting the option button indicates that the file name contains an absolute path; deselecting the option button indicates that the file name does not contain a path.	boolean	No	Deselect

Parameter	Description	Type	Mandator y	Default Value
Validate input field	Checks whether the input field matches the value type. If the value is <b>NO</b> , no check is performed. If the value is <b>YES</b> , whether the input field matches the value type is checked. If the input fields do not match the value type, the line is skipped.	enum	Yes	YES
Input fields	Information about input fields: <ul style="list-style-type: none"> <li>• <b>position</b>: Position of the field after data lines in the source file are separated by delimiters. The position sequence starts from 1.</li> <li>• <b>field name</b>: Field name.</li> <li>• <b>type</b>: Field type.</li> <li>• <b>date format</b>: If the field type is <b>DATE</b>, <b>TIME</b>, or <b>TIMESTAMP</b>, you must specify a time format. If the field type is set to other values, the time format is invalid. An example time format is <b>yyyyMMdd HH:mm:ss</b>.</li> <li>• <b>length</b>: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	Yes	None

### Data Processing Rule

- Each data line is separated into multiple fields by using delimiters and the fields are used by the subsequent conversion operator.
- If the field value does not match the actual type, the data in the line will become dirty data.

- If the number of input field columns is equal to the number of field columns actually included in the original data, the data in the line will become dirty data.

## Example

The following figure shows the source file.

```
2016,year
year,2016
```

Configure the **CSV File Input** operator, set **Delimiter** to a comma (,), and generate fields A and B.

Delimiter: ,

Line Delimiter:

Filename as field:

Absolute path:

Validate input field: YES

Input fields

Import Export

Table Edit Text Area Edit

position	field name	type	date format	length	
1	A	VARCHAR			↑ ↓ ↺ ✕
2	B	VARCHAR			↑ ↓ ↺ ✕

Add

Fields A and B are generated, as shown in the following figure.

```
2016,year
year,2016
```

### 13.7.2.2 Fixed File Input

#### Overview

The **Fixed File Input** operator converts each line in a file into multiple fields by character or byte of a configurable length.

#### Input and Output

- Input: text file
- Output: fields

## Parameter Description

**Table 13-102** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Line Delimiter	Line delimiter, which can be any string specified by users based on the actual situation. The OS line delimiter is used by default.	string	No	\n
Fixed length unit	Length unit. The options are <b>char</b> and <b>byte</b> .	enum	Yes	char
Input fields	<p>Information about input fields:</p> <ul style="list-style-type: none"> <li>• <b>fixed length</b>: Field length. The ending of the first field is the starting of the second field, the ending of the second field is the starting of the third field, and so on.</li> <li>• <b>field name</b>: Names of input fields.</li> <li>• <b>type</b>: Field type.</li> <li>• <b>date format</b>: If the field type is <b>DATE</b>, <b>TIME</b>, or <b>TIMESTAMP</b>, you must specify a time format. If the field type is set to other values, the time format is invalid. An example time format is <b>yyyyMMdd HH:mm:ss</b>.</li> <li>• <b>length</b>: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	Yes	None

## Data Processing Rule

- The source file is split based on the input field length to generate fields.
- If the field value does not match the actual type, the data in the line will become dirty data.
- If the field split length is greater than the length of the original field value, the data split fails and the line becomes dirty data.

## Example

The following figure shows the source file.

```
fusionInsightbigdataprodu
```

Configure the **Fixed File Input** operator to generate fields A, B, and C.

fixed length	filed name	type	date format	length
13	A	VARCHAR		
7	B	VARCHAR		
7	C	VARCHAR		

The three fields are generated, as shown in the following figure.

```
fusionInsight,bigdata,product
```

### 13.7.2.3 Table Input

#### Overview

**Table Input** operator converts specified columns in a relational database table into input fields of the same quantity.

#### Input and Output

- Input: table columns
- Output: fields

## Parameter Description

**Table 13-103** Operator parameters description

Parameter	Description	Type	Mandatory	Default Value
Input fields	Information about relational database input fields: <ul style="list-style-type: none"> <li>• <b>position</b>: position of input fields</li> <li>• <b>field name</b>: input field name</li> <li>• <b>type</b>: field type</li> <li>• <b>length</b>: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	Yes	None

## Data Processing Rule

- Fields are generated in a specified order. Table columns to be converted are specified by **From** in step 2 of job configuration. If **Table column names** is set, the value is the table columns to be converted; if **Table column names** is not set, the table columns to be converted are all table columns in the table by default or the columns specified by the query conditions set by **Table SQL statement**.
- The number of input fields cannot be greater than number of specified columns; otherwise, all data becomes dirty data.
- If the field value does not match the actual type, the data in the line will become dirty data.

## Example

Use SQL Server 2014 as an example. Run the following command to create a **test** table:

```
create table test (id int, name text, value text);
```

Insert three data lines to the test table:

```
insert into test values (1,'zhangshan','zhang');
```

```
insert into test values (2,'lisi','li');
```

**insert into test values (3,'wangwu','wang');**

Query the table:


	id	name	value
1	1	zhangshan	zhang
2	2	lisi	li
3	3	wangwu	wang

Configure the **Table Input** operator to generate the following fields:

After the data connector is set, click **Automatic Identification**. The system will automatically read fields in the database and select required fields for adding. You only need to optimize or modify the fields manually based on service scenarios.

 **NOTE**

Performing this operation will overwrite existing data in the table.



position	field name	type	length
1	A	VARCHAR	
2	B	VARCHAR	
3	C	VARCHAR	

Configure the output operator to output data to HDFS/OBS. The result is as follows:

```
1,zhangshan,zhang  
2,lisi,li  
3,wangwu,wang
```

### 13.7.2.4 HBase Input

#### Overview

The **HBase Input** operator converts specified columns in an HBase table into input fields of the same quantity.

#### Input and Output

- Input: HBase table columns
- Output: fields

## Parameter Description

**Table 13-104** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Hbase Table Type	HBase table type. The options include <b>normal</b> (common HBase table) and <b>phoenix</b> .	enum	Yes	normal
HBase table name	HBase table name. Only one HBase table is supported.	string	Yes	None
HBase input fields	<p>HBase input information:</p> <ul style="list-style-type: none"> <li>• <b>family name</b>: HBase column family name.</li> <li>• <b>column name</b>: HBase column name.</li> <li>• <b>field name</b>: Names of input fields.</li> <li>• <b>type</b>: Field type.</li> <li>• <b>length</b>: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> <li>• <b>is rowkey</b>: Indicates whether a column is a primary key column. A common HBase table can have only one primary key, while a phoenix table can have multiple primary keys. If multiple primary keys are configured, they are combined according to the configuration sequence. At least one primary key column must be configured.</li> </ul>	map	Yes	None

## Data Processing Rule

- If the HBase table name does not exist, the job fails to be submitted.
- If the configured column names are inconsistent with the HBase table column names, the data cannot be read and the number of imported data records is 0.
- If the number of input field columns is greater than the number of field columns actually included in the original data, all data becomes dirty data.
- If the field value does not match the actual type, the data in the line will become dirty data.

## Example

Use the data export from HBase to sqlserver2014 as an example.

In sqlserver2014, run the following statement to create an empty data test\_1 for storing HBase data:


```
create table test_1 (id int, name text, value text);
```

Configure the **HBase Input** operator to generate fields A, B, and C.

After the database connection is set up, click **autoRecognition**. The system will automatically read fields in the database and select required fields for adding. You only need to optimize or modify the fields manually based on service scenarios.

### NOTE

Performing this operation will overwrite existing data in the table.



family name	column name	field name	type	length	is rowkey
fl	A	A	VARCHAR		<input type="checkbox"/>
fl	B	B	VARCHAR		<input type="checkbox"/>
fl	C	C	VARCHAR		<input type="checkbox"/>

Use the **Table Out** operator to export A, B, and C to the test\_1 table.

```
select * from test_1;
```

	id	name	value
1	1	zhangshan	zhang
2	2	lisi	li
3	3	wangwu	wang

### 13.7.2.5 HTML Input

#### Overview

**HTML Input** operator imports a regular HTML file and converts elements in the HTML file into input fields.

#### Input and Output

Input: HTML file

Output: multiple fields

#### Parameter Description

**Table 13-105** Operator parameters description

Parameter	Description	Type	Mandatory	Default Value
parent tag	Upper-layer HTML tag of all fields for limiting the search scope.	string	Yes	None
Filename as field	User-defined field whose value is the name of the file that stores the current data.	string	No	None
Absolute file name	Whether the file name used as the value of <b>Filename as field</b> contains an absolute path. Selecting the option button indicates that the file name contains an absolute path; deselecting the option button indicates that the file name does not contain a path.	boolean	No	No
Validate input field	Whether to check the type matching between the input field and the value. If the value is <b>NO</b> , the field is not checked. If the value is <b>YES</b> , the field will be checked. If the input field does not match the value type, the line is skipped.	enum	Yes	YES

Parameter	Description	Type	Mandatory	Default Value
Input fields	<p>Information about input fields:</p> <ul style="list-style-type: none"> <li>• <b>position</b>: Position of the field. The position sequence starts from 1.</li> <li>• <b>field name</b>: field name</li> <li>• <b>field tag</b>: field tag</li> <li>• <b>keyword</b>: A keyword can be configured to match the content of the tag. Wildcards are supported. For example, if the tag content is <b>name</b>, you can configure the keyword <b>*name*</b>.</li> <li>• <b>type</b>: field type</li> <li>• <b>date format</b>: If the field type is <b>DATE</b>, <b>TIME</b>, or <b>TIMESTAMP</b>, you need to specify the time format. If the field type is neither of them, the time format is invalid. The example time format is <b>yyyyMMdd HH:mm:ss</b>.</li> <li>• <b>length</b>: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	Yes	None

## Data Processing Rule

- **parent tag** is configured first to limit the search scope. The value of **parent tag** must exist; otherwise, the obtained content is empty.
- **Input fields** are configured so that the sub-tags can be used to precisely locate the tags of fields. If the tags are the same, keywords will be used for precise matching.
- The keyword is used to match the content of the field. The configuration method is similar to that of the **File filter** field in the **From** settings. The wildcard (\*) is supported. The following three tags are provided to assist in locating the field:
  - a. **#PART**: indicates the values matched by wildcard \*. If there are multiple \*, you can specify an order from left to right and obtain content that matches the sequence number \*. For example, **#PART1** indicates to

- obtain the value that matches the first \* and **#PART8** indicates to obtain the value that matches the eighth \*).
- b. **#NEXT**: indicates that you can obtain the value next to the value that matches the tag.
- c. **#ALL**: indicates that you can obtain all the values that match the tag.
- If the tag is configured incorrectly, the obtained value is empty, but no error is reported.

## Example

The following figure shows the source file.

```
<html>
<body>
<table>
<tr>
<td>name:zhangshan</td>
<td>department:FusionInght</td>
<td>age:25</td>
</tr>
</table>
</body>
</html>
```

Configure the **HTML Input** operator to generate fields A, B, and C.

position	field name	field tag	keyword	type	date format	length
1	A	td	name:*PART1	VARCHAR		
2	B	td	department:*PAR	VARCHAR		
3	C	td	age:*PART1	VARCHAR		

Three fields are generated, as shown in the following figure.

```
zhangshan,FusionInght,25
```

### 13.7.2.6 Hive input

#### Overview

The **Hive Input** operator converts specified columns in an HBase table into input fields of the same quantity.

#### Input and Output

- Input: Hive table columns
- Output: fields

#### Parameters

**Table 13-106** Operator parameters description

Parameter	Description	No de Type	Man dator y	Defa ult Valu e
Hive database	Name of a Hive database	Stri ng	No	defau lt
Hive table name	Name of the Hive table configured Only one Hive table is supported.	Stri ng	Yes	None .
Partition filter	Configures the partition filter can export data of specific partitions. The parameter is null by default and data of the whole table can be exported.  For example, to export data of a table whose partition field's locale value is <b>CN</b> or <b>US</b> , the input is as follows: <b>locale = "CN" or locale = "US"</b>	Stri ng	No	-
Hive input field	Configures the input information of Hive <ul style="list-style-type: none"> <li>• column name: Hive column name.</li> <li>• field name: Input field name.</li> <li>• type: Field type.</li> <li>• length: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	ma p	Yes	-

## Data Processing Rule

- If the Hive table name does not exist, the job fails to be submitted.
- If the configured column names are inconsistent with the Hive table column names, the data cannot be read and the number of imported data records is 0.
- If the field value does not match the actual type, the data in the line will become dirty data.

## Example

Use the data export from Hive to SQL Server 2014 as an example.

In SQL Server 2014, run the following statement to create an empty table **test\_1** for storing Hive data. Run the following statement:


```
create table test_1 (id int, name text, value text);
```

Configure the **Hive Input** operator to generate fields A, B, and C.

After the data connector is set, click **Automatic Identification**. The system will automatically read fields in the database and select required fields for adding. You only need to optimize or modify the fields manually based on service scenarios.

### NOTE

Performing this operation will overwrite existing data in the table.



column name	field name	type	length	
A	A	VARCHAR		↑ ↓ ↕ ✕
B	B	VARCHAR		↑ ↓ ↕ ✕
C	C	VARCHAR		↑ ↓ ↕ ✕

Use the **Table Out** operator to export A, B, and C to the **test\_1** table.

```
select * from test_1;
```

	id	name	value
1	1	zhangshan	zhang
2	2	lisi	li
3	3	wangwu	wang

### 13.7.2.7 Spark Input

#### Overview

The **Spark Input** operator converts specified columns in an SparkSQL table into input fields of the same quantity.

#### Input and Output

- Input: SparkSQL table column
- Output: fields

#### Parameters

**Table 13-107** Operator parameters description

Parameter	Description	Type	Mandatory	Default Value
Spark database	Name of a Spark SQL database	String	No	default
Spark table name	Configures the SparkSQL table name. Only one SparkSQL table is supported.	String	Yes	None
Partition filter	Configures the partition filter can export data of specific partitions. The parameter is null by default and data of the whole table can be exported.  For example, to export data of a table whose partition field's locale value is <b>CN</b> or <b>US</b> , the input is as follows: <b>locale = "CN" or locale = "US"</b>	String	No	-

Parameter	Description	Type	Mandatory	Default Value
Input fields of Spark	<p>Configures the input information of SparkSQL</p> <ul style="list-style-type: none"> <li>• column name: SparkSQL column name.</li> <li>• field name: Input field name.</li> <li>• type: Field type.</li> <li>• length: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	Yes	-

## Data Processing Rule

- If the SparkSQL table name does not exist, the job fails to be submitted.
- If the configured column names are inconsistent with the SparkSQL table column names, the data cannot be read and the number of imported data records is 0.
- If the field value does not match the actual type, the data in the line will become dirty data.

## Example

Use the data export from Spark to SQL Server 2014 as an example.

In SQL Server 2014, run the following statement to create an empty table **test\_1** for storing SparkSQL data. Run the following statement:

```
create table test_1 (id int, name text, value text);
```

Configure the **Spark Input** operator to generate fields A, B, and C.

After the data connector is set, click **Automatic Identification**. The system will automatically read fields in the database and select required fields for adding. You only need to optimize or modify the fields manually based on service scenarios.

### NOTE

Performing this operation will overwrite existing data in the table.

Hive database name

Hive table name

Hive partition filter

Hive input fields

column name	field name	type	length	
<input type="text" value="A"/>	<input type="text" value="A"/>	VARCHAR ▾	<input type="text"/>	↑ ↓ ↕ ✕
<input type="text" value="B"/>	<input type="text" value="B"/>	VARCHAR ▾	<input type="text"/>	↑ ↓ ↕ ✕
<input type="text" value="C"/>	<input type="text" value="C"/>	VARCHAR ▾	<input type="text"/>	↑ ↓ ↕ ✕

Use the **Table Out** operator to export A, B, and C to the **test\_1** table.

```
select * from test_1;
```

	id	name	value
1	1	zhangshan	zhang
2	2	lisi	li
3	3	wangwu	wang

## 13.7.3 Conversion Operators

### 13.7.3.1 Long Date Conversion

#### Overview

The **Long Date Conversion** operator performs long integer and date conversion.

#### Input and Output

- Input: fields to be converted
- Output: new fields

## Parameter Description

**Table 13-108** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
convert type	Types of long integer and date conversion: <ul style="list-style-type: none"> <li>• <b>long to date</b>: converts long integers to date.</li> <li>• <b>long to time</b>: converts long integers to time.</li> <li>• <b>long to timestamp</b>: converts long integers to timestamp.</li> <li>• <b>date to long</b>: converts date to long integers.</li> <li>• <b>time to long</b>: converts time to long integers.</li> <li>• <b>timestamp to long</b>: converts timestamp to long integers.</li> </ul>	enum	Yes	long to date
input field name	Name of input fields to be converted. Set this parameter to the names of fields generated in the previous conversion step.	string	Yes	None
output field name	Names of output fields.	string	Yes	None
field unit	Unit of a long integer field. According to <b>convert type</b> , the value is an input field or generated field. The options are <b>second</b> and <b>millisecond</b> .	enum	Yes	second
output field type	Output field type. The options are <b>BIGINT</b> , <b>DATE</b> , <b>TIME</b> , and <b>TIMESTAMP</b> .	enum	Yes	BIGINT
date format	Time field format, for example, <b>yyyyMMdd HH:mm:ss</b> .	string	No	None

### Data Processing Rule

- If the original data includes null values, no conversion is performed.
- If the number of input field columns is greater than the number of field columns actually included in the original data, all data becomes dirty data.
- If a type conversion error occurs, the current data is saved as dirty data.

### Example

Use the **CSV File Input** operator to generate fields A and B.

The following figure shows the source file.

```
1453431755874,2016-01-22 10:40:00
```

Configure the **Long Date Conversion** operator to generate four new fields C, D, E, and F. Their types are DATE, TIME, TIMESTAMP, and BIGINT, respectively.

The following figure shows the output of the conversion.

```
1453431755874,2016-01-22,2016-01-22,11:02:35,20160122 11:02:35,1453430400000
```

### 13.7.3.2 Null Value Conversion

#### Overview

The **null value conversion** operator replaces null values with specified values.

#### Input and Output

- Input: fields with null values
- Output: original fields with new values

#### Parameter Description

**Table 13-109** Operator parameters description

Parameter	Description	Node Type	Man datory	Defa ult Value
Input field name	Names of fields that may have null values. Set this parameter to the names of existing fields.	string	Yes	None
Replace by this value	Specified values for replacing null values.	string	Yes	None

## Data Processing Rule

When field values are empty, specified values are added.

### Example

Use the **CSV File Input** operator to generate two fields A and B.

The following figure shows the source file.

```
,value1  
key2,value2  
key3,
```

Configure the **null value conversion** operator, as shown in the following figure.

The screenshot shows the configuration interface for the null value conversion operator. At the top, there are 'Import' and 'Export' buttons. Below them are two tabs: 'Table Edit' (which is selected) and 'Text Area Edit'. The main area contains a table with two columns: 'input field name' and 'Replace by this value'. Under 'input field name', there are two input fields containing 'A' and 'B'. Under 'Replace by this value', there are two input fields containing 'newKey' and 'newValue'. At the bottom left, there is an 'Add' button.

After replacement, the values of fields A and B are as follows:

```
newKey,value1  
key2,value2  
key3,newValue
```

### 13.7.3.3 Constant Field Addition

#### Overview

The **Add Constants** operator generates constant fields.

#### Input and Output

- Input: none
- Output: constant fields

## Parameter Description

**Table 13-110** Operator parameters description

Parameter	Description	Type	Mandatory	Default Value
Constant fields	<p>Information about constant fields:</p> <ul style="list-style-type: none"> <li>• <b>output field name:</b> Names of the configured fields.</li> <li>• <b>type:</b> field type</li> <li>• <b>date format:</b> If the field type is <b>DATE</b>, <b>TIME</b>, or <b>TIMESTAMP</b>, you need to specify the time format. If the field type is neither of them, the time format is invalid. The example time format is <b>yyyyMMdd HH:mm:ss</b>.</li> <li>• <b>length:</b> Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> <li>• <b>constant value:</b> Constant value of the correct type.</li> </ul>	map	Yes	None

## Data Processing Rule

This operator generates constant fields of the specified type.

## Example

Use the **CSV File Input** operator to generate two fields A and B.

The following figure shows the source file.

```
,value1
key2,value2
key3,
```

Configure the **Add Constants** operator to add fields C and D.

After adding the constants, fields A, B, C, and D are generated, as shown in the following figure.

```
,value1,constantsvalue1,2016
key2,value2,constantsvalue1,2016
key3,,constantsvalue1,2016
```

### 13.7.3.4 Random Value Conversion

#### Overview

**Generate Random** operator configures new values as random value fields.

#### Input and Output

- Input: none
- Output: random value fields

#### Parameter Description

Table 13-111 Operator parameters description

Parameter	Description	Type	Mandatory	Default Value
output field name	Names of generated random value fields.	string	Yes	None
length	Field length.	map	Yes	None
type	Field type. The options are <b>VARCHAR</b> , <b>INTEGER</b> , and <b>BIGINT</b> .	enum	Yes	VARCHAR

#### Data Processing Rule

The operator generates random value fields of specified type.

#### Example

Use the **CSV File Input** operator to generate two fields A and B.

The following figure shows the source file.

```
,value1  
key2,value2  
key3,
```

Configure the random value conversion operator to generate fields C, D, and E.

output field name	type
C	VARCHAR ▼
D	INTEGER ▼
E	BIGINT ▼

Five fields are generated.

```
,value1,2druceak69ril,769974975,8452014577467885098  
key2,value2,7oq2dku93q9cg,1631427868,867914116689501757  
key3,,2jg5e7b1m17kq,654806209,2477823020516316030
```

The random value fields generated each time are different.

### 13.7.3.5 Concat Fields

#### Overview

The **Concat Fields** operator concatenates existing fields by using delimiters to generate new fields.

#### Input and Output

- Input: fields to be concatenated
- Output: new fields

## Parameter Description

Table 13-112 Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Output field name	Name of a field generated after concatenation.	string	Yes	None
Delimiter	Concatenation character. The value can be blank.	string	No	Empty string
Fields to be merged	Names of fields to be concatenated. <b>field name</b> must be set to the names of fields generated in the previous conversion step. Multiple field names can be added.	map	Yes	None

## Data Processing Rule

- Use delimiters to concatenate the fields specified by **Fields to be merged** in order and assign the output to **Output field name**.
- If the value of a field is null, the value is changed to an empty string and then concatenated with other field values.

## Example

Use the **CSV File Input** operator to generate fields A, B, and C.

The following figure shows the source file.

```
happy,new,year  
welcome,to,2016
```

Configure the **Concat Fields** operator, set **Delimiter** to blank space, and generate field D.

After concatenation, fields A, B, C, and D are generated, as shown in the following figure.

```
happy,new,year,happy new year
welcome,to,2016,welcome to 2016
```

### 13.7.3.6 Extract Fields

#### Overview

The **Extract Fields** separates an existing field by using delimiters to generate new fields.

#### Input and Output

- Input: field to be separated
- Output: new fields

#### Parameter Description

**Table 13-113** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Input field name	Name of a field to be separated. Set this parameter to the name of a field generated in the previous conversion step.	string	Yes	None
Delimiter	Delimiter.	string	Yes	None

Parameter	Description	Type	Mandatory	Default Value
Fields extracted	Fields generated after field separation. Multiple fields can be generated after field separation. <ul style="list-style-type: none"> <li><b>position:</b> Position of fields generated after field separation.</li> <li><b>output field name:</b> Names of output fields.</li> </ul>	map	Yes	None

### Data Processing Rule

- The value of the input field is separated by specified delimiters and the segments are assigned to the new fields.
- If the number of field columns after separation is greater than the actual number allowed by the original data, the line will become dirty data.

### Example

Use the **CSV File Input** operator to generate field A.

The following figure shows the source file.

```
happy new year
welcome to 2016
```

Configure the **Extract Fields** operator, set **Delimiter** to blank space, and generate three fields B, C, and D.

Input field name:

Delimiter:

Fields extracted

position	output field name
<input type="text" value="1"/>	<input type="text" value="B"/>
<input type="text" value="2"/>	<input type="text" value="C"/>
<input type="text" value="3"/>	<input type="text" value="D"/>

After conversion, fields A, B, C, and D are generated, as shown in the following figure.

```
happy new year,happy,new,year
welcome to 2016,welcome,to,2016
```

### 13.7.3.7 Modulo Integer

#### Overview

The **Modulo Integer** operator performs modulo operations on integer fields to generate new fields.

#### Input and Output

- Input: integer fields
- Output: new fields

#### Parameter Description

**Table 13-114** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Modulo fields	Modulo operation information: <ul style="list-style-type: none"> <li>• <b>input field name:</b> Names of input fields. Set this parameter to the names of fields generated in the previous conversion step.</li> <li>• <b>output field name:</b> Names of output fields.</li> <li>• <b>modulus:</b> Values used for a modulo operation.</li> </ul>	map	Yes	None

#### Data Processing Rule

- The operator generates new fields and the values are those after the modulo operation.
- The field values must be integers; otherwise, the current line becomes dirty data.

#### Example

Use the **CSV File Input** operator to generate fields A and B.

The following figure shows the source file.

```
10,12  
2015,2016
```

Configure the **Modulo Integer** operator to generate two new fields C and D.

input field name	output field name	modulus
A	C	3
B	D	3

After the modulo operation, fields A, B, C, and D are generated, as shown in the following figure.

```
10,12,1,0  
2015,2016,2,0
```

### 13.7.3.8 String Cut

#### Overview

The **String Cut** operator cuts existing fields to generate new fields.

#### Input and Output

- Input: fields to be cut
- Output: new fields

## Parameter Description

**Table 13-115** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Fields to be cut	<p>Information about a cut field:</p> <ul style="list-style-type: none"> <li>• <b>input field name:</b> Names of input fields. Set this parameter to the names of fields generated in the previous conversion step.</li> <li>• <b>output field name:</b> Names of output fields.</li> <li>• <b>start position:</b> Cutting start position, starting from sequence 1.</li> <li>• <b>end position:</b> Cutting end position. If the length of the cut string cannot be determined, you can set this parameter to -1, indicating the end of a string to be cut.</li> <li>• <b>output field type:</b> Type of output fields.</li> <li>• <b>output field length:</b> Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>output field type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>output field type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	Yes	None

### Data Processing Rule

- **start position** and **end position** are used to cut the original fields and generate new fields.
- If **end position** is set to -1, the end of a string is to be cut. In other cases, the value of **end position** must be greater than the value of **start position**.
- If the value of **start position** or **end position** is greater than the length of the input field, the line will become dirty data.

### Example

Use the **CSV File Input** operator to generate fields A and B.

The following figure shows the source file.

```
abcd,product  
FusionInsight,Bigdata
```

After configuring the **String Cut** operator, fields C and D are generated.

input field name	output field name	start position	end position	output field type	output field length
A	C	1	3	VARCHAR	
B	D	1	4	VARCHAR	

After cutting, the following fields are generated.

```
abcd,product,abc,prod  
FusionInsight,Bigdata,Fus,Bigd
```

### 13.7.3.9 EL Operation

#### Overview

The **EL Operation** operator calculates field values and generates new fields. The algorithms that are currently supported include md5sum, sha1sum, sha256sum, and sha512sum.

#### Input and Output

- Input: fields to be converted
- Output: fields generated after the EL expression conversion

## Parameter Description

**Table 13-116** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Field generated by el operation	<p>EL expression configuration:</p> <ul style="list-style-type: none"> <li>• <b>name:</b> Name of the expression output result.</li> <li>• <b>el expression:</b> Expression. The format is <i>expression name(input field name,value indicating whether to use lower case letters to indicate the output result)</i>, for example, md5sum(fieldname,true). <ul style="list-style-type: none"> <li>- md5sum: generates md5 values.</li> <li>- sha1sum: generates sha1 values.</li> <li>- sha256sum: generates sha256 values.</li> <li>- sha512sum: generates sha512 values.</li> </ul> </li> <li>• <b>type:</b> Type of the expression output result. <b>VARCHAR</b> is recommended.</li> <li>• <b>date format:</b> Format of the expression output result.</li> <li>• <b>length:</b> Length of the expression output result.</li> </ul>	map	Yes	None

### Data Processing Rule

- The operator calculates fields values and generates new fields.
- The type of the new fields can only be VARCHAR.

### Example

Use the **CSV File Input** operator to generate fields A and B.

The following figure shows the source file.

```
2016,year
year,2016
```

Configure the **EL Operation** operator to generate fields C, D, E, and F.

name	el expression	type	date format	length
C	md5sum(A,false)	VARCHAR		
D	sha1sum(A,true)	VARCHAR		
E	sha256sum(B,false)	VARCHAR		
F	sha512sum(B,true)	VARCHAR		

Six fields are generated, as shown in the following figure.

```
2016,year,95192C98732387165BF8E396C0F2DAD2,ab39c54239118a4b086b878b7878100f769dd1
97,4CB4EA25583C25647247AE96FC90225D99AD7A6FABC3E2C2FD13C502E323CD9E,779edfe0463b2
596e7a83e4c59083e19242e8c51eace8e2ec57704643be5e15ba80f79af227cf3ea2e2362b4081377
96a1d82cb0535652b99844bb9a62019563
year,2016,84CDC76CABF41BD7C961F6AB12F117D8,4ff0b1538469338a0073e2cdaab6a517801b6a
b4,DA6E2F539726FABD1F8CD7C9469A22B36769137975B28ABC65FE2DC29E659B77,da0ae9104086a
1c58f89f82766ac55a02c8ab44277ce39f959ec0e73391bef651c6f9793657396ce47fbd846068465
ccbf3056764424bed9be7789bd1101ace7
```

### 13.7.3.10 String Operations

#### Overview

The **String Operations** operator converts the upper and lower cases of existing fields to generate new fields.

#### Input and Output

- Input: fields whose case is to be converted
- Output: new fields after conversion

## Parameter Description

**Table 13-117** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Fields to be processed	<p>Information about fields for string case conversion:</p> <ul style="list-style-type: none"> <li><b>input field name:</b> Names of input fields. Set this parameter to the names of fields generated in the previous conversion step.</li> <li><b>output field name:</b> Names of output fields.</li> <li><b>lower/upper:</b> Indicates whether data is to be converted into uppercase letters or lowercase letters.</li> </ul>	map	Yes	None

## Data Processing Rule

- Case conversion is performed for strings.
- If the input data is null, no case conversion is performed.

## Example

Use the **CSV File Input** operator to generate fields A and B.

The following figure shows the source file.

```
abcd,product
FusionInsight,Bigdata
```

After configuring the **String Operations** operator, fields C and D are generated.

input field name	output field name	lower/upper
A	C	Upper
B	D	Lower

After conversion, four fields are generated, as shown in the following figure.

```
abcd,product,ABCD,product
FusionInsight,Bigdata,FUSIONINSIGHT,bigdata
```

### 13.7.3.11 String Reverse

#### Overview

The **String Reverse** operator reverses existing fields to generate new fields.

#### Input and Output

- Input: fields to be reversed
- Output: new fields

#### Parameter Description

Table 13-118 Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Fields to be reversed	<p>Information about fields for string reversal conversion:</p> <ul style="list-style-type: none"> <li>• <b>input field name:</b> Names of input fields. Set this parameter to the names of fields generated in the previous conversion step.</li> <li>• <b>output field name:</b> Names of output fields.</li> <li>• <b>type:</b> Field type.</li> <li>• <b>out field length:</b> Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	Yes	None

#### Data Processing Rule

- Value reversal conversion is performed for fields.
- If the input data is null, no reversal conversion is performed.
- If the number of input field columns is greater than the number of field columns actually included in the original data, all data becomes dirty data.

## Example

Use the **CSV File Input** operator to generate fields A and B.

The following figure shows the source file.

```
abcd,product  
FusionInsight,Bigdata
```

Configure the **String Reverse** operator to generate two new fields C and D.

input field name	output field name	type	output field length
A	C	VARCHAR	
B	D	VARCHAR	

After conversion, four fields are generated, as shown in the following figure.

```
abcd,product,dcba,tcudorp  
FusionInsight,Bigdata,thgisnInoisuF,atadgiB
```

### 13.7.3.12 String Trim

#### Overview

The **String Trim** operator clears spaces contained in existing fields to generate new fields.

#### Input and Output

- Input: fields whose spaces are to be cleared
- Output: new fields

## Parameter Description

**Table 13-119** Operator parameter description

Parameter	Description	Type	Mandatory	Default Value
Fields to be trimmed	<p>Information about fields for clearing spaces contained in strings:</p> <ul style="list-style-type: none"> <li>• <b>input field name:</b> Names of input fields. Set this parameter to the names of fields generated in the previous conversion step.</li> <li>• <b>output field name:</b> Names of output fields.</li> <li>• <b>trim type:</b> Space clearing mode (clearing starting spaces, ending spaces, or starting and ending spaces).</li> </ul>	map	Yes	None

## Data Processing Rule

- Clearing spaces at both ends of a value supports clearing spaces at the left end, at the right end, and at both ends.
- If the input data is null, no conversion is performed.
- If the number of input field columns is greater than the number of field columns actually included in the original data, all data becomes dirty data.

## Example

Use the **CSV File Input** operator to generate fields A, B, and C.

The following figure shows the source file.

```
welcome ,to , 2016
happy ,new , year
```

Configure the **String Trim** operator to generate three new fields D, E, and F.

The screenshot shows the configuration interface for the String Trim operator. At the top, there are buttons for 'Import' and 'Export'. Below them are 'Table Edit' and 'Text Area Edit' tabs. The main configuration area is a table with three columns: 'input field name', 'output field name', and 'trim type'. The table contains three rows of configuration:

input field name	output field name	trim type
A	D	both
B	E	right
C	F	left

At the bottom of the configuration area, there is an 'Add' button.

Six fields are generated, as shown in the following figure.

```
welcome ,to , 2016,welcome,to,2016
happy ,new , year,happy,new,year
```

### 13.7.3.13 Filter Rows

#### Overview

This **Filter Rows** operator filters rows that contain triggering conditions by configuring logic conditions.

#### Input and Output

- Input: fields used to create filter conditions
- Output: none

#### Parameter Description

Table 13-120 Operator parameters description

Parameter	Description	Type	Mandatory	Default Value
Condition logic connector	Condition logic connector. The options include <b>AND</b> and <b>OR</b> .	enum	Yes	AND
Conditions	Filter condition information: <ul style="list-style-type: none"> <li>• <b>input field name:</b> Names of the input fields. Set this parameter to the names of the fields generated in the previous conversion step.</li> <li>• <b>operator:</b> Operator</li> <li>• <b>comparative value.</b> You can directly enter the value of a field referenced in the <b>#{Existing field name}</b> format.</li> </ul>	map	Yes	None

#### Data Processing Rule

- When the condition logic is **AND**, if no filtering condition is added, all data becomes dirty data; if the original data meets all the added filtering conditions, the current line becomes dirty data.
- When the condition logic is **OR**, if no filter condition is added, all data becomes dirty data; if the original data meets any of the added filter conditions, the current line becomes dirty data.

## Example

Use the **CSV File Input** operator to generate two fields A and B.

The following figure shows the source file.

```
test, product  
FusionInsight,Bigdata
```

Configure the **Filter Rows** operator to filter lines that contain test.

input field name	operator	comparative value
A	==	test

After the conversion, enter the original fields. The result is as follows:

```
FusionInsight,Bigdata
```

### 13.7.3.14 Update Fields Operator

#### Overview

The **Update Fields** operator updates fields values when certain conditions are met.

The types supported at present include **BIGINT**, **DECIMAL**, **DOUBLE**, **FLOAT**, **INTEGER**, **SMALLINT**, and **VARCHAR**. When the type is **VARCHAR** and the operator is **+**, strings will be added to the end of field values. The operator **-** is not supported. For other types, **+** and **-** indicate addition and subtraction of values. For all types, **=** indicates new value assignment.

#### Input and Output

Input: field

Output: input field

## Parameter Description

**Table 13-121** Operator parameters description

Parameter	Description	Type	Mandatory	Default Value
update field name	Fields to be updated	string	Yes	None
update operator	Operator, which can be +, -, or =.	enum	Yes	+
update value	Values to be updated	The type is the same as the field type.	No	None
Condition logic connector	Condition logic connector. The options include <b>AND</b> and <b>OR</b> .	enum	Yes	AND
Conditions	Filter condition information: <ul style="list-style-type: none"> <li>• <b>input field name:</b> Names of the input fields. Set this parameter to the names of the fields generated in the previous conversion step.</li> <li>• <b>operator:</b> Operator</li> <li>• <b>comparative value.</b> You can directly enter the value of a field referenced in the <b>#{Existing field name}</b> format.</li> </ul>	map	Yes	None

### Data Processing Rule

- The operator checks whether conditions are met. If yes, the operator updates the field values. If no, the operator does not update the field values.
- If the field values are digits, the updated values are digits.
- If the fields are of the string type, the operator - cannot be used.

### Example

Use the **CSV File Input** operator to generate two fields A and B.

The following figure shows the source file.

```
test, product
FusionInsight,Bigdata
```

Configure the **Update Fields** operator to update a value by adding good to the end of the value if the value contains test.

update field name: A

update operator: +

update value: good

Conditions logic connector: AND

Conditions

Import Export

Table Edit Text Area Edit

input field name	operator	comparative value
A	==	test

Add

The following figure shows the output result.

```
testgood ,product  
FusionInsight,Bigdata
```

## 13.7.4 Output Operators

### 13.7.4.1 Hive output

#### Overview

The **Hive Output** operator exports existing fields to specified columns of a Hive table.

#### Input and Output

- Input: fields to be exported
- Output: Hive table

## Parameters

**Table 13-122** Operator parameters description

Parameter	Description	No de Type	Man dator y	Defa ult Valu e
Hive file storage format	<p>Hive configuration file storage format. CSV, ORC, and RC are supported at present.</p> <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>Parquet is a column-based storage format. In this format, the output field names of Loader be the same as the field names in Hive tables.</li> <li>For Hive of versions later than 1.2.0, a field name, instead of field number, is used to parse ORC files. Therefore, the output field names of Loader must be the same as those in Hive tables.</li> </ul>	enum	Yes	CSV
Hive file compression format	Hive table file compression format. Select a format from the drop-down list. If you select <b>NONE</b> or do not set this parameter, data is not compressed.	enum	Yes	NONE
Hive ORC file version	Version of the ORC file (when the storage format of the Hive table file is ORC).	enum	Yes	0.12
Output delimiter	Delimiter.	string	Yes	None

Parameter	Description	No de Type	Man dator y	Defa ult Valu e
Output fields	<p>Information about output fields:</p> <ul style="list-style-type: none"> <li>• position: Position of output fields.</li> <li>• field name: Names of output fields.</li> <li>• type: Field type. If type is set to <b>DATE</b>, <b>TIME</b>, or <b>TIMESTAMP</b>, you must specify a time format. If type is set to other values, the time format is invalid. An example time format is <b>yyyyMMdd HH:mm:ss</b>.</li> <li>• decimal format: scale and precision of the decimal.</li> <li>• length: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> <li>• partition key: indicates whether a column is a partition column. You can specify zero or multiple partition columns. If multiple primary keys are configured, they are combined according to the configuration sequence.</li> </ul>	map	Yes	None

### Data Processing Rule

- The field values are exported to the Hive table.
- If one or more columns are specified as partition columns, the **Partition Handlers** feature is displayed on the **To** page in Step 4 of the job configuration. **Partition Handlers** specifies the number of handlers for processing data partitioning.
- If no column is designated as partition columns, input data does not need to be partitioned, and **Partition Handlers** is hidden by default.

### Example

Use the **CSV File Input** operator to generate two fields A and B.

The following figure shows the source file.

```
2016,year
year,2016
```

Configure the **Hive Output** operator to export a\_str and b\_str to the Hive table.

Hive Output-Hive Output

Hive File Storage Format: ORC

Hive File Compression Format: NONE

Hive ORC File Version: 0.12

Output delimiter:

Output fields

associate Import Export

Table Edit Text Area Edit

position	field name	type	decimal Format	length	is partitionkey
1	a_str	STRING			<input type="checkbox"/>
2	b_str	VARCHAR			<input type="checkbox"/>

Add

After the execution is complete, view the table data.

```
0: jdbc:hive2://10.52.0.97:21066/> select * from hive_test;
+-----+-----+
| hive_test.a_str | hive_test.b_str |
+-----+-----+
| 2016            | year            |
| year           | 2016           |
+-----+-----+
2 rows selected (1.6 seconds)
```

### 13.7.4.2 Spark Output

#### Overview

The **Spark Output** operator exports existing fields to specified columns of a Spark SQL table.

#### Input and Output

- Input: fields to be exported
- Output: SparkSQL table

## Parameter Description

Table 13-123 Operator parameters description

Parameter	Description	No de Type	Man dator y	Defa ult Value
Spark file storage format	<p>SparkSQL configuration file storage format. CSV, ORC, RC and PARQUET are supported at present.</p> <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>• PARQUET is a column-based storage format. In this format, the output field names of Loader be the same as the field names in the SparkSQL table.</li> <li>• For Hive of versions later than 1.2.0, a field name, instead of field number, is used to parse ORC files. Therefore, the output field names of Loader must be the same as those in the SparkSQL table.</li> </ul>	enum	Yes	CSV
Spark file compression format	<p>SparkSQL table file compression format. Select a format from the drop-down list. If you select <b>NONE</b> or do not set this parameter, data is not compressed.</p>	enum	Yes	NONE
Spark ORC file version	<p>Version of the ORC file (when the storage format of the SparkSQL table file is ORC).</p>	enum	Yes	0.12
Output delimiter	<p>Delimiter.</p>	string	Yes	None

Parameter	Description	No de Type	Man dator y	Defa ult Valu e
Output fields	<p>Information about output fields:</p> <ul style="list-style-type: none"> <li>• position: Position of output fields.</li> <li>• field name: Names of output fields.</li> <li>• type: Field type. If type is set to <b>DATE</b>, <b>TIME</b>, or <b>TIMESTAMP</b>, you must specify a time format. If type is set to other values, the time format is invalid. An example time format is <b>yyyyMMdd HH:mm:ss</b>.</li> <li>• decimal format: scale and precision of the decimal.</li> <li>• length: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> <li>• partition key: indicates whether a column is a partition column. You can specify zero or multiple partition columns. If multiple primary keys are configured, they are combined according to the configuration sequence.</li> </ul>	map	Yes	None

### Data Processing Rule

- The field values are exported to the SparkSQL table.
- If one or more columns are specified as partition columns, the **Partition Handlers** feature is displayed on the **To** page in Step 4 of the job configuration. **Partition Handlers** specifies the number of handlers for processing data partitioning.
- If no column is designated as partition columns, input data does not need to be partitioned, and **Partition Handlers** is hidden by default.

### Example

Use the **CSV File Input** operator to generate two fields A and B.

The following figure shows the source file.

```
2016, year
year, 2016
```

Configure the **Spark Output** operator to export A and B to the SparkSQL table.

### 13.7.4.3 Table Output

#### Overview

The **Table Output** operator exports output fields to specified columns in a relational database table.

#### Input and Output

- Input: fields to be exported
- Output: relational database table

#### Parameters

**Table 13-124** Operator parameters description

Parameter	Description	No de Type	Man dator y	Defa ult Valu e
Output delimiter	Delimiter. <b>NOTE</b> This configuration applies only to the MySQL dedicated connector. If the data column content contains the default delimiter, you need to set a user-defined delimiter. Otherwise, data disorder may occur.	string	No	,

Parameter	Description	No de Type	Man dator y	Defa ult Valu e
Line delimiter	Line delimiter, which can be any string specified by users based on the actual situation. Any character string is supported. The OS line delimiter is used by default.  <b>NOTE</b> This configuration applies only to the MySQL dedicated connector. If the data column content contains the default delimiter, you need to set a user-defined delimiter. Otherwise, data disorder may occur.	string	No	\n
Output fields	Information about relational database output fields: <ul style="list-style-type: none"> <li>• field name: Names of output fields.</li> <li>• table column name: Names of database table columns.</li> <li>• type: Field type. The value must be consistent with the field type configured in the database.</li> <li>• length: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	Yes	None

## Data Processing Rule

The field values are exported to the table.

## Example

Use the data export from HBase to sqlserver2014 as an example.

In sqlserver2014, run the following statement to create an empty data test\_1 for storing HBase data. Run the following statement:

```
create table test_1 (id int, name text, value text);
```

Use the HBase Input operator to generated three fields A, B, and C.

Use the **Table Output** operator to export A, B, and C to the test\_1 table.

The screenshot shows a configuration panel with the following elements:

- Output delimiter:** A text input field.
- Line Delimiter:** A text input field.
- Output fields:** A section containing three buttons: "associate", "Import", and "Export".
- Table Edit:** A tab that is currently selected, with a "Text Area Edit" tab also visible.
- Table:** A table with three columns: "field name", "table column name", and "type".
 

field name	table column name	type
A	id	VARCHAR
B	name	VARCHAR
C	value	VARCHAR
- Add:** A button located below the table.

The command output is as follows:

	id	name	value
1	1	zhangshan	zhang
2	2	lisi	li
3	3	wangwu	wang

### 13.7.4.4 File Output

#### Overview

The **File Output** operator uses delimiters to concatenate existing fields and exports new fields to a file.

#### Input and Output

- Input: fields to be exported
- Output: files

#### Parameter Description

**Table 13-125** Operator parameters description

Parameter	Description	Type	Mandatory	Default Value
Output delimiter	Set a delimiter.	string	Yes	None

Parameter	Description	Type	Mandatory	Default Value
Line breaker	Line delimiter, which can be any string specified by users based on the actual situation. Any character string is supported. The OS line delimiter is used by default.	string	No	\n
Output fields	<p>Information about output fields:</p> <ul style="list-style-type: none"> <li>• <b>position</b>: Position of output fields.</li> <li>• <b>field name</b>: Names of output fields.</li> <li>• <b>type</b>: Field type. If type is set to <b>DATE</b>, <b>TIME</b>, or <b>TIMESTAMP</b>, you must specify a time format. If type is set to other values, the time format is invalid. The example time format is <b>yyyyMMdd HH:mm:ss</b>.</li> <li>• <b>length</b>: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> </ul>	map	No	None

## Data Processing Rule

The field is exported to a file.

## Example

Use the **CSV File Input** operator to generate two fields A and B.

The following figure shows the source file.

```
aaa,product
bbb,Bigdata
```

Configure the **File Output** operator, set **Output delimiter** to a comma (,), and export A and B to a file, as shown in the following figure.

The following figure shows the result.

```
aaa,product
bbb,Bigdata
```

### 13.7.4.5 HBase Output

#### Overview

The **HBase Output** operator exports existing fields to specified columns of an HBase Outputtable.

#### Input and Output

- Input: fields to be exported
- Output: HBase table

#### Parameters

**Table 13-126** Operator parameters description

Parameter	Description	No de Type	Man dator y	Defa ult Valu e
HBase table type	HBase table type. The options include normal (common HBase table) and phoenix.	enu m	Yes	norm al

Parameter	Description	Node Type	Mandatory	Default Value
NULL value processing mode	Null value processing mode. Selecting the option button indicates to convert null values to empty strings and save them. Deselecting the option button indicates the data is not saved.	boolean	No	The option button is not selected.
HBase output fields	<p>HBase output information:</p> <ul style="list-style-type: none"> <li>• field name: Names of output fields.</li> <li>• table name: HBase table name.</li> <li>• family name: HBase column family name.</li> <li>• column name: HBase column name.</li> <li>• type: Field type. If type is set to <b>DATE</b>, <b>TIME</b>, or <b>TIMESTAMP</b>, you must specify a time format. If type is set to other values, the time format is invalid. An example time format is <b>yyyyMMdd HH:mm:ss</b>.</li> <li>• length: Field value length. If the actual field value is excessively long, the value is cut based on the configured length. When <b>type</b> is set to <b>CHAR</b>, spaces are added to the field value for supplement if the actual field value length is less than the configured length. When <b>type</b> is set to <b>VARCHAR</b>, no space is added to the field value for supplement if the actual field value length is less than the configured length.</li> <li>• Primary Key: Indicates whether a column is a primary key column. A common HBase table can have only one primary key, while a phoenix table can have multiple primary keys. If multiple primary keys are configured, they are combined according to the configuration sequence. At least one primary key column must be configured.</li> </ul>	map	Yes	None

## Data Processing Rule

- The field values are exported to the HBase table.
- When the original data contains NULL values, if the **NULL value processing mode** is selected, the NULL values are converted to empty strings and saved. If the **NULL value processing mode** button is not selected, the data is not saved.

## Example

Using table input as an example, after the fields are generated, the HBase Output operator exports them to the related HBase table and stores the data in the test table, as shown in the following figure.

	id	name	value
1	1	zhangshan	zhang
2	2	lisi	li
3	3	wangwu	wang

Create an HBase table.

```
create 'hbase_test','f1','f2';
```

Configure the **HBase Output** operator, as shown in the following figure.

After the job execution is complete, view the data in the hbase\_test table.

```
hbase(main):001:0> scan 'hbase_test'
ROW
1
1
2
2
3
3
3 row(s) in 0.2720 seconds

COLUMN+CELL
column=f1:B, timestamp=1455855645760, value=zhangshan
column=f1:C, timestamp=1455855645760, value=zhang
column=f1:B, timestamp=1455855645760, value=lisi
column=f1:C, timestamp=1455855645760, value=li
column=f1:B, timestamp=1455855645760, value=wangwu
column=f1:C, timestamp=1455855645760, value=wang
```

### 13.7.4.6 ClickHouse Output

#### Overview

The **ClickHouse Output** operator exports existing fields to specified columns of a ClickHouse table.

## Input and Output

- Input: fields to be exported
- Output: ClickHouse table

## Parameters

Table 13-127 Operator parameters

Parameter	Description	Type	Mandatory	Default Value
ClickHouse database name	Database where the ClickHouse table is located.	string	Yes	default
ClickHouse table name	Name of the ClickHouse table to which data is written.	string	Yes	None

## Data Processing Rule

The field values are exported to the ClickHouse table.

## Example

Use the **CSV File Input** operator to generate 12 fields.

The following figure shows the source file.

```
1, 'b', 'abcd', '2021-06-15', '12:00:06', '2021-06-15 12:00:06', 1, 12, 6.8, 18.6, 12.8, true
2, 'abc', 'abcd', '2021-06-15', '12:00:06', '2021-06-15 12:00:06', 1, 12, 6.8, 18.6, 12.8, true
3, 'ab', 'abcd', '2021-06-15', '12:00:06', '2021-06-15 12:00:06', 1, 12, 6.8, 18.6, 12.8, true
4, 'abcdef', 'abcd', '2021-06-15', '12:00:06', '2021-06-15 12:00:06', 1, 12, 6.8, 18.6, 12.8, true
5, 'a', 'abcd', '2021-06-15', '12:00:06', '2021-06-15 12:00:06', 1, 12, 6.8, 18.6, 12.8, true
6, 'bg', 'cde', '2020-06-15', '13:00:06', '2021-06-15 12:00:06', 1, 12, 6.8, 18.6, 12.8, true
7, 'f', 'cde', '2020-06-15', '13:00:06', '2021-06-15 12:00:06', 1, 12, 6.8, 18.6, 12.8, true
8, 'h', 'cde', '2020-06-15', '13:00:06', '2021-06-15 12:00:06', 1, 12, 6.8, 18.6, 12.8, true
```

Run the following statements to create a ClickHouse table:

```
CREATE TABLE IF NOT EXISTS testck4 ON CLUSTER default_cluster(
```

```
  a Int32,
```

```
  b VARCHAR(100) NOT NULL,
```

```
  c char(100),
```

```
  d DateTime,
```

```
  e DateTime,
```


```
  f DateTime,
```

```
  g smallint,
```


```

h bigint,
l Float32,
j Float64,
k decimal(10,2),
m boolean
)
ENGINE = ReplicatedMergeTree('/clickhouse/tables/{shard}/default/testck4',
'{replica}')
PARTITION BY toYYYYMM(d)ORDER BY a;
    
```

Configure the **ClickHouse Output** operator, as shown in the following figure.



After the job execution is complete, view the data in the **testck4** table.



## 13.7.5 Associating, Editing, Importing, or Exporting the Field Configuration of an Operator

### Scenario

This section describes how to associate, import, or export the field configuration information of an operator when creating or editing a Loader job.

- Associating the field configuration of an operator  
Associate the field configuration information of an input operator with an output operator.
- Editing the field configuration of an operator  
Edit the field configuration information of an operator.
- Importing the field configuration of an operator  
Import the field configuration information to an operator by using an operator export file or operator template file.
- Exporting the field configuration of an operator  
Export the field configuration information of an operator to a JSON file and save the file to a local directory.

### Prerequisites

You have obtained the username and password for logging in to the Loader web UI.


### Procedure

- **Associating Field Configuration of an Operator**

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-98** Loader web UI



**Step 2** Edit an existing job or create a new job. The **Transform** page is displayed.

**Step 3** Double-click a specified input operator (such as **CSV File Input**) to go to the edit page. Add the configuration information to the parameter table of the input field.

**Step 4** Double-click a specified output operator (such as **File Output**) to go to the edit page, click **associate**, and select the required field information in the displayed **associate** dialog box.

**NOTE**

- The field name already exists in the field table of the output operator and is not displayed in the **associate** window.
- You can also select the required field from the **field name** list. The corresponding configuration information is displayed in the parameter table of the output field.

**Step 5** Click **OK**. The selected field is displayed in the parameter table of the output field.


----End

• **Editing the Field Configuration of an Operator**

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-99** Loader web UI




**Step 2** Edit an existing job or create a new job. The **Transform** page is displayed.

**Step 3** Double-click a specified operator (such as **CSV File Input**) to go to the edit page. On the **Table Edit** tab page of the input field, click **Add** and enter the field information based on the parameter requirements of the operator.

**Step 4** You can move (up or down), insert a row under, and delete a field by clicking buttons corresponding to the field.

Click **Text Area Edit** to edit the field list in text format. Use commas (,) to separate field attributes.



**Step 5** Click **OK**.


----End

- **Importing the Field Configuration of an Operator**

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

**Figure 13-100** Loader web UI



**Step 2** Edit an existing job or create a new job. The **Transform** page is displayed.

**Step 3** Double-click a specified operator to go to the editing page and add related configuration information to the parameter table of the input or output field. Click **Import**.

**Step 4** Select an import type.

- **Export File**  
Field configuration information is imported by using the JSON file exported by the operator.
- **Specified Template**  
Field configuration information is imported by using the TXT file compiled based on the operator template.

**Step 5** Click  and select the upload file path.

**Step 6** Click **Upload**. The field configuration information is imported to the operator.


----End

- **Exporting the Field Configuration of an Operator**

**Step 1** Access the Loader web UI.

1. Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).
2. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Loader**.
3. Click **LoaderServer(Node name, Active)**. The Loader web UI is displayed.

Figure 13-101 Loader web UI



**Step 2** Edit an existing job or create a new job. The **Transform** page is displayed.

**Step 3** Double-click a specified operator to go to the editing page, add related configuration information to the parameter table of the input or output field, and click **Export**.

**Step 4** Select an export type.

- All  
All field information is exported as a JSON file and saved to a local directory.
- Specified Field Name  
Fields selected in the field list are exported as a JSON file and saved to a local directory.

**Step 5** Click **OK**.

----End

## 13.7.6 Using Macro Definitions in Configuration Items

When creating or editing Loader jobs, users can use macro definitions during parameter configuration. Then the parameters can be automatically changed to corresponding macro values when a job is implemented.

### NOTE

- The macro definitions take effect in the job only.
- Macro definitions can be imported and exported together with an import or export job. If a job uses macro definitions, the exported job includes the macro definitions. Macro definitions are imported by default when a job is imported.
- For details about the **dateformat** definition of the first parameter in the time macro dataformat, see **java.text.SimpleDateFormat.java**. The restrictions of the target system must be followed. For example, HDFS/OBS directories do not support special characters.

## Macro Definitions of Loader

At present, Loader supports the following time macro definitions by default:

**Table 13-128** Common macro definitions of Loader

Name	Result After the Replacement	Description
<code>@{dateformat("yyyy-MM-dd")}@</code>	2016-05-17	Indicates the current date.
<code>@{dateformat("yyyy-MM-dd HH:mm:ss")}@</code>	2016-05-17 16:50:00	Indicates current date and time
<code>@{timestamp()}@</code>	1463476137557	Indicates milliseconds since 1970.
<code>@{dateformat("yyyy-MM-dd HH:mm:ss",-7,DAYS)}@</code>	2016-05-10 16:50:00	Indicates the latest seven days (the present time minus seven days). The second parameter supports addition and subtraction. The third parameter is a time unit for calculation. According to definitions in the <b>java.util.concurrent.TimeUnit.java</b> , time units include DAYS, HOURS, MINUTES, and SECONDS.

In the following scenarios, parameters can be configured by using macro definitions.

- Specifying a data directory that is named by the current date  
The parameter is set to `/user/data/inputdate_@{dateformat("yyyy-MM-dd")}@`.
- Querying data in the latest seven days by using SQL  
`select * from table where time between '@{dateformat("yyyy-MM-dd HH:mm:ss",-7,DAYS)}@' and '@{dateformat("yyyy-MM-dd HH:mm:ss")}'@`
- Specifying a table that is named by the current date  
The parameter is set to `table_@{dateformat("yyyy-MM-dd")}@parmvalue`.

### 13.7.7 Operator Data Processing Rules

In Loader data import and export tasks, each operator defines different processing rules for null values and empty strings in raw data. Dirty data cannot be imported or exported.

The following table describes the operator data processing rules for each conversion procedure.

**Table 13-129** Data processing rules

Procedure	Description
CSV file input	<ul style="list-style-type: none"> <li>● If a delimiter appears twice consecutively in the original data, an empty string field is generated.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>● If a type conversion error occurs, the current data is saved as dirty data.</li> </ul>
Fixed file input	<ul style="list-style-type: none"> <li>● If the original data includes null values, no conversion is performed.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>● If the configured field conversion type is different from the actual type of the original data, all data becomes dirty data. For example, convert the string type to the numeric type.</li> <li>● If the configured field split length is greater than the length of the original field value, the data split fails and the current line becomes dirty data.</li> </ul>
Table input	<ul style="list-style-type: none"> <li>● If the original data includes null values, no conversion is performed.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>● If the configured field conversion type is different from the actual type of the original data, all data becomes dirty data. For example, convert the string type to the numeric type.</li> </ul>

Procedure	Description
HBase input	<ul style="list-style-type: none"> <li>● If the original data includes null values, no conversion is performed.</li> <li>● If the HBase table name is incorrect, all data becomes dirty data.</li> <li>● If the primary key column is not configured in <b>Is rowkey</b>, all data becomes dirty data.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>● If the configured field conversion type is different from the actual type of the original data, all data becomes dirty data. For example, convert the string type to the numeric type.</li> </ul>
Long integer time conversion	<ul style="list-style-type: none"> <li>● If the original data includes null values, no conversion is performed.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>● If a type conversion error occurs, the current data is saved as dirty data.</li> </ul>
Null value conversion	<ul style="list-style-type: none"> <li>● If the original data contains null values, data is converted to a specified value.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> </ul>
Random value conversion	Processing of null value and empty string is not involved, and dirty data is not generated.
Constant field addition	Processing of null value and empty string is not involved, and dirty data is not generated.
Concat fields	<ul style="list-style-type: none"> <li>● If the original data contains null values, data is converted to empty string.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> </ul>
Extracts fields	<ul style="list-style-type: none"> <li>● If the original data contains null values, the current line becomes dirty data.</li> <li>● If the number of field columns after separation is greater than the actual number allowed by the original data, the line will become dirty data.</li> </ul>

Procedure	Description
Modulo integer	<ul style="list-style-type: none"> <li>● If the original data contains null values, the current line becomes dirty data.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>● If data type conversion fails, the current line becomes dirty data.</li> </ul>
String cut	<ul style="list-style-type: none"> <li>● If the input data is null, no conversion is performed.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>● If the start or end position of the string to be truncated is greater than the length of the input field, the current line becomes dirty data.</li> </ul>
EL operation	<ul style="list-style-type: none"> <li>● If the input data is null, no conversion is performed.</li> <li>● Enter the value of one or more fields and output the calculation result.</li> <li>● When the input type is incompatible with the operator, the current row is dirty data.</li> </ul>
String case conversion	<ul style="list-style-type: none"> <li>● If the input data is null, no conversion is performed.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> </ul>
String reverse	<ul style="list-style-type: none"> <li>● If the input data is null, no conversion is performed.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> </ul>
String trim	<ul style="list-style-type: none"> <li>● If the input data is null, no conversion is performed.</li> <li>● It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> </ul>

Procedure	Description
Filter rows	<ul style="list-style-type: none"> <li>• When the condition logic is <b>AND</b>, if no filter condition is added, all data becomes dirty data; if the original data meets all the added filter conditions, the current line becomes dirty data.</li> <li>• When the condition logic is <b>OR</b>, if no filter condition is added, all data becomes dirty data; if the original data meets all the added filter conditions, the current line becomes dirty data.</li> </ul>
File output	<ul style="list-style-type: none"> <li>• If the input data is null, no conversion is performed.</li> </ul>
Table output	<ul style="list-style-type: none"> <li>• It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>• If data type conversion fails, the current line becomes dirty data.</li> </ul>
HBase output	<ul style="list-style-type: none"> <li>• If the original data contains null values and <b>Store null column</b> is set to <b>true</b>, data is converted to empty string and saved. If <b>Store null column</b> is set to <b>false</b>, data will not be saved.</li> <li>• It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>• If data type conversion fails, the current line becomes dirty data.</li> </ul>
Hive output	<ul style="list-style-type: none"> <li>• If one or more columns are designated as partition columns, the <b>Partition Handlers</b> feature is displayed on the <b>To</b> page. <b>Partition Handlers</b> specifies the number of handlers for processing data partitioning.</li> <li>• If no column is designated as partition columns, input data does not need to be partitioned, and <b>Partition Handlers</b> is hidden by default.</li> <li>• It can be configured that all data becomes dirty data when the number of input field columns is greater than the number of field columns actually included in the original data.</li> <li>• If data type conversion fails, the current line becomes dirty data.</li> </ul>

## 13.8 Client Tool Description

## 13.8.1 Running a Loader Job by Using Commands

### Scenario

Generally, users can manually manage data import and export jobs on the Loader UI. If you need to update and run Loader jobs by executing the shell script, you must configure the installed Loader client.

#### NOTE

Loader is incompatible with the client of an earlier version. If you reinstall the cluster or the Loader service, download and install the client again, and then use the client.

### Prerequisites

- The Loader client has been installed. During the installation of the Loader client using a non-root user, if another user wants to use the client, the user needs to be authorized by the user who installs the client or a user with more rights (the Loader client installation directory needs to be granted with right 755). Please pay attention to the security problems after the authorization.
- The user for accessing the Loader service has been created. If the user is a machine-machine user, the keytab file must be downloaded..

### Procedure

#### Step 1 Configure the Loader shell client.

1. Log in to the node where the client is located as the user who installs the client.
2. Run the following command to disable logout upon timeout:

```
TMOUT=0
```

#### NOTE

After the operations in this section are complete, run the **TMOUT=Timeout interval** command to restore the timeout interval in a timely manner. For example, **TMOUT=600** indicates that a user is logged out if the user does not perform any operation within 600 seconds.

3. Run the following command to go to the directory where the Loader client installation package is stored. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:
4. Run the following command to configure environment variables:
5. If the cluster is in security mode, run the following command to authenticate the user. In normal mode, user authentication is not required.

```
kinit Component service user
```

6. Run the following command to modify the tool authorization configuration file **login-info.xml**, save the file, and exit. For the parameters in the configuration file, see [Table 13-130](#).

```
vi loader-tools-1.99.3/loader-tool/job-config/login-info.xml
```

**Table 13-130** Parameters of **login-info.xml**

Parameter	Description
hadoop.config.path	Storage directory of the <b>core-site.xml</b> , <b>hdfs-site.xml</b> , and <b>krb5.conf</b> configuration files of the MRS cluster. These three files are stored in the <b>Loader Client installation directory/Loader/loader-tools-1.99.3/loader-tool/hadoop-config/</b> directory by default.
authentication.type	Authentication type of the Loader service. Set this parameter based on MRS cluster authentication mode. <ul style="list-style-type: none"> <li>- <b>kerberos</b> indicates the security mode.</li> <li>- <b>simple</b> indicates the normal mode.</li> </ul>
user.keytab	Whether to use the keytab file for authentication. The options are <b>true</b> , and <b>false</b> .
authentication.user	User for login when the normal mode or password authentication is used.  In the keytab login mode, this parameter does not need to be set.
authentication.password	Encrypted password of the user for accessing the Loader service if the keytab file authentication is not used in the security mode.  <b>NOTE</b> Run the following command to encrypt the password as the user who installs the client. When the encryption tool runs for the first time, a random dynamic key is automatically generated and stored in <b>.loader-tools.key</b> . The encryption tool uses this dynamic key to encrypt passwords every time. After <b>.loader-tools.key</b> is deleted, a new random key will be generated and stored in <b>.loader-tools.key</b> when the encryption tool runs.  <b>sh Loader client installation directory/Loader/loader-tools-1.99.3/encrypt_tool password</b>

Parameter	Description
authentication.principal	<b>Machine-Machine</b> username for accessing the Loader service when the keytab file authentication is used in the security mode.
authentication.keytab	Absolute keytab file directory of the Machine-Machine user for accessing the Loader service when the keytab file authentication is used in the security mode.
zookeeper.quorum	IP address and port for accessing ZooKeeper. The value format is <b>IP1:port,IP2:port,IP3:port</b> . The default port number is 2181.
sqoop.server.list	Floating IP address and port for accessing Loader. The value format is <b>floatip:port</b> . The default port number is <b>21351</b> .

**Step 2** Use the Loader shell client.

1. Run the following command to go to the Loader shell client directory. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:  
**cd /opt/hadoopclient/Loader/loader-tools-1.99.3/shell-client/**
2. Run the following command to use the Loader shell client to run a job:  
**./submit\_job.sh -n <arg> -u <arg> -jobType <arg> -connectorType <arg> -frameworkType <arg>**

**Table 13-131** Parameters of the Loader shell client tool

Parameter	Description
-n	(Mandatory) Job name.
-u	(Mandatory) If the parameter is set to <b>y</b> , the job parameters are updated and the job is executed. In this scenario, parameters <b>-jobType</b> , <b>-connectorType</b> , and <b>-frameworkType</b> need to be set. If the parameter is set to <b>n</b> , the job is directly executed without updating parameters.

Parameter	Description
-jobType	<p>Job type. This parameter is mandatory when <b>-u</b> is set to <b>y</b>.</p> <p><b>import</b> indicates the data import job. <b>export</b> indicates the data export job.</p>
-connectorType	<p>Connector type. This parameter is mandatory when <b>-u</b> is set to <b>y</b>. Parameters of external data sources can be modified as required.</p> <p><b>sftp</b> indicates the connector is an SFTP connector.</p> <ul style="list-style-type: none"> <li>- In a data import job, you can modify the source file input path <b>-inputPath</b>, the source file encode format <b>-encodeType</b>, and the suffix <b>-suffixName</b> added to the input file after the source file is imported.</li> <li>- In a data export job, you can modify the output path <b>-outputPath</b> or the name of the exported file.</li> </ul> <p><b>rdb</b> indicates the connector is a relational database connector.</p> <ul style="list-style-type: none"> <li>- In a data import job, you can modify the database mode name <b>-schemaName</b>, table name <b>-tableName</b>, SQL statement <b>-sql</b>, names of columns to be imported <b>-columns</b>, and names of partition columns <b>-partitionColumn</b>.</li> <li>- In a data export job, you can modify the database mode name <b>-schemaName</b>, table name <b>-tableName</b>, and the temporary table name <b>-stageTableName</b>.</li> </ul>

Parameter	Description
-frameworkType	<p>Data storage type on MRS. This parameter is mandatory when <b>-u</b> is set to <b>y</b>. Parameters of data storage types can be modified as required.</p> <p><b>hdfs</b> indicates that the HDFS is used to store data on Hadoop.</p> <ul style="list-style-type: none"> <li>- In a data import job, you can modify the number of started maps <b>-extractors</b> and the storage directory of imported data in the HDFS <b>-outputDirectory</b>.</li> <li>- In a data export job, you can modify the number of started maps <b>-extractors</b>, the input path of data exported from the HDFS <b>-inputDirectory</b>, and the file filter criteria of the data export job <b>-fileFilter</b>.</li> </ul> <p><b>hbase</b> indicates that HBase is used to store data on MRS. In the data import and export job, you can modify the number of started maps <b>-extractors</b>.</p>

----End

## Task Examples

- Run a job whose name is **sftp-hdfs** without updating job parameters:  
`./submit_job.sh -n sftp-hdfs -u n`
- Update the input path, encoding type, suffix, output path, and number of started maps of the data import job whose name is **sftp-hdfs**, and run the job:  
`./submit_job.sh -n sftp-hdfs -u y -jobType import -connectorType sftp -inputPath /opt/tempfile/1 -encodeType UTF-8 -suffixName " -frameworkType hdfs -outputDirectory /user/user1/tttest -extractors 10`
- Update the database mode, table name, and output path of the data import job whose name is **db-hdfs**, and run the job.  
`./submit_job.sh -n db-hdfs -u y -jobType import -connectorType rdb -schemaName public -tableName sq_submission -sql " -partitionColumn sqs_id -frameworkType hdfs -outputDirectory /user/user1/dbdbt`

## 13.8.2 loader-tool Usage Guide

### Overview

loader-tool is a Loader client tool. It consists of three tools: **lt-ucc**, **lt-ucj**, **lt-ctl**.

Loader supports two modes, parameter mode and job template mode. Either mode can be used to create, update, query, and delete connectors, and to create, update, query, delete, start, and stop Loader jobs.

 **NOTE**

loader-tool implements an asynchronous interface. After a command is submitted, the command output is not returned to the console in real time. Therefore, the results of the creation, update, query, and deletion operations on a connector and the creation, update, query, deletion, start, and stop operations on a Loader job must be confirmed on the Loader WebUI or by querying server logs.

- Parameter mode:

Add a parameter invoking script with specific parameters.

- Job template mode:

Change the values of all parameters in a job template and reference the job template when invoking a script.

After a Loader client is installed, the system automatically generates job templates for various scenarios in the *Loader client installation directory*/**loader-tools-1.99.3/loader-tool/job-config/** directory. The parameters vary according to job templates. Job templates contain information about jobs and associated connectors.

Job templates are XML files. The file name format is *original data location-to-new data location.xml*, for example, **sftp-to-hdfs.xml**. If a job supports conversion step, a json conversion step configuration file with the same name exists, for example, **sftp-to-hdfs.json**.

 **NOTE**

Job templates contain the configuration information of connectors. During the connector creation and updating, only the connector information in job templates is invoked.

## Scenarios

The parameters vary according to connectors or jobs.

- To modify some parameters, use the parameter mode.
- To create a connector or job, use the job template mode.

 **NOTE**

This tool currently supports the FTP, HDFS, JDBC, MySQL, Oracle, and Oracle dedicated connectors. If other types of connectors are used, you are advised to use the open-source sqoop-shell tool.

## Parameters

Assume that the Loader client installation directory is **/opt/hadoopclient/Loader/**.

- **lt-ucc usage description**

lt-ucc is a connector configuration tool of loader-tool user-configuration-connection and is used to create, update, and delete connectors.

**Table 13-132** lt-ucc script parameter description

Parameter	Description	Example Value
-help	Help information.	-
-a <arg>	Connector action. The values include <b>create</b> , <b>update</b> and <b>delete</b> for creating, updating, and deleting connectors respectively.	create
-at <arg>	Login authentication type. The values include <b>kerberos</b> and <b>simple</b> .	kerberos
-uk <arg>	Whether to use the keytab file.	true
-au <arg>	Login authentication username.	bar
-ap <arg>	Login authentication password. The value must be an encrypted password. The password encryption method is described as follows: <b>sh Loader client installation directory/Loader/loader-tools-1.99.3/encrypt_tool non-encrypted user password</b> <b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, <b>'1q2w#e\$r'</b> . If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.	d2NjX2NyeXB0ATQxNDU1MzVGNDM0Mj
-c <arg>	Login authentication principal.	bar
-k <arg>	Login authentication keytab file.	/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/hadoop-config/user.keytab
-h <arg>	Specifies the configuration file path of the MRS cluster.	-h /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/hadoop-config



Use the operation of saving SFTP data to HDFS as an example. Edit the **sftp-to-hdfs.xml** file in *Loader client installation directory/loader-tools-1.99.3/loader-tool/job-config/* directory. The connector configuration is as follows:

```
<!-- Database connection information -->
<sqoop.connection name="vt_sftp_test" type="sftp-connector">
<connection.sftpServerIp>10.96.26.111</connection.sftpServerIp>
<connection.sftpServerPort>22</connection.sftpServerPort>
<connection.sftpUser>root</connection.sftpUser>
<connection.sftpPassword>d2NjX2NyeXB0ATQxNDU1MzVGNDM0MjQzOzMzMzkzOTMwMzI0NTM5MzQzOTM1Mzk0NTMwMzIzNTM4NDZlNzQzMzIzNjQyMzMzMzMDM4MzZlMzQ1MzYzODQxMzQ7OzMyMzUzMzMDMwO0EzMTUzM0ExNTAyNDhENzE3QTRBRTICQkRBQzIFRkFEOzYyOEE4NTIDODc2MkMyNzU7NTc0MzQzNUY0MzUyNTk1MDU0NUY0NDQ1NDY0MTU1NEM1NDVGNzQ0RjRENDE0OTRFOzMwOzMxMzQzNTM2MzZlMzMTMyMzgzMzZlMzIzNzMwOw</connection.sftpPassword>
</sqoop.connection>
```

- Creation command:  
*./lt-ucc -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -w /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/ftp-to-hdfs.xml -a create*
- Update command:  
*./lt-ucc -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -w /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/ftp-to-hdfs.xml -a update*
- Deletion command:  
*./lt-ucc -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -w /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/ftp-to-hdfs.xml -a delete*

- **lt-ucj usage description**

lt-ucj is a job configuration tool of loader-tool user-configuration-job and is used to create, update, and delete jobs.

**Table 13-133** lt-ucj script parameter description

Parameter	Description	Example Value
-help	Help information.	-
-a <arg>	Job action. The values include <b>create</b> , <b>update</b> , and <b>delete</b> for creating, updating and deleting jobs respectively.	create
-at <arg>	Login authentication type. The values include <b>kerberos</b> and <b>simple</b> .	kerberos
-uk <arg>	Whether to use the keytab file.	true
-au <arg>	Login authentication username.	bar

Parameter	Description	Example Value
-ap <arg>	<p>Login authentication password. The value must be an encrypted password.</p> <p>The password encryption method is described as follows:</p> <p><b>sh</b> <i>Loader client installation directory/Loader/loader-tools-1.99.3/encrypt_tool non-encrypted user password</i></p> <p><b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, '1q2w#e\$'. If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.</p>	d2NjX2NyeXB0ATQxNDU1MzVGNDMOMj
-c <arg>	Login authentication principal.	bar
-k <arg>	Login authentication keytab file.	/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/hadoop-config/user.keytab
-h <arg>	Specifies the configuration file path of the MRS cluster.	-h /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/hadoop-config
-l <arg>	Login template file.	/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml
-s <arg>	<p>Floating IP address and port for Loader.</p> <p>Format: <i>floating IP address: port</i></p> <p>The default port is 21351.</p>	127.0.0.1:21351

Parameter	Description	Example Value
-w <arg>	Job template file for obtaining job details.	/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.xml
-z <arg>	IP address and port number of ZooKeeper quorum instances. The format is <i>IP address: port</i> . Use <b>commas (,)</b> to separate multiple addresses and port numbers.	127.0.0.0:2181, 127.0.0.1:2181
-n <arg>	Name of the job.	Sftp.to.Hdfs
-cn <arg>	Connector name	vt_sftp_test
-ct <arg>	Connector type	sftp-connector
-t <arg>	Job type. The values include <b>IMPORT</b> and <b>EXPORT</b> .	IMPORT
-trans <arg>	Job associated conversion step file.	/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.json
-priority <arg>	Job priority. The values include <b>LOW</b> , <b>NORMAL</b> , and <b>HIGH</b> .	NORMAL
-queue <arg>	Queues	default
-storageType <arg>	Storage type	HDFS
-P <arg>	Used to update the value of an attribute. The format is - Pparam1=value1. param1 indicates the attribute name of the connector in the job template. Password parameters are required for updating SFTP and FTP connector information.  - Pconnection.sftpPassword= <i>Encrypted password</i>	- Pconnection.sftpServerIp=10.6.26.11

A complete example is as follows:

```
./bin/lt-ucj -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/  
job-config/login-info.xml -n Sftp.to.Hdfs -t IMPORT -ct sftp-connector -  
Poutput.outputDirectory=/user/loader/sftp-to-hdfs-test8888 -a update
```

Configuration description of a lt-ucj script job template:

Use the operation of saving SFTP data to HDFS as an example. Edit the file *loader client installation directory/loader-tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.xml*. The job configuration is as follows:

```
<!-- Job name, globally unique.-->  
<sqoop.job name="Sftp.to.Hdfs" type="IMPORT" queue="default" priority=" Priority NORMAL ">  
  
<!-- External data source parameter configuration -->  
<data.source connectionName="vt_sftp_test" connectionType="sftp-connector">  
<file.inputPath>/opt/houjt/hive/all</file.inputPath>  
<file.splitType>FILE</file.splitType>  
<file.filterType>WILDCARD</file.filterType>  
<file.pathFilter>*</file.pathFilter>  
<file.fileFilter>*</file.fileFilter>  
<file.encodeType>GBK</file.encodeType>  
<file.suffixName></file.suffixName>  
<file.isCompressive>FALSE</file.isCompressive>  
</data.source>  
  
<!-- MRS cluster, parameter configuration -->  
<hadoop.source storageType="HDFS" >  
<output.outputDirectory>/user/loader/sftp-to-hdfs</output.outputDirectory>  
<output.fileOprType>OVERRIDE</output.fileOprType>  
<throttling.extractors>3</throttling.extractors>  
<output.fileType>TEXT_FILE</output.fileType>  
</hadoop.source>  
  
<!-- Job associated conversion step file -->  
<sqoop.job.trans.file>/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/sftp-to-  
hdfs.json</sqoop.job.trans.file>  
</sqoop.job>
```

– Creation command:

```
./bin/lt-ucj -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-  
tool/job-config/login-info.xml -w /opt/hadoopclient/Loader/loader-  
tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.xml -a create
```

– Update command:

```
./bin/lt-ucj -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-  
tool/job-config/login-info.xml -w /opt/hadoopclient/Loader/loader-  
tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.xml -a update
```

– Deletion command:

```
./bin/lt-ucj -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-  
tool/job-config/login-info.xml -w /opt/hadoopclient/Loader/loader-  
tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.xml -a delete
```

- **lt-ctl usage description**

lt-ctl is a job management tool of loader-tool controller and is used to start or stop jobs, query job status and progress, and check whether jobs are running.

**Table 13-134** lt-ctl script parameter description

Paramet er	Description	Example Value
-help	Help information.	-

Parameter	Description	Example Value
-a <arg>	Job action. The values include <b>status</b> , <b>start</b> , <b>stop</b> , and <b>is running</b> for querying job status, starting or stopping jobs, and checking whether jobs are running.	create
-at <arg>	Login authentication type. The values include <b>kerberos</b> and <b>simple</b> .	kerberos
-uk <arg>	Whether to use the keytab file.	true
-au <arg>	Login authentication username.	bar
-ap <arg>	<p>Login authentication password. The value must be an encrypted password.</p> <p>The password encryption method is described as follows:</p> <p><b>sh Loader client installation directory/Loader/loader-tools-1.99.3/encrypt_tool non-encrypted user password</b></p> <p><b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, '1q2w#e\$'. If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.</p>	d2NjX2NyeXB0ATQxNDU1MzVGNDM0Mj
-c <arg>	Login authentication principal.	bar
-k <arg>	Login authentication keytab file.	/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/hadoop-config/user.keytab
-h <arg>	Specifies the configuration file path of the MRS cluster.	-h /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/hadoop-config

Parameter	Description	Example Value
-l <arg>	Login template file.	/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml
-n <arg>	Name of the job.	Sftp.to.Hdfs
-s <arg>	Floating IP address and port for Loader. Format: <i>floating IP address: port</i> The default port is 21351.	127.0.0.1:21351
-w <arg>	Job template file for obtaining job details.	/opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.xml
-z <arg>	IP address and port number of ZooKeeper quorum instances. The format is <i>IP address: port</i> . Use <b>commas (,)</b> to separate multiple addresses and port numbers.	127.0.0.0:2181, 127.0.0.1:2181

- Command for starting jobs:  
***./bin/lt-ctl -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -n Sftp.to.Hdfs -a start***
- Command for viewing job status:  
***./bin/lt-ctl -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -n Sftp.to.Hdfs -a status***
- Command for checking whether jobs are running:  
***./bin/lt-ctl -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -n Sftp.to.Hdfs -a isrunning***
- Command for stopping jobs:  
***./bin/lt-ctl -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -n Sftp.to.Hdfs -a stop***

### 13.8.3 loader-tool Usage Example

#### Scenario

loader-tool can be used to create, update, query, and delete a connector or job by using a job template or setting parameters.

This section describes how to use loader-tool in the job template mode. The job of importing data from the SFTP server to HDFS is used as an example.



 NOTE

Each Loader job needs to be associated with a connector. Connectors are used to read data from external data sources when data is imported to a cluster and used to write data into external data sources when data is exported from the cluster. In the preceding example, an SFTP data source connector is configured. To configure an SFTP and FTP data source connector, a password needs to be set and encrypted. The password encryption method is described as follows:

1. Run the following command to go to the **loader-tools-1.99.3** directory. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3
```

2. Run the following command to encrypt the non-encrypted password:

```
./encrypt_tool Unencrypted password
```

- Step 4** Run the following command to go to the directory where loader-tool is located:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool
```

- Step 5** Run the following command to use the lt-ucc tool to create a connector:

```
./bin/lt-ucc -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -w /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.xml -a create
```

If no error is reported and the following information is displayed, the connector creation task is submitted successfully:

```
User login success. begin to execute task.
```

- Step 6** Run the following command to use the lt-ucj tool to create a job:

```
./bin/lt-ucj -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -w /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/sftp-to-hdfs.xml -a create
```

If no error is reported and the following information is displayed, the job creation task is submitted successfully:

```
User login success. begin to execute task.
```

- Step 7** Run the following command to use the lt-ctl tool to submit the job:

```
./bin/lt-ctl -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -n Sftp.to.Hdfs -a start
```

If the following information is displayed, the job is submitted successfully:

```
Start job success.
```

- Step 8** Run the following command to view the job status:

```
./bin/lt-ctl -l /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/login-info.xml -n Sftp.to.Hdfs -a status
```

```
Job:Sftp.to.Hdfs  
Status:RUNNING  
Progress: 0.0
```

**----End**

## 13.8.4 schedule-tool Usage Guide

### Overview

schedule-tool is used to submit jobs of SFTP data sources. You can modify the input path and file filtering criteria before submitting a job. You can modify the output path if the target source is HDFS.

### Parameters

**Table 13-135** Configuration parameters of schedule.properties

Configuration parameters	Description	Example Value
server.url	Floating IP address and port for Loader. The default port is 21351. For compatibility, multiple IP addresses and ports can be configured and need to be separated by commas (,). The first IP address and port must be those of Loader. The others can be configured based on service requirements.	10.96.26.111:21351,127.0.0.2:21351
authentication.type	Login authentication mode. <ul style="list-style-type: none"> <li>• <b>kerberos</b> indicates that the security mode is used and Kerberos authentication is performed. Kerberos authentication provides two authentication modes: the password mode and the keytab file mode.</li> <li>• <b>simple</b> indicates that the normal mode is used and Kerberos authentication is not performed.</li> </ul>	kerberos
authentication.user	User for login when the normal mode or password authentication is used. In the keytab login mode, this parameter does not need to be set.	bar

Configuration parameters	Description	Example Value
<p>authentication.password</p>	<p>User password for login when the password authentication mode is used. In the normal mode or keytab login mode, this parameter does not need to be set.</p> <p>The password needs to be encrypted. The encryption method is described as follows:</p> <ol style="list-style-type: none"> <li>Go to the directory where <b>encrypt_tool</b> is located. For example, if the Loader client installation directory is <b>/opt/hadoopclient/Loader</b>, run the following command: <b>cd /opt/hadoopclient/Loader/loader-tools-1.99.3</b></li> <li>Run the following command to encrypt the non-encrypted password: <b>./encrypt_tool Unencrypted password</b></li> </ol> <p>The obtained encrypted password is used as the value of <b>authentication.password</b>.</p> <p><b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, <b>'1q2w#e\$'</b>. If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.</p>	<p>43B80E33A96DF 3D203ABBDFD10 50C041</p>
<p>use.keytab</p>	<p>Whether to use the keytab mode to log in.</p> <ul style="list-style-type: none"> <li><b>true</b> indicates using the keytab file to log in.</li> <li><b>false</b> indicates using the password to log in.</li> </ul>	<p>true</p>

Configuration parameters	Description	Example Value
client.principal	User principal for accessing the Loader service when the keytab authentication mode is used.  In the normal mode or password login mode, this parameter does not need to be set.	loader/ hadoop. <i>System domain name</i>  <b>NOTE</b> You can log in to FusionInsight Manager, choose <b>System &gt; Permission &gt; Domain and Mutual Trust</b> , and view the value of <b>Local Domain</b> , which is the current system domain name.
client.keytab	Directory where the used keytab file is located when the keytab authentication mode is used.  In the normal mode or password login mode, this parameter does not need to be set.	/opt/client/conf/ loader.keytab
krb5.conf.file	Directory where the <b>krb5.conf</b> file is located when the keytab authentication mode is used.  In the normal mode or password login mode, this parameter does not need to be set.	/opt/client/conf/ krb5.conf

**Table 13-136** Configuration parameters of job.properties

Configuration parameters	Description	Example Value
job.jobName	Job name.	job1
file.fileName.prefix	File name prefix.	table1
file.fileName.posfix	File name suffix.	.txt

Configuration parameters	Description	Example Value
file.filter	File filter, which filters files by matching file names. <ul style="list-style-type: none"> <li>• <b>true</b> indicates that the preceding prefix or suffix is used to match all files in the input path. For details, see the example.</li> <li>• <b>false</b> indicates that the preceding prefix or suffix is used to match a file in the input path. For details, see the example.</li> </ul>	true
date.day	Number of delayed days, which is matched with the date in the name of an imported file. For example, if the input date is 20160202 and the number of delayed days is 3, files that contain the 20160205 date field in the input path are matched. For details, see <a href="#">schedule-tool Usage Example</a> .	3
file.date.format	Log format included in the name of the file to be imported.	yyyyMMdd
parameter.date.format	Entered date format when a script is invoked, which is usually consistent with <b>file.date.format</b> .	yyyyMMdd
file.format.iscompressed	Whether the file to be imported is a compressed file.	false
storage.type	Storage type. The final type of the file to be imported include HDFS, HBase, and Hive.	HDFS

 **NOTE**

schedule-tool supports the configuration of multiple jobs at the same time. When multiple jobs are configured at the same time, **job.jobName**, **file.fileName.prefix**, and **file.fileName.posfix** in [Table 13-136](#) need to be configured with multiple values, and the values need to be separated by **commas (,)**.

## Precautions

**server.url** must be set to a format string of two IP addresses and port numbers, and the IP addresses and ports need to be separated by **commas (,)**.

## 13.8.5 schedule-tool Usage Example

### Scenario

After a job is created using the Loader WebUI or Loader-tool, use schedule-tool to execute the job.

### Prerequisites

The Loader client has been installed and configured. For details, see [Running a Loader Job by Using Commands](#).

### Procedure

- Step 1** In the directory `/opt/houjt/test03` on the SFTP server, create multiple files with **table1** as the prefix, **.txt** as the suffix, and **yyyyMMdd** as the date format in the middle of the file name.

**Figure 13-102** Example

```
[root@C12-RHEL64-ZYL111 test03]# ll
total 36
-rw-r--r--. 1 root root 54 Feb 29 19:11 table120160221.txt
-rw-r--r--. 1 root root 54 Feb 29 19:11 table120160222.txt
-rw-r--r--. 1 root root 54 Feb 29 19:11 table120160223.txt
-rw-r--r--. 1 root root 54 Feb 29 19:11 table120160224.txt
-rw-r--r--. 1 root root 54 Feb 29 19:11 table120160225.txt
-rw-r--r--. 1 root root 54 Feb 29 19:11 table120160226.txt
-rw-r--r--. 1 root root 54 Feb 29 18:43 table120160227.txt
-rw-r--r--. 1 root root 54 Feb 29 19:11 table120160228.txt
-rw-r--r--. 1 root root 54 Feb 29 19:11 table120160229.txt
```

- Step 2** Create a Loader job of importing data from the SFTP server to HDFS. For details, see [Typical Scenario: Importing Data from an SFTP Server to HDFS or OBS](#).
- Step 3** Log in to the node where the client is located as the user who installs the client.
- Step 4** Run the following command to go to the **conf** directory of schedule-tool. For example, if the Loader client installation directory is `/opt/hadoopclient/Loader`, run the following command:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/schedule-tool/conf
```

- Step 5** Run the following command to edit the `schedule.properties` file and configure the login mode:

```
vi schedule.properties
```

schedule-tool supports two login modes. Only one mode can be selected. For parameter details, see [schedule-tool Usage Guide](#).

- When the password mode is used for login, the configuration information example is as follows:

```
[server.url = 10.10.26.187:21351,127.0.0.2:21351]
[authentication.type = kerberos]
[use.keytab = false]
[authentication.user = admin]
[authentication.password=
```



- Date format included in the file name:  
file.date.format = yyyyMMdd
  - Entered date parameter for invoking the script:  
parameter.date.format = yyyyMMdd
  - Number of delayed days.  
date.day = 1
- For example, if the input date parameter of the script is **20160220**, the result is **20160221** by using the addition.

 NOTE

If the `./run.sh 20160220 /user/loader/schedule_01` command is executed, the preceding filtering rules will be combined into a string: `"table1"+"20160221"+.txt = table120160221.txt`.

**Step 7** Select a filtering rule according to the value of **file.filter**.

- If a file is to be exactly matched, go to [Step 8](#).
- If a series of files are to be fuzzily matched, go to [Step 9](#).

**Step 8** Change the value of **file.filter** in the **job.properties** file to **false**.

Run the following commands to run the job. The task is completed.

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/schedule-tool
```

```
./run.sh 20160220 /user/loader/schedule_01
```

*20160220* indicates the input date, and */user/loader/schedule\_01* indicates the output path.

 NOTE

The string **table120160221.txt** obtained by combining the preceding filtering rules will be used as the file name and appended to the input path of the job. Therefore, the job will only process the uniquely matched file **table120160221.txt**.

**Step 9** In the **job.properties** file, change the value of **file.filter** to **true**, and set the value of **file.fileName.prefix** to **\***.

Run the following commands to run the job. The task is completed.

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/schedule-tool
```

```
./run.sh 20160220 /user/loader/schedule_01
```

*20160220* indicates the input date, and */user/loader/schedule\_01* indicates the output path.

 NOTE

The string **\*20160221.txt** obtained by combining the preceding filtering rules will be used as the fuzzy match mode of the file filter. In the input path of the job, all files matching **\*20160221.txt** will be processed by the job.

----End

## 13.8.6 Using loader-backup to Back Up Job Data

### Scenario

After a job is created using the Loader WebUI or loader-tool, use loader-backup to back up data.

#### NOTE

- Only Loader jobs of data export support data backup.
- This tool is an internal Loader interface and is invoked by the upper-layer component HBase. Only the data backup from HDFS to SFTP is supported.

### Prerequisites

The Loader client has been installed and configured. For details, see [Running a Loader Job by Using Commands](#).

### Procedure

**Step 1** Log in to the node where the client is installed as the user who installs the client. For details, see [Running a Loader Job by Using Commands](#).

**Step 2** Run the following command to go to the directory where the **backup.properties** file is located. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-backup/conf
```

**Step 3** Run the following command to modify the configuration parameters of **backup.properties**. For details about the parameters, see [Table 13-137](#).

```
vi backup.properties
```

```
server.url = 10.0.0.1:21351,10.0.0.2:12000  
authentication.type = kerberos  
authentication.user =  
authentication.password=  
job.jobId = 1  
use.keytab = true  
client.principal = loader/hadoop  
client.keytab = /opt/client/conf/loader.keytab
```

**Table 13-137** Configuration parameters

Configuration parameters	Description	Example Value
server.url	<p>Floating IP address and port (21351) for Loader.</p> <p>For compatibility, multiple IP addresses and ports can be configured and need to be separated by commas (,). The first IP address and port must be those of Loader (21351). The others can be configured based on service requirements.</p>	10.0.0.1:21351,10.0.0.2:12000
authentication.type	<p>Login authentication mode.</p> <ul style="list-style-type: none"> <li>• <b>kerberos</b> indicates that the security mode is used and Kerberos authentication is performed. Kerberos authentication provides two authentication modes: the password mode and the keytab file mode.</li> <li>• <b>simple</b> indicates that the normal mode is used and Kerberos authentication is not performed.</li> </ul>	kerberos
authentication.user	<p>User for login when the normal mode or password authentication is used.</p> <p>In the keytab login mode, this parameter does not need to be set.</p>	bar

Configuration parameters	Description	Example Value
authentication.password	<p>User password for login when the password authentication mode is used.</p> <p>In the normal mode or keytab login mode, this parameter does not need to be set.</p> <p>The password needs to be encrypted. The encryption method is described as follows:</p> <ol style="list-style-type: none"> <li>1. Go to the directory where <b>encrypt_tool</b> is located. For example, if the Loader client installation directory is <b>/opt/hadoopclient/Loader</b>, run the following command: <b>cd /opt/hadoopclient/Loader/loader-tools-1.99.3</b></li> <li>2. Run the following command to encrypt the non-encrypted password: <i>./encrypt_tool Unencrypted password</i></li> </ol> <p>The obtained encrypted password is used as the value of <b>authentication.password</b>.</p> <p><b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, <b>'1q2w#e\$r'</b>. If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.</p>	43B80E33A96DF 3D203ABBDFD10 50C041
job.jobId	<p>ID of the job whose data is to be backed up.</p> <p>Job IDs can be viewed under created jobs on the Loader web UI.</p>	1

Configuration parameters	Description	Example Value
use.keytab	Whether to use the keytab mode to log in. <ul style="list-style-type: none"> <li>• <b>true</b> indicates using the keytab file to log in.</li> <li>• <b>false</b> indicates using the password to log in.</li> </ul>	true
client.principal	User principal for accessing the Loader service when the keytab authentication mode is used. In the normal mode or password login mode, this parameter does not need to be set.	loader/hadoop
client.keytab	Directory where the used keytab file is located when the keytab authentication mode is used. In the normal mode or password login mode, this parameter does not need to be set.	/opt/client/conf/loader.keytab

**Step 4** Run the following command to go to the directory where the backup script **run.sh** is located. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-backup
```

**Step 5** Run the following command to run the backup script **run.sh** to back up Loader job data. The system backs up data to a directory at the same layer of the job output directory.

```
./run.sh Backup data input directory
```

For example, the backup data input directory is **/user/hbase/**, and the job output directory is **/opt/client/sftp/sftp1**. **sftp1** acts as a placeholder. Run the following command to back up data to the **/opt/client/sftp/hbase** directory:

```
./run.sh /user/hbase/
```

```
----End
```

## 13.8.7 Open Source sqoop-shell Tool Usage Guide

### Overview

Sqoop-shell is a shell tool of Loader. All its functions are implemented by executing the **sqoop2-shell** script.

The sqoop-shell tool provides the following functions:

- Creating and updating connectors
- Creating and updating jobs
- Deleting connectors and jobs
- Starting jobs in the synchronous or asynchronous mode.
- Stopping jobs
- Viewing job status
- Viewing historical execution records of jobs
- Cloning connectors and jobs
- Creating and updating conversion steps
- Specifying line and field separators

The sqoop-shell tool supports the following modes:

- Interaction mode  
Users execute the **sqoop2-shell** script without parameters to go to the particular interaction window of Loader. After the contents of the script are input, the tool returns the relevant information to the interaction window.
- Batch mode  
The **sqoop2-shell** script has a file name as a parameter and multiple commands are stored in lines in the file. The sqoop-shell tool runs all commands in the file in sequence by executing the script. Alternatively, users can execute the **sqoop2-shell** script, to the end of which a command is attached with the **-c** parameter as the bridge. In this case, the sqoop-shell tool runs one command each time.

The sqoop-shell implements functions of Loader by running the commands in [Table 13-138](#).

**Table 13-138** Command list

Com man d	Description
exit	Exists the interaction mode. This command is supported only in the interaction mode.
histor y	Views the executed commands. This command is supported only in the interaction mode.
help	Views the tool help information.
set	Sets server attributes.
show	Displays service attributes and all the metadata information of Loader.
creat e	Creates connectors and jobs.
updat e	Updates connectors and jobs.

Com man d	Description
delet e	Deletes connectors and jobs.
clone	Clones connectors and jobs.
start	Starts jobs.
stop	Stops jobs.
status	Views job status.

## Commands

- The sqoop2-shell tool provides two methods to obtain login authentication information. The first method is to obtain login authentication information from the configuration file. For details about the configuration items, see [Example for Using the Open-Source sqoop-shell Tool \(SFTP-HDFS\)](#) and [Example for Using the Open-Source sqoop-shell Tool \(Oracle-HBase\)](#). The second one is to obtain the authentication information by using parameters. Two modes are available in the second method: password mode and Kerberos authentication mode.

- Command for accessing the interaction mode

Execute the **sqoop2-shell** script without parameters to go to the sqoop tool window and run the commands one by one.

Run the following command to obtain the authentication information by reading the configuration file:

```
./sqoop2-shell
```

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal
```

The following information is displayed:

```
Welcome to sqoop client
Use the username and password authentication mode
Authentication success.
Sqoop Shell: Type 'help' or '\h' for help.

sqoop:000>
```

- Command for entering the batch mode

Two methods are available for accessing the batch mode.

1. Execute the **sqoop2-shell** script, in which a file name is used as a parameter and multiple commands are stored in lines in this file. The sqoop-shell tool runs all commands in the file in sequence. The script must be stored in the home directory of the current user, for example, **/root/batchCommand.sh**.

Run the following command to authenticate login by reading configuration files:

```
./sqoop2-shell /root/batchCommand.sh
```

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword /root/  
batchCommand.sh
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal /root/  
batchCommand.sh
```

*batchCommand.sh* is the user-defined name of the text file.

2. Execute the **sqoop2-shell** script, to the end of which a command is attached with the **-c** parameter as the bridge. The **sqoop-shell** tool will execute the command.

Run the following command to authenticate login by reading configuration files:

```
./sqoop2-shell -c expression
```

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword -c expression
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal -c expression
```

*expression* is the attached statement, whose format is the same as that in the text file in the first method.

- Exit command

This command is used for exiting the interaction mode and supported only in the interaction mode.

Example:

```
Welcome to sqoop client  
Use the username and password authentication mode  
Authentication success.  
Sqoop Shell: Type 'help' or '\h' for help.  
  
sqoop:000> exit  
10-5-211-9:/opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell#
```

- History command

This command is used for viewing the executed commands and supported only in the interaction mode.

Example:

```
sqoop:000> history  
0 show connector  
1 create connection -c 4  
2 show connections;  
3 show connection;  
4 show connection -a;  
5 show connections;  
6 show connection;  
7 show connection -x 53;  
8 show connection -x 52;  
9 show connection -x 2  
10 show connection -x 53;  
11 show connection  
12 show connection -x 53
```

```
13 create job -x 53 -t import
14 show connector
15 create connection -c 5
16 show connection -x 54
17 exit
18 show connector
19 create connection -c 5
20 exit
21 show connector
22 create connection -c 6
23 create job -x 20 -t import
24 start job -j 85 -s
25 \x
26 exit
27 history
sqoop:000>
```

- **Help command**

This command is used for viewing the tool help information.

Example:

```
sqoop:000> help
For information about Sqoop, visit: http://sqoop.apache.org/docs/1.99.3/index.html

Available commands:
exit (\x ) Exit the shell
history (\H ) Display, manage and recall edit-line history
help (\h ) Display this help message
set (\st ) Set server or option Info
show (\sh ) Show server, connector, framework, connection, job, submission or option Info
create (\cr ) Create connection or job Info
delete (\d ) Delete connection or job Info
update (\up ) Update connection or job Info
clone (\cl ) Clone connection or job Info
start (\sta) Start job
stop (\stp) Stop job
status (\stu) Status job

For help on a specific command type: help command

sqoop:000>
```

- **Set command**

The set command is used for setting attributes of clients and servers and supports the following attributes:

- **server** indicates setting the connection attributes for servers.

 **NOTE**

When attribute -u is set, attributes -h, -p, and -w can be ignored.

- **option** indicates setting the client attributes.

 **NOTE**

**option** can be set by key values. For example, **set option --name verbose --value true**.

Attribute Type	Subattribute	Description
server	-h,--host	Service IP address.
	-p,--port	Service Port

Attribute Type	Subattribute	Description
	-w,--webapp	Tomcat application name.
	-u,--url	Sqoop service URL.
option	verbose	Redundancy mode, which indicates that more information is printed.
	poll-timeout	Sets the polling timeout duration.

Example:

```
set option --name verbose --value false
set server --host 10.0.0.1 --port 21351 --webapp loader
```

- **show** command

This command is used for displaying information, such as variable information and storage metadata information.

Attribute Type	Subattribute	Description
server	-a,--all	Displays all server attributes.
	-p,--port	Displays the service port.
	-w,--webapp	Displays the Tomcat application name.
	-h,--host	Displays the service IP address.
option	-name	Displays the attributes of the specified name.
connector	-a,--all	Displays information about all connection types.
	-c,--cid	Displays information about the connection type of a specified ID.
framework	None.	Displays metadata information about frameworks.
connection	-a,--all	Displays all connection attributes.

Attribute Type	Subattribute	Description
	-x,--xid	Displays the attributes of a specified connection.
	-n,--name	Displays the connection attributes of a specified name.
job	-a,--all	Displays information about all jobs.
	-j,--jid	Displays job information about a specified ID.
	-n,--name	Displays job information about a specified name.
submission	-j,--jid	Displays the submission record of a specified job.
	-d,--detail	Displays details.

Example:

```
show server -all
show option --name verbose
show connector -all
show framework
show connection -all
show connection -n sftp-example
show job -all
show job -j 1
show submission --jid 1
show submission --jid 1 -d
```

- Create command

This command is used for creating connectors and jobs.

Attribute Type	Subattribute	Description
connection	-c,--cid	Specifies the ID of a connector type.
	-cn,--cname	Specifies the name of a specified connector type.
job	-x,--xid	Specifies the connector ID.
	-xn,--xname	Specifies the connector name.

Attribute Type	Subattribute	Description
	-t,--type	Specifies the job type. Possible values: <ul style="list-style-type: none"> <li>import</li> <li>export</li> </ul>

- In the interaction mode, enter the attribute values one by one as prompted.

Example for creating connectors:

```
create connection -c 1
create connection -cn example
```

Example for creating jobs:

```
create job -x 1 -t import
create job -xn job_example -t export
```

- In the batch mode, run the following command to view the specific attribute and then set a value for the attribute:

**create job -t import -x 1 --help**

You can run the above command in either of the following ways:

Save the command to a text file and attach this file to the end of the **sqoop-shell** script, and run the following command:

```
./sqoop2-shell batchCommand.sh
```

Attach a command with the **-c** parameter to the end of the **sqoop-shell** script and run the following command:

```
./sqoop2-shell -c expression
```

For details about command execution, refer to previous description in this section. The following shows two complete commands:

Example for creating connectors:

```
create connection -c 4 --connector-connection-sftpPassword xxxxx --connector-connection-sftpServerIp 10.0.0.1 --connector-connection-sftpServerPort 22 --connector-connection-sftpUser root--name testConnection
```

Example for creating jobs:

```
create job -t import -x 1 --connector-file-inputPath /opt/tempfile --connector-file-fileFilter * --framework-output-outputDirectory /user/loader/1 --framework-output-storageType HDFS --framework-throttling-extractorSize 120 --framework-output-fileType TEXT_FILE --connector-file-splitType FILE -queue default -priority low -name newJob
```

- In the batch mode, you can attach a statement using the **-c** parameter as the bridge.

Example for creating connectors:

```
./sqoop2-shell -c "create connection -c 4 --connector-connection-sftpPassword xxxxx --connector-connection-sftpServerIp 10.0.0.1 --connector-connection-sftpServerPort 22 --connector-connection-sftpUser root--name testConnection"
```

- **update** command

This command is used for updating connectors and jobs.

Attribute Type	Subattribute	Description
connection	-x,--xid	Specifies the connector ID. <b>NOTE</b> When the connectors are updated, the password must be set.
job	-j,--jid	Specifies the job ID.

– Interaction mode

Example for updating connectors:

```
update connection --xid 1
```

Example for updating jobs:

```
update job --jid 1
```

– Batch mode

Example for updating connectors:

```
update connection -x 6 --connector-connection-sftpServerPort 21 - --name sfp_130--connector-connection-sftpPassword xxxx
```

Example for updating jobs:

```
update job -jid 1 -name sftp2hdfs --connector-file-fileFilter *.txt
```

- **delete** command

This command is used for deleting connectors and jobs.

Attribute Type	Subattribute	Description
connection	-x,--xid	Specifies the connector ID.
	-n,--name	Specifies the connector name.
job	-j,--jid	Specifies the job ID.
	-n,--name	Specifies the job name.

Example:

```
delete connection -x 1
delete connection --name abc
delete job -j 1
delete job -n qwerty
```

- **clone** command

This command is used for cloning connectors and jobs.

Attribute Type	Subattribute	Description
connection	-x,--xid	Specifies the connector ID. <b>NOTE</b> The password and connector name must be entered when the connectors are cloned.
job	-j,--jid	Specifies the job ID.

Example:

```
clone job -j 1
```

- **start** command

This command is used for starting jobs.

Attribute Type	Subattribute	Description
job	-j,--jid	Specifies the job ID.
	-n,--name	Specifies the job name.
	-s,--synchronous	Whether to start jobs in the synchronous mode or not.

Example for starting jobs in the asynchronous mode:

```
start job -j 1
start job -n abc
```

Example for starting jobs in the synchronous mode:

```
start job -j 1 -s
start job --name abc --synchronous
```

- **stop** command

This command is used for stopping jobs.

Attribute Type	Subattribute	Description
job	-j,--jid	Specifies the job ID.
	-n,--name	Specifies the job name.

Example:

```
stop job -j 1
stop job -n abc
```

- **Status** command

This command is used for viewing job status.

Attribute Type	Subattribute	Description
job	-j,--jid	Specifies the job ID.

When **-s** parameter is attached to the command, the result only contains the enumerated value of job status.

Example:

```
status job -j 1
status job -j 1 -s
```

## Extended Attributes of Create Command

For the scenario in which HDFS exchanges data with the SFTP server or RDB, MRS extends the create command attributes on the basis of the open source sqoop-shell tool, so as to specify line and field separators and conversion steps when jobs are created.

**Table 13-139** Extended Attributes of Create Command

Property	Description
fields-terminated-by	Default field separator.
lines-terminated-by	Default line separator.
input-fields-terminated-by	Inputs the step field separator. If the step field separator is not specified, the value equals to <b>fields-terminated-by</b> by default.
input-lines-terminated-by	Inputs the step line separator. If the step line separator is not specified, the value equals to <b>lines-terminated-by</b> by default.
output-fields-terminated-by	Outputs the step field separator. If the step field separator is not specified, the value equals to <b>fields-terminated-by</b> by default.
output-lines-terminated-by	Outputs the step line separator. If the step line separator is not specified, the value equals to <b>lines-terminated-by</b> by default.

Property	Description
trans	Specifies the conversion steps. The value is the directory where the conversion step file is located. When the relative directory of file is specified, the file is by default stored in the directory where the <b>sqoop2-shell</b> script is located. When the attribute is set, the other extended attributes can be ignored.

## Interconnecting Sqoop1 with MRS

- Step 1** Download the open source Sqoop from <http://www.apache.org/dyn/closer.lua/sqoop/1.4.7>.
- Step 2** Save the downloaded **sqoop-1.4.7.bin\_\_hadoop-2.6.0.tar.gz** package to the **/opt/sqoop** directory on the Master node in the MRS cluster and decompress the package.

```
tar zxvf sqoop-1.4.7.bin__hadoop-2.6.0.tar.gz
```

- Step 3** Go to the directory where the package is decompressed and modify the configuration.

```
cd /opt/sqoop/sqoop-1.4.7.bin__hadoop-2.6.0/conf
```

```
cp sqoop-env-template.sh sqoop-env.sh
```

```
vi sqoop-env.sh
```

Add the following configurations:

```
export HADOOP_COMMON_HOME=/opt/client/HDFS/hadoop
```

```
export HADOOP_MAPRED_HOME=/opt/client/HDFS/hadoop
```

```
export HIVE_HOME=/opt/Bigdata/MRS_1.9.X/install/FusionInsight-Hive-3.1.0/hive  
(Enter the actual path.)
```

```
export HIVE_CONF_DIR=/opt/client/Hive/config
```

```
export HCAT_HOME=/opt/client/Hive/HCatalog
```

- Step 4** Add the system variable **SQOOP\_HOME** to **PATH**.

```
vi /etc/profile
```

Add the following information:

```
export SQOOP_HOME=/opt/sqoop/sqoop-1.4.7.bin__hadoop-2.6.0
```

```
export PATH=$PATH:$SQOOP_HOME/bin
```

- Step 5** Run the following command to copy the **jline-2.12.jar** file to the **lib** file.

```
cp /opt/share/jline-2.12/jline-2.12.jar /opt/sqoop/  
sqoop-1.4.7.bin__hadoop-2.6.0/lib
```

**Step 6** Run the following command to add the following configuration to the file.

```
vim $JAVA_HOME/jre/lib/security/java.policy  
  
permission javax.management.MBeanTrustPermission "register";
```

**Step 7** Run the following command to interconnect sqoop1 with MRS.

```
source /etc/profile  
  
----End
```

## 13.8.8 Example for Using the Open-Source sqoop-shell Tool (SFTP-HDFS)

### Scenario

Taking importing data from SFTP to HDFS as an example, this section introduces how to use the sqoop-shell tool to create and start Loader jobs in the interaction mode and batch mode.

### Prerequisites

The Loader client has been installed and configured. For details, see [Running a Loader Job by Using Commands](#).

### Example for the Interaction Mode

**Step 1** Log in to the node where the Loader client is installed as the user who installs the client.

**Step 2** Run the following command to go to the **conf** directory of the sqoop-shell tool. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell/conf
```

**Step 3** Run the following command to configure authentication information:

```
vi client.properties  
server.url=10.0.0.1:21351  
# simple or kerberos  
authentication.type=simple  
# true or false  
use.keytab=true  
  
authentication.user=  
authentication.password=  
  
client.principal=hdfs/hadoop@<system domain name>  
  
# keytab file  
client.keytab.file=./conf/login/hdfs.keytab
```

 NOTE

Log in to FusionInsight Manager and choose **System > Permission > Domain and Mutual Trust**. The value of **Local Domain** is the current system domain name.

**Table 13-140** Configuration parameters

Configuration parameters	Description	Example Value
server.url	Floating IP address and port (21351) for Loader.  For compatibility, multiple IP addresses and ports can be configured and need to be separated by commas (,). The first IP address and port must be those of Loader (21351). The others can be configured based on service requirements.	10.0.0.1:21351
authentication.type	Login authentication mode. <ul style="list-style-type: none"> <li>• <b>kerberos</b> indicates that the security mode is used and Kerberos authentication is performed. Kerberos authentication provides two authentication modes: the password mode and the keytab file mode.</li> <li>• <b>simple</b> indicates that the normal mode is used and Kerberos authentication is not performed.</li> </ul>	kerberos
authentication.user	User for login when the normal mode or password authentication is used.  In the keytab login mode, this parameter does not need to be set.	bar

Configuration parameters	Description	Example Value
<p>authentication.password</p>	<p>User password for login when the password authentication mode is used.</p> <p>In the normal mode or keytab login mode, this parameter does not need to be set.</p> <p>The password needs to be encrypted. The encryption method is described as follows:</p> <ol style="list-style-type: none"> <li>1. Go to the directory where <b>encrypt_tool</b> is located. For example, if the Loader client installation directory is <b>/opt/hadoopclient/Loader</b>, run the following command: <b>cd /opt/hadoopclient/Loader/loader-tools-1.99.3</b></li> <li>2. Run the following command to encrypt the non-encrypted password: <i>./encrypt_tool Unencrypted password</i></li> </ol> <p>The obtained encrypted password is used as the value of <b>authentication.password</b>.</p> <p><b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, <b>'1q2w#e\$r'</b>. If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.</p>	<p>43B80E33A96DF 3D203ABBDFD10 50C041</p>

Configuration parameters	Description	Example Value
use.keytab	Whether to use the keytab mode to log in. <ul style="list-style-type: none"> <li>• <b>true</b> indicates using the keytab file to log in.</li> <li>• <b>false</b> indicates using the password to log in.</li> </ul>	true
client.principal	User principal for accessing the Loader service when the keytab authentication mode is used. In the normal mode or password login mode, this parameter does not need to be set.	loader/hadoop
client.keytab.file	Directory where the used keytab file is located when the keytab authentication mode is used. In the normal mode or password login mode, this parameter does not need to be set.	/opt/client/conf/loader.keytab

**Step 4** Run the following command to go to the interaction mode:

```
source /opt/hadoopclient/bigdata_env
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell
./sqoop2-shell
```

The preceding commands obtain authentication information by reading the configuration file.

Alternatively, you can also use the password or Kerberos authentication.

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal
```

```
Welcome to sqoop client
Use the username and password authentication mode
Authentication success.
Sqoop Shell: Type 'help' or '\h' for help.
sqoop:000>
```

**Step 5** Run the following command to view the corresponding ID of the current connector:

```
show connector
```

The following information is displayed:

Id	Name	Version	Class
1	generic-jdbc-connector	2.0.6-SNAPSHOT	org.apache.sqoop.connector.jdbc.GenericJdbcConnector
2	ftp-connector	2.0.5-SNAPSHOT	org.apache.sqoop.connector.ftp.FtpConnector
3	hdfs-connector	2.0.5-SNAPSHOT	org.apache.sqoop.connector.hdfs.HdfsConnector
4	oracle-connector	2.0.1-SNAPSHOT	org.apache.sqoop.connector.oracle.OracleConnector
5	mysql-fastpath-connector	2.0.1-SNAPSHOT	org.apache.sqoop.connector.mysql.MySqlConnector
6	<b>sftp-connector</b>	<b>2.0.5-SNAPSHOT</b>	<b>org.apache.sqoop.connector.sftp.SftpConnector</b>
7	oracle-partition-connector	2.0.6-SNAPSHOT	org.apache.sqoop.connector.oracle.partition.OraclePartitionConnector

The preceding information indicates that the SFTP connector ID is 6.

**Step 6** Run the following command to create connectors and enter the specific connector information as prompted:

**create connection -c *connector ID***

For example, if the connector ID is 6, run the following command:

**create connection -c 6**

```
sqoop:000> create connection -c 6
Creating connection for connector with id 6
Please fill following values to create new connection object
Name: sftp14

Connection configuration

Sftp server IP: 10.0.0.1
Sftp server port: 22
Sftp user name: root
Sftp password: *****
Sftp public key:
New connection was successfully created with validation status FINE and persistent id 20
sqoop:000>
```

The preceding information indicates that the connection ID is 20.

**Step 7** Based on the connection ID, run the following command to create jobs:

**create job -x *connection ID* -t import**

For example, if the connection ID is 20, run the following command:

**create job -x 20 -t import**

The following information is displayed:

```
Creating job for connection with id 20
Please fill following values to create new job object
Name: sftp-hdfs-test

File configuration

Input path: /opt/tempfile
File split type:
0 : FILE
1 : SIZE
Choose: 0
```

```
Filter type:
 0 : WILDCARD
 1 : REGEX
Choose: 0
Path filter: *
File filter: *
Encode type:
Suffix name:
Compression:

Output configuration

Storage type:
 0 : HDFS
 1 : HBASE_BULKLOAD
 2 : HBASE_PUTLIST
 3 : HIVE
Choose: 0
File type:
 0 : TEXT_FILE
 1 : SEQUENCE_FILE
 2 : BINARY_FILE
Choose: 0
Compression format:
 0 : NONE
 1 : DEFAULT
 2 : DEFLATE
 3 : GZIP
 4 : BZIP2
 5 : LZ4
 6 : SNAPPY
Choose:
Output directory: /user/loader/test
File operate type:
 0 : OVERRIDE
 1 : RENAME
 2 : APPEND
 3 : IGNORE
 4 : ERROR
Choose: 0

Throttling resources

Extractors: 2
Extractor size:
New job was successfully created with validation status FINE and persistent id 85
sqoop:000>
```

The preceding information indicates that the job ID is 85.

**Step 8** Run the following command to start the job:

```
start job -j job ID -s
```

For example, if the job ID is 85, run the following command:

```
start job -j 85 -s
```

Displaying the **SUCCEEDED** information indicates that the job is started successfully.

```
Submission details
Job ID: 85
Server URL: https://10.0.0.0:21351/loader/
Created by: admin
Creation date: 2016-07-20 16:25:38 GMT+08:00
Lastly updated by: admin
2016-07-20 16:25:38 GMT+08:00: BOOTING - Progress is not available
2016-07-20 16:25:46 GMT+08:00: BOOTING - 0.00 %
2016-07-20 16:25:53 GMT+08:00: BOOTING - 0.00 %
```

```
2016-07-20 16:26:08 GMT+08:00: RUNNING - 90.00 %
2016-07-20 16:26:08 GMT+08:00: RUNNING - 90.00 %
2016-07-20 16:26:27 GMT+08:00: SUCCEEDED
```

----End

## Example for the Batch Mode

**Step 1** Log in to the node where the Loader client is installed as the user who installs the client.

**Step 2** Run the following command to go to the **conf** directory of the sqoop-shell tool. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell/conf
```

**Step 3** Run the following command to configure authentication information:

```
vi client.properties
server.url= 10.0.0.1:21351
# simple or kerberos
authentication.type=simple
# true or false
use.keytab=true

authentication.user=
authentication.password=

client.principal=hdfs/hadoop@<system domain name>

# keytab file
client.keytab.file=./conf/login/hdfs.keytab
```

**Table 13-141** Configuration parameters

Configuration parameters	Description	Example Value
server.url	Floating IP address and port (21351) for Loader. For compatibility, multiple IP addresses and ports can be configured and need to be separated by commas (,). The first IP address and port must be those of Loader (21351). The others can be configured based on service requirements.	10.0.0.1:21351

Configuration parameters	Description	Example Value
authentication.type	<p>Login authentication mode.</p> <ul style="list-style-type: none"><li>• <b>kerberos</b> indicates that the security mode is used and Kerberos authentication is performed. Kerberos authentication provides two authentication modes: the password mode and the keytab file mode.</li><li>• <b>simple</b> indicates that the normal mode is used and Kerberos authentication is not performed.</li></ul>	kerberos
authentication.user	<p>User for login when the normal mode or password authentication is used.</p> <p>In the keytab login mode, this parameter does not need to be set.</p>	bar

Configuration parameters	Description	Example Value
<p>authentication.password</p>	<p>User password for login when the password authentication mode is used.</p> <p>In the normal mode or keytab login mode, this parameter does not need to be set.</p> <p>The password needs to be encrypted. The encryption method is described as follows:</p> <ol style="list-style-type: none"> <li>1. Go to the directory where <b>encrypt_tool</b> is located. For example, if the Loader client installation directory is <b>/opt/hadoopclient/Loader</b>, run the following command: <b>cd /opt/hadoopclient/Loader/loader-tools-1.99.3</b></li> <li>2. Run the following command to encrypt the non-encrypted password: <i>./encrypt_tool Unencrypted password</i></li> </ol> <p>The obtained encrypted password is used as the value of <b>authentication.password</b>.</p> <p><b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, <b>'1q2w#e\$r'</b>. If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.</p>	<p>43B80E33A96DF 3D203ABBDFD10 50C041</p>

Configuration parameters	Description	Example Value
use.keytab	Whether to use the keytab mode to log in. <ul style="list-style-type: none"> <li>• <b>true</b> indicates using the keytab file to log in.</li> <li>• <b>false</b> indicates using the password to log in.</li> </ul>	true
client.principal	User principal for accessing the Loader service when the keytab authentication mode is used.  In the normal mode or password login mode, this parameter does not need to be set.	loader/hadoop
client.keytab.file	Directory where the used keytab file is located when the keytab authentication mode is used.  In the normal mode or password login mode, this parameter does not need to be set.	/opt/client/conf/loader.keytab

**Step 4** Run the following command to go to the directory where the **sqoop2-shell** script is located and create a text file in the directory, such as **batchCommand.sh**:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell
```

```
vi batchCommand.sh
```

An example of **batchCommand.sh** is displayed as follows:

```
View parameters
create connection -c 6 --help

// Create a connector
create connection -c 6 -name sftp-connection --connector-connection-sftpServerIp 10.0.0.1 --connector-connection-sftpServerPort 22 --connector-connection-sftpUser root --connector-connection-sftpPassword
xxxxx

Create a job
create job -t import -x 20 --connector-file-inputPath /opt/tempfile --connector-file-fileFilter * --framework-output-outputDirectory /user/loader/1 --framework-output-storageType HDFS --framework-throttling-extractorSize 120 --framework-output-fileType TEXT_FILE --connector-file-splitType FILE -name test

Start a job
start job -j 85 -s
```

xxxxx is the password for the connector.

**Step 5** Run the following command and the sqoop-shell tool will run the preceding commands in sequence:

```
./sqoop2-shell batchCommand.sh
```

The commands above authenticate login by reading configuration files. Alternatively, you can attach the authentication information to the command, that is, use the password mode or Kerberos mode to authenticate login.

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword  
batchCommand.sh
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal batchCommand.sh
```

Displaying the **SUCCEEDED** information indicates that the job is started successfully.

```
Welcome to sqoop client
Use the username and password authentication mode
Authentication success.
sqoop:000> create connection -c 6 --help
usage: Show connection parameters:
  --connector-connection-sftpPassword <arg>
  --connector-connection-sftpServerIp <arg>
  --connector-connection-sftpServerPort <arg>
  --connector-connection-sftpUser <arg>
  --framework-security-maxConnections <arg>
  --name <arg>
====> FINE
sqoop:000> create connection -c 6 -name sftp-connection --connector-connection-sftpServerIp 10.0.0.1 --
connector-connection-sftpServerPort 22 --connector-connection-sftpUser root --connector-connection-
sftpPassword xxxxx
Creating connection for connector with id 6
New connection was successfully created with validation status FINE and persistent id 20
====> FINE
sqoop:000> create job -t import -x 20 --connector-file-inputPath /opt/tempfile --connector-file-fileFilter * --
framework-output-outputDirectory /user/loader/1 --framework-output-storageType HDFS --framework-
throttling-extractorSize 120 --framework-output-fileType TEXT_FILE --connector-file-splitType FILE -name
test
Creating job for connection with id 20
New job was successfully created with validation status FINE and persistent id 85
====> FINE

Submission details
Job ID: 85
Server URL: https://10.0.0.0:21351/loader/
Created by: admin
Creation date: 2016-07-20 16:25:38 GMT+08:00
Lastly updated by: admin
2016-07-20 16:25:38 GMT+08:00: BOOTING - Progress is not available
2016-07-20 16:25:46 GMT+08:00: BOOTING - 0.00 %
2016-07-20 16:25:53 GMT+08:00: BOOTING - 0.00 %
2016-07-20 16:26:08 GMT+08:00: RUNNING - 90.00 %
2016-07-20 16:26:08 GMT+08:00: RUNNING - 90.00 %
2016-07-20 16:26:27 GMT+08:00: SUCCEEDED
```

**Step 6** In the batch mode, the **-c** parameter can be used to attach a command. sqoop-shell can execute only the attached command at a time.

Run the following command to create a connection:

```
./sqoop2-shell -c "create connection -c 6 -name sftp-connection --connector-
connection-sftpServerIp 10.0.0.1 --connector-connection-sftpServerPort 22 --
connector-connection-sftpUser root --connector-connection-sftpPassword
xxxxx"
```

You can also use the password mode or Kerberos mode to attach the authentication information to the command.

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword -c "create connection -c 6 -name sftp-connection --connector-connection-sftpServerIp 10.0.0.1 --connector-connection-sftpServerPort 22 --connector-connection-sftpUser root --connector-connection-sftpPassword xxxxx"
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal -c "create connection -c 6 -name sftp-connection --connector-connection-sftpServerIp 10.0.0.1 --connector-connection-sftpServerPort 22 --connector-connection-sftpUser root --connector-connection-sftpPassword xxxxx"
```

Displaying the **FINE** information indicates the connection is created successfully.

```
Welcome to sqoop client
Use the username and password authentication mode
Authentication success.
sqoop:000> create connection -c 6 -name sftp-connection --connector-connection-sftpServerIp 10.0.0.1 --connector-connection-sftpServerPort 22 --connector-connection-sftpUser root --connector-connection-sftpPassword xxxxx
Creating connection for connector with id 6
New connection was successfully created with validation status FINE and persistent id 20
====> FINE
```

----End

## 13.8.9 Example for Using the Open-Source sqoop-shell Tool (Oracle-HBase)

### Scenario

Taking **Importing Data from Oracle to HBase** as an example, this section introduces how to use the sqoop-shell tool to create and start Loader jobs in the interaction mode and batch mode.

### Prerequisites

The Loader client has been installed and configured. For details, see [Running a Loader Job by Using Commands](#).

### Example for the Interaction Mode

**Step 1** Log in to the node where the Loader client is installed as the user who installs the client.

**Step 2** Run the following command to go to the **conf** directory of the sqoop-shell tool. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell/conf
```

**Step 3** Run the following command to configure authentication information:

```
vi client.properties
```

```
server.url=10.0.0.1:21351
# simple or kerberos
```

```
authentication.type=simple
# true or false
use.keytab=true

authentication.user=
authentication.password=

client.principal=oracle/hadoop@<system domain name>

# keytab file
client.keytab.file=./conf/login/oracle.keytab
```

 **NOTE**

Log in to FusionInsight Manager and choose **System > Permission > Domain and Mutual Trust**. The value of **Local Domain** is the current system domain name.

**Table 13-142** Configuration parameters

Configuration parameters	Description	Example Value
server.url	Floating IP address and port (21351) for Loader.  For compatibility, multiple IP addresses and ports can be configured and need to be separated by <b>commas (,)</b> . The first IP address and port must be those of Loader (21351). The others can be configured based on service requirements.	10.0.0.1:21351
authentication.type	Login authentication mode. <ul style="list-style-type: none"><li>• <b>kerberos</b> indicates that the security mode is used and Kerberos authentication is performed. Kerberos authentication provides two authentication modes: the password mode and the keytab file mode.</li><li>• <b>simple</b> indicates that the normal mode is used and Kerberos authentication is not performed.</li></ul>	kerberos
authentication.user	User for login when the normal mode or password authentication is used.  In the keytab login mode, this parameter does not need to be set.	bar

Configuration parameters	Description	Example Value
<p>authentication.password</p>	<p>User password for login when the password authentication mode is used.</p> <p>In the normal mode or keytab login mode, this parameter does not need to be set.</p> <p>The password needs to be encrypted. The encryption method is described as follows:</p> <ol style="list-style-type: none"> <li>1. Go to the directory where <b>encrypt_tool</b> is located. For example, if the Loader client installation directory is <b>/opt/hadoopclient/Loader</b>, run the following command: <b>cd /opt/hadoopclient/Loader/loader-tools-1.99.3</b></li> <li>2. Run the following command to encrypt the non-encrypted password: <i>./encrypt_tool Unencrypted password</i></li> </ol> <p>The obtained encrypted password is used as the value of <b>authentication.password</b>.</p> <p><b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, <b>'1q2w#e\$r'</b>. If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.</p>	<p>43B80E33A96DF 3D203ABBDFD10 50C041</p>

Configuration parameters	Description	Example Value
use.keytab	Whether to use the keytab mode to log in. <ul style="list-style-type: none"> <li>• <b>true</b> indicates using the keytab file to log in.</li> <li>• <b>false</b> indicates using the password to log in.</li> </ul>	true
client.principal	User principal for accessing the Loader service when the keytab authentication mode is used. In the normal mode or password login mode, this parameter does not need to be set.	loader/hadoop
client.keytab.file	Directory where the used keytab file is located when the keytab authentication mode is used. In the normal mode or password login mode, this parameter does not need to be set.	/opt/client/conf/loader.keytab

**Step 4** Run the following command to go to the interaction mode:

```
source /opt/hadoopclient/bigdata_env
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell
./sqoop2-shell
```

The preceding commands obtain authentication information by reading the configuration file.

Alternatively, you can also use the password or Kerberos authentication.

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal
```

```
Welcome to sqoop client
Use the username and password authentication mode
Authentication success.
Sqoop Shell: Type 'help' or '\h' for help.
sqoop:000>
```

**Step 5** Run the following command to view the corresponding ID of the current connector:

```
show connector
```

The following information is displayed:

Id	Name	Version	Class
1	generic-jdbc-connector	2.0.7-SNAPSHOT	org.apache.sqoop.connector.jdbc.GenericJdbcConnector
2	ftp-connector	2.0.5-SNAPSHOT	org.apache.sqoop.connector.ftp.FtpConnector
3	hdfs-connector	2.0.5-SNAPSHOT	org.apache.sqoop.connector.hdfs.HdfsConnector
4	<b>oracle-connector</b>	<b>2.0.1-SNAPSHOT</b>	<b>org.apache.sqoop.connector.oracle.OracleConnector</b>
5	mysql-fastpath-connector	2.0.1-SNAPSHOT	org.apache.sqoop.connector.mysql.MySqlConnector
6	sftp-connector	2.0.6-SNAPSHOT	org.apache.sqoop.connector.sftp.SftpConnector
7	oracle-partition-connector	2.0.6-SNAPSHOT	org.apache.sqoop.connector.oracle.partition.OraclePartitionConnector

The preceding information indicates that the Oracle connector ID is 4.

**Step 6** Run the following command to create connectors and enter the specific connector information as prompted:

**create connection -c *connector ID***

For example, if the connector ID is 4, run the following command:

**create connection -c 4**

```
sqoop:000> create connection -c 4
Creating connection for connector with id 4
Please fill following values to create new connection object
Name: oracle14

Oracle connection configuration

JDBC connection string: jdbc:oracle:thin:@189.120.84.106:1521:orcl
Username: oracledba
Password: *****
JDBC connection properties:
There are currently 0 values in the map:
entry#
New connection was successfully created with validation status FINE and persistent id 3
sqoop:000>
```

The preceding information indicates that the connection ID is 3.

**Step 7** Based on the connection ID, run the following command to create jobs:

**create job -x *connection ID* -t import --trans *absolute path of job-config/oracle-hbase.json***

For example, if the connection ID is 3, run the following command:

**create job -x 3 -t import --trans /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/oracle-hbase.json**

The following information is displayed:

```
sqoop:000> create job -x 3 -t import --trans /opt/hadoopclient/Loader/loader-tools-1.99.3/loader-tool/job-config/oracle-to-hbase.json
Creating job for connection with id 3
Please fill following values to create new job object
Name: run

Database target

Table name: test
```

```
Columns:
Conditions:
Data split method:
 0 : ROWID
 1 : PARTITION
Choose:
Table Partitions:
Data split allocation method:
 0 : ROUNDROBIN
 1 : SEQUENTIAL
 2 : RANDOM
Choose:
JDBC fetch size:

Output configuration

Storage type:
 0 : HDFS
 1 : HBASE_BULKLOAD
 2 : HBASE_PUTLIST
 3 : HIVE
 4 : SPARK
Choose: 1
HBase instance: HBase
Clear data before import : false

Throttling resources

Extractors: 10
Extractor size:
New job was successfully created with validation status FINE and persistent id 7
sqoop:000>
```

The preceding information indicates that the job ID is 7.

**Step 8** Run the following command to start the job:

```
start job -j job ID -s
```

For example, if the job ID is 7, run the following command:

```
start job -j 7 -s
```

Displaying the **SUCCEEDED** information indicates that the job is started successfully.

```
Submission details
Job ID: 7
Server URL: https://10.0.0.0:21351/loader/
Created by: admintest
Creation date: 2019-12-04 16:37:34 CST
Lastly updated by: admintest
2019-12-04 16:37:34 CST: BOOTING - Progress is not available
2019-12-04 16:37:42 CST: BOOTING - 0.00 %
2019-12-04 16:37:57 CST: RUNNING - 0.00 %
2019-12-04 16:38:12 CST: RUNNING - 45.00 %
2019-12-04 16:38:12 CST: RUNNING - 45.00 %
2019-12-04 16:38:27 CST: SUCCEEDED
```

----End

## Example for the Batch Mode

**Step 1** Log in to the node where the Loader client is installed as the user who installs the client.

**Step 2** Run the following command to go to the **conf** directory of the sqoop-shell tool. For example, if the Loader client installation directory is **/opt/hadoopclient/Loader**, run the following command:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell/conf
```

**Step 3** Run the following command to configure authentication information:

```
vi client.properties
```

```
server.url=10.0.0.1:21351
# simple or kerberos
authentication.type=simple
# true or false
use.keytab=true

authentication.user=
authentication.password=

client.principal=hdfs/hadoop.<system domain name>@<system domain name>

# keytab file
client.keytab.file=./conf/login/hdfs.keytab
```

**Table 13-143** Configuration parameters

Configuration parameters	Description	Example Value
server.url	Floating IP address and port (21351) for Loader. For compatibility, multiple IP addresses and ports can be configured and need to be separated by <b>commas (,)</b> . The first IP address and port must be those of Loader (21351). The others can be configured based on service requirements.	10.0.0.1:21351
authentication.type	Login authentication mode. <ul style="list-style-type: none"> <li>• <b>kerberos</b> indicates that the security mode is used and Kerberos authentication is performed. Kerberos authentication provides two authentication modes: the password mode and the keytab file mode.</li> <li>• <b>simple</b> indicates that the normal mode is used and Kerberos authentication is not performed.</li> </ul>	kerberos

<b>Configuration parameters</b>	<b>Description</b>	<b>Example Value</b>
authentication.user	User for login when the normal mode or password authentication is used. In the keytab login mode, this parameter does not need to be set.	bar

Configuration parameters	Description	Example Value
<p>authentication.password</p>	<p>User password for login when the password authentication mode is used.</p> <p>In the normal mode or keytab login mode, this parameter does not need to be set.</p> <p>The password needs to be encrypted. The encryption method is described as follows:</p> <ol style="list-style-type: none"> <li>1. Go to the directory where <b>encrypt_tool</b> is located. For example, if the Loader client installation directory is <b>/opt/hadoopclient/Loader</b>, run the following command: <b>cd /opt/hadoopclient/Loader/loader-tools-1.99.3</b></li> <li>2. Run the following command to encrypt the non-encrypted password: <i>./encrypt_tool Unencrypted password</i></li> </ol> <p>The obtained encrypted password is used as the value of <b>authentication.password</b>.</p> <p><b>NOTE</b> If a non-encrypted password contains special characters, the special characters must be escaped. For example, the dollar sign (\$) is a special character and can be escaped using single quotation marks ('), for example, <b>'1q2w#e\$r'</b>. If a non-encrypted password contains single quotation marks, use double quotation marks to escape the single quotation marks. If a non-encrypted password contains double quotation marks, use backslashes (\) to escape the double quotation marks. For details, see the shell escape character rules.</p>	<p>43B80E33A96DF 3D203ABBDFD10 50C041</p>

Configuration parameters	Description	Example Value
use.keytab	Whether to use the keytab mode to log in. <ul style="list-style-type: none"> <li>• <b>true</b> indicates using the keytab file to log in.</li> <li>• <b>false</b> indicates using the password to log in.</li> </ul>	true
client.principal	User principal for accessing the Loader service when the keytab authentication mode is used. In the normal mode or password login mode, this parameter does not need to be set.	loader/hadoop
client.keytab.file	Directory where the used keytab file is located when the keytab authentication mode is used. In the normal mode or password login mode, this parameter does not need to be set.	/opt/client/conf/loader.keytab

**Step 4** Run the following command to go to the directory where the **sqoop2-shell** script is located and create a text file in the directory, such as **batchCommand.sh**:

```
cd /opt/hadoopclient/Loader/loader-tools-1.99.3/sqoop-shell
```

```
vi batchCommand.sh
```

An example of **batchCommand.sh** is displayed as follows:

```
View parameters
create connection -c 4 --help

// Create a connector
create connection -c 4 -name oracle-connection --connector-connection-oracleServerIp 10.0.0.1 --connector-connection-oracleServerPort 22 --connector-connection-oracleUser root --connector-connection-oraclePassword xxxxx

Create a job
create job -t import -x 3 --connector-file-inputPath /opt/tempfile --connector-file-fileFilter * --framework-output-outputDirectory /user/loader/1 --framework-output-storageType HBase --framework-throttling-extractorSize 120 --framework-output-fileType TEXT_FILE --connector-file-splitType FILE -name test

Start a job
start job -j 7 -s
```

xxxxx is the password for the connector.

**Step 5** Run the following command and the sqoop-shell tool will run the preceding commands in sequence:

```
./sqoop2-shell batchCommand.sh
```

The commands above authenticate login by reading configuration files. Alternatively, you can attach the authentication information to the command, that is, use the password mode or Kerberos mode to authenticate login.

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword  
batchCommand.sh
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal batchCommand.sh
```

Displaying the **SUCCEEDED** information indicates that the job is started successfully.

```
Welcome to sqoop client
Use the username and password authentication mode
Authentication success.
sqoop:000> create connection -c 4 --help
usage: Show connection viparameters:
  --connector-connection-oraclePassword <arg>
  --connector-connection-oracleServerIp <arg>
  --connector-connection-oracleServerPort <arg>
  --connector-connection-oracleUser <arg>
  --framework-security-maxConnections <arg>
  --name <arg>
====> FINE
sqoop:000> create connection -c 4 -name oracle-connection --connector-connection-oracleServerIp 10.0.0.1
--connector-connection-oracleServerPort 22 --connector-connection-oracleUser root --connector-connection-
oraclePassword xxxxx
Creating connection for connector with id 4
New connection was successfully created with validation status FINE and persistent id 3
====> FINE
sqoop:000> create job -t import -x 3 --connector-file-inputPath /opt/tempfile --connector-file-fileFilter * --
framework-output-outputDirectory /user/loader/1 --framework-output-storageType HDFS --framework-
throttling-extractorSize 120 --framework-output-fileType TEXT_FILE --connector-file-splitType FILE -name
test
Creating job for connection with id 3
New job was successfully created with validation status FINE and persistent id 7
====> FINE
Submission details
Job ID: 7
Server URL: https://10.0.0.0:21351/loader/
Created by: admintest
Creation date: 2019-12-04 16:37:34 CST
Lastly updated by: admintest
2019-12-04 16:37:34 CST: BOOTING - Progress is not available
2019-12-04 16:37:42 CST: BOOTING - 0.00 %
2019-12-04 16:37:42 CST: BOOTING - 0.00 %
2019-12-04 16:37:57 CST: RUNNING - 0.00 %
2019-12-04 16:38:12 CST: RUNNING - 45.00 %
2019-12-04 16:38:12 CST: RUNNING - 45.00 %
2019-12-04 16:38:27 CST: SUCCEEDED
```

**Step 6** In the batch mode, the **-c** parameter can be used to attach a command. sqoop-shell can execute only the attached command at a time.

Run the following command to create a connection:

```
./sqoop2-shell -c "create connection -c 4 -name oracle-connection --  
connector-connection-oracleServerIp 10.0.0.1 --connector-connection-  
oracleServerPort 22 --connector-connection-oracleUser root --connector-  
connection-oraclePassword xxxxx"
```

You can also use the password mode or Kerberos mode to attach the authentication information to the command.

Run the following command to authenticate login using the password mode:

```
./sqoop2-shell -uk false -u username -p encryptedPassword -c "create connection -c 4 -name oracle-connection --connector-connection-oracleServerIp 10.0.0.1 --connector-connection-oracleServerPort 22 --connector-connection-oracleUser root --connector-connection-oraclePassword xxxxx"
```

Run the following command to authenticate login using the Kerberos mode:

```
./sqoop2-shell -uk true -k user.keytab -s userPrincipal -c "create connection -c 4 -name oracle-connection --connector-connection-oracleServerIp 10.0.0.1 --connector-connection-oracleServerPort 22 --connector-connection-oracleUser root --connector-connection-oraclePassword xxxxx"
```

Displaying the **FINE** information indicates the connection is created successfully.

```
Welcome to sqoop client
Use the username and password authentication mode
Authentication success.
sqoop:000> create connection -c 4 -name oracle-connection --connector-connection-oracleServerIp 10.0.0.1
--connector-connection-oracleServerPort 22 --connector-connection-oracleUser root --connector-connection-
oraclePassword xxxxx
Creating connection for connector with id 4
New connection was successfully created with validation status FINE and persistent id 3
====> FINE
```

----End

## 13.9 Loader Log Overview

### Log Description

**Log path:** The default storage path of Loader log files is **/var/log/Bigdata/loader/Log category**.

- runlog: /var/log/Bigdata/loader/runlog (run logs)
- scriptlog: /var/log/Bigdata/loader/scriptlog/ (script execution logs)
- catalina: /var/log/Bigdata/loader/catalina (Tomcat startup and stop logs)
- audit: /var/log/Bigdata/loader/audit (audit logs)

**Log archive rule:**

The automatic compression and archiving function are enabled for Loader run logs and audit logs. By default, when the size of a log file exceeds 10 MB, the log file is automatically compressed into a log file named in the following rule: *<Original log file name>-<yyyymm-dd\_hh-mm-ss>.[ID].log.zip*. A maximum of 20 latest compressed files are reserved. The number of compressed files can be configured on the Manager portal.

**Table 13-144** Loader log list

Log Type	Log File Name	Description
Run log	loader.log	Loader system log file that records most of the logs generated when the TelcoFS system is running.
	loader-omm-***-pid***-gc.log.*.current	Loader process GC log file
	sqoopInstanceCheck.log	Loader instance health check log file
Audit log	default.audit	Loader operation audit log file that records operations such as adding, deleting, modifying, and querying jobs and user login
Tomcat log	catalina.out	Tomcat run log file.
	catalina. <yyyy-mm-dd >.log	Tomcat run log file
	host-manager. <yyyy-mm-dd >.log	Tomcat run log file
	localhost_access_log. <yyyy-mm-dd >.txt	Tomcat run log file
	manager <yyyy-mm-dd >.log	Tomcat run log file
	localhost. <yyyy-mm-dd >.log	Tomcat run log file
Script log	postInstall.log	Loader installation script log file Log file generated during the execution of the Loader installation script ( <b>postInstall.sh</b> )
	preStart.log	Pre-startup script log file of the Loader service During startup of the Loader service, a series of preparation operations are first performed (by executing <b>preStart.sh</b> ), such as generating the keytab file. This log file records information about these operations

Log Type	Log File Name	Description
	loader_ctl.log	Log file generated when Loader executes the service start and stop script ( <b>sqoop.sh</b> )

## Log Level

**Table 13-145** describes the log levels provided by Loader. The priorities of log levels are ERROR, WARN, INFO, and DEBUG in descending order. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 13-145** Log levels

Level	Description
ERROR	Error information about the current event processing.
WARN	Exception information about the current event processing.
INFO	Normal running status information about the system and events.
DEBUG	System information and system debugging information.

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of Loader by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** On the menu bar on the left, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Save the configuration. In the displayed dialog box, click **OK** to make the configurations take effect.

 **NOTE**

The configurations take effect immediately without the need to restart the service.

----End

## Log Formats

The following table lists the Loader log formats.

**Table 13-146** Log formats

Log Type	Format	Example
Run log	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> <Thread that generates the log> <Message in the log> <Location of the log event>	2015-06-29 14:54:35,553   INFO   [localhost-startStop-1]   ConnectionRequestHandler initialized   org.apache.sqoop.handler.ConnectionRequestHandler.<init>(ConnectionRequestHandler.java:100)
Audit log	<yyyy-MM-dd HH:mm:ss,SSS> <Log Level> default <Message in the log> <Location of the log event>	2015-06-29 15:35:40,969 INFO default: UserName=admin, UserIP=10.52.0.111, Time=2015-06-29 15:35:40,969, Operation=submit, Resource=submission@21, Result=Failure, Detail={[reason:GET_SFTP_SESSION_FAILED:Failed to get sftp session - 10.162.0.35 (caused by: Auth cancel) ]; [config:null]}

## 13.10 Common Issues About Loader


### 13.10.1 How to Resolve the Problem that Failed to Save Data When Using Internet Explorer 10 or Internet Explorer 11 ?

#### Question

Internet Explorer 11 or Internet Explorer 10 is used to access the web UI of Loader. After data is submitted, an error occurs.

#### Answer

- Symptom
  - a. When the submitted data is saved, a similar error occurs.



- Cause  
Some Internet Explorer 11 versions convert POST requests into GET requests after receiving the HTTP 307 response. As a result, POST data cannot be delivered to the server.
- Solution  
Use Google Chrome.

## 13.10.2 Differences Among Connectors Used During the Process of Importing Data from the Oracle Database to HDFS

### Question

Three types of connectors are available for importing data from the Oracle database to HDFS using Loader. That is, generic-jdbc-connector, oracle-connector, and oracle-partition-connector. Which one should I select? What are the differences between them?

### Answers

- generic-jdbc-connector  
Reads data from the Oracle database in JDBC mode. It is applicable to databases that support JDBC.  
In this mode, data loading performance of Loader is subject to data distribution in a partition column. When data skew occurs (data has only one value or several values) in a partition column, a few Maps process a significant portion of data. As a result, the index becomes invalid, causing a sharp decline in SQL query performance.  
**generic-jdbc-connector** supports view import and export, but oracle-partition-connector and oracle-connector do not support. Therefore, only this connector can be used to import views.
- Both **oracle-partition-connector** and **oracle-connector**  
can use the ROWID of Oracle for partitioning. oracle-partition-connector is self-developed and oracle-connector is an open-source edition. The two types of connectors share similar performance.

**oracle-connector** requires more system table permissions. The following lists the read permissions required by the system tables of **oracle-connector** and **oracle-connector**.

- **oracle-connector**: dba\_tab\_partitions, dba\_constraints, dba\_tables t, dba\_segments, v\$instance, dba\_objects, v\$instance, SYS\_CONTEXT function, dba\_extents, and dba\_tab\_subpartitions
- **oracle-partition-connector**: DBA\_OBJECTS and DBA\_EXTENTS

Compared with **generic-jdbc-connector**, **oracle-partition-connector** and **oracle-connector** have the following advantages:

- a. Load balancing: Number and scope of data segments are determined by the storage structure (data blocks) of the source table rather than the data on the source table. In terms of granularity, a data block can occupy a partition.
- b. Stable performance: Invalid index faults caused by data skew and bound variable snooping can be completely eliminated.
- c. Fast query speed: Using data segmentation delivers a higher query speed than that of using index.
- d. Excellent horizontal scalability: The number of generated segments increases with the increase of data volume. In this case, ideal performance can be delivered when you increase the number of concurrent tasks. Contrarily, decreasing concurrent tasks saves resources.
- e. Simplified data segmentation logic: Problems like precision loss, type compatibility, and bound variables can be prevented.
- f. Enhanced usability: Users do not need to create partition columns and tables for Loader.

# 14 Using MapReduce

---

## 14.1 Converting MapReduce from the Single Instance Mode to the HA Mode

### Scenario

The JobHistoryServer service of MapReduce is a single instance, or the single instance is used to install the MapReduce service during cluster installation. To avoid the MapReduce single point of failure (SPOF) problem, you can enable JobHistoryServer HA to ensure high availability of the MapReduce service.

### Impact on the System

- Before the conversion, change the MapReduce server parameter **JHS\_FLOAT\_IP** to an available floating IP address. (The service IP address of the node is used by default in the single instance mode.)
- During the conversion, component services that depend on MapReduce will expire. In this case, restart the expired component services, such as Yarn, Hive, and HBase.
- After the conversion, update the configuration file of the Yarn client. If the configuration file is not updated, application task logs on the native Yarn page may fail to be queried.

### Procedure

- Step 1** Log in to Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **MapReduce** > **Configurations** to go to the configuration page of the MapReduce service.
- Step 2** Change the value of **JHS\_FLOAT\_IP** to an available floating IP address and click **Save**. On the displayed dialog box, click **OK**.
- Step 3** Choose **Instance** > **Add Instance**, select a node, and choose **Next** > **Next** > **Submit**. The instance is successfully added.

**Step 4** On the Manager home page, click **\*\*\*** next to the name of the target cluster and select **Restart Configuration-Expired Instances**. The instance is restarted successfully.

**Step 5** View the restarted instances. For example, the active and standby instances of MapReduce are normally displayed and run properly.

----End

## 14.2 Configuring the Log Archiving and Clearing Mechanism

### Scenario

Job and task logs are generated during execution of a MapReduce application.

- Job logs are generated by the MRApplicationMaster, which record details about the start and running time of jobs and each task, Counter value, and other information. After being analyzed by HistoryServer, the job logs are used to view job execution details.
- A task log records the log information generated by each task running in a container. By default, task logs are stored only on the local disk of each NodeManager. After the log aggregation function is enabled, the NodeManager merges local task logs and writes them into HDFS after job execution completes.

The job logs and task logs of the MapReduce are stored on HDFS (when the log aggregation function is enabled). If the mechanism for periodically archiving and deleting log files is not configured for a cluster with a large number of computation tasks, the log files will occupy large memory space of HDFS and increase the cluster load.

Log archive is implemented by Hadoop Archives. The number (number of Map tasks) of concurrent archiving tasks started by the Hadoop Archives is related to the total size of log files to be archived. The formula is as follows: Number of concurrent archive tasks = Total size of log files to be archived/Size of archive files.

### Configuration

Go to the **All Configurations** page of the MapReduce service. For details, see [Modifying Cluster Service Configuration Parameters](#).

Enter a parameter name in the search box. In addition, you need to configure the following information in the **mapred-site.xml** configuration file in the *Client installation directory/HDFS/hadoop/etc/hadoop/ directory* on the MapReduce client node:

**Table 14-1** Parameter description

Parameter	Description	Default Value
mapreduce.jobhistory.cleaner.enable	Whether to enable the job log file deletion function.	true
mapreduce.jobhistory.cleaner.interval-ms	Period for starting a log file cleanup. Only log files whose retention period is longer than the time specified by <b>mapreduce.jobhistory.max-age-ms</b> can be deleted.	86,400,000 ms (1 day)
mapreduce.jobhistory.max-age-ms	Log files whose retention period is longer than the retention period in milliseconds specified by this parameter will be deleted.	1,296,000,000 ms (15 days)

You can configure the following parameters in the **yarn-site.xml** file on the ResourceManager, NodeManager, and MapReduce HistoryServer nodes. The **yarn.nodemanager.remote-app-log-dir** and **yarn.nodemanager.remote-app-log-archive-dir** parameters need to be configured on the Yarn client, and the configurations of the ResourceManager, NodeManager, and MapReduce HistoryServer nodes must be the same as those on the Yarn client.

**Table 14-2** Parameter description

Parameter	Description	Default Value
yarn.nodemanager.remote-app-log-dir	Indicates the HDFS path for aggregating the MapReduce job logs.	/tmp/logs
yarn.nodemanager.remote-app-log-archive-dir	Indicates the HDFS path for archiving the MapReduce job logs.	/tmp/archived
yarn.log-aggregation.archive.files.minimum	Indicates the minimum number of archived MapReduce job log files. The archiving task starts when the number of files in the <b>yarn.nodemanager.remote-app-log-dir</b> folder is greater than or equal to the value of this parameter.	5,000
yarn.log-aggregation.archive-check-interval-seconds	Indicates the MapReduce job log archiving interval, in seconds. Log files are archived only when the number of log files reaches the value of <b>yarn.log-aggregation.archive.files.minimum</b> . The archiving function is disabled when the period is set to <b>0</b> or <b>-1</b> .	-1

Parameter	Description	Default Value
yarn.log-aggregation.retain-seconds	Indicates the retention period on HDFS for archiving the MapReduce job logs. The value -1 indicates that log files are stored permanently.	1,296,000
yarn.log-aggregation.retain-check-interval-seconds	Indicates the check period (in seconds) of the MapReduce job log deletion task. If this parameter is set to -1, the check period is one tenth of the log retention period.	86400

## 14.3 Reducing Client Application Failure Rate

### Scenario

When the network is unstable or the cluster I/O and CPU are overloaded, client applications might encounter running failures.

### Configuration

Adjust the following parameters in the **mapred-site.xml** configuration file on the client to reduce the client application failure rate:

#### NOTE

The **mapred-site.xml** configuration file is in the **conf** directory of the client installation path, for example, **/opt/client/Yarn/conf**.

**Table 14-3** Parameter description

Parameter	Description	Default Value
mapreduce.reduce.shuffle.max-host-failures	Indicates the number of allowed failures of an MR task to read remote shuffle data in the Reduce process. When the number is set to be over 5, the client application failure rate can be reduced.	5
mapreduce.client.submit.file.replication	Indicates the backup of job files on HDFS. MR tasks are dependent on the job files during running. When the number of backups is set to be over 10, the client application failure rate can be reduced.	10

## 14.4 Transmitting MapReduce Tasks from Windows to Linux

### Scenarios

To submit MapReduce tasks from Windows to Linux, set **mapreduce.app-submission.cross-platform** to **true**. If this parameter does not exist in the cluster or the value of this parameter is **false**, the cluster does not support this function. Perform the following operations to add this parameter or change the value of this parameter to enable it.

### Configuration Description

Adjust the following parameter in the **mapred-site.xml** configuration file on the client to enable the running of MapReduce tasks: The **mapred-site.xml** configuration file is in the **conf** directory of the client installation path, for example, **/opt/client/Yarn/config**.

**Table 14-4** Parameters

Parameter	Description	Default Value
mapreduce.app-submission.cross-platform	Indicates whether to support running of MapReduce tasks after they are transmitted from Windows to Linux. When the parameter value is <b>true</b> , the running of MapReduce tasks is supported. When the parameter value is <b>false</b> , the running of MapReduce tasks is not supported.	true

## 14.5 Configuring the Distributed Cache

### Scenarios

Distributed caching is useful in the following scenarios:

#### Rolling Upgrade


During the upgrade, applications must keep the text content (JAR file or configuration file) unchanged. The content is not based on Yarn of the current version, but on the version when it is submitted. This is a challenging issue. Generally, applications (such as MapReduce, Hive, and Tez) need to be installed locally. Libraries need to be installed on all cluster servers (clients and servers). When a rolling upgrade or downgrade starts in the cluster, the version of the locally installed library changes during application running. During the rolling upgrade, only a few NodeManagers are upgraded first. These NodeManagers obtain the software of the latest version. This leads to inconsistent behavior and can result in run-time errors.

### Co-existence of Multiple Yarn Versions

Cluster administrators may run tasks that use multiple versions of Yarn and Hadoop JARs in a cluster. However, this task is difficult to be implemented because the JARs have been localized and have only one version.

The MapReduce application framework can be deployed through the distributed cache and does not depend on the static version copied during installation. Therefore, you can store multiple versions of Hadoop in HDFS and configure the **mapred-site.xml** file to specify the default version used by the task. You can run different versions of MapReduce by setting proper configuration attributes without using the versions deployed in the cluster.

**Figure 14-1** Clusters with NodeManagers and Applications of multiple versions



As shown in [Figure 14-1](#), the application can use Hadoop JARs in HDFS instead of the local version. Therefore, during the rolling upgrade, even if NodeManager has been upgraded, the application can still run Hadoop of the earlier version.

### Configuration Description

**Step 1** Save the MapReduce **.tar** package of the specified version to a directory that can be accessed by applications in HDFS, as shown in the following command.

```
$HADOOP_HOME/bin/hdfs dfs -put hadoop-x.tar.gz /mapred/framework/
```

**Step 2** Set parameters in the **mapred-site.xml** file based on [Table 14-5](#).

**Table 14-5** Distributed cache parameters

Parameter	Description	Default Value
mapreduce.application.framework.path	<p>Indicates the URL directing to the archive location.</p> <p><b>NOTE</b> This property can also create an alias for the archive if the URL fragment identity name is specified as follows. In this example, the alias is set to <b>mr-framework</b>.</p> <pre>&lt;property&gt; &lt;name&gt;mapreduce.application.framework.path&lt;/name&gt; &lt;value&gt;hdfs://mapred/framework/hadoop-x.tar.gz#mr-framework&lt;/value&gt; &lt;/property&gt;</pre>	NA
mapreduce.application.classpath	<p>Indicates the parameter property, which contains the MapReduce JARs in the class directory.</p> <p><b>NOTE</b> For example, the alias <b>mr-framework</b> used in the framework path is used to match the directory.</p> <pre>&lt;property&gt; &lt;name&gt;mapreduce.application.classpath&lt;/name&gt; &lt;value&gt;\$PWD/mr-framework/hadoop/share/hadoop/mapreduce/*: \$PWD/mr-framework/hadoop/share/hadoop/mapreduce/lib/*: \$PWD/mr-framework/hadoop/share/hadoop/common/*:\$PWD/mr- framework/hadoop/share/hadoop/common/lib/*:\$PWD/mr- framework/hadoop/share/hadoop/yarn/*:\$PWD/mr-framework/ hadoop/share/hadoop/yarn/lib/*:\$PWD/mr-framework/hadoop/share/ hadoop/hdfs/*:\$PWD/mr-framework/hadoop/share/hadoop/ hdfs/lib*/etc/hadoop/conf/secure&lt;/value&gt;&lt;/property&gt;</pre>	N/A

You can upload MapReduce tarballs of multiple versions to HDFS. Different **mapred-site.xml** files indicate different locations. After that, you can run tasks for a specific **mapred-site.xml** file. The following is an example of running an MapReduce task for the MapReduce tarball of the *x* version:

```
hadoop jar share/hadoop/mapreduce/hadoop-mapreduce-examples-*.jar pi -conf
etc/hadoop-x/mapred-site.xml 10 10
```

----End

## 14.6 Configuring the MapReduce Shuffle Address

### Scenario

When the MapReduce shuffle service is started, it attempts to bind an IP address based on local host. If the MapReduce shuffle service is required to connect to a specific IP address, no configuration is available. The following description allows you to configure a connection to a specific IP address.

### Configuration

To bind a specific IP address to the MapReduce shuffle service, set the following parameters in the **mapred-site.xml** configuration file of the node where the NodeManager instance resides:

**Table 14-6** Parameter description

Parameter	Description	Default Value
mapreduce.shuffle.address	<p>Indicates the specified address to run the shuffle service. The format is <i>IP:PORT</i>. The default value is empty. If this parameter is left empty, the local host IP address is bound. The default port number is 13562.</p> <p><b>NOTE</b> If the value of <i>PORT</i> is different from that of <b>mapreduce.shuffle.port</b>, the <b>mapreduce.shuffle.port</b> value does not take effect.</p>	-

## 14.7 Configuring the Cluster Administrator List

### Scenario

This function is used to specify the MapReduce cluster administrator.

The MRS cluster administrator list is specified by **mapreduce.cluster.administrators**. The cluster administrator **admin** has all operation permissions.

### Configuration

On the **All Configurations** page of the MapReduce service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).

**Table 14-7** Parameter description

Parameter	Description	Default Value
mapreduce.cluster.acls.enabled	Indicates whether to enable permission control on Job History Server.	true

Parameter	Description	Default Value
mapreduce.cluster.administrators	Indicates the administrator list of the MapReduce cluster. You can configure both users and user groups. Multiple users or user groups are separated by commas (,), and users and user groups are separated by spaces, for example, userA,userB groupA,groupB. The value * indicates all users or user groups.	mapred supergroup,System_administrator_186

## 14.8 Introduction to MapReduce Logs

### Log Description

#### Log paths:

- JobhistoryServer: `/var/log/Bigdata/mapreduce/jobhistory` (run log) and `/var/log/Bigdata/audit/mapreduce/jobhistory` (audit log)
- Container: `/srv/BigData/hadoop/data1/nm/containerlogs/application_${appid}/container_${$contid}`

#### NOTE

The logs of running tasks are stored in the preceding paths. After the running is complete, the system determines whether to aggregate the logs to an HDFS directory based on the Yarn configuration. For details, see [Common Yarn Parameters](#).

#### Log archive rule:

The automatic compression and archive function is enabled for MapReduce logs. By default, a log file is automatically compressed when the size of the log file is greater than 50 MB. The name of the compressed log file is in the following format: `<Name of the original log>-<yyyy-mm-dd_hh-mm-ss>.[NO].log.zip`. A maximum of 100 latest compressed files are reserved. The number of compressed files can be configured on the parameter configuration page.

In MapReduce, JobhistoryServer cleans the old log files stored in HDFS periodically. The default storage directory is `/mr-history/done`. `mapreduce.jobhistory.max-age-ms` is used to set the cleanup interval. The default value of this parameter is 1,296,000,000 ms, which indicates 15 days.

**Table 14-8** MapReduce log list

Type	Name	Description
Run log	jhs-daemon-start-stop.log	Startup log file of the daemon process

Type	Name	Description
	hadoop-<SSH_USER>- jhshadaemon- <hostname>.log	Run log file of the daemon process
	hadoop-<SSH_USER>- <process_name>- <hostname>.out	Log that records the MapReduce running environment information
	historyserver-<SSH_USER>- <DATE>-<PID>-gc.log	Log that records the garbage collection of the MapReduce service
	jhs-haCheck.log	Log that records the active and standby status of MapReduce instances
	yarn-start-stop.log	Log that records the startup and stop of the MapReduce service
	yarn-prestart.log	Log that records cluster operations before the MapReduce service startup
	yarn-postinstall.log	Work log before the MapReduce service startup and after the installation
	yarn-cleanup.log	Log that records the cleanup logs about the uninstallation of the MapReduce service
	mapred-service-check.log	Log that records the health check details of the MapReduce service
	container_{\$contid}	Container log
	hadoop-<SSH_USER>- <process_name>- <hostname>.log	MR run log
	mapred-switch-jhs.log	MR active/standby switchover log
	env.log	Environment information log before the instance is started or stopped
Audit log	mapred-audit-jobhistory.log	MapReduce operation audit log

Type	Name	Description
	SecurityAuth.audit	MapReduce security audit log

## Log Level

**Table 14-9** describes the log levels supported by MapReduce. The log levels are FATAL, ERROR, WARN, INFO, and DEBUG from high priority to low. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 14-9** Log level

Level	Description
FATAL	Logs of this level record critical error information about the current event processing.
ERROR	Logs of this level record error information about the current event processing.
WARN	Logs of this level record unexpected alarm information about the current event processing.
INFO	Logs of this level record normal running status information about the system and events.
DEBUG	Logs of this level record the system information and system debugging information.

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of the MapReduce service. For details, see [Modifying Cluster Service Configuration Parameters](#).
- Step 2** On the left menu bar, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Save the configuration. In the displayed dialog box, click **OK** to make the configurations take effect.

 **NOTE**

The configurations take effect immediately without restarting the service.

----End

## Log Format

The following table lists the MapReduce log formats.

**Table 14-10** Log format

Type	Format	Example
Run log	<i>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt; &lt;Log level&gt; &lt;Name of the thread that generates the log&gt; &lt;Message in the log&gt;  &lt;Location where the log event occurs&gt;</i>	2020-01-26 14:18:59,109   INFO   main   Client environment:java.compiler=<N A>   org.apache.zookeeper.Environ ment.logEnv(Environment.java :100)
Audit log	<i>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt; &lt;Log level&gt; &lt;Name of the thread that generates the log&gt; &lt;Message in the log&gt;  &lt;Location where the log event occurs&gt;</i>	2020-01-26 14:24:43,605   INFO   main-EventThread   USER=omm OPERATION=refreshAdminAcl s TARGET=AdminService RESULT=SUCCESS   org.apache.hadoop.yarn.server. resourcemanager.RMAuditLog ger\$LogLevel \$6.printLog(RMAuditLogger.ja va:91)

## 14.9 MapReduce Performance Tuning

### 14.9.1 Optimization Configuration for Multiple CPU Cores

#### Scenario

Optimization can be performed when the number of CPU cores is large, for example, the number of CPU cores is three times the number of disks.

#### Procedure

You can set the following parameters in either of the following ways:

- Configuration on the server:  
On the **All Configurations** page of the Yarn service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).
- Configuration on the client:  
Modify the corresponding configuration file on the client.

 **NOTE**

- Path of configuration files on the HDFS client: *Client installation directory*/HDFS/hadoop/etc/hadoop/hdfs-site.xml
- Path of configuration files on the Yarn client: *Client installation directory*/HDFS/hadoop/etc/hadoop/yarn-site.xml.
- Path of configuration files on the MapReduce client: *Client installation directory*/HDFS/hadoop/etc/hadoop/mapred-site.xml.

**Table 14-11** Settings of multiple CPU cores

Configuration	Description	Parameter	Default Value	Server/Client	Impact	Remarks
Number of slots in a node container	The combination of the following parameters determines the number of concurrent tasks (Map and Reduce tasks) of each node: <ul style="list-style-type: none"> <li>• yarn.nodemanager.resource.memory-mb</li> <li>• mapreduce.map.memory.mb</li> <li>• mapreduce.reduce.memory.mb</li> </ul>	yarn.nodemanager.resource.memory-mb <b>NOTE</b> You need to configure this parameter on FusionInsight Manager.	16384	Server	If data needs to be read from and written into disks for all tasks (Map/Reduce tasks), a disk may be accessed by multiple processes at the same time, which leads to poor disk I/O performance. To ensure disk I/O performance, the number of concurrent access requests from a client to a disk cannot exceed 3.	The maximum number of concurrent containers must be [2.5 x Number of disks configured in Hadoop].
		mapreduce.map.memory.mb <b>NOTE</b> You need to set this parameter in the configuration file on the client in the <i>Client installation directory</i> /HDFS/hadoop/etc/hadoop/mapred-site.xml path.	4096	Client		

Conf igauration	Descriptio n	Parameter	Defa ult Valu e	Serv er/ Clie nt	Impact	Remarks
		<p>mapreduce.re duce.memory. mb</p> <p><b>NOTE</b> You need to set this parameter in the configuration file on the client in the <i>Client installation directory/HDFS/hadoop/etc/hadoop/mapred-site.xml</i> path.</p>	4096	Clie nt		
Map out put and com pression	<p>The Map task output before being written into disks can be compressed. This can save disk space, offer faster data write, and reduce the data traffic delivered to Reducer. You need to configure the following parameters on the client:</p> <ul style="list-style-type: none"> <li>• <b>mapred uce.ma</b></li> </ul>	<p>mapreduce.m ap.output.co mpress</p> <p><b>NOTE</b> You need to set this parameter in the configuration file on the client in the <i>Client installation directory/HDFS/hadoop/etc/hadoop/mapred-site.xml</i> path.</p>	true	Clie nt	The disk I/O is the bottleneck. Therefore, use a compression algorithm with a high compression rate.	Snappy is used. The benchmark test results show that Snappy delivers high performance and efficiency.

Conf igure tion	Descriptio n	Parameter	Defa ult Valu e	Serv er/ Clie nt	Impact	Remarks
	<p><b>p.output.compress:</b> The Map task output can be compressed before it is transmitted over the network. It is a per-job configuration.</p> <ul style="list-style-type: none"> <li>• <b>mapreduce.map.output.compress.codec:</b> the codec used for data compression</li> </ul>	<p>mapreduce.map.output.compress.codec</p> <p><b>NOTE</b>                      You need to set this parameter in the configuration file on the client in the <i>Client installation directory/HDFS/hadoop/etc/hadoop/mapred-site.xml</i> path.</p>	org.apache.hadoop.io.compress.Lz4Codec	Client		

Conf iguretion	Descriptio n	Parameter	Defa ult Valu e	Serv er/ Clie nt	Impact	Remarks
Spills	mapreduce .map.sort.s pill.percent	mapreduce.m ap.sort.spill.pe rcent <b>NOTE</b> You need to set this parameter in the configuration file on the client in the <i>Client installation directory/HDFS/hadoop/etc/hadoop/mapred-site.xml</i> path.	0.8	Clie nt	Disk I/Os are the bottleneck. You can set the value of <b>mapreduce.task.io.sort.mb</b> to minimize the memory spilled to the disk.	-
Data pack et size	When the HDFS client writes data to a data node, the data will be accumulated until a packet is generated. Then, the packet is transmitted over the network. <b>dfs.client-write-packet-size</b> specifies the data packet size. It can be specified by each job.	dfs.client-write-packet-size <b>NOTE</b> You need to set this parameter in the configuration file on the client in the <i>Client installation directory/HDFS/hadoop/hdfs-site.xml/</i> path.	262144	Clie nt	The data node receives data packets from the HDFS client and writes data into disks through single threads. When disks are in the concurrent write state, increasing the data packet size can reduce the disk seek time and improve the I/O performance.	dfs.client-write-packet-size = 262144

## 14.9.2 Determining the Job Baseline

### Scenario

The performance optimization effect is verified by comparing actual values with the baseline data. Therefore, determining optimal job baseline is critical to performance optimization.

When determining the job baseline, comply with the following rules:

- Making full use of cluster resources
- Setting the number of Map and Reduce tasks appropriately
- Setting the runtime of each task appropriately

### Procedure

- **Rule 1: Making full use of cluster resources**

Enable all nodes to handle tasks as actively as they can when a job is executed. Maximizing the number of concurrent tasks helps make full use of resources. You can achieve this purpose by adjusting the data volume to be processed and the number of Map and Reduce tasks.

You can set **mapreduce.job.reduces** to control the number of Reduce tasks.

The number of Map tasks depends on the InputFormat type and whether the data file to be processed can be split. By default, TextFileInputFormat allocates Map tasks based on the number of blocks, that is, one Map task for each block. You can adjust the following parameters to improve resource utilization.

Parameter portal:

On the **All Configurations** page of the Yarn service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).

Parameter	Description	Default Value
mapreduce.input.fileinputformat.split.maxsize	<p>Indicates the maximum size of the data block into which the Map input information is to be split.</p> <p>The shard size can be calculated based on its size customized by the user and the block size of each file. The formula is as follows:</p> $\text{splitSize} = \text{Math.max}(\text{minSize}, \text{Math.min}(\text{maxSize}, \text{blockSize}))$ <p>If <b>maxSize</b> is bigger than <b>blockSize</b>, a block is a shard. If <b>maxSize</b> is smaller than <b>blockSize</b>, a block will be split into multiple shards. If the size of the remaining data in a block is smaller than <b>splitSize</b>, the remaining data will be treated as a separated shard.</p>	-
mapreduce.input.fileinputformat.split.minsize	Indicates the minimum size of a data shard.	0

- **Principle 2: Setting Reduce tasks to be executed in one round.**

Avoid the following scenarios:

- Most of Reduce tasks are completed in the first round, but there is still one Reduce task left running. The execution of the last Reduce task extends the runtime of the job. Therefore, reduce the number of Reduce tasks to enable all of them to run at the same time.
- All Map tasks are completed, but there are still Reduce tasks running on some nodes. In this case, the cluster resources are not fully utilized. You need to increase the number of Reduce tasks to enable each node to handle tasks.

- **Rule 3: Setting the runtime of each task appropriately**

If each Map or Reduce task of a job takes only a few seconds, most time of the job is wasted on scheduling tasks and starting and stopping processes. Therefore, you need to increase the data volume to be processed in each task. The preferred processing time for each task is 1 minute.

You can configure the following parameters to adjust the processing time in a task.

Parameter portal:

On the **All Configurations** page of the Yarn service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).


Parameter	Description	Default Value
mapreduce.input.fileinputformat.split.maxsize	<p>Indicates the maximum size of the data block into which the Map input information is to be split.</p> <p>The shard size can be calculated based on its size customized by the user and the block size of each file. The formula is as follows:</p> <pre>splitSize = Math.max(minSize, Math.min(maxSize, blockSize))</pre> <p>If <b>maxSize</b> is bigger than <b>blockSize</b>, a block is a shard. If <b>maxSize</b> is smaller than <b>blockSize</b>, a block will be split into multiple shards. If the size of the remaining data in a block is smaller than <b>splitSize</b>, the remaining data will be treated as a separated shard.</p>	-
mapreduce.input.fileinputformat.split.minsize	Indicates the minimum size of a data shard.	0

### 14.9.3 Streamlining Shuffle

#### Scenario

During the shuffle procedure of MapReduce, the Map task writes intermediate data into disks, and the Reduce task copies and adds the data to the reduce function. Hadoop provides lots of parameters for the optimization.

Figure 14-2 Shuffle process



## Procedure

### 1. Improving Performance in Map Phase

- Determine the memory used by Map.

To determine whether Map has sufficient memory, check the number of GCs and the ratio of the GC time over the total task time in counters of completed jobs. Normally, the GC time cannot exceed 10% of the task time (that is, GC time elapsed (ms)/CPU time spent (ms) < 10%).

You can improve Map performance by adjusting the following parameters.

Parameter portal:

On the **All Configurations** page of the Yarn service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).

**Table 14-12** Parameter description

Parameter	Description	Default Value
mapreduce.map.memory.mb	Memory restriction of a Map task.	4096
mapreduce.map.java.opts	JVM parameter of the Map subtask. If this parameter is set, it will replace the <b>mapred.child.java.opts</b> parameter. If <b>-Xmx</b> is not set, the value of <b>Xmx</b> is calculated based on <b>mapreduce.map.memory.mb</b> and <b>mapreduce.job.heap.memory-mb.ratio</b> .	- Djava.net.preferIPv4Stack=true - Djava.security.krb5.conf=\${KRB5_CONFIG}

It is recommended that the **-Xmx** in **mapreduce.map.java.opts** is 0.8 times the value of **mapreduce.map.memory.mb**.

- Using Combiner

Combiner is an optional procedure in the Map phase, in which the intermediate results with the same key value are combined. Generally, set the reduce class to combiner. Combiner helps reduce the intermediate result output of Map, thereby consuming less network bandwidth during the shuffle process. You can use the following API to set a combiner class for a specific job.

**Table 14-13** Combiner API

Class	API	Description
org.apache.hadoop.mapreduce.Job	public void setCombinerClass(Class<? extends Reducer> cls)	API used to set a combiner class for a specific job.

2. **Improving Performance in Copy Phase**

- Compress data.

Compress the intermediate output of Map. Data compression reduces the data to be transferred over the network. However, data compression and decompression consume more CPU. Determine whether to compress the intermediate results of Map based on site requirements. If a task is bandwidth-intensive, data compression improves processing performance. As for the bulkload optimization, compression of the intermediate output improves the performance by 60%.

To improve copy performance, set **mapreduce.map.output.compress** to **true** and **mapreduce.map.output.compress.codec** to **org.apache.hadoop.io.compress.SnappyCodec**.

3. **Improving Performance in Merge Phase**

To improve merge performance, configure the following parameters to reduce the number of times that Reduce writes data to disks.

Parameter portal:

On the **All Configurations** page of the Yarn service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).

**Table 14-14** Parameter description

Parameter	Description	Default Value
mapreduce.reduce.merge.inmem.threshold	Threshold of the number of files for the in-memory merge process. When the accumulated number of files reaches the threshold, the process of in-memory merge and spilling to disks is initiated. If the value is less than or equal to <b>0</b> , the threshold does not take effect and the merge is triggered only based on the RAMFS memory usage.	1000

Parameter	Description	Default Value
mapreduce.reduce.shuffle.merge.percent	Usage threshold for initiating in-memory merge, indicating the percentage of memory allocated to the Map outputs (defined by <b>mapreduce.reduce.shuffle.input.buffer.percent</b> ).	0.66
mapreduce.reduce.shuffle.input.buffer.percent	Percentage of memory to be allocated from the maximum heap size to storing Map outputs during the Shuffle.	0.70
mapreduce.reduce.input.buffer.percent	Percentage of memory (relative to the maximum heap size) to retain Map outputs during the Reduce. When the Shuffle is completed, all remaining Map outputs in memory must use less than this threshold before the Reduce begins.	0.0

## 14.9.4 AM Optimization for Big Tasks

### Scenario

A big job containing 100,000 Map tasks fails. It is found that the failure is triggered by the slow response of ApplicationMaster (AM).

When the number of tasks increases, the number of objects managed by the AM increases, which requires much more memory for management. The default memory heap for AM is 1 GB.

### Procedure

You can improve the AM performance by setting the following parameters.

Navigation path for setting parameters:

Adjust the following parameters in the **mapred-site.xml** configuration file on the client to adjust the following parameters: The **mapred-site.xml** configuration file is in the **conf** directory of the client installation path, for example, **/opt/client/Yarn/config**.

Parameter	Description	Default Value
yarn.app.mapreduce.am.resource.mb	This parameter must be greater than the heap size specified by <b>yarn.app.mapreduce.am.command-opts</b> . Unit: MB	1536
yarn.app.mapreduce.am.command-opts	Indicates the JVM startup parameters loaded to MapReduce ApplicationMaster.	-Xmx1024m -XX: +UseConcMarkSweepGC -XX: +CMSParallelRemarkEnabled - verbose:gc - Djava.security.krb5.conf=\$ {KRB5_CONFIG} - Dhadoop.home.dir=\$ {BIGDATA_HOME}/ FusionInsight_HD_xxx/install/ FusionInsight-Hadoop-xxx/hadoop

## 14.9.5 Speculative Execution

### Scenario

If a cluster has hundreds or thousands of nodes, the hardware or software fault of a node may prolong the execution time of the entire task (as most tasks are already completed, the system is still waiting for the task running on the faulty node). Speculative execution allows a task to be executed on multiple machines. You can disable speculative execution for small clusters.

### Procedure

Navigation path for setting parameters:

On the **All Configurations** page of the Yarn service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).

Parameter	Description	Default Value
mapreduce.map.speculative	Sets whether to execute multiple instances of some map tasks concurrently. <b>true</b> indicates that speculative execution is enabled.	false
mapreduce.reduce.speculative	Sets whether to execute multiple instances of some reduce tasks concurrently. <b>true</b> indicates that speculative execution is enabled.	false

## 14.9.6 Using Slow Start

### Scenario

The Slow Start feature specifies the proportion of Map tasks to be completed before Reduce tasks are started. If the Reduce tasks are started too early, resources will be occupied, thereby reducing task running efficiency. However, if the Reduce tasks are started at an appropriate time, resource usage during shuffle and task running efficiency will be improved. For example, the MapReduce job includes 15 Map tasks and a cluster can start 10 Map tasks, there are 5 Map tasks remained after a round of Map tasks is completed and the cluster has available resources. In this case, you can configure the value of Slow Start to a value less than 1 (for example, 0.8), then the Reduce tasks can make use of the remaining cluster resources.

### Procedure

Parameter portal:

On the **All Configurations** page of the MapReduce service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).

Parameter	Description	Default Value
mapreduce.job.reduce.slowlstart.completedmaps	Fraction of the number of Maps in the job which should be completed before Reduces are scheduled for the job. By default, the Reduce tasks start when all the Map tasks are completed.	1.0

## 14.9.7 Optimizing Performance for Committing MR Jobs

### Scenario

By default, if an MR job generates a large number of output files, it takes a long time for the job to commit the temporary outputs of a task to the final output directory in the commit phase. In large clusters, the time-consuming commit process of jobs greatly affects the performance.

In this case, you can set the **mapreduce.fileoutputcommitter.algorithm.version** to **2** to improve the performance in the commit phase of MR jobs.

### Procedure

Navigation path for setting parameters:

On the **All Configurations** page of the Yarn service, enter a parameter name in the search box. For details, see [Modifying Cluster Service Configuration Parameters](#).

**Table 14-15** Parameter description

Parameter	Description	Default Value
mapreduce.fileoutputcommitter.algorithm.version	<p>Indicates the algorithm version submitted by a job. The value is 1 or 2.</p> <p><b>NOTE</b> 2 is the recommended algorithm version. This algorithm enables tasks to directly commit the output results of each task to the final result output directory, reducing the time for the results of large jobs are committed.</p>	2

## 14.10 Common Issues About MapReduce

### 14.10.1 Why Does It Take a Long Time to Run a Task Upon ResourceManager Active/Standby Switchover?

#### Question

MapReduce job takes a very long time (more than 10minutes) when the ResourceManager switch while the job is running.

#### Answer

This is because, ResorceManager HA is enabled but the ResourceManager work preserving restart is not enabled.

If ResorceManager work preserving restart is not enabled, then ResorceManager switch containers are killed which causes the ResorceManager to timeout the ApplicationMaster. For ResorceManager work preserving restart feature details, see <http://hadoop.apache.org/docs/r3.1.1/hadoop-yarn/hadoop-yarn-site/ResourceManagerRestart.html>.

The following method can be used to solve the issue:

Enable the ResorceManager work preserving restart feature by configuring the following parameter.

**yarn.resourcemanager.work-preserving-recovery.enabled=true**

### 14.10.2 Why Does a MapReduce Task Stay Unchanged for a Long Time?

#### Question

MapReduce job is not progressing for long time

## Answer

This is because of less memory. When the memory is less, the time taken by the job to copy the map output increases significantly.

In order to reduce the waiting time, increase the heap memory.

The job configuration should be tuned according to number of mappers and data size processed by each mapper. Based on the input data size, tune the following configurations accordingly for feasible performance.

- **mapreduce.reduce.memory.mb**
- **mapreduce.reduce.java.opts**

**Example:** If the data size is 5 GB with 10 mappers, then the ideal heap memory would be 1.5 GB. Increase the heap memory size according with the increase in data size.

### 14.10.3 Why the Client Hangs During Job Running?

#### Question

Why is the client unavailable when the MR ApplicationMaster or ResourceManager is moved to the D state during job running?

#### Answer

When a task is running, the MR ApplicationMaster or ResourceManager is moved to D state (uninterrupted sleep state) or T state (stopped state). The client waits to return the task running state, but the MR ApplicationMaster does not return. Therefore, the client remains in the waiting state.

To avoid the preceding scenario, use the **ipc.client.rpc.timeout** configuration item in the **core-site.xml** file to set the client timeout interval.

The value of this parameter is millisecond. The default value is **0**, indicating that no timeout occurs. The client timeout interval ranges from 0 ms to 2,147,483,647 ms.

#### NOTE

- If the Hadoop process is in the D state, restart the node where the process is located.
- The **core-site.xml** configuration file is stored in the **conf** directory of the client installation path, for example, **/opt/hadoopClient/Yarn/config**.

### 14.10.4 Why Cannot HDFS\_DELEGATION\_TOKEN Be Found in the Cache?

#### Question

In security mode, why delegation token HDFS\_DELEGATION\_TOKEN is not found in the cache?

## Answer

In MapReduce, by default HDFS\_DELEGATION\_TOKEN will be canceled after the job completion. So if the token has to be re-used for the next job then the token will not be found in the cache.

To re-use the same token in subsequent job set the below parameter for the MR job configuration. When it is false the user can re-sue the same token.

```
jobConf.setBoolean("mapreduce.job.complete.cancel.delegation.tokens", false);
```

## 14.10.5 How Do I Set the Task Priority When Submitting a MapReduce Task?

### Question

How do I set the job priority when submitting a MapReduce task?

### Answer

You can add the parameter **-Dmapreduce.job.priority=<priority>** in the command to set task priority when submitting MapReduce tasks on the client. The format is as follows:

```
yarn jar <jar> [mainClass] -Dmapreduce.job.priority=<priority> [path1] [path2]
```

The parameters in the command are described as follows:

- *<jar>*: specifies the name of the JAR package to be run.
- *[mainClass]*: specifies the **main** method of the class for an application project in a JAR file.
- *<priority>*: specifies the priority of a task. The value can be **VERY\_HIGH**, **HIGH**, **NORMAL**, **LOW**, or **VERY\_LOW**.
- *[path1]*: specifies the data input path.
- *[path2]*: specifies the data output path.

For example, set the **/opt/client/HDFS/hadoop/share/hadoop/mapreduce/hadoop-mapreduce-examples\*.jar** package to a high-priority task.

```
yarn jar /opt/client/HDFS/hadoop/share/hadoop/mapreduce/hadoop-mapreduce-examples*.jar wordcount -Dmapreduce.job.priority=VERY_HIGH /DATA.txt /out/
```

## 14.10.6 Why Physical Memory Overflow Occurs If a MapReduce Task Fails?

### Question

The HBase bulkload task has 210,000 Map tasks and 10,000 Reduce tasks. The MapReduce task fails to be executed, and the physical memory of ApplicationMaster overflows.

For more detailed output, check the application tracking page:[https://bigdata-55:8090/cluster/app/application\\_1449841777199\\_0003](https://bigdata-55:8090/cluster/app/application_1449841777199_0003)

```
Then click on links to logs of each attempt.
Diagnostics: Container [pid=21557,containerID=container_1449841777199_0003_02_000001] is running
beyond physical memory limits
Current usage: 1.0 GB of 1 GB physical memory used; 3.6 GB of 5 GB virtual memory used. Killing container.
Dump of the process-tree for container_1449841777199_0003_02_000001 :
|- PID PPID PGRP PID SESSID CMD_NAME USER_MODE TIME(MILLIS) SYSTEM_TIME(MILLIS)
VMEM_USAGE(BYTES) RSSMEM_USAGE(PAGES) FULL_CMD_LINE
|- 21584 21557 21557 21557 (java) 12342 1627 3871748096 271331 ${BIGDATA_HOME}/jdk1.8.0_51//bin/
java
-Djava.io.tmpdir=/srv/BigData/hadoop/data1/nm/localdir/usercache/hbase/appcache/
application_1449841777199_0003/container_1449841777199_0003_02_000001/tmp -
Dlog4j.configuration=container-log4j.properties
-Dyarn.app.container.log.dir=/srv/BigData/hadoop/data1/nm/containerlogs/
application_1449841777199_0003/container_1449841777199_0003_02_000001 -
Dyarn.app.container.log.filesize=0 -Dhadoop.root.logger=INFO,CLA
-Dhadoop.root.logfile=syslog -Xmx784m org.apache.hadoop.mapreduce.v2.app.MRAppMaster
|- 21557 21547 21557 21557 (bash) 0 0 13074432 368 /bin/bash -c ${BIGDATA_HOME}/jdk1.8.0_51//bin/
java
-Djava.io.tmpdir=/srv/BigData/hadoop/data1/nm/localdir/usercache/hbase/appcache/
application_1449841777199_0003/container_1449841777199_0003_02_000001/tmp -
Dlog4j.configuration=container-log4j.properties
-Dyarn.app.container.log.dir=/srv/BigData/hadoop/data1/nm/containerlogs/
application_1449841777199_0003/container_1449841777199_0003_02_000001 -
Dyarn.app.container.log.filesize=0 -Dhadoop.root.logger=INFO,CLA
-Dhadoop.root.logfile=syslog -Xmx784m org.apache.hadoop.mapreduce.v2.app.MRAppMaster 1>/srv/
BigData/hadoop/data1/nm/containerlogs/application_1449841777199_0003/
container_1449841777199_0003_02_000001/stdout
2>/srv/BigData/hadoop/data1/nm/containerlogs/application_1449841777199_0003/
container_1449841777199_0003_02_000001/stderr
Container killed on request. Exit code is 143
Container exited with a non-zero exit code 143
Failing this attempt. Failing the application.
```

## Answer

This is a performance specification problem. The root cause of the MapReduce task execution failure is the memory overflow of ApplicationMaster, that is, the NodeManager kills the task due to the physical memory overflow.

### Solutions:

Increase the memory of ApplicationMaster and optimize the following parameters in the **mapred-site.xml** configuration file on the client:

- **yarn.app.mapreduce.am.resource.mb**
- **yarn.app.mapreduce.am.command-opts**. The recommended value of **-Xmx** is **0.8 x yarn.app.mapreduce.am.resource.mb**.

### Specification:

ApplicationMaster supports 24,000 concurrent containers when the configuration is as follows:

- **yarn.app.mapreduce.am.resource.mb=2048**
- In **yarn.app.mapreduce.am.command-opts**, **-Xmx** is **1638m**.

## 14.10.7 After the Address of MapReduce JobHistoryServer Is Changed, Why the Wrong Page is Displayed When I Click the Tracking URL on the ResourceManager WebUI?

### Question

After the address of MapReduce JobHistoryServer is changed, why the wrong page is displayed when I click the tracking URL on the ResourceManager WebUI?

### Answer

JobHistoryServer address (mapreduce.jobhistory.address / mapreduce.jobhistory.webapp.<https.>address) is the parameter of MapReduce. The MapReduce client will submit the address together with jobs to ResourceManager. After ResourceManager completing the jobs, the parameter is saved in RMStateStore as the target address for viewing history job information.

If the JobHistoryServer address is changed, update the address in the configuration file of the MapReduce client in time. If the address is not updated, the page of earlier JobHistoryServer is displayed when you click the tracking URL of the new job. The target address of information about MapReduce jobs running before the change of address cannot be changed, so the wrong page is also displayed when you click the tracking URL. You can check the history information by accessing the new JobHistoryServer address.

## 14.10.8 MapReduce Job Failed in Multiple NameService Environment

### Question

MapReduce or Yarn job fails in multiple nameService environment using viewFS.

### Answer

When using viewFS only the mount directories are accessible, so the most possible cause is that the path configured is not in one of the mounted paths. For example:

```
<property>
<name>fs.defaultFS</name>
<value>viewfs://ClusterX/</value>
</property>
<property>
<name>fs.viewfs.mounttable.ClusterX.link./folder1</name>
<value>hdfs://NS1/folder1</value>
</property>
<property>
<name>fs.viewfs.mounttable.ClusterX.link./folder2</name>
<value>hdfs://NS2/folder2</value>
</property>
```

For all the MR properties which depends on HDFS, should use the paths inside mount folders.

**Incorrect:**

```
<property>  
<name>yarn.app.mapreduce.am.staging-dir</name>  
<value>/tmp/hadoop-yarn/staging</value>  
</property>
```

As the root folder (/) is not accessible in viewFS.

**Correct:**

```
<property>  
<name>yarn.app.mapreduce.am.staging-dir</name>  
<value>/folder1/tmp/hadoop-yarn/staging</value>  
</property>
```

## 14.10.9 Why a Fault MapReduce Node Is Not Blacklisted?

### Question

MapReduce task fails and the ratio of fault nodes to all nodes is smaller than the blacklist threshold configured by **yarn.resourcemanager.am-scheduling.node-blacklisting-disable-threshold**. Why the fault node not be blacklisted?

### Answer

If the blacklisted percentage exceeds the threshold, all blacklisted nodes are released. Traditionally, the blacklist percentage is the ratio of fault nodes to all nodes in the cluster. Currently, each node has a label expression. Therefore, the blacklist percentage needs to be calculated based on the number of nodes related to valid node label expressions. In other way, the blacklist percentage is the ratio of fault nodes related to valid node label expressions.

Assume that there are 100 nodes in the cluster, including 10 nodes (labelA) related to valid node label expressions. Assume that all nodes related to valid node label expressions are faulty and default blacklist threshold is 0.33. In traditional calculation method,  $10/100 = 0.1$ , which is far smaller than the threshold (0.33). In this case, the 10 nodes will never get released. Therefore, MapReduce always cannot obtain nodes and applications cannot run properly. In practice, the blacklist percentage needs to be calculated based on the total number of nodes related to valid node label expressions:  $10/10 = 1$  is greater than the blacklist threshold and all nodes are released.

Therefore, even the ratio of fault nodes to all nodes in the cluster is below the threshold, all nodes in the blacklist are released.

# 15 Using Oozie

---

## 15.1 Using Oozie from Scratch

Oozie is an open-source workflow engine that is used to schedule and coordinate Hadoop jobs.

Oozie can be used to submit a wide array of jobs, such as Hive, Spark2x, Loader, MapReduce, Java, DistCp, Shell, HDFS, SSH, SubWorkflow, Streaming, and scheduled jobs.

This section describes how to use the Oozie client to submit a MapReduce job.

### Prerequisites

The client has been installed. For example, the installation directory is **/opt/client**. The client directory in the following operations is only an example. Change it based on the actual installation directory onsite.

### Procedure

- Step 1** Log in to the node where the client is installed as the client installation user.
- Step 2** Run the following command to go to the client installation directory. Assume that the client is installed in **/opt/client**.  
**cd /opt/client**
- Step 3** Run the following command to configure environment variables:  
**source bigdata\_env**
- Step 4** Check the cluster authentication mode.
  - If the cluster is in security mode, run the following command to authenticate the user: *UserOozie* indicates the user who submits tasks.  
**kinit UserOozie**
  - If the cluster is in normal mode, go to [Step 5](#).
- Step 5** Upload the Oozie configuration file and JAR package to HDFS.

```
hdfs dfs -mkdir /user/UserOozie
```

```
hdfs dfs -put -f /opt/client/Oozie/oozie-client-*/examples /user/UserOozie/
```

*UserOozie* indicates the user who submits tasks.

**Step 6** Run the following commands to modify the job execution configuration file:

```
cd /opt/client/Oozie/oozie-client-*/examples/apps/map-reduce/
```

```
vi job.properties
```

```
nameNode=hdfs://hacluster
resourceManager=10.64.35.161:8032 (10.64.35.161 is the service plane IP address of the Yarn
resourceManager (active) node, and 8032 is the port number of yarn.resourcemanager.port)
queueName=default
examplesRoot=examples
user.name=admin
oozie.wf.application.path=${nameNode}/user/${user.name}/${examplesRoot}/apps/map-reduce#
HDFS upload path
outputDir=map-reduce
oozie.wf.rerun.failnodes=true
```

**Step 7** Run the following command to execute the Oozie job:

```
oozie job -oozie https://Host name of the Oozie role:21003/oozie/ -config
job.properties -run
```

```
[root@kwephispra44947 map-reduce]# oozie job -oozie https://kwephispra44948:21003/oozie/ -config
job.properties -run
.....
job: 0000000-200730163829770-oozie-omm-W
```

**Step 8** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#).

**Step 9** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Oozie**, click the hyperlink next to **Oozie WebUI** to go to the Oozie page, and view the task execution result on the Oozie web UI.

**Figure 15-1** Task execution result

Job Id	Name	User	Group	Created	Started	Last Modified	Ended
1 0000000-200730163829770-oozie-...	map-reduce-wf	jedis		Thu, 30 Jul 2020 09:55:11 ...	Thu, 30 Jul 2020 09:55:12 ...	Thu, 30 Jul 2020 09:55:12 ...	Thu, 30 Jul 2020 09:55:12 ...
2 0000001-200730163829770-oozie-...	map-reduce-wf	jedis		Thu, 30 Jul 2020 09:59:07 ...			
3 0000002-200730163829770-oozie-...	map-reduce-wf	jedis		Thu, 30 Jul 2020 10:01:36 ...			

----End

## 15.2 Using the Oozie Client

### Scenario

This section describes how to use the Oozie client in an O&M scenario or service scenario.

## Prerequisites

- The client has been installed. For example, the installation directory is **/opt/hadoopclient**. The client directory in the following operations is only an example. Change it to the actual installation directory.
- Service component users are created by the administrator as required. In security mode, machine-machine users need to download the keytab file. A human-machine user must change the password upon the first login.

## Using the Oozie Client

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to go to the client installation directory.

```
cd /opt/hadoopclient
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** Check the cluster authentication mode.

- If the cluster is in security mode, run the following command to authenticate the user: *exampleUser* indicates the name of the user who submits tasks.  

```
kinit exampleUser
```
- If the cluster is in normal mode, go to [Step 5](#).

**Step 5** Perform the following operations to configure Hue:

1. Configure the Spark2x environment (skip this step if the Spark2x task is not involved):

```
hdfs dfs -put /opt/hadoopclient/Spark2x/spark/jars/*.jar /user/oozie/  
share/lib/spark2x/
```

2. Upload the Oozie configuration file and JAR package to HDFS.

```
hdfs dfs -mkdir /user/exampleUser
```

```
hdfs dfs -put -f /opt/hadoopclient/Oozie/oozie-client-*/examples /user/  
exampleUser/
```

 NOTE

- *exampleUser* indicates the name of the user who submits tasks.
- If the user who submits the task and other files except **job.properties** are not changed, client installation directory **/Oozie/oozie-client-\*/examples** can be repeatedly used after being uploaded to HDFS.
- When the JAR package in the HDFS directory **/user/oozie/share** changes, you need to restart the Oozie service.
- Resolve the JAR file conflict between Spark and Yarn about Jetty.

```
hdfs dfs -rm -f /user/oozie/share/lib/spark/jetty-all-9.2.22.v20170606.jar
```

- In normal mode, if **Permission denied** is displayed during the upload, run the following commands:

```
su - omm
source /opt/hadoopclient/bigdata_env
hdfs dfs -chmod -R 777 /user/oozie
exit
```

----End

## 15.3 Enabling Oozie High Availability (HA)

### Scenario

When multiple Oozie nodes provide services at the same time, you can use ZooKeeper to provide high availability (HA), which helps avoid single points of failure (SPOFs) and prevent multiple nodes from concurrently processing the same task.

### Impact on the System

Enabling Oozie HA requires an Oozie restart, and Oozie cannot provide services during the restart.

### Prerequisites

- Oozie and ZooKeeper have been installed and are running properly.
- No task is running.
- The current cluster is of the latest version. If it is not, copy the **curator-x-discovery-4.2.0.jar** package from the **\$BIGDATA\_HOME/FusionInsight\_Porter\_X.X.X/install/FusionInsight-Oozie-X.X.X/oozie-X.X.X/embedded-oozie-server/webapp/WEB-INF/lib** directory to the **\$BIGDATA\_HOME/FusionInsight\_Porter\_X.X.X/install/FusionInsight-Oozie-X.X.X/oozie-X.X.X/lib** directory.

### Procedure

- Step 1** On **FusionInsight Manager**, choose **Cluster > Services > Oozie**. On the displayed page, click the **Configurations** tab, and then click **All Configurations**. In the navigation pane, choose **Customization** under **oozie(Role)**, and add the configuration items listed in the following table for **oozie.site.configs**. Click **Save** after the modification. In the displayed dialog box, click **OK**.

Parameter	Setting	Description
oozie.services.ext	org.apache.oozie.service.ZKLocksService,org.apache.oozie.service.ZKXLoggingService,org.apache.oozie.service.ZKJobsConcurrencyService,org.apache.oozie.service.ZKUIDService	Services providing enhanced HA
oozie.zookeeper.connection.string	<i>ZooKeeper instance service IP address:Port number.</i> Use commas (,) to separate multiple IP address:port pairs.	ZooKeeper connection information
oozie.zookeeper.namespace	oozie	Oozie path on ZooKeeper
oozie.zookeeper.secure	Security cluster: true Normal cluster: not required	Whether to enable Kerberos on ZooKeeper.

**Step 2** On the **Dashboard** page of Oozie, click **Stop Service** in the upper-right corner, and select **Restart Service** to restart Oozie.

----End

## 15.4 Using Oozie Client to Submit an Oozie Job

### 15.4.1 Submitting a Hive Job

#### Scenario

This section describes how to use the Oozie client to submit a Hive job.

Hive jobs are divided into the following types:

- Hive job  
Hive job that is connected in JDBC mode
- Hive2 job  
Hive job that is connected in Beeline mode

This section describes how to submit a Hive job using the Oozie client.

#### NOTE

- The procedure for submitting a Hive2 job using the Oozie client is the same as that for submitting a Hive job. You only need to change **/Hive** in the procedure to **/Hive2**.  
For example, if the Hive job running directory is **/opt/client/Oozie/oozie-\*/examples/apps/hive/**, then the running directory of Hive2 is **/opt/client/Oozie/oozie-client-\*/examples/apps/hive2/**.
- You are advised to download the latest client.

## Prerequisites

- The Hive and Oozie components and clients have been installed and are running properly.
- You have created or obtained the human-machine account and password for accessing the Oozie service.

### NOTE

- This user must belong to the **hadoop**, **supergroup**, and **hive** groups and be assigned with the Oozie role operation permission.
- This user must also be assigned the **manager\_viewer** role at least.
- You have obtained the URL of the Oozie server (any instance) in the running state, for example, **https://10.1.130.10:21003/oozie**.
- You have obtained the name of the Oozie server, for example, **10-1-130-10**.
- You have obtained the IP address of the active Yarn ResourceManager, for example, **10.1.130.11**.

## Procedure

**Step 1** Log in to the node where the Oozie client is installed as the client installation user.

**Step 2** Run the following command to obtain the installation environment. In the command, **/opt/client/** indicates the client installation path.

```
source /opt/client/bigdata_env
```

**Step 3** Check the cluster authentication mode.

- If the cluster is in security mode, run the **kinit** command to authenticate users.

For example, the **oozieuser** user is authenticated using the following command:

```
kinit oozieuser
```

- If the cluster is in normal mode, go to [Step 4](#).

**Step 4** Run the following command to go to the example directory:

```
cd /opt/client/Oozie/oozie-client-*/examples/apps/hive/
```

[Table 15-1](#) lists the files that you need to pay attention to in the directory.

**Table 15-1** File description

File	Description
hive-site.xml	Configuration file of a Hive job
job.properties	Parameter definition file of a workflow
script.q	SQL script of a Hive job
workflow.xml	Rule definition file of a workflow

**Step 5** Run the following command to edit the **job.properties** file:

### vi job.properties

Perform the following modifications:

Change the value of **userName** to the name of the human-machine user who submits the job, for example, **userName=oozieuser**.

**Step 6** Run the **oozie job** command to run the workflow file:

```
oozie job -oozie https://Host name of the Oozie role:21003/oozie/ -config job.properties -run
```

#### NOTE

- The command parameters are described as follows:
  - oozie** URL of the Oozie server that executes a job
  - config** Workflow property file
  - run** Executing a workflow
- If a job ID, for example, **job: 0000021-140222101051722-oozie-omm-W**, is displayed after the workflow file is executed, the job is successfully submitted. You can view the execution results on the Oozie management page.

Log in to the Oozie web UI at **https://IP address of the Oozie role:21003/oozie** as user **oozieuser**.

On the Oozie web UI, you can view the submitted workflow information based on the job ID in the table on the page.

----End

## 15.4.2 Submitting a Spark2x Job

### Scenario

This section describes how to submit a Spark2x job using the Oozie client.

#### NOTE

You are advised to download the latest client.

### Prerequisites

- The Spark2x and Oozie components and clients have been installed and are running properly.

If the current client is an earlier version, you need to download and install the client again.
- You have created or obtained the human-machine account and password for accessing the Oozie service.

#### NOTE

- This user must belong to the **hadoop**, **supergroup**, and **hive** groups and be assigned with the Oozie role operation permission.
- This user must also be assigned the **manager\_viewer** role at least.
- You have obtained the URL of the Oozie server (any instance) in the running state, for example, **https://10.1.130.10:21003/oozie**.

- You have obtained the name of the Oozie server, for example, **10-1-130-10**.
- You have obtained the IP address of the active Yarn ResourceManager, for example, **10.1.130.11**.

## Procedure

**Step 1** Log in to the node where the Oozie client is installed as the client installation user.

**Step 2** Run the following command to obtain the installation environment. In the preceding command, **/opt/client/** indicates the client installation path.

```
source /opt/client/bigdata_env
```

**Step 3** Check the cluster authentication mode.

- If the cluster is in security mode, run the **kinit** command to authenticate users.

For example, the **oozieuser** user is authenticated using the following command:

```
kinit oozieuser
```

- If the cluster is in normal mode, go to [Step 4](#).

**Step 4** Run the following command to go to the example directory:

```
cd /opt/client/Oozie/oozie-client-*/examples/apps/spark2x/
```

[Table 15-2](#) lists the files that you need to pay attention to in the directory.

**Table 15-2** File description

File	Description
job.properties	Parameter definition file of a workflow
workflow.xml	Rule definition file of a workflow
lib	Directory of the JAR file on which a workflow depends

**Step 5** Run the following command to edit the **job.properties** file:

```
vi job.properties
```

Perform the following modifications:

Change the value of **userName** to the name of the human-machine user who submits the job, for example, **userName=oozieuser**.

**Step 6** Run the **oozie job** command to run the workflow file:

```
oozie job -oozie https://Host name of the Oozie role:21003/oozie/ -config job.properties -run
```

 NOTE

- The command parameters are described as follows:
  - oozie** URL of the Oozie server that executes a job
  - config** Workflow property file
  - run** Executing a workflow
- If a job ID, for example, **job: 0000021-140222101051722-oozie-omm-W**, is displayed after the workflow file is executed, the job is successfully submitted. You can view the execution results on the Oozie management page.  
Log in to the Oozie web UI at **https://IP address of the Oozie role:21003/oozie** as user **oozieuser**.  
On the Oozie web UI, you can view the submitted workflow information based on the job ID in the table on the page.

----End

## 15.4.3 Submitting a Loader Job

### Scenario

This section describes how to submit a Loader job using the Oozie client.

 NOTE

You are advised to download the latest client.

### Prerequisites

- The Hive and Oozie components and clients have been installed and are running properly.
- You have created or obtained the human-machine account and password for accessing the Oozie service.

 NOTE

- This user must belong to the **hadoop**, **supergroup**, and **hive** groups and be assigned with the Oozie role operation permission.
- This user must also be assigned the **manager\_viewer** role at least.
- You have obtained the URL of the Oozie server (any instance) in the running state, for example, **https://10.1.130.10:21003/oozie**.
- You have obtained the name of the Oozie server, for example, **10-1-130-10**.
- You have obtained the IP address of the active Yarn ResourceManager, for example, **10.1.130.11**.
- You have created a Loader job to be scheduled and obtained the job ID.

### Procedure

**Step 1** Log in to the node where the Oozie client is installed as the client installation user.

**Step 2** Run the following command to obtain the installation environment. In the command, **/opt/client/** indicates the client installation path.

```
source /opt/client/bigdata_env
```

**Step 3** Check the cluster authentication mode.

- If the cluster is in security mode, run the **kinit** command to authenticate users.

For example, the **oozieuser** user is authenticated using the following command:

```
kinit oozieuser
```

- If the cluster is in normal mode, go to [Step 4](#).

**Step 4** Run the following command to go to the example directory:

```
cd /opt/client/Oozie/oozie-client-*/examples/apps/sqoop/
```

[Table 15-3](#) lists the files that you need to pay attention to in the directory.

**Table 15-3** File description

File	Description
job.properties	Parameter definition file of a workflow
workflow.xml	Rule definition file of a workflow

**Step 5** Run the following command to edit the **job.properties** file:

```
vi job.properties
```

Perform the following modifications:

Change the value of **userName** to the name of the human-machine user who submits the job, for example, **userName=oozieuser**.

**Step 6** Run the following command to edit the **workflow.xml** file:

```
vi workflow.xml
```

Perform the following modifications:

Change the value of **command** to the ID of the Loader job to be scheduled, for example, **1**.

Upload the **workflow.xml** file to the HDFS path in the **job.properties** file.

```
hdfs dfs -put -f workflow.xml /user/userName/examples/apps/sqoop
```

**Step 7** Run the **oozie job** command to run the workflow file:

```
oozie job -oozie https://Host name of the Oozie role:21003/oozie/ -config job.properties -run
```

 NOTE

- The command parameters are described as follows:
  - oozie** URL of the Oozie server that executes a job
  - config** Workflow property file
  - run** Executing a workflow
- If a job ID, for example, **job: 0000021-140222101051722-oozie-omm-W**, is displayed after the workflow file is executed, the job is successfully submitted. You can view the execution results on the Oozie management page.

Log in to the Oozie web UI at **https://IP address of the Oozie role:21003/oozie** as user **oozieuser**.

On the Oozie web UI, you can view the submitted workflow information based on the job ID in the table on the page.

----End

## 15.4.4 Submitting a DistCp Job

### Scenario

This section describes how to submit a DistCp job using the Oozie client.

 NOTE

You are advised to download the latest client.

### Prerequisites

- The HDFS and Oozie components and clients have been installed and are running properly.  
If the current client is an earlier version, you need to download and install the client again.
- You have created or obtained the human-machine account and password for accessing the Oozie service.

 NOTE

- This user must belong to the **hadoop**, **supergroup**, and **hive** groups and be assigned with the Oozie role operation permission.
- This user must also be assigned the **manager\_viewer** role at least.
- You have obtained the URL of the Oozie server (any instance) in the running state, for example, **https://10.1.130.10:21003/oozie**.
- You have obtained the name of the Oozie server, for example, **10-1-130-10**.
- You have obtained the IP address of the active Yarn ResourceManager, for example, **10.1.130.11**.

### Procedure

**Step 1** Log in to the node where the Oozie client is installed as the client installation user .

**Step 2** Run the following command to obtain the installation environment. In the preceding command, **/opt/client/** indicates the client installation path.

**source /opt/client/bigdata\_env**

**Step 3** Check the cluster authentication mode.

- If the cluster is in security mode, run the **kinit** command to authenticate users.

For example, the **oozieuser** user is authenticated using the following command:

**kinit oozieuser**

- If the cluster is in normal mode, go to [Step 4](#).

**Step 4** Run the following command to go to the example directory:

**cd /opt/client/Oozie/oozie-client-\*/examples/apps/distcp/**

[Table 15-4](#) lists the files that you need to pay attention to in the directory.

**Table 15-4** File description

File	Description
job.properties	Parameter definition file of a workflow
workflow.xml	Rule definition file of a workflow

**Step 5** Run the following command to edit the **job.properties** file:

**vi job.properties**

Perform the following modifications:

Change the value of **userName** to the name of the human-machine user who submits the job, for example, **userName=oozieuser**.

**Step 6** If DistCp is not deployed across security clusters, go to [9](#). Otherwise, go to [7](#).

**Step 7** Establish cross-Manager mutual trust between two clusters.

**Step 8** Run the following commands to back up and modify the **workflow.xml** file:

**cp workflow.xml workflow.xml.bak**

**vi workflow.xml**

Modify the following content:

```
<workflow-app xmlns="uri:oozie:workflow:1.0" name="distcp-wf">
  <start to="distcp-node"/>
  <action name="distcp-node">
    <distcp xmlns="uri:oozie:distcp-action:1.0">
      <resource-manager>${resourceManager}</resource-manager>
      <name-node>${nameNode}</name-node>
      <prepare>
        <delete path="hdfs://target_ip:target_port/user/${userName}/${examplesRoot}/output-data/${outputDir}"/>
      </prepare>
      <configuration>
        <property>
          <name>mapred.job.queue.name</name>
          <value>${queueName}</value>
        </property>
      </configuration>
    </distcp>
  </action>
</workflow-app>
```

```
<property>
  <name>oozie.launcher.mapreduce.job.hdfs-servers</name>
  <value>hdfs://source_ip:source_port,hdfs://target_ip:target_port</value>
</property>
</configuration>
<arg>${nameNode}/user/${userName}/${examplesRoot}/input-data/text/data.txt</arg>
<arg>hdfs://target_ip:target_port/user/${userName}/${examplesRoot}/output-data/${outputDir}/
data.txt</arg>
</distcp>
<ok to="end"/>
<error to="fail"/>
</action>
<kill name="fail">
  <message>DistCP failed, error message[${wf.errorMessage(wf.lastErrorNode())}]</message>
</kill>
<end name="end"/>
</workflow-app>
```

**target\_ip:target\_port** is the HDFS active NameNode address of the other trusted cluster, for example, **10.10.10.233:25000**.

**source\_ip:source\_port** indicates the HDFS active NameNode address of the source cluster, for example, **10.10.10.223:25000**.

Change the two IP addresses and port numbers based on the site requirements.

**Step 9** Run the **oozie job** command to run the workflow file:

```
oozie job -oozie https://Host name of the Oozie role:21003/oozie/ -config job.properties -run
```

#### NOTE

- The command parameters are described as follows:
  - oozie** URL of the Oozie server that executes a job
  - config** Workflow property file
  - run** Executing a workflow
- If a job ID, for example, **job: 0000021-140222101051722-oozie-omm-W**, is displayed after the workflow file is executed, the job is successfully submitted. You can view the execution results on the Oozie management page.

Log in to the Oozie web UI at **https://IP address of the Oozie role:21003/oozie** as user **oozieuser**.

On the Oozie web UI, you can view the submitted workflow information based on the job ID in the table on the page.

----End

## 15.4.5 Submitting Other Jobs

### Scenario

In addition to Hive, Spark2x, and Loader jobs, MapReduce, Java, Shell, HDFS, SSH, SubWorkflow, Streaming, and scheduled jobs can be submitted using the Oozie client.

#### NOTE

You are advised to download the latest client.

## Prerequisites

- The Oozie component and its client have been installed and are running properly.
- You have created or obtained the human-machine account and password for accessing the Oozie service.

### NOTE

- Shell job:  
This user must belong to the **hadoop** and **supergroup** groups and be assigned the Oozie role operation permission. The Shell script must have the execution permission on each NodeManager.
- SSH job:  
This user must belong to the **hadoop** and **supergroup** groups and be assigned the Oozie role operation permission. The mutual trust configuration is complete.
- Other jobs:  
This user must belong to the **hadoop** and **supergroup** groups and be assigned the Oozie role operation permission and other required permissions.
- This user must also be assigned the **manager\_viewer** role at least.
- You have obtained the URL of the Oozie server (any instance) in the running state, for example, **https://10.1.130.10:21003/oozie**.
- You have obtained the name of the Oozie server, for example, **10-1-130-10**.
- You have obtained the IP address of the active Yarn ResourceManager, for example, **10.1.130.11**.

## Procedure

**Step 1** Log in to the node where the Oozie client is installed as the client installation user.

**Step 2** Run the following command to obtain the installation environment. In the command, **/opt/client/** indicates the client installation path.

```
source /opt/client/bigdata_env
```

**Step 3** Check the cluster authentication mode.

- If the cluster is in security mode, run the **kinit** command to authenticate users.

For example, the **oozieuser** user is authenticated using the following command:

```
kinit oozieuser
```

- If the cluster is in normal mode, go to [Step 4](#).

**Step 4** Go to the example directory based on the type of the task you submit.

**Table 15-5** List of example directories

Job Type	Example Directory
MapReduce job	<i>Client installation directory</i> /Oozie/oozie-client-*/examples/apps/map-reduce

Job Type	Example Directory
Java job	<i>Client installation directory</i> /Oozie/oozie-client-*/examples/apps/java-main
Shell job	<i>Client installation directory</i> /Oozie/oozie-client-*/examples/apps/shell
Streaming job	<i>Client installation directory</i> /Oozie/oozie-client-*/examples/apps/streaming
SubWorkflow job	<i>Client installation directory</i> /Oozie/oozie-client-*/examples/apps/subwf
SSH job	<i>Client installation directory</i> /Oozie/oozie-client-*/examples/apps/ssh
Scheduled job	<i>Client installation directory</i> /Oozie/oozie-client-*/examples/apps/cron

 **NOTE**

The examples of other jobs contain HDFS job examples.

**Table 15-6** lists the files that you need to pay attention to in the example directory.

**Table 15-6** File description

File	Description
job.properties	Parameter definition file of a workflow
workflow.xml	Rule definition file of a workflow
lib	Directory of the JAR file on which a workflow depends
coordinator.xml	Scheduled job configuration file which can be used to set a scheduled policy. The file is in the <b>cron</b> directory.
oozie_shell.sh	Shell script file required for submitting shell jobs. The file is in the <b>shell</b> directory.

**Step 5** Run the following command to edit the **job.properties** file:

**vi job.properties**

Perform the following modifications:

Change the value of **userName** to the name of the human-machine user who submits the job, for example, **userName=oozieuser**.

**Step 6** Run the **oozie job** command to run the workflow file:

```
oozie job -oozie https://Host name of the oozie role:21003/oozie -config File path of job.properties -run
```

Example:

```
oozie job -oozie https://10-1-130-10:21003/oozie -config /opt/client/Oozie/oozie-client-*/examples/apps/map-reduce/job.properties -run
```

 **NOTE**

- The command parameters are described as follows:
  - oozie** URL of the Oozie server that executes a job
  - config** Workflow property file
  - run** Executing a workflow
- If a job ID, for example, **job: 0000021-140222101051722-oozie-omm-W**, is displayed after the workflow file is executed, the job is successfully submitted. You can view the execution results on the Oozie management page.  
Log in to the Oozie web UI at **https://IP address of the Oozie role:21003/oozie** as user **oozieuser**.  
On the Oozie web UI, you can view the submitted workflow information based on the job ID in the table on the page.

----End

## 15.5 Using Hue to Submit an Oozie Job

### 15.5.1 Creating a Workflow

#### Scenario

You can submit an Oozie job on the Hue management page, but a workflow must be created before the job is submitted.

#### Prerequisites

Before using Hue to submit an Oozie job, configure the Oozie client and upload the sample configuration file and JAR file to the specified HDFS directory. For details, see [Using the Oozie Client](#).

#### Procedure

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** In the navigation tree on the left, click  and choose **Workflow** to open the Workflow editor.

**Step 3** Select **Actions** from the **DOCUMENTS** drop-down list, select the job type to be created and drag it to the operation area.

For submitting different job types, follow instructions in the following sections:

- [Submitting a Hive2 Job](#)
- [Submitting a Spark2x Job](#)
- [Submitting a Java Job](#)
- [Submitting a Loader Job](#)
- [Submitting a MapReduce Job](#)
- [Submitting a Sub-workflow Job](#)
- [Submitting a Shell Job](#)
- [Submitting an HDFS Job](#)
- [Submitting a DistCp Job](#)

----End

## 15.5.2 Submitting a Workflow Job

### 15.5.2.1 Submitting a Hive2 Job

#### Scenario

This section describes how to submit an Oozie job of the Hive2 type on the Hue web UI.

#### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **HiveServer2 Script** and drag it to the operation area.

**Step 3** In the **HiveServer2 Script** dialog box that is displayed, configure the script path in the HDFS, for example, `/user/admin/examples/apps/hive2/script.q`, and click **Add**.


**Step 4** Click **PARAMETER+** to add input and output parameters.

For example, if the input parameter is **INPUT=/user/admin/examples/input-data/table**, the output parameter is **OUTPUT=/user/admin/examples/output-data/hive2\_workflow**.



**Step 5** Click the configuration button  in the upper right corner. On the configuration page that is displayed, click **Delete +** to delete a directory, for example, `/user/admin/examples/output-data/hive2_workflow`.

**Step 6** Configure the job XML, for example, to the HDFS path `/user/admin/examples/apps/hive2/hive-site.xml`.



 **NOTE**

If the preceding parameters and values are modified, you can query them in **Oozie client installation directory/oozie-client-\*/conf/hive-site.xml**.

**Step 7** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **Hive2-Workflow**.

**Step 8** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

## 15.5.2.2 Submitting a Spark2x Job

### Scenario

This section describes how to submit an Oozie job of the Spark2x type on Hue.

### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **Spark program** and drag it to the operation area.

**Step 3** In the Spark window that is displayed, set the value of **Files**, for example, to `hdfs://hacluster/user/admin/examples/apps/spark2x/lib/oozie-examples.jar`. Set the value of **jar/py name**, for example, to `org.apache.oozie.example.SparkFileCopy`, and click **Add**.

**Step 4** Set the value of **Main class**, for example, `org.apache.oozie.example.SparkFileCopy`.

**Step 5** Click **PARAMETER+** to add related input and output parameters.

For example, add the following parameters:

- `hdfs://hacluster/user/admin/examples/input-data/text/data.txt`
- `hdfs://hacluster/user/admin/examples/output-data/spark_workflow`

**Step 6** In the **Options list** text box, specify Spark parameters, for example, `--conf spark.yarn.archive=hdfs://hacluster/user/spark2x/jars/8.1.2.2/spark-archive-2x.zip --conf spark.eventLog.enabled=true --conf spark.eventLog.dir=hdfs://hacluster/spark2xJobHistory2x`.

#### NOTE

The version 8.1.2.2 is used as an example. You can log in to FusionInsight Manager, click  in the upper right corner, choose **About** from the drop-down list, and view the FusionInsight Manager version in the dialog box that is displayed.

**Step 7** Click the configuration button  in the upper right corner. Set the value of **Spark Master**, for example, to `yarn-cluster`. Set the value of **Mode**, for example, `cluster`.

**Step 8** On the configuration page that is displayed, click **Delete +** to delete a directory, for example, `hdfs://hacluster/user/admin/examples/output-data/spark_workflow`.

**Step 9** Click **PROPERTIES+** and add `sharelib` used by Oozie. Enter the attribute name `oozie.action.sharelib.for.spark` in the left text box and the attribute value `spark2x` in the right text box.

**Step 10** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **Spark-Workflow**.

**Step 11** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

### 15.5.2.3 Submitting a Java Job

#### Scenario

This section describes how to submit an Oozie job of the Java type on the Hue web UI.

#### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **Java program** and drag it to the operation area.

**Step 3** In the **Jar program** window that is displayed, set the value of **Jar name**, for example, `/user/admin/examples/apps/java-main/lib/oozie-examples-5.1.0.jar`. Set the value of **Main class**, for example, `org.apache.oozie.example.DemoJavaMain`. Click **Add**.

**Step 4** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **Java-Workflow**.

**Step 5** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

### 15.5.2.4 Submitting a Loader Job

#### Scenario

This section describes how to submit an Oozie job of the Loader type on the Hue web UI.

## Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **Loader** and drag it to the operation area.

**Step 3** In the **Loader** window that is displayed, set **Job id**, for example, to **1**. Click **Add**.

### NOTE

**Job id** is the ID of the Loader job to be orchestrated and can be obtained from the Loader page.

You can create a Loader job to be scheduled and obtain its job ID. For details, see [Using Loader](#).

**Step 4** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **Loader-Workflow**.

**Step 5** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

## 15.5.2.5 Submitting a MapReduce Job

### Scenario

This section describes how to submit an Oozie job of the MapReduce type on the Hue web UI.

### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **MapReduce job** and drag it to the operation area.

**Step 3** In the displayed **MapReduce job** dialog box, set **Jar name**, for example, to **/user/admin/examples/apps/map-reduce/lib/oozie-examples-5.1.0.jar**. Click **Add**.

**Step 4** Click **PROPERTIES+** to add input and output properties.

For example, set the value of **mapred.input.dir** to **/user/admin/examples/input-data/text** and set the value of **mapred.output.dir** to **/user/admin/examples/output-data/map-reduce\_workflow**.

**Step 5** Click the configuration button  in the upper right corner. On the configuration page that is displayed, click **Delete +** to delete a directory, for example, `/user/admin/examples/output-data/map-reduce_workflow`.

**Step 6** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **MapReduce-Workflow**.

**Step 7** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

### 15.5.2.6 Submitting a Sub-workflow Job

#### Scenario

This section describes how to submit an Oozie job of the Sub-workflow type on the Hue web UI.

#### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **Sub workflow** and drag it to the operation area.

**Step 3** In the **Sub workflow** dialog box that is displayed, set **Sub-workflow**, for example, to **Java-Workflow** (one of the created workflows) from the drop-down list box, and click **Add**.

**Step 4** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **Subworkflow-Workflow**.

**Step 5** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

## 15.5.2.7 Submitting a Shell Job

### Scenario

This section describes how to submit an Oozie job of the Shell type on the Hue web UI.

### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **Shell** and drag it to the operation area.

**Step 3** In the **Shell** window that is displayed, set **Shell command**, for example, to **oozie\_shell.sh**, and click **Add**.

**Step 4** Click **FILE+** to add the Shell command execution file and Oozie example execution file, for example, **/user/admin/examples/apps/shell/oozie\_shell.sh**.

**Step 5** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **Shell-Workflow**.

**Step 6** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

#### NOTE

- When configuring a shell command as a Linux command, specify it as the original command instead of the shortcut key command. For example, do not set **ls -l** to **ll**. You can configure it as the shell command **ls**, and add a parameter **-l**.
- When uploading the shell script to HDFS on Windows, make sure that the shell script format is Unix. If the format is incorrect, the shell job fails to be submitted.

----End

## 15.5.2.8 Submitting an HDFS Job

### Scenario

This section describes how to submit an Oozie job of the HDFS type on the Hue web UI.

### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **Fs** and drag it to the operation area.

**Step 3** In the **Fs** window that is displayed, click **Add**.

**Step 4** Click **CREATE DIRECTORY+** to add the HDFS directories to be created, for example, `/user/admin/examples/output-data/mkdir_workflow` and `/user/admin/examples/output-data/mkdir_workflow1`.

**Step 5** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **HDFS-Workflow**.

**Step 6** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

## 15.5.2.9 Submitting a DistCp Job

### Scenario

This section describes how to submit an Oozie job of the DistCp type on the Hue web UI.

### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** On the workflow editing page, select  next to **DistCp** and drag it to the operation area.

**Step 3** Determine whether the current DistCp operation is performed across clusters.

- If yes, go to [Step 4](#).
- If no, go to [Step 7](#).

**Step 4** Establish cross-Manager mutual trust between two clusters.

**Step 5** In the **Distcp** window that is displayed, set the value of **Source**, for example, to `hdfs://hacluster/user/admin/examples/input-data/text/data.txt`. Set **Destination**, for example, to `hdfs://target_ip:target_port/user/admin/examples/output-data/distcp-workflow/data.txt`. Click **Add**.

**Step 6** Click the configuration button  in the upper right corner. On the **Properties** tab page, click **PROPERTIES+**, enter the attribute name `oozie.launcher.mapreduce.job.hdfs-servers` in the text box on the left, enter the attribute value `hdfs://source_ip:source_port,hdfs://target_ip:target_port` in the text box on the right, and go to [Step 8](#).

 **NOTE**

*source\_ip*: service address of the HDFS NameNode in the source cluster  
*source\_port*: port number of the HDFS NameNode in the source cluster.  
*target\_ip*: service address of the HDFS NameNode in the target cluster  
*target\_port*: port number of the HDFS NameNode in the target cluster.

**Step 7** In the **Distcp** window that is displayed, set the value of **Source**, for example, to **/user/admin/examples/input-data/text/data.txt**. Set **Destination**, for example, to **/user/admin/examples/output-data/distcp-workflow/data.txt**. Click **Add**.

**Step 8** Click  in the upper right corner. On the configuration page that is displayed, click **Delete+** and add the directory to be deleted, for example, **/user/admin/examples/output-data/distcp-workflow**.

**Step 9** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **Distcp-Workflow**.

**Step 10** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

## 15.5.2.10 Example of Mutual Trust Operations

### Scenario

This section guides you to enable unidirectional password-free mutual trust when Oozie nodes are used to execute shell scripts of external nodes through SSH jobs.

### Prerequisites

You have installed Oozie, and it can communicate with external nodes (nodes connected using SSH).

### Procedure

**Step 1** Ensure that the user used for SSH connection exists on the external node, and the user directory **~/.ssh** exists.

**Step 2** Log in to the Oozie node as user **omm** and run the **ssh-keygen -t rsa** command to generate public and private keys.

**Step 3** Run the **cat ~/.ssh/id\_rsa.pub >> ~/.ssh/authorized\_keys** statement to add the public key to the **authorized\_keys** file.

**Step 4** Upload the **id\_rsa.pub** file to an existing directory, for example, **/opt/**, on the external node as user **root**.

**scp ~/.ssh/id\_rsa.pub root@IP address of the external node:/opt/id\_rsa.pub**

**Step 5** Log in to the external node where the shell is located and go to the directory described in [Step 4](#). The `id_rsa.pub` file can be found.

Run the `cat id_rsa.pub >> ~/.ssh/authorized_keys` statement to add the public key to the `authorized_keys` file of the shell user.

**Step 6** Change the permission on the directory.

```
chmod 700 ~/.ssh
```

```
chmod 600 /opt/id_rsa.pub
```

```
chmod 600 ~/.ssh/authorized_keys
```

 **NOTE**

- The user of the node where shell resides (external node) has the permission to execute shell scripts and access all directories and files involved in the Shell scripts.
- If Oozie has multiple nodes, perform [Step 2](#) to [Step 6](#) on all Oozie nodes.

----End

## 15.5.2.11 Submitting an SSH Job

### Scenario

This section guides you to submit an Oozie job of the SSH type on the Hue web UI.

### Procedure

**Step 1** Create a workflow. For details, see [Creating a Workflow](#).

**Step 2** For details about how to add the trust relationship, see [Example of Mutual Trust Operations](#).

**Step 3** On the workflow editing page, select the **Ssh** button  and drag it to the operation area.

**Step 4** In the **Ssh** window that is displayed, set **User and Host** and **Ssh command** commands and click **Add**.

**Step 5** Click  in the upper right corner of the Oozie editor.

If you need to modify the job name before saving the job (default value: **My Workflow**), click the name directly for modification, for example, **Ssh-Workflow**.

**Step 6** After the configuration is saved, click , and submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

## 15.5.2.12 Submitting a Hive Script

### Scenario

This section describes how to submit a Hive job on the Hue web UI.

### Procedure

- Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).
- Step 2** In the navigation tree on the left, click  and choose **Workflow** to open the Workflow editor.
- Step 3** Click **Documents**, click  to select a Hive script from the operation list, and drag it to the operation page.
- Step 4** In the **HiveServer2 Script** dialog box that is displayed, select the saved Hive script. For details about how to save the Hive script, see [Using HiveQL Editor on the Hue Web UI](#). Select a script and click **Add**.



- Step 5** Configure the Job XML, for example, to the HDFS path `/user/admin/examples/apps/hive2/hive-site.xml`. For details, see [Submitting a Hive2 Job](#).
- Step 6** Click  in the upper right corner of the Oozie editor.
- Step 7** After the configuration is saved, click , and submit the job.  
After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on Hue.

----End

## 15.5.2.13 Submitting an Email Job

### Scenario

This section describes how to add an email job on the Hue web UI.

### Procedure

- Step 1** Log in to Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Oozie** > **Configurations**, switch from **Basic Configurations** to **All Configurations**, and search for the `oozie.site.configs` parameter.



**Step 2** Add the following parameters and click **Save**. In the displayed dialog box, click **OK**.

**Table 15-7** Parameters


Name	Value
oozie.email.smtp.host	<i>SMTP server, for example, xxx.xxx.com.</i>
oozie.email.from.address	<i>Sender email address, for example, zhangsan@xx.com.</i>
oozie.email.smtp.auth	<b>true</b>
oozie.email.smtp.username	<i>Sender account, for example, zhangsan.</i>
oozie.email.smtp.password	<i>Sender account password, for example, 111111.</i>
oozie.email.attachment.enabled	<b>true</b>
oozie.email.smtp.port	<i>SMTP server port number, for example, 25.</i>

**Step 3** On the Oozie dashboard page, choose **More > Restart Service**, enter the administrator password, and click **OK** to restart the Oozie service.

**Step 4** Log in to the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 5** In the navigation tree on the left, click  and choose **Workflow** to open the Workflow editor.

**Step 6** Click **Documents**, click  to select a Hive script from the operation list, and drag it to the operation page.



**Step 7** In the displayed dialog box, configure **To addresses**, **Subject**, and **Body**, and click **Add**.

- **To addresses:** specifies the recipient email address. Separate multiple email addresses with commas (,).
- **Subject:** specifies the email subject.
- **Body:** specifies the email body.

**Step 8** You can configure **cc**, **bcc**, and **Attachment** in the displayed dialog box based on service requirements.

- **cc:** specifies the address that will receive the carbon copy of the email. Separate multiple email addresses with commas (,).
- **bcc:** specifies the address that will receive the carbon copy of the email and is invisible to the recipient. Separate multiple email addresses with commas (,).
- **Attachment:** specifies the HDFS address of the attachment.

The screenshot shows an 'Email' configuration dialog box. It contains the following fields and values:

To addresses	1111@xxx.com
cc	2222@xxx.com
bcc	3333@xxx.com
Attachment	/user/admintest/examples/apps/shell/test.sh
Content-type	text/plain
Subject	test email job
Body	test 1111

**Step 9** Click  in the upper right corner of the Oozie editor to save the job.

**Step 10** After the job is saved, click . In the displayed dialog box, click **Submit** to submit the job.

After the job is submitted, you can view the related contents of the job, such as the detailed information, logs, and processes, on the Hue web UI.

----End

## 15.5.3 Submitting a Coordinator Periodic Scheduling Job

### Scenario

This section describes how to submit a job of the periodic scheduling type on the Hue web UI.

## Prerequisites

Required workflow jobs have been configured before the coordinator task is submitted.

## Procedure

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** In the navigation tree on the left, click  and choose **Schedule** to open the Coordinator editor.

**Step 3** On the job editing page, click **My Schedule** to change the job name.

**Step 4** Click **Choose a Workflow...** to select the workflow to be orchestrated.

**Step 5** Select a workflow, set the job execution frequency as prompted, and click  in the upper right corner to save the workflow job.

### NOTE

Because the time zone is changed, the difference between the time and the local time may be several hours.

**Step 6** Click  in the upper right corner of the editor, set the start value and end value of the time range for executing the scheduled job, and click **Submit** to submit the job.

### NOTE

Because the time zone is changed, the difference between the time and the local time may be several hours.

----End

## 15.5.4 Submitting a Bundle Batch Processing Job

### Scenario

In the case that multiple scheduled jobs exist at the same time, you can manage the jobs in batches over the Bundle task. This section describes how to submit a job of the batch type on the Hue web UI.

## Prerequisites

Required related workflow and Coordinator jobs have been configured before the Bundle batch processing job is submitted.

## Procedure

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** In the navigation tree on the left, click  and choose **Bundle** to open the Bundle editor.

**Step 3** On the job editing page, click **My Bundle** to change the job name.

**Step 4** Click **+Add a coordinator** to select the Coordinator job to be orchestrated.

**Step 5** Set the start time and the end time for the scheduled coordinator jobs as prompted and click  in the upper right corner to save the job.

**Step 6** Click  in the upper right corner of the editor, select  from the displayed menu, set the start time of the bundle task, click **+Add parameter** to add parameters, and close the dialog box to save the settings.

 **NOTE**

Because the time zone is changed, the difference between the time and the local time may be several hours.

**Step 7** Click  in the upper right corner of the editor. In the dialog box that is displayed, click **Submit** to submit the job.

----End

## 15.5.5 Querying the Operation Results

### Scenario

After the jobs are submitted, you can view the execution status of a specific job on Hue.

### Procedure

**Step 1** Access the Hue web UI. For details, see [Accessing the Hue Web UI](#).

**Step 2** Click . On the displayed page, you can view information about the Workflow, Schedule, and Bundle tasks.

----End

## 15.6 Oozie Log Overview

### Log Description

**Log path:** The default storage paths of Oozie log files are as follows:

- Run log: `/var/log/Bigdata/oozie`
- Audit log: `/var/log/Bigdata/audit/oozie`

**Log archiving rule:** Oozie logs are classified into run logs, script logs, and audit logs. The maximum size of a run log file is 20 MB, and a maximum of 20 run log files can be reserved. The maximum size of an audit log file is 20 MB, and a maximum of 20 audit log files can be reserved.

 NOTE

A compressed log file is generated for **oozie.log** every hour. 720 compressed files (log files of one month) are retained by default.

**Table 15-8** Oozie log list

Log Type	Log File Name	Description
Run log	jetty.log	Oozie built-in jetty server log file, which is used to process the request and response information of OozieServlet
	jetty.out	Oozie process startup log file
	oozie_db_temp.log	Oozie database connection log
	oozie-instrumentation.log	Oozie dashboard log file, which records the Oozie running status and configuration information of each component
	oozie-jpa.log	openJPa run log file
	oozie.log	Oozie run log file
	oozie-<SSH_USER>-<DATE>-<PID>-gc.log	Log file that records the garbage collection of the Oozie service
	oozie-ops.log	Oozie operation log file
	threadDump-<DATE>.log	Log file that records stack information when the service process exits normally
Script logs	postinstallDetail.log	Work log file generated after the installation and before the startup
	prestartDetail.log	Pre-startup log file
	startDetail.log	Service startup log file
	stopDetail.log	Service stop log file
	upload-sharelib.log	Operation logs uploaded by <b>sharelib</b>
Audit log	oozie-audit.log	Audit log

## Log Level

**Table 15-9** describes the log levels provided by Oozie.

The priorities of log levels are ERROR, WARN, INFO, and DEBUG in descending order. Logs whose levels are higher than or equal to the set level are printed. The number of printed logs decreases as the configured log level increases.

**Table 15-9** Log levels

Level	Description
ERROR	Logs of this level record abnormal information about events that cause process exceptions.
WARN	Logs of this level record exception information about the current event processing.
INFO	Logs of this level record normal running status information about the system and events.
DEBUG	Logs of this level record system information and information about database underlying data transmission.

To modify log levels, perform the following operations:

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster > Name of the desired cluster > Services > Oozie > Configurations**.
- Step 3** Select **All Configurations**.
- Step 4** On the menu bar on the left, select the log menu of the target role.
- Step 5** Select a desired log level.
- Step 6** Click **Save**, and then click **OK**. The settings take effect after the processing is complete.

----End

## Log Formats

The following table lists the Oozie log formats.

**Table 15-10** Log formats

Log Type	Format	Example
Run log	<yyy-MM-dd HH:mm:ss,SSS><Log level><Location where the log event occurs><Log level><Message in the log>	2015-05-29 21:01:45,268 INFO StatusTransitService\$StatusTransitRun- nable:539 - USER[-] GROUP[-] Released lock for [org.apache.oozie.service.StatusTransitSe rvice]
Script logs	<yyy-MM-dd HH:mm:ss,SSS><Host name > <Log level > <Message in the log>	2015-06-01 17:18:03 001 suse11-192-168-0-111 oozie INFO Running oozie service check script

Log Type	Format	Example
Audit log	<i>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt; &lt;Log Level&gt; &lt; Thread name // Message in the log   Location where the log event occurs</i>	2015-06-01 22:38:41,323   INFO   http- bio-21003-exec-8   IP [192.168.0.111] USER [null], GROUP [null], APP [null], JOBID [null], OPERATION [null], PARAMETER [null], RESULT [SUCCESS], HTTPCODE [200], ERRORCODE [null], ERRORMESSAGE [null]   org.apache.oozie.util.XLog.log(XLog.java: 539)

## 15.7 Common Issues About Oozie

### 15.7.1 How Do I Resolve the Problem that the Oozie Client Fails to Submit a MapReduce Job?

#### Question

The Oozie client fails to submit a MapReduce job and a message "Error: AUTHENTICATION: Could not authenticate, Authentication failed, status: 403, message: Forbidden" is displayed. How do I resolve this problem?

#### Answer

If the SolrServer or SolrServerAdmin instance is deployed on the node where the Oozie service is deployed, the Oozie client needs to use the host name of the node where the Oozie service locates to submit a job, but cannot use the service plane IP address of the node where the Oozie service locates.

For example, if the Oozie service is deployed on the host **hostname**, you need to run the **oozie job -oozie https://hostname:21003/oozie/ -config job.properties -run** command.

### 15.7.2 Oozie Scheduled Tasks Are Not Executed on Time

#### Question

Why are not Coordinator scheduled jobs executed on time on the Hue or Oozie client?

#### Answer

Use UTC time. For example, set **start=2016-12-20T09:00Z** in **job.properties** file.

## 15.7.3 The Update of the share lib Directory of Oozie Does Not Take Effect

### Question

Why cannot a class error be found during task execution after a new JAR file is uploaded to the **/user/oozie/share/lib** directory on HDFS?

### Answer

Restart Oozie to make the directory take effect.

# 16 Using Ranger

---

## 16.1 Logging In to the Ranger Web UI

Ranger provides a centralized permission management framework to implement fine-grained permission control on components such as HDFS, HBase, Hive, and Yarn. In addition, Ranger also provides a web UI for Ranger administrators to perform operations.

### Ranger User Type

Ranger users are classified into **admin**, **user**, and **auditor**. Different users have different permissions to view and operate the Ranger management interface.


- **Admin:** A security administrator can view all page content, manage permission management plug-ins and access control policies, view audit information, and set user types.
- **Auditor:** An audit administrator can view the permission management plug-ins and access control policies.
- **User:** A common user who can be assigned with specific permissions by the administrator.

### Logging In to the Ranger Web UI

Security mode (Kerberos authentication is enabled for clusters)

- Step 1** Log in to FusionInsight Manager as user **admin**. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Ranger**. The Ranger service overview page is displayed.
- Step 2** Click **RangerAdmin** in the **Basic Information** area. The Ranger web UI is displayed.
  - The **admin** user in Ranger belongs to the **User** type and can only view the **Access Manager** as well as **Security Zone** pages.
  - To view all management pages, switch to user **rangeradmin** or other users who have the Ranger administrator permissions.

- a. On the Ranger WebUI, click the user name in the upper right corner and choose **Log Out** to log out of the Ranger WebUI.



- b. Log in to the system as user **rangeradmin** or another user who has the Ranger administrator permissions.

----End

Normal mode (Kerberos authentication is disabled for clusters)

**Step 1** Log in to FusionInsight Manager as user **admin**. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Ranger**. The Ranger service overview page is displayed.

**Step 2** Click **RangerAdmin** in the **Basic Information** area. The Ranger web UI is displayed.

The **admin** user in Ranger belongs to the **Admin** type and can view all management pages of Ranger without switching to user **rangeradmin**.

 **NOTE**

When a user logs in to the Ranger WebUI as user **rangeradmin** in normal mode, error 401 is reported.

----End

On the homepage of Ranger web UI, you can view the permission management plug-ins of the services integrated in Ranger. The plug-ins can be used to set more fine-grained permissions. For details about functions of main operations you can perform on the page, see [Table 16-1](#).

**Table 16-1** Functions of each operation portal on the Ranger page

Portal	Function
Access Manager	You can view the permission management plug-ins of each service integrated in Ranger. The plug-ins can be used to set more fine-grained permissions. For details, see <a href="#">Configuring Component Permission Policies</a> .
Audit	You can view the audit logs related to Ranger running and permission control. For details, see <a href="#">Viewing Ranger Audit Information</a> .
Security Zone	Ranger administrators can divide resources of each component into multiple security zones where different administrators set security policies for specified resources of services to facilitate management. For details, see <a href="#">Configuring a Security Zone</a> .

Portal	Function
Settings	You can view Ranger permission settings, such as users, user groups, and roles. For details, see <a href="#">Viewing Ranger Permission Information</a> .

## 16.2 Enabling Ranger Authentication

### Scenario

This section guides you how to enable Ranger authentication. Ranger authentication is enabled by default in security mode and disabled by default in normal mode.


### Procedure

- Step 1** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Cluster > Services > Name of the service for which Ranger authentication is enabled**.
- Step 2** In the upper right corner of the **Dashboard** page, click **More** and select **Enable Ranger**. In the displayed dialog box, enter the password and click **OK**. After the operation is successful, click **Finish**.

#### NOTE

If **Enable Ranger** is dimmed, Ranger authentication is enabled, as shown in [Figure 16-1](#).

**Figure 16-1** Enabling Ranger Authentication



- Step 3** Perform a rolling service restart or restart the service.

----End

## 16.3 Configuring Component Permission Policies

In the newly installed MRS cluster, Ranger is installed by default, with the Ranger authentication model enabled. The Ranger administrator can set fine-grained security policies for accessing component resources through the component permission plug-ins.

Currently, the following components in a cluster in security mode support Ranger: HDFS, Yarn, HBase, Hive, Spark2x, Kafka, HetuEngine.

### Configuring User Permission Policies Using Ranger

**Step 1** Log in to the Ranger management page as the Ranger administrator.

**Step 2** In the **Service Manager** area on the Ranger homepage, click the permission plug-in name of a component. The page for security access policy list of the component is displayed.

 **NOTE**

In the policy list of each component, many items are generated by default to ensure the permissions of some default users or user groups (such as the **supergroup** user group). Do not delete these items. Otherwise, the permissions of the default users or user groups are affected.

**Step 3** Click **Add New Policy** and configure resource access policies for related users or user groups based on the service scenario plan.

The following policies are examples for different components:

- [Adding a Ranger Access Permission Policy for HDFS](#)
- [Adding a Ranger Access Permission Policy for HBase](#)
- [Adding a Ranger Access Permission Policy for Hive](#)
- [Adding a Ranger Access Permission Policy for Yarn](#)
- [Adding a Ranger Access Permission Policy for Spark2x](#)
- [Adding a Ranger Access Permission Policy for Kafka](#)
- [Adding a Ranger Access Permission Policy for HetuEngine](#)


After the policies are added, wait for about 30 seconds for them to take effect.

 **NOTE**

Each time a component is started, the system checks whether the default Ranger service of the component exists. If the service does not exist, the system creates the Ranger service and adds a default policy for it. If a service is deleted by mistake, you can restart or restart the corresponding component service in rolling mode to restore the service. If the default policy is deleted by mistake, you can manually delete the service and then restart the component service.

**Step 4** Choose **Access Manager > Reports** to view all security access policies of each component.

If there are many system policies, filter and search for policies by the policy name, policy type, component, resource, policy label, security zone, user, or user group. Alternatively, click **Export** to export related policies.



**NOTE**

- Generally, only one policy can be configured for a fixed resource object. If multiple policies are configured for the same resource object, the policies cannot be saved.
- For details about the priorities of different policies, see [Condition Priorities of the Ranger Permission Policy](#).


----End

### Condition Priorities of the Ranger Permission Policy

When configuring a permission policy for a resource, you can configure Allow Conditions, Exclude from Allow Conditions, Deny Conditions, and Exclude from Deny Conditions for the resource, to meet unexpected requirements in different scenarios.

The priorities of different conditions are listed in descending order: Exclude from Deny Conditions > Deny Conditions > Exclude from Allow Conditions > Allow Conditions

The following figure shows the process of determining condition priorities. If the component resource request does not match the permission policy in Ranger, the system rejects the access by default. However, for HDFS and Yarn, the system delivers the decision to the access control layer of the component for determination.



For example, if you want to grant the read and write permissions of the **FileA** folder to the **groupA** user group, but the user in the group is not **UserA**, you can add an allowed condition and an exception condition.

## 16.4 Viewing Ranger Audit Information

The Ranger administrator can view audit logs of the Ranger running and the permission control after Ranger authentication is enabled on the Ranger web UI.

### Viewing Ranger Audit Information

- Step 1** Log in to the Ranger management page.
- Step 2** Click **Audit** to view the audit information. For details about the content on each tab page, see [Table 16-2](#). If there are a large number of items, click the search box and filter the items based on the keyword field.

**Table 16-2** Audit information

Tab	Description
Access	Records audit information about users' access to component resources through Ranger authentication.
Admin	Records operation audit information on Ranger, such as the creation, update, and deletion of security access policies, component permission policies, and roles.
Login Sessions	Records session audit information for users who have logged in to Ranger.
Plugins	Records permission policy information of components in Ranger.
Plugin Status	Records audit information about permission policies of each component node.
User Sync	Records synchronized audit information of LDAP and Ranger users.

----End

## 16.5 Configuring a Security Zone

Security zone can be configured using Ranger. Ranger administrators can divide resources of each component into multiple security zones where administrators set security policies for specified resources in the zones to facilitate management. Policies defined in a security zone apply only to resources in the zone. After service resources are allocated to the security zone, the access permission policies for the resources in the non-security zone do not take effect. The administrator of a security zone can set policies only in the security zone that the administrator belongs to.

## Adding a Security Zone

**Step 1** Log in to the Ranger management page as the Ranger administrator.

**Step 2** Click **Security Zone**. On the zone list page, click  to add a zone.

**Table 16-3** Parameters for configuring a security zone

Parameter	Description	Example Value
Zone Name	Security zone	test
Zone Description	Description of the security zone	-
Admin Users/ Admin Usergroups	Management users and user groups in a security zone. You can add and modify permission policies for related resources in the security zone. At least one user or user group must be configured.	zone_admin
Auditor Users/ Auditor Usergroups	Audit users or user groups to be added. You can view the resource permission policies in the security zone. At least one user or user group must be configured.	zone_user
Select Tag Services	Tag information of a service	-
Select Resource Services	Services and resources in a security zone. After selecting a service, you need to add specific resource objects in the <b>Resource</b> column, such as the file directories of the HDFS server, Yarn queues, Hive databases and tables, Elasticsearch indexes, and HBase tables and columns.	/ testzone

For example, to create a security zone for the **/testzone** directory in HDFS, the configuration is as follows:

**Zone Details :**

---

Zone Name \*

Zone Description

**Zone Administration :**

---

Admin Users

Admin Usergroups

Auditor Users

Auditor Usergroups

**Services :**

---

Select Tag Services

Select Resource Services \*

Service Name	Service Type	Resource
hacluster	HDFS	<input type="text" value="path: /testzone"/> <input type="button" value="✖"/> <input type="button" value="✕"/> <input type="button" value="+"/>

**Step 3** Click **Save** and wait until the security zone is added successfully.


The Ranger administrator can view all security zones on the **Security Zone** page and click **Edit** to modify the attributes of a security zone. If resources do not need to be managed in a security zone, the Ranger administrator can click **Delete** to delete the security zone.

-----End

## Configuring Permission Policies in a Security Zone

**Step 1** Log in to the Ranger management page as the administrator of a security zone.

**Step 2** Select a security zone from the **Security Zone** drop-down list in the upper right corner of the Ranger home page to switch to the permission view of the security zone.




**Step 3** Click the permission plug-in name of a component. The page for security access policy list of the component is displayed.

 **NOTE**

In the policy list of each component, the default items generated by the system are automatically inherited to the security zone to ensure the permissions of some default users or user groups in the cluster.

**Step 4** Click **Add New Policy** and configure resource access policies for related users or user groups based on the service scenario plan.

In this example, a policy that allows user test to access the **/testzone/test** directory is configured in the security zone.



Select Role	Select Group	Select User	Permissions
Select Roles	Select Groups	test	Read Write Execute

The following access policies are examples for different components:

- [Adding a Ranger Access Permission Policy for HDFS](#)
- [Adding a Ranger Access Permission Policy for HBase](#)
- [Adding a Ranger Access Permission Policy for Hive](#)
- [Adding a Ranger Access Permission Policy for Yarn](#)
- [Adding a Ranger Access Permission Policy for Spark2x](#)
- [Adding a Ranger Access Permission Policy for Kafka](#)
- [Adding a Ranger Access Permission Policy for HetuEngine](#)

After the policies are added, wait for about 30 seconds for them to take effect.

 **NOTE**

- Policies defined in a security zone apply only to resources in the zone. After service resources are allocated to the security zone, the access permission policies for the resources in the non-security zone do not take effect.
- To configure access policies for resources outside the current security zone, click **Security Zone** in the upper right corner of the Ranger homepage to exit the current security zone.

----End

## 16.6 Changing the Ranger Data Source to LDAP for a Normal Cluster

By default, the Ranger data source of the security cluster can be accessed by FusionInsight Manager LDAP users. By default, the Ranger data source of a common cluster can be accessed by Unix users.

### Prerequisites

- Check whether the cluster is in normal mode.
- The Ranger component has been installed.

### Procedure

**Step 1** Log in to the MRS management console.

**Step 2** Choose **Clusters > Active Clusters**, select a running cluster, and click its name to switch to the cluster details page.

**Step 3** Click the **Nodes** tab and select the node group whose **Node Type** is **Master**.

**Step 4** Go to the ECS page of the active Master node and click **Remote Login**.

**Step 5** Log in to the active Master node as user **root**, go to the **/opt/Bigdata/components/FusionInsight\_HD\_8.1.2.2/Ranger** directory, and change the value of **ranger.usersync.sync.source** in the **configurations.xml** file to **ldap**.

```
ranger.usersync.sync.source  
<value model="NoSec">ldap</value>
```

**Step 6** Run the following commands on the active Master node to restart the controller process:

```
su - omm
```

```
sh /opt/Bigdata/om-server_8.1.2.2/om/sbin/restart-controller.sh
```

#### NOTE

When the controller process is restarted, the Manager page cannot be accessed for a short period of time, which is normal. After the controller process is restarted, you can access the MRS Manager page properly.

**Step 7** Log in to FusionInsight Manager. For details, see [Accessing FusionInsight Manager](#). Choose **Clusters > Services > Ranger**. In the upper right corner of the **Dashboard** page, click **More** and choose **Synchronize Configuration**.

**Step 8** On the Ranger instance page, select the **UserSync** instance and choose **More > Restart Instance**.

**Step 9** On the **Dashboard** page of the Ranger service, click **RangerAdmin** and choose **Settings > Users/Groups/Roles** to check whether LDAP users exist.

----End

## 16.7 Viewing Ranger Permission Information

You can view Ranger permission settings, such as users, user groups, and roles.

### Viewing Ranger Permission Information

- Step 1** Log in to the Ranger management page as the Ranger administrator.
- Step 2** Choose **Settings > Users/Groups/Roles** to view information about users, user groups, or roles in the system.
- **Users:** displays all user information synchronized from LDAP or OS to Ranger.
  - **Groups:** displays information about all user groups and role information synchronized from LDAP or OS to Ranger.
  - **Roles:** displays information about roles created in Ranger.

 **NOTE**

- The users, roles, user groups created on FusionInsight Manager are automatically synchronized to Ranger periodically. The default period is 300,000 milliseconds (5 minutes). After roles and user groups in FusionInsight Manager are synchronized to Ranger, they become user groups. Only roles and user groups that are associated with users can be automatically synchronized to Ranger.
- The role created on the Ranger page is a set of users or user groups, which is used to flexibly set the permission access policies of components. The role is different from that on FusionInsight Manager.

----End

### Adjusting Ranger User Types

- Step 1** Log in to the Ranger management page.
- To change the Ranger user type, you must log in as an **admin** user. For details about the user types, see [Ranger User Type](#).
- Step 2** Choose **Settings > Users/Groups/Roles**. In the list of users, click the name of the user whose type you want to change.
- Step 3** Set **Select Role** to the type to be modified.
- Step 4** Click **Save**.

----End

### Creating a Ranger Role

The ranger administrator can flexibly configure permission access policies for components based on users, user groups, or roles. User and user group information is automatically synchronized from LDAP, and roles can be manually added.

- Step 1** Log in to the Ranger management page.
- Step 2** Choose **Settings > Users/Groups/Roles > Roles > Add New Role**.

**Step 3** Enter the role name and description as prompted.

**Step 4** Add users, user groups, and sub-roles to the role.

- In the **Users** area, select a created user in the system and click **Add Users**.
- In the **Groups** area, select a created user group and click **Add Group**.
- In the **Roles** area, select a created role in the system and click **Add Role**.

Users:

User Name	Is Role Admin	Action
test01	<input type="checkbox"/>	<input type="button" value="✖"/>

Select User

Groups:

Group Name	Is Role Admin	Action
hadoop	<input type="checkbox"/>	<input type="button" value="✖"/>

Select Group

Roles:

Role Name	Is Role Admin	Action
admin	<input type="checkbox"/>	<input type="button" value="✖"/>

Select Role

**Step 5** Click **Save**. The role is added successfully.

----End

## 16.8 Adding a Ranger Access Permission Policy for HDFS

### Scenario

The ranger administrator can use Ranger to configure the read, write, and execution permissions on HDFS directories or files for HDFS users.

### Prerequisites

- The Ranger service has been installed and is running properly.
- You have created users, user groups, or roles for which you want to configure permissions.

### Procedure

**Step 1** Log in to the Ranger management page.

**Step 2** On the homepage, click the component plug-in name in the **HDFS** area, for example, **hacluster**.

**Step 3** Click **Add New Policy** to add an HDFS permission control policy.


**Step 4** Configure the parameters listed in the table below based on the service demands.

**Table 16-4** HDFS permission parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Resource Path	<p>Resource path, which is the HDFS path folder or file to which the current policy applies. You can enter multiple values and use the wildcard (*), for example, <b>/test/*</b>.</p> <p>To enable a subdirectory to inherit the permission of its upper-level directory, enable the recursion function.</p> <p>If recursion is enabled for the parent directory and a policy is configured for the subdirectory, the policy configured for the subdirectory is used.</p> <ul style="list-style-type: none"> <li>● <b>non-recursive</b>: recursion disabled</li> <li>● <b>recursive</b>: recursion enabled</li> </ul>
Description	Policy description.
Audit Logging	Whether to audit the policy.

Parameter	Description
Allow Conditions	<p>Permission and exception conditions allowed by a policy. The priority of an exception condition is higher than that of a normal condition.</p> <p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the role, user group, or user to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, and click <b>Add Permissions</b> to add the corresponding permission.</p> <ul style="list-style-type: none"> <li>• <b>Read</b>: permission to read data</li> <li>• <b>Write</b>: permission to write data</li> <li>• <b>Execute</b>: execution permission</li> <li>• <b>Select/Deselect All</b>: Select or deselect all.</li> </ul> <p>If users or user groups in the current condition need to manage this policy, select <b>Delegate Admin</b>. These users or user groups will become the agent administrators. The agent administrators can update and delete this policy and create sub-policies based on the original policy.</p> <p>To add multiple permission control rules, click . To delete a permission control rule, click .</p> <p><b>Exclude from Allow Conditions</b>: exception rules excluded from the allowed conditions</p>
Deny All Other Accesses	<p>Whether to reject all other access requests.</p> <ul style="list-style-type: none"> <li>• <b>True</b>: All other access requests are rejected.</li> <li>• <b>False</b>: <b>Deny Conditions</b> can be configured.</li> </ul>
Deny Conditions	<p>Policy rejection condition, which is used to configure the permissions and exceptions to be denied in the policy. The configuration method is the same as that of <b>Allow Conditions</b>. The priority of the rejection condition is higher than that of the allowed conditions configured in <b>Allow Conditions</b>.</p> <p><b>Exclude from Deny Conditions</b>: exception rules excluded from the denied conditions</p>

For example, to add the write permission for the **/user/test** directory of user **testuser**, the configuration is as follows:



**Table 16-5** Setting permissions

Task	Role Authorization
Setting the HDFS administrator permission	<ol style="list-style-type: none"> <li>1. On the homepage, click the component plug-in name in the <b>HDFS</b> area, for example, <b>hacluster</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - path</b> and click  to edit the policy.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> </ol>
Setting the permission for users to check and recover HDFS	<ol style="list-style-type: none"> <li>1. Add a folder or a file path in <b>Resource Path</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Read</b> and <b>Execute</b>.</li> </ol>
Setting the permission for users to read directories or files of other users	<ol style="list-style-type: none"> <li>1. Add a folder or a file path in <b>Resource Path</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Read</b> and <b>Execute</b>.</li> </ol>
Setting the permission for users to write data to files of other users	<ol style="list-style-type: none"> <li>1. Add a folder or a file path in <b>Resource Path</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Write</b> and <b>Execute</b>.</li> </ol>
Setting the permission for users to create or delete sub-files or sub-directories in the directory of other users	<ol style="list-style-type: none"> <li>1. Add a folder or a file path in <b>Resource Path</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Write</b> and <b>Execute</b>.</li> </ol>

Task	Role Authorization
Setting the permission for users to execute directories or files of other users	<ol style="list-style-type: none"> <li>1. Add a folder or a file path in <b>Resource Path</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Execute</b>.</li> </ol>
Setting the permission for allowing subdirectories to inherit all permissions of their parent directories	<ol style="list-style-type: none"> <li>1. Add a folder or a file path in <b>Resource Path</b>.</li> <li>2. Enable the recursion function. <b>Recursive</b> indicates that recursion is enabled.</li> </ol>

**Step 5** (Optional) Add the validity period of the policy. Click **Add Validity period** in the upper right corner of the page, set **Start Time** and **End Time**, and select **Time**

**Zone**. Click **Save**. To add multiple policy validity periods, click . To delete a policy validity period, click .

**Step 6** Click **Add** to view the basic information about the policy in the policy list. After the policy takes effect, check whether the related permissions are normal.

To disable a policy, click  to edit the policy and set the policy to **Disabled**.

If a policy is no longer used, click  to delete it.

----End

## 16.9 Adding a Ranger Access Permission Policy for HBase

### Scenario

Ranger administrators can use Ranger to configure permissions on HBase tables, column families, and columns for HBase users.

### Prerequisites

- The Ranger service has been installed and is running properly.
- You have created users, user groups, or roles for which you want to configure permissions.

### Procedure

**Step 1** Log in to the Ranger management page.

**Step 2** On the home page, click the component plug-in name in the **HBASE** area, for example, **HBase**.

**Step 3** Click **Add New Policy** to add an HBase permission control policy.

**Step 4** Configure the parameters listed in the table below based on the service demands.

**Table 16-6** HBase permission parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
HBase Table	Name of a table to which the policy applies. The value can contain wildcard (*). For example, <b>table1:*</b> indicates all tables in <b>table1</b> . The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object. <b>NOTE</b> The value of <b>hbase.rpc.protection</b> of the HBase service plug-in on Ranger must be the same as that of <b>hbase.rpc.protection</b> on the HBase server. For details, see <a href="#">When an HBase Policy Is Added or Modified on Ranger, Wildcard Characters Cannot Be Used to Search for Existing HBase Tables</a> .
HBase Column-family	Name of the column families to which the policy applies. The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
HBase Column	Name of the column to which the policy applies. The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
Description	Policy description.
Audit Logging	Whether to audit the policy.

Parameter	Description
Allow Conditions	<p>Policy allowed condition. You can configure permissions and exceptions allowed by the policy.</p> <p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the role, user group, or user to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, and click <b>Add Permissions</b> to add the corresponding permission.</p> <ul style="list-style-type: none"> <li>● <b>Read</b>: permission to read data</li> <li>● <b>Write</b>: permission to write data</li> <li>● <b>Create</b>: permission to create data</li> <li>● <b>Admin</b>: permission to manage data</li> <li>● <b>Select/Deselect All</b>: Select or deselect all.</li> </ul> <p>If users or user groups in the current condition need to manage this policy, select <b>Delegate Admin</b>. These users or user groups will become the agent administrators. The agent administrators can update and delete this policy and create sub-policies based on the original policy.</p> <p>To add multiple permission control rules, click . To delete a permission control rule, click .</p> <p>Exclude from Allow Conditions: policy exception conditions</p>
Deny All Other Accesses	<p>Whether to reject all other access requests.</p> <ul style="list-style-type: none"> <li>● <b>True</b>: All other access requests are rejected.</li> <li>● <b>False</b>: <b>Deny Conditions</b> can be configured.</li> </ul>
Deny Conditions	<p>Policy rejection condition, which is used to configure the permissions and exceptions to be denied in the policy. The configuration method is similar to that of <b>Allow Conditions</b>.</p> <p>The priority of <b>Deny Conditions</b> is higher than that of allowed conditions configured in <b>Allow Conditions</b>.</p> <p><b>Exclude from Deny Conditions</b>: exception rules excluded from the denied conditions</p>

**Table 16-7** Setting permissions

Task	Role Authorization
Setting the HBase administrator permission	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>HBase</b> area, for example, <b>HBase</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - table, column-family, column</b> and click  to edit the policy.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> </ol>
Setting the permission for users to create tables	<ol style="list-style-type: none"> <li>1. In <b>HBase Table</b>, specify a table name.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Create</b>.</li> <li>4. This user has the following permissions: create table drop table truncate table alter table enable table flush table flush region compact disable enable desc</li> </ol>
Setting the permission for users to write data to tables	<ol style="list-style-type: none"> <li>1. In <b>HBase Table</b>, specify a table name.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Write</b>.</li> <li>4. The user has the <b>put, delete, append, incr</b> and <b>bulkload</b> operation permissions.</li> </ol>
Setting the permission for users to read data from tables	<ol style="list-style-type: none"> <li>1. In <b>HBase Table</b>, specify a table name.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Read</b>.</li> <li>4. This user has the <b>get</b> and <b>scan</b> permissions.</li> </ol>

Task	Role Authorization
Setting the permission for users to manage namespaces or tables	<ol style="list-style-type: none"> <li>1. In <b>HBase Table</b>, specify a table name.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Admin</b>.</li> <li>4. The user has the <b>rsgroup, peer, assign</b> and <b>balance</b> operation permissions.</li> </ol>
Setting the permission for reading data from or writing data to columns	<ol style="list-style-type: none"> <li>1. In <b>HBase Table</b>, specify a table name.</li> <li>2. In <b>HBase Column-family</b>, specify the column family name.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Read</b> and <b>Write</b>.</li> </ol>

 **NOTE**

If a user performs the **desc** operation in **hbase shell**, the user must be granted the read permission on the **hbase:quota** table.

**Step 5** (Optional) Add the validity period of the policy. Click **Add Validity period** in the upper right corner of the page, set **Start Time** and **End Time**, and select **Time Zone**. Click **Save**. To add multiple policy validity periods, click . To delete a policy validity period, click .

**Step 6** Click **Add** to view the basic information about the policy in the policy list. After the policy takes effect, check whether the related permissions are normal.

To disable a policy, click  to edit the policy and set the policy to **Disabled**.

If a policy is no longer used, click  to delete it.

----End

## 16.10 Adding a Ranger Access Permission Policy for Hive

### Scenario

The ranger administrator can use Ranger to set permissions for Hive users. The default administrator account of Hive is **hive** and the initial password is **Hive@123**.

## Prerequisites

- The Ranger service has been installed and is running properly.
- You have created users, user groups, or roles for which you want to configure permissions.
- The users must be added to the **hive** group.

## Procedure

- Step 1** Log in to the Ranger management page.
- Step 2** On the home page, click the component plug-in name in the **HADOOP SQL** area, for example, **Hive**.
- Step 3** On the **Access** tab page, click **Add New Policy** to add a Hive permission control policy.
- Step 4** Configure the parameters listed in the table below based on the service demands.

**Table 16-8** Hive permission parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
database	Name of the Hive database to which the policy applies. The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
table	Name of the Hive table to which the policy applies. To add a UDF-based policy, switch to UDF and enter the UDF name. The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
Hive Column	Name of the column to which the policy applies. The value * indicates all columns. The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
Description	Policy description.
Audit Logging	Whether to audit the policy.

Parameter	Description
Allow Conditions	<p>Policy allowed condition. You can configure permissions and exceptions allowed by the policy.</p> <p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the role, user group, or user to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, and click <b>Add Permissions</b> to add the corresponding permission.</p> <ul style="list-style-type: none"> <li>● select: permission to query data</li> <li>● update: permission to update data</li> <li>● Create: permission to create data</li> <li>● Drop: permission to drop data</li> <li>● Alter: permission to alter data</li> <li>● Index: permission to index data</li> <li>● All: all permissions</li> <li>● Read: permission to read data</li> <li>● Write: permission to write data</li> <li>● Temporary UDF Admin: temporary UDF management permission</li> <li>● Select/Deselect All: Select or deselect all.</li> </ul> <p>To add multiple permission control rules, click .</p> <p>If users or user groups in the current condition need to manage this policy, select <b>Delegate Admin</b>. These users will become the agent administrators. The agent administrators can update and delete this policy and create sub-policies based on the original policy.</p>
Deny Conditions	<p>Policy rejection condition, which is used to configure the permissions and exceptions to be denied in the policy. The configuration method is similar to that of <b>Allow Conditions</b>.</p>

**Table 16-9** Setting permissions

Task	Role Authorization
<p><b>role admin</b> operation</p>	<ol style="list-style-type: none"> <li>1. On the home page, click <b>Settings</b> and choose <b>Roles</b>.</li> <li>2. Click the role with <b>Role Name</b> set to <b>admin</b>. In the <b>Users</b> area, click <b>Select User</b> and select a username.</li> <li>3. Click <b>Add Users</b>, select <b>Is Role Admin</b> in the row where the username is located, and click <b>Save</b>.</li> </ol> <p><b>NOTE</b> Only user <b>rangeradmin</b> has the permission to access the <b>Settings</b> option on the Ranger page. After being bound to the Hive administrator role, perform the following operations during each maintenance operation:</p> <ol style="list-style-type: none"> <li>1. Log in to the node where the Hive client is installed as the client installation user.</li> <li>2. Run the following command to configure environment variables: For example, if the Hive client installation directory is <b>/opt/hiveclient</b>, run <b>source /opt/hiveclient/bigdata_env</b>.</li> <li>3. Run the following command to authenticate the user: <b>kinit Hive service user</b></li> <li>4. Run the following command to log in to the client tool: <b>beeline</b></li> <li>5. Run the following command to update the administrator permissions: <b>set role admin;</b></li> </ol>
<p>Creating a database table</p>	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter or select the corresponding database on the right side of <b>database</b> and enter or select * on the right side of <b>column</b>. (To create a table, enter or select the corresponding table on the right side of <b>table</b>.)</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Create</b>.</li> </ol>
<p>Deleting a table</p>	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter or select the corresponding database on the right side of <b>database</b> and enter and select * on the right side of <b>column</b>. (To delete a table, enter or select the corresponding table on the right side of <b>table</b>.)</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Drop</b>.</li> </ol>

Task	Role Authorization
Query operation ( <b>select</b> , <b>desc</b> , and <b>show</b> )	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter or select the corresponding database on the right side of <b>database</b> and enter or select * (* indicates all columns) on the right side of <b>column</b>. (To create a table, enter or select the corresponding table on the right side of <b>table</b>.)</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>select</b>.</li> </ol>
<b>Alter</b> operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter and select the corresponding database on the right side of <b>database</b> and enter or select * on the right side of <b>column</b>. (For tables, enter or select the corresponding table on the right side of <b>table</b>.)</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Alter</b>.</li> </ol>
<b>LOAD</b> operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. On the right side of <b>database</b>, enter or select the corresponding database. On the right side of <b>table</b>, enter or select the corresponding table. On the right side of <b>column</b>, enter a column and select *.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>update</b>.</li> </ol>
<b>INSERT</b> and <b>DELETE</b> operations	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. On the right side of <b>database</b>, enter or select the corresponding database. On the right side of <b>table</b>, enter or select the corresponding table. On the right side of <b>column</b>, enter a column and select *.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>update</b>.</li> <li>5. Configure the <b>submit</b> permission on the Yarn task queue. For details about how to configure the permission, see <a href="#">Adding a Ranger Access Permission Policy for Yarn</a>.</li> </ol>

Task	Role Authorization
GRANT/REVOKE operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. On the right side of <b>database</b>, enter or select the corresponding database. On the right side of <b>table</b>, enter or select the corresponding table. On the right side of <b>column</b>, enter a column and select *.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Select <b>Delegate Admin</b>.</li> </ol>
ADD JAR operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Click <b>database</b>, and select <b>global</b> from the drop-down list. On the right of <b>global</b>, enter related information or select *.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Temporary UDF Admin</b>.</li> </ol>
UDF operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter or select the corresponding database on the right of <b>database</b>, and enter the corresponding udf function name on the right of <b>udf</b>.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select required permissions for the user (<b>udf</b> supports the <b>Create</b>, <b>select</b>, and <b>Drop</b> permissions).</li> </ol>
VIEW operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. On the right side of <b>database</b>, enter or select the corresponding database. On the right side of <b>table</b>, enter or select the corresponding table to be viewed. On the right side of <b>column</b>, enter a column and select *.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select permissions for the user as required.</li> </ol>
dfs command operation	<p>The <b>dfs</b> operation can be performed only after you have run the <b>set role admin</b> command.</p>
Operations on other user database tables	<ol style="list-style-type: none"> <li>1. Perform the preceding operations to add the corresponding permissions.</li> <li>2. Grant the read, write, and execution permissions on the HDFS paths of other user database tables to the user. For details, see <a href="#">Adding a Ranger Access Permission Policy for HDFS</a>.</li> </ol>

 **NOTE**

- If you have specified an HDFS path when running commands, you need to be granted with the read, write, and execution permissions on the HDFS paths. For details, see [Adding a Ranger Access Permission Policy for HDFS](#). You do not need to configure the Ranger policy of HDFS. You can use the Hive permission plug-in to add permissions to the role and assign the role to the corresponding user. If the HDFS Ranger policy can match the file or directory permission of the Hive database table, the HDFS Ranger policy is preferentially used.
- The URL policy in the Ranger policy is involved in the scenario where the Hive table is stored on OBS. Set the URL to the complete path of the object on OBS. The Read and Write permissions are used together with the URL. URL policies are not involved in other scenarios.
- The global policy in the Ranger policy is used only with the **Temporary UDF Admin** permission to control the upload of UDF packages.
- The **hiveservice** policy in the Ranger policy is used only with the **Service Admin** permission to control the permission to run the **kill query <queryId>** command to end the task that is being executed.
- The **lock**, **index**, **refresh**, and **replAdmin** permissions are not supported.
- Run the **show grant** command to view the table permission. The **grantor** column of the table **owner** is displayed as user **hive**. If the Ranger page is used or the **grant** command is used to grant permissions in the background, the **grantor** column is displayed as the corresponding user. To view the result of using the Hive permission plug-in, set **hive-ext.ranger.previous.privileges.enable** to **true** and run the **show grant** command.

**Step 5** Click **Add** to view the basic information about the policy in the policy list. After the policy takes effect, check whether the related permissions are normal.

To disable a policy, click  to edit the policy and set the policy to **Disabled**.

If a policy is no longer used, click  to delete it.

----End

## Hive Data Masking

Ranger supports data masking for Hive data. It can process the returned result of the **select** operation you performed to mask sensitive information.

**Step 1** Log in to the Ranger web UI. Click **Hive** in the **HADOOP SQL** area on the homepage.

**Step 2** On the **Masking** tab page, click **Add New Policy** to add a Hive permission control policy.

**Step 3** Configure the parameters listed in the table below based on the service demands.

**Table 16-10** Hive data masking parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.

Parameter	Description
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Hive Database	Name of the Hive database to which the current policy applies.
Hive Table	Name of the Hive table to which the current policy applies.
Hive Column	Column name.
Description	Policy description.
Audit Logging	Whether to audit the policy.
Mask Conditions	<p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the object to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, then click <b>Add Permissions</b>, and select <b>select</b>. Click <b>Select Masking Option</b> and select a data masking policy.</p> <ul style="list-style-type: none"> <li>• Redact: Use <b>x</b> to mask all letters and <b>n</b> to mask all digits.</li> <li>• Partial mask: show last 4: Only the last four characters are displayed, and the rest characters are displayed using <b>x</b>.</li> <li>• Partial mask: show first 4: Only the first four characters are displayed, and the rest characters are displayed using <b>x</b>.</li> <li>• Hash: Replace the original value with the hash value. The Hive built-in function <b>mask_hash</b> is used. This is valid only for fields of the string, character, and varchar types. NULL is returned for fields of other types.</li> <li>• Nullify: Replace the original value with the NULL value.</li> <li>• Unmasked (retain original value): Keep the original value.</li> <li>• Date: show only year: Only the year part of the date string is displayed, and the default month and date start from January and Monday (<b>01/01</b>).</li> <li>• Custom: You customize policies using any valid return data type which is the same as the data type in the masked column.</li> </ul> <p>To add a multi-column masking policy, click .</p>

**Step 4** Click **Add** to view the basic information about the policy in the policy list.

**Step 5** After you perform the **select** operation on a table configured with a data masking policy on the Hive client, the system processes and displays the data.

 **NOTE**


To process data, you must have the permission to submit tasks to the Yarn queue.

----End

## Hive Row-Level Data Filtering

Ranger allows you to filter data at the row level when you perform the **select** operation on Hive data tables.

- Step 1** Log in to the Ranger web UI. Click **Hive** in the **HADOOP SQL** area on the homepage.
- Step 2** On the **Row Level Filter** tab page, click **Add New Policy** to add a row data filtering policy.



- Step 3** Configure the parameters listed in the table below based on the service demands.

**Table 16-11** Parameters for filtering Hive row data

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Hive Database	Name of the Hive database to which the current policy applies.
Hive Table	Name of the Hive table to which the current policy applies.
Description	Policy description.
Audit Logging	Whether to audit the policy.

Parameter	Description
Row Filter Conditions	<p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the object to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, then click <b>Add Permissions</b>, and select <b>Select</b>. Click <b>Row Level Filter</b> and enter data filtering rules.</p> <p>For example, if you want to filter the data in the <b>zhangsan</b> row in the <b>name</b> column of <b>table A</b>, the filtering rule is <b>name &lt;&gt;'zhangsan'</b>. For more information, see the official Ranger document.</p> <p>To add more rules, click .</p>

**Step 4** Click **Add** to view the basic information about the policy in the policy list.

**Step 5** After you perform the **select** operation on a table configured with a data masking policy on the Hive client, the system processes and displays the data.

 **NOTE**

To process data, you must have the permission to submit tasks to the Yarn queue.

----End

## 16.11 Adding a Ranger Access Permission Policy for Yarn

### Scenario

The ranger administrator can use Ranger to configure Yarn administrator permissions for Yarn users, allowing them to manage Yarn queue resources.

### Prerequisites

- The Ranger service has been installed and is running properly.
- You have created users, user groups, or roles for which you want to configure permissions.

### Procedure

**Step 1** Log in to FusionInsight Manager, choose **Cluster > Services > Yarn**.

**Step 2** Choose **Configurations > All Configurations**. Search for the parameter **yarn.acl.enable** and change the value to **true**. If the value of this parameter is true, no action is required.

**Step 3** Log in to the Ranger management page.

**Step 4** On the home page, click the component plug-in name in the **YARN** area, for example, **Yarn**.

**Step 5** Click **Add New Policy** to add a Yarn permission control policy.

**Step 6** Configure the parameters listed in the table below based on the service demands.

**Table 16-12** Yarn permission parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10,192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Queue	Queue name. The wildcard (*) is supported. To enable a sub-queue to inherit the permission of its upper-level queue, enable the recursion function. <ul style="list-style-type: none"> <li>● <b>Non-recursive</b>: recursion disabled</li> <li>● <b>Recursive</b>: recursion enabled</li> </ul>
Description	Policy description.
Audit Logging	Whether to audit the policy.
Allow Conditions	<p>Policy allowed condition. You can configure permissions and exceptions allowed by the policy.</p> <p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the role, user group, or user to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, and click <b>Add Permissions</b> to add the corresponding permission.</p> <ul style="list-style-type: none"> <li>● submit-app: permission to submit queue tasks</li> <li>● admin-queue: permission to manage queue tasks</li> <li>● Select/Deselect All: Select or deselect all.</li> </ul> <p>If users or user groups in the current condition need to manage this policy, select <b>Delegate Admin</b>. These users will become the agent administrators. The agent administrators can update and delete this policy and create sub-policies based on the original policy.</p> <p>To add multiple permission control rules, click . To delete a permission control rule, click .</p> <p>Exclude from Allow Conditions: policy exception conditions</p>

Parameter	Description
Deny All Other Accesses	Whether to reject all other access requests. <ul style="list-style-type: none"> <li>• True: All other access requests are rejected.</li> <li>• <b>False: Deny Conditions</b> can be configured.</li> </ul>
Deny Conditions	Policy rejection condition, which is used to configure the permissions and exceptions to be denied in the policy. The configuration method is similar to that of <b>Allow Conditions</b> . The priority of <b>Deny Conditions</b> is higher than that of allowed conditions configured in <b>Allow Conditions</b> . Exclude from Deny Conditions: exception rules excluded from the denied conditions

**Table 16-13** Setting permissions

Task	Role Authorization
Setting the Yarn administrator permission	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>YARN</b> area, for example, <b>Yarn</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - queue</b> and click  to edit the policy.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> </ol>
Setting the permission for a user to submit tasks in a specified Yarn queue	<ol style="list-style-type: none"> <li>1. In <b>Queue</b>, specify a queue name.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>submit-app</b>.</li> </ol>
Setting the permission for a user to manage tasks in a specified Yarn queue	<ol style="list-style-type: none"> <li>1. In <b>Queue</b>, specify a queue name.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>admin-queue</b>.</li> </ol>

**Step 7** (Optional) Add the validity period of the policy. Click **Add Validity period** in the upper right corner of the page, set **Start Time** and **End Time**, and select **Time Zone**. Click **Save**. To add multiple policy validity periods, click . To delete a policy validity period, click .

**Step 8** Click **Add** to view the basic information about the policy in the policy list. After the policy takes effect, check whether the related permissions are normal.

To disable a policy, click  to edit the policy and set the policy to **Disabled**.

If a policy is no longer used, click  to delete it.

----End

 NOTE

The permissions on Ranger Yarn are independent of each other. There is inclusion relationship among the permissions. Currently, the following permissions are supported:

- **submit-app**: permission to submit queue tasks
- **admin-queue**: permission to manage queue tasks

Although the **admin-queue** has the permission to submit tasks, it does not have the inclusion relationship with the **submit-app** permission.

## 16.12 Adding a Ranger Access Permission Policy for Spark2x

### Scenario

The ranger administrator can use Ranger to set permissions for Spark2x users.

 NOTE

1. After Ranger authentication is enabled or disabled on Spark2x, you need to restart Spark2x.
2. Download the client again or manually update the client configuration file *Client installation directory*/**Spark2x/spark/conf/spark-defaults.conf**.  
Enable Ranger: **spark.ranger.plugin.authorization.enable=true**  
Disable Ranger: **spark.ranger.plugin.authorization.enable=false**
3. In Spark2x, spark-beeline (applications connected to JDBCServer) supports the Ranger IP address filtering policy (**Policy Conditions** in the Ranger permission policy), while spark-submit and spark-sql do not.

### Prerequisites

- The Ranger service has been installed and is running properly.
- The Ranger authentication function of the Hive service has been enabled. After the Hive service is restarted, the Spark2x service is restarted.
- You have created users, user groups, or roles for which you want to configure permissions.
- The created user has been added to the **hive** user group.

### Procedure

- Step 1** Log in to the Ranger management page.
- Step 2** On the home page, click the component plug-in name in the **HADOOP SQL** area, for example, **Hive**.
- Step 3** On the **Access** tab page, click **Add New Policy** to add a Spark2x permission control policy.

**Step 4** Configure the parameters listed in the table below based on the service demands.

**Table 16-14** Spark2x permission parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
database	Name of the Spark2x database to which the policy applies. The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
table	Name of the Spark2x table to which the policy applies. To add a UDF-based policy, switch to UDF and enter the UDF name. The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
column	Name of the column to which the policy applies. The value * indicates all columns. The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
Description	Policy description.
Audit Logging	Whether to audit the policy.

Parameter	Description
Allow Conditions	<p>Policy allowed condition. You can configure permissions and exceptions allowed by the policy.</p> <p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the role, user group, or user to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, and click <b>Add Permissions</b> to add the corresponding permission.</p> <ul style="list-style-type: none"> <li>● select: permission to query data</li> <li>● update: permission to update data</li> <li>● Create: permission to create data</li> <li>● Drop: permission to drop data</li> <li>● Alter: permission to alter data</li> <li>● Index: permission to index data</li> <li>● All: all permissions</li> <li>● Read: permission to read data</li> <li>● Write: permission to write data</li> <li>● Temporary UDF Admin: temporary UDF management permission</li> <li>● Select/Deselect All: Select or deselect all.</li> </ul> <p>To add multiple permission control rules, click  .</p> <p>If users or user groups in the current condition need to manage this policy, select <b>Delegate Admin</b>. These users will become the agent administrators. The agent administrators can update and delete this policy and create sub-policies based on the original policy.</p>
Deny Conditions	<p>Policy rejection condition, which is used to configure the permissions and exceptions to be denied in the policy. The configuration method is similar to that of <b>Allow Conditions</b>.</p>

**Table 16-15** Setting permissions

Task	Operation
<p><b>role admin</b> operation</p>	<ol style="list-style-type: none"> <li>1. On the home page, click <b>Settings</b> and choose <b>Roles &gt; Add New Role</b>.</li> <li>2. Set <b>Role Name</b> to <b>admin</b>. In the <b>Users</b> area, click <b>Select User</b> and select a username.</li> <li>3. Click <b>Add Users</b>, select <b>Is Role Admin</b> in the row where the username is located, and click <b>Save</b>.</li> </ol> <p><b>NOTE</b> After being bound to the Hive administrator role, perform the following operations during each maintenance operation:</p> <ol style="list-style-type: none"> <li>1. Log in to the node where the Hive client is installed as the client installation user.</li> <li>2. Run the following command to configure environment variables: For example, if the Spark2x client installation directory is <b>/opt/client</b>, run <b>source /opt/client/bigdata_env</b>.</li> <li>3. Run the following command to perform user authentication: <b>kinit Spark2xService user</b></li> <li>4. Run the following command to log in to the client tool: <b>spark-beeline</b></li> <li>5. Run the following command to update the administrator permissions: <b>set role admin;</b></li> </ol>
<p>Creating a database table</p>	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter and select the corresponding database on the right of <b>database</b>. (If you want to create a database, enter the name of the database to be created or enter <b>*</b> to indicate a database with any name, and then select the name.) Enter and select the corresponding table name on the right of <b>table</b> and <b>column</b>. Wildcard characters (<b>*</b>) are supported.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Create</b>.</li> </ol>

Task	Operation
Deleting a table	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter and select the corresponding database on the right of <b>database</b>. (If you want to delete a database, enter the name of the database to be created or enter * to indicate a database with any name, and then select the name.) Enter and select the corresponding table name on the right of <b>table</b> and <b>column</b>. Wildcard characters (*) are supported.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Drop</b>.</li> </ol> <p><b>NOTE</b> For CarbonData tables, only the owner of the corresponding database or table can perform the <b>drop</b> operation.</p>
<b>ALTER</b> operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter and select the corresponding database on the right of <b>database</b>, enter and select the corresponding table on the right of <b>table</b>, and enter and select the corresponding column name on the right of <b>column</b>. Wildcard characters (*) are supported.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Alter</b>.</li> </ol>
<b>LOAD</b> operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter and select the corresponding database on the right of <b>database</b>, enter and select the corresponding table on the right of <b>table</b>, and enter and select the corresponding column name on the right of <b>column</b>. Wildcard characters (*) are supported.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>update</b>.</li> </ol>

Task	Operation
INSERT operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter and select the corresponding database on the right of <b>database</b>, enter and select the corresponding table on the right of <b>table</b>, and enter and select the corresponding column name on the right of <b>column</b>. Wildcard characters (*) are supported.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>update</b>.</li> <li>5. The user also needs to have the <b>submit-app</b> permission of the Yarn task queue. By default, the Hadoop user group has the <b>submit-app</b> permission of all Yarn task queues. For details about how to load a network instance to a cloud connection, see <a href="#">Adding a Ranger Access Permission Policy for Yarn</a>.</li> </ol>
GRANT operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter and select the corresponding database on the right of <b>database</b>, enter and select the corresponding table on the right of <b>table</b>, and enter and select the corresponding column name on the right of <b>column</b>. Wildcard characters (*) are supported.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Select <b>Delegate Admin</b>.</li> </ol>
ADD JAR operation	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Click <b>database</b>, and select <b>global</b> from the drop-down list. On the right of <b>global</b>, enter related information and select <b>*</b>.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Select/Deselect All</b>.</li> </ol>

Task	Operation
<b>VIEW</b> and <b>INDEX</b> permissions	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. On the right side of <b>database</b>, enter the database name and select the corresponding database. (If you want to delete a database, enter the database name and select *.) On the right side of <b>table</b>, enter a table name and select the view and index names. On the right side of <b>column</b>, enter a Hive column name, and select *.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select permissions for the user as required.</li> </ol>
Operations on other user database tables	<ol style="list-style-type: none"> <li>1. Perform the preceding operations to add the corresponding permissions.</li> <li>2. Grant the read, write, and execution permissions on the HDFS paths of other user database tables to the current user. For details, see <a href="#">Adding a Ranger Access Permission Policy for HDFS</a>.</li> </ol>

 **NOTE**

After Spark SQL access policy is added on Ranger, you need to add the corresponding path access policies in the HDFS access policy. Otherwise, data files cannot be accessed. For details, see [Adding a Ranger Access Permission Policy for HDFS](#).

- The global policy in the Ranger policy is only used to associate with the **Temporary UDF Admin** permission to control the upload of UDF packages.
- When Ranger is used to control Spark SQL permissions, the **empower** syntax is not supported.

**Step 5** Click **Add** to view the basic information about the policy in the policy list. After the policy takes effect, check whether the related permissions are normal.

To disable a policy, click  to edit the policy and set the policy to **Disabled**.

If a policy is no longer used, click  to delete it.

----End

## Data Masking of the Spark2x Table

Ranger supports data masking for Spark2x data. It can process the returned result of the **select** operation you performed to mask sensitive information.

**Step 1** Log in to the Ranger WebUI and click the component plug-in name, for example, **Hive**, in the **HADOOP SQL** area on the home page.

**Step 2** On the **Masking** tab page, click **Add New Policy** to add a Spark2x permission control policy.

**Step 3** Configure the parameters listed in the table below based on the service demands.

**Table 16-16** Spark2x data masking parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Hive Database	Name of the Spark2x database to which the current policy applies.
Hive Table	Name of the Spark2x table to which the current policy applies.
Hive Column	Name of the Spark2x column to which the current policy applies.
Description	Policy description.
Audit Logging	Whether to audit the policy.

Parameter	Description
Mask Conditions	<p>In the <b>Select Group</b> and <b>Select User</b> columns, select the user group or user to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, then click <b>Add Permissions</b>, and select <b>select</b>.</p> <p>Click <b>Select Masking Option</b> and select a data masking policy.</p> <ul style="list-style-type: none"> <li>● Redact: Use <b>x</b> to mask all letters and <b>n</b> to mask all digits.</li> <li>● Partial mask: show last 4: Only the last four characters are displayed.</li> <li>● Partial mask: show first 4: Only the first four characters are displayed.</li> <li>● Hash: Perform hash calculation for data.</li> <li>● Nullify: Replace the original value with the NULL value.</li> <li>● Unmasked(retain original value): The original data is displayed.</li> <li>● Date: show only year: Only the year information is displayed.</li> <li>● Custom: You can use any valid Hive UDF (returns the same data type as the data type in the masked column) to customize the policy.</li> </ul> <p>To add a multi-column masking policy, click .</p>
Deny Conditions	<p>Policy rejection condition, which is used to configure the permissions and exceptions to be denied in the policy. The configuration method is similar to that of <b>Allow Conditions</b>.</p>

----End

## Spark2x Row-Level Data Filtering

Ranger allows you to filter data at the row level when you perform the **select** operation on Spark2x data tables.

- Step 1** Log in to the Ranger WebUI and click the component plug-in name, for example, **Hive**, in the **HADOOP SQL** area on the home page.
- Step 2** On the **Row Level Filter** tab page, click **Add New Policy** to add a row data filtering policy.
- Step 3** Configure the parameters listed in the table below based on the service demands.

**Table 16-17** Parameters for filtering Spark2x row data

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Hive Database	Name of the Spark2x database to which the current policy applies.
Hive Table	Name of the Spark2x table to which the current policy applies.
Description	Policy description.
Audit Logging	Whether to audit the policy.
Row Filter Conditions	<p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the object to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, then click <b>Add Permissions</b>, and select <b>select</b>. Click <b>Row Level Filter</b> and enter data filtering rules.</p> <p>For example, if you want to filter the data in the <b>zhangsan</b> row in the <b>name</b> column of <b>table A</b>, the filtering rule is <b>name &lt;&gt;'zhangsan'</b>. For more information, see the official Ranger document.</p> <p>To add more rules, click .</p>

**Step 4** Click **Add** to view the basic information about the policy in the policy list.

**Step 5** After you perform the **select** operation on a table configured with a data masking policy on the Spark2x client, the system processes and displays the data.

----End

## 16.13 Adding a Ranger Access Permission Policy for Kafka

### Scenario

The ranger administrator can use Ranger to configure the read, write, and management permissions of the Kafka topic and the management permission of the cluster for the Kafka user. This section describes how to add the production permission of the **test** topic for the **test** user.

## Prerequisites

- The Ranger service has been installed and is running properly.
- You have created users, user groups, or roles for which you want to configure permissions.

## Procedure

- Step 1** Log in to the Ranger management page.
- Step 2** On the home page, click the component plug-in name in the **KAFKA** area, for example, **Kafka**.
- Step 3** Click **Add New Policy** to add a Kafka permission control policy.
- Step 4** Configure the following parameters based on the service demands.


**Table 16-18** Kafka permission parameters

Parameter	Description
Policy Type	Access type.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
topic	Name of the topic applicable to the current policy. You can enter multiple values. The value can contain wildcards, such as <b>test</b> , <b>test*</b> , and <b>*</b> .  The <b>Include</b> policy applies to the current input object, and the <b>Exclude</b> policy applies to objects other than the current input object.
Description	Policy description.
Audit Logging	Whether to audit the policy.

Parameter	Description
Allow Conditions	<p>Permission and exception conditions allowed by a policy. The priority of an exception condition is higher than that of a normal condition.</p> <p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the role, user group, or user to which you want to assign permissions.</p> <p>Click <b>Add Conditions</b>, add the IP address range to which the policy applies, and click <b>Add Permissions</b> to add corresponding permissions.</p> <ul style="list-style-type: none"> <li>● Publish: production permission</li> <li>● Consume: consumption permission</li> <li>● Describe: query permission</li> <li>● Create: topic creation permission</li> <li>● Delete: topic deletion permission</li> <li>● Describe Configs: configuration query permission</li> <li>● Alter: permission to change the number of partitions of a topic.</li> <li>● Alter Configs: configuration modification permission</li> <li>● Select/Deselect All: Select or deselect all.</li> </ul> <p>To add multiple permission control rules, click .</p> <p>If users or user groups in the current condition need to manage this policy, select <b>Delegate Admin</b>. These users will become the agent administrators. The agent administrators can update and delete this policy and create sub-policies based on the original policy.</p>
Deny Conditions	<p>Policy rejection condition, which is used to configure the permissions and exceptions to be denied in the policy. The configuration method is the same as that of <b>Allow Conditions</b>. The priority of the rejection condition is higher than that of the allowed conditions configured in <b>Allow Conditions</b>.</p>

For example, to add the production permission for the **test** topic of user **testuser**, configure the following information:

**Figure 16-2** Kafka permission parameters



**Table 16-19** Setting permissions

Scenario	Role Authorization
Setting the Kafka administrator permissions	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>KAFKA</b> area, for example, <b>Kafka</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - topic</b> and click  to edit the policy.</li> <li>3. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>4. Click <b>Add Permissions</b> and select <b>Select/ Deselect All</b>.</li> </ol>
Setting the permission for a user to create a topic	<ol style="list-style-type: none"> <li>1. Specify a topic name in <b>topic</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Create</b>.</li> </ol> <p><b>NOTE</b> Currently, the Kafka kernel supports the <b>--zookeeper</b> and <b>--bootstrap-server</b> methods to create topics. The <b>--zookeeper</b> method will be deleted from the community in later versions. Therefore, you are advised to use the <b>--bootstrap-server</b> method to create topics.</p> <p>Note: Currently, Kafka supports only the authentication of topic creation in <b>--bootstrap-server</b> mode and does not support that in <b>--zookeeper</b> mode.</p>

Scenario	Role Authorization
Setting the permission for a user to delete a topic	<ol style="list-style-type: none"> <li>1. Specify a topic name in <b>topic</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Delete</b>.</li> </ol> <p><b>NOTE</b> Currently, the Kafka kernel supports the <b>--zookeeper</b> and <b>--bootstrap-server</b> methods to delete topics. The <b>--zookeeper</b> method will be deleted from the community in later versions. Therefore, you are advised to use the <b>--bootstrap-server</b> method to delete topics.</p> <p>Note: Currently, Kafka supports only the authentication of topic deletion in <b>--bootstrap-server</b> mode and does not support that in <b>--zookeeper</b> mode.</p>
Setting the permission for a user to query a topic	<ol style="list-style-type: none"> <li>1. Specify a topic name in <b>topic</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Describe</b> and <b>Describe Configs</b>.</li> </ol> <p><b>NOTE</b> Currently, the Kafka kernel supports the <b>--zookeeper</b> and <b>--bootstrap-server</b> methods to query topics. The <b>--zookeeper</b> method will be deleted from the community in later versions. Therefore, you are advised to use the <b>--bootstrap-server</b> method to query topics.</p> <p>Note: Currently, Kafka supports only the authentication of topic query in <b>--bootstrap-server</b> mode and does not support that in <b>--zookeeper</b> mode.</p>
Setting the production permission of a user on a topic	<ol style="list-style-type: none"> <li>1. Specify a topic name in <b>topic</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Publish</b>.</li> </ol>
Setting the consumption permission of a user on a topic	<ol style="list-style-type: none"> <li>1. Specify a topic name in <b>topic</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Consume</b>.</li> </ol> <p><b>NOTE</b> During topic consumption, offset management is involved. Therefore, the <b>Consume</b> permission of <b>ConsumerGroup</b> must be enabled at the same time. For details, see <b>Setting a User's Permission to Submit ConsumerGroup Offsets</b>.</p>
Setting the permission for a user to expand a topic (by adding partitions)	<ol style="list-style-type: none"> <li>1. Specify a topic name in <b>topic</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Alter</b>.</li> </ol>

Scenario	Role Authorization
Setting the permission for a user to modify the topic configuration	Currently, the Kafka kernel does not support to modify topic parameters based on <b>--bootstrap-server</b> . Therefore, Ranger does not support authentication for this behavior.
Setting all the management permissions of a user on a cluster	<ol style="list-style-type: none"> <li>1. Enter a cluster name and select the cluster on the right side of <b>cluster</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Kafka Admin</b>.</li> </ol>
Setting the permission for a user to create a cluster	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>KAFKA</b> area, for example, <b>Kafka</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - cluster</b> and click  to edit the policy.</li> <li>3. Enter a cluster name and select the cluster on the right side of <b>cluster</b>.</li> <li>4. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>5. Click <b>Add Permissions</b> and select <b>Create</b>.</li> </ol> <p><b>NOTE</b> The authentication of the <b>Create</b> operation of a cluster involves the following two scenarios:</p> <ol style="list-style-type: none"> <li>1. After the <b>auto.create.topics.enable</b> parameter is enabled in the cluster, the client sends data to a topic that has not been created in the service. In this case, the system checks whether the user has the <b>Create</b> permission of the cluster.</li> <li>2. If a user creates a large number of topics and is granted the <b>Cluster Create</b> permission, the user can create any topic in the cluster.</li> </ol>
Setting the permission for a user to modify the cluster configuration	<ol style="list-style-type: none"> <li>1. Enter a cluster name and select the cluster on the right side of <b>cluster</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Alter Configs</b>.</li> </ol> <p><b>NOTE</b> The configuration modification permission allows you to modify the Broker and Broker Logger configurations. After the configuration modification permission is granted to a user, the user can query configuration details even if the user does not have the query permission. (The configuration modification permission includes the configuration query permission.)</p>

Scenario	Role Authorization
<p>Setting the permission for a user to query the cluster configuration</p>	<ol style="list-style-type: none"> <li>1. Enter a cluster name and select the cluster on the right side of <b>cluster</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Describe</b> and <b>Describe Configs</b>.</li> </ol> <p><b>NOTE</b> You can only query Broker and Broker Logger information in the cluster, excluding topics.</p>
<p>Setting the Idempotent Write permission in a cluster for a user</p>	<ol style="list-style-type: none"> <li>1. Enter a cluster name and select the cluster on the right side of <b>cluster</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Idempotent Write</b>.</li> </ol> <p><b>NOTE</b> This permission authenticates the <b>Idempotent Produce</b> behavior of the user's client.</p>
<p>Setting the permission to migrate partitions in a cluster for a user</p>	<ol style="list-style-type: none"> <li>1. Enter a cluster name and select the cluster on the right side of <b>cluster</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Alter</b>.</li> </ol> <p><b>NOTE</b> The <b>Alter</b> permission of a cluster can be used to control permissions in the following scenarios:</p> <ol style="list-style-type: none"> <li>1. In the <b>Partition Reassign</b> scenario, migrate the storage directory of replicas.</li> <li>2. Elect a leader replica in each partition of the cluster.</li> <li>3. Add or delete ACLs.</li> </ol> <p>Operations in scenarios <a href="#">Step 4.1</a> and <a href="#">Step 4.2</a> are between a controller and broker and between brokers in the cluster. When a cluster is created, this permission is granted to the built-in Kafka user by default. It is meaningless for a common user to be granted with this permission.</p> <p>Scenario <a href="#">Step 4.3</a> involves the ACL management. ACLs are designed for authentication. Currently, Kafka authentication is hosted to Ranger. Therefore, this scenario is not involved (the configuration does not take effect).</p>

Scenario	Role Authorization
<p>Setting the Cluster Action permission in a cluster for a user</p>	<ol style="list-style-type: none"> <li>1. Enter a cluster name and select the cluster on the right side of <b>cluster</b>.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Cluster Action</b>.</li> </ol> <p><b>NOTE</b> This permission controls the synchronization between the leader and follower replicas in the cluster and the communication between nodes. It has been granted to the built-in Kafka user during cluster creation. It is meaningless for a common user to grant this permission.</p>
<p>Setting the TransactionalId permission for a user</p>	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>KAFKA</b> area, for example, <b>Kafka</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - transactionalid</b> and click  to edit the policy. <ol style="list-style-type: none"> <li>1. Set <b>transactionalid</b> to a transaction ID.</li> <li>2. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>3. Click <b>Add Permissions</b> and select <b>Publish</b> and <b>Describe</b>.</li> </ol> <p><b>NOTE</b> The <b>Publish</b> permission is used to authenticate client requests for which the transaction feature is enabled, for example, starting and ending a transaction, submitting an offset, and generating transactional data. The <b>Describe</b> permission is used to authenticate the requests from the client and coordinator that have enabled the transaction feature. If the transaction feature is enabled, you are advised to grant both the <b>Publish</b> and <b>Describe</b> permissions to users.</p> </li> </ol>

Scenario	Role Authorization
<p>Setting the DelegationToken permission for a user</p>	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>KAFKA</b> area, for example, <b>Kafka</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - delegationtoken</b> and click  to edit the policy.</li> <li>3. Set <b>delegationtoken</b> to a delegation token.</li> <li>4. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>5. Click <b>Add Permissions</b> and select <b>Describe</b>.</li> </ol> <p><b>NOTE</b> Currently, Ranger only controls the query permission of DelegationToken, but does not control its <b>create</b>, <b>renew</b>, and <b>expire</b> permissions.</p>
<p>Setting the permission for a user to query ConsumerGroup Offsets</p>	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>KAFKA</b> area, for example, <b>Kafka</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - consumergroup</b> and click  to edit the policy.</li> <li>3. In <b>consumergroup</b>, configure the consumer group to be managed.</li> <li>4. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>5. Click <b>Add Permissions</b> and select <b>Describe</b>.</li> </ol>
<p>Set the user's submission permission on <b>ConsumerGroup Offsets</b>.</p>	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>KAFKA</b> area, for example, <b>Kafka</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - consumergroup</b> and click  to edit the policy.</li> <li>3. In <b>consumergroup</b>, configure the consumer group to be managed.</li> <li>4. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>5. Click <b>Add Permissions</b> and select <b>Consume</b>.</li> </ol> <p><b>NOTE</b> After a user is granted with the <b>Consume</b> permission of <b>ConsumerGroup</b>, the user is also granted with the <b>Describe</b> permission.</p>

Scenario	Role Authorization
Setting the permission for a user to delete ConsumerGroup Offsets	<ol style="list-style-type: none"> <li>1. On the home page, click the component plug-in name in the <b>KAFKA</b> area, for example, <b>Kafka</b>.</li> <li>2. Select the policy whose <b>Policy Name</b> is <b>all - consumergroup</b> and click  to edit the policy.</li> <li>3. In <b>consumergroup</b>, configure the consumer group to be managed.</li> <li>4. In the <b>Allow Conditions</b> area, select a user from the <b>Select User</b> drop-down list.</li> <li>5. Click <b>Add Permissions</b> and select <b>Delete</b>.</li> </ol> <p><b>NOTE</b> When a user is granted with the <b>Delete</b> permission of <b>ConsumerGroup</b>, the user is also granted with the <b>Describe</b> permission.</p>

**Step 5** (Optional) Add the validity period of the policy. Click **Add Validity period** in the upper right corner of the page, set **Start Time** and **End Time**, and select **Time Zone**. Click **Save**. To add multiple policy validity periods, click . To delete a policy validity period, click .

**Step 6** Click **Add** to view the basic information about the policy in the policy list. After the policy takes effect, check whether the related permissions are normal.

To disable a policy, click  to edit the policy and set the policy to **Disabled**.

If a policy is no longer used, click  to delete it.

----End

## 16.14 Adding a Ranger Access Permission Policy for HetuEngine

### Scenario

Ranger administrators can use Ranger to configure the permission to manage databases, tables, and columns of data sources for HetuEngine users.

### Prerequisites

- The Ranger service has been installed and is running properly.
- You have created users, user groups, or roles for which you want to configure permissions.
- The users have been added to the **hetuadmin** group.

- Before using HetuEngine, ensure that the client operator or user in the configuration file for connecting to the data source has the expected operation permission. If the user does not have it, configure the permission by referring to the corresponding data source permission requirements.

## Procedure

- Step 1** Log in to the Ranger web UI. Click **HetuEngine** in the **PRESTO** area on the homepage.
- Step 2** On the **Access** tab page, click **Add New Policy** to add a HetuEngine permission control policy.
- Step 3** Configure the parameters listed in the table below based on the service demands.

**Table 16-20** HetuEngine permission parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service. <ul style="list-style-type: none"> <li>• <b>Enabled:</b> Enable the current policy.</li> <li>• <b>Disabled:</b> Disable the current policy.</li> </ul>
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10,192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Presto Catalog	Name of the data source catalog to which the policy applies. If this parameter is set to *, the policy applies to all catalogs. <ul style="list-style-type: none"> <li>• <b>Include:</b> The policy applies to the current input object.</li> <li>• <b>Exclude:</b> The policy applies to objects other than the current input.</li> </ul>
Schema	Name of the schema to which the policy applies. The value * indicates all schemas. <ul style="list-style-type: none"> <li>• <b>Include:</b> The policy applies to the current input object.</li> <li>• <b>Exclude:</b> The policy applies to objects other than the current input.</li> </ul>

Parameter	Description
table	<p>Name of the table or view to which the policy applies. If this parameter is set to *, the policy applies to all tables.</p> <ul style="list-style-type: none"> <li>● <b>Include:</b> The policy applies to the current input object.</li> <li>● <b>Exclude:</b> The policy applies to objects other than the current input.</li> </ul>
Column	Name of the column to which the policy applies. The value * indicates all columns.
Description	Policy description.
Audit Logging	Whether to audit the policy.
Allow Conditions	<p>Policy allowed condition. You can configure permissions and exceptions allowed by the policy.</p> <p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the role, user group, or user to which you want to assign permissions. Click <b>Add Conditions</b>, add the IP address range to which the policy applies, and click <b>Add Permissions</b> to add corresponding permissions.</p> <ul style="list-style-type: none"> <li>● <b>Select:</b> permission to query data</li> <li>● <b>Insert:</b> permission to insert data</li> <li>● <b>Create:</b> permission to create data</li> <li>● <b>Drop:</b> permission to drop data</li> <li>● <b>Delete:</b> permission to delete data</li> <li>● <b>Use:</b> permission to use data</li> <li>● <b>Alter:</b> permission to alter data</li> <li>● <b>Update:</b> permission to update data</li> <li>● <b>Admin:</b> admin permissions (control ACL operations, such as <b>SET SESSION</b>, <b>GRANT</b>, and <b>REVOKE</b>)</li> <li>● <b>All:</b> all permissions (including the <b>Admin</b> permission)</li> <li>● <b>Select/Deselect All:</b> Select or deselect all.</li> </ul> <p>To add multiple permission control rules, click .</p> <p>If users or user groups in the current condition need to manage this policy, select <b>Delegate Admin</b>. These users will become the agent administrators. The agent administrators can update and delete this policy and create sub-policies based on the original policy.</p>
Deny Conditions	<p>Policy rejection condition, which is used to configure the permissions and exceptions to be denied in the policy. The configuration method is the same as that of <b>Allow Conditions</b>.</p>

**Table 16-21** Setting permissions

Task	Role Authorization
<p>Granting the access policy to the catalog where the table is located</p>	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the resource to be authorized, for example, <b>hive</b>.</li> <li>3. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>4. In <b>Permissions</b>, select <b>Select</b>.</li> </ol> <p><b>NOTE</b> This policy is a basic policy. Before configuring other policies, ensure that this policy has been configured.</p>
<p>Granting the permission to access the remote HetuEngine table</p>	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the table to be authorized, for example, <b>systemremote</b> and <b>svc</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter * in the text box.</li> <li>4. Select <b>table</b> from the drop-down list box under <b>schema</b> and enter * in the text box.</li> <li>5. Select <b>column</b> from the drop-down list box under <b>table</b> and enter * in the text box.</li> <li>6. Enter the authorized remote HetuEngine user in the <b>Select User</b> text box.</li> <li>7. In <b>Permissions</b>, select <b>Create, Drop, Select, and Insert</b>.</li> </ol> <p><b>NOTE</b> This policy is a basic policy for remote HetuEngine tables. Before configuring other policies, ensure that this policy has been configured.</p>
<p>Create schemas</p>	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the target schema to be authorized in the text box. If this parameter is set to *, all schemas under the current catalog are authorized.</li> <li>4. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>5. In <b>Permissions</b>, select <b>Create</b>.</li> </ol>

Task	Role Authorization
Drop schemas	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the target schema to be authorized in the text box. If this parameter is set to *, all schemas under the current catalog are authorized.</li> <li>4. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>5. In <b>Permissions</b>, select <b>Drop</b>.</li> </ol>
Create table	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the schema where the target table to be authorized resides in the text box, for example, <b>default</b>.</li> <li>4. Select <b>table</b> from the drop-down list box under <b>schema</b> and enter the name of the target table to be authorized in the text box. If this parameter is set to *, all tables under the current schema are authorized.</li> <li>5. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>6. In <b>Permissions</b>, select <b>Create</b>.</li> </ol>
Drop tables	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the schema where the target table to be authorized resides in the text box, for example, <b>default</b>.</li> <li>4. Select <b>table</b> from the drop-down list box under <b>schema</b> and enter the name of the target table to be authorized in the text box. If this parameter is set to *, all tables under the current schema are authorized.</li> <li>5. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>6. In <b>Permissions</b>, select <b>Drop</b>.</li> </ol>

Task	Role Authorization
Alter tables	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the schema where the target table to be authorized resides in the text box, for example, <b>default</b>.</li> <li>4. Select <b>table</b> from the drop-down list box under <b>schema</b> and enter the name of the target table to be authorized in the text box. If this parameter is set to *, all tables under the current schema are authorized.</li> <li>5. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>6. In <b>Permissions</b>, select <b>Alter</b>.</li> </ol> <p><b>NOTE</b> ALTER TABLE table_name DROP [IF EXISTS] PARTITION partition_spec[, PARTITION partition_spec, ...]; requires the table-level <b>delete</b> and column-level <b>select</b> permissions.</p>
Show tables	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the target schema that allows to show table in the text box, for example, <b>default</b>.</li> <li>4. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>5. In <b>Permissions</b>, select <b>Select</b>.</li> </ol>
Insert tables	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the schema where the target table to be authorized resides in the text box, for example, <b>default</b>.</li> <li>4. Select <b>table</b> from the drop-down list box under <b>schema</b> and enter the name of the target table to be authorized in the text box. If this parameter is set to *, all tables under the current schema are authorized.</li> <li>5. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>6. In <b>Permissions</b>, select <b>Insert</b>.</li> </ol>

Task	Role Authorization
Delete	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the schema where the target table to be authorized resides in the text box, for example, <b>default</b>.</li> <li>4. Select <b>table</b> from the drop-down list box under <b>schema</b> and enter the name of the target table to be authorized in the text box. If this parameter is set to *, all tables under the current schema are authorized.</li> <li>5. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>6. In <b>Permissions</b>, select <b>Delete</b>.</li> </ol>
Select	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the schema where the target table to be authorized resides in the text box.</li> <li>4. Select <b>table</b> from the drop-down list box under <b>schema</b> and enter the name of the target table to be authorized in the text box. If this parameter is set to *, all tables under the current schema are authorized.</li> <li>5. Select <b>column</b> from the drop-down list box under <b>table</b> and enter the name of the target column to be authorized in the text box. If this parameter is set to *, all columns under the current table are authorized.</li> <li>6. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>7. In <b>Permissions</b>, select <b>Select</b>.</li> </ol>

Task	Role Authorization
Show columns	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. In <b>Presto Catalog</b>, enter the catalog of the target table to be authorized, for example, <b>hive</b>.</li> <li>3. Select <b>schema</b> from the drop-down list box under <b>Presto Catalog</b> and enter the name of the schema where the target table to be authorized resides in the text box, for example, <b>default</b>.</li> <li>4. Select <b>table</b> from the drop-down list box under <b>schema</b> and enter the name of the target table to be authorized in the text box. If this parameter is set to *, all tables under the current schema are authorized.</li> <li>5. Select <b>column</b> from the drop-down list box under <b>table</b> and enter the name of the target column to be authorized in the text box. If this parameter is set to *, all columns under the current table are authorized.</li> <li>6. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>7. In <b>Permissions</b>, select <b>Select</b>.</li> </ol>
Set sessions	<ol style="list-style-type: none"> <li>1. Enter the policy name in <b>Policy Name</b>.</li> <li>2. Enter * in the <b>Presto Catalog</b> text box.</li> <li>3. Enter the authorized Hetu user in the <b>Select User</b> text box.</li> <li>4. Select <b>Delegate Admin</b>.</li> </ol>

 **NOTE**

- The configuration takes effect about 30 seconds after the permission is configured.
- The current permission control is available to columns.

**Step 4** (Optional) Add the validity period of the policy. Click **Add Validity period** in the upper right corner of the page, set **Start Time** and **End Time**, and select **Time Zone**. Click **Save**. To add multiple policy validity periods, click . To delete a policy validity period, click .

**Step 5** Click **Add** to view the basic information about the policy in the policy list. After the policy takes effect, check whether the related permissions are normal.

To disable a policy, click  to edit the policy and set the policy to **Disabled**.

If a policy is no longer used, click  to delete it.

----End

## HetuEngine Data Masking

Ranger supports data masking for HetuEngine data. It can process the return result of the **select** operation performed by a user to mask sensitive information.

- Step 1** Log in to the Ranger web UI. Click **HetuEngine** in the **PRESTO** area on the homepage.
- Step 2** On the **Masking** tab page, click **Add New Policy** to add a HetuEngine data masking policy.
- Step 3** Configure the parameters listed in the table below based on the service demands.

**Table 16-22** HetuEngine data masking parameters

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10,192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Presto Catalog	Name of the catalog to which the current policy applies.
Presto Schema	Name of the database to which the current policy applies.
Presto Table	Name of the table to which the current policy applies.
Presto Column	Name of the column to which the current policy applies.
Description	Policy description.
Audit Logging	Whether to audit the policy.

Parameter	Description
Mask Conditions	<p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the object to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, then click <b>Add Permissions</b>, and select <b>Select</b>.</p> <p>Click <b>Select Masking Option</b> and select a data masking policy.</p> <ul style="list-style-type: none"> <li>● <b>Redact</b>: Use <b>x</b> to mask all letters and <b>n</b> to mask all digits.</li> <li>● <b>Partial mask: show last 4</b>: Only the last four characters are displayed, and the rest characters are displayed using <b>x</b>.</li> <li>● <b>Partial mask: show first 4</b>: Only the first four characters are displayed, and the rest characters are displayed using <b>x</b>.</li> <li>● <b>Hash</b>: Replace the original value with the hash value.</li> <li>● <b>Nullify</b>: Replace the original value with the NULL value.</li> <li>● <b>Unmasked (retain original value)</b>: Keep the original value.</li> <li>● <b>Custom</b>: You customize policies using any valid return data type which is the same as the data type in the masked column.</li> </ul> <p>To add a multi-column masking policy, click .</p>

**Step 4** Click **Add** to view the basic information about the policy in the policy list.

**Step 5** After a user performs the **select** operation on a table for which a data masking policy has been configured on a HetuEngine client, the system processes the data and displays it.

----End

## HetuEngine Row-level Data Filtering

Ranger allows you to filter data at the row level when you perform the select operation on a HetuEngine data table.

**Step 1** Log in to the Ranger web UI. Click **HetuEngine** in the **PRESTO** area on the homepage.

**Step 2** On the **Row Level Filter** tab page, click **Add New Policy** to add a row data filtering policy.

**Step 3** Configure the parameters listed in the table below based on the service demands.

**Table 16-23** Parameters for filtering HetuEngine row data

Parameter	Description
Policy Name	Policy name, which can be customized and must be unique in the service.

Parameter	Description
Policy Conditions	IP address filtering policy, which can be customized. You can enter one or more IP addresses or IP address segments. The IP address can contain the wildcard character (*), for example, <b>192.168.1.10</b> , <b>192.168.1.20</b> , or <b>192.168.1.*</b> .
Policy Label	A label specified for the current policy. You can search for reports and filter policies based on labels.
Presto Catalog	Name of the catalog to which the current policy applies.
Presto Schema	Name of the database to which the current policy applies.
Presto Table	Name of the table to which the current policy applies.
Description	Policy description.
Audit Logging	Whether to audit the policy.
Row Filter Conditions	<p>In the <b>Select Role</b>, <b>Select Group</b>, and <b>Select User</b> columns, select the object to which the permission is to be granted, click <b>Add Conditions</b>, add the IP address range to which the policy applies, then click <b>Add Permissions</b>, and select <b>Select</b>. Click <b>Row Level Filter</b> and enter data filtering rules.</p> <p>For example, if you want to filter the data in the <b>zhangsan</b> row in the <b>name</b> column of <b>table A</b>, the filtering rule is <b>name &lt;&gt;'zhangsan'</b>. For more information, see the official Ranger document.</p> <p>To add more rules, click .</p>

**Step 4** Click **Add** to view the basic information about the policy in the policy list.

**Step 5** After a user performs the **select** operation on a table for which a data masking policy has been configured on a HetuEngine client, the system processes the data and displays it.

----End

## 16.15 Ranger Log Overview

### Log Description

**Log path:** The default storage path of Ranger logs is **/var/log/Bigdata/ranger/Role name**.

- RangerAdmin: **/var/log/Bigdata/ranger/rangeradmin** (run logs)
- TagSync: **/var/log/Bigdata/ranger/tagsync** (run logs)
- UserSync: **/var/log/Bigdata/ranger/usersync** (run logs)

**Log archive rule:** The automatic compression and archive function is enabled for Ranger logs. By default, when the size of a log file exceeds 20 MB, the log file is

automatically compressed. The naming rule of the compressed log file is as follows: <Original log file name>-<yyyy-mm-dd\_hh-mm-ss>.[ID].log.zip. A maximum of 20 compressed file are retained.

**Table 16-24** HDFS log list

Type	Name	Description
RangerAdmin run log file	access_log.<DATE>.log	Tomcat access log
	catalina.out	Tomcat service run log
	gc-worker.log	RangerAdmin garbage collection (GC) log
	postinstallDetail.log	Work log generated after an instance is started before installation
	prestartDetail.log	Log that records preparations before instance startup
	ranger-admin-<hostname>.log	RangerAdmin run log
	ranger_admin_sql-<hostname>.log	RangerAdmin log used to retrieve DBService
	startDetail.log	Instance startup log
TagSync run log	cleanupDetail.log	Instance clearing log
	gc-worker.log	GC log file of an instance
	postinstallDetail.log	Work log generated after an instance is started before installation
	prestartDetail.log	Log that records preparations before instance startup
	ranger-tagsync-<hostname>.log	TagSync run log
	startDetail.log	Instance startup log
	tagsync.out	TagSync run log
UserSync run log	auth.log	UnixAuth service run log
	cleanupDetail.log	Instance clearing log
	gc-worker.log	GC log file of an instance

Type	Name	Description
	postinstallDetail.log	Work log generated after an instance is started before installation
	prestartDetail.log	Log that records preparations before instance startup
	ranger-usersync- <i>&lt;hostname&gt;</i> .log	UserSync run log
	startDetail.log	Instance startup log

## Log Levels

**Table 16-25** describes the log levels provided by HDFS. The priorities of log levels are FATAL, ERROR, WARN, INFO, and DEBUG in descending order. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 16-25** Log levels

Level	Description
FATAL	Logs of this level record fatal error information about the current event processing that may result in a system crash.
ERROR	Logs of this level record error information about the current event processing, which indicates that system running is abnormal.
WARN	Logs of this level record abnormal information about the current event processing. These abnormalities will not result in system faults.
INFO	Logs of this level record normal running status information about the system and events.
DEBUG	Logs of this level record the system information and system debugging information.

To modify log levels, perform the following operations:

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster > Services > Ranger > Configurations**.
- Step 3** Select **All Configurations**.

- Step 4** On the menu bar on the left, select the log menu of the target role.
- Step 5** Select a desired log level.
- Step 6** Click **Save**. In the displayed dialog box, click **OK** to make the configuration take effect.

 **NOTE**

The configurations take effect immediately without the need to restart the service.

----End

## Log Formats

The following table lists the Ranger log formats.

**Table 16-26** Log formats

Type	Format	Example Value
Run log	<i>&lt;yyyy-MM-dd HH:mm:ss,SSS&gt; &lt;Log level&gt; &lt;Name of the thread that generates the log&gt; &lt;Message in the log&gt; &lt;Location where the log event occurs&gt;</i>	2020-04-29 20:09:28,543   INFO   http-bio-21401- exec-56   Request comes from API call, skip cas filter.   CasAuthenticationFilter- Wrapper.java:25

## 16.16 Common Issues About Ranger

### 16.16.1 Why Ranger Startup Fails During the Cluster Installation?

#### Problem

During cluster installation, Ranger fails to be started, and the error message "ERROR: cannot drop sequence X\_POLICY\_REF\_ACCESS\_TYPE\_SEQ " is displayed in the task list of the Manager process. How do I resolve this problem and properly install Ranger?

#### Answer

This issue may occur when two RangerAmdin instances are installed. If the instance installation fails, manually restart one RangerAdmin instance and then restart the other instance.

## 16.16.2 How Do I Determine Whether the Ranger Authentication Is Used for a Service?

### Question

How do I determine whether the Ranger authentication is enabled for a service that supports the authentication?

### Answer

Log in to FusionInsight Manager and choose **Cluster > Services > Name of the desired service**. On the service details page, click **More** and check whether the **Enable Ranger** option is available.

- If yes, the Ranger authentication plug-in is not enabled for the service. You can click **Enable Ranger** to enable the function.
- If no, the Ranger authentication plug-in has been enabled for the service. You can configure the permission policy for accessing the service resources on the Ranger management page.

## 16.16.3 Why Cannot a New User Log In to Ranger After Changing the Password?

### Question

When a new user logs in to Ranger, why is the 401 error reported after the password is changed?

### Answer

The UserSync synchronizes user data at an interval of 5 minutes by default. Therefore, a new user created on Manager cannot log in to the Ranger before the user data is successfully synchronized because the Ranger database does not have the user information. The user can log in to the Ranger only after the specified interval ends.

In non-security mode, the Ranger does not synchronize user data from Manager. Therefore, only the **admin** user can log in to the Ranger page.

## 16.16.4 When an HBase Policy Is Added or Modified on Ranger, Wildcard Characters Cannot Be Used to Search for Existing HBase Tables

### Question

When a Ranger access permission policy is added for HBase and wildcard characters are used to search for an existing HBase table in the policy, the table cannot be found. The following error is reported in `/var/log/Bigdata/ranger/rangeradmin/ranger-admin-*log`:

```
Caused by: javax.security.sasl.SaslException: No common protection layer between client and server at com.sun.security.sasl.gsskerb.GssKrb5Client.doFinalHandshake(GssKrb5Client.java:253)
```

```
at com.sun.security.sasl.gsskerb.GssKrb5Client.evaluateChallenge(GssKrb5Client.java:186)
at
org.apache.hadoop.hbase.security.AbstractHBaseSaslRpcClient.evaluateChallenge(AbstractHBaseSaslRpcClient.java:142)
at org.apache.hadoop.hbase.security.NettyHBaseSaslRpcClientHandler
$2.run(NettyHBaseSaslRpcClientHandler.java:142)
at org.apache.hadoop.hbase.security.NettyHBaseSaslRpcClientHandler
$2.run(NettyHBaseSaslRpcClientHandler.java:138)
at java.security.AccessController.doPrivileged(Native Method)
at javax.security.auth.Subject.doAs(Subject.java:422)
at org.apache.hadoop.security.UserGroupInformation.doAs(UserGroupInformation.java:1761)
at
org.apache.hadoop.hbase.security.NettyHBaseSaslRpcClientHandler.channelRead0(NettyHBaseSaslRpcClientHandler.java:138)
at
org.apache.hadoop.hbase.security.NettyHBaseSaslRpcClientHandler.channelRead0(NettyHBaseSaslRpcClientHandler.java:42)
at
org.apache.hadoop.hbase.thirdparty.io.netty.channel.SimpleChannelInboundHandler.channelRead(SimpleChannelInboundHandler.java:105)
at
org.apache.hadoop.hbase.thirdparty.io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:362)
```

## Answer

The value of **hbase.rpc.protection** of the HBase service plug-in on Ranger must be the same as that of **hbase.rpc.protection** on the HBase server.

- Step 1** Log in to the Ranger management page. For details, see [Logging In to the Ranger Web UI](#).
- Step 2** In the **HBASE** area on the home page, click the component plug-in name, for example, the  button of HBase.
- Step 3** Search for the configuration item **hbase.rpc.protection** and change its value to the value of **hbase.rpc.protection** on the HBase server.
- Step 4** Click **Save**.

----End

# 17 Using Spark2x

## 17.1 Basic Operation

### 17.1.1 Getting Started

This section describes how to use Spark2x to submit Spark applications, including Spark Core and Spark SQL. Spark Core is the kernel module of Spark. It executes tasks and is used to compile Spark applications. Spark SQL is a module that executes SQL statements.

#### Scenario Description

Develop a Spark application to perform the following operations on logs about netizens' dwell time for online shopping on a weekend.

- Collect statistics on female netizens who dwell on online shopping for more than 2 hours on the weekend.
- The first column in the log file records names, the second column records genders, and the third column records the dwell durations in the unit of minute. Three columns are separated by comma (,).

**log1.txt:** logs collected on Saturday

```
LiuYang,female,20  
YuanJing,male,10  
GuoYijun,male,5  
CaiXuyu,female,50  
Liyuan,male,20  
FangBo,female,50  
LiuYang,female,20  
YuanJing,male,10  
GuoYijun,male,50  
CaiXuyu,female,50  
FangBo,female,60
```

**log2.txt:** logs collected on Sunday

```
LiuYang,female,20  
YuanJing,male,10  
CaiXuyu,female,50  
FangBo,female,50
```

```
GuoYijun,male,5  
CaiXuyu,female,50  
Liyuan,male,20  
CaiXuyu,female,50  
FangBo,female,50  
LiuYang,female,20  
YuanJing,male,10  
FangBo,female,50  
GuoYijun,male,50  
CaiXuyu,female,50  
FangBo,female,60
```

## Prerequisites

- On Manager, you have created a user and granted the HDFS, Yarn, Kafka, and Hive permissions to the user.
- You have installed and configured tools such as IntelliJ IDEA and JDK based on the development language.
- You have installed the Spark2x client and configured the client network connection.
- For Spark SQL programs, you have started Spark SQL or Beeline on the client to enter SQL statements.

## Procedure

**Step 1** Obtain the sample project and import it to IDEA. Import the JAR package on which the sample project depends. Use IDEA to configure and generate JAR packages.

**Step 2** Prepare the data required by the sample project.

Save the original log files in the scenario description to the HDFS system.

1. Create two text files (**input\_data1.txt** and **input\_data2.txt**) on the local host and copy the content in the **log1.txt** and **log2.txt** files to the **input\_data1.txt** and **input\_data2.txt** files, respectively.
2. Create the **/tmp/input** directory in HDFS, and upload **input\_data1.txt** and **input\_data2.txt** to the **/tmp/input** directory:

**Step 3** Upload the generated JAR package to the Spark2x running environment (Spark2x client), for example, **/opt/female**.

**Step 4** Go the client directory, configure the environment variables, and log in to the system.

```
source bigdata_env
```

```
source Spark2x/component_env
```

```
kinit <service user for authentication>
```

**Step 5** Run the following script in the **bin** directory to submit the Spark application:

```
spark-submit --class com.xxx.bigdata.spark.examples.FemaleInfoCollection --master yarn-client /opt/female/FemaleInfoCollection.jar <inputPath>
```

**Step 6** (Optional) After calling the **spark-sql** or **spark-beeline** script in the **bin** directory, directly enter SQL statements to perform operations such as query.


For example, create a table, insert a piece of data, and then query the table.

```
spark-sql> CREATE TABLE TEST(NAME STRING, AGE INT);  
Time taken: 0.348 seconds  
spark-sql>INSERT INTO TEST VALUES('Jack', 20);  
Time taken: 1.13 seconds  
spark-sql> SELECT * FROM TEST;  
Jack    20  
Time taken: 0.18 seconds, Fetched 1 row(s)
```

**Step 7** View the running result of the Spark application.


- View the running result data in a specified file.  
The storage path and format of the result data are specified by the Spark application.
- Check the running status on the web page.
  - a. Log in to Manager. Select **Spark2x** from the **Service** drop-down list.
  - b. Go to the Spark2x overview page and click an instance, for example, **JobHistory2x(host2)**.
  - c. The History Server UI is displayed.  
Select the part file of an application. The History Server UI is used to display the status of Spark applications that are complete or incomplete.

**Figure 17-1** History Server UI



- d. Select an application ID and click this page to go to the Spark UI of the application.  
Spark UI: used to display the status of running applications.

**Figure 17-2** Spark UI



- View Spark logs to learn application runtime conditions.  
View [Spark2x Logs](#) to learn application running status, and adjust applications based on log information.

----End

## 17.1.2 Configuring Parameters Rapidly

### Overview

This section describes how to quickly configure common parameters and lists parameters that are not recommended to be modified when Spark2x is used.

### Common parameters to be configured

Some parameters have been adapted during cluster installation. However, the following parameters need to be adjusted based on application scenarios. Unless otherwise specified, the following parameters are configured in the **spark-defaults.conf** file on the Spark2x client.

**Table 17-1** Common parameters to be configured

Configuration Item	Description	Default Value
spark.sql.parquet.compression.codec	Used to set the compression format of a non-partitioned Parquet table. Set the queue in the <b>spark-defaults.conf</b> configuration file on the JDBCServer server.	snappy
spark.dynamicAllocation.enabled	Indicates whether to use dynamic resource scheduling, which is used to adjust the number of executors registered with the application according to scale. Currently, this parameter is valid only in Yarn mode. The default value for JDBCServer is <b>true</b> , and that for the client is <b>false</b> .	false
spark.executor.memory	Indicates the memory size used by each executor process. Its character string is in the same format as the JVM memory (example: 512 MB or 2 GB).	4G

Configuration Item	Description	Default Value
spark.sql.autoBroadcastJoinThreshold	<p>Indicates the maximum value for the broadcast configuration when two tables are joined.</p> <ul style="list-style-type: none"> <li>When the size of a field in a table involved in an SQL statement is less than the value of this parameter, the system broadcasts the SQL statement.</li> <li>If the value is set to <b>-1</b>, broadcast is not performed.</li> </ul>	10485760
spark.yarn.queue	<p>Specifies the Yarn queue where JDBCServer resides.</p> <p>Set the queue in the <b>spark-defaults.conf</b> configuration file on the JDBCServer server.</p>	default
spark.driver.memory	<p>In a large cluster, you are advised to configure the memory used by the 32 GB to 64 GB driver process, that is, the SparkContext initialization process (for example, 512 MB and 2 GB).</p>	4G
spark.yarn.security.credentials.hbase.enabled	<p>Indicates whether to enable the function of obtaining HBase tokens. If the Spark on HBase function is required and a security cluster is configured, set this parameter to <b>true</b>. Otherwise, set this parameter to <b>false</b>.</p>	false
spark.serializer	<p>Used to serialize the objects that are sent over the network or need to be cached.</p> <p>The default value of Java serialization applies to any Serializable Java object, but the running speed is slow. Therefore, you are advised to use <b>org.apache.spark.serializer.KryoSerializer</b> and configure Kryo serialization. It can be any subclass of <b>org.apache.spark.serializer.Serializer</b>.</p>	org.apache.spark.serializer.JavaSerializer

Configuration Item	Description	Default Value
spark.executor.cores	Indicates the number of kernels used by each executor. Set this parameter in standalone mode and Mesos coarse-grained mode. When there are sufficient kernels, the application is allowed to execute multiple executable programs on the same worker. Otherwise, each application can run only one executable program on each worker.	1
spark.shuffle.service.enabled	Indicates a long-term auxiliary service in NodeManager for improving shuffle computing performance.	false
spark.sql.adaptive.enabled	Indicates whether to enable the adaptive execution framework.	false
spark.executor.memoryOverhead	Indicates the heap memory to be allocated to each executor, in MB. This is the memory that occupies the overhead of the VM, similar to the internal string and other built-in overhead. The value increases with the executor size (usually 6% to 10%).	1GB
spark.streaming.kafka.direct.lifo	Indicates whether to enable the LIFO function of Kafka.	false

## Parameters Not Recommended to Be Modified

The following parameters have been adapted during cluster installation. You are not advised to modify them.

**Table 17-2** Parameters not recommended to be modified

Configuration Item	Description	Default Value or Configuration Example
spark.password.factory	Selects the password parsing mode.	org.apache.spark.om.util.FIPasswordFactory
spark.ssl.ui.protocol	Sets the SSL protocol of the UI.	TLSv1.2

Configuratio n Item	Description	Default Value or Configuration Example
spark.yarn.archive	Archives Spark JAR files, which are distributed to Yarn cache. If this parameter is set, the value will replace <code>&lt;code&gt;spark.yarn.jars &lt;/code&gt;</code> and be archived in the containers of all applications. The archive should contain the JAR files in its root directory. Archives can also be hosted on HDFS to speed up file distribution.	hdfs://hacluster/user/spark2x/jars/8.1.2.2/spark-archive-2x.zip <b>NOTE</b> The version 8.1.2.2 is used as an example. Replace it with the actual version number.
spark.yarn.am.extraJavaOptions	Indicates a string of extra JVM options to pass to the YARN ApplicationMaster in client mode. Use <b>spark.driver.extraJavaOptions</b> in cluster mode.	-Dlog4j.configuration=./__spark_conf__/_hadoop_conf__/log4j-executor.properties -Djava.security.auth.login.config=./__spark_conf__/_hadoop_conf__/jaas-zk.conf - Dzookeeper.server.principal=zookeeper/hadoop.<system domain name> - Djava.security.krb5.conf=./__spark_conf__/_hadoop_conf__/kdc.conf - Djdk.tls.ephemeralDHKeySize=2048
spark.shuffle.servicev2.port	Indicates the port for the shuffle service to monitor requests for obtaining data.	27338
spark.ssl.historyServer.enabled	Sets whether the history server uses SSL.	true
spark.files.override	When the target file exists and its content does not match that of the source file, whether to overwrite the file added through <b>SparkContext.addFile()</b> .	false

Configuration Item	Description	Default Value or Configuration Example
spark.yarn.cluster.driver.extraClassPath	Indicates the extraClassPath of the driver in Yarn-cluster mode. Set the parameter to the path and parameters of the server.	<code>\${BIGDATA_HOME}/common/runtime/security</code>
spark.driver.extraClassPath	Indicates the extra class path entries attached to the class path of the driver.	<code>\${BIGDATA_HOME}/common/runtime/security</code>
spark.yarn.dist.innerfiles	Sets the files that need to be uploaded to HDFS from Spark in Yarn mode.	<code>/Spark_path/spark/conf/s3p.file,/Spark_path/spark/conf/locals3.jceks</code> <i>Spark_path</i> is the installation path of the Spark client.
spark.sql.bigdata.register.dialect	Registers the SQL parser.	<code>org.apache.spark.sql.hbase.HBaseSQLParser</code>
spark.shuffle.manager	Indicates the data processing mode. There are two implementation modes: sort and hash. The sort shuffle has a higher memory utilization. It is the default option in Spark 1.2 and later versions.	<code>SORT</code>
spark.deploy.zookeeper.url	Indicates the address of ZooKeeper. Multiple addresses are separated by commas (,).	For example: <code>host1:2181,host2:2181,host3:2181</code>
spark.broadcast.factory	Indicates the broadcast mode.	<code>org.apache.spark.broadcast.TorrentBroadcastFactory</code>
spark.sql.session.state.builder	Session state constructor.	<code>org.apache.spark.sql.hive.FIHiveACLSessionStateBuilder</code>

Configuration Item	Description	Default Value or Configuration Example
spark.executor.extraLibraryPath	Sets the special library path used when the executor JVM is started.	\${BIGDATA_HOME}/ FusionInsight_HD_8.1.2.2/install/ FusionInsight-Hadoop-3.1.1/hadoop/lib/ native
spark.ui.customErrorPage	Indicates whether to display the custom error information page when an error occurs on the page.	true
spark.httpdProxy.enable	Indicates whether to use the httpd proxy.	true
spark.ssl.ui.enabledAlgorithms	Sets the SSL algorithm of UI.	TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384,TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384,TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256,TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256,TLS_DHE_RSA_WITH_AES_256_GCM_SHA384,TLS_DHE_DSS_WITH_AES_256_GCM_SHA384,TLS_DHE_RSA_WITH_AES_128_GCM_SHA256,TLS_DHE_DSS_WITH_AES_128_GCM_SHA256
spark.ui.logout.enabled	Sets the logout button for the web UI of the Spark component.	true
spark.security.hideInfo.enabled	Indicates whether to hide sensitive information on the UI.	true
spark.yarn.cluster.driver.extraLibraryPath	Indicates the <b>extraLibraryPath</b> of the driver in Yarn-cluster mode. Set this parameter to the path and parameters of the server.	\${BIGDATA_HOME}/ FusionInsight_HD_8.1.2.2/install/ FusionInsight-Hadoop-3.1.1/hadoop/lib/ native
spark.driver.extraLibraryPath	Sets a special library path for starting the driver JVM.	\${DATA_NODE_INSTALL_HOME}/ hadoop/lib/native

Configuration Item	Description	Default Value or Configuration Example
spark.ui.killedEnabled	Allows stages and jobs to be stopped on the web UI.	true
spark.yarn.access.hadoopFileSystems	Spark can access multiple NameService instances. If there are multiple NameService instances, set this parameter to all the NameService instances and separate them with commas (,).	hdfs://hacluster,hdfs://hacluster
spark.yarn.cluster.driver.extraJavaOptions	Indicates extra JVM option passed to the executor, for example, GC setting and logging. Do not set Spark attributes or heap size using this option. Instead, set Spark attributes using the SparkConf object or the <b>spark-defaults.conf</b> file specified when the spark-submit script is called. Set heap size using <b>spark.executor.memory</b> .	-Xloggc:<LOG_DIR>/gc.log -XX: +PrintGCDetails -XX:-OmitStackTraceln- FastThrow -XX:+PrintGCTimeStamps -XX: +PrintGCDateStamps -XX: +UseGCLogFileRotation - XX:NumberOfGCLogFiles=20 - XX:GCLogFileSize=10M - Dlog4j.configuration=../_spark_conf_ _hadoop_conf_/log4j-executor.properties -Djava.security.auth.login.config=/ _spark_conf___hadoop_conf_/jaas- zk.conf - Dzookeeper.server.principal=zookeeper/ hadoop.<system domain name> - Djava.security.krb5.conf=../_spark_conf_ _hadoop_conf_/kdc.conf - Djetty.version=x.y.z - Dorg.xerial.snappy.tmpdir=\$ {BIGDATA_HOME}/tmp/spark2x_app - Dcarbon.properties.filepath=/ _spark_conf___hadoop_conf_ carbon.properties - Djdk.tls.ephemeralDHKeySize=2048

Configuration Item	Description	Default Value or Configuration Example
spark.driver.extraJavaOptions	Indicates a series of extra JVM options passed to the driver,	-Xloggc:\${SPARK_LOG_DIR}/indexserver-omm-%p-gc.log -XX:+PrintGCDetails -XX:-OmitStackTracelnFastThrow -XX:+PrintGCTimeStamps -XX:+PrintGCDateStamps -XX:MaxDirectMemorySize=512M -XX:MaxMetaspaceSize=512M -XX:+UseGCLogFileRotation -XX:NumberOfGCLogFiles=20 -XX:GCLogFileSize=10M -XX:OnOutOfMemoryError='kill -9 %p' -Djetty.version=x.y.z -Dorg.xerial.snappy.tmpdir=\${BIGDATA_HOME}/tmp/spark2x/JDBCServer/snappy_tmp -Djava.io.tmpdir=\${BIGDATA_HOME}/tmp/spark2x/JDBCServer/io_tmp -Dcarbon.properties.filepath=\${SPARK_CONF_DIR}/carbon.properties -Djdk.tls.ephemeralDHKeySize=2048 -Dspark.ssl.keyStore=\${SPARK_CONF_DIR}/child.keystore #{java_stack_prefer}
spark.eventLog.overwrite	Indicates whether to overwrite any existing file.	false
spark.eventLog.dir	Indicates the directory for logging Spark events if <b>spark.eventLog.enabled</b> is set to <b>true</b> . In this directory, Spark creates a subdirectory for each application and logs events of the application in the subdirectory. You can also set a unified address similar to the HDFS directory so that the History Server can read historical files.	hdfs://hacluster/spark2xJobHistory2x

Configuratio n Item	Description	Default Value or Configuration Example
spark.rando m.port.min	Sets the minimum random port.	22600
spark.authen ticate	Indicates whether Spark authenticates its internal connections. If the application is not running on Yarn, see <b>spark.authenticat e.secret</b> .	true
spark.rando m.port.max	Sets the maximum random port.	22899
spark.eventL og.enabled	Indicates whether to log Spark events, which are used to reconstruct the web UI after the application execution is complete.	true

Configuration Item	Description	Default Value or Configuration Example
spark.executor.extraJavaOptions	Indicates extra JVM option passed to the executor, for example, GC setting and logging. Do not set Spark attributes or heap size using this option.	<pre>-Xloggc:&lt;LOG_DIR&gt;/gc.log -XX: +PrintGCDetails -XX:-OmitStackTraceln- FastThrow -XX:+PrintGCTimeStamps -XX: +PrintGCDateStamps -XX: +UseGCLogFileRotation - XX:NumberOfGCLogFiles=20 - XX:GCLogFileSize=10M - Dlog4j.configuration=./log4j- executor.properties - Djava.security.auth.login.config=./jaas- zk.conf - Dzookeeper.server.principal=zookeeper/ hadoop.&lt;system domain name&gt; - Djava.security.krb5.conf=./kdc.conf - Dcarbon.properties.filepath=./ carbon.properties  -Xloggc:&lt;LOG_DIR&gt;/gc.log -XX: +PrintGCDetails -XX:-OmitStackTraceln- FastThrow -XX:+PrintGCTimeStamps -XX: +PrintGCDateStamps -XX: +UseGCLogFileRotation - XX:NumberOfGCLogFiles=20 - XX:GCLogFileSize=10M - Dlog4j.configuration=./_spark_conf_/ _hadoop_conf_/log4j-executor.properties -Djava.security.auth.login.config=./ _spark_conf_/_hadoop_conf_/jaas- zk.conf - Dzookeeper.server.principal=zookeeper/ hadoop.&lt;system domain name&gt; - Djava.security.krb5.conf=./_spark_conf_/ _hadoop_conf_/kdc.conf - Dcarbon.properties.filepath=./ _spark_conf_/_hadoop_conf_/ carbon.properties - Djdk.tls.ephemeralDHKeySize=2048</pre>
spark.sql.authorization.enabled	Indicates whether to enable authentication for the Hive client.	true

### 17.1.3 Common Parameters

#### Overview

This section describes common configuration items used in Spark. This section is divided into sub-sections based on features to help you quickly find required

configuration items. If you use a MRS cluster, most parameters described in this section have been adapted and you do not need to configure them again. For details about the parameters that need to be configured based on the site requirements, see [Configuring Parameters Rapidly](#).

## Configuring the Number of Stage Retries

When `FetchFailedException` occurs in a Spark task, a stage retry is triggered. To prevent infinite stage retries, the number of stage retries is limited. The number of retry times can be adjusted based on the site requirements.

Configure the following parameters in the `spark-defaults.conf` file on the Spark client.

**Table 17-3** Parameter description

Parameter	Description	Default Value
<code>spark.stage.maxConsecutiveAttempts</code>	Indicates the maximum number of stage retries.	4

## Configuring Whether to Use Cartesian Product

To enable the Cartesian product function, configure the following parameter in the `spark-defaults.conf` configuration file of Spark.

**Table 17-4** Cartesian product parameters

Parameter	Description	Default Value
<code>spark.sql.crossJoin.enabled</code>	Indicates whether to allow implicit Cartesian product execution. <ul style="list-style-type: none"> <li><b>true:</b> Implicit Cartesian product execution is allowed.</li> <li><b>false:</b> Implicit Cartesian product execution is not allowed. In this case, only CROSS JOIN can be explicitly included in the query.</li> </ul>	true

 **NOTE**

- For JDBC applications, configure this parameter in the `spark-defaults.conf` configuration file of the server.
- For tasks submitted by the Spark client, configure this parameter in the `spark-defaults.conf` configuration file of the client.

## Configuring Security Authentication for Long-Time Spark Tasks

In security mode, if the **kinit** command is used for security authentication when the Spark CLI (such as `spark-shell`, `spark-sql`, or `spark-submit`) is used, the task fails due to authentication expiration when the task is running for a long time.

Set the following parameters in the **spark-defaults.conf** configuration file on the client. After the configuration is complete, run the Spark CLI again.

 **NOTE**

If this parameter is set to **true**, ensure that the values of **keytab** and **principal** in **spark-defaults.conf** and **hive-site.xml** are the same.

**Table 17-5** Parameter description

Parameter	Description	Default Value
spark.kerberos.principal	Indicates the principal user who has the Spark operation permission. Contact the MRS cluster administrator to obtain the principal user.	-
spark.kerberos.keytab	Indicates the name and path of the keytab file used to configure Spark operation permissions. Contact the MRS cluster administrator to obtain the keytab file.	-
spark.security.bigdata.loginOnce	<p>Indicates whether the principal user logs in to the system only once. <b>true</b>: single login; <b>false</b>: multiple logins.</p> <p>The difference between a single login and multiple logins is as follows: The Spark community uses the Kerberos user to log in to the system for multiple times. However, the TGT or token may expire, causing the application to fail to run for a long time. The Kerberos login mode of DataSight is modified to allow users to log in only once, which effectively resolves the expiration problem. The restrictions are as follows: The principal and keytab configuration items of Hive must be the same as those of Spark.</p> <p><b>NOTE</b> If this parameter is set to <b>true</b>, ensure that the values of <b>keytab</b> and <b>principal</b> in <b>spark-defaults.conf</b> and <b>hive-site.xml</b> are the same.</p>	true

## Python Spark

Python Spark is the third programming language of Spark except Scala and Java. Different from Java and Scala that run on the JVM platform, Python Spark has its own Python process as well as the JVM process. The following configuration items

apply only to Python Spark scenarios. However, other configuration items can also take effect in Python Spark scenarios.

**Table 17-6** Parameter description

Parameter	Description	Default Value
spark.python.profile	Indicates whether to enable profiling on the Python worker. Use <b>sc.show_profiles()</b> to display the analysis results or display the analysis results before the Driver exits. You can use <b>sc.dump_profiles(path)</b> to dump the results to a disk. If some analysis results have been manually displayed, they will not be automatically displayed before the driver exits.  By default, <b>pyspark.profiler.BasicProfiler</b> is used. You can transfer the specified profiler during SparkContext initialization to overwrite the default profiler.	false
spark.python.worker.memory	Indicates the memory size that can be used by each Python worker process during aggregation. The value format is the same as that of the specified JVM memory, for example, 512 MB and 2 GB. If the memory used by a process during aggregation exceeds the value of this parameter, data will be written to disks.	512m
spark.python.worker.reuse	Indicates whether to reuse Python workers. If the reuse function is enabled, a fixed number of Python workers will be reused by the next batch of submitted tasks instead of forking a Python process for each task. This function is useful in large-scale broadcasting because the data does not need to be transferred from the JVM to the Python workers again for the next batch of submitted tasks.	true

## Dynamic Allocation

Dynamic resource scheduling is a unique feature of the On Yarn mode. This function can be used only after Yarn External Shuffle is enabled. When Spark is used as a resident service, dynamic resource scheduling greatly improves resource utilization. For example, the JDBCServer process does not accept JDBC requests in most of the time. Therefore, releasing resources in this period greatly reduces the waste of cluster resources.

**Table 17-7** Parameter description

Parameter	Description	Default Value
spark.dynamicAllocation.enabled	Indicates whether to use dynamic resource scheduling, which is used to adjust the number of executors registered with the application according to scale. Currently, this parameter is valid only in Yarn mode.  To enable dynamic resource scheduling, set <b>spark.shuffle.service.enabled</b> to <b>true</b> . Related parameters are as follows: <b>spark.dynamicAllocation.minExecutors</b> , <b>spark.dynamicAllocation.maxExecutors</b> , and <b>spark.dynamicAllocation.initialExecutors</b> .	<ul style="list-style-type: none"> <li>JDBCServer2x: true</li> <li>SparkResource2x: false</li> </ul>
spark.dynamicAllocation.minExecutors	Indicates the minimum number of executors.	0
spark.dynamicAllocation.initialExecutors	Indicates the number of initial executors.	spark.dynamicAllocation.minExecutors
spark.dynamicAllocation.maxExecutors	Indicates the maximum number of executors.	2048
spark.dynamicAllocation.schedulerBacklogTimeout	Indicates the first timeout period for scheduling. The unit is second.	1s
spark.dynamicAllocation.sustainedSchedulerBacklogTimeout	Indicates the second and later timeout interval for scheduling.	1s
spark.dynamicAllocation.executorIdleTimeout	Indicates the idle timeout interval for common executors. The unit is second.	60

Parameter	Description	Default Value
spark.dynamicAllocation.cachedExecutorIdleTimeout	Indicates the idle timeout interval for executors with cached blocks.	<ul style="list-style-type: none"> <li>JDBCServer2x: 2147483647s</li> <li>IndexServer2x: 2147483647s</li> <li>SparkResource2x: 120</li> </ul>

## Spark Streaming

Spark Streaming is a streaming data processing function provided by the Spark batch processing platform. It processes data input from external systems in **mini-batch** mode.

Configure the following parameters in the **spark-defaults.conf** file on the Spark client.

**Table 17-8** Parameter description

Parameter	Description	Default Value
spark.streaming.receiver.writeAheadLog.enable	Indicates whether to enable the write-ahead log (WAL) function. After this function is enabled, all input data received by the receiver is saved in the WAL. WAL ensures that data can be restored if the driver program becomes faulty.	false
spark.streaming.unpersist	Determines whether to automatically remove RDDs generated and saved by Spark Streaming from the Spark memory. If this function is enabled, original data received by Spark Streaming is also automatically cleared. If this function is disabled, original data and RDDs cannot be automatically cleared. External applications can access the data in Streaming. This, however, occupies more Spark memory resources.	true

## Spark Streaming Kafka

The receiver is an important component of Spark Streaming. It receives external data, encapsulates the data into blocks, and provides the blocks for Streaming to

consume. The most common data source is Kafka. Spark Streaming integrates Kafka to ensure reliability and can directly use Kafka as the RDD input.

**Table 17-9** Parameter description

Parameter	Description	Default Value
spark.streaming.kafka.maxRatePerPartition	Indicates the maximum rate (number of records per second) for reading data from each Kafka partition if the Kafka direct stream API is used.	-
spark.streaming.blockInterval	Indicates the interval (ms) for accumulating data received by a Spark Streaming receiver into a data block before the data is stored in Spark. A minimum value of 50 ms is recommended.	200ms
spark.streaming.receiver.maxRate	Indicates the maximum rate (number of records per second) for each receiver to receive data. The value <b>0</b> or a negative value indicates no limit to the rate.	-
spark.streaming.receiver.writeAheadLog.enabled	Indicates whether to use ReliableKafkaReceiver. This receiver ensures the integrity of streaming data.	false

## Netty/NIO and Hash/Sort Configuration

Shuffle is critical for big data processing, and the network is critical for the entire shuffle process. Currently, Spark supports two shuffle modes: hash and sort. There are two network modes: Netty and NIO.

**Table 17-10** Parameter description

Parameter	Description	Default Value
spark.shuffle.manager	Indicates the data processing mode. There are two implementation modes: sort and hash. The sort shuffle has a higher memory utilization. It is the default option in Spark 1.2 and later versions.	SORT

Parameter	Description	Default Value
spark.shuffle.consolidateFiles	(Only in hash mode) To merge intermediate files created during shuffle, set this parameter to <b>true</b> . Decreasing the number of files to be created can improve the processing performance of the file system and reduce risks. If the <b>ext4</b> or <b>xfs</b> file system is used, you are advised to set this parameter to <b>true</b> . Due to file system restrictions, this setting on <b>ext3</b> may reduce the processing performance of a server with more than eight cores.	false
spark.shuffle.sort.byPassMergeThreshold	This parameter is valid only when <b>spark.shuffle.manager</b> is set to <b>sort</b> . When Map aggregation is not performed and the number of partitions for Reduce tasks is less than or equal to the value of this parameter, do not merge and sort data to prevent performance deterioration caused by unnecessary sorting.	200
spark.shuffle.io.maxRetries	(Only in Netty mode) If this parameter is set to a non-zero value, fetch failures caused by I/O-related exceptions will be automatically retried. This retry logic helps the large shuffle keep stable when long GC pauses or intermittent network disconnections occur.	12
spark.shuffle.io.numConnectionsPerPeer	(Only in Netty mode) Connections between hosts are reused to reduce the number of connections between large clusters. For a cluster with many disks but a few hosts, this function may make concurrent requests unable to occupy all disks. Therefore, you can increase the value of this parameter.	1
spark.shuffle.io.preferDirectBufs	(Only in Netty mode) The off-heap buffer is used to reduce GC during shuffle and cache block transfer. In an environment where off-heap memory is strictly limited, you can disable it to force all applications from Netty to use heap memory.	true
spark.shuffle.io.retryWait	(Only in Netty mode) Specifies the duration for waiting for fetch retry, in seconds. The maximum delay caused by retry is <b>maxRetries</b> x <b>retryWait</b> . The default value is 15 seconds.	5

## Common Shuffle Configuration

**Table 17-11** Parameter description

Parameter	Description	Default Value
spark.shuffle.spill	If this parameter is set to <b>true</b> , data is overflowed to the disk to limit the memory usage during a Reduce task.	true
spark.shuffle.spill.compress	Indicates whether to compress the data overflowed during shuffle. The algorithm specified by <b>spark.io.compression.codec</b> is used for data compression.	true
spark.shuffle.file.buffer	Specifies the size of the memory buffer for storing output streams of each shuffle file, in KB. These buffers can reduce the number of disk seek and system calls during the creation of intermediate shuffle file streams. You can also set this parameter by setting <b>spark.shuffle.file.buffer.kb</b> .	32KB
spark.shuffle.compress	Indicates whether to compress the output files of a Map task. You are advised to compress the broadcast variables. using <b>spark.io.compression.codec</b> .	true
spark.reducer.maxSizeInFlight	Specifies the maximum output size of the Map task that fetches data from each Reduce task, in MB. Each output requires a buffer, which is the fixed memory overhead of each Reduce task. Therefore, keep the value small unless there is a large amount of memory. You can also set this parameter by setting <b>spark.reducer.maxMbInFlight</b> .	48MB

## Driver Configuration

Spark driver can be considered as the client of Spark applications. All code parsing is completed in this process. Therefore, the parameters of this process are especially important. The following describes how to configure parameters for Spark driver.

- **JavaOptions:** parameter following **-D** in the Java command, which can be obtained by **System.getProperty**
- **ClassPath:** path for loading the Java classes and Native library
- **Java Memory and Cores:** memory and CPU usage of the Java process
- **Spark Configuration:** Spark internal parameter, which is irrelevant to the Java process

**Table 17-12** Parameter description

Parameter	Description	Default Value
spark.driver.extraJavaOptions	<p>Indicates a series of extra JVM options passed to the driver, for example, GC setting and logging.</p> <p>Note: In client mode, this configuration cannot be set directly in the application using SparkConf because the driver JVM has been started. You can use <b>--driver-java-options</b> or the default property file to set the parameter.</p>	For details, see <a href="#">Configuring Parameters Rapidly</a> .
spark.driver.extraClassPath	<p>Indicates the extra class path entries attached to the class path of the driver.</p> <p>Note: In client mode, this configuration cannot be set directly in the application using SparkConf because the driver JVM has been started. You can use <b>--driver-java-options</b> or the default property file to set the parameter.</p>	For details, see <a href="#">Configuring Parameters Rapidly</a> .
spark.driver.userClassPathFirst	<p>(Trial) Indicates whether to allow JAR files added by users to take precedence over Spark JAR files when classes are loaded in the driver. This feature can be used to mitigate conflicts between Spark dependencies and user dependencies. This feature is in the trial phase and is used only in cluster mode.</p>	false
spark.driver.extraLibraryPath	<p>Sets a special library path for starting the driver JVM.</p> <p>Note: In client mode, this configuration cannot be set directly in the application using SparkConf because the driver JVM has been started. You can use <b>--driver-java-options</b> or the default property file to set the parameter.</p>	<ul style="list-style-type: none"> <li>JDBCServer2x: \$ {SPARK_INSTALLED_HOME}/spark/native</li> <li>SparkResource2x: \$ {DATA_NODE_INSTANCE_HOME}/hadoop/lib/native</li> </ul>

Parameter	Description	Default Value
spark.driver.cores	Specifies the number of cores used by the driver process. This parameter is available only in cluster mode.	1
spark.driver.memory	Indicates the memory used by the driver process, that is, the memory used by the SparkContext initialization process (for example, 512 MB and 2 GB).  Note: In client mode, this configuration cannot be set directly in the application using SparkConf because the driver JVM has been started. You can use <b>--driver-java-options</b> or the default property file to set the parameter.	4G
spark.driver.maxResultSize	Indicates the total size of serialization results of all partitions for each Spark action operation (for example, collect). The value must be at least 1 MB. If this parameter is set to <b>0</b> , the size is not limited. If the total amount exceeds this limit, the task will be aborted. If the value is too large, the memory of the driver may be insufficient (depending on the object memory overhead of <b>spark.driver.memory</b> and JVM). Set a proper limit to ensure sufficient memory for the driver.	1G
spark.driver.host	Specifies the host name or IP address for the driver to listen on, which is used for the driver to communicate with the executor.	(local hostname)
spark.driver.port	Specifies the port for the driver to listen on, which is used for the driver to communicate with the executor.	(random)

## ExecutorLauncher Configuration

ExecutorLauncher exists only in Yarn-client mode. In Yarn-client mode, ExecutorLauncher and the driver are not in the same process. Therefore, you need to configure parameters for ExecutorLauncher.

**Table 17-13** Parameter description

Parameter	Description	Default Value
spark.yarn.am.extraJavaOptions	Indicates a string of extra JVM options to pass to the YARN ApplicationMaster in client mode. Use <b>spark.driver.extraJavaOptions</b> in cluster mode.	For details, see <a href="#">Configuring Parameters Rapidly</a> .
spark.yarn.am.memory	Indicates the amount of memory to use for the YARN ApplicationMaster in client mode, in the same format as JVM memory strings (for example, 512 MB or 2 GB). In cluster mode, use <b>spark.driver.memory</b> instead.	1G
spark.yarn.am.memoryOverhead	This parameter is the same as <b>spark.yarn.driver.memoryOverhead</b> . However, this parameter applies only to ApplicationMaster in client mode.	-
spark.yarn.am.cores	Indicates the number of cores to use for the YARN ApplicationMaster in client mode. Use <b>spark.driver.cores</b> in cluster mode.	1

## Executor Configuration

An executor is a Java process. However, unlike the driver and ApplicationMaster, an executor can have multiple processes. Spark supports only same configurations. That is, the process parameters of all executors must be the same.

**Table 17-14** Parameter description

Parameter	Description	Default Value
spark.executor.extraJavaOptions	Indicates extra JVM option passed to the executor, for example, GC setting and logging. Do not set Spark attributes or heap size using this option. Instead, set Spark attributes using the SparkConf object or the <b>spark-defaults.conf</b> file specified when the spark-submit script is called. Set heap size using <b>spark.executor.memory</b> .	For details, see <a href="#">Configuring Parameters Rapidly</a> .

Parameter	Description	Default Value
spark.executor.extraClassPath	Indicates the extra classpath attached to the executor classpath. This parameter ensures compatibility with historical versions of Spark. Generally, you do not need to set this parameter.	-
spark.executor.extraLibraryPath	Sets the special library path used when the executor JVM is started.	For details, see <a href="#">Configuring Parameters Rapidly</a> .
spark.executor.userClassPathFirst	(Trial) Same function as <b>spark.driver.userClassPathFirst</b> . However, this parameter applies to executor instances.	false
spark.executor.memory	Indicates the memory size used by each executor process. Its character string is in the same format as the JVM memory (example: 512 MB or 2 GB).	4G
spark.executorEnv.[EnvironmentVariableName]	Adds the environment variable specified by <b>EnvironmentVariableName</b> to the executor process. You can specify multiple environment variables.	-
spark.executor.logs.rolling.maxRetainedFiles	Sets the number of latest log files to be retained by the system during rolling. The old log files are deleted. This function is disabled by default.	-
spark.executor.logs.rolling.size.maxBytes	Sets the maximum size of the executor log file for rolling. This function is disabled by default. The value is in bytes. To automatically clear old logs, see <b>spark.executor.logs.rolling.maxRetainedFiles</b> .	-
spark.executor.logs.rolling.strategy	Sets the executor log rolling policy. Rolling is disabled by default. The value can be <b>time</b> (time-based rolling) or <b>size</b> (size-based rolling). If this parameter is set to <b>time</b> , the value of the <b>spark.executor.logs.rolling.time.interval</b> attribute is used as the log rolling interval. If this parameter is set to <b>size</b> , <b>spark.executor.logs.rolling.size.maxBytes</b> is used to set the maximum size of the file for rolling.	-

Parameter	Description	Default Value
spark.executor.logs.rolling.time.interval	Sets the time interval for executor log rolling. This function is disabled by default. The value can be <b>daily</b> , <b>hourly</b> , <b>minutely</b> , or any number of seconds. To automatically clear old logs, see <b>spark.executor.logs.rolling.maxRetainedFiles</b> .	daily

## WebUI

The Web UI displays the running process and status of the Spark application.

**Table 17-15** Parameter description

Parameter	Description	Default Value
spark.ui.killEnabled	Allows stages and jobs to be stopped on the web UI. <b>NOTE</b> For security purposes, the default value of this parameter is set to <b>false</b> to prevent misoperations. To enable this function, set this parameter to <b>true</b> in the <b>spark-defaults.conf</b> configuration file. Exercise caution when performing this operation.	true
spark.ui.port	Specifies the port for your application's dashboard, which displays memory and workload data.	<ul style="list-style-type: none"> <li>• JDBC Server2x: <b>4040</b></li> <li>• Spark Resource2x: 0</li> <li>• Index Server2x: 22901</li> </ul>
spark.ui.retainedJobs	Specifies the number of jobs recorded by the Spark UI and status API before GC.	1000
spark.ui.retainedStages	Specifies the number of stages recorded by the Spark UI and status API before GC.	1000

## HistoryServer

A History Server reads the **EventLog** file in the file system and displays the running status of the Spark application.

**Table 17-16** Parameter description

Parameter	Description	Default Value
spark.history.fs.logDirectory	Specifies the log directory of a History Server.	-
spark.history.ui.port	Specifies the port for JobHistory listening to connection.	18080
spark.history.fs.updateInterval	Specifies the update interval of the information displayed on a History Server, in seconds. Each update checks for changes made to the event logs in the persistent store.	10s
spark.history.fs.updateInterval.seconds	Specifies the interval for checking the update of each event log. This parameter has the same function as <b>spark.history.fs.updateInterval</b> . <b>spark.history.fs.updateInterval</b> is recommended.	10s
spark.history.updateInterval	This parameter has the same function as <b>spark.history.fs.updateInterval.seconds</b> and <b>spark.history.fs.updateInterval</b> . <b>spark.history.fs.updateInterval</b> is recommended.	10s

## History Server UI Timeout and Maximum Number of Access Times

**Table 17-17** Parameter description

Parameter	Description	Default Value
spark.session.maxAge	Specifies the session timeout interval, in seconds. This parameter applies only to the security mode. This parameter cannot be set in normal mode.	600
spark.connection.maxRequest	Specifies the maximum number of concurrent client access requests to JobHistory.	5000

## EventLog

During the running of Spark applications, the running status is written into the file system in JSON format in real time for the History Server service to read and reproduce the application running status.

**Table 17-18** Parameter description

Parameter	Description	Default Value
spark.eventLog.enabled	Indicates whether to log Spark events, which are used to reconstruct the web UI after the application execution is complete.	true
spark.eventLog.dir	Indicates the directory for logging Spark events if <b>spark.eventLog.enabled</b> is set to <b>true</b> . In this directory, Spark creates a subdirectory for each application and logs events of the application in the subdirectory. You can also set a unified address similar to the HDFS directory so that the History Server can read historical files.	hdfs://hacluster/spark2x/jobHistory2x
spark.eventLog.compress	Indicates whether to compress logged events when <b>spark.eventLog.enabled</b> is set to <b>true</b> .	false

## Periodic Clearing of Event Logs

Event logs on JobHistory increases with submitted tasks. Too many event log files exist as the number of submitted tasks increases. Spark provides the function for periodically clearing event logs. You can enable this function and set the clearing interval using related parameters.

**Table 17-19** Parameter description

Parameter	Description	Default Value
spark.history.fs.cleaner.enabled	Indicates whether to enable the clearing function.	true
spark.history.fs.cleaner.interval	Indicates the check interval of the clearing function.	1d
spark.history.fs.cleaner.maxAge	Indicates the maximum duration for storing logs.	4d

## Kryo

Kryo is a highly efficient Java serialization framework, which is integrated into Spark by default. Almost all Spark performance tuning requires the process of converting the default serializer of Spark into a Kryo serializer. Kryo serialization

supports only serialization at the Spark data layer. To configure Kryo serialization, set **spark.serializer** to **org.apache.spark.serializer.KryoSerializer** and configure the following parameters to optimize Kryo serialization performance:

**Table 17-20** Parameter description

Parameter	Description	Default Value
spark.kryo.classesToRegister	Specifies the name of the class that needs to be registered with Kryo when Kryo serialization is used. Multiple classes are separated by commas (,).	-
spark.kryo.referenceTracking	Indicates whether to trace the references to the same object when Kryo is used to serialize data. This function is applicable to the scenario where the object graph has circular references or the same object has multiple copies. Otherwise, you can disable this function to improve performance.	true
spark.kryo.registrationRequired	Indicates whether Kryo is used to register an object. When this parameter is set to <b>true</b> , an exception is thrown if an object that is not registered with Kryo is serialized. When it is set to <b>false</b> (default value), Kryo writes unregistered class names to the serialized object. This operation causes a large amount of performance overhead. Therefore, you need to enable this option before deleting a class from the registration queue.	false
spark.kryo.registrationRequired	If Kryo serialization is used, use Kryo to register the class with the custom class. Use this property if you need to register a class in a custom way, such as specifying a custom field serializer. Otherwise, use <b>spark.kryo.classesToRegister</b> , which is simpler. Set this parameter to a class that extends KryoRegistrar.	-
spark.kryo.serializer.buffer.max	Specifies the maximum size of the Kryo serialization buffer, in MB. The value must be greater than the object that attempts to be serialized. If the error "buffer limit exceeded" occurs in Kryo, increase the value of this parameter. You can also set this parameter by setting <b>spark.kryo.serializer.buffer.max</b> .	64MB

Parameter	Description	Default Value
spark.kryoserializer.buffer	Specifies the initial size of the Kryo serialization buffer, in MB. Each core of each worker has a buffer. If necessary, the buffer size will be increased to the value of <b>spark.kryoserializer.buffer.max</b> . You can also set this parameter by setting <b>spark.kryoserializer.buffer</b> .	64KB

## Broadcast

Broadcast is used to transmit data blocks between Spark processes. In Spark, broadcast can be used for JAR packages, files, closures, and returned results. Broadcast supports two modes: Torrent and HTTP. The Torrent mode divides data into small fragments and distributes them to clusters. Data can be obtained remotely if necessary. The HTTP mode saves files to the local disk and transfers the entire files to the remote end through HTTP if necessary. The former is more stable than the latter. Therefore, Torrent is the default broadcast mode.

**Table 17-21** Parameter description

Parameter	Description	Default Value
spark.broadcast.factory	Indicates the broadcast mode.	org.apache.spark.broadcast.TorrentBroadcastFactory
spark.broadcast.blockSize	Indicates the block size of <b>TorrentBroadcastFactory</b> . If the value is too large, the concurrency during broadcast is reduced (the speed is slow). If the value is too small, BlockManager performance may be affected.	4096
spark.broadcast.compress	Indicates whether to compress broadcast variables before sending them. You are advised to compress the broadcast variables.	true

## Storage

Spark features in-memory computing. Spark Storage is used to manage memory resources. Storage stores data blocks generated during RDD caching. The heap memory in the JVM acts as a whole. Therefore, **Storage Memory Size** is an important concept during Spark Storage management.

**Table 17-22** Parameter description

Parameter	Description	Default Value
spark.storage.memoryMapThreshold	Specifies the block size. If the size of a block exceeds the value of this parameter, Spark performs memory mapping for the disk file. This prevents Spark from mapping too small blocks during memory mapping. Generally, memory mapping for blocks whose page size is close to or less than that of the operating system has high overhead.	2m

## PORT

**Table 17-23** Parameter description

Parameter	Description	Default Value
spark.ui.port	Specifies the port for your application's dashboard, which displays memory and workload data.	<ul style="list-style-type: none"> <li>JDBC Server2x: <b>4040</b></li> <li>SparkResource2x: 0</li> </ul>
spark.blockManager.port	Specifies all ports listened by BlockManager. These ports are on both the driver and executor.	<b>Range of Random Ports</b>
spark.driver.port	Specifies the port for the driver to listen on, which is used for the driver to communicate with the executor.	<b>Range of Random Ports</b>

### Range of Random Ports

All random ports must be within a certain range.

**Table 17-24** Parameter description

Parameter	Description	Default Value
spark.random.port.min	Sets the minimum random port.	22600
spark.random.port.max	Sets the maximum random port.	22899

## TIMEOUT

By default, computation tasks that can well process medium-scale data are configured in Spark. However, if the data volume is too large, the tasks may fail due to timeout. In the scenario with a large amount of data, the timeout parameter in Spark needs to be assigned a larger value.

**Table 17-25** Parameter description

Parameter	Description	Default Value
spark.files.fetchTimeout	Specifies the communication timeout (in seconds) when fetching files added using <b>SparkContext.addFile()</b> of the driver.	60s
spark.network.timeout	Specifies the default timeout for all network interactions, in seconds. You can use this parameter to replace <b>spark.core.connection.ack.wait.timeout</b> , <b>spark.akka.timeout</b> , <b>spark.storage.blockManagerSlaveTimeoutMs</b> , or <b>spark.shuffle.io.connectionTimeout</b> .	360s
spark.core.connection.ack.wait.timeout	Specifies the timeout for a connection to wait for a response, in seconds. To avoid long-time waiting caused by GC, you can set this parameter to a larger value.	60

## Encryption

Spark supports SSL for Akka and HTTP (for the broadcast and file server) protocols, but does not support SSL for the web UI and block transfer service.

SSL must be configured on each node and configured for each component involved in communication using a particular protocol.

**Table 17-26** Parameter description

Parameter	Description	Default Value
spark.ssl.enabled	Indicates whether to enable SSL connections for all supported protocols.  All SSL settings similar to <b>spark.ssl.xxx</b> indicate the global configuration of all supported protocols. To override the global configuration of a particular protocol, you must override the property in the namespace specified by the protocol.  Use <b>spark.ssl.YYY.XXX</b> to overwrite the global configuration of the particular protocol specified by <b>YYY</b> . <b>YYY</b> can be either <b>akka</b> for Akka-based connections or <b>fs</b> for the broadcast and file server.	false
spark.ssl.enabledAlgorithms	Indicates the comma-separated list of passwords. The specified passwords must be supported by the JVM.	-
spark.ssl.keyPassword	Specifies the password of a private key in the keystore.	-
spark.ssl.keystore	Specifies the path of the keystore file. The path can be absolute or relative to the directory where the component is started.	-
spark.ssl.keystorePassword	Specifies the password of the keystore.	-
spark.ssl.protocol	Specifies the protocol name. This protocol must be supported by the JVM. The reference list of protocols is available on this page.	-
spark.ssl.trustStore	Specifies the path of the truststore file. The path can be absolute or relative to the directory where the component is started.	-
spark.ssl.trustStorePassword	Specifies the password of the truststore.	-

## Security

Spark supports shared key-based authentication. You can use **spark.authenticate** to configure authentication. This parameter controls whether the Spark communication protocol uses the shared key for authentication. This authentication is a basic handshake that ensures that both sides have the same shared key and are allowed to communicate. If the shared keys are different, the communication is not allowed. You can create shared keys as follows:

- For Spark on Yarn deployments, set **spark.authenticate** to **true**. Then, shared keys are automatically generated and distributed. Each application exclusively occupies a shared key.

- For other types of Spark deployments, configure Spark parameter **spark.authenticate.secret** on each node. All masters, workers, and applications use this key.

**Table 17-27** Parameter description

Parameter	Description	Default Value
spark.acls.enable	Indicates whether to enable Spark ACLs. If Spark ACLs are enabled, the system checks whether the user has the permission to access and modify jobs. Note that this requires the user to be identifiable. If the user is identified as invalid, the check will not be performed. Filters can be used to verify and set users on the UI.	true
spark.admin.acls	Specifies the comma-separated list of users/administrators that have the permissions to view and modify all Spark jobs. This list can be used if you are running on a shared cluster and working with the help of an MRS cluster administrator or developer.	admin
spark.authenticate	Indicates whether Spark authenticates its internal connections. If the application is not running on Yarn, see <b>spark.authenticate.secret</b> .	true
spark.authenticate.secret	Sets the key for authentication between Spark components. This parameter must be set if Spark does not run on Yarn and authentication is disabled.	-
spark.modify.acls	Specifies the comma-separated list of users who have the permission to modify Spark jobs. By default, only users who have enabled Spark jobs have the permission to modify the list (for example, delete the list).	-
spark.ui.view.acls	Specifies the comma-separated list of users who have the permission to access the Spark web UI. By default, only users who have enabled Spark jobs have the access permission.	-

## Enabling the Authentication Mechanism Between Spark Processes

Spark processes support shared key-based authentication. You can configure **spark.authenticate** to control whether Spark performs authentication during communication. In this authentication mode, the two communication parties share the same key only using simple handshakes.

Configure the following parameters in the **spark-defaults.conf** file on the Spark client.

**Table 17-28** Parameter description

Parameter	Description	Default Value
spark.authenticate	For Spark on Yarn deployments, set this parameter to <b>true</b> . Then, keys are automatically generated and distributed, and each application uses a unique key.	true

## Compression

Data compression is policy that optimizes memory usage at the expense of CPU. Therefore, when the Spark memory is severely insufficient (this issue is common due to the characteristics of in-memory computing), data compression can greatly improve performance. Spark supports three types of compression algorithm: Snappy, LZ4, and LZF. Snappy is the default compression algorithm and invokes the native method to compress and decompress data. In Yarn mode, pay attention to the impact of non-heap memory on the container process.

**Table 17-29** Parameter description

Parameter	Description	Default Value
spark.io.compression.codec	Indicates the codec for compressing internal data, such as RDD partitions, broadcast variables, and shuffle output. By default, Spark supports three types of compression algorithm: LZ4, LZF, and Snappy. You can specify algorithms using fully qualified class names, such as <b>org.apache.spark.io.LZ4CompressionCodec</b> , <b>org.apache.spark.io.LZFCompressionCodec</b> , and <b>org.apache.spark.io.SnappyCompressionCodec</b> .	lz4
spark.io.compression.lz4.block.size	Indicates the block size (bytes) used in LZ4 compression when the LZ4 compression algorithm is used. When LZ4 is used, reducing the block size also reduces the shuffle memory usage.	32768
spark.io.compression.snappy.block.size	Indicates the block size (bytes) used in Snappy compression when the Snappy compression algorithm is used. When Snappy is used, reducing the block size also reduces the shuffle memory usage.	32768
spark.shuffle.compress	Indicates whether to compress the output files of a Map task. You are advised to compress the broadcast variables. using <b>spark.io.compression.codec</b> .	true

Parameter	Description	Default Value
spark.shuffle.spill.compress	Indicates whether to compress the data overflowed during shuffle using <b>spark.io.compression.codec</b> .	true
spark.eventLog.compress	Indicates whether to compress logged events when <b>spark.eventLog.enabled</b> is set to <b>true</b> .	false
spark.broadcast.compress	Indicates whether to compress broadcast variables before sending them. You are advised to compress the broadcast variables.	true
spark.rdd.compress	Indicates whether to compress serialized RDD partitions (for example, the <b>StorageLevel.MEMORY_ONLY_SER</b> partition). Substantial space can be saved at the cost of some extra CPU time.	false

## Reducing the Probability of Abnormal Client Application Operations When Resources Are Insufficient

When resources are insufficient, ApplicationMaster tasks must wait and will not be processed until enough resources are available for use. If the actual waiting time exceeds the configured waiting time, the ApplicationMaster tasks will be deleted. Adjust the following parameters to reduce the probability of abnormal client application operation.

Configure the following parameters in the **spark-defaults.conf** file on the client.

**Table 17-30** Parameter description

Parameter	Description	Default Value
spark.yarn.applicationMaster.waitTries	Specifies the number of the times that ApplicationMaster waits for Spark master, which is also the times that ApplicationMaster waits for SparkContext initialization. Enlarge this parameter value to prevent ApplicationMaster tasks from being deleted and reduce the probability of abnormal client application operations.	10
spark.yarn.am.memory	Specifies the ApplicationMaster memory. Enlarge this parameter value to prevent ApplicationMaster tasks from being deleted by ResourceManager due to insufficient memory and reduce the probability of abnormal client application operations.	1G

## 17.1.4 Spark on HBase Overview and Basic Applications

### Scenario

Spark on HBase allows users to query HBase tables in Spark SQL and to store data for HBase tables by using the Beeline tool. You can use HBase APIs to create, read data from, and insert data into tables.

### Procedure

- Step 1** Log in to Manager and choose **Cluster** > *Name of the desired cluster* > **Cluster Properties** to check whether the cluster is in security mode.
- If yes, go to [Step 2](#).
  - If no, go to [Step 5](#).
- Step 2** Choose **Cluster** > *Name of the desired cluster* > **Service** > **Spark2x** > **Configuration** > **All Configurations** > **JDBCServer2x** > **Default**, and modify the following parameter.

**Table 17-31** Parameter list 1

Parameter	Default Value	Changed To
spark.yarn.security.credentials.hbase.enabled	false	true

#### NOTE

To ensure that Spark2x can access HBase for a long time, do not modify the following parameters of the HBase and HDFS services:

- dfs.namenode.delegation.token.renew-interval
- dfs.namenode.delegation.token.max-lifetime
- hbase.auth.key.update.interval
- hbase.auth.token.max.lifetime (The value is fixed to **604800000** ms, that is, 7 days.)

If the preceding parameter configuration must be modified based on service requirements, ensure that the value of the HDFS parameter **dfs.namenode.delegation.token.renew-interval** is not greater than the values of the HBase parameters **hbase.auth.key.update.interval**, **hbase.auth.token.max.lifetime**, and **dfs.namenode.delegation.token.max-lifetime**.

- Step 3** Choose **SparkResource2x** > **Default** and modify the following parameters.

**Table 17-32** Parameter list 2

Parameter	Default Value	Changed To
spark.yarn.security.credentials.hbase.enabled	false	true

**Step 4** Restart the Spark2x service for the configuration to take effect.

 **NOTE**

To use the Spark on HBase function on the Spark2x client, you need to download and install the Spark2x client again.

**Step 5** On the Spark2x client, use the spark-sql or spark-beeline connection to query tables created by Hive on HBase. You can create an HBase table by running SQL commands or create an external table to associate the HBase table. Before creating tables, ensure that HBase tables exist in HBase. The HBase table **table1** is used as an example.

1. Run the following commands to create the HBase table using the Beeline tool:

```
create table hbaseTable
(
  id string,
  name string,
  age int
)
using org.apache.spark.sql.hbase.HBaseSource
options(
  hbaseTableName "table1",
  keyCols "id",
  colsMapping "
name=cf1.cq1,
age=cf1.cq2
");
```

 **NOTE**

- **hbaseTable**: name of the created Spark table
  - **id string, name string, age int**: field name and field type of the Spark table
  - **table1**: name of the HBase table
  - *id*: row key column name of the HBase table
  - *name=cf1.cq1, age=cf1.cq2*: mapping between columns in the Spark table and columns in the HBase table. The **name** column of the Spark table maps the **cq1** column in the **cf1** column family of the HBase table, and the **age** column of the Spark table maps the **cq2** column in the **cf1** column family of the HBase table.
2. Run the following command to import data to the HBase table using a CSV file:

```
hbase org.apache.hadoop.hbase.mapreduce.ImportTsv -  
Dimporttsv.separator="," -  
Dimporttsv.columns=HBASE_ROW_KEY,cf1:cq1,cf1:cq2,cf1:cq3,cf1:cq4,cf1:cq5  
table1 /hperson
```

Where **table1** indicates the name of the HBase table, and **/hperson** indicates the path where the CSV file is stored.

- Run the following command to query data in spark-sql or spark-beeline, where *hbaseTable* is the corresponding Spark table name: The command is as follows:

```
select * from hbaseTable;
```

----End

## 17.1.5 Spark on HBase V2 Overview and Basic Applications

### Scenario

Spark on HBase V2 allows users to query HBase tables in Spark SQL and to store data for HBase tables by using the Beeline tool. You can use HBase APIs to create, read data from, and insert data into tables.

### Procedure

- Log in to Manager and choose **Cluster** > *Name of the desired cluster* > **Cluster Properties** to check whether the cluster is in security mode.
  - If yes, go to [Step 2](#).
  - If no, go to [Step 5](#).
- Choose **Cluster** > *Name of the desired cluster* > **Service** > **Spark2x** > **Configuration** > **All Configurations** > **JDBCServer2x** > **Default**, and modify the following parameter.

**Table 17-33** Parameter list 1

Parameter	Default Value	Changed To
spark.yarn.security.credentials.hbase.enabled	false	true

#### NOTE

To ensure that Spark2x can access HBase for a long time, do not modify the following parameters of the HBase and HDFS services:

- dfs.namenode.delegation.token.renew-interval
- dfs.namenode.delegation.token.max-lifetime
- hbase.auth.key.update.interval
- hbase.auth.token.max.lifetime (The value is fixed to **604800000** ms, that is, 7 days.)

If the preceding parameter configuration must be modified based on service requirements, ensure that the value of the HDFS parameter **dfs.namenode.delegation.token.renew-interval** is not greater than the values of the HBase parameters **hbase.auth.key.update.interval**, **hbase.auth.token.max.lifetime**, and **dfs.namenode.delegation.token.max-lifetime**.

- Choose **SparkResource2x** > **Default** and modify the following parameters.

**Table 17-34** Parameter list 2

Parameter	Default Value	Changed To
spark.yarn.security.credentials.hbase.enabled	false	true

**Step 4** Restart the Spark2x service for the configuration to take effect.

 **NOTE**

If you need to use the Spark on HBase function on the Spark2x client, download and install the Spark2x client again.

**Step 5** On the Spark2x client, use the spark-sql or spark-beeline connection to query tables created by Hive on HBase. You can create an HBase table by running SQL commands or create an external table to associate the HBase table. For details, see the following description. The following uses the HBase table **table1** as an example.

1. Run the following commands to create a table using the spark-beeline tool:

```
create table hbaseTable1
(id string, name string, age int)
using org.apache.spark.sql.hbase.HBaseSourceV2
options(
hbaseTableName "table2",
keyCols "id",
colsMapping "name=cf1.cq1,age=cf1.cq2");
```

 **NOTE**

- **hbaseTable1**: name of the created Spark table
  - **id string, name string, age int**: field name and field type of the Spark table
  - **table2**: name of the HBase table
  - **id**: row key column name of the HBase table
  - **name=cf1.cq1, age=cf1.cq2**: mapping between columns in the Spark table and columns in the HBase table. The **name** column of the Spark table maps the **cq1** column in the **cf1** column family of the HBase table, and the **age** column of the Spark table maps the **cq2** column in the **cf1** column family of the HBase table.
2. Run the following command to import data to the HBase table using a CSV file:
- ```
hbase org.apache.hadoop.hbase.mapreduce.ImportTsv -
Dimporttsv.separator="," -
Dimporttsv.columns=HBASE_ROW_KEY,cf1:cq1,cf1:cq2,cf1:cq3,cf1:cq4,cf1:cq5
table2 /hperson
```
- Where **table2** indicates the name of the HBase table, and **/hperson** indicates the path where the CSV file is stored.
3. Run the following command to query data in spark-sql or spark-beeline.

```
select * from hbaseTable1;
```

----End

## 17.1.6 SparkSQL Permission Management(Security Mode)

### 17.1.6.1 Spark SQL Permissions

#### SparkSQL Permissions

Similar to Hive, Spark SQL is a data warehouse framework built on Hadoop, providing storage of structured data like structured query language (SQL).

MRS supports users, user groups, and roles. Permission must be assigned to roles and then roles are bound to users or user groups. Users can obtain permissions only by binding a role or joining a group that is bound with a role.

#### NOTE

- If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. For details, see [Adding a Ranger Access Permission Policy for Spark2x](#).
- After Ranger authentication is enabled or disabled on Spark2x, you need to restart Spark2x and download the client again or update the client configuration file `spark/conf/spark-defaults.conf`.

Enable Ranger authentication: `spark.ranger.plugin.authorization.enable=true`

Disable Ranger authentication: `spark.ranger.plugin.authorization.enable=false`

#### Permission Management


Spark SQL permission management indicates the permission system for managing and controlling users' operations on databases, to ensure that different users can operate databases separately and securely. A user can operate another user's tables and databases only with the corresponding permissions. Otherwise, operations will be rejected.

Spark SQL permission management integrates the functions of Hive management. The MetaStore service of Hive and the permission granting function on the page are required to enable Spark SQL permission management.

**Figure 17-3** shows the basic architecture of SparkSQL permission management. This architecture includes two parts: granting permissions on the page, and obtaining and judging a service.

- Granting permissions on the page: Spark SQL only supports granting permissions on the page. On FusionInsight Manager, choose **System > Permission** to add or delete a user, user group, or a role, and to grant permissions or cancel permissions.
- Obtaining and judging a service: When the DDL and DML commands are received from a client, Spark SQL will obtain the client's permissions on database information from MetaStore, and check whether the required permissions are included. If the required permissions are included, continue the execution. If the required permissions are not included, reject the user's operations. After the MetaStore permissions are checked, ACL permission also needs to be checked on HDFS.

**Figure 17-3** Spark SQL permission management architecture



Additionally, Spark SQL provides column and view permissions to meet requirements of different scenarios.

- Column permission
  - Spark SQL permission control consists of metadata permission control and HDFS ACL permission control. When Hive MetaStore automatically synchronizes table permissions to the HDFS ACL, column-level permissions are not synchronized. In other words, a user with partial or all column-level permissions cannot access the entire HDFS file using the HDFS client.
    - In **spark-sql** mode, users with only column-level permissions cannot access HDFS files. Therefore, they cannot access the columns of the corresponding tables.
    - In Beeline/JDBCServer mode, permissions are assigned among users, for example, the permissions on the table created by user A are assigned to user B.
      - **hive.server2.enable.doAs=true** (configured in the **hive-site.xml** file on the Spark server)  
In this case, user B cannot query the information. You need to manually assign the read permission on the file in HDFS.
      - **hive.server2.enable.doAs=false**
        - Users A and B are connected by Beeline. User B can query the information.
        - User A creates a table using SQL statements, and user B can query the table in Beeline.

However, information query is not supported in other scenarios, for example, user A uses Beeline to create a table and user B uses SQL

to query the table, or user A uses SQL to create a table and user B uses SQL to query the table. You need to manually assign the read permission on the file in HDFS.

 **NOTE**

The **spark** user is an Spark administrator in HDFS ACL permission control. The permission control of the Beeline client user depends only on the metadata permission on Spark.

- View permission

View permission indicates the operation permission such as query and modification on the view of a table, regardless of the corresponding permission of a table. Namely, if you have the permission to query the view of a table, the permission to query the table is not mandatory. The view permission is applicable to the whole table but not to the columns.

Restrictions of view and column permissions on SparkSQL are similar. The following uses the view permission as an example:

- In spark-sql mode, if you have only the view permission but not the table permission and do not have the permission to read HDFS, you cannot access the table data stored in HDFS. That is, you cannot query the view of the table.
- In Beeline/JDBCServer mode, permissions are assigned among users, for example, the permissions on the view created by user A are assigned to user B.

- **hive.server2.enable.doAs=true** (configured in the **hive-site.xml** file on the Spark server)

In this case, user B cannot query the information. You need to manually assign the read permission on the file in HDFS.

- **hive.server2.enable.doAs=false**
  - Users A and B are connected by Beeline. User B can query the information.
  - User A creates a view using SQL statements, and user B can query the view in Beeline.

However, information query is not supported in other scenarios. For example, user A uses Beeline to create a view but user B cannot use SQL to query the view, or user A uses SQL to create a view but user B cannot use SQL to query the view. You need to manually assign the read permission on the file in HDFS.

Permission of operations on the view of a table is as follows:

- To create a view, you must have the CREATE permission on the database and the SELECT and SELECT\_of\_GRANT permissions on the tables.
- Creating and describing a view only entail the SELECT permission on the view. Querying views and tables at the same time entails the SELECT permission on other tables. For example, to perform **select \* from v1 join t1**, you must have the SELECT permission on the **v1** view and **t1** table, even through the **v1** view depends on the **t1** table.

 NOTE

In Beeline/JDBCServer mode, to query a view, you must have the SELECT permission on the tables. In spark-sql mode, to query a view, you must have the SELECT permission on the view and tables.

- Deleting and modifying a view entail the permission of owner on the view.

## SparkSQL Permission Model

If you want to perform SQL operations using SparkSQL, you must be granted with permissions of SparkSQL databases and tables (include external tables and views). The complete permission model of SparkSQL consists of the meta data permission and HDFS file permission. Permissions required to use a database or a table is just one type of SparkSQL permission.

- Metadata permissions

Metadata permissions are controlled at the metadata layer. Similar to traditional relational databases, SparkSQL databases involve the CREATE and SELECT permissions, and tables and columns involve the SELECT, INSERT, UPDATE, and DELETE permissions. SparkSQL also supports the Spark permissions of **OWNERSHIP** and **ADMIN**.

- Data file permissions (that is, HDFS file permissions)

SparkSQL database and table files are stored in HDFS. The created databases or tables are saved in the **/user/hive/warehouse** directory of HDFS by default. The system automatically creates subdirectories named after database names and database table names. To access a database or table, you must have the **Read**, **Write** and **Execute** permissions on the corresponding file in HDFS.

To perform various operations on SparkSQL databases or tables, you need to associate the metadata permission and HDFS file permission. For example, to query SparkSQL data tables, you need to associate the metadata permission **SELECT** and HDFS file permissions **Read** and **Execute**.

Using the management function of Manager GUI to manage the permissions of SparkSQL databases and tables, only requires the configuration of metadata permission, and the system will automatically associate and configure the HDFS file permission. In this way, operations on the interface are simplified, and the efficiency is improved.

## Usage Scenarios and Related Permissions

Creating a database with SparkSQL service requires users to join in the hive group, without granting a role. Users have all permissions on the databases or tables created by themselves in Hive or HDFS. They can create tables, select, delete, insert, or update data, and grant permissions to other users to allow them to access the tables and corresponding HDFS directories and files.

A user can access the tables or database only with permissions. Users' permissions vary depending on different SparkSQL scenarios.

**Table 17-35** SparkSQL scenarios

| Typical Scenario                             | Required Permission  |
|--|--|
| Using SparkSQL tables, columns, or databases | Permissions required in different scenarios are as follows: <ul style="list-style-type: none"> <li>• To create a table, the CREATE permission is required.</li> <li>• To query data, the SELECT permission is required.</li> <li>• To insert data, the INSERT permission is required.</li> </ul> |
| Associating and using other components       | In some scenarios, except the SparkSQL permission, other permissions may be also required. For example:<br>Using Spark on HBase to query HBase data in SparkSQL requires HBase permissions.  |

In some special SparkSQL scenarios, other permissions must be configured separately.

**Table 17-36** SparkSQL scenarios and required permissions

| Scenario  | Required Permission  |
|---|--|
| Creating SparkSQL databases, tables, and external tables, or adding partitions to created Hive tables or external tables when data files specified by Hive users are saved to other HDFS directories except <b>/user/hive/warehouse</b> | <ul style="list-style-type: none"> <li>• The directory must exist, the client user must be the owner of the directory, and the user must have the <b>Read, Write, and Execute</b> permissions on the directory. The user must have the <b>Read</b> and <b>Execute</b> permissions of all the upper-layer directories of the directory.</li> <li>• If the Spark version is later than 2, the <b>Create</b> permission of the Hive database is required if you want to create a HBase table. However, in Spark 1.5, the <b>Create</b> permissions of both the Hive database and HBase namespace are required if you want to create a HBase table.</li> </ul> |

| Scenario   | Required Permission   |
|--|---|
| Importing all the files or specified files in a specified directory to the table using load  | <ul style="list-style-type: none"> <li>• The data source is a Linux local disk, the specified directory exists, and the system user <b>omm</b> has read and execute permission of the directory and all its upper-layer directories. The specified file exists, and user <b>omm</b> has the <b>Read</b> permission on the file and has the <b>Read</b> and <b>Execute</b> permissions on all the upper-layer directories of the file.</li> <li>• The data source is HDFS, the specified directory exists, and the SparkSQL user is the owner of the directory and has the <b>Read, Write, and Execute</b> permissions on the directory and its subdirectories, and has the <b>Read</b> and <b>Execute</b> permissions on all its upper-layer directories. The specified file exists, and the SparkSQL user is the owner of the file and has the <b>Read, Write, and Execute</b> permissions on the file and has the <b>Read</b> and <b>Execute</b> permissions on all its upper-layer directories.</li> </ul> |
| Creating or deleting functions or modifying any database   | The <b>ADMIN</b> permission is required.  |
| Performing operations on all databases and tables in Hive  | The user must be added to the <b>supergroup</b> user group, and be assigned the <b>ADMIN</b> permission.  |
| After assigning the <b>Insert</b> permission on some DataSource tables, assigning the <b>Write</b> permission on table directories in HDFS before performing the insert or analyze operation | When the <b>Insert</b> permission is assigned to the <b>spark datasource</b> table, if the table format is text, CSV, JSON, Parquet, or ORC, the permission on the table directory is not changed. After the <b>Insert</b> permission is assigned to the DataSource table of the preceding formats, you need to assign the <b>Write</b> permission to the table directories in HDFS separately so that users can perform the insert or analyze operation on the tables.   |

### 17.1.6.2 Creating a Spark SQL Role

#### Scenario

This section describes how to create and configure a SparkSQL role on Manager as the MRS cluster administrator. The Spark SQL role can be configured with the Spark administrator permission or the permission of performing operations on the table data.

Creating a database with Hive requires users to join in the **hive** group, without granting a role. Users have all permissions on the databases or tables created by themselves in Hive or HDFS. They can create tables, select, delete, insert, or update data, and grant permissions to other users to allow them to access the

tables and corresponding HDFS directories and files. The created databases or tables are saved in the `/user/hive/warehouse` directory of HDFS by default.

 **NOTE**

- If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. For details, see [Adding a Ranger Access Permission Policy for Spark2x](#).
- After Ranger authentication is enabled or disabled on Spark2x, you need to restart Spark2x and download the client again or update the client configuration file `spark/conf/spark-defaults.conf`.

Enable Ranger authentication: `spark.ranger.plugin.authorization.enable=true`

Disable Ranger authentication: `spark.ranger.plugin.authorization.enable=false`

## Procedure

1. Log in to Manager, and choose **System > Permission > Role**.
2. Click **Create Role** and set a role name and enter description.
3. Set **Configure Resource Permission**. For details, see [Table 17-37](#).
  - **Hive Admin Privilege:** Hive administrator permissions.
  - **Hive Read Write Privileges:** Hive data table management permission, which is the operation permission to set and manage the data of created tables.

 **NOTE**

- Hive role management supports the administrator permission, and the permissions of accessing tables and views, without granting the database permission.
- The permissions of the Hive administrator do not include the permission to manage HDFS.
- If there are too many tables in the database or too many files in tables, the permission granting may last a while. For example, if a table contains 10,000 files, the permission granting lasts about 2 minutes.

**Table 17-37** Setting a role

| Task                          | Operation  |
|-------------------------------|--|
| Hive administrator permission | <p>In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Hive</b> and select <b>Hive Admin Privilege</b>.</p> <p>After being bound to the Hive administrator role, perform the following operations during each maintenance operation:</p> <ol style="list-style-type: none"> <li>1. Log in to the node where the Spark2x client is installed as the client installation user.</li> <li>2. Run the following command to configure environment variables:<br/>For example, if the Spark2x client installation directory is <code>/opt/client</code>, run <b>source /opt/client/bigdata_env</b>.<br/><b>source /opt/client/Spark2x/component_env</b></li> <li>3. Run the following command to perform user authentication:<br/><b>kinit Hive service user</b></li> <li>4. Run the following command to log in to the client tool:<br/><b>/opt/client/Spark2x/spark/bin/beeline -u "jdbc:hive2://&lt;zkNode1_IP&gt;:&lt;zkNode1_Port&gt;,&lt;zkNode2_IP&gt;:&lt;zkNode2_Port&gt;,&lt;zkNode3_IP&gt;:&lt;zkNode3_Port&gt;/;serviceDiscovery-Mode=zooKeeper;zooKeeperNamespace=sparkthriftserver2x;user.principal=spark2x/hadoop.&lt;system domain name&gt;@&lt;system domain name&gt;;sasLQop=auth-conf;auth=KERBEROS;principal=spark2x/hadoop.&lt;system domain name&gt;@&lt;system domain name&gt;;"</b></li> </ol> |

| Task   | Operation   |
|--|---|
|  | <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>• <code>&lt;zkNode1_IP&gt;:&lt;zkNode1_Port&gt;</code>, <code>&lt;zkNode2_IP&gt;:&lt;zkNode2_Port&gt;</code>, <code>&lt;zkNode3_IP&gt;:&lt;zkNode3_Port&gt;</code> indicates the ZooKeeper URL, for example, 192.168.81.37:2181,192.168.195.232:2181,192.168.169.84:2181.</li> <li>• <code>sparkthriftserver</code> indicates a ZooKeeper directory, from which a random TriftServer or ProxyThriftServer is connected by the client.</li> <li>• You can log in to Manager, choose <b>System &gt; Permission &gt; Domain and Mutual Trust</b>, and view the value of <b>Local Domain</b>, which is the current system domain name. <code>spark2x/hadoop.&lt;System domain name&gt;</code> is the username. All letters in the system domain name contained in the username are lowercase letters. For example, <b>Local Domain</b> is set to <code>9427068F-6EFA-4833-B43E-60CB641E5B6C.COM</code>, and the username is <code>spark2x/hadoo.9427068f-6efa-4833-b43e-60cb641e5b6c.com</code>.</li> </ul> <p>5. Run the following command to update the administrator permissions:<br/><b>set role admin;</b></p> |
| Setting the permission to query a table of another user in the default database          | <ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Hive</b> &gt; <b>Hive Read Write Privileges</b>.</li> <li>2. Click the name of the specified database in the database list. Tables in the database are displayed.</li> <li>3. In the <b>Permission</b> column of the specified table, select <b>SELECT</b>.</li> </ol>   |
| Setting the permission to import data to a table of another user in the default database | <ol style="list-style-type: none"> <li>1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> &gt; <b>Hive</b> &gt; <b>Hive Read Write Privileges</b>.</li> <li>2. Click the name of the specified database in the database list. Tables in the database are displayed.</li> <li>3. In the <b>Permission</b> column of the specified table, select <b>DELETE</b> and <b>INSERT</b>.</li> </ol>   |

4. Click **OK**.

### 17.1.6.3 Configuring Permissions for SparkSQL Tables, Columns, and Databases

#### Scenario

You can configure related permissions if you need to access tables or databases created by other users. SparkSQL supports column-based permission control. If a user needs to access some columns in tables created by other users, the user must be granted the permission for columns. The following describes how to grant table, column, and database permissions to users by using the role management function of Manager.

#### Procedure

The operations for granting permissions on SparkSQL tables, columns, and databases are the same as those for Hive. For details, see [Permission Management](#).

#### NOTE

- Any permission for a table in the database is automatically associated with the HDFS permission for the database directory to facilitate permission management. When any permission for a table is canceled, the system does not automatically cancel the HDFS permission for the database directory to ensure performance. In this case, users can only log in to the database and view table names.
- When the query permission on a database is added to or deleted from a role, the query permission on tables in the database is automatically added to or deleted from the role. This mechanism is inherited from Hive.
- In Spark, the column name of the struct data type cannot contain special characters, that is, characters other than letters, digits, and underscores (\_). If the column name of the struct data type contains special characters, the column cannot be displayed on the FusionInsight Manager console when you grant permissions to roles on the role page.

#### Concepts

SparkSQL statements are processed in SparkSQL. [Table 17-38](#) describes the permission requirements.

**Table 17-38** Scenarios of using SparkSQL tables, columns, or databases

| Scenario              | Required Permission  |
|-----------------------|--|
| CREATE TABLE          | <b>CREATE</b> , RWX+ownership (for creating external tables - the location)<br><b>NOTE</b><br>When creating datasource tables in a specified file path, the RWX and ownership permission on the file next to the path is required. |
| DROP TABLE            | <b>Ownership</b> (of table)  |
| DROP TABLE PROPERTIES | <b>Ownership</b>   |
| DESCRIBE TABLE        | <b>Select</b>  |

| Scenario                                       | Required Permission   |
|--|---|
| SHOW PARTITIONS                                | <b>Select</b>   |
| ALTER TABLE LOCATION                           | <b>Ownership</b> , RWX+ownership (for new location)   |
| ALTER PARTITION LOCATION                       | <b>Ownership</b> , RWX+ownership (for new partition location)   |
| ALTER TABLE ADD PARTITION                      | <b>Insert</b> , RWX and ownership (for partition location)  |
| ALTER TABLE DROP PARTITION                     | <b>Delete</b>   |
| ALTER TABLE(all of them except the ones above) | <b>Update, Ownership</b>  |
| TRUNCATE TABLE                                 | <b>Ownership</b>  |
| CREATE VIEW                                    | <b>Select, Grant Of Select, CREATE</b>  |
| ALTER VIEW PROPERTIES                          | <b>Ownership</b>  |
| ALTER VIEW RENAME                              | <b>Ownership</b>  |
| ALTER VIEW ADD PARTS                           | <b>Ownership</b>  |
| ALTER VIEW AS                                  | <b>Ownership</b>  |
| ALTER VIEW DROPPARTS                           | <b>Ownership</b>  |
| ANALYZE TABLE                                  | <b>Search, Insert</b>   |
| SHOW COLUMNS                                   | <b>Select</b>   |
| SHOW TABLE PROPERTIES                          | <b>Select</b>   |
| CREATE TABLE AS SELECT                         | <b>Select, CREATE</b>   |
| SELECT   | <b>Select</b><br><b>NOTE</b><br>The same as tables, you need to have the <b>Select</b> permission on a view when performing a SELECT operation on the view. |
| INSERT   | <b>Insert, Delete (for overwrite)</b>   |
| LOAD   | <b>Insert, Delete</b> , RWX+ownership(input location)   |
| SHOW CREATE TABLE                              | <b>Select, Grant Of Select</b>  |
| CREATE FUNCTION                                | <b>ADMIN</b>  |
| DROP FUNCTION                                  | <b>ADMIN</b>  |
| DESC FUNCTION                                  | -   |
| SHOW FUNCTIONS                                 | -   |

| Scenario               | Required Permission |
|------------------------|---------------------|
| MSCK (metastore check) | <b>Ownership</b>    |
| ALTER DATABASE         | <b>ADMIN</b>        |
| CREATE DATABASE        | -                   |
| SHOW DATABASES         | -                   |
| EXPLAIN                | <b>Select</b>       |
| DROP DATABASE          | <b>Ownership</b>    |
| DESC DATABASE          | -                   |
| CACHE TABLE            | <b>Select</b>       |
| UNCACHE TABLE          | <b>Select</b>       |
| CLEAR CACHE TABLE      | <b>ADMIN</b>        |
| REFRESH TABLE          | <b>Select</b>       |
| ADD FILE               | <b>ADMIN</b>        |
| ADD JAR                | <b>ADMIN</b>        |
| HEALTHCHECK            | -                   |

### 17.1.6.4 Configuring Permissions for SparkSQL to Use Other Components

#### Scenario

SparkSQL may need to be associated with other components. For example, Spark on HBase requires HBase permissions. The following describes how to associate SparkSQL with HBase.

#### Prerequisites

- The Spark client has been installed. For example, the installation directory is **/opt/client**.
- You have obtained a user account with the MRS cluster administrator permissions, such as **admin**.

#### Procedure

- **Spark on HBase authorization**  
After the permissions are assigned, you can use statements that are similar to SQL statements to access HBase tables from SparkSQL. The following uses the procedure for assigning a user the permissions to query HBase tables as an example.

 **NOTE**

Set `spark.yarn.security.credentials.hbase.enabled` to `true`.

- a. On Manager, create a role, for example, **hive\_hbase\_create**, and grant the permission to create HBase tables to the role.

In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **HBase** > **HBase Scope** > **global**. Select **create** of the namespace **default**, and click **OK**.

 **NOTE**

In this example, the created table is saved in the default database of Hive and has the CREATE permission of the default database. If you save the table to a Hive database other than **default**, perform the following operations:

In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **Hive** > **Hive Read Write Privileges**, select **CREATE** for the desired database, and click **OK**.

- b. On Manager, create a role, for example, **hive\_hbase\_submit**, and grant the permission to submit tasks to the Yarn queue.

In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **Yarn** > **Scheduling Queue** > **root**. Select **Submit** of **default**, and click **OK**.

- c. On Manager, create a human-machine user, for example, **hbase\_creates\_user**, add the user to the **hive** group, and bind the **hive\_hbase\_create** and **hive\_hbase\_submit** roles to create SparkSQL and HBase tables.

- d. Log in to the node where the client is installed as the client installation user.

- e. Run the following command to configure environment variables:

```
source /opt/client/bigdata_env
source /opt/client/Spark2x/component_env
```

- f. Run the following command to authenticate the user:

```
kinit hbase_creates_user
```

- g. Run the following commands to enter the shell environment on the Spark JDBCServer client:

```
/opt/client/Spark2x/spark/bin/beeline -u "jdbc:hive2://
<zkNode1_IP>:<zkNode1_Port>,<zkNode2_IP>:<zkNode2_Port>,<zkNode3_IP>:<zkNode3_Port>";serviceDiscoveryMode=zooKeeper;zooKeeperNamespace=sparkthriftserver2x;user.principal=spark2x/hadoop.<system domain name>@<system domain name>;sasLQop=auth-conf;auth=KERBEROS;principal=spark2x/hadoop.<system domain name>@<system domain name>;"
```

- h. Run the following command to create a table in SparkSQL and HBase, for example, create the **hbaseTable** table:

```
create table hbaseTable (id string, name string, age int) using
org.apache.spark.sql.hbase.HBaseSource options (hbaseTableName
"table1", keyCols "id", colsMapping = "", name=cf1.cq1, age=cf1.cq2");
```

The created SparkSQL table and the HBase table are stored in the Hive database **default** and the HBase namespace **default**, respectively.

- i. On Manager, create a role, for example, **hive\_hbase\_select**, and grant the role the permission to query SparkSQL on HBase table **hbaseTable** and HBase table **hbaseTable**.

- In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **HBase** > **HBase Scope** > **global** > **default**. Select **read** for the **hbaseTable** table, and click **OK** to grant the table query permission to the HBase role.
- Edit the role. In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **HBase** > **HBase Scope** > **global** > **hbase**. Select **Execute** for **hbase:meta**, and click **OK**.
- Edit the role. In the **Configure Resource Permission** table, choose *Name of the desired cluster* > **Hive** > **Hive Read Write Privileges** > **default**. Select **SELECT** for the **hbaseTable** table, and click **OK**.
- j. On Manager, create a human-machine user, for example, **hbase\_select\_user**, add the user to the **hive** group, and bind the **hive\_hbase\_select** role to the user for querying SparkSQL and HBase tables.
- k. Run the following command to configure environment variables:  
**source /opt/client/bigdata\_env**  
**source /opt/client/Spark2x/component\_env**
- l. Run the following command to authenticate users:  
**kinit hbase\_select\_user**
- m. Run the following commands to enter the shell environment on the Spark JDBCServer client:  
**/opt/client/Spark2x/spark/bin/beeline -u "jdbc:hive2://**  
**<zkNode1\_IP>:<zkNode1\_Port>,<zkNode2\_IP>:<zkNode2\_Port>,<zkNode3\_IP>:<zkNode3\_Port>;serviceDiscoveryMode=zooKeeper;zooKeeperNamespace=sparkthriftserver2x;user.principal=spark2x/hadoop.<system domain name>@<system domain name>;sasLQop=auth-conf;auth=KERBEROS;principal=spark2x/hadoop.<system domain name>@<system domain name>";**
- n. Run the following command to use a SparkSQL statement to query HBase table data:  
**select \* from thh;**

### 17.1.6.5 Configuring the Client and Server

This section describes how to configure SparkSQL permission management functions (client configuration is similar to server configuration). To enable table permission, add following configurations on the client and server:

- **spark-defaults.conf** configuration file

**Table 17-39** Parameter description (1)

| Parameter                       | Description  | Default Value |
|---------------------------------|--|---------------|
| spark.sql.authorization.enabled | Specifies whether to enable permission authentication of the datasource statement. It is recommended that the parameter value be set to <b>true</b> to enable permission authentication. | true          |

- **hive-site.xml** configuration file

**Table 17-40** Parameter description (2)

| Parameter                            | Description   | Default Value   |
|--------------------------------------|---|---|
| hive.metastore.uris                  | Specifies the MetaStore service address of the Hive component, for example, <b>thrift://10.10.169.84:21088,thrift://10.10.81.37:21088</b> .                     | -   |
| hive.metastore.sasl.enabled          | Specifies whether the MetaStore service uses SASL to improve security. The table permission function must be enabled.   | true  |
| hive.metastore.kerberos.principal    | Specifies the principal of the MetaStore service in the Hive component, for example, <b>hive/hadoop.&lt;system domain name&gt;@&lt;system domain name&gt;</b> . | hive-metastore / _HOST@EXAMPLE.COM                                    |
| hive.metastore.thrift.sasl.qop       | After the SparkSQL permission management function is enabled, set the parameter to <b>auth-conf</b> .   | auth-conf   |
| hive.metastore.token.signature       | Specifies the token identifier of the MetaStore service, which is set to <b>HiveServer2ImpersonationToken</b> .   | HiveServer2ImpersonationToken   |
| hive.security.authentication.manager | Specifies the manager authenticated by the Hive client, which is set to <b>org.apache.hadoop.hive.ql.security.SessionStateUserGroupAuthenticator</b> .          | org.apache.hadoop.hive.ql.security.SessionStateUserGroupAuthenticator |
| hive.security.authorization.enabled  | Specifies whether to enable client authentication, which is set to <b>true</b> .  | true  |

| Parameter  | Description  | Default Value |
|--|--|---------------|
| hive.security.authorization.createtable.owner.grants | Specifies which permissions are granted to the owner who creates the table, which is set to <b>ALL</b> . | ALL           |

- **core-site.xml** configuration file of the MetaStore service

**Table 17-41** Parameter description (3)

| Parameter                     | Description   | Default Value |
|-------------------------------|---|---------------|
| hadoop.proxyuser.spark.hosts  | Specifies the hosts from which Spark users can be masqueraded, which is set to *, indicating all hosts.             | -             |
| hadoop.proxyuser.spark.groups | Specifies the user groups from which Spark users can be masqueraded, which is set to *, indicating all user groups. | -             |

## 17.1.7 Scenario-Specific Configuration

### 17.1.7.1 Configuring Multi-active Instance Mode

#### Scenarios

In this mode, multiple ThriftServers coexist in the cluster and the client can randomly connect any ThriftServer to perform service operations. When one or multiple ThriftServers stop working, a client can connect to another functional ThriftServer.

#### Configuration Description

Log in to Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x** > **Configurations**, click **All Configurations**, and search for and modify the following parameters.

**Table 17-42** Parameter description

| Parameter                                       | Description  | Default Value |
|---|--|---------------|
| spark.thriftserver.zookeeper.connection.timeout | Specifies the timeout interval of connection between ZooKeeper client and ThriftServer. The unit is millisecond. | 60000         |

| Parameter                                    | Description  | Default Value |
|--|--|---------------|
| spark.thriftserver.zookeeper.session.timeout | Specifies the timeout interval of a ZooKeeper client session. The unit is millisecond. | 90000         |
| spark.thriftserver.zookeeper.retry.times     | Specifies the retry times after ZooKeeper disconnection.                               | 3             |
| spark.yarn.queue                             | Specifies the Yarn queue where the JDBCServer service resides.                         | default       |

### 17.1.7.2 Configuring the Multi-tenant Mode

#### Scenarios

In multi-tenant mode, JDBCServer are bound with tenants. Each tenant corresponds to one or more JDBCServer, and a JDBCServer provides services for only one tenant. Different tenants can be configured with different Yarn queues to implement resource isolation.

#### Configuration Description

Log in to Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x** > **Configurations**, click **All Configurations**, and search for and modify the following parameters.

**Table 17-43** Parameter description

| Parameter  | Description  | Default Value   |
|--|--|---|
| spark.proxyserver.hash.enabled                     | Specifies whether to connect to ProxyServer using the Hash algorithm. <ul style="list-style-type: none"> <li><b>true</b> indicates using the Hash algorithm. In multi-tenant mode, this parameter must be configured to <b>true</b>.</li> <li><b>false</b> indicates using random connection. In multi-active instance mode, this parameter must be configured to <b>false</b>.</li> </ul> | true<br><b>NOTE</b><br>After this parameter is modified, you need to download the client again. |
| spark.thriftserver.proxy.maxThriftServerPerTenancy | Specifies the maximum number of JDBCServer instances that can be started by a tenant in multi-tenant mode.   | 1   |

| Parameter   | Description  | Default Value |
|---|--|---------------|
| spark.thriftserver.proxy.maxSessionPerThriftServer    | Specifies the maximum number of sessions in a single JDBCServer instance in multi-tenant mode. If the number of sessions exceeds this value and the number of JDBCServer instances does not exceed the upper limit, a new JDBCServer instance is started. Otherwise, an alarm log is output. | 50            |
| spark.thriftserver.proxy.sessionWaitTime              | Specifies the wait time before a JDBCServer instance is stopped when it has no session connections in multi-tenant mode.   | 180000        |
| spark.thriftserver.proxy.sessionThreshold             | In multi-tenant mode, when the session usage (formula: number of current sessions/<br>spark.thriftserver.proxy.maxSessionPerThriftServer x number of current JDBCServer instances) of the JDBCServer instance reaches the threshold, a new JDBCServer instance is automatically added.       | 100           |
| spark.thriftserver.proxy.healthcheck.period           | Specifies the period of JDBCServer health checks conducted by the JDBCServer proxy in multi-tenant mode.   | 60000         |
| spark.thriftserver.proxy.healthcheck.recheckTimes     | Specifies the number of JDBCServer health check retries conducted by the JDBCServer proxy in multi-tenant mode.  | 3             |
| spark.thriftserver.proxy.healthcheck.waitTime         | Specifies the wait time for JDBCServer to respond to a health check request sent by the JDBCServer proxy.  | 10000         |
| spark.thriftserver.proxy.session.check.interval       | Specifies the period of JDBCServer proxy sessions in multi-tenant mode.  | 6h            |
| spark.thriftserver.proxy.idle.session.timeout         | Specifies the idle time interval of a JDBCServer proxy session in multi-tenant mode. If no operation is performed within this period, the session is closed.   | 7d            |
| spark.thriftserver.proxy.idle.session.check.operation | Specifies whether to check that operations still exist on a JDBCServer proxy session when the session is checked for expiration in multi-tenant mode.  | true          |

| Parameter                                       | Description   | Default Value |
|---|---|---------------|
| spark.thriftserver.proxy.idle.operation.timeout | Specifies the timeout interval of an operation in multi-tenant mode. An operation that times out is closed. | 5d            |

### 17.1.7.3 Configuring the Switchover Between the Multi-active Instance Mode and the Multi-tenant Mode

#### Scenarios

When using a cluster, if you want to switch between multi-active instance mode and multi-tenant mode, the following configurations are required.

- Switch from multi-tenant mode to multi-active instance mode.  
Modify the following parameters of the Spark2x service:
  - spark.thriftserver.proxy.enabled=false
  - spark.scheduler.allocation.file=#{conf\_dir}/fairscheduler.xml
  - spark.proxyserver.hash.enabled=false
- Switch from multi-active instance mode to multi-tenant mode.  
Modify the following parameters of the Spark2x service:
  - spark.thriftserver.proxy.enabled=true
  - spark.scheduler.allocation.file=../\_spark\_conf\_\_/\_hadoop\_conf\_\_/\_fairscheduler.xml
  - spark.proxyserver.hash.enabled=true

#### Configuration Description

Log in to Manager, choose **Cluster** > *Name of the desired cluster* > **Service** > **Spark2x** > **Configuration**, click **All Configurations**, and search for and modify the following parameters.

**Table 17-44** Parameter description

| Parameter                       | Description   | Default Value                                      |
|---------------------------------|---|--|
| spark.scheduler.allocation.file | Specifies the fair scheduling file path. <ul style="list-style-type: none"> <li>• If the multi-active instance mode is used, the path is changed to <b>#{conf_dir}/fairscheduler.xml</b>.</li> <li>• If multi-tenant mode is used, the path is changed to <b>../_spark_conf__/_hadoop_conf__/_fairscheduler.xml</b>.</li> </ul> | ../_spark_conf__/_hadoop_conf__/_fairscheduler.xml |

| Parameter                          | Description   | Default Value   |
|------------------------------------|---|---|
| spark.proxyserver.has<br>h.enabled | <p>Specifies whether to connect to ProxyServer using the Hash algorithm.</p> <ul style="list-style-type: none"> <li>• <b>true</b> indicates using the Hash algorithm. In multi-tenant mode, this parameter must be configured to <b>true</b>.</li> <li>• <b>false</b> indicates using random connection. In multi-active instance mode, this parameter must be configured to <b>false</b>.</li> </ul> | <p>true</p> <p><b>NOTE</b><br/>After this parameter is modified, you need to download the client again.</p> |

### 17.1.7.4 Configuring the Size of the Event Queue

#### Scenarios

Functions such as UI, EventLog, and dynamic resource scheduling in Spark are implemented through event transfer. Events include SparkListenerJobStart and SparkListenerJobEnd, which record each important process.

Each event is saved to a queue after it occurs. When creating a SparkContext object, Driver starts a thread to obtain an event from the queue in sequence and sends the event to each Listener. Each Listener processes the event after detecting the event.

Therefore, when the queuing speed is faster than the read speed, the queue overflows. As a result, the overflow event is lost, affecting the UI, EventLog, and dynamic resource scheduling functions. Therefore, a configuration item is added for more flexible use. You can set a proper value based on the memory size of the driver.

#### Configuration Description

##### Navigation path for setting parameters:

Before executing an application, modify the Spark service configuration. On Manager, choose **Cluster > Name of the desired cluster > Service > Spark2x > Configuration** and click **All Configurations**. Enter a parameter name in the search box.

**Table 17-45** Parameter description

| Parameter   | Description  | Default Value |
|---|--|---------------|
| spark.scheduler.l<br>istenerbus.event<br>queue.capacity | Specifies the size of the event queue. Configure this parameter based on the memory of the driver. | 100000<br>0   |

 **NOTE**

If the following information is displayed in the Driver log, the queue overflows.

1. Common application:  
Dropping SparkListenerEvent because no remaining room in event queue.  
This likely means one of the SparkListeners is too slow and cannot keep up with the rate at which tasks are being started by the scheduler.
2. Spark Streaming application:  
Dropping StreamingListenerEvent because no remaining room in event queue.  
This likely means one of the StreamingListeners is too slow and cannot keep up with the rate at which events are being started by the scheduler.

### 17.1.7.5 Configuring Executor Off-Heap Memory

#### Scenario

When the executor off-heap memory is too small, or processes with higher priority preempt resources, the physical memory usage will exceed the maximal value. To prevent the physical memory usage from exceeding, set the following parameter.

#### Configuration

**Navigation path for setting parameters:**

When submitting an application, set the following parameter using **--conf** or adjust the parameter in the **spark-defaults.conf** configuration file on the client.

**Table 17-46** Parameter description

| Parameter                     | Description   | Default Value |
|-------------------------------|---|---------------|
| spark.executor.memoryOverhead | Indicates the off-heap memory of each executor, in MB. Increasing the value of this parameter prevents the physical memory usage from exceeding the maximal value. The value is calculated based on $\max(384, \text{Executor} - \text{Memory} \times 0.1)$ . The minimal value is 384. | 1024          |

### 17.1.7.6 Enhancing Stability in a Limited Memory Condition

#### Scenario

A large amount of memory is required when Spark SQL executes a query, especially during Aggregate and Join operations. If the memory is limited, OutOfMemoryError may occur. Stability in a limited memory condition ensures queries to be run in limited memory without OutOfMemoryError.

 **NOTE**

Limited memory does not mean infinitely small memory, but ensures stable queries by using disks in a scenario where memory fails to store the data amount that is several times larger than the available memory size. For example, for queries involving Join, the data of the same key used for Join needs to be stored in memory. If the data amount is too large to be stored in the available memory, OutOfMemoryError occurs.

Stability in a limited memory condition involves the following sub-functions:

1. ExternalSort

If the memory is inadequate during sorting, partial data overflows to disks.

2. TungstenAggregate

By default, ExternalSort is used to sort data before data aggregation. Therefore, if the memory is inadequate, the data overflows to disks during sorting. The data has been properly sorted before aggregation and only aggregation results of the current key are remained, which use a small amount of memory.

3. SortMergeJoin and SortMergeOuterJoin

SortMergeJoin and SortMergeOuterJoin are based on the equivalence join of sorted data. By default, ExternalSort is used to sort the data before the equivalence join. Therefore, if the memory is inadequate, the data overflows to disks during sorting. The data has been properly sorted before the equivalence join and only the data of the same key are remained, which uses a small amount of memory.

## Configuration

**Navigation path for setting parameters:**

When submitting an application, set the following parameters using `--conf` or adjust the parameters in the `spark-defaults.conf` configuration file on the client.

**Table 17-47** Parameter description

| Parameter                  | Scenario | Description   | Default Value |
|----------------------------|----------|---|---------------|
| spark.sql.tungsten.enabled | /        | Type: Boolean<br><ul style="list-style-type: none"> <li>If the value is <b>true</b>, tungsten is enabled. That is, the logic plan is equivalent to the codegeneration function, and the physical plan uses the corresponding tungsten execution plan.</li> <li>If the value is <b>false</b>, tungsten is disabled.</li> </ul> | true          |

| Parameter                    | Scenario | Description  | Default Value |
|------------------------------|----------|--|---------------|
| spark.sql.codegen.wholeStage |          | Type: Boolean <ul style="list-style-type: none"> <li>If the value is <b>true</b>, codegeneration is enabled. That is, for some specified queries, the logic plan code will be generated dynamically when running.</li> <li>If the value is <b>false</b>, codegeneration is disabled and the existing static code is used.</li> </ul> | true          |

 NOTE

- To enable ExternalSort, you need to set **spark.sql.planner.externalSort** to **true** and **spark.sql.unsafe.enabled** to **false** or **spark.sql.codegen.wholeStage** to **false**.
- To enable TungstenAggregate, use either of the following methods:  
 Set **spark.sql.codegen.wholeStage** and **spark.sql.unsafe.enabled** to **true** in the configuration file or CLI.  
 If neither **spark.sql.codegen.wholeStage** nor **spark.sql.unsafe.enabled** is **true** or either of them is **true**, TungstenAggregate is enabled as long as **spark.sql.tungsten.enabled** is set to **true**.

### 17.1.7.7 Viewing Aggregated Container Logs on the Web UI


#### Scenarios

When **yarn.log-aggregation-enable** of Yarn is set to **true**, the container log aggregation function is enabled. Log aggregation indicates that after applications are run on Yarn, NodeManager aggregates all container logs of the node to HDFS and deletes local logs. For details, see [Configuring Container Log Aggregation](#).

However, all logs will be aggregated to an HDFS directory and can only be viewed by accessing an HDFS file. Open-source Spark and Yarn do not support the function of viewing aggregated logs on the web UI.

Spark supports this function. As shown in [Figure 17-4](#), the **AggregatedLogs** tab is added to the HistoryServer page. You can click **logs** to view aggregated logs.

Figure 17-4 Log aggregation page



| Process Name        | Container ID                               | Logs                 |
|---------------------|--|----------------------|
| ApplicationMaster 1 | container_e01_1624275077629_0012_01_000001 | <a href="#">logs</a> |
| Executor 2          | container_e01_1624275077629_0012_01_000002 | <a href="#">logs</a> |
| Executor 1          | container_e01_1624275077629_0012_01_000005 | <a href="#">logs</a> |

## Configuration Description

To display logs on the web UI, aggregated logs need to be parsed and presented. Spark parses aggregation logs using JobHistoryServer of Hadoop. Therefore, you can use the **spark.jobhistory.address** parameter to specify the URL of the JobHistoryServer page to parse and present the logs.

### Navigation path for setting parameters:

When submitting an application, set these parameters using **--conf** or adjust the following parameter in the **spark-defaults.conf** configuration file on the client.

#### NOTE

- This function depends on JobHistoryServer of Hadoop. Therefore, ensure that JobHistoryServer is running properly before using the log aggregation function.
- If the parameter value is empty, the **AggregatedLogs** tab page still exists, but you cannot view logs by clicking **logs**.
- The aggregated container logs can be viewed only when the application is running and event log files of the application exist on HDFS.
- You can click the log link on the **Executors** page to view the logs of a running task. After the task completes, the logs are aggregated to HDFS, and the log link on the **Executors** page becomes invalid. In this case, you can click **logs** on the **AggregatedLogs** page to view the aggregated logs.

**Table 17-48** Parameter description

| Parameter                | Description  | Default Value |
|--------------------------|--|---------------|
| spark.jobhistory.address | <p>URL of the JobHistoryServer page. The format is <i>http(s)://ip:port/jobhistory</i>. For example, <b>https://10.92.115.1:26014/jobhistory</b>.</p> <p>The default value is empty, indicating that container aggregation logs cannot be viewed on the web UI.</p> <p>Restart the service for the configuration to take effect.</p> | -             |

### 17.1.7.8 Configuring Whether to Display Spark SQL Statements Containing Sensitive Words

#### Scenario

SQL statements executed by users may contain sensitive information (such as passwords). Disclosure of such information may incur security risks. You can configure the **spark.sql.redaction.string.regex** parameter to shield SQL keywords that contain sensitive words in logs and on the web UI.

Spark SQL statements consist of two parts:

1. Spark SQL statements in logs:
  - Driver log: In the JDBCServer service, each time an SQL statement is executed through Beeline, the corresponding SQL statement is added to the Driver log, for example, **Running query'show tables' with 0f8fee16-4291-4854-a7b4-b87a162f7cbb.**
  - eventLog log: If the eventLog writing function is enabled for each Spark application (**spark.eventLog.enabled** is set to **true**), event logs will be written. SQL statements executed using JDBCServer and Spark SQL will also be added to the eventLog file.
2. Spark SQL statements on the web UI:
  - SparkUI: When executing SQL statements, you can view the executed SQL statements on the **Jobs** and **Stages** tab pages on the SparkUI.
  - HistoryServer: HistoryServer reads the eventLog file and displays app information on the page. Therefore, if the eventLog file contains SQL statement records, you can view the corresponding SQL statements on the HistoryServer page.

## Configuration

**Table 17-49** Parameter description

| Parameter                        | Description   | Default Value |
|----------------------------------|---|---------------|
| spark.sql.redaction.string.regex | Regular expression that determines which part in a string generated by Spark is sensitive words. If the regular expression matches sensitive words of the string, these sensitive words are replaced with <b>***** (redacted)</b> .<br><b>NOTE</b><br>The value must be a regular expression. | pwd password  |

 **NOTE**

- If Spark Beeline is used, you need to restart JDBCServer for the configuration to take effect. If spark-sql is used, you need to restart spark-sql for the configuration to take effect.
- The preceding parameters are valid only for the SQL statements that are executed after the configuration.

### 17.1.7.9 Configuring Environment Variables in Yarn-Client and Yarn-Cluster Modes

#### Scenario

Values of some configuration parameters of Spark client vary depending on its work mode (YARN-Client or YARN-Cluster). If you switch Spark client between different modes without first changing values of such configuration parameters, Spark client fails to submit jobs in the new mode.

To avoid this, configure parameters as described in [Table 17-50](#).

- In Yarn-Cluster mode, use the new parameters (path and parameters of Spark server).
- In Yarn-Client mode, uses the original parameters.  
They are **spark.driver.extraClassPath**, **spark.driver.extraJavaOptions**, and **spark.driver.extraLibraryPath**.

 NOTE

If you choose not to add the parameters in [Table 17-50](#), Spark client can continue to operate well in either mode but the mode switch requires changes to some of its configuration parameters.

## Configuration Parameters

### Navigation path for setting parameters:

On Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x** > **Configurations**. Click **All Configurations** and enter a parameter name in the search box.

**Table 17-50** Parameter description

| Parameter                                | Description   | Default Value                            |
|--|---|--|
| spark.yarn.cluster.driver.extraClassPath | Indicates the extraClassPath of the driver in Yarn-cluster mode. Set the parameter to the path and parameters of the server.<br><br>The original parameter <b>spark.driver.extraClassPath</b> indicates the extraClassPath of Spark client. By using different parameters to separate the settings of Spark server from the settings of Spark client, you can switch Spark client to different modes without changing parameter values. | \${BIGDATA_HOME}/common/runtime/security |

| Parameter                                 | Description  | Default Value  |
|---|--|--|
| spark.yarn.client.driver.extraJavaOptions | <p>Indicates the extraJavaOptions of Driver in Yarn-Cluster mode and is set to path and parameters of extraJavaOptions of Spark server.</p> <p>The original parameter <b>spark.driver.extraJavaOptions</b> indicates the path of extraJavaOptions of Spark client. By using different parameters to separate the settings of Spark server from the settings of Spark client, you can switch Spark client to different modes without changing parameter values.</p> | <p>-Xloggc:&lt;LOG_DIR&gt;/gc.log -XX:+PrintGCDetails -XX:-OmitStackTraceInFastThrow -XX:+PrintGCTimeStamps -XX:+PrintGCDateStamps -XX:+UseGCLogFileRotation -XX:NumberOfGCLogFiles=20 -XX:GCLogFileSize=10M -Dlog4j.configuration=./__spark_conf__/__hadoop_conf__/log4j-executor.properties -Djava.security.auth.login.config=./__spark_conf__/__hadoop_conf__/jaas-zk.conf -Dzookeeper.server.principal=zookeeper/hadoop.&lt;system domain name&gt; -Djava.security.krb5.conf=./__spark_conf__/__hadoop_conf__/kdc.conf -Djetty.version=x.y.z -Dorg.xerial.snappy.tmpdir=\${BIGDATA_HOME}/tmp/spark2x_app -Dcarbon.properties.filepath=./__spark_conf__/__hadoop_conf__/carbon.properties -Djdk.tls.ephemeralDHKeySize=2048</p> |

### 17.1.7.10 Configuring the Default Number of Data Blocks Divided by SparkSQL

#### Scenarios

By default, SparkSQL divides data into 200 data blocks during shuffle. In data-intensive scenarios, each data block may have excessive size. If a single data block of a task is larger than 2 GB, an error similar to the following will be reported while Spark attempts to fetch the data block:

```
Adjusted frame length exceeds 2147483647: 2717729270 - discarded
```

For example, setting the number of default data blocks to 200 causes SparkSQL to encounter an error in running a TPCDS 500-GB test. To avoid this, increase the number of default blocks in data-intensive scenarios.

## Configuration parameters

### Navigation path for setting parameters:

On Manager, choose **Cluster > Name of the desired cluster > Service > Spark2x > Configuration** and click **All Configurations**. Enter a parameter name in the search box.

**Table 17-51** Parameter description

| Parameter                    | Description  | Default Value |
|------------------------------|--|---------------|
| spark.sql.shuffle.partitions | Indicates the default number of blocks divided during shuffle. | 200           |

### 17.1.7.11 Configuring the Compression Format of a Parquet Table

#### Scenarios

The compression format of a Parquet table can be configured as follows:

1. If the Parquet table is a partitioned one, set the **parquet.compression** parameter of the Parquet table to specify the compression format. For example, set **tblproperties** in the table creation statement: **"parquet.compression"="snappy"**.
2. If the Parquet table is a non-partitioned one, set the **spark.sql.parquet.compression.codec** parameter to specify the compression format. The configuration of the **parquet.compression** parameter is invalid, because the value of the **spark.sql.parquet.compression.codec** parameter is read by the **parquet.compression** parameter. If the **spark.sql.parquet.compression.codec** parameter is not configured, the default value is **snappy** and will be read by the **parquet.compression** parameter.

Therefore, the **spark.sql.parquet.compression.codec** parameter can only be used to set the compression format of a non-partitioned Parquet table.

## Configuration parameters

### Navigation path for setting parameters:

On Manager, choose **Cluster > Name of the desired cluster > Service > Spark2x > Configuration**. Click **All Configurations** and enter a parameter name in the search box.

**Table 17-52** Parameter description

| Parameter                           | Description  | Default Value |
|-------------------------------------|--|---------------|
| spark.sql.parquet.compression.codec | Used to set the compression format of a non-partitioned Parquet table. | snappy        |

### 17.1.7.12 Configuring the Number of Lost Executors Displayed in WebUI

#### Scenario

In Spark WebUI, the **Executor** page can display information about Lost Executor. Executors are dynamically recycled. If the JDBCServer tasks are large, there may be too many lost executors displayed in WebUI. Therefore, the number of displayed lost executors can be configured.

#### Procedure

Configure the following parameter in the **spark-defaults.conf** file on Spark client.

**Table 17-53** Parameter description

| Parameter                      | Description  | Default Value |
|--------------------------------|--|---------------|
| spark.ui.retainedDeadExecutors | The maximum number of Lost Executors displayed in Spark WebUI. | 100           |

### 17.1.7.13 Setting the Log Level Dynamically

#### Scenarios

In some scenarios, to locate problems or check information by changing the log level,

you can add the **-Dlog4j.configuration.watch=true** parameter to the JVM parameter of a process before the process is started. After the process is started, you can modify the log4j configuration file corresponding to the process to change the log level.

The following processes support the dynamic setting of log levels: driver, executor, ApplicationMaster, JobHistory and JDBCServer.

Allowed log levels are as follows: FATAL, ERROR, WARN, INFO, DEBUG, TRACE, and ALL.

## Configuration Description

Add the following parameters to the JVM parameter corresponding to a process.

**Table 17-54** Parameter description

| Parameter                    | Description   | Default Value   |
|------------------------------|---|---|
| - Dlog4j.configuration.watch | Indicates a JVM parameter of a process. If this parameter is set to <b>true</b> , the dynamic configuration of log levels is enabled. | Left blank, indicating that the dynamic configuration of log levels is disabled |

**Table 17-55** lists the JVM parameters of the driver, executor, and ApplicationMaster processes. Configure the following parameters in the **spark-defaults.conf** file on the Spark client. Set the log levels of the driver, executor, and ApplicationMaster processes in the log4j configuration file specified by the - **Dlog4j.configuration** parameter.

**Table 17-55** JVM parameters of processes (1)

| Parameter                       | Description   | Default Log Level |
|---------------------------------|---|-------------------|
| spark.driver.extraJavaOptions   | Indicates the JVM parameter of the driver process.            | INFO              |
| spark.executor.extraJavaOptions | Indicates the JVM parameter of the executor process.          | INFO              |
| spark.yarn.am.extraJavaOptions  | Indicates the JVM parameter of the ApplicationMaster process. | INFO              |

**Table 17-56** describes the JVM parameters of JobHistory Server and JDBCServer. Set the parameters in the **ENV\_VARS** configuration file. Set the log levels of JobHistory Server and JDBCServer in the **log4j.properties** configuration file.

**Table 17-56** JVM parameters of processes (2)

| Parameter         | Description   | Default Log Level |
|-------------------|---|-------------------|
| GC_OPTS           | Indicates the JVM parameter of the JobHistory Server process. | INFO              |
| SPARK_SUBMIT_OPTS | Indicates the JVM parameter of JDBCServer.                    | INFO              |

### Example:

To change the log level of the executor process to DEBUG dynamically, modify the **spark.executor.extraJavaOptions** JVM parameter of the executor process in the **spark-defaults.conf** file and run the following command to add the following configuration before the process is started:

```
-Dlog4j.configuration.watch=true
```

After the user application is submitted, change the log level in the log4j configuration file (for example, **-Dlog4j.configuration=file:\${BIGDATA\_HOME}/FusionInsight\_Spark2x\_8.1.2.2/install/FusionInsight-Spark2x-3.1.1/spark/conf/log4j-executor.properties**) specified by the **-Dlog4j.configuration** parameter in **spark.executor.extraJavaOptions** to DEBUG:

```
log4j.rootCategory=DEBUG, sparklog
```

It takes several seconds for the DEBUG level to take effect.

## 17.1.7.14 Configuring Whether Spark Obtains HBase Tokens

### Scenario

When Spark is used to submit tasks, the driver obtains tokens from HBase by default. To access HBase, you need to configure the **jaas.conf** file for security authentication. If the **jaas.conf** file is not configured, the application will fail to run.

Therefore, perform the following operations based on whether the application involves HBase:

- If the application does not involve HBase, you do not need to obtain the HBase tokens. In this case, set **spark.yarn.security.credentials.hbase.enabled** to **false**.
- If the application involves HBase, set **spark.yarn.security.credentials.hbase.enabled** to **true** and configure the **jaas.conf** file on the driver as follows:

```
{client}/spark/bin/spark-sql --master yarn-client --principal {principal} --keytab {keytab} --driver-java-options "-Djava.security.auth.login.config={LocalPath}/jaas.conf"
```

Specify Keytab and Principal in the **jaas.conf** file. The following is an example:

```
Client {  
  com.sun.security.auth.module.Krb5LoginModule required  
  useKeyTab=true  
  keyTab = "{LocalPath}/user.keytab"  
  principal="super@<System domain name>"  
  useTicketCache=false  
  debug=false;  
};
```

### Configuration

Configure the following parameter in the **spark-defaults.conf** file of the Spark client.

**Table 17-57** Parameter description

| Parameter                                     | Description  | Default Value |
|---|--|---------------|
| spark.yarn.security.credentials.hbase.enabled | Indicates whether HBase obtains a token. <ul style="list-style-type: none"> <li>• <b>true</b>: HBase obtains a token.</li> <li>• <b>false</b>: HBase does not obtain a token.</li> </ul> | false         |


### 17.1.7.15 Configuring LIFO for Kafka

#### Scenario

If the Spark Streaming application is connected to Kafka, after the Spark Streaming application is terminated abnormally and restarted from the checkpoint, the system preferentially processes the tasks that are not completed before the application is terminated (Period A) and the tasks generated based on data that enters Kafka during the period (Period B) from the application termination to the restart. Then the application processes the tasks generated based on data that enters Kafka after the application is restarted (Period C). For data that enters Kafka in period B, Spark generates a corresponding number of tasks based on the end time (**batch** time). The first task reads all data, but other tasks may not read data. As a result, the task processing pressure is uneven.

If the tasks in Period A and Period B are processed slowly, the processing of tasks in period C is affected. To cope with the preceding scenario, Spark provides the last-in first-out (LIFO) function for Kafka.

**Figure 17-5** Time axis for restarting the Spark Streaming application



After this function is enabled, Spark preferentially schedules tasks in Period C. If there are multiple tasks in Period C, Spark schedules and executes the tasks in the sequence of task generation. Then Spark executes the tasks in Periods A and B. For data that enters Kafka in Period B, Spark generates tasks based on the end time

and evenly distributes all data that enters Kafka in this period to each task to avoid uneven task processing pressure.

Constraints:

- This function applies only to the direct mode of Spark Streaming, and the execution result does not depend on the processing result of the previous batch (that is, stateless operation, for example, **updatestatebykey**). Multiple data input streams must be comparatively independent from each other. Otherwise, the result may change after the data is divided.
- The Kafka LIFO function can be enabled only when the application is connected to the Kafka input source.
- If both Kafka LIFO and flow control functions are enabled when the application is submitted, the flow control function is not enabled for the data that enters Kafka in Period B to ensure that the task scheduling priority for reading the data is the lowest. Flow control is enabled for the tasks in Period C after the application is restarted.

## Configuration

Configure the following parameters in the **spark-defaults.conf** file on the Spark driver.

**Table 17-58** Parameter description

| Parameter                                  | Description   | Default Value  |
|--|---|--|
| spark.streaming.kafka.direct.lifo          | Specifies whether to enable the LIFO function of Kafka. | false  |
| spark.streaming.kafka010.inputstream.class | Obtains the decoupled class on FusionInsight.           | org.apache.spark.streaming.kafka010.HWDDirectKafkaInputDStream |

### 17.1.7.16 Configuring Reliability for Connected Kafka

#### Scenario

When the Spark Streaming application is connected to Kafka and the application is restarted, the application reads data from Kafka based on the last read topic offset and the latest offset of the current topic.

If the leader of a Kafka topic fails and the offset of the Kafka leader is greatly different from that of the Kafka follower, the Kafka follower and leader are switched over after the Kafka service is restarted. As a result, the offset of the topic decreases after the Kafka service is restarted.

- If the Spark Streaming application keeps running, the start position for reading Kafka data is greater than the end position because the offset of the topic in Kafka decreases. As a result, the application cannot read data from Kafka and reports an error.

- Before restarting the Kafka service, stop the Spark Streaming application. After the Kafka service is restarted, restart the Spark Streaming application to restore the application from the checkpoint. In this case, the Spark Streaming application records the offset position read before the termination and uses the position as the reference to read subsequent data. The Kafka offset decreases (for example, from 100,000 to 10,000). Spark Streaming consumes data only after the offset of the Kafka leader increases to 100,000. As a result, the newly sent data whose offset is between 10,000 and 100,000 is lost.

To resolve the preceding problem, you can configure reliability for Kafka connected to Spark Streaming. After the reliability function of connected Kafka is enabled:

- If the offset of a topic in Kafka decreases when the Spark Streaming application is running, the latest offset of the topic in Kafka is used as the start position for reading Kafka data and subsequent data is read.

For a task that has been generated but has not been scheduled, if the read Kafka offset is greater than the latest offset of the topic in Kafka, the task fails to be executed.

 **NOTE**

If a large number of tasks fail, the Executor is added to the blacklist. As a result, subsequent tasks cannot be deployed and run. If this happens, you can set **spark.blacklist.enabled** to disable the blacklist function. The blacklist function is enabled by default.

- If the offset of a topic in Kafka decreases, the Spark Streaming application restarts to restore the unfinished tasks. If the read Kafka offset range is greater than the latest offset of the topic in Kafka, the task is directly discarded.

 **NOTE**

If the state function is used in the Spark Streaming application, do not enable the reliability function of connected Kafka.

## Configuration

Configure the following parameter in the **spark-defaults.conf** file of the Spark client.

**Table 17-59** Parameter description

| Parameter                         | Description   | Default Value |
|-----------------------------------|---|---------------|
| spark.streaming.Kafka.reliability | Indicates whether to enable the reliability function for Kafka connected to Spark Streaming. <ul style="list-style-type: none"> <li>• <b>true:</b> The reliability function is enabled.</li> <li>• <b>false:</b> The reliability function is disabled.</li> </ul> | false         |

### 17.1.7.17 Configuring Streaming Reading of Driver Execution Results

#### Scenario

When a query statement is executed, the returned result may be large (containing more than 100,000 records). In this case, JDBCServer out of memory (OOM) may occur. Therefore, the data aggregation function is provided to avoid OOM without sacrificing the performance.

#### Configuration

Two data aggregation function configuration parameters are provided. The two parameters are set in the **tunning** option on the Spark JDBCServer server. After the setting is complete, restart JDBCServer.

**Table 17-60** Parameter description

| Parameter                                     | Description   | Default Value |
|---|---|---------------|
| spark.sql.bigdata.thriftServer.useHdfsCollect | <p>Indicates whether to save result data to HDFS instead of the memory.</p> <p>Advantages: The query result is stored in HDFS. Therefore, JDBCServer OOM does not occur.</p> <p>Disadvantages: The query is slow.</p> <ul style="list-style-type: none"> <li>● <b>true</b>: Result data is saved to HDFS.</li> <li>● <b>false</b>: This function is disabled.</li> </ul> <p><b>NOTICE</b><br/>When <b>spark.sql.bigdata.thriftServer.useHdfsCollect</b> is set to <b>true</b>, result data is saved to HDFS. However, the job description on the native JobHistory page cannot be associated with the corresponding SQL statement. In addition, the execution ID in the spark-beeline command output is null. To solve the JDBCServer OOM problem and ensure correct information display, you are advised to set <b>spark.sql.userlocalFileCollect</b>.</p> | false         |

| Parameter                     | Description   | Default Value |
|-------------------------------|---|---------------|
| spark.sql.useLocalFileCollect | <p>Indicates whether to save result data to the local disk instead of memory.</p> <p>Advantages: In the case of small data volume, the performance loss can be ignored compared with the data storage mode using the native memory. In the case of large data volume (hundreds of millions of data records), the performance is much better than that when data is stored in the HDFS and native memory.</p> <p>Disadvantages: Optimization is required. In the case of large data volume, it is recommended that the JDBCServer driver memory be 10 GB and each core of the executor be allocated with 3 GB memory.</p> <ul style="list-style-type: none"> <li>● <b>true</b>: This function is enabled.</li> <li>● <b>false</b>: This function is disabled.</li> </ul> | false         |
| spark.sql.collect.Hive        | <p>This parameter is valid only when <b>spark.sql.useLocalFileCollect</b> is set to <b>true</b>. It indicates whether to save the result data to a disk in direct serialization mode or in indirect serialization mode.</p> <p>Advantage: For queries of tables with a large number of partitions, the aggregation performance of the query results is better than that of the storage mode that query results are directly stored on the disk.</p> <p>Disadvantages: The disadvantages are the same as those when <b>spark.sql.useLocalFileCollect</b> is enabled.</p> <ul style="list-style-type: none"> <li>● <b>true</b>: This function is enabled.</li> <li>● <b>false</b>: This function is disabled.</li> </ul>  | false         |
| spark.sql.collect.serialize   | <p>This parameter takes effect only when both <b>spark.sql.useLocalFileCollect</b> and <b>spark.sql.collect.Hive</b> are set to <b>true</b>.</p> <p>The function is to further improve performance.</p> <ul style="list-style-type: none"> <li>● <b>java</b>: Data is collected in Java serialization mode.</li> <li>● <b>kryo</b>: Data is collected in kryo serialization mode. The performance is better than that when the Java serialization mode is used.</li> </ul>  | java          |

 NOTE

`spark.sql.bigdata.thriftServer.useHdfsCollect` and `spark.sql.uselocalFileCollect` cannot be set to `true` at the same time.

### 17.1.7.18 Filtering Partitions without Paths in Partitioned Tables

#### Scenario

When you perform the *select* query in Hive partitioned tables, the **FileNotFoundException** exception is displayed if a specified partition path does not exist in HDFS. To avoid the preceding exception, configure `spark.sql.hive.verifyPartitionPath` parameter to filter partitions without paths.

#### Procedure

Perform either of the following methods to filter partitions without paths:

- Configure the following parameter in the `spark-defaults.conf` file on Spark client.

**Table 17-61** Parameter description

| Parameter                                       | Description  | Default Value |
|---|--|---------------|
| <code>spark.sql.hive.verifyPartitionPath</code> | Whether to filter partitions without paths when reading Hive partitioned tables.<br><b>true</b> : enables the filtering<br><b>false</b> : disables the filtering | false         |

- When running the `spark-submit` command to submit an application, configure the `--conf` parameter to filter partitions without paths.

For example:

```
spark-submit --class org.apache.spark.examples.SparkPi --conf spark.sql.hive.verifyPartitionPath=true $SPARK_HOME/lib/spark-examples_*.jar
```

### 17.1.7.19 Configuring Spark2x Web UI ACLs

#### Scenario

Users need to implement security protection for Spark2x web UI when some data on the UI cannot be viewed by other users. Once a user attempts to log in to the UI, Spark2x can check the view ACL of the user to determine whether to allow the user to access the UI.

Spark2x has two types of web UI. One is for running tasks. You can access the web UI using the application link on the native Yarn page or the REST APIs. The other one is for ended tasks. You can access the web UI using the Spark2x JobHistory service or the REST APIs. Spark2x and Spark configurations differ from each other.

- Configuring the ACL of the web UI for running tasks  
Use the following parameters for configuration:
  - **spark.admin.acls**: specifies the web UI administrator list.
  - **spark.admin.acls.groups**: specifies the administrator group list.
  - **spark.ui.view.acls**: specifies the Yarn page visitor list.
  - **spark.modify.acls.groups**: specifies the Yarn page visitor group list.
  - **spark.modify.acls**: specifies the web UI modifier list.
  - **spark.ui.view.acls.groups**: specifies the web UI modifier group list.
- Configuring the ACL of the web UI for ended tasks  
For ended tasks, use client parameter **spark.history.ui.acls.enable** to enable or disable the ACL access permission.  
If ACL control is enabled, configure client parameters **spark.admin.acls** and **spark.admin.acls.groups** to specify the web UI administrator list and administrator group list. Use client parameters **spark.ui.view.acls** and **spark.modify.acls.groups** to specify the visitor list and visitor group list that view web UI task details. Use client parameters **spark.modify.acls** and **spark.ui.view.acls.groups** to specify the visitor list and group list that modify web UI task details.

## Configuration

Log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > Spark2x > Configurations**, click **All Configurations**, search for **acl**, and modify the following parameters on the JobHistory, JDBCServer, SparkResource, and Spark pages.

**Table 17-62** Parameter description

| Parameter                    | Description  | Default Value |
|------------------------------|--|---------------|
| spark.history.ui.acls.enable | Indicates whether JobHistory supports the permission verification of a single task.  | true          |
| spark.acls.enable            | Indicates whether to enable Spark permission management.<br>If this function is enabled, the system checks whether the user has the permission to access and modify task information.                        | true          |
| spark.admin.acls             | Indicates the list of Spark administrators. All members in the list have the rights to manage all Spark tasks. You can configure multiple administrators and separate them from each other using commas (,). | admin         |

| Parameter                 | Description  | Default Value |
|---------------------------|--|---------------|
| spark.admin.acls.groups   | Indicates the list of Spark administrator groups. All groups in the list have the permission to manage all Spark tasks. You can configure multiple administrator groups and separate them from each other using commas (,).                      | -             |
| spark.modify.acls         | Indicates the list of members that have the permission to modify Spark tasks. By default, the user who starts a task has the permission to modify the task. You can configure multiple users and separate them from each other using commas (,). | -             |
| spark.modify.acls.groups  | Indicates the list of groups that have the permission to modify Spark tasks. You can configure multiple groups and separate them from each other using commas (,).   | -             |
| spark.ui.view.acls        | Indicates the list of members that have the permission to access Spark tasks. By default, the user who starts a task has the permission to modify the task. You can configure multiple users and separate them from each other using commas (,). | -             |
| spark.ui.view.acls.groups | Indicates the list of groups that have the permission to access Spark tasks. You can configure multiple groups and separate them from each other using commas (,).   | -             |

 NOTE

If you use a client to submit tasks, you must download the client again after modifying the `spark.admin.acls`, `spark.admin.acls.groups`, `spark.modify.acls`, `spark.modify.acls.groups`, `spark.ui.view.acls`, and `spark.ui.view.acls.groups` parameters.

### 17.1.7.20 Configuring Vector-based ORC Data Reading

#### Scenario

ORC is a column-based storage format in the Hadoop ecosystem. It originates from Apache Hive and is used to reduce the Hadoop data storage space and accelerate the Hive query speed. Similar to Parquet, ORC is not a pure column-based storage format. In the ORC format, the entire table is split based on the row

group, data in each row group is stored by column, and data is compressed as much as possible to reduce storage space consumption. Vector-based ORC data reading significantly improves the ORC data reading performance. In Spark2.3, SparkSQL supports vector-based ORC data reading (this function is supported in earlier Hive versions). Vector-based ORC data reading improves the data reading performance by multiple times.

This function is controlled by the following parameters:

- **spark.sql.orc.enableVectorizedReader**: Specifies whether vector-based ORC data reading is supported. The default value is **true**.
- **spark.sql.codegen.wholeStage**: Specifies whether to compile all stages of multiple operations into a Java method. The default value is **true**.
- **spark.sql.codegen.maxFields**: Specifies the maximum number of fields (including nested fields) supported by all stages of codegen. The default value is **100**.
- **spark.sql.orc.impl**: Specifies whether Hive or Spark SQL native is used as the SQL execution engine to read ORC data. The default value is **hive**.

## Parameters

Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x**. On the displayed page, choose **Configurations** > **All Configurations**. Search for parameters listed in the following table and configure them as required.

| Parameter                            | Description  | Default Value | Value Range   |
|--------------------------------------|--|---------------|---------------|
| spark.sql.orc.enableVectorizedReader | Specifies whether vector-based ORC data reading is supported. The default value is <b>true</b> .                                       | true          | [true,false]  |
| spark.sql.codegen.wholeStage         | Specifies whether to compile all stages of multiple operations into a Java method. The default value is <b>true</b> .                  | true          | [true,false]  |
| spark.sql.codegen.maxFields          | Specifies the maximum number of fields (including nested fields) supported by all stages of codegen. The default value is <b>100</b> . | 100           | ≥ 1           |
| spark.sql.orc.impl                   | Specifies whether Hive or Spark SQL native is used as the SQL execution engine to read ORC data. The default value is <b>hive</b> .    | hive          | [hive,native] |

 NOTE

1. To use vector-based ORC data reading of SparkSQL, the following conditions must be met:
  - `spark.sql.orc.enableVectorizedReader` must be set to **true** (default value). Generally, the value is not changed.
  - `spark.sql.codegen.wholeStage` must be set to **true** (default value). Generally, the value is not changed.
  - The value of `spark.sql.codegen.maxFields` must be greater than or equal to the number of columns in scheme.
  - All data is of the AtomicType. Specifically, data is not null or of the UDT, array, or map type. If there is data of the preceding types, expected performance cannot be obtained.
  - `spark.sql.orc.impl` must be set to **native**. The default value is **hive**.
2. If a task is submitted through the client, modification of the following parameters takes effect only after you download the client again: `spark.sql.orc.enableVectorizedReader`, `spark.sql.codegen.wholeStage`, `spark.sql.codegen.maxFields`, and `amd spark.sql.orc.impl`.

### 17.1.7.21 Broaden Support for Hive Partition Pruning Predicate Pushdown

#### Scenario

In earlier versions, the predicate for pruning Hive table partitions is pushed down. Only comparison expressions between column names and integers or character strings can be pushed down. In version 2.3, pushdown of the null, in, and, or expressions are supported.

#### Parameters

Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x**. On the displayed page, choose **Configurations** > **All Configurations**. Search for the parameter listed in the following table and configure it as required.

| Parameter  | Description   | Default Value | Value Range  |
|--|---|---------------|--------------|
| <code>spark.sql.hive.advancedPartitionPredicatePushdown.enabled</code> | Specifies whether to broaden the support for Hive partition pruning predicate pushdown. | true          | [true,false] |

### 17.1.7.22 Hive Dynamic Partition Overwriting Syntax

#### Scenario

In earlier versions, when the **insert overwrite** syntax is used to overwrite partition tables, only partitions with specified expressions are matched, and partitions without specified expressions are deleted. In Spark2.3, partitions without specified

expressions are automatically matched. The syntax is the same as that of the dynamic partition matching syntax of Hive.

## Parameters

Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x** > **Configurations**, click **All Configurations**, and search for the following parameter.

| Parameter                                 | Description   | Default Value | Value Range      |
|---|---|---------------|------------------|
| spark.sql.sources.partitionOverwrite-Mode | Specifies the mode for inserting data in partition tables by running the <b>insert overwrite</b> command, which can be <b>STATIC</b> or <b>DYNAMIC</b> . When it is set to <b>STATIC</b> , Spark deletes all partitions based on the matching conditions. When it is set to <b>DYNAMIC</b> , Spark matches partitions based on matching conditions and dynamically matches partitions without specified conditions. | STATIC        | [STATIC,DYNAMIC] |

### 17.1.7.23 Configuring the Column Statistics Histogram to Enhance the CBO Accuracy

#### Scenarios

The execution plan for SQL statements is optimized in Spark. Common optimization rules are heuristic optimization rules. Heuristic optimization rules are provided based on the characteristics of logical plans, and the data characteristics and the execution costs of operators are not considered. Spark 2.20 introduces the Cost-Based Optimization (CBO). CBO collects statistics on tables and columns and estimates the number of output records and size of each operator in bytes based on the input data sets of operators, which is the cost of executing an operator.

CBO will adjust the execution plan to minimize the end-to-end query time. The main points are as follows:

- Filter out irrelevant data as soon as possible.
- Minimize the cost of each operator.

The CBO optimization process is divided into two steps:

1. Collect statistics.
2. Estimate the output data sets of a specific operator based on the input data sets.

Table-level statistics includes: number of records and the total size of a table data file.

Column-level statistics includes: number of unique values, maximum value, minimum value, number of null values, average length, maximum length, and the histogram.

After the statistics is obtained, the execution cost of operators can be estimated. Common operators include filter and join operators.

Histogram is a type of column statistics. It can clearly describe the distribution of column data. The column data is distributed to a specified number of bins that are displayed in ascending order by size. The upper and lower limits of each bin are calculated. The amount of data in all bins is the same (a contour histogram). After the data is distributed, the cost estimation of each operator is more accurate and the optimization effect is better.

This feature can be enabled by using the following parameter.

**spark.sql.statistics.histogram.enabled:** specifies whether to enable the histogram function. The default value is **false**.

## Parameter Configuration

Log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > Spark2x > Configurations**, click **All Configurations**, and search for the following parameters.

| Parameter                              | Description  | Default Value | Value Range  |
|--|--|---------------|--------------|
| spark.sql.cbo.enabled                  | Enables CBO to estimate the statistics for the execution plan.   | false         | [true,false] |
| spark.sql.cbo.joinReorder.enabled      | Enables CBO join for reordering.   | false         | [true,false] |
| spark.sql.cbo.joinReorder.dp.threshold | Specifies the maximum number of nodes that can be joined in the dynamic planning algorithm.  | 12            | >=1          |
| spark.sql.cbo.joinReorder.card.weight  | Specifies the proportion of dimension (number of rows) in the comparison of planned cost during reconnection: Number of rows x Proportion of dimension + File size x (1 - Proportion of dimension) | 0.7           | 0-1          |

| Parameter                                    | Description   | Default Value | Value Range  |
|--|---|---------------|--------------|
| spark.sql.statistics.size.autoUpdate.enabled | Enables the function of automatically updating the table size when the table data volume changes.<br>Note: If there are a large number of data files in a table, this operation is time consume, and the data processing speed is reduced.                            | false         | [true,false] |
| spark.sql.statistics.histogram.enabled       | After this function is enabled, a histogram is generated when column statistics is collected. Histogram can improve the estimation accuracy, but collecting histogram information requires additional workload.   | false         | [true,false] |
| spark.sql.statistics.histogram.numBins       | Specifies the number of bins for the generated histogram.   | 254           | >=2          |
| spark.sql.statistics.ndv.maxError            | Specifies the maximum estimation deviation allowed by the HyperLogLog++ algorithm when the column level statistics is generated.  | 0.05          | 0-1          |
| spark.sql.statistics.percentile.accuracy     | Specifies the accuracy rate of the percentile estimation when the contour histogram is generated. The larger the value is, the more accurate the estimation is. The estimation error value can be obtained through (1.0/ Accuracy rate of the percentile estimation). | 10000         | >=1          |

 NOTE

- If you want the histogram to take effect in CBO, the following conditions must be met:
  - Set **spark.sql.statistics.histogram.enabled** to **true**. The default value is **false**. Change the value to **true** to enable the histogram function.
  - Set **spark.sql.cbo.enabled** to **true**. The default value is **false**. Change the value to **true** to enable CBO.
  - Set **spark.sql.cbo.joinReorder.enabled** to **true**. The default value is **false**. Change the value to **true** to enable connection reordering.
- If a client is used to submit a task, you need to download the client again after configuring the following parameters: **spark.sql.cbo.enabled**, **spark.sql.cbo.joinReorder.enabled**, **spark.sql.cbo.joinReorder.dp.threshold**, **spark.sql.cbo.joinReorder.card.weight**, **spark.sql.statistics.size.autoUpdate.enabled**, **spark.sql.statistics.histogram.enabled**, **spark.sql.statistics.histogram.numBins**, **spark.sql.statistics.ndv.maxError**, and **spark.sql.statistics.percentile.accuracy**.

### 17.1.7.24 Configuring Local Disk Cache for JobHistory

#### Scenarios

JobHistory can use local disks to cache the historical data of Spark applications to prevent the JobHistory memory from loading a large amount of application data, reducing the memory pressure. In addition, the cached data can be reused to improve the speed for subsequent application access.

#### Parameter Configuration

Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x** > **Configurations**, click the **All Configurations** tab, and search for the following parameters:

| Parameter                        | Description   | Default Value                           |
|----------------------------------|---|---|
| spark.history.store.path         | Specifies the local directory for storing historical information for JobHistory. If this parameter is specified, JobHistory caches historical application data in the local disk instead of the memory. | \${BIGDATA_HOME}/tmp/spark2x_JobHistory |
| spark.history.store.maxDiskUsage | Specifies the maximum available space of the local disk cache.  | 10 GB                                   |

### 17.1.7.25 Configuring Spark SQL to Enable the Adaptive Execution Feature

#### Scenario

The Spark SQL adaptive execution feature enables Spark SQL to optimize subsequent execution processes based on intermediate results to improve overall execution efficiency. The following features have been implemented:

1. Automatic configuration of the number of shuffle partitions  
 Before the adaptive execution feature is enabled, Spark SQL specifies the number of partitions for a shuffle process by specifying the **spark.sql.shuffle.partitions** parameter. This method lacks flexibility when multiple SQL queries are performed on an application and cannot ensure optimal performance in all scenarios. After adaptive execution is enabled, Spark SQL automatically configures the number of partitions for each shuffle process, instead of using the general configuration. In this way, the proper number of partitions is automatically used during each shuffle process.
2. Dynamic adjusting of the join execution plan  
 Before the adaptive execution feature is enabled, Spark SQL creates an execution plan based on the optimization results of rule-based optimization (RBO) and Cost-Based Optimization (CBO). This method ignores changes of result sets during data execution. For example, when a view created based on a large table is joined with other large tables, the execution plan cannot be adjusted to BroadcastJoin even if the result set of the view is small. After the adaptive execution feature is enabled, Spark SQL can dynamically adjust the execution plan based on the execution result of the previous stage to obtain better performance.
3. Automatic processing of data skew  
 If data skew occurs during SQL statement execution, the memory overflow of an executor or slow task execution may occur. After the adaptive execution feature is enabled, Spark SQL can automatically process data skew scenarios. Multiple tasks are started for partitions where data skew occurs. Each task reads several output files obtained from the shuffle process and performs union operations on the join results of these tasks to eliminate data skew.

## Parameters

Log in to FusionInsight Manager, choose **Cluster > Services > Spark2x > Configurations**, click **All Configurations**, and search for the following parameter.

| Parameter   | Description  | Default Value |
|---|--|---------------|
| spark.sql.adaptive.enabled                          | Specifies whether to enable the adaptive execution function.<br><br>Note: If AQE and Static Partition Pruning (DPP) are enabled at the same time, DPP takes precedence over AQE during SparkSQL task execution. As a result, AQE does not take effect. | false         |
| spark.sql.optimizer.dynamicPartitionPruning.enabled | The switch to enable DPP.  | true          |

| Parameter   | Description   | Default Value |
|---|---|---------------|
| spark.sql.adaptive.coalescePartitions.enabled             | If this parameter is set to <b>true</b> and <b>spark.sql.adaptive.enabled</b> is set to <b>true</b> , Spark combines partitions that are consecutively random played based on the target size (specified by <b>spark.sql.adaptive.advisoryPartitionSizeInBytes</b> ) to prevent too many small tasks from being executed.   | true          |
| spark.sql.adaptive.coalescePartitions.initialPartitionNum | Initial number of shuffle partitions before merge. The default value is the same as the value of <b>spark.sql.shuffle.partitions</b> . This parameter is valid only when <b>spark.sql.adaptive.enabled</b> and <b>spark.sql.adaptive.coalescePartitions.enabled</b> are set to <b>true</b> . This parameter is optional. The initial number of partitions must be a positive number.                | 200           |
| spark.sql.adaptive.coalescePartitions.minPartitionNum     | Minimum number of shuffle partitions after merge. If this parameter is not set, the default degree of parallelism (DOP) of the Spark cluster is used. This parameter is valid only when <b>spark.sql.adaptive.enabled</b> and <b>spark.sql.adaptive.coalescePartitions.enabled</b> are set to <b>true</b> . This parameter is optional. The initial number of partitions must be a positive number. | 1             |
| spark.sql.adaptive.shuffle.targetPostShuffleInputSize     | Target size of a partition after shuffling. Spark 3.0 and later versions do not support this parameter.   | 64MB          |
| spark.sql.adaptive.advisoryPartitionSizeInBytes           | Size of a shuffle partition (unit: byte) during adaptive optimization ( <b>spark.sql.adaptive.enabled</b> is set to <b>true</b> ). This parameter takes effect when Spark aggregates small shuffle partitions or splits shuffle partitions where skew occurs.   | 64MB          |

| Parameter   | Description   | Default Value |
|---|---|---------------|
| spark.sql.adaptive.fetchShuffleBlocksInBatch      | Whether to obtain consecutive shuffle blocks in batches. For the same map job, reading consecutive shuffle blocks in batches can reduce I/Os and improve performance, instead of reading blocks one by one. Note that multiple consecutive blocks exist in a single read request only when <b>spark.sql.adaptive.enabled</b> and <b>spark.sql.adaptive.coalescePartitions.enabled</b> are set to <b>true</b> . This feature also relies on a relocatable serializer that uses cascading to support the codec and the latest version of the shuffle extraction protocol. | true          |
| spark.sql.adaptive.localShuffleReader.enabled     | If the value of this parameter is <b>true</b> and the value of <b>spark.sql.adaptive.enabled</b> is <b>true</b> , Spark attempts to use the local shuffle reader to read shuffle data when shuffling of partitions is not required, for example, after sort-merge join is converted to broadcast-hash join.   | true          |
| spark.sql.adaptive.skewJoin.enabled               | Specifies whether to enable the function of automatic processing of the data skew in join operations. The function is enabled when this parameter is set to <b>true</b> and <b>spark.sql.adaptive.enabled</b> is set to <b>true</b> .   | true          |
| spark.sql.adaptive.skewJoin.skewedPartitionFactor | This parameter is a multiplier used to determine whether a partition is a data skew partition. If the data size of a partition exceeds the value of this parameter multiplied by the median of the all partition sizes except this partition and exceeds the value of <b>spark.sql.adaptive.skewJoin.skewedPartitionThresholdInBytes</b> , this partition is considered as a data skew partition.   | 5             |

| Parameter   | Description   | Default Value |
|---|---|---------------|
| spark.sql.adaptive.skewJoin.skewedPartitionThresholdInBytes | If the partition size (unit: byte) is greater than the threshold as well as the product of the <b>spark.sql.adaptive.skewJoin.skewedPartitionFactor</b> value and the median partition size, skew occurs in the partition. Ideally, the value of this parameter should be greater than that of <b>spark.sql.adaptive.advisoryPartitionSizeInBytes..</b> | 256MB         |
| spark.sql.adaptive.nonEmptyPartitionRatioForBroadcastJoin   | If the ratio of non-null partitions is less than the value of this parameter when two tables are joined, broadcast hash join cannot be properly performed regardless of the partition size. This parameter is valid only when <b>spark.sql.adaptive.enabled</b> is set to <b>true</b> .   | 0.2           |

### 17.1.7.26 Configuring Event Log Rollover

#### Scenario

When the event log mode is enabled for Spark, that is, **spark.eventLog.enabled** is set to **true**, events are written to a configured log file to record the program running process. If a program, for example JDBCServer or Spark Streaming, runs for a long period of time and has run many jobs and tasks during this period, many events are recorded in the log file, significantly increasing the file size.

When log rollover is enabled, metadata events are written into the log file and job events are written into a new log file (whether a job event is written to the new log file depends on the file size). Metadata events include EnvironmentUpdate, BlockManagerAdded, BlockManagerRemoved, UnpersistRDD, ExecutorAdded, ExecutorRemoved, MetricsUpdate, ApplicationStart, ApplicationEnd, and LogStart. Job events include StageSubmitted, StageCompleted, TaskResubmit, TaskStart, TaskEnd, TaskGettingResult, JobStart, and JobEnd. For Spark SQL applications, job events also include ExecutionStart and ExecutionEnd.

The UI for the HistoryServer service of Spark is obtained by reading and parsing these log files. The memory size is preset before the HistoryServer process starts. Therefore, when the size of log files is large, loading and parsing these files may cause problems such as insufficient memory and driver GC.

To load large log files in small memory mode, you need to enable log rollover for large applications. Generally, it is recommended that this function be enabled for long-running applications.

## Parameters

Log in to FusionInsight Manager, choose **Cluster > Services > Spark2x > Configurations**, click **All Configurations**, and search for the following parameters.

| Parameter                              | Description  | Default Value |
|--|--|---------------|
| spark.eventLog.rolling.enabled         | Whether to enable rollover for event log files. If this parameter is set to <b>true</b> , the size of each event log file is reduced to the configured size.                                   | true          |
| spark.eventLog.rolling.maxFileSize     | Maximum size of the event log file to be rolled over when <b>spark.eventlog.rolling.enabled</b> is set to <b>true</b> .  | 128M          |
| spark.eventLog.compression.codec       | Codec used to compress event logs. By default, Spark provides four types of codecs: LZ4, LZF, Snappy, and ZSTD. If this parameter is not specified, <b>spark.io.compression.codec</b> is used. | None          |
| spark.eventLog.logStageExecutorMetrics | Whether to write each stage peak value (for each executor) of executor metrics to the event log.   | false         |

## 17.1.8 Adapting to the Third-party JDK When Ranger Is Used

### Scenarios

When Ranger is used as the permission management service of Spark SQL, the certificate in the cluster is required for accessing RangerAdmin. If you use a third-party JDK instead of the JDK or JRE in the cluster, RangerAdmin fails to be accessed. As a result, the Spark application fails to be started.

In this scenario, you need to perform the following operations to import the certificate in the cluster to the third-party JDK or JRE.

### Configuration Method

**Step 1** Run the following command to export the certificate from the cluster:

1. Install the cluster client. Assume that the installation path is **/opt/client**.
2. Run the following command to go to the client installation directory.  
**cd /opt/client**
3. Run the following command to configure environment variables:  
**source bigdata\_env**
4. Generate the certificate file.

```
keytool -export -alias fusioninsightsubroot -storepass changeit -  
keystore /opt/client/JRE/jre/lib/security/cacerts -file  
fusioninsightsubroot.crt
```

**Step 2** Import the certificate in the cluster to the third-party JDK or JRE.

Copy the **fusioninsightsubroot.crt** file generated in [Step 1](#) to the third-party JRE node, set the **JAVA\_HOME** environment variable of the node, and run the following command to import the certificate:

```
keytool -import -trustcacerts -alias fusioninsightsubroot -storepass changeit -  
file fusioninsightsubroot.crt -keystore MY_JRE/lib/security/cacerts
```

 **NOTE**

**MY\_JRE** indicates the installation path of the third-party JRE. Change it based on the site requirements.

----End

## 17.2 Spark2x Logs

### Log Description

**Log paths:**

- Executor run log: `${BIGDATA_DATA_HOME}/hadoop/data${i}/nm/containerlogs/application_${appid}/container_${Scontid}`

 **NOTE**

The logs of running tasks are stored in the preceding path. After the running is complete, the system determines whether to aggregate the logs to an HDFS directory based on the Yarn configuration. For details, see [Common Yarn Parameters](#).

- Other logs: `/var/log/Bigdata/spark2x`

**Log archiving rule:**

- When tasks are submitted in **yarn-client** or **yarn-cluster** mode, executor log files are stored each time when the size of the log files reaches 50 MB. A maximum of 10 log files can be reserved without being compressed.
- The JobHistory2x log file is backed up each time when the size of the log file reaches 100 MB. A maximum of 100 log files can be reserved without being compressed.
- The JDBCServer2x log file is backed up each time when the size of the log file reaches 100 MB. A maximum of 100 log files can be reserved without being compressed.
- The IndexServer2x log file is backed up each time when the size of the log file reaches 100 MB. A maximum of 100 log files can be reserved without being compressed.
- The JDBCServer2x audit log file is backed up each time when the size of the log file reaches 20 MB by default. A maximum of 20 log files can be reserved without being compressed.
- The log file size and the number of compressed files to be reserved can be configured on FusionInsight Manager.

**Table 17-63** Spark2x log list

| Log Type             | Name   | Description   |
|----------------------|--|---|
| SparkResource2x logs | spark.log  | Spark2x service initialization log  |
|                      | prestart.log   | Prestart script log   |
|                      | cleanup.log  | Cleanup log file for instance installation and uninstallation                                     |
|                      | spark-availability-check.log   | Spark2x service health check log  |
|                      | spark-service-check.log  | Spark2x service check log   |
| JDBCServer2x logs    | JDBCServer-start.log   | JDBCServer2x startup log  |
|                      | JDBCServer-stop.log  | JDBCServer2x stop log   |
|                      | JDBCServer.log   | JDBCServer2x run log on the server  |
|                      | jdbc-state-check.log   | JDBCServer2x health check log   |
|                      | jdbcserver-omm-pid***-gc.log.*.current   | JDBCServer2x process GC log   |
|                      | spark-omm-org.apache.spark.sql.hive.thriftserver.HiveThriftProxyServer2-***.out* | JDBCServer2x process startup log. If the process stops, the <b>jstack</b> information is printed. |
| JobHistory2x logs    | jobHistory-start.log   | JobHistory2x startup log  |
|                      | jobHistory-stop.log  | JobHistory2x stop log   |
|                      | JobHistory.log   | JobHistory2x running process log  |
|                      | jobhistory-omm-pid***-gc.log.*.current   | JobHistory2x process GC log   |
|                      | spark-omm-org.apache.spark.deploy.history.HistoryServer-***.out*                 | JobHistory2x process startup log. If the process stops, the <b>jstack</b> information is printed. |
| IndexServer2x logs   | IndexServer-start.log  | IndexServer2x startup log   |
|                      | IndexServer-stop.log   | IndexServer2x stop log  |
|                      | IndexServer.log  | IndexServer2x run log on the server   |
|                      | indexserver-state-check.log  | IndexServer2x health check log  |

| Log Type  | Name   | Description  |
|-----------|--|--|
|           | indexserver-omm-pid***-gc.log.*.current                                    | IndexServer2x process GC log   |
|           | spark-omm-org.apache.spark.sql.hive.thriftserver.IndexServerProxy-***.out* | IndexServer2x process startup log. If the process stops, the <b>jstack</b> information is printed. |
| Audit Log | jdbcservice-audit.log<br>ranger-audit.log                                  | JDBCServer2x audit log   |

## Log levels

**Table 17-64** describes the log levels supported by Spark2x. The priorities of log levels are ERROR, WARN, INFO, and DEBUG in descending order. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 17-64** Log levels

| Level | Description  |
|-------|--|
| ERROR | Error information about the current event processing                                     |
| WARN  | Exception information about the current event processing                                 |
| INFO  | Logs of this level record normal running status information about the system and events. |
| DEBUG | Logs of this level record the system information and system debugging information.       |

To modify log levels, perform the following operations:

 **NOTE**

By default, the service does not need to be restarted after the Spark2x log levels are configured.

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster** > *Name of the desired cluster* > **Service** > **Spark2x** > **Configuration**.
- Step 3** Select **All Configurations**.
- Step 4** On the menu bar on the left, select the log menu of the target role.
- Step 5** Select a desired log level.

**Step 6** Click **Save**. Then, click **OK**.

----End

## Log Format

**Table 17-65** Log Format

| Type    | Format   | Example  |
|---------|--|--|
| Run log | <i>&lt;yyyy-MM-dd<br/>HH:mm:ss,SSS&gt; &lt;Log level&gt; <br/>&lt;Name of the thread that<br/>generates the log&gt; <br/>&lt;Message in the log&gt; <br/>&lt;Location where the log<br/>event occurs&gt;</i> | 2014-09-22 11:16:23,980<br>INFO DAGScheduler: Final<br>stage: Stage 0(reduce at<br>SparkPi.scala:35) |

## 17.3 Obtaining Container Logs of a Running Spark Application

Container logs of running Spark applications are distributed on multiple nodes. This section describes how to quickly obtain container logs.

### Scenario Description

You can run the **yarn logs** command to obtain the logs of applications running on Yarn. In different scenarios, you can run the following commands to obtain required logs:

1. Obtain complete logs of the application: **yarn logs --applicationId <appld> -out <outputDir>**.

Example: **yarn logs --applicationId application\_1574856994802\_0016 -out /opt/test**

The following figure shows the command output.

- a. If the application is running, container logs in the **dead** state cannot be obtained.
- b. If the application is stopped, all archived container logs can be obtained.

2. Obtain logs of a specified container: **yarn logs -applicationId <appld> -containerId <containerId>**.

Example: **yarn logs -applicationId application\_1574856994802\_0018 -containerId container\_e01\_1574856994802\_0018\_01\_000003**

The following figure shows the command output.

- a. If the application is running, container logs in the **dead** state cannot be obtained.
- b. If the application is stopped, you can obtain logs of any container.

3. Obtain container logs in any state: **yarn logs -applicationId <appld> -containerId <containerId> -nodeAddress <nodeAddress>**

Example: **yarn logs -applicationId application\_1574856994802\_0019 -containerId container\_e01\_1574856994802\_0019\_01\_000003 -nodeAddress 192-168-1-1:8041**

Execution result: Logs of any container can be obtained.

 NOTE

You need to set *nodeAddress* in the command. You can run the following command to obtain the value:

```
yarn node -list -all
```

## 17.4 Small File Combination Tools

### Tool Overview

In a large-scale Hadoop production cluster, HDFS metadata is stored in the NameNode memory, and the cluster scale is restricted by the memory limitation of each NameNode. If there are a large number of small files in the HDFS, a large amount of NameNode memory is consumed, which greatly reduces the read and write performance and prolongs the job running time. Based on the preceding information, the small file problem is a key factor that restricts the expansion of the Hadoop cluster.

This tool provides the following functions:

1. Checks the number of small files whose size is less than the threshold configured by the user in tables and returns the average size of all data files in the table directory.
2. Provides the function of combination table files. Users can set the average file size after combination.

### Supported Table Types

Spark: Parquet, ORC, CSV, Text, and Json.

Hive: Parquet, ORC, CSV, Text, RCFile, Sequence and Bucket.

 NOTE

1. After tables with compressed data are merged, Spark uses the default compression format Snappy for data compression. You can configure **spark.sql.parquet.compression.codec** (available values: **uncompressed**, **gzip**, **lzo**, and **snappy**) and **spark.sql.orc.compression.codec** (available values: **uncompressed**, **zlib**, **lzo**, and **snappy**) on the client to select the compression format for the Parquet and ORC tables. Compression formats available for Hive and Spark tables are different, except the preceding compression formats, other compression formats are not supported.
2. To merge bucket table data, you need to add the following configurations to the **hive-site.xml** file on the Spark2x client:

```
<property>
<name>hive.enforce.bucketing</name>
<value>>false</value>
</property>
<property>
<name>hive.enforce.sorting</name>
<value>>false</value>
</property>
```
3. Spark does not support the feature of encrypting data columns in Hive.

## Tool Usage

Download and install the client. For example, the installation directory is **/opt/client**. Go to **/opt/client/Spark2x/spark/bin** and run the **mergetool.sh** script.

### Environment variables loading

```
source /opt/client/bigdata_env
```

```
source /opt/client/Spark2x/component_env
```

### Scanning function

Command: **sh mergetool.sh scan <db.table> <filesize>**

The format of *db.table* is *Database name, Table name*. *filesize* is the user-defined threshold of the small file size (unit: MB). The returned result is the number of files that is smaller than the threshold and the average size of data files in the table directory.

Example: **sh mergetool.sh scan default.table1 128**

### Combination function

Command: **sh mergetool.sh merge <db.table> <filesize> <shuffle>**

The format of *db.table* is *Database name, Table name*. **filesize** is the user-defined average file size after file combination (unit: MB). **shuffle** is a Boolean value, and the value is **true** or **false**, which is used to configure whether to allow data to be shuffled during the merge.

Example: **sh mergetool.sh merge default.table1 128 false**

If the following information is displayed, the operation is successful:

```
SUCCESS: Merge succeeded
```

 NOTE

1. Ensure that the current user is the owner of the merged table.
2. Before combination, ensure that HDFS has sufficient storage space, greater than the size of the combined table.
3. Table data must be combined separately. If a table is read during table data combination, the file may not be found temporarily. After the combination is complete, this problem is resolved. During the combination, do not write data to the corresponding tables. Otherwise, data inconsistency may occur.
4. If an error occurs indicating that the file does not exist when the query of data in a partitioned table is performed on the session spark-beeline/spark-sql that is always in the connected status. You can run the **refresh table** *Table name* command as prompted to query the data again.
5. Configure **filesize** based on the site requirements. For example, you can set **filesize** to a value greater than the average during file merging after obtaining the average file size by file scan. Otherwise, the number of files may increase after the file merging.
6. During the file merging, data in the original tables is removed to the recycle bin. In the case of any exception occurs on the data after file merging, the data in the original tables are used to replace the damaged data. If an exception occurs during the process, restore the data in the trash directory by using the **mv** command in HDFS.
7. In the HDFS router federation scenario, if the target NameService of the table root path is different from that of the root path **/user**, you need to manually clear the original table files stored in the recycle bin during the second combination. Otherwise, the combination fails.
8. This tool uses the configuration of the client. Performance optimization can be performed modifying required configuration in the client configuration file.

### shuffle configuration

For the combination function, you can roughly estimate the change on the number of partitions before and after the combination.

Generally, if the number of old partitions is greater than the number of new partitions, set **shuffle** to **false**. However, if the number of old partitions is much greater than that of new partitions (for example, more than 100 times), you can set **shuffle** to **true** to increase the degree of parallelism and improve the combination speed.

---

**NOTICE**

- If **shuffle** is set to **true** (repartition), the performance is improved. However, due to the particularity of the Parquet and ORC storage modes, repartition will reduce the compression ratio and the total size of the table in HDFS increases by 1.3 times.
- If **shuffle** is set to **false** (coalesce), the merged files may have some difference in size, which is close to the value of the configured **filesize**.

---

### Log storage location

The default log storage path is **/tmp/SmallFilesLog.log4j**. To customize the log storage path, you can configure **log4j.appender.logfile.File** in **/opt/client/Spark2x/spark/tool/log4j.properties**.

## 17.5 Using CarbonData for First Query

### Tool Overview

The first query of CarbonData is slow, which may cause a delay for nodes that have high requirements on real-time performance.

The tool provides the following functions:

- Preheat the tables that have high requirements on query delay for the first time.

### Tool Usage

Download and install the client. For example, the installation directory is `/opt/client`. Go to the `/opt/client/Spark2x/spark/bin` directory and run `start-prequery.sh`.

Configure `prequeryParams.properties` by referring to [Table 17-66](#).

**Table 17-66** Parameters

Parameter	Description	Example
<code>spark.prequery.period.max.minute</code>	Maximum preheating duration, in minutes.	60
<code>spark.prequery.tables</code>	Table name configuration, <i>database.table:int</i> . The table name supports the wildcard (*). <b>int</b> indicates the duration (unit: day) within which the table is updated before it is preheated.	default.test*:10
<code>spark.prequery.maxThreads</code>	Maximum number of concurrent threads during preheating	50
<code>spark.prequery.sslEnable</code>	The value is <b>true</b> in security mode and <b>false</b> in non-security mode.	true

Parameter	Description	Example
spark.prequery.driver	IP address and port number of JDBCServer. The format is <i>IP address:Port number</i> . If multiple servers need to be preheated, enter multiple <i>IP address:Port number</i> of the servers and separate them with commas (,).	192.168.0.2:22550
spark.prequery.sql	SQL statement for preheating. Different statements are separated by colons (:).	SELECT COUNT(*) FROM %s;SELECT * FROM %s LIMIT 1
spark.security.url	URL required by JDBC in security mode	;sasLQop=auth-conf;auth=KERBEROS;principal=spark2x/hadoop.hadoop.com@HADOOP.COM;

 NOTE

The statement configured in **spark.prequery.sql** is executed in each preheated table. The table name is replaced with **%s**.

**Script Usage**

Command format: **sh start-prequery.sh**

To run this command, place **user.keytab** or **jaas.conf** (either of them) and **krb5.conf** (mandatory) in the **conf** directory.

 NOTE

- Currently, this tool supports only Carbon tables.
- This tool initializes the Carbon environment and pre-reads table metadata to JDBCServer. Therefore, this tool is more suitable for multi-active instances and static allocation mode.

## 17.6 Spark2x Performance Tuning

### 17.6.1 Spark Core Tuning

## 17.6.1.1 Data Serialization

### Scenario

Spark supports the following types of serialization:

- JsonSerializer
- KryoSerializer

Data serialization affects the Spark application performance. In specific data format, KryoSerializer offers 10X higher performance than JsonSerializer. For Int data, performance optimization can be ignored.

KryoSerializer depends on Chill of Twitter. Not all Java Serializable objects support KryoSerializer. Therefore, class must be manually registered.

Serialization involves task serialization and data serialization. Only JsonSerializer can be used for Spark task serialization. JsonSerializer and KryoSerializer can be used for data serialization.

### Procedure

When the Spark program is running, a large volume of data needs to be serialized during the shuffle and RDD cache procedures. By default, JsonSerializer is used. You can also configure KryoSerializer as the data serializer to improve serialization performance.

Add the following code to enable KryoSerializer to be used:

- Implement the class registrar and manually register the class.

```
package com.etl.common;

import com.esotericsoftware.kryo.Kryo;
import org.apache.spark.serializer.KryoRegistrar;

public class DemoRegistrar implements KryoRegistrar
{
    @Override
    public void registerClasses(Kryo kryo)
    {
        //Class examples are given below. Register the custom classes.
        kryo.register(AggrateKey.class);
        kryo.register(AggrateValue.class);
    }
}
```

You can configure **spark.kryo.registrationRequired** on Spark client. Whether to require registration with Kryo. If set to 'true', Kryo will throw an exception if an unregistered class is serialized. If set to false (the default), Kryo will write unregistered class names along with each object. Writing class names can cause significant performance overhead. This operation will affect the system performance. If the value of **spark.kryo.registrationRequired** is configured to **true**, you need to manually register the class. For a class that is not serialized, the system will not automatically write the class name, but display an exception. Compare the configuration of **true** with that of **false**, the configuration of **true** has the better performance.

- Configure KryoSerializer as the data serializer and class registrar.

```
val conf = new SparkConf()
conf.set("spark.serializer", "org.apache.spark.serializer.KryoSerializer")
.set("spark.kryo.registrator", "com.etl.common.DemoRegistrar")
```

## 17.6.1.2 Optimizing Memory Configuration

### Scenario

Spark is a memory-based computing frame. If the memory is insufficient during computing, the Spark execution efficiency will be adversely affected. You can determine whether memory becomes the performance bottleneck by monitoring garbage collection (GC) and evaluating the resilient distributed dataset (RDD) size in the memory, and take performance optimization measures.

To monitor GC of node processes, add the `-verbose:gc -XX:+PrintGCDetails -XX:+PrintGCTimeStamps` parameter to the `spark.driver.extraJavaOptions` and `spark.executor.extraJavaOptions` in the client configuration file `conf/spark-default.conf`. If "Full GC" is frequently reported, GC needs to be optimized. Cache the RDD and query the RDD size in the log. If a large value is found, change the RDD storage level.

### Procedure

- To optimize GC, adjust the ratio of the young generation and tenured generation. Add `-XX:NewRatio` parameter to the `spark.driver.extraJavaOptions` and `spark.executor.extraJavaOptions` in the client configuration file `conf/spark-default.conf`. For example, export `SPARK_JAVA_OPTS="-XX:NewRatio=2"`. The new generation accounts for 1/3 of the heap, and the tenured generation accounts for 2/3.
- Optimize the RDD data structure when compiling Spark programs.
  - Use primitive arrays to replace fastutil arrays, for example, use fastutil library.
  - Avoid nested structure.
  - Avoid using String in keys.
- Suggest serializing the RDDs when developing Spark programs.

By default, data is not serialized when RDDs are cached. You can set the storage level to serialize the RDDs and minimize memory usage. For example:

```
testRDD.persist(StorageLevel.MEMORY_ONLY_SER)
```

## 17.6.1.3 Setting the DOP

### Scenario

The degree of parallelism (DOP) specifies the number of tasks to be executed concurrently. It determines the number of data blocks after the shuffle operation. Configure the DOP to improve the processing capability of the system.

Query the CPU and memory usage. If the tasks and data are not evenly distributed among nodes, increase the DOP. Generally, set the DOP to two or three times that of the total CPUs in the cluster.

### Procedure

Configure the DOP parameter using one of the following methods based on the actual memory, CPU, data, and application logic conditions:

- Configure the DOP parameter in the operation function that generates the shuffle. This method has the highest priority.  
`testRDD.groupByKey(24)`
- Configure the DOP using **spark.default.parallelism**. This method has the lower priority than the preceding one.  
`val conf = new SparkConf();  
conf.set("spark.default.parallelism", 24);`
- Configure the value of **spark.default.parallelism** in the **\$SPARK\_HOME/conf/spark-defaults.conf** file. This method has the lowest priority.  
`spark.default.parallelism 24`

### 17.6.1.4 Using Broadcast Variables

#### Scenario

Broadcast distributes data sets to each node. It allows data to be obtained locally when a data set is needed during a Spark task. If broadcast is not used, data serialization will be scheduled to tasks each time when a task requires data sets. It is time-consuming and makes the task get bigger.

1. If a data set will be used by each slice of a task, broadcast the data set to each node.
2. When small and big tables need to be joined, broadcast small tables to each node. This eliminates the shuffle operation, changing the join operation into a common operation.

#### Procedure

Add the following code to broadcast the testArr data to each node:

```
def main(args: Array[String]) {  
  ...  
  val testArr: Array[Long] = new Array[Long](200)  
  val testBroadcast: Broadcast[Array[Long]] = sc.broadcast(testArr)  
  val resultRdd: RDD[Long] = inpputRdd.map(input => handleData(testBroadcast, input))  
  ...  
}  
  
def handleData(broadcast: Broadcast[Array[Long]], input: String) {  
  val value = broadcast.value  
  ...  
}
```

### 17.6.1.5 Using the external shuffle service to improve performance

#### Scenario

When the Spark system runs applications that contain a shuffle process, an executor process also writes shuffle data and provides shuffle data for other executors in addition to running tasks. If the executor is heavily loaded and GC is triggered, the executor cannot provide shuffle data for other executors, affecting task running.

The external shuffle service is an auxiliary service in NodeManager. It captures shuffle data to reduce the load on executors. If GC occurs on an executor, tasks on other executors are not affected.

## Procedure

- Step 1** Log in to FusionInsight Manager.
- Step 2** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x** > **Configurations**. Select **All Configurations**.
- Step 3** Choose **SparkResource2x** > **Default** and modify the following parameters.

**Table 17-67** Parameter list

Parameter	Default Value	Changed To
spark.shuffle.service.enabled	false	true

- Step 4** Restart the Spark2x service for the configuration to take effect.

 **NOTE**

To use the External Shuffle Service function on the Spark2x client, you need to download and install the Spark2x client again.

----End

### 17.6.1.6 Configuring Dynamic Resource Scheduling in Yarn Mode

#### Scenario

Resources are a key factor that affects Spark execution efficiency. When a long-running service (such as the JDBCServer) is allocated with multiple executors without tasks but resources of other applications are insufficient, resources are wasted and scheduled improperly.

Dynamic resource scheduling can add or remove executors of applications in real time based on the task load. In this way, resources are dynamically scheduled to applications.

#### Procedure

- Step 1** Configure the external shuffle service.
- Step 2** Log in to FusionInsight Manager, and choose **Cluster** > *Name of the desired cluster* > **Service** > **Spark2x** > **Configuration** > **All Configurations**. Enter **spark.dynamicAllocation.enabled** in the search box and set its value to **true** to enable the dynamic resource scheduling function. This function is disabled by default.

----End

**Table 17-68** lists some optional configuration items.

**Table 17-68** Parameters for dynamic resource scheduling

Configuration Item	Description	Default Value
spark.dynamicAllocation.minExecutors	Indicates the minimum number of executors.	0
spark.dynamicAllocation.initialExecutors	Indicates the number of initial executors.	0
spark.dynamicAllocation.maxExecutors	Indicates the maximum number of executors.	2048
spark.dynamicAllocation.schedulerBacklogTimeout	Indicates the first timeout period for scheduling.	1s
spark.dynamicAllocation.sustainedSchedulerBacklogTimeout	Indicates the second and later timeout interval for scheduling.	1s
spark.dynamicAllocation.executorIdleTimeout	Indicates the idle timeout interval for common executors.	60s
spark.dynamicAllocation.cachedExecutorIdleTimeout	Indicates the idle timeout interval for executors with cached blocks.	<ul style="list-style-type: none"> <li>• JDBCServer2x: 2147483647s</li> <li>• IndexServer2x: 2147483647s</li> <li>• SparkResource2x: 120</li> </ul>

 **NOTE**

The external shuffle service must be configured before using the dynamic resource scheduling function.

### 17.6.1.7 Configuring Process Parameters

#### Scenario

There are three processes in Spark on Yarn mode: driver, ApplicationMaster, and executor. The Driver and Executor handle the scheduling and running of the task. The ApplicationMaster handles the start and stop of the container.

Therefore, the configuration of the driver and executor is very important to run the Spark application. You can optimize the performance of the Spark cluster according to the following procedure.

#### Procedure

**Step 1** Configure the driver memory.

The driver schedules tasks and communicates with the executor and the ApplicationMaster. Add driver memory when the number and parallelism level of the tasks increases.

You can configure the driver memory based on the number of the tasks.

- Set **spark.driver.memory** in **spark-defaults.conf** to a proper value.
- Add the **--driver-memory MEM** parameter to configure the memory when using the **spark-submit** command.

### Step 2 Configure the number of the executors.

One core in an executor can run one task at the same time. Therefore, more tasks can be processed at the same time if you increase the number of the executors. You can add the number of the executors to increase the efficiency if resources are sufficient.

- Set **spark.executor.instance** in **spark-defaults.conf** or **SPARK\_EXECUTOR\_INSTANCES** in **spark-env.sh** to a proper value.
- Add the **--num-executors NUM** parameter to configure the number of the executors when using the **spark-submit** command.

### Step 3 Configure the number of the executor cores.

Multiple cores in an executor can run multiple tasks at the same time, which increases the task concurrency. However, because all cores share the memory of an executor, you need to balance the memory and the number of cores.

- Set **spark.executor.cores** in **spark-defaults.conf** or **SPARK\_EXECUTOR\_CORES** in **spark-env.sh** to a proper value.
- When you run the **spark-submit** command, add the **--executor-cores NUM** parameter to set the number of executor cores.

### Step 4 Configure the executor memory.

The executor memory is used for task execution and communication. You can increase the memory for a big task that needs more resources, and reduce the memory to increase the concurrency level for a small task that runs fast.

- Set **spark.executor.memory** in **spark-defaults.conf** or **SPARK\_EXECUTOR\_MEMORY** in **spark-env.sh** to a proper value.
- When you run the **spark-submit** command, add the **--executor-memory MEM** parameter to set the memory.

----End

## Example

- During the **spark wordcount** calculation, the amount of data is 1.6 TB and the number of the executors is 250.  
The execution fails under the default configuration, and the **Futures timed out** and **OOM** errors occur.

However each task of wordcount is small and runs fast, the amount of the data is big and the tasks are too many. Therefore the objects on the driver end become huge when there are many tasks. Besides the fact that the executor communicates with the driver once each task is finished, the

problem of disconnection between processes caused by insufficient memory occurs.

The application runs successfully when the memory of the Driver is set to 4 GB.

- Many errors still occurred in the default configuration when running TPC-DS test on JDBCServer, such as "Executor Lost". When there is 30 GB of driver memory, 2 executor cores, 125 executors, and 6 GB of executor memory, all tasks can be successfully executed.

### 17.6.1.8 Designing the Direction Acyclic Graph (DAG)

#### Scenario

Optimal program structure helps increase execution efficiency. During application programming, avoid shuffle operations and combine narrow-dependency operations.


#### Procedure

This topic describes how to design the DAG using the following example:

- **Data format:** Time passing through the toll station, vehicle license plate number, toll station number ...
- **Logic:** Two vehicles are determined to be raveling together if the following conditions are met:
  - The two vehicles pass through tool stations in the same sequence.
  - The time difference that the two vehicles pass through the same toll station is below the specified value.

This example can be implemented in two ways:

**Figure 17-6** Implementation logic 1




Logic of implementation 1:

1. Collect information about the toll stations passed by each vehicle based on the vehicle license plate number and sort the toll stations. The following data is obtained:  
vehicle license plate number 1, [(time, toll station 3), (time, toll station 2), (time, toll station 4), (time, toll station 5)]
2. Determine the sequence in which the vehicle passed through.  
(toll station 3, (vehicle license plate number 1, time, 1st toll station))  
(toll station 2, (vehicle license plate number 1, time, 2nd toll station))  
(toll station 4, (vehicle license plate number 1, time, 3rd toll station))  
(toll station 5, (vehicle license plate number 1, time, 4th toll station))
3. Aggregate data by toll station.  
toll station 1, [(vehicle license plate number 1, time, 1st toll station), (vehicle license plate number 2, time, 5th toll station), (vehicle license plate number 3, time, 2nd toll station)]
4. Determine whether the time difference that two vehicles passed through the same toll station is below the specified value. If yes, fetch information about the two vehicles.  
(vehicle license plate number 1, vehicle license plate number 2),(1st toll station, 5th toll station)  
(vehicle license plate number 1, vehicle license plate number 3),(1st toll station, 2nd toll station)
5. Aggregate data based on the vehicle license plate numbers that passed through the same toll stations.  
(vehicle license plate number 1, vehicle license plate number 2), [(1st toll station, 5th toll station), (2nd toll station, 6th toll station), (1st toll station, 7th toll station), (3rd toll station, 8th toll station)]
6. If the two vehicles pass through the same toll stations in sequence, for example, toll stations 3, 4, 5 are the first, second, and third toll station passed by vehicle 1 and the 6th, 7th, and 8th toll station passed by vehicle 2, and the number of toll stations meets the specified requirements, the two vehicles are determined to be traveling together.

The logic of implementation 1 has the following disadvantages:

- The logic is complex.
- Too many shuffle operations affect performance.

**Figure 17-7** Implementation logic 2



Logic of implementation 2:

1. Collect information about the toll stations passed by each vehicle based on the vehicle license plate number and sort the toll stations. The following data is obtained:  
vehicle license plate number 1, [(time, toll station 3), (time, toll station 2), (time, toll station 4), (time, toll station 5)]
2. Based on the number of toll stations that must be passed by peer vehicles (it is 3 in this example), divide the toll station sequence as follows:  
toll station 3->toll station 2->toll station 4, (vehicle license plate number 1, [time passing through toll station 3, time passing through toll station 2, time passing through toll station 4])  
toll station 2->toll station 4->toll station 5, (vehicle license plate number 1, [time passing through toll station 2, time passing through toll station 4, time passing through toll station 5])
3. Aggregate the vehicles that passed through tool stations in the same sequence.  
toll station 3->toll station 2->toll station 4, [(vehicle license plate number 1, [time passing through toll station 3, time passing through toll station 2, time passing through toll station 4]), (vehicle license plate number 2, [time passing through toll station, time passing through toll station 3,time passing through toll station, time passing through toll station 2, time passing through toll station 4]), (vehicle license plate number 3, [time passing through toll station 3, time passing through toll station 2, time passing through toll station 4])]
4. Determine whether the time difference that these vehicles passed through the same toll station is below the specified value. If yes, the vehicles are determined to be raveling together.

The logic of implementation 2 has the following advantages:

- The logic is simplified.
- One groupByKey is reduced, that is, one less shuffle operation is performed. It helps improve performance.

### 17.6.1.9 Experience

#### Use mapPartitions to calculate data by partition.

If the overhead of each record is high, for example:

```
rdd.map{x=>conn=getDBConn;conn.write(x.toString);conn.close}
```

Use mapPartitions to calculate data by partition.

```
rdd.mapPartitions(records => conn.getDBConn;for(item <- records)  
write(item.toString); conn.close)
```

Use mapPartitions to flexibly operate data. For example, to calculate the TopN of a large data, mapPartitions can be used to calculate the TopN of each partition and then sort the TopN of all partitions when N is small. Compared with sorting full data for the TopN, this method has the higher efficiency.

#### Use coalesce to adjust the number of slices.

Use coalesce to adjust the number of slices. There are two coalesce functions:

```
coalesce(numPartitions: Int, shuffle: Boolean = false)
```

When **shuffle** is set to **true**, the function is the same as `repartition(numPartitions:Int)`. Partitions are recreated using the shuffle. When **shuffle** is set to **false**, partitions of the parent resilient distributed datasets (RDD) are calculated in the same task. In this case, if the value of **numPartitions** is larger than the number of sections of the parent RDD, partitions will not be recreated.

The following scenario is encountered, you can choose the coalesce operator:

- If the previous operation involves a large number of filters, use coalesce to minimize the number of zero-loaded tasks. In `coalesce(numPartitions, false)`, the value of **numPartitions** is smaller than the number of sections of the parent RDD.
- Use coalesce when the number of slices entered is too big to execute.
- Use coalesce when the programs are suspended in the shuffle operation because of a large number of tasks or the Linux resources are limited. In this case, use `coalesce(numPartitions, true)` to recreate partitions.

#### Configure a localDir for each disk.

During the shuffle procedure of Spark, data needs to be written into local disks. The performance bottleneck of Spark is shuffle, and the bottleneck of shuffle is the I/O. To improve the I/O performance, you can configure multiple disks to implement concurrent data writing. If a node is mounted with multiple disks, configure a Spark local Dir for each disk. This can effectively distribute shuffle files in multiple locations, improving disk I/O efficiency. The performance cannot be improved effectively if a disk is configured with multiple directories.

#### Collect small data sets.

The collect operation does not apply to a large data volume.

When the collect operation is performed, the Executor data will be sent to the Driver. Before performing this operation, ensure that the memory of Driver is sufficient. Otherwise, the Driver process may encounter an OutOfMemory error. If the data volume is unknown, perform the saveAsTextFile operation to write data into the HDFS. If the data volume is known and the Driver has sufficient memory, perform the collect operation.

## Use reduceByKey

reduceByKey causes local aggregation on the Map side, which offers a smooth shuffle procedure. The shuffle operations, like groupByKey, will not perform aggregation on the Map side. Therefore, use reduceByKey as possible as you can, and avoid groupByKey().map(x=>(x.\_1,x.\_2.size)).

## Broadcast map instead of array.

If table query is required for each record of the data transmitted from the Driver side, broadcast the data in the set/map instead of Iterator. The query speed of Set/Map is approximately  $O(1)$ , while the query speed of Iterator is  $O(n)$ .

## Avoid data skew.

If data skew occurs (certain data volume is extremely large), the execution time of tasks is inconsistent even if there is no Garbage Collection (GC).

- Redefine the keys. Use keys of smaller granularity to optimize the task size.
- Modify the degree of parallelism (DOP).

## Optimize the data structure.

- Store data by column. As a result, only the required columns are scanned when data is read.
- When using the Hash Shuffle, set **spark.shuffle consolidateFiles** to **true** to combine the intermediate files of shuffle, minimize the number of shuffle files and file I/O operations, and improve performance. The number of final files is the number of reduce tasks.

## 17.6.2 Spark SQL and DataFrame Tuning

### 17.6.2.1 Optimizing the Spark SQL Join Operation

#### Scenario

When two tables are joined in Spark SQL, the broadcast function (see section "Using Broadcast Variables") can be used to broadcast tables to each node. This minimizes shuffle operations and improves task execution efficiency.

#### NOTE

The join operation refers to the inner join operation only.

## Procedure

The following describes how to optimize the join operation in Spark SQL. Assume that both tables A and B have the **name** column. Join tables A and B as follows:

1. Estimate the table sizes.

Estimate the table size based on the size of data loaded each time.

You can also check the table size in the directory of the Hive database. In the **hive-site.xml** configuration file of Spark, view the Hive database directory, which is **/user/hive/warehouse** by default.

```
<property>
  <name>hive.metastore.warehouse.dir</name>
  <value>${test.warehouse.dir}</value>
  <description></description>
</property>
```

Run the **hadoop** command to check the size of the table. For example, run the following command to view the size of table **A**:

```
hadoop fs -du -s -h ${test.warehouse.dir}/a
```

### NOTE

To perform the broadcast operation, ensure that at least one table is not empty.

2. Configure a threshold for automatic broadcast.

The threshold for triggering broadcast for a table is 10485760 (that is, 10 MB) in Spark. If either of the table sizes is smaller than 10 MB, skip this step.

**Table 17-69** lists configuration parameters of the threshold for automatic broadcasting.

**Table 17-69** Parameter description

Parameter	Default Value	Description
spark.sql.autoBroadcastJoinThreshold	10485760	<p>Indicates the maximum value for the broadcast configuration when two tables are joined.</p> <ul style="list-style-type: none"> <li>• When the size of a field in a table involved in an SQL statement is less than the value of this parameter, the system broadcasts the SQL statement.</li> <li>• If the value is set to <b>-1</b>, broadcast is not performed.</li> </ul> <p>For details, visit <a href="https://spark.apache.org/docs/3.1.1/sql-programming-guide.html">https://spark.apache.org/docs/3.1.1/sql-programming-guide.html</a>.</p>

Methods for configuring the threshold for automatic broadcasting:

- Set **spark.sql.autoBroadcastJoinThreshold** in the **spark-defaults.conf** configuration file of Spark.

```
spark.sql.autoBroadcastJoinThreshold = <size>
```

- Run the Hive command to set the threshold. Before joining the tables, run the following command:  

```
SET spark.sql.autoBroadcastJoinThreshold=<size>
```
- 3. Join the tables.
  - The size of each table is smaller than the threshold.
    - If the size of table A is smaller than that of table B, run the following command:  

```
SELECT A.name FROM B JOIN A ON A.name = B.name;
```
    - If the size of table B is smaller than that of table A, run the following command:  

```
SELECT A.name FROM A JOIN B ON A.name = B.name;
```
  - One table size is smaller than the threshold, while the other table size is greater than the threshold.  
Broadcast the smaller table.
  - The size of each table is greater than the threshold.  
Compare the size of the field involved in the query with the threshold.
    - If the values of the fields in a table are smaller than the threshold, the corresponding data in the table is broadcast.
    - If the values of the fields in the two tables are greater than the threshold, do not broadcast either of the table.
- 4. (Optional) In the following scenarios, you need to run the Analyze command (***ANALYZE TABLE tableName COMPUTE STATISTICS noscan;***) to update metadata before performing the broadcast operation:
  - The table to be broadcasted is a newly created partitioned table and the file type is non-Parquet.
  - The table to be broadcasted is a newly updated partitioned table.

## Reference

A task is ended if a timeout occurs during the execution of the to-be-broadcasted table.

By default, BroadCastJoin allows only 5 minutes for the to-be-broadcasted table calculation. If the time is exceeded, a timeout will occur. However, the broadcast task of the to-be-broadcasted table calculation is still being executed, resulting in resource waste.

The following methods can be used to address this issue:

- Modify the value of **spark.sql.broadcastTimeout** to increase the timeout duration.
- Reduce the value of **spark.sql.autoBroadcastJoinThreshold** to disable the optimization of BroadCastJoin.

### 17.6.2.2 Improving Spark SQL Calculation Performance Under Data Skew

#### Scenario

When multiple tables are joined in Spark SQL, skew occurs in join keys and the data volume in some Hash buckets is much higher than that in other buckets. As a

result, some tasks with a large amount of data run slowly, resulting low computing performance. Other tasks with a small amount of data are quickly completed, which frees many CPUs and results in a waste of CPU resources.

If the automatic data skew function is enabled, data that exceeds the bucketing threshold is bucketed. Multiple tasks proceed data in one bucket. Therefore, CUP usage is enhanced and the system performance is improved.

 **NOTE**

Data that has no skew is bucketed and run in the original way.

Restrictions:

- Only the join between two tables is supported.
- FULL OUTER JOIN data does not support data skew.  
For example, the following SQL statement indicates that the skew of table **a** or table **b** cannot trigger the optimization.  
***select aid FROM a FULL OUTER JOIN b ON aid=bid;***
- LEFT OUTER JOIN data does not support the data skew of the right table.  
For example, the following SQL statement indicates that the skew of table **b** cannot trigger the optimization.  
***select aid FROM a LEFT OUTER JOIN b ON aid=bid;***
- RIGHT OUTER JOIN does not support the data skew of the left table.  
For example, the following SQL statement indicates that the skew of table **a** cannot trigger the optimization.  
***select aid FROM a RIGHT OUTER JOIN b ON aid=bid;***

## Configuration Description

Add the following parameters in the following table to the **spark-defaults.conf** configuration file on the Spark driver.

**Table 17-70** Parameter description

Parameter	Description	Default Value
spark.sql.adaptive.enabled	The switch to enable the adaptive execution feature.  Note: If AQE and Static Partition Pruning (DPP) are enabled at the same time, DPP takes precedence over AQE during SparkSQL task execution. As a result, AQE does not take effect. The DPP in the cluster is enabled by default. Therefore, you need to disable it when enabling the AQE.	false
spark.sql.optimize.r.dynamicPartitionPruning.enabled	The switch to enable DPP.	true

Parameter	Description	Default Value
spark.sql.adaptive.skewJoin.enabled	Specifies whether to enable the function of automatic processing of the data skew in join operations. The function is enabled when this parameter is set to <b>true</b> and <b>spark.sql.adaptive.enabled</b> is set to <b>true</b> .	true
spark.sql.adaptive.skewJoin.skewedPartitionFactor	This parameter is a multiplier used to determine whether a partition is a data skew partition. If the data size of a partition exceeds the value of this parameter multiplied by the median of the all partition sizes except this partition and exceeds the value of <b>spark.sql.adaptive.skewJoin.skewedPartitionThresholdInBytes</b> , this partition is considered as a data skew partition.	5
spark.sql.adaptive.skewjoin.skewedPartitionThresholdInBytes	If the partition size (unit: byte) is greater than the threshold as well as the product of the <b>spark.sql.adaptive.skewJoin.skewedPartitionFactor</b> value and the median partition size, skew occurs in the partition. Ideally, the value of this parameter should be greater than that of <b>spark.sql.adaptive.advisoryPartitionSizeInBytes..</b>	256MB
spark.sql.adaptive.shuffle.targetPostShuffleInputSize	Minimum amount of shuffle data processed by each task. The unit is byte.	67108864

### 17.6.2.3 Optimizing Spark SQL Performance in the Small File Scenario

#### Scenario

A Spark SQL table may have many small files (far smaller than an HDFS block), each of which maps to a partition on the Spark by default. In other words, each small file is a task. If the small files are great in number, Spark must initiate a large number of tasks. If shuffle operations exist in Spark SQL, the number of hash buckets increases, affecting performance.

In this scenario, you can manually specify the split size of each task to avoid an excessive number of tasks and improve performance.

#### NOTE

If the SQL logic does not involve shuffle operations, this optimization does not improve performance.

## Configuration

If you want to enable small file optimization, configure the **spark-defaults.conf** file on the Spark client.

**Table 17-71** Parameter description

Parameter	Description	Default Value
spark.sql.files.maxPartitionBytes	The maximum number of bytes that can be packed into a single partition when a file is read. Unit: byte	134217728 (128 MB)
spark.files.openCostInBytes	The estimated cost to open a file, measured by the number of bytes that can be scanned in the same time. This is used when putting multiple files into a partition. It is better to over estimate, then the partitions with small files will be faster than partitions with larger files.	4 MB

### 17.6.2.4 Optimizing the INSERT...SELECT Operation

#### Scenario

The INSERT...SELECT operation needs to be optimized if any of the following conditions is true:

- Many small files need to be queried.
- A few large files need to be queried.
- The INSERT...SELECT operation is performed by a non-spark user in Beeline/JDBCServer mode.

#### Procedure

Optimize the INSERT...SELECT operation as follows:

- If the table to be created is the Hive table, set the storage type to Parquet. This enables INSERT...SELECT statements to be run faster.
- Perform the INSERT...SELECT operation as a spark-sql user or spark user (if in Beeline/JDBCServer mode). In this way, it is no longer necessary to change the file owner repeatedly, accelerating the execution of INSERT...SELECT statements.

#### NOTE

In Beeline/JDBCServer mode, the executor user is the same as the driver user. The driver user is a spark user because the driver is a part of JDBCServer service and started by a spark user. If the Beeline user is not a spark user, the file owner must be changed to the Beeline user (actual user) because the executor is unaware of the Beeline user.

- If many small files need to be queried, set `spark.sql.files.maxPartitionBytes` and `spark.files.openCostInBytes` to set the maximum size in bytes of partition and combine multiple small files in a partition to reduce file amount. This accelerates file renaming, ultimately enabling `INSERT...SELECT` statements to be run faster.

 **NOTE**

The preceding optimizations are not a one-size-fits-all solution. In the following scenario, it still takes long to perform the `INSERT...SELECT` operation:

The dynamic partitioned table contains many partitions.

## 17.6.2.5 Multiple JDBC Clients Concurrently Connecting to JDBCServer

### Scenario

Multiple clients can be connected to JDBCServer at the same time. However, if the number of concurrent tasks is too large, the default configuration of JDBCServer must be optimized to adapt to the scenario.

### Procedure

1. Set the fair scheduling policy of JDBCServer.

The default scheduling policy of Spark is **FIFO**, which may cause a failure of short tasks in multi-task scenarios. Therefore, the fair scheduling policy must be used in multi-task scenarios to prevent task failure.

- a. For details about how to configure Fair Scheduler in Spark, visit <http://spark.apache.org/docs/3.1.1/job-scheduling.html#scheduling-within-an-application>.
- b. Configure Fair Scheduler on the JDBC client.
  - i. In the Beeline command line client or the code defined by JDBC, run the following statement:

**PoolName** is a scheduling pool for Fair Scheduler.

```
SET spark.sql.thriftserver.scheduler.pool=PoolName;
```

- ii. Run the SQL command. The Spark task will be executed in the preceding scheduling pool.
2. Set the **BroadCastHashJoin** timeout interval.

There is a timeout parameter of **BroadCastHashJoin**. The task query fails if the query period exceeds the preset timeout interval. In multi-task scenarios, the Spark task of `BroadCastHashJoin` may fail due to resource preemption. Therefore, it is necessary to modify the timeout interval in the `spark-defaults.conf` file of JDBCServer.

**Table 17-72** Parameter description

Parameter	Description	Default Value
spark.sql.broadcastTimeout	The timeout interval in the broadcast table of <b>BroadcastHashJoin</b> . If there are many concurrent tasks, set the parameter to a larger value or a negative number.	-1 (Numeral type. The actual value is 5 minutes.)

### 17.6.2.6 Optimizing Memory when Data Is Inserted into Dynamic Partitioned Tables

#### Scenario

When SparkSQL inserts data to dynamic partitioned tables, the more partitions there are, the more HDFS files a single task generates and the more memory metadata occupies. In this case, Garbage Collection (GC) is severe and Out of Memory (OOM) may occur.

Assume there are 10240 tasks and 2000 partitioned. Before the rename operation of HDFS files from a temporary directory to the target directory, there is about 29 GB FileStatus metadata.

#### Procedure

Insert **distribute by** followed by partition fields into dynamic partition statements.

For example:

```
insert into table store_returns partition (sr_returned_date_sk) select
sr_return_time_sk,sr_item_sk,sr_customer_sk,sr_demo_sk,sr_hdemo_sk,sr_addr_sk,
sr_store_sk,sr_reason_sk,sr_ticket_number,sr_return_quantity,sr_return_amt,sr_return_tax,sr_return_amt_inc_tax,sr_fee,sr_return_ship_cost,sr_refunded_cash,sr_reversed_charge,sr_store_credit,sr_net_loss,sr_returned_date_sk from $
{SOURCE}.store_returns distribute by sr_returned_date_sk;
```


### 17.6.2.7 Optimizing Small Files

#### Scenario

A Spark SQL table may have many small files (far smaller than an HDFS block), each of which maps to a partition on the Spark by default. In other words, each small file is a task. In this way, Spark has to start many such tasks. If a shuffle operation is involved in the SQL logic, the number of hash buckets soars, severely hindering system performance.

In case of massive number of small files, when DataSource creates an RDD, it splits small files in the Spark SQL table to PartitionedFiles and then merges the PartitionedFiles to a partition to avoid generating too many hash buckets during the shuffle operation. See [Figure 17-8](#).

Figure 17-8 Merging small files



## Procedure

If you want to enable small file optimization, configure the **spark-defaults.conf** file on the Spark client.

Table 17-73 Parameter description

Parameter	Description	Default Value
spark.sql.files.maxPartitionBytes	The maximum number of bytes that can be packed into a single partition when a file is read. Unit: byte	134217728 (128 MB)
spark.files.openCostInBytes	The estimated cost to open a file, measured by the number of bytes that can be scanned in the same time. This is used when putting multiple files into a partition. It is better to over estimate, then the partitions with small files will be faster than partitions with larger files.	4 MB

### 17.6.2.8 Optimizing the Aggregate Algorithms

#### Scenario

Spark SQL supports hash aggregate algorithm. Namely, use fast aggregate hashmap as cache to improve aggregate performance. The hashmap replaces the previous ColumnarBatch to avoid performance problems caused by the wide mode (multiple key or value fields) of an aggregate table.

## Procedure

If you want to enable optimization of aggregate algorithm, configure following parameters in the **spark-defaults.conf** file on the Spark client.

**Table 17-74** Parameter description

Parameter	Description	Default Value
spark.sql.codegen.aggregate.map.twolevel.enabled	Specifies whether to enable aggregation algorithm optimization. <ul style="list-style-type: none"><li>• <b>true</b>: Enable</li><li>• <b>false</b>: Disable</li></ul>	true

### 17.6.2.9 Optimizing Datasource Tables

#### Scenario

Save the partition information about the datasource table to the Metastore and process partition information in the Metastore.

- Optimize the datasource tables, support syntax such as adding, deletion, and modification in the table based on partitions, improving compatibility with Hive.
- Support statements of partition tailoring and push down to the Metastore to filter unmatched partitions.

Example:

```
select count(*) from table where partCol=1; //partCol (partition column)
```

You need only to process data corresponding to partCol=1 when performing the TableScan operation in the physical plan.

#### Procedure

If you want to enable Datasource table optimization, configure the **spark-defaults.conf** file on the Spark client.

**Table 17-75** Parameter description

Parameter	Description	Default Value
spark.sql.hive.manageFilesourcePartitions	<p>Specifies whether to enable Metastore partition management (including datasource tables and converted Hive).</p> <ul style="list-style-type: none"> <li>• <b>true</b> indicates enabling Metastore partition management. In this case, datasource tables are stored in Hive and Metastore is used to tailor partitions in query statements.</li> <li>• <b>false</b> indicates disabling Metastore partition management.</li> </ul>	true
spark.sql.hive.metastorePartitionPruning	<p>Specifies whether to support pushing down predicate to Hive Metastore.</p> <ul style="list-style-type: none"> <li>• <b>true</b> indicates supporting pushing down predicate to Hive Metastore. Only the predicate of Hive tables is supported.</li> <li>• <b>false</b> indicates not supporting pushing down predicate to Hive Metastore.</li> </ul>	true
spark.sql.hive.filesourcePartitionFileCacheSize	<p>The cache size of the partition file metadata in the memory.</p> <p>All tables share a cache that can use up to specified num bytes for file metadata.</p> <p>This parameter is valid only when <b>spark.sql.hive.manageFilesourcePartitions</b> is set to <b>true</b>.</p>	250 * 1024 * 1024
spark.sql.hive.convertMetastoreOrc	<p>The processing approach of ORC tables.</p> <ul style="list-style-type: none"> <li>• <b>false</b>: Spark SQL uses Hive SerDe to process ORC tables.</li> <li>• <b>true</b>: Spark SQL uses the Spark built-in mechanism to process ORC tables.</li> </ul>	true

### 17.6.2.10 Merging CBO

#### Scenario

Spark SQL supports rule-based optimization by default. However, the rule-based optimization cannot ensure that Spark selects the optimal query plan. Cost-Based Optimizer (CBO) is a technology that intelligently selects query plans for SQL statements. After CBO is enabled, the CBO optimizer performs a series of

estimations based on the table and column statistics to select the optimal query plan.

## Procedure

Perform the following steps to enable CBO:

1. You need to run corresponding SQL commands to collect required table and column statistics.

SQL commands are as follows (to be chosen as required):

- Generate table-level statistics (table scanning):

***ANALYZE TABLE src COMPUTE STATISTICS***

This command generates **sizeInBytes** and **rowCount**.

When you use the ANALYZE statement to collect statistics, sizes of tables not from HDFS cannot be calculated.

- Generate table-level statistics (no table scanning):

***ANALYZE TABLE src COMPUTE STATISTICS NOSCAN***

This command generates only **sizeInBytes**. Compared with the originally generated **sizeInBytes** and **rowCount** if the **sizeInBytes** remains unchanged, **rowCount** (if any) reserves. Otherwise, **rowCount** is cleared.

- Generate column-level statistics:

***ANALYZE TABLE src COMPUTE STATISTICS FOR COLUMNS a, b, c***

This command generates column statistics and updates table statistics for consistency. Statistics of complicated data types (such as Seq and Map) and HiveStringType cannot be generated.

- Display statistics:

***DESC FORMATTED src***

This command displays *xxx* bytes and *xxx* rows in **Statistics** to indicate table-level statistics. You can also run the following command to display column statistics:

***DESC FORMATTED src a***

**Limitation:** The current statistics collection does not support statistics for partition levels for partitioned tables.

2. Configure parameters in [Table 17-76](#) in the **spark-defaults.conf** file on the Spark client.

**Table 17-76** Parameter description

Parameter	Description	Default Value
spark.sql.cbo.enabled	<p>The switch to enable or disable CBO.</p> <ul style="list-style-type: none"> <li>• <b>true:</b> Enable</li> <li>• <b>false:</b> Disable</li> </ul> <p>To enable this function, ensure that statistics of related tables and columns are generated.</p>	false

Parameter	Description	Default Value
spark.sql.cbo.joinReorder.enabled	<p>Specifies whether to automatically adjust the sequence of consecutive inner joins by using CBO.</p> <ul style="list-style-type: none"> <li>• <b>true</b>: Enable</li> <li>• <b>false</b>: Disable</li> </ul> <p>To enable this function, ensure that statistics of related tables and columns are generated and CBO is enabled.</p>	false
spark.sql.cbo.joinReorder.dp.threshold	<p>Specifies the threshold of the number of tables that the sequence of consecutive inner joins is automatically adjusted by CBO.</p> <p>If the threshold is exceeded, the sequence of joins is not adjusted.</p>	12

### 17.6.2.11 Optimizing SQL Query of Data of Multiple Sources

#### Scenario

This section describes how to enable or disable the query optimization for inter-source complex SQL.

#### Procedure

- (Optional) Prepare for connecting to the MPPDB data source.  
If the data source to be connected is MPPDB, a class name conflict occurs because the MPPDB Driver file **gsjdbc4.jar** and the Spark JAR package **gsjdbc4-VXXXRXXXCXXSPCXXX.jar** contain the same class name. Therefore, before connecting to the MPPDB data source, perform the following steps:
  - a. Move **gsjdbc4-VXXXRXXXCXXSPCXXX.jar** from Spark. Spark running does not depend on this JAR file. Therefore, moving this JAR file to another directory (for example, the **/tmp** directory) will not affect Spark running.
    - i. Log in to the Spark server and move **gsjdbc4-VXXXRXXXCXXSPCXXX.jar** from the **`\${BIGDATA\_HOME}/FusionInsight\_Spark2x\_8.1.2.2/install/FusionInsight-Spark2x-3.1.1/spark/jars** directory.
    - ii. Log in to the Spark client host and move **gsjdbc4-VXXXRXXXCXXSPCXXX.jar** from the **/opt/client/Spark2x/spark/jars** directory.
  - b. Obtain the MPPDB Driver file **gsjdbc4.jar** from the MPPDB installation package and upload the file to the following directories:

- `/${BIGDATA_HOME}/FusionInsight_Spark2x_8.1.2.2/install/FusionInsight-Spark2x-3.1.1/spark/jars` on the Spark server.
- `/opt/client/Spark2x/spark/jars` on the Spark client.
- c. Update the `/user/spark2x/jars/8.1.2.2/spark-archive-2x.zip` package stored in the HDFS.
  - i. Log in to the node where the client is installed as a client installation user. Run the following command to switch to the client installation directory, for example, `/opt/client`:  
**cd /opt/client**
  - ii. Run the following command to configure environment variables:  
**source bigdata\_env**
  - iii. If the cluster is in security mode, run the following command to get authenticated:  
**kinit Component service user**
  - iv. Run the following commands to create the temporary file `./tmp`, obtain `spark-archive-2x.zip` from HDFS, and decompress it to the `tmp` directory:  
**mkdir tmp**  
**hdfs dfs -get /user/spark2x/jars/8.1.2.2/spark-archive-2x.zip ./**  
**unzip spark-archive-2x.zip -d ./tmp**
  - v. Switch to the `tmp` directory, delete the `gsjdbc4-VXXXRXXXCXXSPCXXX.jar` file, upload the MPPDB Driver file `gsjdbc4.jar` to the `tmp` directory, and run the following command to compress the file again:  
**zip -r spark-archive-2x.zip \*.jar**
  - vi. Delete `spark-archive-2x.zip` from the HDFS and update the `spark-archive-2x.zip` package generated in `c.v` to the `/user/spark2x/jars/8.1.2.2/` directory in the HDFS.  
**hdfs dfs -rm /user/spark2x/jars/8.1.2.2/spark-archive-2x.zip**  
**hdfs dfs -put ./spark-archive-2x.zip /user/spark2x/jars/8.1.2.2**
- d. Restart the Spark service. After the Spark service is restarted, restart the Spark client.
- Enable the optimization function.

For all modules that support query pushdown, you can run the **SET** command on the `spark-beeline` client to enable the cross-source query optimization function. By default, the function is disabled.

Pushdown configurations can be performed in dimensions of global, data sources, and tables. Commands are as follows:

  - Global (valid for all data sources):  
**SET spark.sql.datasource.jdbc = project,aggregate,orderby-limit**
  - Data sources:  
**SET spark.sql.datasource.\${url} = project,aggregate,orderby-limit**
  - Tables:

**SET spark.sql.datasource.{\$url}.{\$table} = project,aggregate,orderby-limit**

When you run the **SET** command to configure preceding parameters, you are allowed to specify multiple pushdown modules and separate them by commas. The following table lists parameters of corresponding pushdown modules.

**Table 17-77** Parameters of modules

Module	Parameter Value in the SET Command
project	project
aggregate	aggregate
order by, limit over project or aggregate	orderby-limit

The following is a statement for creating an external table of MySQL:

```
create table if not exists pdmysql using org.apache.spark.sql.jdbc
options(driver "com.mysql.jdbc.Driver", url "jdbc:mysql://ip2:3306/test",
user "hive", password "123456", dbtable "mysqldata");
```

In the preceding statement:

- {\$url} = jdbc:mysql://ip2:3306/test
- {\$table} = mysqldata

 **NOTE**

- On the right of the equal sign (=) is the operators (separated by commas) to be enabled by pushdown.
- Priority: table > data source > global. If the table switch is set, the global switch of the data source is invalid for the table. If a data source switch is set, the global switch is invalid for the data source.
- The equal sign (=) is not allowed in URL. Equal signs (=) are automatically deleted in the SET clause.
- After multiple SET operations, results with different keys will not overwrite each other.
- Add functions that support query pushdown.

In addition to query pushdown of mathematical, time, and string functions such as abs(), month(), and length(), you can run the **SET** command to add a data source that supports query pushdown. Run the following command on the Spark-beeline client:

```
SET park.sql.datasource.{$datasource}.functions = fun1,fun2
```

- Reset the configuration set by the **SET** command.

Currently, you can only run the **RESET** command on the **spark-beeline** client to cancel all **SET** content. After running the **RESET** command, all values in the **SET** command will be cleared. Exercise caution when performing this operation.

The **SET** command is valid in the current session on the client. After the client is shut down, the content in the **SET** command turns invalid.

Alternatively, change the value of **spark.sql.locale.support** in the **spark-defaults.conf** file to **true**.

## Precautions

Only MySQL, MPPDB, Hive, oracle, and PostgreSQL data sources are supported.

### 17.6.2.12 SQL Optimization for Multi-level Nesting and Hybrid Join

#### Scenario

This section describes the optimization suggestions for SQL statements in multi-level nesting and hybrid join scenarios.

#### Prerequisites

The following provides an example of complex query statements:

```
select
s_name,
count(1) as numwait
from (
select s_name from (
select
s_name,
t2.l_orderkey,
l_suppkey,
count_suppkey,
max_suppkey
from
test2 t2 right outer join (
select
s_name,
l_orderkey,
l_suppkey from (
select
s_name,
t1.l_orderkey,
l_suppkey,
count_suppkey,
max_suppkey
from
test1 t1 join (
select
s_name,
l_orderkey,
l_suppkey
from
orders o join (
select
s_name,
l_orderkey,
l_suppkey
from
nation n join supplier s
on
s.s_nationkey = n.n_nationkey
and n.n_name = 'SAUDI ARABIA'
join lineitem l
on
s.s_suppkey = l.l_suppkey
```

```
where
l.l_receiptdate > l.l_commitdate
and l.l_orderkey is not null
) l1 on o.o_orderkey = l1.l_orderkey and o.o_orderstatus = 'F'
) l2 on l2.l_orderkey = t1.l_orderkey
) a
where
(count_suppkey > 1)
or ((count_suppkey=1)
and (l_suppkey <> max_suppkey))
) l3 on l3.l_orderkey = t2.l_orderkey
) b
where
(count_suppkey is null)
or ((count_suppkey=1)
and (l_suppkey = max_suppkey))
) c
group by
s_name
order by
numwait desc,
s_name
limit 100;
```

## Procedure

### Step 1 Analyze business.

Analyze business to determine whether SQL statements can be simplified through measures, for example, by combining tables to reduce the number of nesting levels and join times.

### Step 2 If the SQL statements cannot be simplified, configure the driver memory.

- If SQL statements are executed through spark-submit or spark-sql, go to [Step 3](#).
- If SQL statements are executed through spark-beeline, go to [Step 4](#).

### Step 3 During execution of SQL statements, specify the **driver-memory** parameter. An example of SQL statements is as follows:

```
/spark-sql --master=local[4] --driver-memory=512M -f /tpch.sql
```

### Step 4 Before running SQL statements, change the memory size as the MRS cluster administrator.

1. Log in to FusionInsight Manager and choose **Cluster** > *Name of the desired cluster* > **Services** > **Spark2x** > **Configurations**.
2. On the displayed page, click **All Configurations** and search for **SPARK\_DRIVER\_MEMORY**.
3. Modify the **SPARK\_DRIVER\_MEMORY** parameter value to increase the memory size. The parameter value consists of two parts: memory size (an integer) and the unit (M or G), for example, **512M**.

----End

## Reference

In the event of insufficient driver memory, the following error may be displayed during the query:

```

2018-02-11 09:13:14,683 | WARN | Executor task launch worker for task 5 | Calling spill() on
RowBasedKeyValueBatch. Will not spill but return 0. |
org.apache.spark.sql.catalyst.expressions.RowBasedKeyValueBatch.spill(RowBasedKeyValueBatch.java:173)
2018-02-11 09:13:14,682 | WARN | Executor task launch worker for task 3 | Calling spill() on
RowBasedKeyValueBatch. Will not spill but return 0. |
org.apache.spark.sql.catalyst.expressions.RowBasedKeyValueBatch.spill(RowBasedKeyValueBatch.java:173)
2018-02-11 09:13:14,704 | ERROR | Executor task launch worker for task 2 | Exception in task 2.0 in stage
1.0 (TID 2) | org.apache.spark.internal.Logging$class.logError(Logging.scala:91)
java.lang.OutOfMemoryError: Unable to acquire 262144 bytes of memory, got 0
    at org.apache.spark.memory.MemoryConsumer.allocateArray(MemoryConsumer.java:100)
    at org.apache.spark.unsafe.map.BytesToBytesMap.allocate(BytesToBytesMap.java:791)
    at org.apache.spark.unsafe.map.BytesToBytesMap.<init>(BytesToBytesMap.java:208)
    at org.apache.spark.unsafe.map.BytesToBytesMap.<init>(BytesToBytesMap.java:223)
    at
org.apache.spark.sql.execution.UnsafeFixedWidthAggregationMap.<init>(UnsafeFixedWidthAggregationMap.j
ava:104)
    at
org.apache.spark.sql.execution.aggregate.HashAggregateExec.createHashMap(HashAggregateExec.scala:307)
    at org.apache.spark.sql.catalyst.expressions.GeneratedClass
$GeneratedIterator.agg_doAggregateWithKeys$(Unknown Source)
    at org.apache.spark.sql.catalyst.expressions.GeneratedClass$GeneratedIterator.processNext(Unknown
Source)
    at org.apache.spark.sql.execution.BufferedRowIterator.hasNext(BufferedRowIterator.java:43)
    at org.apache.spark.sql.execution.WholeStageCodegenExec$$anonfun$8$$anon
$1.hasNext(WholeStageCodegenExec.scala:381)
    at scala.collection.Iterator$$anon$11.hasNext(Iterator.scala:408)
    at
org.apache.spark.shuffle.sort.BypassMergeSortShuffleWriter.write(BypassMergeSortShuffleWriter.java:126)
    at org.apache.spark.scheduler.ShuffleMapTask.runTask(ShuffleMapTask.scala:96)
    at org.apache.spark.scheduler.ShuffleMapTask.runTask(ShuffleMapTask.scala:53)
    at org.apache.spark.scheduler.Task.run(Task.scala:99)
    at org.apache.spark.executor.Executor$TaskRunner.run(Executor.scala:325)
    at java.util.concurrent.ThreadPoolExecutor.runWorker(ThreadPoolExecutor.java:1149)
    at java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:624)
    at java.lang.Thread.run(Thread.java:748)

```

## 17.6.3 Spark Streaming Tuning

### Scenario

Streaming is a mini-batch streaming processing framework that features second-level delay and high throughput. To optimize Streaming is to improve its throughput while maintaining second-level delay so that more data can be processed per unit time.

#### NOTE

This section applies to the scenario where the input data source is Kafka.

### Procedure

A simple streaming processing system consists of a data source, a receiver, and a processor. The data source is Kafka, the receiver is the Kafka data source receiver of Streaming, and the processor is Streaming.

Streaming optimization is to optimize the performance of the three components.

- **Data source optimization**

In actual application scenarios, the data source stores the data in the local disks to ensure the error tolerance of the data. However, the calculation results of the Streaming are stored in the memory, and the data source may become the largest bottleneck of the streaming system.

Kafka can be optimized from the following aspects:

- Use Kafka-0.8.2 or later version that allows you to use new Producer APIs in asynchronous mode.
- Configure multiple Broker directories, multiple I/O threads, and a proper number of partitions for a topic.

For details, see section **Performance Tuning** in the Kafka open source documentation at <http://kafka.apache.org/documentation.html>.

- **Receiver optimization**

Streaming has multiple data source receivers, such as Kafka, Flume, MQTT, and ZeroMQ. Kafka has the most receiver types and is the most mature receiver.

Kafka provides three types of receiver APIs:

- `KafkaReceiver` directly receives Kafka data. If the process is abnormal, data may be lost.
- `ReliableKafkaReceiver` receives data displacement through ZooKeeper records.
- `DirectKafka` reads data from each partition of Kafka through the RDD, ensuring high reliability.

According to the implementation mechanism and test results, `DirectKafka` provides better performance than the other two APIs. Therefore, the `DirectKafka` API is recommended to implement the receiver.

For details about the Kafka receivers and their optimization methods, see the Kafka open source documentation at <http://kafka.apache.org/documentation.html>.

- **Processor optimization**

The bottom layer of Spark Streaming is executed by Spark. Therefore, most optimization measures for Spark can also be applied to Spark Streaming. The following is an example:

- Data serialization
- Memory configuration
- Configuring DOP
- Using the external shuffle service to improve performance

 **NOTE**

Higher performance of Spark Streaming indicates lower overall reliability. Examples:

If `spark.streaming.receiver.writeAheadLog.enable` is set to `false`, disk I/Os are reduced and performance is improved. However, because WAL is disabled, data is lost during fault recovery.

Therefore, do not disable configuration items that ensure data reliability in production environments during Spark Streaming tuning.

- **Log archive optimization**

The `spark.eventLog.group.size` parameter is used to group **JobHistory** logs of an application based on the specified number of jobs. Each group creates a file recording log to prevent **JobHistory** reading failures caused by an oversized log generated during the long-term running of the application. If this parameter is set to `0`, logs are not grouped.

Most Spark Streaming jobs are small jobs and are generated at a high speed. As a result, frequent grouping is performed and a large number of small log

files are generated, consuming disk I/O resources. You are advised to increase the parameter value to, for example, **1000** or greater.

## 17.6.4 Spark on OBS Tuning

### Scenario

In the scenario where a small number of requests are frequently sent from Spark on OBS to OBS, you can disable OBS monitoring to improve performance.

### Configuration

Modify the configuration in the **core-site.xml** file on the Spark client.

**Table 17-78** Parameter description

Parameter	Description	Default Value
fs.obs.metrics.switch	Specifies whether to report OBS monitoring metrics. <ul style="list-style-type: none"> <li>• <b>true</b>: enable</li> <li>• <b>false</b>: disable</li> </ul>	true
fs.obs.metrics.consumer	Specifies the processing mode of OBS monitoring metrics. <ul style="list-style-type: none"> <li>• <b>org.apache.hadoop.fs.obs.metrics.OBSAMetricsProvider</b>: indicates that OBS monitoring metrics are collected.</li> <li>• <b>org.apache.hadoop.fs.obs.DefaultMetricsConsumer</b>: indicates that OBS monitoring metrics are not collected.</li> </ul> <p>To use the OBS monitoring function, ensure that the function of reporting OBS monitoring metrics is enabled.</p>	org.apache.hadoop.fs.obs.metrics.OBSAMetricsProvider

## 17.7 Common Issues About Spark2x

### 17.7.1 Spark Core

#### 17.7.1.1 How Do I View Aggregated Spark Application Logs?

##### Question

How do I view the aggregated container logs on the page when the log aggregation function is enabled on YARN?

## Answer

For details, see [Viewing Aggregated Container Logs on the Web UI](#).

### 17.7.1.2 Why Is the Return Code of Driver Inconsistent with Application State Displayed on ResourceManager WebUI?

#### Question

Communication between ApplicationMaster and ResourceManager remains abnormal for a long time. Why is the driver return code inconsistent with application status on ResourceManager WebUI?

#### Answer

In yarn-client mode, Spark Driver and ApplicationMaster run as two independent processes. When Driver exits, it notifies ApplicationMaster to call the unregister API to deregister itself with ResourceManager.

This is a remote call and susceptible to network faults. If there exists a network fault, ApplicationMaster uses the retry mechanism of the Yarn client to try again. If the network is recovered before the maximum number of retries is reached, ApplicationMaster exits gracefully.

If the number and duration of retries are reached, ApplicationMaster fails to deregister itself, and ResourceManager declares ApplicationMaster to have exited forcibly and tries to restart ApplicationMaster. After the restart, if ApplicationMaster fails to connect to the exited Driver, ResourceManager flags the Application being failed.

This problem rarely occurs and it does not impact the display of application states by SparkSQL. You can also increase the number of Yarn client connections and the connection duration to reduce the probability of this event. For details about the configuration, see <http://hadoop.apache.org/docs/r3.1.1/hadoop-yarn/hadoop-yarn-common/yarn-default.xml>.

### 17.7.1.3 Why Cannot Exit the Driver Process?

#### Question

Why cannot exit the Driver process after running the **yarn application -kill applicationID** command to stop the Spark Streaming application?

#### Answer

Running the **yarn application -kill applicationID** command can only stop the SparkContext corresponding to Spark Streaming application, but cannot exit the current Driver process. If there are other permanent threads in the Driver process (for example, the spark shell is continually checking command input or Spark Streaming is continually reading data from data source), the Driver process will not be killed when the SparkContext is stopped. To exit the Driver process, you are advised to run the **kill -9 pid** command to kill the current Driver process by hand.

## 17.7.1.4 Why Does FetchFailedException Occur When the Network Connection Is Timed out

### Question

On a large cluster of 380 nodes, run the ScalaSort test case in the HiBench test that runs the 29T data, and configure Executor as **--executor-cores 4**. The following abnormality is displayed:

```
org.apache.spark.shuffle.FetchFailedException: Failed to connect to /192.168.114.12:23242
    at
org.apache.spark.storage.ShuffleBlockFetcherIterator.throwFetchFailedException(ShuffleBlockFetcherIterator.scala:321)
    at org.apache.spark.storage.ShuffleBlockFetcherIterator.next(ShuffleBlockFetcherIterator.scala:306)
    at org.apache.spark.storage.ShuffleBlockFetcherIterator.next(ShuffleBlockFetcherIterator.scala:51)
    at scala.collection.Iterator$$anon$11.next(Iterator.scala:328)
    at scala.collection.Iterator$$anon$13.hasNext(Iterator.scala:371)
    at scala.collection.Iterator$$anon$11.hasNext(Iterator.scala:327)
    at org.apache.spark.util.CompletionIterator.hasNext(CompletionIterator.scala:32)
    at org.apache.spark.InterruptibleIterator.hasNext(InterruptibleIterator.scala:39)
    at org.apache.spark.util.collection.ExternalSorter.insertAll(ExternalSorter.scala:217)
    at org.apache.spark.shuffle.hash.HashShuffleReader.read(HashShuffleReader.scala:102)
    at org.apache.spark.rdd.ShuffledRDD.compute(ShuffledRDD.scala:90)
    at org.apache.spark.rdd.RDD.computeOrReadCheckpoint(RDD.scala:301)
    at org.apache.spark.rdd.RDD.iterator(RDD.scala:265)
    at org.apache.spark.rdd.MapPartitionsRDD.compute(MapPartitionsRDD.scala:38)
    at org.apache.spark.rdd.RDD.computeOrReadCheckpoint(RDD.scala:301)
    at org.apache.spark.rdd.RDD.iterator(RDD.scala:265)
    at org.apache.spark.rdd.MapPartitionsRDD.compute(MapPartitionsRDD.scala:38)
    at org.apache.spark.rdd.RDD.computeOrReadCheckpoint(RDD.scala:301)
    at org.apache.spark.rdd.RDD.iterator(RDD.scala:265)
    at org.apache.spark.rdd.UnionRDD.compute(UnionRDD.scala:87)
    at org.apache.spark.rdd.RDD.computeOrReadCheckpoint(RDD.scala:301)
    at org.apache.spark.rdd.RDD.iterator(RDD.scala:265)
    at org.apache.spark.scheduler.ShuffleMapTask.runTask(ShuffleMapTask.scala:73)
    at org.apache.spark.scheduler.ShuffleMapTask.runTask(ShuffleMapTask.scala:41)
    at org.apache.spark.scheduler.Task.run(Task.scala:87)
    at org.apache.spark.executor.Executor$TaskRunner.run(Executor.scala:213)
    at java.util.concurrent.ThreadPoolExecutor.runWorker(ThreadPoolExecutor.java:1142)
    at java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:617)
    at java.lang.Thread.run(Thread.java:745)
Caused by: java.io.IOException: Failed to connect to /192.168.114.12:23242
    at org.apache.spark.network.client.TransportClientFactory.createClient(TransportClientFactory.java:214)
    at org.apache.spark.network.client.TransportClientFactory.createClient(TransportClientFactory.java:167)
    at org.apache.spark.network.netty.NettyBlockTransferService$$anon
$1.createAndStart(NettyBlockTransferService.scala:91)
    at org.apache.spark.network.shuffle.RetryingBlockFetcher.fetchAllOutstanding(RetryingBlockFetcher.java:
140)
    at org.apache.spark.network.shuffle.RetryingBlockFetcher.access$200(RetryingBlockFetcher.java:43)
    at org.apache.spark.network.shuffle.RetryingBlockFetcher$1.run(RetryingBlockFetcher.java:170)
    at java.util.concurrent.Executors$RunnableAdapter.call(Executors.java:511)
    at java.util.concurrent.FutureTask.run(FutureTask.java:266)
    ... 3 more
Caused by: java.net.ConnectException: Connection timed out: /192.168.114.12:23242
    at sun.nio.ch.SocketChannelImpl.checkConnect(Native Method)
    at sun.nio.ch.SocketChannelImpl.finishConnect(SocketChannelImpl.java:717)
    at io.netty.channel.socket.nio.NioSocketChannel.doFinishConnect(NioSocketChannel.java:224)
    at io.netty.channel.nio.AbstractNioChannel$AbstractNioUnsafe.finishConnect(AbstractNioChannel.java:
289)
    at io.netty.channel.nio.NioEventLoop.processSelectedKey(NioEventLoop.java:528)
    at io.netty.channel.nio.NioEventLoop.processSelectedKeysOptimized(NioEventLoop.java:468)
    at io.netty.channel.nio.NioEventLoop.processSelectedKeys(NioEventLoop.java:382)
    at io.netty.channel.nio.NioEventLoop.run(NioEventLoop.java:354)
    at io.netty.util.concurrent.SingleThreadEventExecutor$2.run(SingleThreadEventExecutor.java:111)
    ... 1 more
```

## Answer

When an application is run, configure the Executor parameter as **--executor-cores 4**. The degree of parallelism (DOP) is high in a single process, resulting in that the IO is highly occupied and the task works slowly.

```
16/02/26 10:04:53 INFO TaskSetManager: Finished task 2139.0 in stage 1.0 (TID 151149) in 376455 ms on 10-196-115-2 (694/153378)
```

Because running a single task takes more than 6 minutes. The network connection is timed out and the running task fails.

Set the number of cores as 1, which is **--executor-cores 1**. A task is executed smoothly in proper time (within 15s).

```
16/02/29 02:24:46 INFO TaskSetManager: Finished task 59564.0 in stage 1.0 (TID 208574) in 15088 ms on 10-196-115-6 (59515/153378)
```

Therefore, to process the task of network connection timed out and avoid such error, you can reduce the core number of a single Executor.

### 17.7.1.5 How to Configure Event Queue Size If Event Queue Overflows?

#### Question

How to configure the event queue size if the following Driver log information is displayed indicating that the event queue overflows?

- Common applications  
Dropping SparkListenerEvent because no remaining room in event queue.  
This likely means one of the SparkListeners is too slow and cannot keep up with the rate at which tasks are being started by the scheduler.
- Spark Streaming applications  
Dropping StreamingListenerEvent because no remaining room in event queue.  
This likely means one of the StreamingListeners is too slow and cannot keep up with the rate at which events are being started by the scheduler.

#### Answer

1. Stop the application. Set the configuration option **spark.event.listener.logEnable** in the Spark configuration file **spark-defaults.conf** to **true**. And set the configuration option **spark.eventQueue.size** to **1000W**. If you need to control the logging rate (in milliseconds), also change the value of the configuration option **spark.event.listener.logRate**.

By default, the logging rate is 1000 ms, which means that one log is printed out every 1000 ms.

2. Start the application.

The following log information is displayed, including the event consumption rate, event production rate, and **MaxSize** (maximum size of messages in the queue).

```
INFO LiveListenerBus: [SparkListenerBus]:16044 events are consumed in 5000 ms.  
INFO LiveListenerBus: [SparkListenerBus]:51381 events are produced in 5000 ms, eventQueue still has 86417 events, MaxSize: 171764.
```

3. Change the value of the configuration option **spark.eventQueue.size** in the Spark configuration file **spark-defaults.conf** based on the **MaxSize** in the log information.

For example, if **MaxSize** is 250000, the appropriate message queue size is 300000.

### 17.7.1.6 What Can I Do If the `getApplicationReport` Exception Is Recorded in Logs During Spark Application Execution and the Application Does Not Exit for a Long Time?

#### Question

During Spark application execution, if the driver fails to connect to ResourceManager, the following error is reported and it does not exit for a long time. What can I do?

```
16/04/23 15:31:44 INFO RetryInvocationHandler: Exception while invoking getApplicationReport of class ApplicationClientProtocolPBClientImpl over 37 after 1 fail over attempts. Trying to fail over after sleeping for 44160ms.
java.net.ConnectException: Call From vm1/192.168.39.30 to vm1:8032 failed on connection exception: java.net.ConnectException: Connection refused; For more details see: http://wiki.apache.org/hadoop/ConnectionRefused
```

#### Answer

In Spark, there is a scheduled thread that listens to the status of ApplicationMaster by connecting to ResourceManager. The connection to the ResourceManager times out. As a result, the preceding error is reported and the system keeps trying to connect to the ResourceManager. In the ResourceManager, the number of retry times is limited. By default, the number of retry times is 30 and the retry interval is about 30 seconds. The preceding error is reported during each retry. The driver exits only after the number of times is exceeded.

**Table 17-79** describes the retry-related configuration items in the ResourceManager.

**Table 17-79** Parameter description

Parameter	Description	Default Value
<code>yarn.resourcemanager.connect.max-wait.ms</code>	Maximum waiting time for connecting to the ResourceManager.	900000
<code>yarn.resourcemanager.connect.retry-interval.ms</code>	Interval for reconnecting to the ResourceManager.	30000

Number of retries (**`yarn.resourcemanager.connect.max-wait.ms`**/**`yarn.resourcemanager.connect.retry-interval.ms`**) = Maximum waiting time for connecting to the ResourceManager/Interval for reconnecting to the ResourceManager

On the Spark client, modify the **`conf/yarn-site.xml`** file to add and configure **`yarn.resourcemanager.connect.max-wait.ms`** and **`yarn.resourcemanager.connect.retry-interval.ms`**. In this way, the number of retry times can be changed, and the Spark application can exit in advance.

## 17.7.1.7 What Can I Do If "Connection to ip:port has been quiet for xxx ms while there are outstanding requests" Is Reported When Spark Executes an Application and the Application Ends?

### Question

When Spark executes an application, an error similar to the following is reported and the application ends. What can I do?

```
2016-04-20 10:42:00,557 | ERROR | [shuffle-server-2] | Connection to 10-91-8-208/10.18.0.115:57959 has
been quiet for 180000 ms while there are outstanding requests. Assuming connection is dead; please adju
st spark.network.timeout if this is wrong. |
org.apache.spark.network.server.TransportChannelHandler.userEventTriggered(TransportChannelHandler.java:
128)
2016-04-20 10:42:00,558 | ERROR | [shuffle-server-2] | Still have 1 requests outstanding when connection
from 10-91-8-208/10.18.0.115:57959 is closed | org.apache.spark.network.client.TransportResponseHandl
er.channelUnregistered(TransportResponseHandler.java:102)
2016-04-20 10:42:00,562 | WARN | [yarn-scheduler-ask-am-thread-pool-160] | Error sending message
[message = DoShuffleClean(application_1459995017785_0108,319)] in 1 attempts |
org.apache.spark.Logging$class
s.logWarning(Logging.scala:92)
java.io.IOException: Connection from 10-91-8-208/10.18.0.115:57959 closed
    at
    org.apache.spark.network.client.TransportResponseHandler.channelUnregistered(TransportResponseHandler.j
ava:104)
    at
    org.apache.spark.network.server.TransportChannelHandler.channelUnregistered(TransportChannelHandler.jav
a:94)
    at
    io.netty.channel.AbstractChannelHandlerContext.invokeChannelUnregistered(AbstractChannelHandlerContext.j
ava:158)
    at
    io.netty.channel.AbstractChannelHandlerContext.fireChannelUnregistered(AbstractChannelHandlerContext.ja
va:144)
    at
    io.netty.channel.ChannelInboundHandlerAdapter.channelUnregistered(ChannelInboundHandlerAdapter.java:
53)
    at
    io.netty.channel.AbstractChannelHandlerContext.invokeChannelUnregistered(AbstractChannelHandlerContext.j
ava:158)
    at
    io.netty.channel.AbstractChannelHandlerContext.fireChannelUnregistered(AbstractChannelHandlerContext.ja
va:144)
    at
    io.netty.channel.ChannelInboundHandlerAdapter.channelUnregistered(ChannelInboundHandlerAdapter.java:
53)
    at
    io.netty.channel.AbstractChannelHandlerContext.invokeChannelUnregistered(AbstractChannelHandlerContext.j
ava:158)
    at
    io.netty.channel.AbstractChannelHandlerContext.fireChannelUnregistered(AbstractChannelHandlerContext.ja
va:144)
    at
    io.netty.channel.ChannelInboundHandlerAdapter.channelUnregistered(ChannelInboundHandlerAdapter.java:
53)
    at
    io.netty.channel.AbstractChannelHandlerContext.invokeChannelUnregistered(AbstractChannelHandlerContext.j
ava:158)
    at
    io.netty.channel.AbstractChannelHandlerContext.fireChannelUnregistered(AbstractChannelHandlerContext.ja
va:144)
    at
    io.netty.channel.DefaultChannelPipeline.fireChannelUnregistered(DefaultChannelPipeline.java:739)
    at io.netty.channel.AbstractChannel$AbstractUnsafe$8.run(AbstractChannel.java:659)
    at io.netty.util.concurrent.SingleThreadEventExecutor.runAllTasks(SingleThreadEventExecutor.java:357)
    at io.netty.channel.nio.NioEventLoop.run(NioEventLoop.java:357)
    at io.netty.util.concurrent.SingleThreadEventExecutor$2.run(SingleThreadEventExecutor.java:111)
    at java.lang.Thread.run(Thread.java:745)
```

```
2016-04-20 10:42:00,573 | INFO | [dispatcher-event-loop-14] | Starting task 177.0 in stage 1492.0 (TID 1996351, linux-254, PROCESS_LOCAL, 2106 bytes) | org.apache.spark.Logging$class.logInfo(Logging.scala:59)
2016-04-20 10:42:00,574 | INFO | [task-result-getter-0] | Finished task 85.0 in stage 1492.0 (TID 1996259) in 191336 ms on linux-254 (106/3000) | org.apache.spark.Logging$class.logInfo(Logging.scala:59)
2016-04-20 10:42:00,811 | ERROR | [Yarn application state monitor] | Yarn application has already exited with state FINISHED! | org.apache.spark.Logging$class.logError(Logging.scala:75)
```

## Answer

Symptom: The value of **spark.rpc.io.connectionTimeout** is less than the value of **spark.rpc.askTimeout**. In full GC or network delay scenarios, when the channel reaches the expiration time and still receives no response, the channel is terminated. When detecting that the channel is terminated, the AM considers the driver as disconnected, and the entire application is stopped.

Solution: Set the parameter in the **spark-defaults.conf** file on the Spark client by running the **set** command. During parameter configuration, ensure that the channel expiration time (**spark.rpc.io.connectionTimeout**) is greater than or equal to the RPC response timeout (**spark.rpc.askTimeout**).

**Table 17-80** Parameter description

Parameter	Description	Default Value
spark.rpc.askTimeout	RPC response timeout. If this parameter is not set, the value of <b>spark.network.timeout</b> is used by default.	120s

### 17.7.1.8 Why Do Executors Fail to be Removed After the NodeManager Is Shut Down?

#### Question

If the NodeManager is shut down with the Executor dynamic allocation enabled, the Executors on the node where the NodeManager is shut down fail to be removed from the driver page after the idle time expires.

#### Answer

When the ResourceManager detects that the NodeManager is shut down, the driver has requested to kill Executors due to idle time expiry. However, the Executors cannot actually be killed because the NodeManager is shut down. The driver cannot detect the LOST events of these Executors and does not remove Executors from its Executor list. Therefore, the Executors are not removed from the driver page. This phenomenon is normal after the YARN NodeManager is shut down. The Executors will be removed after the NodeManager restarts.

### 17.7.1.9 What Can I Do If the Message "Password cannot be null if SASL is enabled" Is Displayed?

#### Question

ExternalShuffle is enabled for the application that runs Spark. Task loss occurs in the application because the message "java.lang.NullPointerException: Password cannot be null if SASL is enabled" is displayed. The following shows some key logs:

```
2016-05-13 12:05:27.093 | WARN | [task-result-getter-2] | Lost task 98.0 in stage 22.1 (TID 193603, linux-173, 2): FetchFailed(BlockManagerId(13, 172.168.100.13, 27337), org.apache.spark.shuffle.FetchFailedException: java.lang.NullPointerException: Password cannot be null if SASL is enabled
at org.apache.spark.project.guava.base.Preconditions.checkNotNull(Preconditions.java:208)
at org.apache.spark.network.sasl.SparkSaslServer.encodePassword(SparkSaslServer.java:196)
at org.apache.spark.network.sasl.SparkSaslServer$DigestCallbackHandler.handle(SparkSaslServer.java:166)
at com.sun.security.sasl.digest.DigestMD5Server.validateClientResponse(DigestMD5Server.java:589)
at com.sun.security.sasl.digest.DigestMD5Server.evaluateResponse(DigestMD5Server.java:244)
at org.apache.spark.network.sasl.SparkSaslServer.response(SparkSaslServer.java:110)
at org.apache.spark.network.sasl.SaslRpcHandler.receive(SaslRpcHandler.java:100)
at org.apache.spark.network.server.TransportRequestHandler.processRpcRequest(TransportRequestHandler.java:128)
at org.apache.spark.network.server.TransportRequestHandler.handle(TransportRequestHandler.java:99)
at org.apache.spark.network.server.TransportChannelHandler.channelRead0(TransportChannelHandler.java:104)
```

#### Answer

The cause is that NodeManager restarts. When ExternalShuffle is used, Spark uses NodeManager to transmit shuffle data. Therefore, the memory of NodeManager may be seriously insufficient.

In the FusionInsight of the current version, the default memory of NodeManager is only 1 GB. When the data volume of Spark tasks is large (greater than 1 TB), the memory is severely insufficient and the message response is slow. As a result, the FusionInsight health check determines that the NodeManager process exits and forcibly restarts the NodeManager, causing the preceding problem.

#### Solution

Adjust the memory of the NodeManager. If the data volume is large (greater than 1 TB), the memory of NodeManager must be greater than 4 GB.

### 17.7.1.10 What Should I Do If the Message "Failed to CREATE\_FILE" Is Displayed in the Restarted Tasks When Data Is Inserted Into the Dynamic Partition Table?

#### Question

When inserting data into the dynamic partition table, a large number of shuffle files are damaged due to the disk disconnection, node error, and the like. In this case, why the message **Failed to CREATE\_FILE** is displayed in the restarted tasks?

```
2016-06-25 15:11:31,323 | ERROR | [Executor task launch worker-0] | Exception in task 15.0 in stage 10.1 (TID 1258) | org.apache.spark.Logging$class.logError(Logging.scala:96)
org.apache.hadoop.hive.ql.metadata.HiveException:
org.apache.hadoop.ipc.RemoteException(org.apache.hadoop.hdfs.protocol.AlreadyBeingCreatedException):
Failed to CREATE_FILE /user/hive/warehouse/testdb.db/we
b_sales/.hive-staging_hive_2016-06-25_15-09-16_999_8137121701603617850-1/-ext-10000/_temporary/0/
_temporary/attempt_201606251509_0010_m_000015_0/ws_sold_date=1999-12-17/part-00015 for
DFSCClient_attempt_2016
06251509_0010_m_000015_0_353134803_151 on 10.1.1.5 because this file lease is currently owned by
DFSCClient_attempt_201606251509_0010_m_000015_0_-848353830_156 on 10.1.1.6
```

## Answer

The last step of inserting data into the dynamic partition table is to read shuffle files and then write the data to the mapped partition files.

After a large number of shuffle files are damaged, a large number of tasks fail, causing the restart of jobs. Before the restart of jobs, Spark closes the handles that write table partition files. However, the HDFS cannot process the scenario of batch tasks closing handles. After tasks restart next time, the handles are not released in a timely manner on the NameNode. As a result, the message **Failed to CREATE\_FILE** is displayed.

This error only occurs when a large number of shuffle files are damaged. The tasks will restart after the error occurs and the restart can be completed within milliseconds.

### 17.7.1.11 Why Tasks Fail When Hash Shuffle Is Used?

#### Question

When Hash shuffle is used to run a job that consists of 1000000 map tasks x 100000 reduce tasks, run logs report many message failures and Executor heartbeat timeout, leading to task failures. Why does this happen?

#### Answer

During the shuffle process, Hash shuffle just writes the data of different reduce partitions to their respective disk files according to hash results without sorting the data.

If there are many reduce partitions, a large number of disk files will be generated. In your case,  $10^{11}$  shuffle files, that is,  $1000000 * 100000$  shuffle files, will be generated. The sheer number of disk files will have a great impact on the file read and write performance. In addition, the operations such as sorting and compressing will consume a large amount of temporary memory space because a large number of file handles are open, presenting great challenges to memory management and garbage collection and incurring the possibility that the Executor fails to respond to Driver.


Sort shuffle, instead of Hash shuffle, is recommended to run a job.

### 17.7.1.12 What Can I Do If the Error Message "DNS query failed" Is Displayed When I Access the Aggregated Logs Page of Spark Applications?

#### Question

When the `http(s)://<spark ip>:<spark port>` mode is used to access the Spark JobHistory page, if the displayed Spark JobHistory page is not the page of FusionInsight Manager (the URL of FusionInsight Manager is similar to `https://<oms ip>:20026/Spark2x/JobHistory2x/xx/`), click an application and click **AggregatedLogs**, click the logs of an executor to be viewed. An error message in [Figure 17-9](#) is displayed.

Figure 17-9 DNS query failure




## Answer

**Cause:** The domain name is not added to the **hosts** file of the Windows OS in the pop-up URL (for example, **https://<hostname>:20026/Spark2x/JobHistory2x/xx/history/application\_xxx/jobs/**). As a result, the DNS query fails and the web page cannot be displayed.

### Solution:

- You are advised to visit **Spark JobHistory** page using the FusionInsight Manager. Click the links in the blue box in **Figure 17-10**.

Figure 17-10 Spark2x page of FusionInsight Manager



- If you do not want to access the **Spark JobHistory** page using the FusionInsight Manager, change **<hostname>** in the URL to the IP address or add the domain name to the **hosts** file of the Windows OS.

### 17.7.1.13 What Can I Do If Shuffle Fetch Fails Due to the "Timeout Waiting for Task" Exception?

#### Question

When I execute a 100 TB TPC-DS test suite in the JDBCServer mode, the "Timeout waiting for task" is displayed. As a result, shuffle fetch fails, the stage keeps retrying, and the task cannot be completed properly. What can I do?

#### Answer

The ShuffleService function is used in JDBCServer mode. In the reduce phase, all executors obtain data from NodeManager. When the data volume reaches a level (more than 10 TB), the NodeManager may reach the bottleneck (ShuffleService is in the NodeManager process). As a result, some tasks for obtaining data time out. Therefore, the problem occurs.

You are advised to disable ShuffleService for Spark tasks whose data volume is greater than 10 TB. That is, set **spark.shuffle.service.enabled** in the **Spark-defaults.conf** configuration file to **false**.

### 17.7.1.14 Why Does the Stage Retry due to the Crash of the Executor?

#### Question

When I run Spark tasks with a large data volume, for example, 100 TB TPCDS test suite, why does the Stage retry due to Executor loss sometimes? The message "Executor 532 is lost rpc with driver, but is still alive, going to kill it" is displayed, indicating that the loss of the Executor is caused by a JVM crash.

The log of the key JVM crash is as follows:

```
#  
# A fatal error has been detected by the Java Runtime Environment:  
#  
# Internal Error (sharedRuntime.cpp:834), pid=241075, tid=140476258551552  
# fatal error: exception happened outside interpreter, nmethods and vtable stubs at pc  
0x00007fcda9eb8eb1
```

#### Answer

This error does not affect services. This error is caused by defects of the Oracle JVM, but not the platform code. There is the fault tolerance mechanism for Executors in Spark: the Stage retries in case of an Executor crash to ensure the success execution of tasks.

### 17.7.1.15 Why Do the Executors Fail to Register Shuffle Services During the Shuffle of a Large Amount of Data?

#### Question

When more than 50 terabytes of data is shuffled, some executors fail to register shuffle services due to timeout. The shuffle tasks then fail. Why? The error log is as follows:

```

2016-10-19 01:33:34,030 | WARN | ContainersLauncher #14 | Exception from container-launch with
container ID: container_e1452_1476801295027_2003_01_004512 and exit code: 1 |
LinuxContainerExecutor.java:397
ExitCodeException exitCode=1:
at org.apache.hadoop.util.Shell.runCommand(Shell.java:561)
at org.apache.hadoop.util.Shell.run(Shell.java:472)
at org.apache.hadoop.util.Shell$ShellCommandExecutor.execute(Shell.java:738)
at
org.apache.hadoop.yarn.server.nodemanager.LinuxContainerExecutor.launchContainer(LinuxContainerExecuto
r.java:381)
at
org.apache.hadoop.yarn.server.nodemanager.containermanager.launcher.ContainerLaunch.call(ContainerLau
ch.java:312)
at
org.apache.hadoop.yarn.server.nodemanager.containermanager.launcher.ContainerLaunch.call(ContainerLau
ch.java:88)
at java.util.concurrent.FutureTask.run(FutureTask.java:266)
at java.util.concurrent.ThreadPoolExecutor.runWorker(ThreadPoolExecutor.java:1142)
at java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:617)
at java.lang.Thread.run(Thread.java:745)
2016-10-19 01:33:34,031 | INFO | ContainersLauncher #14 | Exception from container-launch. |
ContainerExecutor.java:300
2016-10-19 01:33:34,031 | INFO | ContainersLauncher #14 | Container id:
container_e1452_1476801295027_2003_01_004512 | ContainerExecutor.java:300
2016-10-19 01:33:34,031 | INFO | ContainersLauncher #14 | Exit code: 1 | ContainerExecutor.java:300
2016-10-19 01:33:34,031 | INFO | ContainersLauncher #14 | Stack trace: ExitCodeException exitCode=1: |
ContainerExecutor.java:300
    
```

## Answer

The imported data exceeds 50 TB, which exceeds the shuffle processing capability. The shuffle may fail to respond to the registration request of an executor in a timely manner due to the heavy load.

The timeout interval for an executor to register the shuffle service is 5 seconds. The maximum number of retries is 3. This parameter is not configurable.

You are advised to increase the number of task retry times and the number of allowed executor failure times.

Configure the following parameters in the **spark-defaults.conf** file on the client: If **spark.yarn.max.executor.failures** does not exist, manually add it.

**Table 17-81** Parameter Description

Parameter	Description	Default Value
spark.task.maxFailures	Specifies task retry times.	4
spark.yarn.max.executor.failures	Specifies executor failure attempt times. Set <b>spark.dynamicAllocation.enabled</b> to <b>false</b> , to disable the dynamic allocation of executors.	numExecutors * 2, with minimum of 3

Parameter	Description	Default Value
	Specifies executor failure attempt times.  Set <b>spark.dynamicAllocation.enabled to true</b> , to enable the dynamic allocation of executors.	3

### 17.7.1.16 Why Does the Out of Memory Error Occur in NodeManager During the Execution of Spark Applications

#### Question

During the execution of Spark applications, if the YARN External Shuffle service is enabled and there are too many shuffle tasks, the **java.lang.OutOfMemoryError: Direct buffer Memory** error occurs, indicating insufficient memory. The error log is as follows:

```
2016-12-06 02:01:00,768 | WARN | shuffle-server-38 | Exception in connection from /192.168.101.95:53680
| TransportChannelHandler.java:79
io.netty.handler.codec.DecoderException: java.lang.OutOfMemoryError: Direct buffer memory
    at io.netty.handler.codec.ByteToMessageDecoder.channelRead(ByteToMessageDecoder.java:153)
    at
io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:
333)
    at
io.netty.channel.AbstractChannelHandlerContext.fireChannelRead(AbstractChannelHandlerContext.java:319)
    at io.netty.channel.DefaultChannelPipeline.fireChannelRead(DefaultChannelPipeline.java:787)
    at io.netty.channel.nio.AbstractNioByteChannel$NioByteUnsafe.read(AbstractNioByteChannel.java:130)
    at io.netty.channel.nio.NioEventLoop.processSelectedKey(NioEventLoop.java:511)
    at io.netty.channel.nio.NioEventLoop.processSelectedKeysOptimized(NioEventLoop.java:468)
    at io.netty.channel.nio.NioEventLoop.processSelectedKeys(NioEventLoop.java:382)
    at io.netty.channel.nio.NioEventLoop.run(NioEventLoop.java:354)
    at io.netty.util.concurrent.SingleThreadEventExecutor$2.run(SingleThreadEventExecutor.java:116)
    at java.lang.Thread.run(Thread.java:745)
Caused by: java.lang.OutOfMemoryError: Direct buffer memory
    at java.nio.Bits.reserveMemory(Bits.java:693)
    at java.nio.DirectByteBuffer.<init>(DirectByteBuffer.java:123)
    at java.nio.ByteBuffer.allocateDirect(ByteBuffer.java:311)
    at io.netty.buffer.PoolArena$DirectArena.newChunk(PoolArena.java:434)
    at io.netty.buffer.PoolArena.allocateNormal(PoolArena.java:179)
    at io.netty.buffer.PoolArena.allocate(PoolArena.java:168)
    at io.netty.buffer.PoolArena.reallocate(PoolArena.java:277)
    at io.netty.buffer.PooledByteBuf.capacity(PooledByteBuf.java:108)
    at io.netty.buffer.AbstractByteBuf.ensureWritable(AbstractByteBuf.java:251)
    at io.netty.buffer.AbstractByteBuf.writeBytes(AbstractByteBuf.java:849)
    at io.netty.buffer.AbstractByteBuf.writeBytes(AbstractByteBuf.java:841)
    at io.netty.buffer.AbstractByteBuf.writeBytes(AbstractByteBuf.java:831)
    at io.netty.handler.codec.ByteToMessageDecoder.channelRead(ByteToMessageDecoder.java:146)
    ... 10 more
```

#### Answer

In the Shuffle Service of YARN, the number of started threads are twice of the number of available CPU cores. The default size of direct buffer memory is 128

MB. If there are too many shuffle tasks connected at the same time, the direct buffer memory allocated to each thread service is insufficient. For example, if there are 40 CPU cores and there are 80 threads started by the Shuffle Service of YARN, the direct buffer memory allocated to each thread is less than 2 MB.

To solve this problem, increase the directory buffer memory based on the number of CPU cores in NodeManager. For example, if there are 40 of CPU cores, increase the direct buffer memory to 512 MB, that is, configure the **GC\_OPTS** parameter of NodeManager as follows:

`-XX:MaxDirectMemorySize=512M`

 **NOTE**

By default, `-XX:MaxDirectMemorySize` is not configured in the **GC\_OPTS** parameter. To configure it, you need to add it to the **GC\_OPTS** parameter as a custom option.

To configure the **GC\_OPTS** parameter, log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Services > Yarn > Configurations**, click **All Configurations**, and choose **NodeManager > System**, and then modify the **GC\_OPTS** parameter.

**Table 17-82** Parameter description

Parameter	Description	Default Value
GC_OPTS	The GC parameter of YARN NodeManger.	128M

### 17.7.1.17 Why Does the Realm Information Fail to Be Obtained When SparkBench is Run on HiBench for the Cluster in Security Mode?

#### Question

Execution of the sparkbench task (for example, Wordcount) of HiBench6 fails. The bench.log indicates that the Yarn task fails to be executed. The failure information displayed on the Yarn UI is as follows:

```
Exception in thread "main" org.apache.spark.SparkException: Unable to load YARN support
at org.apache.spark.deploy.SparkHadoopUtil$.liftedTree$1$1(SparkHadoopUtil.scala:390)
at org.apache.spark.deploy.SparkHadoopUtil$.yarn$lzycompute(SparkHadoopUtil.scala:385)
at org.apache.spark.deploy.SparkHadoopUtil$.yarn(SparkHadoopUtil.scala:385)
at org.apache.spark.deploy.SparkHadoopUtil$.get(SparkHadoopUtil.scala:410)
at org.apache.spark.deploy.yarn.ApplicationMaster$.main(ApplicationMaster.scala:796)
at org.apache.spark.deploy.yarn.ExecutorLauncher$.main(ApplicationMaster.scala:821)
at org.apache.spark.deploy.yarn.ExecutorLauncher.main(ApplicationMaster.scala)
Caused by: java.lang.IllegalArgumentException: Can't get Kerberos realm
at org.apache.hadoop.security.HadoopKerberosName.setConfiguration(HadoopKerberosName.java:65)
at org.apache.hadoop.security.UserGroupInformation.initialize(UserGroupInformation.java:288)
at org.apache.hadoop.security.UserGroupInformation.setConfiguration(UserGroupInformation.java:336)
at org.apache.spark.deploy.SparkHadoopUtil.<init>(SparkHadoopUtil.scala:51)
at org.apache.spark.deploy.yarn.YarnSparkHadoopUtil.<init>(YarnSparkHadoopUtil.scala:49)
at sun.reflect.NativeConstructorAccessorImpl.newInstance0(Native Method)
at sun.reflect.NativeConstructorAccessorImpl.newInstance(NativeConstructorAccessorImpl.java:62)
at sun.reflect.DelegatingConstructorAccessorImpl.newInstance(DelegatingConstructorAccessorImpl.java:45)
at java.lang.reflect.Constructor.newInstance(Constructor.java:423)
at java.lang.Class.newInstance(Class.java:442)
at org.apache.spark.deploy.SparkHadoopUtil$.liftedTree$1$1(SparkHadoopUtil.scala:387)
... 6 more
```

```
Caused by: java.lang.reflect.InvocationTargetException
at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:62)
at sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:43)
at java.lang.reflect.Method.invoke(Method.java:498)
at org.apache.hadoop.security.authentication.util.KerberosUtil.getDefaultRealm(KerberosUtil.java:88)
at org.apache.hadoop.security.HadoopKerberosName.setConfiguration(HadoopKerberosName.java:63)
... 16 more
Caused by: KrbException: Cannot locate default realm
at sun.security.krb5.Config.getDefaultRealm(Config.java:1029)
... 22 more
```

## Answer

In C80SPC200 and later, the file stored in the **/etc/krb5.conf** directory is no longer replaced during cluster installation. Instead, the file is stored in the corresponding path on the client through parameter configurations, and HiBench does not reference the client configuration file. Solution: Use the file stored in the **/opt/client/KrbClient/kerberos/var/krb5kdc/krb5.conf** directory on the client to overwrite that in the **/etc/krb5.conf** directories of all nodes. Make a backup before the overwriting.

## 17.7.2 Spark SQL and DataFrame

### 17.7.2.1 What Do I have to Note When Using Spark SQL ROLLUP and CUBE?

#### Question

Suppose that there is a table src(d1, d2, m) with the following data:

```
1 a 1
1 b 1
2 b 2
```

The results for statement "select d1, sum(d1) from src group by d1, d2 with rollup" are shown as below:

```
NULL 0
1 2
2 2
1 1
1 1
2 2
```

Why the first line of the above results is (NULL,0), rather than (NULL,4)?

#### Answer

When conducting the rollup and cube operation, we usually perform the dimension-based analysis and what we need is the measurement result, so we would not conduct aggregation operation on the dimension.

Suppose that there is a table src(d1, d2, m), so the statement 1 "select d1, sum(m) from src group by d1, d2 with rollup" conducts the rollup operation on the dimension d1 and d2 to compute the result of m. It has actual business meaning, and its results are in line with the expectation. However, the statement 2 "select d1, sum(d1) from src group by d1, d2 with rollup" cannot be explained from the business perspective. For the statement 2, the result for all aggregations (sum/avg/max/min) is 0.

**NOTE**

Only when there is an aggregation operation for fields in "group by" in the rollup and cube operation, the result is 0. For non-rollup and non-cube operations, the result will be in line with the expectation.

### 17.7.2.2 Why Spark SQL Is Displayed as a Temporary Table in Different Databases?

#### Question

Why temporary tables of the previous database are displayed after the database is switched?

1. Create a temporary DataSource table, for example:

```
create temporary table ds_parquet
using org.apache.spark.sql.parquet
options(path '/tmp/users.parquet');
```

2. Switch to another database, and run **show tables**. The temporary table created in the previous table is displayed.

```
0: jdbc:hive2://192.168.169.84:22550/default> show tables;
+-----+-----+
| tableName | isTemporary |
+-----+-----+
| ds_parquet | true      |
| cmb_tbl_carbon | false    |
+-----+-----+
2 rows selected (0.109 seconds)
0: jdbc:hive2://192.168.169.84:22550/default>
```


#### Answer

The table management hierarchy of Spark is shown in [Figure 17-11](#). The lowest layer stores all temporary DataSource tables. There is no such concept as database at this layer. DataSource tables are visible in various databases.

The MetaStore of Hive is located at the upper layer. This layer distinguishes among databases. In each database, there are two types of Hive table, permanent and temporary. Therefore, Spark supports data tables of the same name at three layers.

During query, SparksSQL first checks for temporary Spark tables, then temporary Hive tables in the current database, and at last the permanent tables in the current database.

**Figure 17-11** Spark table management hierarchy



When a session quits, temporary tables related to the user operation are automatically deleted. Manual deletion of temporary files is not recommended.

When deleting temporary files, use the same priority as that for query. The priorities are temporary Spark table, temporary Hive table, and permanent Hive table ranging from high to low. If you want to directly delete Hive tables but not temporary Spark tables, you can directly use the ***drop table dbName.TableName*** command.

### 17.7.2.3 How to Assign a Parameter Value in a Spark Command?

#### Question

Is it possible to assign parameter values through Spark commands, in addition to through a user interface or a configuration file?

#### Answer

Spark configuration options can be defined either in a configuration file or in Spark commands.

To assign a parameter value, run the `--conf` command on a Spark client. The parameter value takes effect immediately after the command is run.

The command format is `--conf + parameter name + parameter value`. Example command:

```
--conf spark.eventQueue.size=50000
```

### 17.7.2.4 What Directory Permissions Do I Need to Create a Table Using SparkSQL?

#### Question

The following error information is displayed when a new user creates a table using SparkSQL:

```
0: jdbc:hive2://192.168.169.84:22550/default> create table testACL(c string);
Error: org.apache.spark.sql.execution.QueryExecutionException: FAILED: Execution Error, return code 1 from
org.apache.hadoop.hive.ql.exec.DDLTask. MetaException(message:Got exception:
org.apache.hadoop.security.AccessControlException
Permission denied: user=testACL, access=EXECUTE, inode="/user/hive/warehouse/
testacl":spark:hadoop:drwxrwx---
    at
org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.checkAccessAcl(FSPermissionChecker.java:
403)
    at org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.check(FSPermissionChecker.java:306)
    at org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.checkTraverse(FSPermissionChecker.java:
259)
    at
org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.checkPermission(FSPermissionChecker.java:
205)
    at
org.apache.hadoop.hdfs.server.namenode.FSPermissionChecker.checkPermission(FSPermissionChecker.java:
190)
    at org.apache.hadoop.hdfs.server.namenode.FSDirectory.checkPermission(FSDirectory.java:1710)
    at
org.apache.hadoop.hdfs.server.namenode.FSDirStatAndListingOp.getFileInfo(FSDirStatAndListingOp.java:109)
    at org.apache.hadoop.hdfs.server.namenode.FSNamesystem.getFileInfo(FSNamesystem.java:3762)
```

```
at org.apache.hadoop.hdfs.server.namenode.NameNodeRpcServer.getFileInfo(NameNodeRpcServer.java:1014)
at
org.apache.hadoop.hdfs.protocolPB.ClientNamenodeProtocolServerSideTranslatorPB.getFileInfo(ClientNamenodeProtocolServerSideTranslatorPB.java:853)
at org.apache.hadoop.hdfs.protocol.proto.ClientNamenodeProtocolProtos$ClientNamenodeProtocol$2.callBlockingMethod(ClientNamenodeProtocolProtos.java)
at org.apache.hadoop.ipc.ProtobufRpcEngine$Server$ProtoBufRpcInvoker.call(ProtobufRpcEngine.java:616)
at org.apache.hadoop.ipc.RPC$Server.call(RPC.java:973)
at org.apache.hadoop.ipc.Server$Handler$1.run(Server.java:2089)
at org.apache.hadoop.ipc.Server$Handler$1.run(Server.java:2085)
at java.security.AccessController.doPrivileged(Native Method)
at javax.security.auth.Subject.doAs(Subject.java:422)
at org.apache.hadoop.security.UserGroupInformation.doAs(UserGroupInformation.java:1675)
at org.apache.hadoop.ipc.Server$Handler.run(Server.java:2083)
) (state=,code=0)
```

## Answer

When you create a table using Spark SQL, the interface of Hive is called by the underlying system and a directory named after the table will be created in the **/user/hive/warehouse** directory. Therefore, you must have the permissions to read, write, and execute the **/user/hive/warehouse** directory or the group permission of Hive.

The **/user/hive/warehouse** is specified by the `hive.metastore.warehouse.dir` parameter.

### 17.7.2.5 Why Do I Fail to Delete the UDF Using Another Service?

## Question

Why do I fail to delete the UDF using another service, for example, delete the UDF created by Hive using Spark SQL.

## Answer

The UDF can be created using any of the following services:

1. Hive client.
2. JDBCServer API. You can connect JDBCServer to Spark Beeline or JDBC client code, and run SQL statements to create the UDF.
3. spark-sql.

The scenarios in which the UDF failed to be deleted may be as follows:

- If you use Spark Beeline to delete the UDF created by other services, you must restart the JDBCServer before the deletion. Otherwise, the deletion fails. If you use spark-sql to delete the UDF created by other services, you must restart the spark-sql before the deletion. Otherwise, the deletion fails.

Cause: After the UDF is created, if the JDBCServer or the spark-sql has not been restarted, the newly created UDF will not be saved by the FunctionRegistry object in the thread where Spark locates. As a result, the UDF failed to be deleted.

Solution: Restart the JDBCServer and spark-sql of the Spark client and delete the UDF.

- When creating UDF on the Hive client, the **add jar** command (e.g. **add jar /opt/test/two\_udfs.jar**) is used to add the **.jar** package instead of specifying the path of **.jar** package in creating UDF statement. As a result, the **ClassNotFound** error occurs when you use other services to delete the UDF.  
Cause: When you use a service to delete the UDF, the service will load the class that corresponds to the UDF to obtain the UDF. However, the **.jar** package is added by the **add jar** command and jar package does not exist in the classpath of other services. As a result, the **ClassNotFound** error occurs and the UDF failed to be deleted.  
Solution: The UDF created using the preceding approach must be deleted using the same approach. No other approaches are allowed.

### 17.7.2.6 Why Cannot I Query Newly Inserted Data in a Parquet Hive Table Using SparkSQL?

#### Question

Why cannot I query newly inserted data in a parquet Hive table using SparkSQL? This problem occurs in the following scenarios:

1. For partitioned tables and non-partitioned tables, after data is inserted on the Hive client, the latest inserted data cannot be queried using SparkSQL.
2. After data is inserted into a partitioned table using SparkSQL, if the partition information remains unchanged, the newly inserted data cannot be queried using SparkSQL.

#### Answer

To improve Spark performance, parquet metadata is cached. When the parquet table is updated by Hive or another means, the cached metadata remains unchanged, resulting in SparkSQL failing to query the newly inserted data.

For a parquet Hive partition table, if the partition information remains unchanged after data is inserted, the cached metadata is not updated. As a result, the newly inserted data cannot be queried by SparkSQL.

To solve the query problem, update metadata before starting a Spark SQL query.

***REFRESH TABLE table\_name;***

*table\_name* indicates the name of the table to be updated. The table must exist. Otherwise, an error is reported.

When the query statement is executed, the latest inserted data can be obtained.

For details, visit <https://spark.apache.org/docs/3.1.1/sql-programming-guide.html#metadata-refreshing>.

### 17.7.2.7 How to Use Cache Table?

#### Question

What is cache table used for? Which point should I pay attention to while using cache table?

## Answer

Spark SQL caches tables into memory so that data can be directly read from memory instead of disks, reducing memory overhead due to disk reads.

Note that cached tables consume Executor's memory. This means that caching large or many tables compromises Executor's stability even if compressed storage has been used to reduce memory overhead as much as possible.

If it is no longer necessary to accelerate data query by means of cache table, run the following command to uncache tables to free up memory:

```
uncache table table_name
```

### NOTE

The Storage tab page of the Spark Driver user interface displays the cached tables.

## 17.7.2.8 Why Are Some Partitions Empty During Repartition?

### Question

During the repartition operation, the number of blocks (**spark.sql.shuffle.partitions**) is set to 4,500, and the number of keys used by repartition exceeds 4,000. It is expected that data corresponding to different keys can be allocated to different partitions. However, only 2,000 partitions have data, and data corresponding to different keys is allocated to the same partition.

### Answer

This is normal.

The partition to which data is distributed is obtained by performing a modulo operation on hashcode of a key. Different hashcodes may have the same modulo result. In this case, data is distributed to the same partition, as a result, some partitions do not have data, and some partitions have data corresponding to multiple keys.

You can adjust the value of **spark.sql.shuffle.partitions** to adjust the cardinality during modulo operation and improve the unevenness of data blocks. After multiple verifications, it is found that the effect is good when the parameter is set to a prime number or an odd number.

Configure the following parameters in the **spark-defaults.conf** file on the Driver client.

**Table 17-83** Parameter Description

Parameter	Description	Default Value
spark.sql.shuffle.partitions	Number of shuffle data blocks during the shuffle operation.	200

### 17.7.2.9 Why Does 16 Terabytes of Text Data Fails to Be Converted into 4 Terabytes of Parquet Data?

#### Question

When the default configuration is used, 16 terabytes of text data fails to be converted into 4 terabytes of parquet data, and the error information below is displayed. Why?

```
Job aborted due to stage failure: Task 2866 in stage 11.0 failed 4 times, most recent failure: Lost task 2866.6 in stage 11.0 (TID 54863, linux-161, 2): java.io.IOException: Failed to connect to /10.16.1.11:23124 at org.apache.spark.network.client.TransportClientFactory.createClient(TransportClientFactory.java:214) at org.apache.spark.network.client.TransportClientFactory.createClient(TransportClientFactory.java:167) at org.apache.spark.network.netty.NettyBlockTransferService$$anon$1.createAndStart(NettyBlockTransferService.scala:92)
```

[Table 17-84](#) lists the default configuration.

**Table 17-84** Parameter Description

Parameter	Description	Default Value
spark.sql.shuffle.partitions	Number of shuffle data blocks during the shuffle operation.	200
spark.shuffle.sasl.timeout	Timeout interval of SASL authentication for the shuffle operation. Unit: second	120s
spark.shuffle.io.connectionTimeout	Timeout interval for connecting to a remote node during the shuffle operation. Unit: second	120s
spark.network.timeout	Timeout interval for all network connection operations. Unit: second	360s

#### Answer

The current data volume is 16 TB, but the number of partitions is only 200. As a result, each task is overloaded and the preceding problem occurs.

To solve the preceding problem, you need to adjust the parameters.

- Increase the number of partitions to divide the task into smaller ones.
- Increase the timeout interval during task execution.

Configure the following parameters in the **spark-defaults.conf** file on the client:

**Table 17-85** Parameter Description

Parameter	Description	Recommended Value
spark.sql.shuffle.partitions	Number of shuffle data blocks during the shuffle operation.	4501
spark.shuffle.sasl.timeout	Timeout interval of SASL authentication for the shuffle operation. Unit: second	2000s
spark.shuffle.io.connectionTimeout	Timeout interval for connecting to a remote node during the shuffle operation. Unit: second	3000s
spark.network.timeout	Timeout interval for all network connection operations. Unit: second	360s

### 17.7.2.10 Why the Operation Fails When the Table Name Is TABLE?

#### Question

When the table name is set to **table**, why the error information similar to the following is displayed after the **drop table table** command or other command is run?

```
16/07/12 18:56:29 ERROR SparkSQLDriver: Failed in [drop table table]
java.lang.RuntimeException: [1.1] failure: identifier expected
table
^
at scala.sys.package$.error(package.scala:27)
at org.apache.spark.sql.catalyst.SqlParserTrait$class.parseTableIdentifier(SqlParser.scala:56)
at org.apache.spark.sql.catalyst.SqlParser$.parseTableIdentifier(SqlParser.scala:485)
```

#### Answer

The word table is a keyword of Spark SQL statements and must not be used as a table name.

### 17.7.2.11 Why Is a Task Suspended When the ANALYZE TABLE Statement Is Executed and Resources Are Insufficient?

#### Question

When the **analyze table** statement is executed using spark-sql, the task is suspended and the information below is displayed. Why?

```
spark-sql> analyze table hivetable2 compute statistics;
Query ID = root_20160716174218_90f55869-000a-40b4-a908-533f63866fed
Total jobs = 1
Launching Job 1 out of 1
```



### 17.7.2.13 Why Do I Fail to Modify MetaData by Running the Hive Command?

#### Question

When do I fail to modify the metadata in the datasource and Spark on HBase table by running the Hive command?

#### Answer

The current Spark version does not support modifying the metadata in the datasource and Spark on HBase tables by running the Hive command.

### 17.7.2.14 Why Is "RejectedExecutionException" Displayed When I Exit Spark SQL?

#### Question

After successfully running Spark tasks with large data volume, for example, 2-TB TPCDS test suite, why is the abnormal stack information "RejectedExecutionException" displayed sometimes? The log is as follows:

```
16/07/16 10:19:56 ERROR TransportResponseHandler: Still have 2 requests outstanding when connection from linux-192/10.1.1.5:59250 is closed
java.util.concurrent.RejectedExecutionException: Task scala.concurrent.impl.CallbackRunnable@5fc1ab rejected from java.util.concurrent.ThreadPoolExecutor@52fa7e19[Terminated, pool size = 0, active threads = 0, queued tasks = 0, completed tasks = 3025]
```

#### Answer

When Spark SQL is closed, the application and the message channel are closed. If there are unprocessed messages, the connection should be closed to rectify the exception. If the thread pool inside Scala is closed, the abnormal stack information "RejectedExecutionException" is displayed. This abnormal stack information will not be displayed if the thread pool inside Scala is not closed.

The error occurs when the application is successfully run and closed. Therefore, the error will not affect the services.

### 17.7.2.15 What Should I Do If the JDBCServer Process is Mistakenly Killed During a Health Check?

#### Question

During a health check, if the concurrent statements exceed the threshold of the thread pool, the health check statements fail to be executed, the health check program times out, and the Spark JDBCServer process is killed.

#### Answer

There are two thread pools HiveServer2-Handler-Pool and HiveServer2-Background-Pool in the current JDBCServer. The HiveServer2-Handler-Pool is used to connect sessions and the HiveServer2-Background-Pool is used to run Spark SQL statements.

The current health check mechanism establishes a session connection and runs the health check command **HEALTHCHECK** in the thread of the session to check the health condition of the Spark JDBCServer. Therefore, one thread must be reserved for the HiveServer2-Handler-Pool respectively to connect sessions and run statements for the health check. Otherwise, the session connection and statement running will fail and the Spark JDBCServer will be killed because it is mistakenly considered unhealthy. For example, if there are 100 threads in the HiveServer2-Handler-Pool respectively, a maximum of 99 sessions can be connected.


### 17.7.2.16 Why No Result Is found When 2016-6-30 Is Set in the Date Field as the Filter Condition?

#### Question

Why no result is found when 2016-6-30 is set in the date field as the filter condition?

As shown in the following figure, `trx_dte_par` in the `select count (*) from trxfintrx2012 a where trx_dte_par='2016-6-30'` statement is a date field. However, no search result is found when the filter condition is where `trx_dte_par='2016-6-30'`. Search results are found only when the filter condition is where `trx_dte_par='2016-06-30'`.

Figure 17-13 Example



```
0: jdbc:hive2://ha-cluster/default> select count(*)
0: jdbc:hive2://ha-cluster/default>   from TRXFINTRX2012 a
0: jdbc:hive2://ha-cluster/default>   where trx_dte_par = '2016-6-30';
+-----+
| _c0   |
+-----+
| 0     |
+-----+
1 row selected (0.498 seconds)
0: jdbc:hive2://ha-cluster/default> select count(*)
0: jdbc:hive2://ha-cluster/default>   from TRXFINTRX2012 a
0: jdbc:hive2://ha-cluster/default>   where trx_dte_par = '2016-06-30';
+-----+
| _c0   |
+-----+
| 8520808 |
+-----+
1 row selected (15.788 seconds)
```

#### Answer

If a data string of the date type is present in Spark SQL statements, the Spark SQL will search the matching character string without checking the date format. In this case, if the date format in the SQL statement is incorrect, the query will fail. For example, if the data format is `yyyy-mm-dd`, then no search results matching `'2016-6-30'` will be found.

### 17.7.2.17 Why Does the "--hivevar" Option I Specified in the Command for Starting spark-beeline Fail to Take Effect?

#### Question

Why does the `--hivevar` option I specified in the command for starting spark-beeline fail to take effect?

In the V100R002C60 version, if I use the `--hivevar <VAR_NAME>=<var_value>` option to define a variable in the command for starting spark-beeline, no error is reported in spark-beeline. However, if the variable `<VAR_NAME>` is used in SQL, the variable cannot be parsed and the `<VAR_NAME>` exception is reported.

For example:

1. Run the following command to start the spark-beeline:  
`spark-beeline --hivevar <VAR_NAME>=<var_value>`
2. After spark-beeline is started successfully, I run the SQL statements `DROP TABLE ${VAR_NAME}` in spark-beeline. The `VAR_NAME` exception occurs.

#### Answer

In the V100R002C60 version, the `--hivevar <VAR_NAME>=<var_value>` feature of Hive is not supported in Spark because multi-session management function is added. Therefore, the `--hivevar` option in the command for starting spark-beeline is invalid.

### 17.7.2.18 Why Does the "Permission denied" Exception Occur When I Create a Temporary Table or View in Spark-beeline?

#### Question

In normal mode, when I create a temporary table or view in spark-beeline, the error message "Permission denied" is displayed, indicating that I have no permissions on the HDFS directory. The error log information is as follows:

```
org.apache.hadoop.security.AccessControlException Permission denied: user=root, access=EXECUTE,
inode="/tmp/spark/sparkhive-scratch/omm/e579a76f-43ed-4014-8a54-1072c07ceeff/_tmp_space.db/
52db1561-60b0-4e7d-8a25-c2eaa44850a9":omm:hadoop:drwx-----
```

#### Answer

In normal mode, if you run the spark-beeline command as a non-omm user, **root** user for example, without specifying the `-n` parameter, your account is still the root user. After spark-beeline is started, a new HDFS directory is created by JDBCServer. In the current version of DataSight, the user that starts the JDBCServer is **omm**. In versions earlier than DataSight V100R002C30, the user is **root**. Therefore, the owner of the HDFS directory is **omm** and the group is **hadoop**. The HDFS directory is used when you create a temporary table or view in spark-beeline and the user **root** is a common user in HDFS and has no permissions on the directory of user **omm**. As a result, the "Permission denied" exception occurs.

In normal mode, only user **omm** can create a temporary table or view. To solve this problem, you can specify the `-n omm` option for user **omm** when starting

spark-beeline. In this way, you have the permissions to perform operations on the HDFS directory.

### 17.7.2.19 Why Is the "Code of method ... grows beyond 64 KB" Error Message Displayed When I Run Complex SQL Statements?

#### Question

When I run a complex SQL statement, for example, SQL statements with multiple layers of nesting statements and a single layer statement contains a large number of logic clauses such as case when, an error message indicating that the code of a certain method exceeds 64 KB is displayed. The log is as follows:

```
java.util.concurrent.ExecutionException: java.lang.Exception: failed to compile:  
org.codehaus.janino.JaninoRuntimeException: Code of method "(Lorg/apache/spark/sql/catalyst/expressions/  
GeneratedClass$SpecificUnsafeProjection;Lorg/apache/spark/sql/catalyst/InternalRow;)V" of class  
"org.apache.spark.sql.catalyst.expressions.GeneratedClass$SpecificUnsafeProjection" grows beyond 64 KB
```

#### Answer

If Project Tungsten is enabled, Spark will use codegen method to generate Java code for part of execution plan. However, each function in Java code to be compiled by JDK must be less than 64 KB. If complex SQL statements are run, the function in the Java code generated by codegen may exceed 64 KB, causing compilation failure.

To solve the problem, go to the **spark-defaults.conf** file on the client and set the **spark.sql.codegen.wholeStage** parameter to **false** to disable Project Tungsten.

### 17.7.2.20 Why Is Memory Insufficient if 10 Terabytes of TPCDS Test Suites Are Consecutively Run in Beeline/JDBCServer Mode?

#### Question

When the driver memory is set to 10 GB and the 10 TB TPCDS test suites are continuously run in Beeline/JDBCServer mode, SQL statements fail to be executed due to insufficient driver memory. Why?

#### Answer

By default, 1000 UI data records of jobs and stages are reserved in the memory.

The function of overflowing UI data to disks has been added to optimize large clusters. The overflow condition is that the size of UI data in each stage reaches the minimum threshold 5 MB. If the number of tasks in each stage is small, the size of UI data in the stage may not reach the threshold. As a result, the UI data in the stage is cached in the memory until the number of UI data records reaches the upper limit (1000 by default). Only then the old UI data is cleared from the memory.

Therefore, before the old UI data is cleared, the UI data occupies a large amount of memory. As a result, the driver memory is insufficient when 10 terabytes of TPCDS test suites are executed.

Workaround:

- Set **spark.ui.retainedJobs** and **spark.ui.retainedStages** based on service requirements to specify the number of UI data records of jobs and stages to be reserved. For details, see [Table 17-15](#) in [Common Parameters](#).
- If a large amount of UI data of jobs and stages needs to be reserved, increase the memory of the driver by setting the **spark.driver.memory** parameter. For details, see [Table 17-12](#) in [Common Parameters](#).

### 17.7.2.21 Why Are Some Functions Not Available when Another JDBCServer Is Connected?

#### Question

##### Scenario 1

I set up permanent functions using the **add jar** statement. After Beeline connects to different JDBCServer or JDBCServer is restarted, I have to run the **add jar** statement again.

Figure 17-14 Error information in scenario 1

```
0: jdbc:hive2://192.168.91.247:23040/default> create function a1 as 'com.huawei.smartcare.dac.hive.udf.UDFArrayGreaterEqual';
+-----+
| result |
+-----+
no rows selected (0.222 seconds)
0: jdbc:hive2://192.168.91.247:23040/default> SELECT test.a1(array(1, 2, 3), array(2));
+-----+
| _c0 |
+-----+
| true |
+-----+
1 row selected (8.282 seconds)
0: jdbc:hive2://192.168.91.247:23040/default> Closing: 0: jdbc:hive2://192.168.91.247:24002,192.168.154.81:24002,192.168.8.27:24002;serviceDiscoveryMode=zookee
p-auth-conf;auth=KERBEROS;principal=spark/hadoop.hadoop.com@HADOOP.COM;
100-106-121-140:/opt/hadoopclient # ./spark-beeline
It's running the fl spark-beeline, it calls /opt/hadoopclient/Spark/spark/bin/beeline
and helps to connect to the JDBCServer automatically
Connecting to jdbc:hive2://192.168.91.247:24002,192.168.154.81:24002,192.168.8.27:24002;serviceDiscoveryMode=zookeeper;zookeeperNamespace=sparkthriftserver;sa
doop.hadoop.com@HADOOP.COM;
2017-06-15 08:17:55,495 | WARN | Thread-2 | TGT refresh thread time adjusted from : Thu Jun 15 05:59:42 GMT+08:00 2017 to : Thu Jun 15 08:18:55 GMT+08:00 2017
fresh interval (60 seconds) from now. | org.apache.zookeeper.Login$.run(Login.java:177)
2017-06-15 08:17:56,743 | WARN | main | unable to load native-hadoop library for your platform... using builtin-java classes where applicable | org.apache.had
ader.java:62)
2017-06-15 08:17:56,773 | WARN | TGT Renewer for sparkuser@HADOOP.COM | Exception encountered while running the renewal command. Aborting renew thread. ExitCo
l requested option while renewing credentials
| org.apache.hadoop.security.UserGroupInformation$.run(UserGroupInformation.java:946)
connected to: spark SQL (version)
Driver: Hive JDBC (version 1.2.1.spark)
Transaction isolation: TRANSACTION_REPEATABLE_READ
Beeline version 1.2.1.spark by Apache Hive
[INFO] unable to bind key for unsupported operation: backward-delete-word
[INFO] unable to bind key for unsupported operation: backward-delete-word
[INFO] unable to bind key for unsupported operation: down-history
[INFO] unable to bind key for unsupported operation: up-history
[INFO] unable to bind key for unsupported operation: up-history
[INFO] unable to bind key for unsupported operation: down-history
[INFO] unable to bind key for unsupported operation: up-history
[INFO] unable to bind key for unsupported operation: down-history
[INFO] unable to bind key for unsupported operation: up-history
[INFO] unable to bind key for unsupported operation: down-history
[INFO] unable to bind key for unsupported operation: up-history
[INFO] unable to bind key for unsupported operation: down-history
0: jdbc:hive2://192.168.8.27:23040/default> SELECT test.a1(array(1, 2, 3), array(2));
Error: org.apache.spark.SparkException: Unable to load UDF class (state=,code=0)
0: jdbc:hive2://192.168.8.27:23040/default> set role admin;
+-----+
| key | value |
+-----+
| role admin | |
+-----+
1 row selected (0.465 seconds)
0: jdbc:hive2://192.168.8.27:23040/default> add jar /home/smartcare-udf-0.0.1-SNAPSHOT.jar;
+-----+
| result |
+-----+
| 0 |
+-----+
```

##### Scenario 2

The **show functions** statement can be used to query functions, but not obtain functions. The reason is that connected JDBC node does not contain jar packages of the corresponding path. However, after I add corresponding **.jar** packages, the **show functions** statement can be used to obtain functions.

Figure 17-15 Error information in scenario 2

```

-----+-----+
| function |
-----+-----+
stddev_pop
stddev_samp
str_to_map
string
struct
substr
substring
substring_index
sum
tan
tanh
test.a1
timestamp
tryint
to_date
to_unix_timestamp
to_utc_timestamp
translate
trim
trunc
ucase
unbase64
unhex
unix_timestamp
upper
var_pop
var_samp
variance
weekofyear
when
window
xpath
0: jdbc:hive2://192.168.8.27:22550/default> use test;
-----+-----+
| Result |
-----+-----+
No rows selected (0.038 seconds)
0: jdbc:hive2://192.168.8.27:22550/default> SELECT test.a1(array(1, 2, 3), array(2));
Error: org.apache.spark.sql.AnalysisException: undefined function: 'test.a1'. This function is neither a registered temporary function nor a permanent function.
0: jdbc:hive2://192.168.8.27:22550/default> show functions;
-----+-----+
| function |
-----+-----+

```

## Answer

### Scenario 1

The **add jar** statement is used to load jars to the jarClassLoader of the JDBCServer connected currently. The **add jar** statement is not shared by different JDBCServer. After the JDBCServer restarts, new jarClassLoader is created. So the add jar statement needs to be run again.

There are two methods to add jar packages: You can run the **spark-sql --jars /opt/test/two\_udfs.jar** statement to add the jar package during the startup of the Spark SQL process; or run the **add jar /opt/test/two\_udfs.jar** statement to add the jar package after the Spark SQL process is started. Note that the path following the add jar statement can be a local path or an HDFS path.

### Scenario 2

The show functions statement is used to obtain all functions in the current database from the external catalog. If functions are used in SQL, thriftJDBC-server loads .jar files related to the function.

If .jar files do not exist, the function cannot obtain corresponding .jar files. Therefore, the corresponding .jar files need to be added.

## 17.7.2.22 Why Does an Exception Occur When I Drop Functions Created Using the Add Jar Statement?

### Question

- Problem 1  
Why can I successfully drop functions without the drop function permission?  
The specific scenario is as follows:
  - a. On the FusionInsight Manager console, I added the user1 user and granted the admin permission to the user1 user.



In addition, the default value of `hive.exec.drop.ignorenonexistent` in Hive is `true`. Therefore, if function does not exist, no exception is reported when the deleting function operation is performed. As a result, no exception is reported when you delete a non-existing function and perform drop operation even though you do not have the drop function permission. When you run the show function command after restarting the session and connecting to the JDBCServer instance that creates the function, the command output indicates that the function still exists. This problem is inherited from the Hive community.

- Solution  
Before running drop function command, run the add jar command. In this way, the drop operation succeeds only when you are granted the drop function permission, and the dropped function will not be displayed if you run the show function command.

### 17.7.2.23 Why Does Spark2x Have No Access to DataSource Tables Created by Spark1.5?

#### Question

When Spark2x accesses the DataSource table created by Spark1.5, a message is displayed indicating that schema information cannot be obtained. As a result, the table cannot be accessed. Why?

#### Answer

- Cause analysis:  
This is because the formats of the DataSource table information stored in Spark2x and Spark1.5 are inconsistent. Spark 1.5 divides schema information into multiple parts and uses `path.park.0` as the key for storage. Spark 1.5 reads information from each part and reassembles the information into complete one. Spark2x directly uses the corresponding key to obtain the corresponding information. In this case, when Spark2x reads the DataSource table created by Spark1.5, the information corresponding to the key cannot be read. As a result, the DataSource table information fails to be parsed.  
When processing Hive tables, Spark2x and Spark1.5 use the same storage mode. Therefore, Spark2x can directly read tables created by Spark1.5.
- Workaround:  
In Spark2x, create a foreign table to point to the actual data in the Spark1.5 table. In this way, the DataSource table created by Spark1.5 can be read in Spark2x. In addition, after Spark1.5 updates data, Spark2x can detect the change. The reverse is also true. In this way, Spark2x can access the DataSource table created by Spark1.5.

### 17.7.2.24 Why Does Spark-beeline Fail to Run and Error Message "Failed to create ThriftService instance" Is Displayed?

#### Question

Why does "Failed to create ThriftService instance" occur when spark beeline fails to run?

Beeline logs are as follows:

```
Error: Failed to create ThriftService instance (state=,code=0)
Beeline version 1.2.1.spark by Apache Hive
[INFO] Unable to bind key for unsupported operation: backward-delete-word
[INFO] Unable to bind key for unsupported operation: backward-delete-word
[INFO] Unable to bind key for unsupported operation: down-history
[INFO] Unable to bind key for unsupported operation: up-history
[INFO] Unable to bind key for unsupported operation: up-history
[INFO] Unable to bind key for unsupported operation: down-history
[INFO] Unable to bind key for unsupported operation: up-history
[INFO] Unable to bind key for unsupported operation: down-history
[INFO] Unable to bind key for unsupported operation: up-history
[INFO] Unable to bind key for unsupported operation: down-history
[INFO] Unable to bind key for unsupported operation: up-history
[INFO] Unable to bind key for unsupported operation: down-history
beeline>
```

In addition, the "Timed out waiting for client to connect" error log is generated on the JDBCServer. The details are as follows:

```
2017-07-12 17:35:11,284 | INFO | [main] | Will try to open client transport with JDBC Uri:
jdbc:hive2://192.168.101.97:23040/default;principal=spark/hadoop.<System domain name>@<System
domain name>;healthcheck=true;saslQop=auth-conf;auth=KERBEROS;user.principal=spark/hadoop.<System
domain name>@<System domain name>;user.keytab=${BIGDATA_HOME}/FusionInsight_HD_8.1.2.2/install/
FusionInsight-Spark-3.1.1/keytab/spark/JDBCServer/spark.keytab |
org.apache.hive.jdbc.HiveConnection.openTransport(HiveConnection.java:317)
2017-07-12 17:35:11,326 | INFO | [HiveServer2-Handler-Pool: Thread-92] | Client protocol version:
HIVE_CLI_SERVICE_PROTOCOL_V8 |
org.apache.proxy.service.ThriftCLIProxyService.OpenSession(ThriftCLIProxyService.java:554)
2017-07-12 17:35:49,790 | ERROR | [HiveServer2-Handler-Pool: Thread-113] | Timed out waiting for client
to connect.
Possible reasons include network issues, errors in remote driver or the cluster has no available resources, etc.
Please check YARN or Spark driver's logs for further information. |
org.apache.proxy.service.client.SparkClientImpl.<init>(SparkClientImpl.java:90)
java.util.concurrent.ExecutionException: java.util.concurrent.TimeoutException: Timed out waiting for client
connection.
at io.netty.util.concurrent.AbstractFuture.get(AbstractFuture.java:37)
at org.apache.proxy.service.client.SparkClientImpl.<init>(SparkClientImpl.java:87)
at org.apache.proxy.service.client.SparkClientFactory.createClient(SparkClientFactory.java:79)
at org.apache.proxy.service.SparkClientManager.createSparkClient(SparkClientManager.java:145)
at org.apache.proxy.service.SparkClientManager.createThriftServerInstance(SparkClientManager.java:160)
at org.apache.proxy.service.ThriftServiceManager.getOrCreateThriftServer(ThriftServiceManager.java:182)
at org.apache.proxy.service.ThriftCLIProxyService.OpenSession(ThriftCLIProxyService.java:596)
at org.apache.hive.service.cli.thrift.TCLIService$Processor$OpenSession.getResult(TCLIService.java:1257)
at org.apache.hive.service.cli.thrift.TCLIService$Processor$OpenSession.getResult(TCLIService.java:1242)
at org.apache.thrift.ProcessFunction.process(ProcessFunction.java:39)
at org.apache.thrift.TBaseProcessor.process(TBaseProcessor.java:39)
at org.apache.hadoop.hive.thrift.HadoopThriftAuthBridge$Server
$TUGIAssumingProcessor.process(HadoopThriftAuthBridge.java:696)
at org.apache.thrift.server.TThreadPoolServer$WorkerProcess.run(TThreadPoolServer.java:286)
at java.util.concurrent.ThreadPoolExecutor.runWorker(ThreadPoolExecutor.java:1142)
at java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:617)
at java.lang.Thread.run(Thread.java:748)
Caused by: java.util.concurrent.TimeoutException: Timed out waiting for client connection.
```

## Answer

This problem occurs when the network is unstable. When a timed-out exception occurs in beeline, Spark does not attempt to reconnect to beeline. Therefore, you need to restart spark-beeline for reconnection.

### 17.7.3 Spark Streaming

### 17.7.3.1 Streaming Task Prints the Same DAG Log Twice

#### Question

When using the Spark Streaming, execute the following command to run the program:

```
spark-submit -master yarn-client --conf spark.logLineage=true --jars $SPARK_HOME/jars/streamingClient/kafka-clients-0.8.2.1.jar,$SPARK_HOME/jars/streamingClient/kafka_2.11-0.8.2.1.jar,$SPARK_HOME/jars/streamingClient/spark-streaming-kafka-0-8_2.11-2.1.0.jar --class com.xxx.bigdata.spark.examples.FemaleInfoCollectionPrint /opt/female/SparkStreamingJavaExample-1.0.jar <checkpoint> <batchTime> <windowTime> <topics> <brokers>
```

In case of no Kafka data input, the RDD DAG structure displayed in a log is printed twice in a batch. The relevant log is as follows:

```
-----
Time: 1491447950000 ms
-----
17/04/06 11:06:00 INFO SparkContext: RDD's recursive dependencies:
(2) MapPartitionsRDD[49] at filter at FemaleInfoCollectionPrint.java:111 []
| MapPartitionsRDD[48] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 []
| CoGroupedRDD[47] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 []
| MapPartitionsRDD[38] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 []
|   CachedPartitions: 2; MemorySize: 8.0 B; ExternalBlockStoreSize: 0.0 B; DiskSize: 0.0 B
| ReliableCheckpointRDD[40] at print at FemaleInfoCollectionPrint.java:123 []
| ShuffledRDD[36] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 []
|   CachedPartitions: 2; MemorySize: 8.0 B; ExternalBlockStoreSize: 0.0 B; DiskSize: 0.0 B
+- (5) MapPartitionsRDD[35] at map at FemaleInfoCollectionPrint.java:81 []
| MapPartitionsRDD[34] at filter at FemaleInfoCollectionPrint.java:81 []
| MapPartitionsRDD[33] at map at FemaleInfoCollectionPrint.java:72 []
| MapPartitionsRDD[32] at map at FemaleInfoCollectionPrint.java:63 []
| KafkaRDD[31] at createDirectStream at FemaleInfoCollectionPrint.java:63 []
| ShuffledRDD[46] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 []
+- (5) MapPartitionsRDD[45] at map at FemaleInfoCollectionPrint.java:81 []
| MapPartitionsRDD[44] at filter at FemaleInfoCollectionPrint.java:81 []
| MapPartitionsRDD[43] at map at FemaleInfoCollectionPrint.java:72 []
| MapPartitionsRDD[42] at map at FemaleInfoCollectionPrint.java:63 []
| KafkaRDD[41] at createDirectStream at FemaleInfoCollectionPrint.java:63 []
17/04/06 11:06:00 INFO SparkContext: RDD's recursive dependencies: (2) MapPartitionsRDD[48] at
reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 [Memory Serialized 1x Replicated]
|   CachedPartitions: 1; MemorySize: 4.0 B; ExternalBlockStoreSize: 0.0 B; DiskSize: 0.0 B
| CoGroupedRDD[47] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 [Memory
Serialized 1x Replicated]
| MapPartitionsRDD[38] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 [Memory
Serialized 1x Replicated]
|   CachedPartitions: 2; MemorySize: 8.0 B; ExternalBlockStoreSize: 0.0 B; DiskSize: 0.0 B
| ReliableCheckpointRDD[40] at print at FemaleInfoCollectionPrint.java:123 [Memory Serialized 1x
Replicated]
| ShuffledRDD[36] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 [Memory Serialized
1x Replicated]
|   CachedPartitions: 2; MemorySize: 8.0 B; ExternalBlockStoreSize: 0.0 B; DiskSize: 0.0 B
+- (5) MapPartitionsRDD[35] at map at FemaleInfoCollectionPrint.java:81 [Memory Serialized 1x
Replicated]
| MapPartitionsRDD[34] at filter at FemaleInfoCollectionPrint.java:81 [Memory Serialized 1x Replicated]
| MapPartitionsRDD[33] at map at FemaleInfoCollectionPrint.java:72 [Memory Serialized 1x Replicated]
| MapPartitionsRDD[32] at map at FemaleInfoCollectionPrint.java:63 [Memory Serialized 1x Replicated]
| KafkaRDD[31] at createDirectStream at FemaleInfoCollectionPrint.java:63 [Memory Serialized 1x
Replicated]
| ShuffledRDD[46] at reduceByKeyAndWindow at FemaleInfoCollectionPrint.java:98 [Memory Serialized
1x Replicated]
|   CachedPartitions: 1; MemorySize: 4.0 B; ExternalBlockStoreSize: 0.0 B; DiskSize: 0.0 B
+- (5) MapPartitionsRDD[45] at map at FemaleInfoCollectionPrint.java:81 [Memory Serialized 1x
Replicated]
| MapPartitionsRDD[44] at filter at FemaleInfoCollectionPrint.java:81 [Memory Serialized 1x Replicated]
| MapPartitionsRDD[43] at map at FemaleInfoCollectionPrint.java:72 [Memory Serialized 1x Replicated]
| MapPartitionsRDD[42] at map at FemaleInfoCollectionPrint.java:63 [Memory Serialized 1x Replicated]
```

```
| KafkaRDD[41] at createDirectStream at FemaleInfoCollectionPrint.java:63 [Memory Serialized 1x  
Replicated]  
-----  
Time: 1491447960000 ms  
-----
```

## Answer

The application uses the print operator in the DStream to display results. The print operator invokes the take operator in the RDD to perform underlying calculations.

The take operator triggers calculations for many times in units of partitions.

In this case, the take operator has two partitions by default because of the shuffle operation. The Spark first calculates the first partition. Fewer than 10 results are obtained because there is no data input. Then, the second calculation is triggered. As a result, the same RDD DAG log is printed twice.

To solve this problem, change the print operator to for each (collect) in the codes.

### 17.7.3.2 What Can I Do If Spark Streaming Tasks Are Blocked?

#### Question

After a Spark Streaming task is run and data is input, no processing result is displayed. Open the web page to view the Spark job execution status. The following figure shows that two jobs are waiting to be executed but cannot be executed successfully.

**Figure 17-18 Active Jobs**

Active Jobs (2)

Job Id	Description	Submitted	Duration	Stages: Succeeded/Total
3	<a href="#">print at test2StreamFromKafka.scala:31</a>	2015/05/25 18:28:55	63.7 h	0/3
2	<a href="#">start at test2StreamFromKafka.scala:34</a>	2015/05/25 18:28:55	63.7 h	0/1

Check the completed jobs. Only two jobs are found, indicating that Spark Streaming does not trigger data computing tasks. (By default, Spark Streaming has two jobs that attempt to run. See the figure below.)

**Figure 17-19 Completed Jobs**

Completed Jobs (2)

Job Id	Description	Submitted	Duration	Stages: Succeeded/Total
1	<a href="#">print at test2StreamFromKafka.scala:31</a>	2015/05/25 18:28:55	0.7 s	2/2 (1 skipped)
0	<a href="#">start at test2StreamFromKafka.scala:34</a>	2015/05/25 18:28:54	1 s	2/2

## Answer

After fault locating, it is found that the number of computing cores of Spark Streaming is less than the number of receivers. As a result, after some receivers are started, no resource is available to run computing tasks. Therefore, the first task keeps waiting and subsequent tasks keep queuing. [Figure 17-18](#) is an example of two queuing tasks.

To address this problem, it is advised to check whether the number of Spark cores is greater than the number of receivers when two tasks are queuing.

 **NOTE**

Receiver is a permanent Spark job in Spark Streaming. It is common for Spark, but its life cycle is the same as that of a Spark Streaming task and occupies one computing core.

Pay attention to the relationship between the number of cores and the number of receivers in scenarios where default configurations are often used, such as debugging and testing.

### 17.7.3.3 What Should I Pay Attention to When Optimizing Spark Streaming Task Parameters?

#### Question

When Spark Streaming tasks are running, the data processing performance does not improve significantly as the number of executors increases. What should I pay attention to if I perform parameter optimization?

#### Answer

When the number of executor cores is 1, comply with the following rules to optimize Spark Streaming running parameters:

- The Spark task processing speed is related to the number of partitions in Kafka. When the number of partitions is less than the specified number of executors, the number of actually used executors is the same as the number of partitions, and other executors will be idle. Therefore, the number of executors must be less than or equal to the number of partitions.
- When data skew occurs on different partitions of Kafka, the executor corresponding to the partition with a large amount of data touches the glass ceiling of data processing. Therefore, when the Producer program is executed, data is sent to each partition on average to improve the processing speed.
- When partition data is evenly distributed, increasing the number of partitions and executors will improve the Spark processing speed. (When the number of partitions is the same as that of executors, the processing speed is the fastest.)
- When partition data is evenly distributed, ensure that the number of partitions is an integer multiple of the number of executors for proper allocation of resources.

### 17.7.3.4 Why Does the Spark Streaming Application Fail to Be Submitted After the Token Validity Period Expires?

#### Question

Change the validity period of the Kerberos ticket and HDFS token to 5 minutes, set **dfs.namenode.delegation.token.renew-interval** to a value less than 60 seconds, and submit the Spark Streaming application. If the token expires, the error message below is displayed, and the application exits. Why?

```
token (HDFS_DELEGATION_TOKEN token 17410 for spark2x) is expired
```

## Answer

- Possible causes:

The credential refresh thread of the ApplicationMaster process uploads the updated credential file to the HDFS based on the *token renew period multiplied by 0.75*.

In the executor process, the credential refresh thread obtains the updated credential file from the HDFS based on the time ratio of the *token renewal period multiplied by 0.8* to update the token in UserGroupInformation, preventing the token from being invalid.

When the credential refresh thread of the executor process detects that the current time is later than the credential file update time (*token renew period x 0.8*), it waits for 1 minute and then obtains the latest credential file from the HDFS to ensure that the AM has stored the updated credential file in the HDFS.

When the value of **dfs.namenode.delegation.token.renew-interval** is less than 60 seconds, the started executor detects that the current time is later than the time when the credential file is updated. One minute later, the executor obtains the latest credential file from the HDFS. However, the token is already invalid, and the task fails to be executed. Then, other executor processes retry within 1 minute. The task also fails to run on other executors. As a result, the executors that fail to run are added to the blacklist. If no executors are available, the application exits.
- Solution:

In the Spark application scenario, set **dfs.namenode.delegation.token.renew-interval** to a value greater than 80 seconds. For details about the **dfs.namenode.delegation.token.renew-interval** parameter, see [Table 17-86](#).

**Table 17-86** Parameter description

Parameter	Description	Default Value
dfs.namenode.delegation.token.renew-interval	This parameter is a server parameter. It specifies the maximum lifetime to renew a token. Unit: milliseconds.	86400000

### 17.7.3.5 Why does Spark Streaming Application Fail to Restart from Checkpoint When It Creates an Input Stream Without Output Logic?

#### Question

Spark Streaming application creates one input stream without output logic. The application fails to restart from checkpoint and an error will be shown like below:

```
17/04/24 10:13:57 ERROR Utils: Exception encountered
java.lang.NullPointerException
at org.apache.spark.streaming.dstream.DStreamCheckpointData$$anonfun$writeObject$1.apply$mcV
```

```
$sp(DStreamCheckpointData.scala:125)
at org.apache.spark.streaming.dstream.DStreamCheckpointData$$anonfun$writeObject
$1.apply(DStreamCheckpointData.scala:123)
at org.apache.spark.streaming.dstream.DStreamCheckpointData$$anonfun$writeObject
$1.apply(DStreamCheckpointData.scala:123)
at org.apache.spark.util.Utils$.tryOrIOException(Utils.scala:1195)
at org.apache.spark.streaming.dstream.DStreamCheckpointData.writeObject(DStreamCheckpointData.scala:
123)
at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:62)
at sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:43)
at java.lang.reflect.Method.invoke(Method.java:498)
at java.io.ObjectStreamClass.invokeWriteObject(ObjectStreamClass.java:1028)
at java.io.ObjectOutputStream.writeSerialData(ObjectOutputStream.java:1496)
at java.io.ObjectOutputStream.writeOrdinaryObject(ObjectOutputStream.java:1432)
at java.io.ObjectOutputStream.writeObject0(ObjectOutputStream.java:1178)
at java.io.ObjectOutputStream.defaultWriteFields(ObjectOutputStream.java:1548)
at java.io.ObjectOutputStream.defaultWriteObject(ObjectOutputStream.java:441)
at org.apache.spark.streaming.dstream.DStream$$anonfun$writeObject$1.apply$mcV$sp(DStream.scala:515)
at org.apache.spark.streaming.dstream.DStream$$anonfun$writeObject$1.apply(DStream.scala:510)
at org.apache.spark.streaming.dstream.DStream$$anonfun$writeObject$1.apply(DStream.scala:510)
at org.apache.spark.util.Utils$.tryOrIOException(Utils.scala:1195)
at org.apache.spark.streaming.dstream.DStream.writeObject(DStream.scala:510)
at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:62)
at sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:43)
at java.lang.reflect.Method.invoke(Method.java:498)
at java.io.ObjectStreamClass.invokeWriteObject(ObjectStreamClass.java:1028)
at java.io.ObjectOutputStream.writeSerialData(ObjectOutputStream.java:1496)
at java.io.ObjectOutputStream.writeOrdinaryObject(ObjectOutputStream.java:1432)
at java.io.ObjectOutputStream.writeObject0(ObjectOutputStream.java:1178)
at java.io.ObjectOutputStream.writeArray(ObjectOutputStream.java:1378)
at java.io.ObjectOutputStream.writeObject0(ObjectOutputStream.java:1174)
at java.io.ObjectOutputStream.defaultWriteFields(ObjectOutputStream.java:1548)
at java.io.ObjectOutputStream.writeSerialData(ObjectOutputStream.java:1509)
at java.io.ObjectOutputStream.writeOrdinaryObject(ObjectOutputStream.java:1432)
at java.io.ObjectOutputStream.writeObject0(ObjectOutputStream.java:1178)
at java.io.ObjectOutputStream.defaultWriteFields(ObjectOutputStream.java:1548)
at java.io.ObjectOutputStream.defaultWriteObject(ObjectOutputStream.java:441)
at org.apache.spark.streaming.DStreamGraph$$anonfun$writeObject$1.apply$mcV$sp(DStreamGraph.scala:
191)
at org.apache.spark.streaming.DStreamGraph$$anonfun$writeObject$1.apply(DStreamGraph.scala:186)
at org.apache.spark.streaming.DStreamGraph$$anonfun$writeObject$1.apply(DStreamGraph.scala:186)
at org.apache.spark.util.Utils$.tryOrIOException(Utils.scala:1195)
at org.apache.spark.streaming.DStreamGraph.writeObject(DStreamGraph.scala:186)
at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:62)
at sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:43)
at java.lang.reflect.Method.invoke(Method.java:498)
at java.io.ObjectStreamClass.invokeWriteObject(ObjectStreamClass.java:1028)
at java.io.ObjectOutputStream.writeSerialData(ObjectOutputStream.java:1496)
at java.io.ObjectOutputStream.writeOrdinaryObject(ObjectOutputStream.java:1432)
at java.io.ObjectOutputStream.writeObject0(ObjectOutputStream.java:1178)
at java.io.ObjectOutputStream.defaultWriteFields(ObjectOutputStream.java:1548)
at java.io.ObjectOutputStream.writeSerialData(ObjectOutputStream.java:1509)
at java.io.ObjectOutputStream.writeOrdinaryObject(ObjectOutputStream.java:1432)
at java.io.ObjectOutputStream.writeObject0(ObjectOutputStream.java:1178)
at java.io.ObjectOutputStream.writeObject(ObjectOutputStream.java:348)
at org.apache.spark.streaming.Checkpoint$$anonfun$serialize$1.apply$mcV$sp(Checkpoint.scala:142)
at org.apache.spark.streaming.Checkpoint$$anonfun$serialize$1.apply(Checkpoint.scala:142)
at org.apache.spark.streaming.Checkpoint$$anonfun$serialize$1.apply(Checkpoint.scala:142)
at org.apache.spark.util.Utils$.tryWithSafeFinally(Utils.scala:1230)
at org.apache.spark.streaming.Checkpoint$.serialize(Checkpoint.scala:143)
at org.apache.spark.streaming.StreamingContext.validate(StreamingContext.scala:566)
at org.apache.spark.streaming.StreamingContext.liftedTree1$1(StreamingContext.scala:612)
at org.apache.spark.streaming.StreamingContext.start(StreamingContext.scala:611)
at com.spark.test.kafka08LifoTwoInkfk$.main(kafka08LifoTwoInkfk.scala:21)
at com.spark.test.kafka08LifoTwoInkfk.main(kafka08LifoTwoInkfk.scala)
at sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method)
```

```
at sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:62)
at sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:43)
at java.lang.reflect.Method.invoke(Method.java:498)
at org.apache.spark.deploy.SparkSubmit$.org$apache$spark$deploy$SparkSubmit$
$runMain(SparkSubmit.scala:772)
at org.apache.spark.deploy.SparkSubmit$.doRunMain$1(SparkSubmit.scala:183)
at org.apache.spark.deploy.SparkSubmit$.submit(SparkSubmit.scala:208)
at org.apache.spark.deploy.SparkSubmit$.main(SparkSubmit.scala:123)
at org.apache.spark.deploy.SparkSubmit.main(SparkSubmit.scala)
```

## Answer

When Streaming Context starts, DStream checkpoint object of application should be serialized with application set to checkpoint and Dstream context will be used during this serialization.

Dstream.context is the Dstream which Streaming Context relies on to check reversely from output Stream, set the context one by one. If Spark Streaming application creates one input stream which does not have output logic, there will be no context set for the input stream. 'NullPointerException' will be reported during serialization.

Solution: If there is no input logic for the output stream in the application, delete the input stream in the code or add the relevant output logic for that input stream.

### 17.7.3.6 Why Is the Input Size Corresponding to Batch Time on the Web UI Set to 0 Records When Kafka Is Restarted During Spark Streaming Running?

#### Question

When the Kafka is restarted during the execution of the Spark Streaming application, the application cannot obtain the topic offset from the Kafka. As a result, the job fails to be generated. As shown in **Figure 17-20, 2017/05/11 10:57:00-2017/05/11 10:58:00** indicates the Kafka restart time. After the restart is successful at 10:58:00 on May,11,2017, the value of **Input Size** is **0 records**.

**Figure 17-20** On the Web UI, the **input size** corresponding to the **batch time** is **0 records**.

Completed Batches (last 9 out of 9)

Batch Time	Input Size	Scheduling Delay (?)	Processing Time (?)	Total Delay (?)	Output Ops: Succeeded/Total
2017/05/11 10:58:50	18 records	0 ms	0.4 s	0.4 s	1/1
<u>2017/05/11 10:58:40</u>	20 records	4 s	0.3 s	4 s	1/1
2017/05/11 10:58:30	20 records	14 s	0.5 s	14 s	1/1
2017/05/11 10:58:20	20 records	23 s	0.4 s	24 s	1/1
2017/05/11 10:58:10	20 records	33 s	0.5 s	33 s	1/1
<u>2017/05/11 10:58:00</u>	0 records	6 ms	43 s	43 s	1/1
<u>2017/05/11 10:57:00</u>	19 records	1 ms	0.9 s	0.9 s	1/1
2017/05/11 10:56:50	20 records	1 ms	0.6 s	0.6 s	1/1
2017/05/11 10:56:40	28 records	13 ms	5 s	5 s	1/1

## Answer

After Kafka is restarted, the application supplements the missing RDD between 10:57:00 on May 11, 2017 and 10:58:00 on May 11, 2017 based on the batch time.

Although the number of read data records displayed on the UI is **0**, the missing data is processed in the supplemented RDD. Therefore, no data loss occurs.

The data processing mechanism during the Kafka restart period is as follows:

The Spark Streaming application uses the **state** function (for example, **updateStateByKey**). After Kafka is restarted, the Spark Streaming application generates a batch task at 10:58:00 on May 11, 2017. The missing RDD between 10:57:00 on May 11, 2017 and 10:58:00 on May 11, 2017 is supplemented based on the batch time (data that is not read in Kafka before Kafka restart, which belongs to the batch before 10:57:00 on May 11, 2017).

## 17.7.4 Why the Job Information Obtained from the restful Interface of an Ended Spark Application Is Incorrect?

### Question

The job information obtained from the restful interface of an ended Spark application is incorrect: the value of **numActiveTasks** is negative, as shown in [Figure 17-21](#):

Figure 17-21 job information

```
[ {  
  "jobId" : 0,  
  "name" : "reduce at SparkPi.scala:36",  
  "submissionTime" : "2016-05-28T09:35:34.415GMT",  
  "completionTime" : "2016-05-28T09:35:35.686GMT",  
  "stageIds" : [ 0 ],  
  "status" : "SUCCEEDED",  
  "numTasks" : 2,  
  "numActiveTasks" : -1,  
  "numCompletedTasks" : 2,  
  "numSkippedTasks" : 2,  
  "numFailedTasks" : 0,  
  "numActiveStages" : 0,  
  "numCompletedStages" : 1,  
  "numSkippedStages" : 0,  
  "numFailedStages" : 0  
} ]
```

### NOTE

numActiveTasks indicates the number of active tasks.

### Answer

The job information can be obtained in either of the following methods:

- Set **spark.history.briefInfo.gather=true** and then view the brief JobHistory information.
- Visit the JobHistory2x page of Spark (URL: <https://IP:port/api/v1/<appid>/jobs/>).

The value of **numActiveTasks** in the job information is calculated from the difference between the number of SparkListenerTaskStart events and the number of SparkListenerTaskEnd events in the **eventLog** file. If some events are not recorded in the **eventLog** file, the job information obtained from the restful interface is incorrect.

## 17.7.5 Why Cannot I Switch from the Yarn Web UI to the Spark Web UI?

### Question

In FusionInsight, the Spark application is run in yarn-client mode on the client. The following error occurs during the switch from the Yarn web UI to the application web UI:

#### Error Occurred.

Problem accessing /proxy/application\_1468986660719\_0045/

Powered by Jetty://

The YARN ResourceManager log shows the following information:

```
2016-07-21 16:35:27,099 | INFO | Socket Reader #1 for port 8032 | Auth successful for mapred/hadoop.<System domain name>@<System domain name> (auth:KERBEROS) | Server.java:1388
2016-07-21 16:35:27,105 | INFO | 1526016381@qtp-1178290888-1015 | admin is accessing unchecked http://10.120.169.53:23011 which is the app master GUI of application_1468986660719_0045 owned by spark | WebAppProxyServlet.java:393
2016-07-21 16:36:02,843 | INFO | Socket Reader #1 for port 8032 | Auth successful for hive/hadoop.<System domain name>@<System domain name> (auth:KERBEROS) | Server.java:1388
2016-07-21 16:36:02,851 | INFO | Socket Reader #1 for port 8032 | Auth successful for hive/hadoop.<System domain name>@<System domain name> (auth:KERBEROS) | Server.java:1388
2016-07-21 16:36:12,163 | WARN | 1526016381@qtp-1178290888-1015 | /proxy/application_1468986660719_0045/: java.net.ConnectException: Connection timed out | Slf4jLog.java:76
2016-07-21 16:37:03,918 | INFO | Socket Reader #1 for port 8032 | Auth successful for hive/hadoop.<System domain name>@<System domain name> (auth:KERBEROS) | Server.java:1388
2016-07-21 16:37:03,926 | INFO | Socket Reader #1 for port 8032 | Auth successful for hive/hadoop.<System domain name>@<System domain name> (auth:KERBEROS) | Server.java:1388
2016-07-21 16:37:11,956 | INFO | AsyncDispatcher event handler | Updating application attempt appattempt_1468986660719_0045_000001 with final state: FINISHING, and exit status: -1000 | RMAAppAttemptImpl.java:1253
```

### Answer

On FusionInsight Manager, the IP address of the Yarn service is in the 192 network segment.

In Yarn logs, the IP address of Spark web UI read by Yarn is http://10.120.169.53:23011, which is in the 10 network segment. The IP addresses in the 192 network segment cannot communicate with those in the 10 network segment. As a result, the Spark web UI fails to be accessed.

Solution:

Log in to the client whose IP address is **10.120.169.53** and change the IP address in the **/etc/hosts** file to the IP address in the 192 network segment. Run the Spark application again. The Spark web UI is displayed.

## 17.7.6 What Can I Do If an Error Occurs when I Access the Application Page Because the Application Cached by HistoryServer Is Recycled?

### Question

An error occurs when I access a Spark application page on the HistoryServer page.

Check the HistoryServer logs. The "FileNotFoundException" exception is found. The related logs are as follows:

```
2016-11-22 23:58:03,694 | WARN | [qtp55429210-232] | /history/application_1479662594976_0001/stages/
stage/ | org.sparkproject.jetty.servlet.ServletHandler.doHandle(ServletHandler.java:628)
java.io.FileNotFoundException: ${BIGDATA_HOME}/tmp/spark/jobHistoryTemp/
blockmgr-5f1f6aca-2303-4290-9845-88fa94d78480/09/temp_shuffle_11f82aaf-e226-46dc-
b1f0-002751557694 (No such file or directory)
```

### Answer

If a Spark application with a large number of tasks is run on the HistoryServer page, the memory overflows to disk and files with the **temp\_shuffle** prefix are generated.

By default, HistoryServer caches 50 Spark applications (determined by the **spark.history.retainedApplications** configuration item). When the number of Spark applications in the memory exceeds 50, HistoryServer reclaims the first cached Spark application and clears the corresponding **temp\_shuffle** file.

When a user is viewing Spark applications to be recycled, the **temp\_shuffle** file may not be found. As a result, the current page cannot be accessed.

If the preceding problem occurs, use either of the following methods to solve the problem:

- Access the HistoryServer page of the Spark application again. The correct page information is displayed.
- If more than 50 Spark applications need to be accessed at the same time, increase the value of **spark.history.retainedApplications**.

Log in to FusionInsight Manager, choose **Cluster > Name of the desired cluster > Service > Spark2x > Configuration**, and click **All Configurations**. In the navigation tree on the left, choose **JobHistory2x > GUI**, and set parameters.

**Table 17-87** Parameter description

Parameter	Description	Default Value
spark.history.retainedApplications	Number of Spark applications cached by HistoryServer. When the number of applications to be cached exceeds the value of this parameter, HistoryServer reclaims the first cached Spark application.	50

## 17.7.7 Why Is not an Application Displayed When I Run the Application with the Empty Part File?

### Question

When I run an application with an empty part file in HDFS with the log grouping function enabled, why is not the application displayed on the homepage of JobHistory?

### Answer

On the JobHistory page, information about applications is updated only with changed sizes of part files in HDFS. If a file is read for the first time, its size is compared with 0. The file is read only when the file size is greater than 0.

When the log grouping function is enabled, if the application you run does not have jobs in running status, the part file is empty. As a result, JobHistory does not read the part file and the application information is not displayed on the JobHistory page. However, if the size of part file is changed later, the application will be displayed on JobHistory.

## 17.7.8 Why Does Spark2x Fail to Export a Table with the Same Field Name?

### Question

The following code fails to be executed on spark-shell of Spark2x:

```
val acctId = List(("49562", "Amal", "Derry"), ("00000", "Fred", "Xanadu"))
val rddLeft = sc.makeRDD(acctId)
val dfLeft = rddLeft.toDF("Id", "Name", "City")
//dfLeft.show
val acctCustId = List(("Amal", "49562", "CO"), ("Dave", "99999", "ZZ"))
val rddRight = sc.makeRDD(acctCustId)
val dfRight = rddRight.toDF("Name", "CustId", "State")
//dfRight.show
val dfJoin = dfLeft.join(dfRight, dfLeft("Id") === dfRight("CustId"), "outer")
dfJoin.show
dfJoin.repartition(1).write.format("com.databricks.spark.csv").option("delimiter", "\t").option("header", "true").option("treatEmptyValuesAsNulls", "true").option("nullValue", "").save("/tmp/outputDir")
```

### Answer

In Spark2x, the duplicate field name of the `join` statement is checked. You need to modify the code to ensure that no duplicate field exists in the saved data.

## 17.7.9 Why JRE fatal error after running Spark application multiple times?

### Question

Why JRE fatal error after running Spark application multiple times?

## Answer

When you run Spark application multiple times, JRE fatal error occurs and this is due to the problem with the Linux Kernel.

To resolve this issue, upgrade the **kernel version to 4.13.9-2.ge7d7106-default**.

## 17.7.10 "This page can't be displayed" Is Displayed When Internet Explorer Fails to Access the Native Spark2x UI

### Question

Occasionally, Internet Explorer 9, Explorer 10, or Explorer 11 fails to access the native Spark2x UI.

### Symptom

Internet Explorer 9, Explorer 10, or Explorer 11 fails to access the native Spark UI, as shown in the following figure.



Turn on TLS 1.0, TLS 1.1, and TLS 1.2 in Advanced settings and try connecting to

### Cause

Some Internet Explorer 9, Explorer 10, or Explorer 11 versions fail to handle SSL handshake issues, causing access failure.

### Solution

Google Chrome 71 and later versions and Firefox browsers 62 and later versions are recommended.

## 17.7.11 How Does Spark2x Access External Cluster Components?

### Question

There are two clusters, cluster 1 and cluster 2. How do I use Spark2x in cluster 1 to access HDFS, Hive, HBase, Solr, and Kafka components in cluster 2?

### Answer

1. Components in two clusters can access each other. However, there are the following restrictions:
  - Only one Hive MetaStore can be accessed. Specifically, Hive MetaStore in cluster 1 and Hive MetaStore in cluster 2 cannot be accessed at the same time.

- User systems in different clusters are not synchronized. When users access components in another cluster, user permission is determined by the user configuration of the peer cluster. For example, if user A of cluster 1 does not have the permissions to access the HBase meta table in cluster 1 but user A of cluster 2 can access the HBase meta table in cluster 2, user A of cluster 1 can access the HBase meta table in cluster 2.
  - To enable components in a security cluster to communicate with each other across Manager, you need to configure mutual trust.
2. The following describes how to access Hive, HBase, Solr, and Kafka components in cluster 2 as user A.

 **NOTE**

The following operations are based on the scenario where a user uses the FusionInsight client to submit the Spark2x application. If the user uses the configuration file directory, the user needs to modify the corresponding file in the configuration directory of the application and upload the configuration file to the executor.

When the HDFS and HBase clients access the server, **hostname** is used to configure the server address. Therefore, the hosts configuration of all nodes to be accessed must be saved in the **/etc/hosts** file on the client. You can add the host of the peer cluster node to the **/etc/hosts** file of the client node in advance.

- Access Hive metastore: Replace the **hive-site.xml** file in the **conf** directory of the Spark2x client in cluster 1 with the **hive-site.xml** file in the **conf** directory of the Spark2x client in cluster 2.  
After the preceding operations are performed, you can use Spark SQL to access Hive MetaStore. To access Hive table data, you need to perform the operations in [Access HDFS of two clusters at the same time](#): and set **nameservice** of the peer cluster to **LOCATION**.
- Access HBase of the peer cluster.
  - i. Configure the IP addresses and host names of all ZooKeeper nodes and HBase nodes in cluster 2 in the **/etc/hosts** file on the client node of cluster 1.
  - ii. Replace the **hbase-site.xml** file in the **conf** directory of the Spark2x client in cluster 1 with the **hbase-site.xml** file in the **conf** directory of the Spark2x client in cluster 2.
- Access Kafka: Set the address of the Kafka Broker to be accessed to the Kafka Broker address in cluster 2.
- Access Solr: Change the addresses of Solr and Zookeeper in the configuration file of Solr to be accessed to the corresponding addresses in cluster 2.
- Access HDFS of two clusters at the same time:
  - Two tokens with the same NameService cannot be obtained at the same time. Therefore, the NameServices of the HDFS in two clusters must be different. For example, one is **hacluster**, and the other is **test**.
    - 1) Obtain the following configurations from the **hdfs-site.xml** file of cluster2 and add them to the **hdfs-site.xml** file in the **conf** directory of the Spark2x client in cluster1:

**dfs.nameservices.mappings, dfs.nameservices, dfs.namenode.rpc-address.test.\*, dfs.ha.namenodes.test, and dfs.client.failover.proxy.provider.test**

The following is an example:

```
<property>
<name>dfs.nameservices.mappings</name>
<value>[{"name":"hacluster","roleInstances":["14","15"]},
{"name":"test","roleInstances":["16","17"]}]</value>
</property>
<property>
<name>dfs.nameservices</name>
<value>hacluster,test</value>
</property>
<property>
<name>dfs.namenode.rpc-address.test.16</name>
<value>192.168.0.1:8020</value>
</property>
<property>
<name>dfs.namenode.rpc-address.test.17</name>
<value>192.168.0.2:8020</value>
</property>
<property>
<name>dfs.ha.namenodes.test</name>
<value>16,17</value>
</property>
<property>
<name>dfs.client.failover.proxy.provider.test</name>
<value>org.apache.hadoop.hdfs.server.namenode.ha.ConfiguredFailoverProxyProvider
</value>
</property>
```

- 2) Modify **spark.yarn.extra.hadoopFileSystems = hdfs://test** and **spark.hadoop.hdfs.externalToken.enable = true** in the **spark-defaults.conf** configuration file under the **conf** directory on the Spark client of cluster 1.

```
spark.yarn.extra.hadoopFileSystems = hdfs://test
spark.hadoop.hdfs.externalToken.enable = true
```

- 3) In the application submission command, add the **--keytab** and **--principal** parameters and set them to the user who submits the task in cluster1.
  - 4) Use the Spark client of cluster1 to submit the application. Then, the two HDFS services can be accessed at the same time.
- Access HBase of two clusters at the same time:

- i. Modify **spark.hadoop.hbase.externalToken.enable = true** in the **spark-defaults.conf** configuration file under the **conf** directory on the Spark client of cluster 1.
- ```
spark.hadoop.hbase.externalToken.enable = true
```
- ii. When accessing HBase, you need to use the configuration file of the corresponding cluster to create a **Configuration** object for creating a **Connection** object.
  - iii. In an MRS cluster, tokens of multiple HBase services can be obtained at the same time to solve the problem that the executor cannot access HBase. The method is as follows:

Assume that you need to access HBase of the current cluster and HBase of cluster2. Save the **hbase-site.xml** file of cluster2 in a compressed package named **external\_hbase\_conf\*\*\***, and use **--archives** to specify the compressed package when submitting the command.

## 17.7.12 Why Does the Foreign Table Query Fail When Multiple Foreign Tables Are Created in the Same Directory?

### Question

Assume there is a data file path named `/test_data_path`. User A creates a foreign table named **tableA** for the directory, and user B creates a foreign table named **tableB** for the directory. When user B performs the insert operation on **tableB**, user A fails to query data using **tableA** and the error "Permission denied" is displayed.

### Answer

After user B performs the insert operation on **tableB**, a new data file is generated in the foreign table path and the file belongs to user B. When user A queries data using **tableA**, all files in the foreign table directory are read. In this case, the query fails because user A does not have the read permissions on the file generated by user B.

This problem also occurs in other scenarios. For example, the **inset overwrite** operation will also duplicate other table files in this directory.

Due to the Spark SQL implementation mechanism, check restrictions in this scenario will lead to inconsistency and performance deterioration. Therefore, no restriction is added in this scenario, and this method is not recommended.

## 17.7.13 What Should I Do If the Native Page of an Application of Spark2x JobHistory Fails to Display During Access to the Page

### Question

After a Spark application that contains a job with millions of tasks. After the application creation is complete, if you access the native page of the application in JobHistory, the native page of the application can be displayed after a long time. If the native page cannot be displayed within 10 minutes, Error information will be generated for the Proxy.

**Figure 17-22** Error information example

#### Proxy Error

```
The proxy server received an invalid response from an upstream server.  
The proxy server could not handle the request GET /Spark2x/JobHistory/77/history/application_1558516306528_00021/jobs/  
Reason: Error reading from remote server
```

### Answer

When you switch to the native page of an application on the JobHistory page, JobHistory needs to play back the event log of the application. If the application contains a large number of event logs, the playback takes a long time and the browser takes a long time to navigate you to the native page.

The current browser uses the HTTPd as the proxy to access the JobHistory native page. The proxy timeout duration is 10 minutes. Therefore, if the JobHistory cannot parse the event log and return the result within 10 minutes, the HTTPd automatically returns the proxy error information to the browser.

## Solution

The local disk cache function is enabled on the JobHistory. When a user accesses an application, the event log of the application is cached on the local disk. In this case, the response speed can be greatly accelerated for the second access. Therefore, in this case, you only need to wait for a while and then access the link again. For the second time, you do not need to wait for a long time.

## 17.7.14 Spark Shuffle Exception Handling

### Question

In some scenarios, the following exception occurs in the Spark shuffle phase:

```
2021-06-18 02:53:08.364 INFO | [shuffle-server-6-1] | DIGEST:Unmatched MACs | java.security.sasl.unwrap(DigestMDSBase.java:148)
2021-06-18 02:53:08.368 WARN | [shuffle-server-6-1] | Exception in connection from /0000000000000000 | org.apache.spark.network.server.TransportChannelHandler.exceptionCaught(TransportChannelHandler.java:97)
io.netty.handler.codec.DecoderException: java.security.sasl.SaslException: DIGEST-MD5: Out of order sequencing of messages from server. Got: 16 Expected: 14
    at io.netty.handler.codec.MessageToMessageDecoder.channelRead(MessageToMessageDecoder.java:80)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:379)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:365)
    at io.netty.channel.AbstractChannelHandlerContext.fireChannelRead(AbstractChannelHandlerContext.java:357)
    at org.apache.spark.network.util.TransportFrameDecoder.channelRead(TransportFrameDecoder.java:102)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:379)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:365)
    at io.netty.channel.AbstractChannelHandlerContext.fireChannelRead(AbstractChannelHandlerContext.java:357)
    at io.netty.channel.DefaultChannelPipeline$HeadContext.channelRead(DefaultChannelPipeline.java:1410)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:379)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:365)
    at io.netty.channel.DefaultChannelPipeline$FireChannelReadOnFailChannelPipeline.java:910
    at io.netty.channel.nio.NioEventLoop.processSelectedKey(NioEventLoop.java:163)
    at io.netty.channel.nio.NioEventLoop.processSelectedKey(NioEventLoop.java:174)
    at io.netty.channel.nio.NioEventLoop.processSelectedKeys(NioEventLoop.java:150)
    at io.netty.channel.nio.NioEventLoop.run(NioEventLoop.java:176)
    at io.netty.util.concurrent.SingleThreadEventExecutor$4.run(SingleThreadEventExecutor.java:989)
    at io.netty.util.internal.ThreadExecutorMap$2.run(ThreadExecutorMap.java:71)
    at io.netty.util.concurrent.FastThreadLocalRunnable.run(FastThreadLocalRunnable.java:30)
    at java.lang.Thread.run(Thread.java:748)
Caused by: java.security.sasl.SaslException: DIGEST-MD5: Out of order sequencing of messages from server. Got: 16 Expected: 14
    at com.sun.security.sasl.digest.DigestMDSBase$DigestPrivacy.unwrap(DigestMDSBase.java:148)
    at com.sun.security.sasl.digest.DigestMDSBase.unwrap(DigestMDSBase.java:233)
    at org.apache.spark.network.sasl.SparkSaslServer.unwrap(SparkSaslServer.java:140)
    at org.apache.spark.network.sasl.SaslEncryptionDecryptionHandler.decodeSaslEncryption(SaslEncryption.java:126)
    at org.apache.spark.network.sasl.SaslEncryptionDecryptionHandler.decodeSaslEncryption(SaslEncryption.java:101)
    at io.netty.handler.codec.MessageToMessageDecoder.channelRead(MessageToMessageDecoder.java:80)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:379)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:365)
    at io.netty.channel.AbstractChannelHandlerContext.fireChannelRead(AbstractChannelHandlerContext.java:357)
    at org.apache.spark.network.util.TransportFrameDecoder.channelRead(TransportFrameDecoder.java:102)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:379)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:365)
    at io.netty.channel.AbstractChannelHandlerContext.fireChannelRead(AbstractChannelHandlerContext.java:357)
    at io.netty.channel.DefaultChannelPipeline$HeadContext.channelRead(DefaultChannelPipeline.java:1410)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:379)
    at io.netty.channel.AbstractChannelHandlerContext.invokeChannelRead(AbstractChannelHandlerContext.java:365)
    at io.netty.channel.DefaultChannelPipeline$FireChannelReadOnFailChannelPipeline.java:910
    at io.netty.channel.nio.NioEventLoop.processSelectedKey(NioEventLoop.java:163)
    at io.netty.channel.nio.NioEventLoop.processSelectedKey(NioEventLoop.java:174)
    at io.netty.channel.nio.NioEventLoop.processSelectedKeys(NioEventLoop.java:150)
    at io.netty.channel.nio.NioEventLoop.run(NioEventLoop.java:176)
    at io.netty.util.concurrent.SingleThreadEventExecutor$4.run(SingleThreadEventExecutor.java:989)
    at io.netty.util.internal.ThreadExecutorMap$2.run(ThreadExecutorMap.java:71)
    at io.netty.util.concurrent.FastThreadLocalRunnable.run(FastThreadLocalRunnable.java:30)
    at java.lang.Thread.run(Thread.java:748)
```

## Solution

For JDBC:

Log in to FusionInsight Manager, change the value of the JDBCServer parameter **spark.authenticate.enableSaslEncryption** to **false**, and restart the corresponding instance.

For client jobs:

When the client submits the application, change the value of **spark.authenticate.enableSaslEncryption** in the **spark-defaults.conf** file to **false**.

# 18 Using Tez

## 18.1 Common Tez Parameters

### Navigation path for setting parameters:

On Manager, choose **Cluster > Service > Tez > Configuration > All Configurations**. Enter a parameter name in the search box.

### Parameter description

Table 18-1 Parameter description

| Parameter              | Description         | Default Value              |
|------------------------|---------------------|----------------------------|
| property.tez.log.dir   | TezUI log directory | /var/log/Bigdata/tez/tezui |
| property.tez.log.level | TezUI log level     | INFO                       |

## 18.2 Accessing TezUI

Tez displays the Tez task execution process on a GUI. You can view the task execution details on the GUI.

### Prerequisite

The TimelineServer instance of the Yarn service has been installed.

### How to Use

Log in to Manager. For details, see [Accessing FusionInsight Manager](#). On Manager, choose **Cluster > Services > Tez**. Click the link on the right of **Tez WebUI** in the **Basic Information** area, and go to Tez web UI. You can view the details about Tez task execution.

## 18.3 Log Overview

### Log Description

**Log path:** The default save path of Tez logs is `/var/log/Bigdata/tez/role name`.

TezUI: `/var/log/Bigdata/tez/tezui` (run logs) and `/var/log/Bigdata/audit/tez/tezui` (audit logs)

**Log archive rule:** The automatic compression and archiving function of Tez is enabled. By default, when the size of a log file exceeds 20 MB (which is adjustable), the log file is automatically compressed. The naming rule of the compressed log file is as follows: `<Original log file name>-<yyyy-mm-dd_hh-mm-ss>.[/D].log.zip` A maximum of 20 latest compressed files are retained. The number of compressed files and compression threshold can be configured.

**Table 18-2** Tez log list

| Log Type  | Name                          | Description                                                         |
|-----------|-------------------------------|---------------------------------------------------------------------|
| Run log   | tezui.out                     | Log file that records TezUI running environment information         |
|           | tezui.log                     | Run log of the TezUI process                                        |
|           | tezui-omm-<Date>-gc.log.<No.> | GC log of the TezUI process                                         |
|           | prestartDetail.log            | Work logs generated before the TezUI is started                     |
|           | check-serviceDetail.log       | Log file that records whether the TezUI service starts successfully |
|           | postinstallDetail.log         | Work logs after the TezUI is installed                              |
|           | startDetail.log               | Startup log of the TezUI process                                    |
|           | stopDetail.log                | Stop log of the TezUI process                                       |
| Audit log | tezui-audit.log               | TezUI audit log                                                     |

### Log Level

**Table 18-3** describes the log levels supported by TezUI.

Levels of run logs are ERROR, WARN, INFO, and DEBUG from the highest to the lowest priority. Run logs of equal or higher levels are recorded. The higher the specified log level, the fewer the logs recorded.

**Table 18-3** Log levels

| Level | Description                                                                              |
|-------|------------------------------------------------------------------------------------------|
| ERROR | Logs of this level record error information about system running.                        |
| WARN  | Exception information about the current event processing                                 |
| INFO  | Logs of this level record normal running status information about the system and events. |
| DEBUG | Logs of this level record the system information and system debugging information.       |

To modify log levels, perform the following operations:

- Step 1** Log in to Manager.
- Step 2** Choose **Cluster > Service > Tez > Configuration**.
- Step 3** Select **All Configurations**.
- Step 4** In the navigation pane, choose **TezUI > Log**.
- Step 5** Select a desired log level.
- Step 6** Click **Save**. In the dialog box that is displayed, click **OK** to save the configuration.
- Step 7** Click **Instance**, select the **TezUI** role, choose **More > Restart Instance**, enter the user password, and click **OK** in the dialog box that is displayed.
- Step 8** Wait until the instance is restarted for the configuration to take effect.

----End

## Log Format

The following table lists the Tez log formats.

**Table 18-4** Log formats

| Log Type   | Format                                                                                                                                                                                     | Example                                                                                                                                                                                                                                                                                                          |
|------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Run log    | <yyyy-MM-dd<br>HH:mm:ss,SSS> <br><LogLevel> <Thread that<br>generates the log> <br><Message in the log> <br><Location of the log<br>event>                                                 | 2020-07-31 11:44:21,378  <br>INFO   TezUI-health-check  <br>Start health check  <br>com.XXX.tez.HealthCheck.run(<br>HealthCheck.java:30)                                                                                                                                                                         |
| Audit logs | <yyyy-MM-dd<br>HH:mm:ss,SSS> <br><LogLevel> <Thread that<br>generates the log> <User<br>Name><User<br>IP><Time><Operation><Re<br>source><Result><Detail > <<br>Location of the log event > | 2018-12-24 12:16:25,319  <br>INFO   HiveServer2-Handler-<br>Pool: Thread-185  <br>UserName=hive<br>UserIP=10.153.2.204<br>Time=2018/12/24 12:16:25<br>Operation=CloseSession<br>Result=SUCCESS Detail=  <br>org.apache.hive.service.cli.thrif<br>t.ThriftCLIService.logAuditEven<br>t(ThriftCLIService.java:434) |

## 18.4 Common Issues

### 18.4.1 TezUI Cannot Display Tez Task Execution Details

#### Question

After a user logs in to Manager and switches to the Tez web UI, the submitted Tez tasks are not displayed.

#### Answer

The Tez task data displayed on the Tez WebUI requires the support of TimelineServer of Yarn. Ensure that TimelineServer has been enabled and is running properly before the task is submitted.

When setting the Hive execution engine to Tez, you need to set **yarn.timeline-service.enabled** to **true**. For details, see [Switching the Hive Execution Engine to Tez](#).

### 18.4.2 Error Occurs When a User Switches to the Tez Web UI

#### Question

When a user logs in to Manager and switches to the Tez web UI, error 404 or 503 is displayed.

## HTTP ERROR 404

Problem accessing /null/applicationhistory. Reason:

Not Found

Adapter operation failed Å» 503: Error accessing https://[redacted];Yarn/TimelineServer/57/ws/v1/timeline/TEZ\_DAG\_ID

### Answer

The Tez web UI depends on the TimelineServer instance of Yarn. Therefore, TimelineServer must be installed in advance and in the **Good** state.

## 18.4.3 Yarn Logs Cannot Be Viewed on the TezUI Page

### Question

A user logs in to the Tez web UI and clicks **Logs**, but the Yarn log page fails to be displayed and data cannot be loaded.

### Answer

Currently, the hostname is used for the access to the Yarn log page from the Tez web UI. Therefore, you need to configure the mapping between the hostname and IP address on the Windows host. Perform the following steps:

Modify the **C:\Windows\System32\drivers\etc\hosts** file on the Windows host and add a line indicating the mapping between the host name and IP address, for example, **10.244.224.45 10-044-224-45**. Save the modification and access the host again.

## 18.4.4 Table Data Is Empty on the TezUI HiveQueries Page

### Question

A user logs in to Manager and switches to the Tez web UI page, but no data for the submitted task is displayed on the **Hive Queries** page.

### Answer

To display Hive Queries task data on the Tez web UI, you need to set the following parameters:

On Manager, choose **Cluster > Service > Hive > Configurations > All Configurations > Hive > Customization**. Add the following configuration to **yarn-site.xml**:

| Attribute                                                 | Attribute Value                 |
|-----------------------------------------------------------|---------------------------------|
| yarn.timeline-service.enabled                             | true                            |
| yarn.timeline-service.webapp.https.address                | #{tl_hostname}:#{tl_https_port} |
| yarn.resourcemanager.system-metrics-publisher.enabled     | true                            |
| yarn.timeline-service.generic-application-history.enabled | true                            |

On Manager, choose **Cluster > Service > Hive > Configurations > All Configurations > HiveServer > Customization**. Add the following configuration to **hive-site.xml**:

| Attribute               | Attribute Value                         |
|-------------------------|-----------------------------------------|
| hive.exec.pre.hooks     | org.apache.hadoop.hive ql.hooks.ATSHook |
| hive.exec.post.hooks    | org.apache.hadoop.hive ql.hooks.ATSHook |
| hive.exec.failure.hooks | org.apache.hadoop.hive ql.hooks.ATSHook |

 **NOTE**

Data display on TezUI depends on the TimelineServer instance of Yarn. If the TimelineServer instance is faulty or not started, you need to set **yarn.timeline-service.enabled** to **false** in **yarn-site.xml**. Otherwise, the Hive task fails to be executed.

# 19 Using Yarn

## 19.1 Common Yarn Parameters

### Allocating Queue Resources

The Yarn service provides one queue (**default**) for users. Users allocate system resources to each queue. After the configuration is complete, you can click **Refresh Queue** or restart the Yarn service for the configuration to take effect.

#### Navigation path for setting parameters:

On Manager, choose **Tenant Resources > Dynamic Resource Plan > Queue Configuration**.

The following uses the **default** tenant who modifies the Superior scheduler as an example. The configurations of other queues are similar. Click **Modify** to edit the parameters.

**Table 19-1** Queue configuration parameters

| Parameter                | Description                                                                                                                                                                                                              |
|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Max Master Shares(%)     | Indicates the maximum percentage of resources occupied by all ApplicationMasters in the current queue.                                                                                                                   |
| Max Allocated vCores     | Indicates the maximum number of cores that can be allocated to a single YARN container in the current queue. The default value is <b>-1</b> , indicating that the number of cores is not limited within the value range. |
| Max Allocated Memory(MB) | Indicates the maximum memory that can be allocated to a single YARN container in the current queue. The default value is <b>-1</b> , indicating that the memory is not limited within the value range.                   |

| Parameter                 | Description                                                                                                                                                                                                                                                                                                                                   |
|---------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Max Running Apps          | Maximum number of tasks that can be executed at the same time in the current queue. The default value is <b>-1</b> , indicating that the number is not limited within the value range (the meaning is the same if the value is empty). The value <b>0</b> indicates that the task cannot be executed. The value ranges from -1 to 2147483647. |
| Max Running Apps per User | Maximum number of tasks that can be executed by each user in the current queue at the same time. The default value is <b>-1</b> , indicating that the number is not limited within the value range. If the value is <b>0</b> , the task cannot be executed. The value ranges from -1 to 2147483647.                                           |
| Max Pending Apps          | Maximum number of tasks that can be suspended at the same time in the current queue. The default value is <b>-1</b> , indicating that the number is not limited within the value range (the meaning is the same if the value is empty). The value <b>0</b> indicates that tasks cannot be suspended. The value ranges from -1 to 2147483647.  |
| Resource Allocation Rule  | Indicates the rule for allocating resources to different tasks of a user. The rule can be FIFO or FAIR.<br>If a user submits multiple tasks in the current queue and the rule is FIFO, the tasks are executed one by one in sequential order; if the rule is FAIR, resources are evenly allocated to all tasks.                               |
| Default Resource Label    | Indicates that tasks are executed on a node with a specified resource label.                                                                                                                                                                                                                                                                  |
| Active                    | <ul style="list-style-type: none"> <li>● <b>ACTIVE</b>: indicates that the current queue can receive and execute tasks.</li> <li>● <b>INACTIVE</b>: indicates that the current queue can receive but cannot execute tasks. Tasks submitted to the queue are suspended.</li> </ul>                                                             |
| Open                      | <ul style="list-style-type: none"> <li>● <b>OPEN</b>: indicates that the current queue is opened.</li> <li>● <b>CLOSED</b>: indicates that the current queue is closed. Tasks submitted to the queue are rejected.</li> </ul>                                                                                                                 |

## Displaying Container Logs on the Web UI

By default, the system collects container logs to HDFS. If you do not need to collect container logs to HDFS, configure the parameters in [Table 19-2](#). For details, see [Modifying Cluster Service Configuration Parameters](#).

**Table 19-2** Parameter description

| Parameter                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 | Default Value |
|-----------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.log-aggregation-enable | <p>Select whether to collect container logs to HDFS.</p> <ul style="list-style-type: none"> <li>If the parameter is set to <b>true</b>, container logs are collected to an HDFS directory. The default directory is <b>{yarn.nodemanager.remote-app-log-dir}/{user}/{thisParam}</b>. You can set the directory by setting the <b>yarn.nodemanager.remote-app-log-dir-suffix</b> parameter on the web UI.</li> <li>If this parameter is set to <b>false</b>, container logs will not be collected to HDFS.</li> </ul> <p>After changing the parameter value, restart the Yarn service for the setting to take effect.</p> <p><b>NOTE</b><br/>The container logs that are generated before the parameter is set to <b>false</b> and the setting takes effect cannot be obtained from the web UI. You can obtain container logs from the directory specified by the <b>yarn.nodemanager.remote-app-log-dir-suffix</b> parameter before the setting takes effect.</p> <p>If you want to view the logs generated before on the web UI, you are advised to set this parameter to <b>true</b>.</p> | true          |

## Increasing the Number of Historical Jobs to Be Displayed on the web UI

By default, the Yarn web UI supports task list pagination. A maximum of 5,000 historical jobs can be displayed on each page, and a maximum of 10,000 historical jobs can be retained. If you need to view more jobs on the WebUI, configure parameters by referring to [Table 19-3](#). For details, see [Modifying Cluster Service Configuration Parameters](#).

**Table 19-3** Parameter description

| Parameter                                       | Description                                                                               | Default Value |
|-------------------------------------------------|-------------------------------------------------------------------------------------------|---------------|
| yarn.resourcemanager.max-completed-applications | Set the total number of historical jobs to be displayed on the web UI.                    | 10000         |
| yarn.resourcemanager.webapp.pagination.enable   | Select whether to enable the job list background pagination function for the Yarn web UI. | true          |

| Parameter                                        | Description                                                                                                                            | Default Value |
|--------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.resourcemanager.webapp.pagination.threshold | Set the maximum number of jobs displayed on each page after the job list background pagination function of the Yarn web UI is enabled. | 5000          |

 NOTE

- If a large number of historical jobs are displayed, the performance will be affected and the time for opening the Yarn web UI will be increased. Therefore, you are advised to enable the background pagination function and modify the **yarn.resourcemanager.max-completed-applications** parameter according to the actual hardware performance.
- After changing the parameter value, restart the Yarn service for the setting to take effect.

## 19.2 Creating Yarn Roles

### Scenario

This section describes how to create and configure a Yarn role. The Yarn role can be assigned with Yarn administrator permission and manage Yarn queue resources.

 NOTE

If the current component uses Ranger for permission control, you need to configure permission management policies based on Ranger. Refer to [Adding a Ranger Access Permission Policy for Yarn](#).

### Prerequisites

- The MRS cluster administrator has understood the service requirements.
- You have logged in to Manager.

### Procedure

**Step 1** Choose System > Permission > Role.

**Step 2** Click **Create Role** and set a role name and enter description.

**Step 3** Refer [Table 19-4](#) to configure resource permissions for roles.

Yarn permissions:

- Cluster management: Yarn administrator permissions.
- Queue scheduling: queue resource management.

**Table 19-4** Setting a role

| Task                                                                        | Operation                                                                                                                                                                                                                                                                                        |
|-----------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Setting the Yarn administrator permission                                   | In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> > <b>Yarn</b> > <b>Cluster Management</b> .<br><b>NOTE</b><br>The Yarn service needs to be restarted to set the Yarn administrator permission so that the saved role configuration can take effect. |
| Setting the permission for a user to submit tasks in a specified Yarn queue | 1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> > <b>Yarn</b> > <b>Scheduling Queue</b> > <b>root</b> .<br>2. In the <b>Permission</b> column of the specified queue, select <b>Submit</b> .                                                     |
| Setting the permission for a user to manage tasks in a specified Yarn queue | 1. In the <b>Configure Resource Permission</b> table, choose <i>Name of the desired cluster</i> > <b>Yarn</b> > <b>Scheduling Queue</b> > <b>root</b> .<br>2. In the <b>Permission</b> column of the specified queue, select <b>Manage</b> .                                                     |

If the Yarn role contains the **Submit** or **Manage** permission of a parent queue, the sub-queue inherits the permission by default, that is, the **Submit** or **Manage** permission is automatically added for the sub-queue. Permissions inherited by sub-queues will not be displayed as selected in the **Configure Resource Permission** table.

If you select only the **Submit** permission of a parent queue when setting the Yarn role, you need to manually specify the queue name when submitting tasks as a user with the permission of this role. Otherwise, when the parent queue has multiple sub-queues, the system does not automatically determine the queue to which the task is submitted and therefore submits the task to the **default** queue.

**Step 4** Click **OK**.

----End

## 19.3 Using the Yarn Client

### Scenario

This section guides users to use a Yarn client in an O&M or service scenario.

### Prerequisites

- The client has been installed.  
For example, the installation directory is **/opt/hadoopclient**. The client directory in the following operations is only an example. Change it to the actual installation directory.

- Service component users are created by the MRS cluster administrator as required. In security mode, machine-machine users need to download the keytab file. A human-machine user must change the password upon the first login. In common mode, you do not need to download the keytab file or change the password.

## Using the Yarn Client

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to go to the client installation directory:

```
cd /opt/hadoopclient
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** If the cluster is in security mode, run the following command to authenticate the user. In normal mode, user authentication is not required.

```
kinit Component service user
```

**Step 5** Run the Yarn command. The following provides an example:

```
yarn application -list
```

```
----End
```

## Client-related FAQs

1. What Do I Do When the Yarn Client Exits Abnormally and Error Message "java.lang.OutOfMemoryError" Is Displayed After the Yarn Client Command Is Run?

This problem occurs because the memory required for running the Yarn client exceeds the upper limit (128 MB by default) set on the Yarn client. You can modify **CLIENT\_GC\_OPTS** in *<Client installation path>/HDFS/component\_env* to change the memory upper limit of the Yarn client. For example, if you want to set the maximum memory to 1 GB, run the following command:

```
export CLIENT_GC_OPTS="-Xmx1G"
```

After the modification, run the following command to make the modification take effect:

```
source <Client installation path>/bigdata_env
```

2. How Can I Set the Log Level When the Yarn Client Is Running?

By default, the logs generated during the running of the Yarn client are printed to the console. The default log level is INFO. To enable the DEBUG log level for fault locating, run the following command to export an environment variable:

```
export YARN_ROOT_LOGGER=DEBUG,console
```

Then run the Yarn Shell command to print DEBUG logs.

If you want to print INFO logs again, run the following command:

```
export YARN_ROOT_LOGGER=INFO,console
```

## 19.4 Configuring Resources for a NodeManager Role Instance

### Scenario

If the hardware resources (such as the number of CPU cores and memory size) of the nodes for deploying NodeManagers are different but the NodeManager available hardware resources are set to the same value, the resources may be wasted or the status may be abnormal. You need to change the hardware resource configuration for each NodeManager to ensure that the hardware resources can be fully utilized.

### Impact on the System

NodeManager role instances must be restarted for the new configuration to take effect, and the role instances are unavailable during restart.

### Prerequisites

You have logged in to Manager.

### Procedure

- Step 1** Choose **Cluster** > *Name of the desired cluster* > **Services** > **Yarn** > **Instance**.
- Step 2** Click the role instance name corresponding to the node where NodeManager is deployed, switch to **Instance Configuration**, and select **All Configurations**.
- Step 3** Enter **yarn.nodemanager.resource.cpu-vcores** in the search box, and set the number of vCPUs that can be used by NodeManager on the current node. You are advised to set this parameter to 1.5 to 2 times the number of actual logical CPUs on the node. Enter **yarn.nodemanager.resource.memory-mb** in the search box, and set the physical memory size that can be used by NodeManager on the current node. You are advised to set this parameter to 75% of the actual physical memory size of the node.

#### NOTE

Enter **yarn.scheduler.maximum-allocation-vcores** in the search box, and set the maximum number of available CPUs in a container. Enter **yarn.scheduler.maximum-allocation-mb** in the search box, and set the maximum available memory of a container. The instance level cannot be changed. The parameter values need to be changed in the configuration of the Yarn service, and the Yarn service needs to be restarted for the changes to take effect.

- Step 4** Click **Save**, and then click **OK**. to restart the NodeManager role instance.

A message is displayed, indicating that the operation is successful. Click **Finish**. The NodeManager role instance is started successfully.

----End

## 19.5 Changing NodeManager Storage Directories

### Scenario

If the storage directories defined by the Yarn NodeManager are incorrect or the Yarn storage plan changes, the MRS cluster administrator needs to modify the NodeManager storage directories on Manager to ensure that the Yarn works properly. The storage directories of NodeManager include the local storage directory **yarn.nodemanager.local-dirs** and log directory **yarn.nodemanager.log-dirs**. Changing the ZooKeeper storage directory includes the following scenarios:

- Change the storage directory of the NodeManager role. In this way, the storage directories of all NodeManager instances are changed.
- Change the storage directory of a single NodeManager instance. In this way, only the storage directory of this instance is changed, and the storage directories of other instances remain the same.

### Impact on the System

- The cluster needs to be stopped and restarted during the process of changing the storage directory of the NodeManager role, and the cluster cannot provide services before started.
- The NodeManager instance needs to be stopped and restarted during the process of changing the storage directory of the instance, and the instance at this node cannot provide services before it is started.
- The directory for storing service parameter configurations must also be updated.
- After the storage directories of NodeManager are changed, you need to download and install the client again.

### Prerequisites

- New disks have been prepared and installed on each data node, and the disks are formatted.
- New directories have been planned for storing data in the original directories.
- The MRS cluster administrator account **admin** has been prepared.

### Procedure

**Step 1** Check the environment.

1. Log in to Manager, choose **Cluster** > *Name of the desired cluster* > **Service** to check whether **Running Status** of Yarn is **Normal**.
  - If yes, go to **1.c**.
  - If no, the Yarn status is unhealthy. In this case, go to **1.b**.
2. Rectify faults of Yarn. No further action is required.
3. Determine whether to change the storage directory of the NodeManager role or that of a single NodeManager instance:

- To change the storage directory of the NodeManager role, go to [2](#).
- To change the storage directory of a single NodeManager instance, go to [3](#).

**Step 2** Change the storage directory of the NodeManager role.

1. Choose **Cluster** > *Name of the desired cluster* > **Service** > **Yarn** > **Stop** to stop the Yarn service.
2. Log in to each data node where the Yarn service is installed as user **root** and perform the following operations:
  - a. Create a target directory.  
For example, to create the target directory `${BIGDATA_DATA_HOME}/yarn/data2`, run the following command:  
**mkdir `${BIGDATA_DATA_HOME}/yarn/data2`**
  - b. Mount the target directory to the new disk.  
For example, mount `${BIGDATA_DATA_HOME}/yarn/data2` to the new disk.
  - c. Modify permissions on the new directory.  
For example, to modify permissions on the `${BIGDATA_DATA_HOME}/yarn/data2` directory, run the following commands:  
**chmod 750 `${BIGDATA_DATA_HOME}/yarn/data2` -R** and **chown omm:wheel `${BIGDATA_DATA_HOME}/yarn/data2` -R**
3. On the Manager portal, choose **Cluster** > *Name of the desired cluster* > **Services** > **Yarn** > **Instance**. Select the NodeManager instance of the corresponding host, click **Instance Configuration**, and select **All Configurations**.  
Change the value of **yarn.nodemanager.local-dirs** or **yarn.nodemanager.log-dirs** to the new target directory, for example, `${BIGDATA_DATA_HOME}/yarn/data2`.
4. Click **Save**, and then click **OK**. Restart the Yarn service.  
Click **Finish** when the system displays "Operation successful". Yarn is successfully started. No further action is required.

**Step 3** Change the storage directory of a single NodeManager instance.

1. Choose **Cluster** > *Name of the desired cluster* > **Service** > **Yarn** > **Instance**, select the NodeManager instance whose storage directory needs to be modified, and choose **More** > **Stop**.
2. Log in to the NodeManager node as user **root**, and perform the following operations:
  - a. Create a target directory.  
For example, to create the target directory `${BIGDATA_DATA_HOME}/yarn/data2`, run the following command:  
**mkdir `${BIGDATA_DATA_HOME}/yarn/data2`**
  - b. Mount the target directory to the new disk.  
For example, mount `${BIGDATA_DATA_HOME}/yarn/data2` to the new disk.
  - c. Modify permissions on the new directory.

For example, to modify permissions on the `${BIGDATA_DATA_HOME}/yarn/data2` directory, run the following commands:

```
chmod 750 ${BIGDATA_DATA_HOME}/yarn/data2 -R and chown omm:wheel ${BIGDATA_DATA_HOME}/yarn/data2 -R
```

3. On Manager, click the specified NodeManager instance, and switch to the **Instance Configuration** page.

Change the value of `yarn.nodemanager.local-dirs` or `yarn.nodemanager.log-dirs` to the new target directory, for example, `${BIGDATA_DATA_HOME}/yarn/data2`.

4. Click **Save**, and then click **OK** to restart the NodeManager instance.  
Click **Finish** when the system displays "Operation successful". The NodeManager instance is successfully started.

----End

## 19.6 Configuring Strict Permission Control for Yarn

### Scenario

In the multi-tenant scenario in security mode, a cluster can be used by multiple users, and tasks of multiple users can be submitted and executed. Users are invisible to each other. A permission control mechanism is required to prevent task information of users from being obtained by other users.

For example, if user B logs in to the system and views the application list when the application submitted by user A is running, user B should not be able to view the application information of user A.

### Configuration Description

- Viewing Yarn configuration parameters

Go to the **All Configurations** page of Yarn and enter a parameter name list in [Table 19-5](#) in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 19-5** Parameter description

| Parameter                              | Description                                                                                                                                                                                                                             | Default Value |
|----------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.acl.enable                        | Whether to enable Yarn permission control                                                                                                                                                                                               | true          |
| yarn.webapp.filter-entity-list-by-user | Whether to enable the strict view function. After this function is enabled, a login user can view only the content that the user has the permission to view. To enable this function, set <code>yarn.acl.enable</code> to <b>true</b> . | true          |

- Viewing MapReduce configuration parameters  
Go to the **All Configurations** page of MapReduce and enter a parameter name in [Table 19-6](#) in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 19-6** Parameter description

| Parameter                              | Description                                                                                                                                                                                                                                                                                                                                                                                                                             | Default Value |
|----------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| mapreduce.cluster.acls.enabled         | Whether to enable permission control of MapReduce JobHistoryServer. This parameter is a client parameter and takes effect after permission control is enabled on the JobHistoryServer server.                                                                                                                                                                                                                                           | true          |
| yarn.webapp.filter-entity-list-by-user | Whether to enable the strict view of MapReduce JobHistoryServer. After the strict view is enabled, a login user can view only the content that the user has the permission to view. This parameter is a server parameter of JobHistoryServer. It indicates that permission control is enabled for JHS. However, whether to control a specific application is determined by the client parameter <b>mapreduce.cluster.acls.enabled</b> . | true          |

**NOTICE**

The preceding configurations affect the RESTful API and Shell command results. After the preceding configurations are enabled, the return results of RESTful API calls and shell commands contain only the information that the user has the permission to view.

If **yarn.acl.enable** or **mapreduce.cluster.acls.enabled** is set to **false**, the Yarn or MapReduce permission verification function is disabled. In this case, any user can submit tasks and view task information on Yarn or MapReduce, which poses security risks. Exercise caution when performing this operation.

## 19.7 Configuring Container Log Aggregation

### Scenario

Yarn provides the container log aggregation function to collect logs generated by containers on each node to HDFS to release local disk space. You can collect logs in either of the following ways:

- After the application is complete, collect container logs to HDFS at a time.
- During application running, periodically collect log segments generated by containers and save them to HDFS.

## Configuration Description

### Navigation path for setting parameters:

Go to the **All Configurations** page of Yarn and enter a parameter name list in [Table 19-7](#) in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

The `yarn.nodemanager.remote-app-log-dir-suffix` parameter must be configured on the Yarn client. The configurations on the ResourceManager, NodeManager, and JobHistory nodes must be the same as those on the Yarn client.

The periodic log collection function applies only to MapReduce applications, for which rolling output of log files must be configured. [Table 19-9](#) describes the configurations in the `mapred-site.xml` configuration file on the MapReduce client node.

**Table 19-7** Parameter description

| Parameter                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              | Default Value |
|-----------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.log-aggregation-enable | <p>Whether to enable container log aggregation</p> <ul style="list-style-type: none"> <li>• If this parameter is set to <b>true</b>, logs are collected to the HDFS directory.</li> <li>• If this parameter is set to <b>false</b>, the function is disabled, and logs are not collected to HDFS.</li> </ul> <p>After changing the parameter value, restart the Yarn service for the setting to take effect.</p> <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>• The container logs that are generated before the parameter is set to <b>false</b> and the setting takes effect cannot be obtained from the web UI.</li> <li>• If you want to view the logs generated before on the web UI, you are advised to set this parameter to <b>true</b>.</li> </ul> | true          |

| Parameter                                                            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            | Default Value |
|----------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.nodemanager.log-aggregation.rolling-monitoring-interval-seconds | <p>Interval for NodeManager to periodically collect logs</p> <ul style="list-style-type: none"><li>• If this parameter is set to <b>-1</b> or <b>0</b>, periodic log collection is disabled. Logs are collected at a time after application running is complete.</li><li>• The minimum collection interval can be set to 3,600 seconds. If this parameter is set to a value greater than 0 and less than 3,600, the collection interval is 3,600 seconds.</li></ul> <p>Interval for NodeManager to wake up and upload logs. If this parameter is set to <b>-1</b> or <b>0</b>, rolling monitoring is disabled and logs are aggregated when the application task is complete. The value must be greater than or equal to <b>-1</b>.</p> | -1            |

| Parameter                                                                                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              | Default Value |
|-----------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| <p>yarn.nodemanager.disk-health-checker.log-dirs.max-disk-utilization-per-disk-percentage</p> | <p>Maximum percentage of the Yarn disk quota that can be occupied by the container log directory on each disk. When the space occupied by the log directory exceeds the value of this parameter, the periodic log collection service is triggered to start a log collection activity beyond the period to release the local disk space. Maximum space for container logs that can be provided on each disk. If the disk space occupied by container logs exceeds this threshold, data aggregation in rolling mode is triggered.</p> <p>The valid value range of the maximum disk quota percentage is -1 to 100. If the value is less than or equal to -1, it is forcibly reset to <b>25</b>. If the value is greater than 100, the value is forcibly reset to <b>25</b>. If you set the value to a negative number, the disk capacity detection function for Container log directory is disabled.</p> <p><b>NOTE</b></p> <ul style="list-style-type: none"> <li>Percentage of the available disk space of the container log directory = Percentage of the available disk space of Yarn (<b>yarn.nodemanager.disk-health-checker.max-disk-utilization-per-disk-percentage</b>) x Percentage of the available disk space of the container log directory (<b>yarn.nodemanager.disk-health-checker.log-dirs.max-disk-utilization-per-disk-percentage</b>)</li> <li>Only applications with the periodic log collection function enabled can trigger log collection when the disk quota of the log directory exceeds the threshold.</li> </ul> | <p>25</p>     |
| <p>yarn.nodemanager.remote-app-log-dir-suffix</p>                                             | <p>Name of the HDFS folder in which container logs are to be stored. This parameter and <b>yarn.nodemanager.remote-app-log-dir</b> form the full path for storing container logs. That is, <b>{yarn.nodemanager.remote-app-log-dir}/{user}/{yarn.nodemanager.remote-app-log-dir-suffix}</b>.</p> <p><b>NOTE</b><br/><i>{user}</i> indicates the username for running the task.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       | <p>logs</p>   |

| Parameter                                                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            | Default Value |
|-----------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.nodemanager.log-aggregator.on-fail.retain-log-in-sec | <p>Duration for retaining container logs on the local host after the logs fail to be collected, in second</p> <ul style="list-style-type: none"> <li>• If this parameter is set to a negative number or <b>0</b>, local logs are deleted immediately.</li> <li>• If this parameter is set to a positive number, local logs are retained for this period.</li> </ul> <p><b>NOTE</b><br/>This parameter takes effect only when <b>yarn.nodemanager.delete.debug-delay-sec</b> is not set to <b>-1</b>. The default value is <b>0</b>. <b>yarn.nodemanager.delete.debug-delay-sec</b> also controls the file deletion function. If this parameter is set to <b>-1</b>, other functions will be changed. Exercise caution when setting this parameter.</p> | 604800        |

Go to the **All Configurations** page of MapReduce and enter a parameter name in **Table 19-8** in the search box by referring to **Modifying Cluster Service Configuration Parameters**.

**Table 19-8** Parameter description

| Parameter                           | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         | Default Value |
|-------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.log-aggregation.retain-seconds | <p>Duration for retaining aggregated logs, in second</p> <ul style="list-style-type: none"> <li>• If this parameter is set to a negative integer, the container logs will be retained permanently in the HDFS.</li> <li>• If this parameter is set to <b>0</b> or a positive integer, container logs will be stored for such a period and deleted after the period expires.</li> </ul> <p><b>NOTE</b><br/>A short period may increase load of the NameNode. Therefore, you are advised to set this parameter to a proper value.</p> | 1296000       |

| Parameter                                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          | Default Value |
|----------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.log-aggregation.retain-check-interval-seconds | <p>Interval for storing container logs in HDFS, in second</p> <ul style="list-style-type: none"> <li>If this parameter is set to <b>-1</b> or <b>0</b>, the interval will be one tenth of the period specified by <b>yarn.log-aggregation.retain-seconds</b>.</li> </ul> <p><b>NOTE</b><br/>If this parameter is set to <b>-1</b> or <b>0</b>, <b>yarn.log-aggregation.retain-seconds</b> cannot be set to <b>0</b>.</p> <ul style="list-style-type: none"> <li>If this parameter is set to a positive number, container logs in HDFS will be scanned at such an interval.</li> </ul> <p><b>NOTE</b><br/>A short interval may increase load of the NameNode. Therefore, you are advised to set this parameter to a proper value.</p> | 86400         |

Go to the **All Configurations** page of Yarn and enter a parameter name list in [Table 19-9](#) in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 19-9** Configuring rolling output of MapReduce application log files

| Parameter                       | Description                                                                                                                                                                                                                          | Default Value |
|---------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| mapreduce.task.userlog.limit.kb | Maximum size of a single task log file of the MapReduce application. When the maximum size of the log file has been reached, a new log file is generated. The value <b>0</b> indicates that the size of the log file is not limited. | 51200         |

| Parameter                                     | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      | Default Value |
|-----------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.app.mapreduce.task.container.log.backups | <p>Maximum number of task logs that can be retained for the MapReduce application. If this parameter is set to <b>0</b>, rolling output is disabled.</p> <p>Number of task log backup files when ContainerRollingLogAppender (CRLA) is used. By default, ContainerLogAppender (CLA) is used and container logs are not rolled back.</p> <p>When both <b>mapreduce.task.userlog.limit.kb</b> and <b>yarn.app.mapreduce.task.container.log.backups</b> are greater than 0, CRLA is enabled. The value ranges from 0 to 999.</p>    | 10            |
| yarn.app.mapreduce.am.container.log.limit.kb  | <p>Maximum size of a single ApplicationMaster log file of the MapReduce application, in KB. When the maximum size of the log file has been reached, a new log file is generated. The value <b>0</b> indicates that the size of a single ApplicationMaster log file is not limited.</p>                                                                                                                                                                                                                                           | 51200         |
| yarn.app.mapreduce.am.container.log.backups   | <p>Maximum number of ApplicationMaster logs that can be retained for the MapReduce application. If this parameter is set to <b>0</b>, rolling output is disabled. Number of ApplicationMaster log backup files when CRLA is used. By default, CLA is used and container logs are not rolled back.</p> <p>When both <b>yarn.app.mapreduce.am.container.log.limit.kb</b> and <b>yarn.app.mapreduce.am.container.log.backups</b> are greater than 0, CRLA is enabled for the ApplicationMaster. The value ranges from 0 to 999.</p> | 20            |
| yarn.app.mapreduce.shuffle.log.backups        | <p>Maximum number of shuffle logs that can be retained for the MapReduce application. If this parameter is set to <b>0</b>, rolling output is disabled.</p> <p>When both <b>yarn.app.mapreduce.shuffle.log.limit.kb</b> and <b>yarn.app.mapreduce.shuffle.log.backups</b> are greater than 0, <b>syslog.shuffle</b> uses CRLA. The value ranges from 0 to 999.</p>                                                                                                                                                               | 10            |

| Parameter                               | Description                                                                                                                                                                                                                                                                                                            | Default Value |
|-----------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.app.mapreduce.shuffle.log.limit.kb | Maximum size of a single shuffle log file of the MapReduce application, in KB. When the maximum size of the log file has been reached, a new log file is generated. If this parameter is set to <b>0</b> , the size of a single shuffle log file is not limited. The value must be greater than or equal to <b>0</b> . | 51200         |

## 19.8 Using CGroups with YARN

### Scenario

CGroups is a Linux kernel feature. In YARN this feature allows containers to be limited in their resource usage (example, CPU usage). Without CGroups, it is hard to limit the container CPU usage. Without CGroups, it is hard to limit the container CPU usage.

 **NOTE**

Currently, CGroups is only used for limiting the CPU usage.

### Configuration Description

For details about how to configure the CGroups function for CPU isolation and security, see the Hadoop official website: <http://hadoop.apache.org/docs/r3.1.1/hadoop-yarn/hadoop-yarn-site/NodeManagerCgroups.html>

CGroups is a Linux kernel feature and is enabled by using LinuxContainerExecutor. For details about how to configure the LinuxContainerExecutor for security, see the official website. You can learn the file system permissions assigned for users and user groups from documentation published on the official website. For details, see <http://hadoop.apache.org/docs/r3.1.1/hadoop-project-dist/hadoop-common/SecureMode.html#LinuxContainerExecutor>.

 **NOTE**

- Do not modify users, user groups, and related permissions of various paths in the corresponding file system. Otherwise, functions of CGroups may become abnormal.
- If the parameter value of **yarn.nodemanager.resource.percentage-physical-cpu-limit** is too small, the number of available cores may be less than one. For example, if the parameter of a four-core node is set to 20%, the number available core is less than one. As a result, all cores will be used. The Quota mode can be used in Linux versions, for example, Cent OS, that do not support Quota mode.

The table below describes the parameter for configuring cpuset mode, that is, only configured CPUs can be used by YARN.

**Table 19-10** Parameter description

| Parameter                                                       | Description                                                                                              | Default Value |
|-----------------------------------------------------------------|----------------------------------------------------------------------------------------------------------|---------------|
| yarn.nodemanager.linux-container-executor.cgroups.cpu-set-usage | Whether to enable the cpuset mode. If this parameter is set to <b>true</b> , the cpuset mode is enabled. | false         |

The table below describes the parameters for configuring the strictcpuset mode, that is, only configured CPUs can be used by containers.

**Table 19-11** Parameter description

| Parameter                                                               | Description                                                                                                                | Default Value |
|-------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.nodemanager.linux-container-executor.cgroups.cpu-set-usage         | Whether to enable the cpuset mode. If this parameter is set to <b>true</b> , the cpuset mode is enabled.                   | false         |
| yarn.nodemanager.linux-container-executor.cgroups.cpuset.strict.enabled | Whether containers use allocated CPUs. If this parameter is set to <b>true</b> , the container can use the allocated CPUs. | false         |

To switch from cpuset mode to quota mode, the following conditions must be met:

- Set the **yarn.nodemanager.linux-container-executor.cgroups.cpu-set-usage** parameter to **false**.
- Delete container folders if exists.
- Delete all the CUPs configured in the **cpuset.cpus** file.

## Procedure

**Step 1** Log in to Manager. Choose **Cluster** > *Name of the desired cluster* > **Services** > **Yarn** > **Configurations** and select **All Configurations**.

**Step 2** In the navigation pane on the left, choose **NodeManager** > **Customization** and find the **yarn-site.xml** file.

**Step 3** Add the parameters in [Table 19-10](#) and [Table 19-11](#) as user-defined parameters.

Based on the configuration files and parameter functions, locate the row where parameter **yarn-site.xml** resides. Enter the parameter name in the **Name** column and enter the parameter value in the **Value** column.

Click + to add a customized parameter.

**Step 4** Click **Save**. In the displayed **Save Configuration** dialog box, confirm the modification and click **OK**. Click **Finish** when the system displays "Operation succeeded". The configuration is successfully saved.

After the configuration is saved, restart the Yarn service whose configuration has expired for the configuration to take effect.

----End

## 19.9 Configuring the Number of ApplicationMaster Retries

### Scenario

When resources are insufficient or ApplicationMaster fails to start, a client probably encounters running errors.

### Configuration Description

Go to the **All Configurations** page of Yarn and enter a parameter name list in [Table 19-12](#) in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 19-12** Parameter description

| Parameter                             | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | Default Value |
|---------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.resource manager.am.max-attempts | Number of retries of the ApplicationMaster. Increasing the number of retries can prevent ApplicationMaster startup failures caused by insufficient resources. This applies to global settings of all ApplicationMasters. Each ApplicationMaster can use an API to set an independent maximum number of retries. However, the number of retries cannot be greater than the global maximum number of retries. If the value is greater than the global maximum number of retries, the ResourceManager overwrites the value to allow at least one retry. The value must be greater than or equal to 1. | 2             |

## 19.10 Configure the ApplicationMaster to Automatically Adjust the Allocated Memory

### Scenario

During the process of starting the configuration, when the ApplicationMaster creates a container, the allocated memory is automatically adjusted according to

the total number of tasks, which makes resource utilization more flexible and improves the fault tolerance of the client application.

## Configuration Description

### Navigation path for setting parameters:

On Manager, choose **Cluster** > *Name of the desired cluster* > **Service** > **Yarn** > **Configuration**. On the displayed page, select **All Configurations** and enter **mapreduce.job.am.memory.policy**.

### Configuration description

If the default value of the parameter is left empty. In this case, the automatic adjustment policy is not enabled. The memory of ApplicationMaster is still affected by the value of **yarn.app.mapreduce.am.resource.mb**.

The value of **mapreduce.job.am.memory.policy** consists of five items, and they are separated by colons (:) and commas (,) in the following format:

**baseTaskCount:taskStep:memoryStep,minMemory:maxMemory**. The format is strictly checked when the value is entered.

**Table 19-13** Parameter description

| Parameter     | Description                                                                                                                                                                                                                                   | Setting Requirement                                                                                                         |
|---------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------|
| baseTaskCount | Indicates the total number of tasks. The configuration of ApplicationMaster is valid only when the total number of tasks (on the sum of the Map and Reduce ends) is greater than or equal to the value of this parameter.                     | The value cannot be empty and must be greater than 0.                                                                       |
| taskStep      | Indicates the incremental step length of tasks. This parameter and <b>memoryStep</b> determine the memory adjustment amount.                                                                                                                  | The value cannot be empty and must be greater than 0.                                                                       |
| memoryStep    | Indicates the incremental memory step. The memory capacity is increased based on the value of <b>yarn.app.mapreduce.am.resource.mb</b> .                                                                                                      | The value cannot be empty and must be greater than 0. The unit is MB.                                                       |
| minMemory     | Indicates the lower limit of the memory that can be automatically adjusted. If the memory after the automatic adjustment is less than or equal to the value of this parameter, the value of <b>yarn.app.mapreduce.am.resource.mb</b> is used. | The value cannot be empty. It must be greater than 0 and cannot be greater than the value of <b>maxMemory</b> .<br>Unit: MB |

| Parameter | Description                                                                                                                                                | Setting Requirement                                                                                                      |
|-----------|------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------|
| maxMemory | Indicates the upper limit of memory that can be automatically adjusted. If the adjusted memory exceeds the upper limit, use this value as the final value. | The value cannot be empty. It must be greater than 0 and cannot be less than the value of <b>minMemory</b> .<br>Unit: MB |

## Example Value

Configuration:

- yarn.app.mapreduce.am.resource.mb=1536
- mapreduce.job.am.memory.policy=100:10:50,1200:2000
- Total number of tasks of an application =120

The calculation process is as follows:

Memory after adjustment =  $1536 + [(120 - 100)/10] \times 50 = 1636$ . In this example, memory after adjustment 1636 is greater than the value of **minMemory 1200**, and less than the value of **maxMemory 2000**. Therefore, the ApplicationMaster memory is set to **1636 MB**.

If the value of **memStep** is changed to **250**, the calculation formula is as follows: Memory after adjustment =  $1536 + [(120 - 100) / 10] \times 250 = 2136$ . In this case, the memory after adjustment is greater than the value of **maxMemory 2000**. As a result, the value of **ApplicationMaster** is set to **2000 MB**.

### NOTE

If the memory after adjustment is lower than the value of **minMemory**, the configuration does not take effect but the value is still printed on the backend server. This value is provided as the reference for adjusting the value of **minMemory**.

## 19.11 Configuring the Access Channel Protocol

### Scenario

The value of the **yarn.http.policy** parameter must be consistent on both the server and clients. Web UIs on clients will be garbled if an inconsistency exists, for example, the parameter value is **HTTPS\_ONLY** on the server but it is left unspecified on a client (the parameter value **HTTP\_ONLY** is applied to the client by default). Set the **yarn.http.policy** parameters on the clients and server to prevent garbled characters from being displayed on the clients.

## Procedure

**Step 1** On Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Yarn** > **Configurations**. On the displayed page, select **All Configurations** and enter **yarn.http.policy**.

- In security mode, set this parameter to **HTTPS\_ONLY**.
- In normal mode, set this parameter to **HTTP\_ONLY**.

**Step 2** Log in to the node where the client is installed as the client installation user.

**Step 3** Run the following command to switch to the client installation directory:

```
cd /opt/client
```

**Step 4** Run the following command to edit the **yarn-site.xml** file:

```
vi Yarn/config/yarn-site.xml
```

Change the value of **yarn.http.policy**.

In security mode, set this parameter to **HTTPS\_ONLY**.

In normal mode, set this parameter to **HTTP\_ONLY**.

**Step 5** Run the **:wq** command to save execution.

**Step 6** Restart the client for the settings to take effect.

----End

## 19.12 Configuring Memory Usage Detection

### Scenario

If memory usage of the submitted application cannot be estimated, you can modify the configuration on the server to determine whether to check the memory usage.

If the memory usage is not checked, the container occupies the memory until the memory overflows. If the memory usage exceeds the configured memory size, the corresponding container is killed.

### Configuration Description

Go to the **All Configurations** page of Yarn and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 19-14** Parameter description

| Parameter                           | Description                                                                                                                                                                                                                                                                                                                                          | Default Value |
|-------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.nodemanager.vmem-check-enabled | Whether to enable virtual memory usage detection. If the memory used by a task exceeds the allocated memory size, the task is forcibly stopped. <ul style="list-style-type: none"> <li>If the value is <b>true</b>, the virtual memory will be checked.</li> <li>If the value is <b>false</b>, the virtual memory will not be checked.</li> </ul>    | true          |
| yarn.nodemanager.pmem-check-enabled | Whether to enable physical memory usage detection. If the memory used by a task exceeds the allocated memory size, the task is forcibly stopped. <ul style="list-style-type: none"> <li>If the value is <b>true</b>, the physical memory will be checked.</li> <li>If the value is <b>false</b>, the physical memory will not be checked.</li> </ul> | true          |

## 19.13 Configuring the Additional Scheduler WebUI

### Scenario

If the custom scheduler is set in ResourceManager, you can set the corresponding web page and other Web applications for the custom scheduler.

### Configuration Description

Go to the **All Configurations** page of Yarn and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 19-15** Configuring the Additional Scheduler WebUI

| Parameter                                   | Description                                                                                                                                                                           | Default Value |
|---------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| hadoop.http.rmwebapp.scheduler.page.classes | Load the corresponding web page for the custom scheduler on the RM WebUI. This parameter is valid only when <b>yarn.resourcemanager.scheduler.class</b> is set to a custom scheduler. | -             |
| yarn.http.rmwebapp.external.classes         | Load the custom web application in the RM Web service.                                                                                                                                | -             |

## 19.14 Configuring Yarn Restart

### Scenario

The Yarn Restart feature includes ResourceManager Restart and NodeManager Restart.

- When ResourceManager Restart is enabled, the new active ResourceManager node loads the information of the previous active ResourceManager node, and takes over container status information on all NodeManager nodes to continue service running. In this way, status information can be saved by periodically executing checkpoint operations, avoiding data loss.
- When NodeManager Restart is enabled, NodeManager locally saves information about containers running on the node. After NodeManager is restarted, the container running progress on the node will not be lost by restoring the saved status information.

### Configuration Description

Go to the **All Configurations** page of Yarn and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

Configure ResourceManager Restart as follows:

**Table 19-16** Parameter description of ResourceManager Restart

| Parameter                                             | Description                                                                                                                                                                | Default Value                                                              |
|-------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------|
| yarn.resourcemanager.recovery.enabled                 | Whether to enable ResourceManager to restore the status after startup. If this parameter is set to <b>true</b> , <b>yarn.resourcemanager.store.class</b> must also be set. | true                                                                       |
| yarn.resourcemanager.store.class                      | State-store class used to store the application and task statuses and certificate content.                                                                                 | org.apache.hadoop.yarn.server.resourcemanager.recovery.AsyncZKRMStateStore |
| yarn.resourcemanager.zk-state-store.parent-path       | Directory for storing ZKRMStateStore in ZooKeeper                                                                                                                          | /rmstore                                                                   |
| yarn.resourcemanager.work-preserving-recovery.enabled | Whether to enable ResourceManager work serving. This configuration is used only for Yarn feature verification.                                                             | true                                                                       |
| yarn.resourcemanager.state-store.async.load           | Whether to apply asynchronous restoration to completed applications.                                                                                                       | true                                                                       |

| Parameter                                             | Description                                                                                                                                                                              | Default Value |
|-------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.resourcemanager.zk-state-store.num-fetch-threads | If asynchronous restoration is enabled, increasing the number of working threads can speed up the restoration of task information stored in ZooKeeper. The value must be greater than 0. | 20            |

Configure NodeManager Restart as follows:

**Table 19-17** Parameter description of NodeManager Restart

| Parameter                            | Description                                                                                                                                                                                       | Default Value                     |
|--------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------|
| yarn.nodemanager.recovery.enabled    | Whether to enable the function of collecting logs upon a log collection failure when NodeManager is restarted and whether to restore the unfinished application                                   | true                              |
| yarn.nodemanager.recovery.dir        | Local directory used by NodeManager to store container status                                                                                                                                     | \${SRV_HOME}/tmp/yarn-nm-recovery |
| yarn.nodemanager.recovery.supervised | Whether NodeManager is monitored. After this parameter is enabled, NodeManager does not clear containers after exit. NodeManager assumes that it will restart and restore containers immediately. | true                              |

## 19.15 Configuring ApplicationMaster Work Preserving

### Scenario


In YARN, ApplicationMasters run on NodeManagers just like every other container (ignoring unmanaged ApplicationMasters in this context). ApplicationMasters may break down, exit, or shut down. If an ApplicationMaster node goes down, ResourceManager kills all the containers of ApplicationAttempt, including containers running on NodeManager. ResourceManager starts a new ApplicationAttempt node on another compute node.

For different types of applications, we want to handle ApplicationMaster restart events in different ways. MapReduce applications aim to prevent task loss but allow the loss of the currently running container. However, for the long-period

YARN service, users may not want the service to stop due to the ApplicationMaster fault.

YARN can retain the status of the container when a new ApplicationAttempt is started. Therefore, running jobs can continue to operate without faults.

**Figure 19-1** ApplicationMaster job preserving



## Configuration Description

Go to the **All Configurations** page of Yarn and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

Set the following parameters based on [Table 19-18](#).

**Table 19-18** Parameter description

| Parameter                                      | Description                                                                                                                               | Default Value |
|------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.app.mapreduce.am.work-preserve            | Whether to enable the ApplicationMaster job retention feature.                                                                            | false         |
| yarn.app.mapreduce.am.umbilical.max.retries    | Maximum number of attempts to restore a running container in the ApplicationMaster job retention feature.                                 | 5             |
| yarn.app.mapreduce.am.umbilical.retry.interval | Specifies the interval at which a running container attempts to recover in the ApplicationMaster job retention feature. Unit: millisecond | 10000         |

| Parameter                            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       | Default Value |
|--------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.resourcemanager.am.max-attempts | <p>The number of retries of ApplicationMaster. Increasing the number of retries prevents ApplicationMaster startup failures caused by insufficient resources.</p> <p>This applies to global settings of all ApplicationMasters. Each ApplicationMaster can use an API to set an independent maximum number of retries. However, the number of retries cannot be greater than the global maximum number of retries. If the value is greater than the global maximum number of retries, the ResourceManager overwrites the value. The value must be greater than or equal to 1.</p> | 2             |

## 19.16 Configuring the Localized Log Levels

### Scenarios

The default log level of localized container is **INFO**. You can change the log level by configuring **yarn.nodemanager.container-localizer.java.opts**.

### Configuration Description

On Manager, choose **Cluster** > *Name of the desired cluster* > **Service** > **Yarn** > **Configuration**. Select **All Configurations** and set the following parameters in the configuration file **yarn-site.xml** of NodeManager to change the log level.

**Table 19-19** Parameter description

| Parameter                                      | Description                                                                            | Default Value                                      |
|------------------------------------------------|----------------------------------------------------------------------------------------|----------------------------------------------------|
| yarn.nodemanager.container-localizer.java.opts | The additional <b>jvm</b> parameters are provided for the localized container process. | -Xmx256m -Djava.security.krb5.conf=\${KRB5_CONFIG} |

The default value is **-Xmx256m -Djava.security.krb5.conf=\${KRB5\_CONFIG}** and the default log level is info. To change the localized log level of the container, add the following content:

```
-Dhadoop.root.logger=<LOG_LEVEL>,localizationCLA
```

#### Example:

To change the local log level to **DEBUG**, set the parameter as follows:

```
-Xmx256m -Dhadoop.root.logger=DEBUG,localizationCLA
```

 **NOTE**

Allowed log levels are as follows: FATAL, ERROR, WARN, INFO, DEBUG, TRACE, and ALL.

## 19.17 Configuring Users That Run Tasks

### Scenario

Currently, YARN allows the user that starts the NodeManager to run the task submitted by all other users, or the users to run the task submitted by themselves.

### Configuration Description

On Manager, choose **Cluster** > *Name of the desired cluster* > **Services** > **Yarn** > **Configurations**. Click **All Configurations** Enter a parameter name in the search box.

**Table 19-20** Parameter description

| Parameter                                      | Description                               | Default Value                                                                                                                                                 |
|------------------------------------------------|-------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|
| yarn.nodemanager.linux-container-executor.user | Indicates the user who runs a task.       | The value is left blank by default.<br><b>NOTE</b><br>The value is left blank by default. The user who submits a task is the actual person who runs the task. |
| yarn.nodemanager.container-executor.class      | Indicates the executor who starts a task. | org.apache.hadoop.yarn.server.nodemanager.EnhancedLinuxContainerExecutor                                                                                      |

 **NOTE**

- Set **yarn.nodemanager.linux-container-executor.user** to configure the user who runs the container. This parameter is left blank by default. The user who submits the task is the person who runs the container. This parameter is valid only when **yarn.nodemanager.container-executor.class** is set to **org.apache.hadoop.yarn.server.nodemanager.EnhancedLinuxContainerExecutor**.
- In non-security mode, if **yarn.nodemanager.linux-container-executor.user** is set to **omm**, **yarn.nodemanager.linux-container-executor.nonsecure-mode.local-user** must also be set to **omm**.
- For security reasons, it is advised to retain the default values of **yarn.nodemanager.linux-container-executor.user** and **yarn.nodemanager.container-executor.class**.

## 19.18 Yarn Log Overview

### Log Description

The default paths for saving Yarn logs are as follows:

- ResourceManager: **/var/log/Bigdata/yarn/rm** (run logs) and **/var/log/Bigdata/audit/yarn/rm** (audit logs)
- NodeManager: **/var/log/Bigdata/yarn/nm** (run logs) and **/var/log/Bigdata/audit/yarn/nm** (audit logs)

Log archive rule: The automatic compression and archive function is enabled for Yarn logs. By default, when the size of a log file exceeds 50 MB, the log file is automatically compressed. The naming rule of the compressed log file is as follows: *<Original log file name>-<yyyy-mm-dd\_hh-mm-ss>.[ID].log.zip*. A maximum of 100 latest compressed files are retained. The number of compressed files can be configured on Manager.

**Log archive rule:**

**Table 19-21** Yarn log list

| Log Type | Log File Name                                   | Description                                                                                          |
|----------|-------------------------------------------------|------------------------------------------------------------------------------------------------------|
| Run log  | hadoop-<SSH_USER>-<process_name>-<hostname>.log | Yarn component log file, which records most of the logs generated when the Yarn component is running |
|          | yarn-<SSH_USER>-<process_name>-<hostname>.out   | Log file that records Yarn running environment information                                           |
|          | <process_name>-<SSH_USER>-<DATE>-<PID>-gc.log   | Garbage collection log file                                                                          |
|          | yarn-haCheck.log                                | ResourceManager active/standby status detection log file                                             |
|          | yarn-service-check.log                          | Log file that records the health check details of the Yarn service                                   |
|          | yarn-start-stop.log                             | Log file that records the startup and stop of the Yarn service                                       |
|          | yarn-prestart.log                               | Log file that records cluster operations before the Yarn service startup                             |

| Log Type   | Log File Name                                            | Description                                                                           |
|------------|----------------------------------------------------------|---------------------------------------------------------------------------------------|
|            | yarn-postinstall.log                                     | Work log file after installation and before startup of the Yarn service               |
|            | hadoop-commission.log                                    | Yarn service entry log file                                                           |
|            | yarn-cleanup.log                                         | Log file that records the cleanup operation during uninstallation of the Yarn service |
|            | yarn-refreshqueue.log                                    | Yarn queue refresh log file                                                           |
|            | upgradeDetail.log                                        | Upgrade log file                                                                      |
|            | stderr/stdin/syslog                                      | Container log file of the applications running on the Yarn service                    |
|            | yarn-application-check.log                               | Check log file of applications running on the Yarn service                            |
|            | yarn-appsummary.log                                      | Running result log file of applications running on the Yarn service                   |
|            | yarn-switch-resourcemanager.log                          | Run log file that records the Yarn active/standby switchover                          |
|            | ranger-yarn-plugin-enable.log                            | Log file that records the enabling of Ranger authentication for Yarn                  |
|            | yarn-nodemanager-period-check.log                        | Periodic check log of Yarn NodeManager                                                |
|            | yarn-resourcemanager-period-check.log                    | Periodic check log of Yarn ResourceManager                                            |
|            | hadoop.log                                               | Hadoop client logs                                                                    |
|            | env.log                                                  | Environment information log file before the instance is started or stopped.           |
| Audit logs | yarn-audit-<process_name>.log<br>ranger-plugin-audit.log | Yarn operation audit log file                                                         |
|            | SecurityAuth.audit                                       | Yarn security audit log file                                                          |

## Log Level

**Table 19-22** describes the log levels supported by Yarn, including OFF, FATAL, ERROR, WARN, INFO, and DEBUG, from high priority to low. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 19-22** Log levels

| Level | Description                                                                              |
|-------|------------------------------------------------------------------------------------------|
| FATAL | Logs of this level record critical error information about the current event processing. |
| ERROR | Logs of this level record error information about the current event processing.          |
| WARN  | Logs of this level record exception information about the current event processing.      |
| INFO  | Logs of this level record normal running status information about the system and events. |
| DEBUG | Logs of this level record the system as well as system debugging information.            |

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of the Yarn service by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** On the menu bar on the left, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Click **Save Configuration**. In the dialog box that is displayed, click **OK** to make the setting take effect.

 **NOTE**

The configurations take effect immediately without the need to restart the service.

----End

## Log Format

The following table lists the Yarn log formats.

**Table 19-23** Log formats

| Log Type  | Format                                                                                                                               | Example                                                                                                                                                                                                                                                                  |
|-----------|--------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Run log   | <yyyy-MM-dd<br>HH:mm:ss,SSS> <Log Level> <br><Thread that generates the<br>log> <Message in the log> <br><Location of the log event> | 2014-09-26 14:18:59,109  <br>INFO   main   Client<br>environment:java.compiler=<br><NA>  <br>org.apache.zookeeper.Enviro<br>nment.logEnv(Environment.<br>java:100)                                                                                                       |
| Audit log | <yyyy-MM-dd<br>HH:mm:ss,SSS> <Log Level> <br><Thread that generates the<br>log> <Message in the log> <br><Location of the log event> | 2014-09-26 14:24:43,605  <br>INFO   main-EventThread  <br>USER=omm<br>OPERATION=refreshAdmin<br>Acls TARGET=AdminService<br>RESULT=SUCCESS  <br>org.apache.hadoop.yarn.ser<br>ver.resourcemanager.RMAu<br>ditLogger\$LogLevel<br>\$6.printLog(RMAuditLogger.<br>java:91) |

## 19.19 Yarn Performance Tuning

### 19.19.1 Preempting a Task

#### Scenario

The capacity scheduler of ResourceManager implements job preemption to simplify job running in queues and improve resource utilization. The process is as follows:

1. Assume that there are two queues (Queue A and Queue B). The capacity of Queue A is 25%, and the capacity of Queue B is 75%.
2. In the initial state, Task 1 is distributed to Queue A for processing, requiring 75% cluster resources. Task 2 is distributed to Queue B for processing, requiring 50% cluster resources.
3. Task 1 uses 25% cluster resources provided by Queue A and 50% resources from Queue B. Queue B reserves 25% cluster resources.
4. If task preemption is enabled, the resources of Task 1 will be preempted. Queue B preempts 25% cluster resources from Queue A for Task 2.
5. Task 1 will be executed when Task 2 is complete and the cluster has sufficient resources.

#### Procedure

Navigation path for setting parameters:

Go to the **All Configurations** page of Yarn and enter a parameter name in the search box by referring to [Modifying Cluster Service Configuration Parameters](#).

**Table 19-24** Parameter description

| Parameter                                                            | Description                                                                                                                                                                                                                                                                                                                                                                                                                          | Default Value                                                                                       |
|----------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------|
| yarn.resourcemanager.scheduler.monitor.enable                        | Whether to start scheduler monitoring according to <b>yarn.resourcemanager.scheduler.monitor.policies</b> . If this parameter is set to <b>true</b> , scheduler monitoring is enabled based on policies specified by <b>yarn.resourcemanager.scheduler.monitor.policies</b> and task resource preemption is enabled based on the scheduler information. If this parameter is set to <b>false</b> , scheduler monitoring is disabled. | false                                                                                               |
| yarn.resourcemanager.scheduler.monitor.policies                      | List of the SchedulingEditPolicy class to be used with the scheduler                                                                                                                                                                                                                                                                                                                                                                 | org.apache.hadoop.yarn.server.resourcemanager.monitor.capacity.ProportionalCapacityPreemptionPolicy |
| yarn.resourcemanager.monitor.capacity.preemption.observe_only        | <ul style="list-style-type: none"> <li>If this parameter is set to <b>true</b>, policies will be applied but task resource preemption will not be performed.</li> <li>If this parameter is set to <b>false</b>, policies will be applied and task resource preemption will be performed based on the policies.</li> </ul>                                                                                                            | false                                                                                               |
| yarn.resourcemanager.monitor.capacity.preemption.monitoring_interval | Monitoring interval, in millisecond. If this parameter is set to a larger value, capacity detection will not be performed frequently.                                                                                                                                                                                                                                                                                                | 3000                                                                                                |

| Parameter                                                                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                          | Default Value |
|-----------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.resourcemanager.monitor.capacity.preemption.max_wait_before_kill       | <p>Interval between the time when a resource preemption request is sent and the time when the container is stopped (resources are released), in millisecond. The value must be greater than or equal to <b>0</b>.</p> <p>By default, if ApplicationMaster does not stop the container within 15 seconds, ResourceManager will forcibly stop the container after 15 seconds.</p>                                                      | 15000         |
| yarn.resourcemanager.monitor.capacity.preemption.total_preemption_per_round | <p>Maximum resource preemption ratio in a period. This value can be used to limit the speed at which containers are reclaimed from the cluster. After the expected total preemption value is calculated, the policy scales the preemption ratio back to this limit.</p>                                                                                                                                                              | 0.1           |
| yarn.resourcemanager.monitor.capacity.preemption.max_ignored_over_capacity  | <p>Resource preemption dead zone = Total number of resources in the cluster x Value of this configuration item + Original resources of a queue (for example, Queue A). When resources actually used by a task in Queue A exceeds the preemption dead zone, the resource beyond the preemption dead zone is preempted. The value range is 0 to 1.</p> <p><b>NOTE</b><br/>A smaller value is recommended for effective preemption.</p> | 0             |

| Parameter                                                                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 | Default Value |
|-----------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.resourcemanager.monitor.capacity.preemption.natural_termination_factor | <p>Preemption percentage. Containers preempt only this percentage of the resources.</p> <p>For example, a termination factor of 0.5 will reclaim almost 95% of resources within 5 times of <b>yarn.resourcemanager.monitor.capacity.preemption.max_wait_before_kill</b>, even in the absence of natural termination. That is, 5 consecutive preemptions will be performed and each time half of the target resources will be preempted. The trend is geometric convergence. The interval of each preemption is <b>yarn.resourcemanager.monitor.capacity.preemption.max_wait_before_kill</b>. The value range is 0 to 1.</p> | 1             |

## 19.19.2 Setting the Task Priority

### Scenario

The resource contention scenarios of a cluster are as follows:

1. Submit two jobs (Job 1 and Job 2) with lower priorities.
2. Some tasks of running Job 1 and Job 2 are in the running state. However, some tasks are pending due to resource deficiency because the capacity of cluster or queue resources is limited.
3. Submit a job (Job 3) with a higher priority. In this case, after the running tasks of Job 1 and Job 2 are complete, their resources will be released and then allocated to the pending tasks of Job 3.
4. After Job 3 is complete, its resources will be released and then allocated to Job 1 and Job 2.

Users can use capacity scheduler of ResourceManager to set the task priority in Yarn because the task priority is implemented by the capacity scheduler of ResourceManager.

### Procedure

Set the **mapreduce.job.priority** parameter and use CLI or API to set the task priority.

- Through the CLI  
When submitting tasks, add the **-Dmapreduce.job.priority=<priority>** parameter.

*<priority>* can be set to any of the following values:

- VERY\_HIGH
  - HIGH
  - NORMAL
  - LOW
  - VERY\_LOW
- Through the API  
You can also set the task priority through the API.  
Set `Configuration.set("mapreduce.job.priority", <priority>)` or `Job.setPriority(JobPriority priority)`.

## 19.19.3 Optimizing Node Configuration

### Scenario

After the scheduler of a big data cluster is properly configured, you can adjust the available memory, CPU resources, and local disk of each node to optimize the performance.

The configuration items are as follows:

- Available memory
- Number of vCPUs
- Physical CPU usage
- Coordination of memory and CPU resources
- Local disk

### Procedure

For details about how to adjust parameter settings, see [Modifying Cluster Service Configuration Parameters](#).

- **Available memory**  
Except the memory allocated to the OS and other services, allocate as much as possible memory to Yarn. You can adjust the following parameters to improve resource utilization.  
Assume that a container uses 512 MB memory by default, then the memory usage formula is: 512 MB x Number of containers.  
By default, the Map or Reduce container uses one vCPU and 1,024 MB memory, and ApplicationMaster uses 1,536 MB memory.

| Parameter                          | Description                                                                                                                                                                                                                                                                                                                         | Default Value |
|------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.nodemanager.resourcememory-mb | Physical memory that can be allocated to containers, in MB. The value must be greater than 0. You are advised to set the parameter value to 75% to 90% of the total physical memory of nodes. If the node has permanent processes of other services, reduce this parameter value to reserve sufficient resources for the processes. | <b>16384</b>  |

- **Number of vCPUs**

You are advised to set this parameter to 1.5 to 2 times the number of logical CPUs. If the upper layer computing applications have low computing capability requirements, you can set the parameter to two times the number of logical CPUs.

| Parameter                                  | Description                                                                                                                                                          | Default Value |
|--------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.nodemanager.resourcememory-cpu-vcores | Number of vCPUs that can be used by Yarn on the node. The default value is <b>8</b> . You are advised to set the value to 1.5 to 2 times the number of logical CPUs. | <b>8</b>      |

- **Physical CPU usage**

You are advised to reserve appropriate CPUs for the OS and the processes, such as database and HBase, and allocate the remaining CPUs to Yarn. You can set the following parameters to adjust the physical CPU usage.

| Parameter                                               | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           | Default Value |
|---------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| yarn.nodemanager.resource.percentage-physical-cpu-limit | <p>Physical CPU percentage that can be used by Yarn on a node. The default value is <b>90</b>, indicating that no CPU control is implemented and Yarn can use all CPU resources. You can only view the parameter. To change the value of this parameter, set the value of RES_CPUSET_PERCENTAGE of YARN. You are advised to set this parameter to the percentage of CPU resources that can be used by the YARN cluster.</p> <p>For example, If 20% of CPU resources are used by other services (such as HBase, HDFS, and Hive) and system processes on the node, the CPU resources can be scheduled for Yarn is <math>1 - 20\% = 80\%</math>. Therefore, you can set this parameter to <b>80</b>.</p> | 90            |

- **Local disk**

MapReduce writes the intermediate job execution results in local disks. Therefore, configure disks as much as possible and disk space as large as possible. A simple way is to configure the same number of disks as DataNode except for the last directory.

 **NOTE**

Use commas (,) to separate multiple disks.

| Parameter                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                   | Default Value                                |
|---------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------|
| yarn.nodemanager.log-dirs | <p>Directories in which logs are stored. Multiple directories can be specified.</p> <p>Storage location of container logs. The default value is % <b>{@auto.detect.datapart.nm.logs}</b>. If there is a data partition, a path list similar to <b>/srv/BigData/hadoop/data1/nm/containerlogs,/srv/BigData/hadoop/data2/nm/containerlogs</b> is generated based on the data partition. If there is no data partition, the default path <b>/srv/BigData/yarn/data1/nm/containerlogs</b> is generated. In addition to using expressions, you can enter a complete list of paths, such as <b>/srv/BigData/yarn/data1/nm/containerlogs</b> or <b>/srv/BigData/yarn/data1/nm/containerlogs,/srv/BigData/yarn/data2/nm/containerlogs</b>. In this way, data is stored in all the configured directories, which are usually on different devices. To ensure disk I/O load balancing, you are advised to provide several paths and each path corresponds to an independent disk. The localized log directory of the application exists in the relative path <b>/application_%{appid}</b>. The log directory of an independent container, that is, <b>container_{\$contid}</b>, is the subdirectory of this directory. Each container directory contains the <b>stderr</b>, <b>stdin</b>, and <b>syslog</b> files generated by the container. To add a directory, for example, <b>/srv/BigData/yarn/data2/nm/containerlogs</b>, you need to delete the files in <b>/srv/BigData/yarn/data2/nm/containerlogs</b> first. Then, assign the same read and write permissions to <b>/srv/BigData/yarn/data2/nm/containerlogs</b> as those of <b>/srv/</b></p> | <p>%<br/>{@auto.detect.datapart.nm.logs}</p> |

| Parameter | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | Default Value |
|-----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
|           | <p><b>BigData/yarn/data1/nm/containerlogs</b>, and change <b>/srv/BigData/yarn/data1/nm/containerlogs</b> to <b>/srv/BigData/yarn/data1/nm/containerlogs,/srv/BigData/yarn/data2/nm/containerlogs</b>. You can add directories, but do not modify or delete existing directories. Otherwise, NodeManager data will be lost and services will be unavailable.</p> <p>Default value: %<br/> <b>{@auto.detect.datapart.nm.logs}</b><br/> <b>}</b></p> <p>Exercise caution when modifying this parameter. If the configuration is incorrect, the services are unavailable. If the value of this configuration item at the role level is changed, the value of this configuration item at all instance levels will be changed. If the value of this configuration item at the instance level is changed, the value of this configuration item of other instances remains unchanged.</p> |               |

| Parameter                   | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       | Default Value                                            |
|-----------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------|
| yarn.nodemanager.local-dirs | <p>Storage location of files after localization. The default value is %<br/> <b>{@auto.detect.datapart.nm.localdir}</b>. If there is a data partition, a path list similar to <b>/srv/BigData/hadoop/data1/nm/localdir,/srv/BigData/hadoop/data2/nm/localdir</b> is generated based on the data partition. If there is no data partition, the default path <b>/srv/BigData/yarn/data1/nm/localdir</b> is generated. In addition to using expressions, you can enter a complete list of paths, such as <b>/srv/BigData/yarn/data1/nm/localdir</b> or <b>/srv/BigData/yarn/data1/nm/localdir,/srv/BigData/yarn/data2/nm/localdir</b>. In this way, data is stored in all the configured directories, which are usually on different devices. To ensure disk I/O load balancing, you are advised to provide several paths and each path corresponds to an independent disk. The localized file directory of the application is stored in the relative path <b>/usercache/%{user}/appcache/application_%{appid}</b>. The working directory of an independent container, that is, <b>container_%{contid}</b>, is the subdirectory of the directory. To add a directory, for example, <b>/srv/BigData/yarn/data2/nm/localdir</b>, you need to delete the files in <b>/srv/BigData/yarn/data2/nm/localdir</b> first. Then, assign the same read and write permissions to <b>/srv/BigData/hadoop/data2/nm/localdir</b> as those of <b>/srv/BigData/hadoop/data1/nm/localdir</b>, and change <b>/srv/BigData/yarn/data1/nm/localdir</b> to <b>/srv/BigData/yarn/data1/nm/localdir,/srv/BigData/yarn/data2/nm/localdir</b>. You can add</p> | <p>%<br/> <b>{@auto.detect.datapart.nm.localdir}</b></p> |

| Parameter | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              | Default Value |
|-----------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
|           | <p>directories, but do not modify or delete existing directories. Otherwise, NodeManager data will be lost and services will be unavailable.</p> <p>Default value: %<br/><b>{@auto.detect.datapart.nm.local dir}</b></p> <p>Exercise caution when modifying this parameter. If the configuration is incorrect, the services are unavailable. If the value of this configuration item at the role level is changed, the value of this configuration item at all instance levels will be changed. If the value of this configuration item at the instance level is changed, the value of this configuration item of other instances remains unchanged.</p> |               |

## 19.20 Common Issues About Yarn

### 19.20.1 Why Mounted Directory for Container is Not Cleared After the Completion of the Job While Using CGroups?

#### Question

Why mounted directory for Container is not cleared after the completion of the job while using CGroups?

#### Answer

The mounted path for the Container should be cleared even if job is failed.

This happens due to the deletion timeout. Some task takes more time to complete than the deletion time.

To avoid this scenario, you can go to the **All Configurations** page of Yarn by referring to [Modifying Cluster Service Configuration Parameters](#). Search for the **yarn.nodemanager.linux-container-executor.cgroups.delete-timeout-ms** configuration item in the search box to change the deletion interval. The value is in milliseconds.

## 19.20.2 Why the Job Fails with HDFS\_DELEGATION\_TOKEN Expired Exception?

### Question

Why is the HDFS\_DELEGATION\_TOKEN expired exception reported when a job fails in security mode?

### Answer

HDFS\_DELEGATION\_TOKEN expires because the token is not updated or it is accessed after max. lifetime.

Ensure the following parameter value of max. lifetime of the token is greater than the job running time.

**dfs.namenode.delegation.token.max-lifetime=604800000** (1 week by default)

Go to the **All Configurations** page of HDFS by referring to [Modifying Cluster Service Configuration Parameters](#) and search for this parameter in the search box.

#### NOTE

You are advised to set this parameter to a value that is multiple times of the number of hours within the max. lifecycle of the token.

## 19.20.3 Why Are Local Logs Not Deleted After YARN Is Restarted?

### Question

If Yarn is restarted in either of the following scenarios, local logs will not be deleted as scheduled and will be retained permanently:

- When Yarn is restarted during task running, local logs are not deleted.
- When the task is complete and logs fail to be collected, restart Yarn before the logs are cleared as scheduled. In this case, local logs are not deleted.

### Answer

NodeManager has a restart recovery mechanism (for details, see [https://hadoop.apache.org/docs/r3.1.1/hadoop-yarn/hadoop-yarn-site/NodeManager.html#NodeManager\\_Restart](https://hadoop.apache.org/docs/r3.1.1/hadoop-yarn/hadoop-yarn-site/NodeManager.html#NodeManager_Restart)). Go to the **All Configurations** page of Yarn by referring to [Modifying Cluster Service Configuration Parameters](#). Set **yarn.nodemanager.recovery.enabled** of NodeManager to **true** to make the configuration take effect. The default value is **true**. In this way, redundant local logs are periodically deleted when the YARN is restarted.

## 19.20.4 Why the Task Does Not Fail Even Though AppAttempts Restarts for More Than Two Times?

### Question

Why the task does not fail even though AppAttempts restarts due to failure for more than two times?

### Answer

During the task execution process, if the **ContainerExitStatus** returns value **ABORTED**, **PREEMPTED**, **DISKS\_FAILED**, or **KILLED\_BY\_RESOURCEMANAGER**, the system will not count it as a failed attempt. Therefore, the task fails only when the AppAttempts fails actually, that is, the return value is not **ABORTED**, **PREEMPTED**, **DISKS\_FAILED**, or **KILLED\_BY\_RESOURCEMANAGER** for two times.

## 19.20.5 Why Is an Application Moved Back to the Original Queue After ResourceManager Restarts?

### Question

After I moved an application from one queue to another, why is it moved back to the original queue after ResourceManager restarts?

### Answer

This problem is caused by the constraints of the ResourceManager. If a running application is moved to another queue, information about the new queue will not be stored in the ResourceManager after the ResourceManager restarts.

Assume that a user submits a MapReduce application to the leaf queue test11. If the leaf queue test11 is deleted when the application is running, the application will go to the lost\_and\_found queue and the application stops. To start the application, the user moves the application to the leaf queue test21 and the application resumes running. If the ResourceManager restarts, the displayed submission queue is lost\_and\_found, but not test21.

If the application is not complete, the ResourceManager only stores the queue information before the application is moved. As a result, the application is moved back to the original queue. To solve this problem, move the application again after the ResourceManager is restarted to write information about the new queue to the ResourceManager.

## 19.20.6 Why Does Yarn Not Release the Blacklist Even All Nodes Are Added to the Blacklist?

### Question

Why does Yarn not release the blacklist even all nodes are added to the blacklist?

## Answer

In Yarn, when the number of application nodes added to the blacklist by ApplicationMaster (AM) reaches a certain proportion (the default value is 33% of the total number of nodes), the AM automatically releases the blacklist. In this way, all available nodes are added to the blacklist and tasks can obtain node resources.

Assume that there are 8 nodes in a cluster and they are divided into pool A and pool B by NodeLabel. There are two nodes in pool B. A user submits a task App1 to pool B, but there is not sufficient HDFS space and App1 fails to run. As a result, two nodes in pool B are added to the blacklist by the AM of App1. According to the preceding principles, 2 is less than the 33% of 8. Therefore, Yarn does not release the blacklist, and App1 cannot obtain resources and keeps running. Even if the node that is added to the blacklisted is recovered, App1 still cannot obtain resources.

The preceding principles do not apply to the resource pool scenario. Therefore, you can change the value of the client parameter **yarn.resourcemanager.am-scheduling.node-blacklisting-disable-threshold** to **(nodes number of pool / total nodes) \* 33%** to solve this problem.

## 19.20.7 Why Does the Switchover of ResourceManager Occur Continuously?

### Question

The switchover of ResourceManager occurs continuously when multiple, for example 2,000, tasks are running concurrently, causing the Yarn service unavailable.

### Answer

The cause is that the time of full GarbageCollection exceeds the interaction duration threshold between the ResourceManager and ZooKeeper duration threshold. As a result, the connection between the ResourceManager and ZooKeeper fails and the switchover of ResourceManager occurs continuously.

When there are multiple tasks, ResourceManager saves the authentication information about multiple tasks and transfers the information to NodeManagers through heartbeat, which is called heartbeat response. The lifecycle of heartbeat response is short. The default value is 1s. Normally, heartbeat response can be reclaimed during the JVM minor GarbageCollection. However, if there are multiple tasks and there are a lot of nodes, for example 5000 nodes, in the cluster, the heartbeat response of multiple nodes occupy a large amount of memory. As a result, the JVM cannot completely reclaim the heartbeat response during minor GarbageCollection. The heartbeat response failed to be reclaimed accumulate and the JVM full GarbageCollection is triggered. The JVM GarbageCollection is in a blocking mode, in other words, no jobs are performed during the GarbageCollection. Therefore, if the duration of full GarbageCollection exceeds the periodical interaction duration threshold between the ResourceManager and ZooKeeper, the switchover occurs.

Log in to FusionInsight Manager and choose **Cluster > Services > Yarn > Configurations > All Configurations**. On the left of the page, choose **Yarn >**

**Customization**, you can add the `yarn.resourcemanager.zk-timeout-ms` customized parameter to the `yarn-site.xml` file under the *Client installation path*/`Yarn/config/` to increase the threshold of the periodic interaction duration between ResourceManager and ZooKeeper (the value range is less than or equal to 90,000 ms) to solve the problem of continuous active/standby ResourceManager switchover.

## 19.20.8 Why Does a New Application Fail If a NodeManager Has Been in Unhealthy Status for 10 Minutes?

### Question

Why does a new application fail if a NodeManager has been in unhealthy status for 10 minutes?

### Answer

When `nodeSelectPolicy` is set to **SEQUENCE** and the first NodeManager connected to the ResourceManager is unavailable, the ResourceManager attempts to assign tasks to the same NodeManager in the period specified by `yarn.nm.liveness-monitor.expiry-interval-ms`.

You can use either of the following methods to avoid the preceding problem:

- Use another `nodeSelectPolicy`, for example, **RANDOM**.
- Go to the **All Configurations** page of Yarn by referring to [Modifying Cluster Service Configuration Parameters](#). Search for the following parameters in the search box and modify the following attributes in the `yarn-site.xml` file:  
`yarn.resourcemanager.am-scheduling.node-blacklisting-enabled = true;`  
`yarn.resourcemanager.am-scheduling.node-blacklisting-disable-threshold = 0.5.`

## 19.20.9 What Is the Queue Replacement Policy?

### Question

If a user belongs to multiple user groups with different default queue configurations, which queue will be selected as the default queue when an application is submitted?

### Answer

In the `superior-users.xml` file, if the default queue of the user is configured, the configured default queue will be used. If the default queue of the user is not specified, the default queue of the first user group in the `superior-users.xml` file is used.

## 19.20.10 Why Does an Error Occur When I Query the ApplicationID of a Completed or Non-existing Application Using the RESTful APIs?

### Question

Why does an error occur when I query the applicationID of a completed or non-existing application using the RESTful APIs?

### Answer

The Superior scheduler only stores the applicationIDs of running applications. If you view the applicationID of a completed or non-existing application by accessing the RESTful API at [https://<SS\\_REST\\_SERVER>/ws/v1/sscheduler/applications/{application\\_id}](https://<SS_REST_SERVER>/ws/v1/sscheduler/applications/{application_id}), the 404 error is returned by the server. If Chrome web browser is used, the **Error Occurred** message is displayed because Chrome preferentially responds in the application/xml format. If Internet Explorer is used, the **404** error code is displayed because IE web browser preferentially responds in the application/json format.

## 19.20.11 Why May A Single NodeManager Fault Cause MapReduce Task Failures in the Superior Scheduling Mode?

### Question

In Superior scheduling mode, if a single NodeManager is faulty, why may the MapReduce tasks fail?

### Answer

In normal cases, when the attempt of a single task of an application fails on a node for three consecutive times, the AppMaster of the application adds the node to the blacklist. Then, the AppMaster instructs the scheduler not to schedule the task to the node to avoid task failure.

However, by default, if 33% nodes in the cluster are added to the blacklist, the scheduler ignores the blacklisted nodes. Therefore, the blacklist feature is prone to become invalid in small cluster scenarios. For example, there are only three nodes in the cluster. If one node is faulty, the blacklist mechanism becomes invalid. The scheduler continues to schedule the task to the node no matter how many times the attempt of the task fails on the node. As a result, the number of attempts of the task reaches the maximum (4 times by default for MapReduce). And the MapReduce tasks failed.

Workaround:

The `yarn.resourcemanager.am-scheduling.node-blacklisting-disable-threshold` parameter indicates the threshold for ignoring blacklisted nodes, in percentage. You are advised to increase the value of this parameter based on the cluster scale. For example, you are advised to set this parameter to **50%** for a three-node cluster.

 NOTE

Currently, the Capacity scheduler does not have this problem. The reason is that the Capacity scheduler allocates resources based on the heartbeat messages reported by NodeManager. When the NodeManager of a node is disconnected, the heartbeat of the node is lost, and the Capacity scheduler does not allocate tasks to the node.

The framework design of the Superior scheduler is time-based asynchronous scheduling. When the NodeManager is faulty, ResourceManager cannot quickly detect that the NodeManager is faulty (10 minutes by default). Therefore, the Superior scheduler still schedules tasks to the node, causing task failures.

## 19.20.12 Why Are Applications Suspended After They Are Moved From Lost\_and\_Found Queue to Another Queue?

### Question

When a queue is deleted when there are applications running in it, these applications are moved to the "lost\_and\_found" queue. When these applications are moved back to another healthy queue, some tasks are suspended.

### Answer

If no label expression is set for the current application, the default label expression of the queue is used as label expression for new container/resource demands requested by the application. If there is no default label expression of the queue, then **default label** is considered as the label expression for new container/resource demands requested by the application.

When application app1 is submitted to the queue Q1, **label1**, the default label expression of the queue, is used for the application's new resource requests/containers. If Q1 is deleted when app1 is running, app1 is moved to the "lost\_and\_found" queue. Because there is no label expression of the "lost\_and\_found" queue, **default label** is used as the label expression of app1's new resource requests/containers. Assume that app1 is moved to another normal queue Q2. If Q2 supports **label1** and **default label**, app1 can run properly. If Q2 does not support **label1** or **default label**, the resource request with **label1** or **default label** cannot obtain resources, causing task suspension.

To solve this problem, ensure that the queue to which the application is moved from "lost\_and\_found" queue supports label expression of the moved application.

You are not advised to delete a queue in which there are running applications.

## 19.20.13 How Do I Limit the Size of Application Diagnostic Messages Stored in the ZKstore?

### Question

How do I limit the size of application diagnostic messages stored in the ZKstore?

### Answer

In some cases, it has been observed that diagnostic messages may grow infinitely. Because diagnostic messages are stored in the ZKstore, it is not recommended

that you allow diagnostic messages to grow indefinitely. Therefore, a property parameter is needed to set the maximum size of the diagnostic message.

If you need to set `yarn.app.attempt.diagnostics.limit.kc`, go to the **All Configurations** page by referring to [Modifying Cluster Service Configuration Parameters](#) and search for the following parameters in the search box:

**Table 19-25** Parameter description

| Parameter                                          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                       | Default Value |
|----------------------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| <code>yarn.app.attempt.diagnostics.limit.kc</code> | Data size of the diagnosis message for each application connection, in kilobytes (number of characters x 1,024). When ZooKeeper is used to store the behavior status of applications, the size of diagnosis messages needs to be limited to prevent Yarn from overloading ZooKeeper. If <code>yarn.resourcemanager.state-store.max-completed-applications</code> is set to a large value, you need to decrease the value of this property to limit the total size of stored data. | 64            |

## 19.20.14 Why Does a MapReduce Job Fail to Run When a Non-ViewFS File System Is Configured as ViewFS?

### Question

Why does a MapReduce job fail to run when a non-ViewFS file system is configured as ViewFS?

### Answer

When a non-ViewFS file system is configured as a ViewFS using cluster, the user permissions on folders in the ViewFS file system are different from those of non-ViewFS folders in the default NameService. The submitted MapReduce job fails to be executed because the directory permissions are inconsistent.

When configuring the ViewFS user in the cluster, you need to check and verify the directory permissions. Before submitting a job, change the ViewFS folder permissions based on the default NameService folder permissions.

The following table lists the default permission structure of directories configured in ViewFS. If the configured directory permissions are not included in the following table, you must change the directory permissions accordingly.

**Table 19-26** Default permission structure of directories configured in ViewFS

| Parameter                                   | Description                                                                                       | Default Value                                                   | Default value and default permissions on the parent directory |
|---------------------------------------------|---------------------------------------------------------------------------------------------------|-----------------------------------------------------------------|---------------------------------------------------------------|
| yarn.nodemanager.remote-app-log-dir         | On the default file system (usually HDFS), specify the directory to which the NM aggregates logs. | logs                                                            | 777                                                           |
| yarn.nodemanager.remote-app-log-archive-dir | Directory for archiving logs                                                                      | -                                                               | 777                                                           |
| yarn.app.mapreduce.am.staging-dir           | Staging directory used when a job is submitted                                                    | /tmp/hadoop-yarn/staging                                        | 777                                                           |
| mapreduce.jobhistory.intermediate-done-dir  | Directory for storing historical files of MapReduce jobs                                          | \${yarn.app.mapreduce.am.staging-dir}/history/done_intermediate | 777                                                           |
| mapreduce.jobhistory.done-dir               | Directory of historical files managed by the MR JobHistory Server.                                | \${yarn.app.mapreduce.am.staging-dir}/history/done              | 777                                                           |

## 19.20.15 Why Do Reduce Tasks Fail to Run in Some OSs After the Native Task Feature is Enabled?

### Question

After the Native Task feature is enabled, Reduce tasks fail to run in some OSs.

### Answer

When - **Dmapreduce.job.map.output.collector.class=org.apache.hadoop.mapred.native.task.NativeMapOutputCollectorDelegator** is executed to enable the Native Task feature during the running of MapReduce tasks that contain Reduce tasks, the tasks fail to run in some OSs, and the error message "version 'GLIBCXX\_3.4.20' not found" is displayed in logs. The cause is that the GLIBCXX version of the OSs is too early. As a result, the libnativetask.so.1.0.0 library on which the feature depends cannot be loaded, leading to task failures.

Workaround:

Set **mapreduce.job.map.output.collector.class** to  
**org.apache.hadoop.mapred.MapTask\$MapOutputBuffer**.

# 20 Using ZooKeeper

---

## 20.1 Using ZooKeeper from Scratch

ZooKeeper is an open-source, highly reliable, and distributed consistency coordination service. ZooKeeper is designed to solve the problem that data consistency cannot be ensured for complex and error-prone distributed systems. There is no need to develop dedicated collaborative applications, which is suitable for high availability services to ensure data consistency.

### Background Information

Before using the client, you need to download and update the client configuration file on all clients except the client of the active management node.

### Procedure

**Step 1** Download the client configuration file.

1. Log in to FusionInsight Manager. For details, see. [Accessing FusionInsight Manager](#)
2. Choose **Cluster** > *Name of the desired cluster* > **Dashboard** > **More** > **Download Client**.
3. Download the cluster client.

Set **Select Client Type** to **Configuration Files Only**, select a platform type, and click **OK** to generate the client configuration file which is then saved in the `/tmp/FusionInsight-Client/` directory on the active management node by default.

**Step 2** Log in to the active management node of Manager.

1. Log in to any node where Manager is deployed as user **root**.
2. Run the following command to identify the active and standby nodes:

```
sh ${BIGDATA_HOME}/om-server/om/sbin/status-oms.sh
```

In the command output, the value of **HAActive** for the active management node is **active**, and that for the standby management node is **standby**. In the

following example, **node-master1** is the active management node, and **node-master2** is the standby management node.

| HAMode       | HostName     | HAVersion   | StartTime           | HAActive |
|--------------|--------------|-------------|---------------------|----------|
| double       |              |             |                     |          |
| NodeName     | HostName     | HAVersion   | StartTime           | HAActive |
| HAAllResOK   | HARunPhase   |             |                     |          |
| 192-168-0-30 | node-master1 | V100R001C01 | 2020-05-01 23:43:02 | active   |
| normal       | Activated    |             |                     |          |
| 192-168-0-24 | node-master2 | V100R001C01 | 2020-05-01 07:14:02 | standby  |
| normal       | Deactivated  |             |                     |          |

- Log in to the primary management node as user **root** and run the following command to switch to user **omm**:

```
sudo su - omm
```

- Step 3** Run the following command to go to the client installation directory, for example, **/opt/client**.

```
cd /opt/client
```

- Step 4** Run the following command to update the client configuration for the active management node.

```
sh refreshConfig.sh /opt/client Full path of the client configuration file package
```

For example, run the following command:

```
sh refreshConfig.sh /opt/client /tmp/FusionInsight-Client/  
FusionInsight_Cluster_1_Services_Client.tar
```

If the following information is displayed, the configurations have been updated successfully:

```
ReFresh components client config is complete.  
Succeed to refresh components client config.
```

- Step 5** Use the client on a Master node.

- On the active management node where the client is updated, for example, node **192-168-0-30**, run the following command to go to the client directory:

```
cd /opt/client
```

- Run the following command to configure environment variables:

```
source bigdata_env
```

- If Kerberos authentication has been enabled for the current cluster, run the following command to authenticate the current user. If Kerberos authentication is disabled for the current cluster, skip this step:

```
kinit MRS cluster user
```

Example: **kinit zookeeperuser**.

- Run the following Zookeeper client command:

```
zkCli.sh -server <zookeeper installation node IP>:<port>
```

Example: **zkCli.sh -server node-master1DGhZ:2181**

- Step 6** Run the ZooKeeper client command.

- Create a ZNode.

```
create /test
```

- View ZNode information.

```
ls /
```

3. Write data to the ZNode.  
set /test "zookeeper test"
4. View the data written to the ZNode.  
get /test
5. Delete the created ZNode.  
delete /test

----End

## 20.2 Common ZooKeeper Parameters

**Navigation path for setting parameters:**

Go to the **All Configurations** page of ZooKeeper by referring to [Modifying Cluster Service Configuration Parameters](#). Enter a parameter name in the search box.

**Table 20-1** Parameters

| Parameter             | Description                                                                                                                                                          | Default Value |
|-----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| skipACL               | Specifies whether to skip the permission check of the ZooKeeper node.                                                                                                | no            |
| maxClientCnxns        | Specifies the maximum number of connections of ZooKeeper. It is recommended this parameter is set to a larger value in scenarios with a large number of connections. | 2000          |
| LOG_LEVEL             | Specifies the log level. This parameter can be set to <b>DEBUG</b> during commissioning.                                                                             | INFO          |
| acl.compare.shortName | Specifies whether to perform ACL authentication only by principal username when the Znode ACL authentication type is SASL.                                           | true          |

| Parameter | Description                                                                                                                                                                                   | Default Value |
|-----------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| synclimit | Specifies the interval of synchronization between the follower and leader (unit: tick). If the leader does not respond within the specified time range, the connection cannot be established. | 15            |
| tickTime  | Specifies the duration of a tick (in milliseconds). It is the basic time unit used by ZooKeeper, which defines heartbeat and timeout durations.                                               | 4000          |

 **NOTE**

The ZooKeeper internal time is determined by **ticktime** and **synclimit**. To increase the ZooKeeper internal timeout interval, increase the timeout interval for the client to connect to ZooKeeper.

## 20.3 Using a ZooKeeper Client

### Scenario

Use a ZooKeeper client in an O&M scenario or service scenario.

### Prerequisites

You have installed the client. For example, the installation directory is **/opt/client**. The client directory in the following operations is only an example. Change it based on the actual installation directory onsite.

### Procedure

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to go to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** Run the following command to authenticate the user: (skip this step in common mode):

```
kinit Component service user
```

**Step 5** Run the following command to log in to the client tool:

```
zkCli.sh -server service IP address of the node where the ZooKeeper role instance locates:client port
```

----End

## 20.4 Configuring the ZooKeeper Permissions

### Scenario

Configure znode permission of ZooKeeper.

ZooKeeper uses an access control list (ACL) to implement znode access control. The ZooKeeper client specifies a znode ACL, and the ZooKeeper server determines whether a client that requests for a znode has related operation permission according to the ACL. ACL configuration involves the following four operations:

- Check znode ACLs in ZooKeeper.
- Add znode ACLs to ZooKeeper.
- Modify znode ACLs in ZooKeeper.
- Delete znode ACLs from ZooKeeper.

The ZooKeeper ACL permission is described as follows:

ZooKeeper supports five types of permission, create, delete, read, write, and admin. ZooKeeper permission control is of a znode level. That is, the permission configuration for a parent znode is not inherited by its child znodes. The ZooKeeper znode default permission is **world:anyone: cdrwa**. That is, any user has all permissions.

#### NOTE

ACL has three parts:

The first part is the authentication type. For example, **world** indicates all authentication types and **sasl** indicates the kerberos authentication type.

The second part is the account. For example, anyone indicates any user.

The third part is permission. For example, **cdrwa** indicates all permissions.

In particular, because starting the client in common mode does not need authentication, ACL with **sasl** authentication type cannot be used in common mode. Authentications of **sasl** scheme in this document are performed in clusters that have the security mode enabled.

**Table 20-2** Five types of ZooKeeper ACLs

| Permission Description | Permission Name | Permission Details                                                       |
|------------------------|-----------------|--------------------------------------------------------------------------|
| Create permission      | create(c)       | Users with this permission can create child znodes in the current znode. |
| Delete permission      | delete(d)       | Users with this permission can delete the current znode.                 |

| Permission Description    | Permission Name | Permission Details                                                                                                  |
|---------------------------|-----------------|---------------------------------------------------------------------------------------------------------------------|
| Read permission           | read(r)         | Users with this permission can obtain data of the current znode and list all the child znodes of the current znode. |
| Write permission          | write(w)        | Users with this permission can write data to the current znode and its child znodes.                                |
| Administration permission | admin(a)        | Users with this permission can set permission for the current znode.                                                |

## Impact on the System

### NOTICE

Modifying ZooKeeper ACLs is a critical operation. If znode permission is modified in ZooKeeper, other users may have no permission to access the znode and some system functions are abnormal. In 3.5.6 and later versions, users must have the read permission for the **getAcl** operation.

## Prerequisites

- The ZooKeeper client has been installed. For example, the installation directory is **/opt/client**.
- You have obtained the password of the MRS cluster administrator account.

## Procedure

**Start the ZooKeeper client.**

**Step 1** Log in to the server where the ZooKeeper client is installed as user **root**.

**Step 2** Run the following command to go to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 4** If the cluster has the security mode enabled, run the following command for user authentication and enter the username and password (Any authorized user. **admin** is used as an example.):

```
kinit admin
```

**Step 5** On the ZooKeeper client, run the following command to go to the ZooKeeper command-line interface (CLI):

```
sh zkCli.sh -server ZooKeeper plane IP address of any instance:clientPort
```

The default **clientPort** is **2181**.

Example: **sh zkCli.sh -server 192.168.0.151:2181**

- Step 6** Run the **ls** command to view the znode list in ZooKeeper. For example, you can view the list of znodes in the root directory.

**ls /**

```
[zk: 192.168.0.151:2181(CONNECTED) 1] ls /  
[hadoop-flag, hadoop-ha, test, test2, test3, test4, test5, test6, zookeeper]
```

**View the ZooKeeper znode ACL.**

- Step 7** Start the ZooKeeper client.

- Step 8** Run the **getAcl** command to view znodes. The following command can be used to view the created znode ACL named **test**:

**getAcl /znode name**

```
[zk: 192.168.0.151:2181(CONNECTED) 2] getAcl /test  
'world,'anyone  
: cdrwa
```

Add a ZooKeeper znode ACL.

- Step 9** Start the ZooKeeper client.

- Step 10** View the old ACL information to check whether the current account has the permission to modify the znode ACL information (a permission). If no, use kinit to switch to a user that has the permission and restart the ZooKeeper client.

**getAcl /znode name**

```
[zk: 192.168.0.151:2181(CONNECTED) 3] getAcl /test  
'world,'anyone  
: cdrwa
```

- Step 11** Run the **setAcl** command to add an ACL. The command for adding an ACL is as follows:

**setAcl /test world:anyone:cdrwa,sasl: username@: <system domain name>:ACL value**

For example, to add the ACL of the **admin** user to the test znode, run the following command:

**setAcl /test world:anyone:cdrwa,sasl:admin@HADOOP.COM:cdrwa**

#### NOTE

When adding a new ACL, reserve the existing ones. The new and old ACLs are separated by a comma. The newly added ACL has three parts:

The first part is the authentication type. For example, **sasl** indicates the kerberos authentication type.

The second part is the account. For example, **admin@HADOOP.COM** indicates user **admin**.

The third part is permission. For example, **cdrwa** indicates all permissions.

- Step 12** After adding the ACL, run the **getAcl** command to check whether the permission is added successfully:

**getAcl /znode name**

```
[zk: 192.168.0.151:2181(CONNECTED) 4] getAcl /test
'world,'anyone
: cdrwa
'sasl,'admin@<system domain name>
: cdrwa
```

### Modify the ZooKeeper znode ACL.

**Step 13** Start the ZooKeeper client.

**Step 14** View the old ACL information to check whether the current account has the permission to modify the znode ACL information (a permission). If no, use kinit to switch to a user that has the permission and restart the ZooKeeper client.

**getAcl** /znode name

```
[zk: 192.168.0.151:2181(CONNECTED) 5] getAcl /test
'world,'anyone
: cdrwa
'sasl,'admin@<system domain name>
: cdrwa
```

**Step 15** Run the **setAcl** command to modify an ACL. The command for adding an ACL is as follows:

**setAcl** /test sasl:Username@<System domain name>:ACL value

For example, to reserve only **admin** user permission and delete **anyone** rw permission, run the following command:

**setAcl** /test sasl:admin@HADOOP.COM:cdrwa

**Step 16** After modifying the ACL, run the **getAcl** command to check whether the permission is modified successfully:

**getAcl** /znode name

```
[zk: 192.168.0.151:2181(CONNECTED) 6] getAcl /test
'sasl,'admin@<system domain name>
: cdrwa
```

### Delete the ZooKeeper znode ACL.

**Step 17** Start the ZooKeeper client.

**Step 18** View the old ACL information to check whether the current account has the permission to modify the znode ACL information (a permission). If no, use kinit to switch to a user that has the permission and restart the ZooKeeper client.

**getAcl** /znode name

```
[zk: 192.168.0.151:2181(CONNECTED) 5] getAcl /test
'world,'anyone
: rw
'sasl,'admin@<system domain name>
: cdrwa
```

**Step 19** Run the **setAcl** command to add an ACL. The command for adding an ACL is as follows:

**setAcl** /test sasl:Username@<System domain name>:ACL value

For example, to reserve only **admin** user permission and delete **anyone** rw permission, run the following command:

```
setAcl /test sasl:admin@HADOOP.COM:cdrwa
```

**Step 20** After modifying the ACL, run the **getAcl** command to check whether the permission is modified successfully:

```
getAcl /znode name
```

```
[zk: 192.168.0.151:2181(CONNECTED) 6] getAcl /test
'sasl,'admin@<system domain name>
: cdrwa
```

```
----End
```

## 20.5 Changing the ZooKeeper Storage Directory

### Scenario

When the defined storage directory of ZooKeeper is incorrect, or when the storage plan of ZooKeeper is changed, log in to FusionInsight Manager to change the storage directory of ZooKeeper to ensure ZooKeeper runs properly. The storage directory of ZooKeeper includes the local data storage directory **dataDir**. Changing the ZooKeeper storage directory includes the following scenarios:

- Change the storage directory of the ZooKeeper role. In this way, the storage directories of all the ZooKeeper instances are also changed.
- Change the storage directory of a single ZooKeeper instance. In this way, only the storage directory of this ZooKeeper instance is changed, and the storage directories of other ZooKeeper instances are not changed.

### Impact on the System

- ZooKeeper and associated services needs to be stopped and restarted during the process of changing the storage directory of ZooKeeper, and the cluster cannot provide services before restarted.
- The ZooKeeper instance needs to stopped and restarted during the process of changing the storage directory of the instance, and the ZooKeeper instance at this node cannot provide services before restarted.

### Prerequisites

- New disks have been prepared and installed on each data node, and the disks are formatted.
- New directories have been planned for storing data in the original directories.
- The MRS cluster administrator account **admin** has been prepared.

### Procedure

**Check the environment.**

**Step 1** Log in to FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Services** to check whether **Running Status** of ZooKeeper is **Normal**.

- If yes, go to [Step 3](#).
- If no, the ZooKeeper status is unhealthy. Go to [Step 2](#).

**Step 2** Rectify the ZooKeeper fault.

**Step 3** Determine whether to change the storage directory of the ZooKeeper role or that of a ZooKeeper instance:

- To change the storage directory of the ZooKeeper role, go to [Step 4](#).
- To change the storage directory of a single ZooKeeper instance, go to [Step 9](#).

#### **Change the storage directory of the ZooKeeper role.**

**Step 4** Choose **Cluster** > *Name of the desired cluster* > **Services** > **ZooKeeper** > **Stop** to stop the ZooKeeper service.

**Step 5** Log in to each node where the ZooKeeper service is installed as user **root** and perform the following operations:

1. Create a target directory.

For example, to create the target directory `${BIGDATA_DATA_HOME}/zookeeper2`, run the following command:

```
mkdir ${BIGDATA_DATA_HOME}/zookeeper2.
```

2. Format the new disk, and mount the target directory to the new disk. For example, mount `${BIGDATA_DATA_HOME}/zookeeper2` to the new disk.
3. Modify permissions on the new directory.

For example, the new directory is `${BIGDATA_DATA_HOME}/zookeeper2`.

```
Run chmod 700 ${BIGDATA_DATA_HOME}/zookeeper2 and chown omm:wheel ${BIGDATA_DATA_HOME}/zookeeper2.
```

4. Run the following commands to copy the original data to the new directory:

```
For example, run cp -pr ${BIGDATA_DATA_HOME}/zookeeper/version-2/ $  
{BIGDATA_DATA_HOME}/zookeeper2/
```

```
cp -pr ${BIGDATA_DATA_HOME}/zookeeper/myid $  
{BIGDATA_DATA_HOME}/zookeeper2/
```

**Step 6** On FusionInsight Manager, choose **Cluster** > *Name of the desired cluster* > **Service** > **ZooKeeper** > **Configuration** to go to the configuration page of the ZooKeeper service.

Set **dataDir** of ZooKeeper and quorumpeer to the new target directory, such as `${BIGDATA_DATA_HOME}/zookeeper2`.

**Step 7** Click **Save**, and then click **OK**. Restart the ZooKeeper service.

Click **Finish** when the system displays "Operation successful". ZooKeeper is successfully started.

**Step 8** Rename the original storage directory `${BIGDATA_DATA_HOME}/zookeeper`. If the directory is a root directory that is mounted to an independent disk, remove the disk before renaming the directory and no further action is required.

#### **Change the storage directory of a single ZooKeeper instance.**

**Step 9** Choose **Cluster** > *Name of the desired cluster* > **Service** > **ZooKeeper** > **Instances**. Select the ZooKeeper instance whose storage directory needs to be modified, and choose **More** > **Stop Instance**.

**Step 10** Log in to the ZooKeeper node as user **root**, and perform the following operations:

1. Create a target directory.  
For example, to create the target directory `${BIGDATA_DATA_HOME}/zookeeper2`, run the following command:  
**`mkdir ${BIGDATA_DATA_HOME}/zookeeper2`**.
2. Mount the target directory to the new disk. For example, mount `${BIGDATA_DATA_HOME}/yarn/data2` to the new disk.
3. Modify permissions on the new directory.  
For example, to modify permissions on the `${BIGDATA_DATA_HOME}/yarn/data2` directory, run the following commands:  
**`chmod 700 ${BIGDATA_DATA_HOME}/zookeeper2`** and **`chown omm:wheel ${BIGDATA_DATA_HOME}/zookeeper2`**
4. Run the following commands to copy the original data to the new directory:  
For example, run **`cp -pr ${BIGDATA_DATA_HOME}/zookeeper/version-2/ ${BIGDATA_DATA_HOME}/zookeeper2/`**  
**`cp -pr ${BIGDATA_DATA_HOME}/zookeeper/myid ${BIGDATA_DATA_HOME}/zookeeper2/`**

**Step 11** On FusionInsight Manager, click the specified ZooKeeper instance, and switch to the **Instance Configuration** page.

Set **dataDir** of ZooKeeper and quorumpeer to the new target directory, such as `${BIGDATA_DATA_HOME}/zookeeper2`.

**Step 12** Click **Save**, and then click **OK**. Restart the ZooKeeper instance.

Click **Finish** when the system displays "Operation successful". The ZooKeeper instance is successfully started.

**Step 13** Rename the original storage directory `${BIGDATA_DATA_HOME}/zookeeper`. If the directory is a root directory that is mounted to an independent disk, remove the disk before renaming the directory and no further action is required.

----End


## 20.6 Configuring the ZooKeeper Connection

### Scenarios

ZooKeeper has `maxClientCnxn` configuration at the server side, and this configuration will verify the connections from each client IP address. But many clients can create countless unnecessary connections and consume all resources of ZooKeeper during the denial-of-service (DOS) attack. This makes other clients fail to create legitimate connections or even triggers the server breakdown.

To limit the maximum number of connections to a single ZooKeeper server, all ZooKeeper servers introduce a new configuration to check the total number of active connections before accepting any new connection requests.

**Figure 20-1** Connection control logic



## Configuration Description

Go to the **All Configurations** page of ZooKeeper by referring to [Modifying Cluster Service Configuration Parameters](#). Enter a parameter name in the search box. Configure **maxClientCnxns** and **maxCnxns** to limit the maximum number of connections on each host and the total number of connections on the ZooKeeper server.

**Table 20-3** Connection policy parameters

| Parameter      | Description                                                                                                                                                                                        | Default Value |
|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| maxClientCnxns | Limits the number of client connections to a ZooKeeper server in the ZooKeeper cluster. Clients are distinguished by IP address. The configuration is the same as that in the open source version. | 2000          |
| maxCnxns       | Specifies the maximum number of client connections allowed by a single ZooKeeper server. Clients are not differentiated by IP address.                                                             | 20000         |

 NOTE


The ZooKeeper connection control function is based on IP addresses instead of specific users. If all connections of an IP address are occupied by few services, other mandatory services from the same IP address may fail to connect to the ZooKeeper. Therefore, ensure that only trusted applications are allowed to connect to ZooKeeper and the maximum number of connections is configured accordingly.

## 20.7 Configuring ZooKeeper Response Timeout Interval

### Scenarios

The ZooKeeper client uses the FIFO queue to send a request to the server and waits for a response from the server. The client maintains the FIFO queue until it acknowledges the server's response to the request. The client waits indefinitely before acknowledging the response from the server. If the client cannot receive a response due to a server or network fault, the client enters the suspended state. Therefore, to avoid infinite waiting time, the client needs to associate with the ACK response timeout.

Figure 20-2 Request timeout logic



### Configuration Description

Change the value of **zookeeper.request.timeout** based on the network latency. If the packet loss duration is greater than the default value **120000 ms**, set this

parameter to a larger value. To set **zookeeper.request.timeout** to *X*, set **Dzookeeper.request.timeout** to *X* when starting the ZooKeeper client.

**Table 20-4** Response timeout duration parameters

| Parameter                 | System Parameter          | Description                                                                                                                                                                                                             | Default Value |
|---------------------------|---------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| zookeeper.request.timeout | zookeeper.request.timeout | If no response is received from the server within the configured time, terminate the request that is not responded with <b>org.apache.zookeeper KeeperException.ConnectionLossException</b> and exit. Unit: millisecond | 120000        |

## Procedure

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to switch to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to edit the **component\_env** file:

```
vi ZooKeeper/component_env
```

Change the value of **zookeeper.request.timeout**.

```
-Dzookeeper.request.timeout=120000
```

**Step 4** Run the **:wq** command to save execution.

**Step 5** Restart the client for the settings to take effect.

```
----End
```

## 20.8 Binding the Client to an IP Address

### Scenarios

To prevent multiple IP nodes, bind the current ZooKeeper client to any available IP address. The data flow layer, management layer, and other network layers in the production environment have different IP address ranges. Bind the ZooKeeper client to the IP address at the data flow layer. This helps locate the failure scenario where the data IP address is unreachable.

### Configuration Description

Configure **zookeeper.client.bind.address** to ensure that the client is always bound to the specified IP address. To set **zookeeper.client.bind.address** to *X*, set **Dzookeeper.client.bind.address** to *X* when starting the ZooKeeper client.

**Table 20-5** Parameter description

| Parameter                     | System Parameter              | Description                                                                                                                                           | Default Value |
|-------------------------------|-------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| zookeeper.client.bind.address | zookeeper.client.bind.address | Optional. IP address or host name bound to the ZooKeeper client. By default, the ZooKeeper client is bound to any available IP address in the system. | -             |

## Procedure

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to switch to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to edit the **component\_env** file:

```
vi ZooKeeper/component_env
```

Add the **zookeeper.client.bind.address** parameter and its value.

Normal mode:

```
export ZOOKEEPER_HOME="/opt/client/ZooKeeper/zookeeper"
PATH_NEW=`echo $PATH | sed "s:$ZOOKEEPER_HOME/bin||g" | sed "s|$ZOOKEEPER_HOME/bin:||g"`
export PATH="$ZOOKEEPER_HOME/bin:$PATH_NEW"
# default heap for zookeeper client
export ZK_CLIENT_HEAP="256"
export CLIENT_JVMFLAGS="-Xmx${ZK_CLIENT_HEAP}m"
export CLIENT_JVMFLAGS="$CLIENT_JVMFLAGS -Dzookeeper.root.logger=WARN,CONSOLE -
Dzookeeper.request.timeout=120000 -Dzookeeper.client.bind.address=X" #Add a parameter. X indicates the
configured IP address.
```

Security mode:

```
if [ "$HADOOP_SECURITY_AUTHENTICATION" = "kerberos" ]; then
  default_realm=`cat $KRB5_CONFIG |grep default_realm|awk -F=" '{gsub(" ","");print $2}'|tr 'A-Z' 'a-z'`
  export ZOO_SERVER_PRINCIPAL="zookeeper/hadoop.${default_realm}"
  export CLIENT_JVMFLAGS="$CLIENT_JVMFLAGS -Djava.security.krb5.conf=$KRB5_CONFIG -
Dzookeeper.kin -Dzookeeper.client.bind.address=X" #Add a parameter. X indicates the configured IP address.
```

**Step 4** Run the **:wq** command to save execution.

**Step 5** Restart the client for the settings to take effect.

----End

## 20.9 Configuring the Port Range Bound to the Client

### Scenarios

When the ZooKeeper client is started, it is bound to a random port. In most cases, you want to bind the ZooKeeper client to a specific port. For example, for the client connection whitelist based on the IP address and port number, users can

configure the port range bound to the client so that the same port range can be configured in the connection whitelist.

## Configuration Description

Set **zookeeper.client.bind.port.range** to *<startPort:endPort>* to ensure that the client is always bound to a port in the specified port range. For example, if **zookeeper.client.bind.port.range** is set to **65510:65512**, the client can be bound only to port **65510**, **65511**, or **65512**.

To set **zookeeper.client.bind.port.range** to *<startPort:endPort>*, set **Dzookeeper.client.bind.port.range** to *<startPort:endPort>* when starting the ZooKeeper client.

**Table 20-6** Parameter description

| Parameter                        | System Parameter                 | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | Default Value |
|----------------------------------|----------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| zookeeper.client.bind.port.range | zookeeper.client.bind.port.range | This parameter is optional. Range of ports that can be used by the client during binding. The format is startPort:endPort (including startPort and endPort). The values of startPort and endPort range from 1024 to 65535, and the value of endPort must be greater than that of startPort. For example, 50000:50050 and 50100:50200.<br><br>The client can be successfully connected only when at least two ports are available. If no port is available in the configured port range, the client fails to connect to the server. If the configured value is invalid, the value is ignored, the error is recorded, and the client will be bound to a random port. | -             |

## Procedure

**Step 1** Log in to the node where the client is installed as the client installation user.

**Step 2** Run the following command to switch to the client installation directory:

```
cd /opt/client
```

**Step 3** Run the following command to edit the **component\_env** file:

```
vi ZooKeeper/component_env
```

Add the **zookeeper.client.bind.port.range** parameter and its value.

Normal mode:

```
export ZOOKEEPER_HOME="/opt/client/ZooKeeper/zookeeper"  
PATH_NEW=`echo $PATH | sed "s|:$ZOOKEEPER_HOME/bin||g" | sed "s|$ZOOKEEPER_HOME/bin:||g"  
export PATH="$ZOOKEEPER_HOME/bin:$PATH_NEW"  
# default heap for zookeeper client  
export ZK_CLIENT_HEAP="256"  
export CLIENT_JVMFLAGS="-Xmx${ZK_CLIENT_HEAP}m"  
export CLIENT_JVMFLAGS="$CLIENT_JVMFLAGS -Dzookeeper.root.logger=WARN,CONSOLE -  
Dzookeeper.request.timeout=120000 -Dzookeeper.client.bind.port.range=<startPort.endPort>" # Add a  
parameter.
```

Security mode:

```
if [ "$HADOOP_SECURITY_AUTHENTICATION" = "kerberos" ]; then  
    default_realm=`cat $KRB5_CONFIG |grep default_realm|awk -F"=" '{gsub(" ","");print $2}'|tr 'A-Z' 'a-z'`  
    export ZOO_SERVER_PRINCIPAL="zookeeper/hadoop.${default_realm}"  
    export CLIENT_JVMFLAGS="$CLIENT_JVMFLAGS -Djava.security.krb5.conf=$KRB5_CONFIG -  
Dzookeeper.client.bind.port.range=<startPort.endPort>" # Add a parameter.
```

**Step 4** Run the `:wq` command to save execution.

**Step 5** Restart the client for the settings to take effect.

----End


## 20.10 Performing Special Configuration on ZooKeeper Clients in the Same JVM

### Scenarios

Currently, ZooKeeper client properties can be configured only through Java system properties. Therefore, all clients in the same JVM have the same configuration. In some cases, the ZooKeeper client needs to connect to different clusters and this requires different client configurations. For example, if users want to connect two different ZooKeeper clusters from the same JVM, one cluster has the security mode enabled and the other does not. The configuration of each client varies. Different configuration methods are required for different clients.

This solution allows each ZooKeeper client to use different configurations. As shown in [Figure 20-3](#), each client uses different configurations, which are initialized in the property file.

**Figure 20-3** Performing special configuration on ZooKeeper clients in the same JVM



## Configuration Description

**Step 1** Create the ZKClientConfig instance and transfer the ZKClientConfig instance to ZooKeeper when creating the ZooKeeper instance.

The methods for creating the ZKClientConfig instance are as follows:

- Method 1:**

```
ZKClientConfig clientConfig = new ZKClientConfig();
```

ZKClientConfig will have all properties of the ZooKeeper client configured in Java.
- Method 2:**

```
ZKClientConfig clientConfig = new ZKClientConfig();
clientConfig.addConfiguration("/somepath/zoo-client.cfg");
```

ZKClientConfig is initialized in the **zoo-client.cfg** file. The properties of the **zoo-client.cfg** file will overwrite the same Java system properties.
- Method 3:**

```
ZKClientConfig clientConfig = new ZKClientConfig();
clientConfig.setProperty(ZKClientConfig.SECURE_CLIENT, "true");
```

After initialization, the clientConfig has the Java system properties. In addition, the additional property **ZKClientConfig.SECURE\_CLIENT** is added through the code **clientConfig.setProperty(ZKClientConfig.SECURE\_CLIENT, "true")**.

**Step 2** After the configuration is complete, use any of the following ZooKeeper APIs to create a client.

```
org.apache.zookeeper.ZooKeeper.ZooKeeper(String, int, Watcher, ZKClientConfig)  
org.apache.zookeeper.ZooKeeper.ZooKeeper(String, int, Watcher, boolean, ZKClientConfig)
```

----End

## Example Code

Use the following code to connect Client1 and Client2 from the same JVM to a cluster with security mode enabled and a cluster in general mode, respectively.

- Connect to a cluster with security mode enabled:  

```
String secureClientConfigPath = "/somepath/zoo-secure-client.cfg";  
ZKClientConfig secureClientConfig = new ZKClientConfig(secureClientConfigPath);  
ZooKeeper secureZooKeeperClient = new ZooKeeper(connectString, sessionTimeout, watcher,  
secureClientConfig);
```
- Connect to a cluster in common mode:  

```
String nonSecureClientConfigPath = "/somepath/zoo-non-secure-client.cfg";  
  
File nonSecureConfigFile = new File(nonSecureClientConfigPath);  
ZKClientConfig nonSecureClientConfig = new ZKClientConfig(nonSecureConfigFile);  
ZooKeeper nonSecureZooKeeperClient = new ZooKeeper(connectString, sessionTimeout, watcher,  
nonSecureClientConfig);
```

## Constraints

When Kerberos realms are different, we can map to KDC by the realm. Therefore, authentication can be performed based on the KDC of the realm of each client.

For example, two KDCs run on 192.168.1.2 and 192.168.1.3. The two KDCs correspond to the realms of HADOOP.COM and EXAMPLE.COM, respectively.

You can map KDC in the **krb5.conf** file based on the realm as follows:

```
[realms]  
HADOOP.COM = {  
  kdc=192.168.1.2  
  admin_server=192.168.1.2  
  other attributes ...  
}  
EXAMPLE.COM = {  
  kdc=192.168.1.3  
  admin_server=192.168.1.3  
  other attributes ...  
}
```

However, when different KDCs have the same realm, the realm cannot map to the corresponding KDC. This is the configuration constraint of multiple ZooKeeper clients in the same JVM. Therefore, multiple ZooKeeper clients in the same JVM, cannot use multiple KDCs with the same realm.

## 20.11 Configuring a Quota for a Znode

### Scenario

Set a quota for Znodes in ZooKeeper of a security cluster in O&M scenarios or service scenarios to restrict the quantity and byte space of Znodes and subnodes.

Two modes are available:

- On Manager, enable the automatic quota setting function and set related configuration items to enable the ZooKeeper service to automatically set the Znode quota. For details, see [Step 1](#) to [Step 8](#).
- On Manager, disable the automatic quota setting function and run commands on the client to manually set the Znode quota. For details, see [Step 1](#) to [Step 3](#).

## Impact on the System

If the configured quantity or capacity quota is less than the quantity or capacity of directories required for normal service running, services may fail to run properly. Exercise cautions when setting the quota.

## Prerequisites

The ZooKeeper client has been installed in a directory, for example, `/opt/client`.

## Procedure

**Use the automatic quota setting function.**

- Step 1** Go to the **All Configurations** page of ZooKeeper. Click the **Quota** tab and set **quotas.auto.check.enable** to **true**, and click **Save**. For details, see [Modifying Cluster Service Configuration Parameters](#).
- Step 2** Determine whether to set the quota of the top directory (for example, Yarn service) on ZooKeeper.
- If yes, go to [Step 3](#).
  - If no, go to [Step 5](#).
- Step 3** Go to the **All Configurations** page of Yarn by referring to [Modifying Cluster Service Configuration Parameters](#) and search for **zk.quota**.
- Step 4** Set the following quotas properly and click Save. The ZooKeeper service periodically sets the quota of the Yarn service on the top directory of ZooKeeper.
1. **zk.quota.number** indicates the directory quota of the service on ZooKeeper.
  2. **zk.quota.bytes** indicates the capacity quota of the service directory on ZooKeeper.

### NOTE

If the configured quantity or capacity quota is less than the actual quantity or capacity quota of the current directory, the setting can be saved successfully. However, an alarm indicating that the setting is invalid is displayed on the page, prompting you to reset the quota.

If the configured quantity or capacity quota is less than the quantity or capacity of directories required for normal service running, services may fail to run properly. Exercise cautions when setting the quota.

- Step 5** Check whether quotas of other custom top directories except service directories need to be configured.
- If yes, go to [Step 6](#).
  - If no, no further action is required.

- Step 6** Go to the **All Configurations** page of ZooKeeper and click the **Quota** tab.
- Step 7** Enter the top directory (for example, `/abc`) of ZooKeeper in the **Value** text box of **customized.quota**.
- Step 8** In the **Value** text box, enter the quantity quota and capacity quota separated by a comma (,). (You can also set only the quantity quota). If you need to set quotas for multiple top directories, click **+** to add quotas. Click **Save**. The ZooKeeper service automatically sets the quota of the top directory periodically. No further action is required.

 **NOTE**

The entered quantity quota cannot be greater than the value of **max.znode.count**. The entered capacity quota cannot be greater than the value of **max.data.size**.

If the top directory on ZooKeeper is not the top directory of a service, and its quota is not specified using **customized.quota**, the ZooKeeper service sets the quota to the value of **defaultQuota**.

**Run commands on the client.**

- Step 9** Go to the **All Configurations** page of ZooKeeper. Click the **Quota** tab and set **quotas.auto.check.enable** to **false**, and click **Save**.
- Step 10** Start the ZooKeeper client. For details, see [Using a ZooKeeper Client](#).

 **NOTE**

In security mode, user authentication is required to start the ZooKeeper client. The ZooKeeper user (system administrator of ZooKeeper) is used for authentication, and the **init zookeeper** command is executed.

- Step 11** Run the **setquota /znode -n number -b byte** command.
- *znode* indicates the node for which you want to set a quota.
  - *number* indicates the maximum number of nodes and subnodes.
  - *byte* indicates the maximum byte space for the node and subnodes.

----End

## 20.12 ZooKeeper Log Overview

### Log Description

**Log path:** `/var/log/Bigdata/zookeeper/quorumpeer` (Run log), `/var/log/Bigdata/audit/zookeeper/quorumpeer` (Audit log)

**Log archive rule:** The automatic ZooKeeper log compression function is enabled. By default, when the size of logs exceeds 30 MB, logs are automatically compressed into a log file. A maximum of 20 compressed file can be reserved. The number of compressed files can be configured on Manager.

**Table 20-7** ZooKeeper log list

| Log Type  | Log File Name                                      | Description                                                                                               |
|-----------|----------------------------------------------------|-----------------------------------------------------------------------------------------------------------|
| Run logs  | zookeeper-<SSH_USER>-<process_name>-<hostname>.log | ZooKeeper system log file, which records most of the logs generated when the ZooKeeper system is running. |
|           | check-serviceDetail.log                            | Log that records whether the ZooKeeper service starts successfully.                                       |
|           | zookeeper-<SSH_USER>-<DATA>-<PID>-gc.log           | ZooKeeper garbage collection log file                                                                     |
|           | instanceHealthDetail.log                           | Log that records the health check details of ZooKeeper instance                                           |
|           | zookeeper-omm-server-<hostname>.out                | Log indicating that ZooKeeper unexpectedly quits                                                          |
|           | zk-err-<zkpid>.log                                 | ZooKeeper fatal error log                                                                                 |
|           | java_pid<zkpid>.hprof                              | ZooKeeper memory overflow log                                                                             |
|           | funcDetail.log                                     | ZooKeeper instance startup log                                                                            |
|           | zookeeper-period-check.log                         | Health check log of the ZooKeeper instance                                                                |
| Audit Log | zk-audit-quorumpeer.log                            | ZooKeeper operation audit log                                                                             |

## Log levels

**Table 20-8** describes the log levels supported by ZooKeeper. The priorities of log levels are FATAL, ERROR, WARN, INFO, and DEBUG in descending order. Logs whose levels are higher than or equal to the specified level are printed. The number of printed logs decreases as the specified log level increases.

**Table 20-8** Log levels

| Level | Description                                                                                                             |
|-------|-------------------------------------------------------------------------------------------------------------------------|
| FATAL | Logs of this level record fatal error information about the current event processing that may result in a system crash. |
| ERROR | Error information about the current event processing, which indicates that system running is abnormal.                  |
| WARN  | Abnormal information about the current event processing. These abnormalities will not result in system faults.          |

| Level | Description                                                                              |
|-------|------------------------------------------------------------------------------------------|
| INFO  | Logs of this level record normal running status information about the system and events. |
| DEBUG | Logs of this level record the system information and system debugging information.       |

To modify log levels, perform the following operations:

- Step 1** Go to the **All Configurations** page of the ZooKeeper service by referring to [Modifying Cluster Service Configuration Parameters](#).
- Step 2** On the menu bar on the left, select the log menu of the target role.
- Step 3** Select a desired log level.
- Step 4** Click **Save**. In the displayed dialog box, click **OK** to make the configuration take effect.

 **NOTE**

The configurations take effect immediately without the need to restart the service.

----End

## Log Format

The following table lists the ZooKeeper log formats.

**Table 20-9** Log Format

| Log Type | Component               | Format                                                                                                                                                                        | Example                                                                                                                                                                                                       |
|----------|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Run logs | zookeeper<br>quorumpeer | <yyyy-MM-dd<br>HH:mm:ss,SSS> <br><Log level> <br><Name of the<br>thread that<br>generates the<br>log> <Message in<br>the log> <br><Location where<br>the log event<br>occurs> | 2020-01-20<br>16:33:43,816  <br>INFO   main  <br>Defaulting to<br>majority quorums<br> <br>org.apache.zooke<br>eper.server.quoru<br>m.QuorumPeerCo<br>nfig.parseProperti<br>es(QuorumPeerCo<br>nfig.java:335) |

| Log Type   | Component               | Format                                                                                                                                                                        | Example                                                                                                                                                                                                                                                                                                                               |
|------------|-------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Audit logs | zookeeper<br>quorumpeer | <yyyy-MM-dd<br>HH:mm:ss,SSS> <br><Log level> <br><Name of the<br>thread that<br>generates the<br>log> <Message in<br>the log> <br><Location where<br>the log event<br>occurs> | 2020-01-20<br>16:33:54,313  <br>INFO  <br>CommitProcessor:<br>13  <br>session=0xd4b067<br>9daea0000<br>ip=10.177.112.145<br>operation=create<br>znode<br>target=ZooKeeper<br>Server znode=/zk-<br>write-test-2<br>result=success  <br>org.apache.zookee<br>per.ZKAuditLogger<br>\$LogLevel<br>\$5.printLog(ZKAu<br>ditLogger.java:70) |

## 20.13 Common Issues About ZooKeeper

### 20.13.1 Why Do ZooKeeper Servers Fail to Start After Many znodes Are Created?

#### Question

After a large number of znodes are created, ZooKeeper servers in the ZooKeeper cluster become faulty and cannot be automatically recovered or restarted.

Logs of followers:

```
2016-06-23 08:00:18,763 | WARN | QuorumPeer[myid=26](plain=/10.16.9.138:2181)(secure=disabled) |
Exception when following the leader |
org.apache.zookeeper.server.quorum.Follower.followLeader(Follower.java:93)
java.net.SocketTimeoutException: Read timed out
    at java.net.SocketInputStream.socketRead0(Native Method)
    at java.net.SocketInputStream.socketRead(SocketInputStream.java:116)
    at java.net.SocketInputStream.read(SocketInputStream.java:170)
    at java.net.SocketInputStream.read(SocketInputStream.java:141)
    at java.io.BufferedInputStream.fill(BufferedInputStream.java:246)
    at java.io.BufferedInputStream.read(BufferedInputStream.java:265)
    at java.io.DataInputStream.readInt(DataInputStream.java:387)
    at org.apache.jute.BinaryInputArchive.readInt(BinaryInputArchive.java:63)
    at org.apache.zookeeper.server.quorum.QuorumPacket.deserialize(QuorumPacket.java:83)
    at org.apache.jute.BinaryInputArchive.readRecord(BinaryInputArchive.java:99)
    at org.apache.zookeeper.server.quorum.Learner.readPacket(Learner.java:156)
    at org.apache.zookeeper.server.quorum.Learner.registerWithLeader(Learner.java:276)
    at org.apache.zookeeper.server.quorum.Follower.followLeader(Follower.java:75)
    at org.apache.zookeeper.server.quorum.QuorumPeer.run(QuorumPeer.java:1094)
2016-06-23 08:00:18,764 | INFO | QuorumPeer[myid=26](plain=/10.16.9.138:2181)(secure=disabled) |
shutdown called | org.apache.zookeeper.server.quorum.Follower.shutdown(Follower.java:198)
```

```
java.lang.Exception: shutdown Follower
    at org.apache.zookeeper.server.quorum.Follower.shutdown(Follower.java:198)
    at org.apache.zookeeper.server.quorum.QuorumPeer.stopFollower(QuorumPeer.java:1141)
    at org.apache.zookeeper.server.quorum.QuorumPeer.run(QuorumPeer.java:1098)
```

Logs of the leader:

```
2016-06-23 07:30:57,481 | WARN | QuorumPeer[myid=25](plain=/10.16.9.136:2181)(secure=disabled) |
Unexpected exception | org.apache.zookeeper.server.quorum.QuorumPeer.run(QuorumPeer.java:1108)
java.lang.InterruptedExcpetion: Timeout while waiting for epoch to be acked by quorum
    at org.apache.zookeeper.server.quorum.Leader.waitForEpochAck(Leader.java:1221)
    at org.apache.zookeeper.server.quorum.Leader.lead(Leader.java:487)
    at org.apache.zookeeper.server.quorum.QuorumPeer.run(QuorumPeer.java:1105)
2016-06-23 07:30:57,482 | INFO | QuorumPeer[myid=25](plain=/10.16.9.136:2181)(secure=disabled) |
Shutdown called | org.apache.zookeeper.server.quorum.Leader.shutdown(Leader.java:623)
java.lang.Exception: shutdown Leader! reason: Forcing shutdown
    at org.apache.zookeeper.server.quorum.Leader.shutdown(Leader.java:623)
    at org.apache.zookeeper.server.quorum.QuorumPeer.stopLeader(QuorumPeer.java:1149)
    at org.apache.zookeeper.server.quorum.QuorumPeer.run(QuorumPeer.java:1110)
```

## Answer

After a large number of znodes are created, a large volume of data needs to be synchronized between the follower and leader. If the data synchronization is not complete within the specified time, all ZooKeeper servers fail to start.

Go to the **All Configurations** page of the ZooKeeper service by referring to [Modifying Cluster Service Configuration Parameters](#). To recover ZooKeeper servers, increase the values of **syncLimit** and **initLimit** in the ZooKeeper configuration file **zoo.cfg** until ZooKeeper servers are successfully started.

**Table 20-10** Parameters

| Parameter | Description                                                                                                                                                                                                                         | Default Value |
|-----------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| syncLimit | Interval (unit: tick) at which data is synchronized between the follower and the leader. If the leader does not respond to the follower within the specified time, the connection between the leader and follower cannot be set up. | 15            |
| initLimit | Interval (unit: tick) within which the connection and synchronization between the follower and leader must be completed.                                                                                                            | 15            |

If ZooKeeper servers do not recover even after **initLimit** and **syncLimit** are set to **300** ticks, check that no other application is killing the ZooKeeper. For example, if the parameter value is **300** and the ticket duration is 2000 ms, the maximum synchronization duration is 600s (300 x 2000 ms).

There may exist the situation where an overwhelming amount of data is created in ZooKeeper and it takes long to synchronize data between the follower and the leader and to save data to the hard disk. This means that ZooKeeper needs to run for a long time. Ensure that no other monitoring application kills the ZooKeeper while ZooKeeper is running.

## 20.13.2 Why Does the ZooKeeper Server Display the java.io.IOException: Len Error Log?

### Question

After a large number of znodes are created in a parent directory, the ZooKeeper client will fail to fetch all child nodes of this parent directory in a single request.

Logs of client:

```
2017-07-11 13:17:19,610 [myid:] - WARN [New I/O worker #3:ClientCnxnSocketNetty
$ZKClientHandler@468] - Exception caught: [id: 0xb66cbb85, /10.18.97.97:49192 ->
10.18.97.97/10.18.97.97:2181] EXCEPTION: java.nio.channels.ClosedChannelException
java.nio.channels.ClosedChannelException
at org.jboss.netty.handler.ssl.SslHandler$6.run(SslHandler.java:1580)
at org.jboss.netty.channel.socket.ChannelRunnableWrapper.run(ChannelRunnableWrapper.java:40)
at org.jboss.netty.channel.socket.nio.AbstractNioWorker.executeInIoThread(AbstractNioWorker.java:71)
at org.jboss.netty.channel.socket.nio.NioWorker.executeInIoThread(NioWorker.java:36)
at org.jboss.netty.channel.socket.nio.AbstractNioWorker.executeInIoThread(AbstractNioWorker.java:57)
at org.jboss.netty.channel.socket.nio.NioWorker.executeInIoThread(NioWorker.java:36)
at org.jboss.netty.channel.socket.nio.AbstractNioChannelSink.execute(AbstractNioChannelSink.java:34)
at org.jboss.netty.handler.ssl.SslHandler.channelClosed(SslHandler.java:1566)
at org.jboss.netty.channel.Channels.fireChannelClosed(Channels.java:468)
at org.jboss.netty.channel.socket.nio.AbstractNioWorker.close(AbstractNioWorker.java:376)
at org.jboss.netty.channel.socket.nio.NioWorker.read(NioWorker.java:93)
at org.jboss.netty.channel.socket.nio.AbstractNioWorker.process(AbstractNioWorker.java:109)
at org.jboss.netty.channel.socket.nio.AbstractNioSelector.run(AbstractNioSelector.java:312)
at org.jboss.netty.channel.socket.nio.AbstractNioWorker.run(AbstractNioWorker.java:90)
at org.jboss.netty.channel.socket.nio.NioWorker.run(NioWorker.java:178)
at java.util.concurrent.ThreadPoolExecutor.runWorker(ThreadPoolExecutor.java:1142)
at java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:617)
at java.lang.Thread.run(Thread.java:745)
```

Logs of leader:

```
2017-07-11 13:17:33,043 [myid:1] - WARN [New I/O worker #7:NettyServerCnxn@445] - Closing
connection to /10.18.101.110:39856
java.io.IOException: Len error 45
at org.apache.zookeeper.server.NettyServerCnxn.receiveMessage(NettyServerCnxn.java:438)
at org.apache.zookeeper.server.NettyServerCnxnFactory
$CnxnChannelHandler.processMessage(NettyServerCnxnFactory.java:267)
at org.apache.zookeeper.server.NettyServerCnxnFactory
$CnxnChannelHandler.messageReceived(NettyServerCnxnFactory.java:187)
at org.jboss.netty.channel.SimpleChannelHandler.handleUpstream(SimpleChannelHandler.java:88)
at org.jboss.netty.channel.DefaultChannelPipeline.sendUpstream(DefaultChannelPipeline.java:564)
at org.jboss.netty.channel.DefaultChannelPipeline.sendUpstream(DefaultChannelPipeline.java:559)
at org.jboss.netty.channel.Channels.fireMessageReceived(Channels.java:268)
at org.jboss.netty.channel.Channels.fireMessageReceived(Channels.java:255)
at org.jboss.netty.channel.socket.nio.NioWorker.read(NioWorker.java:88)
at org.jboss.netty.channel.socket.nio.AbstractNioWorker.process(AbstractNioWorker.java:109)
at org.jboss.netty.channel.socket.nio.AbstractNioSelector.run(AbstractNioSelector.java:312)
at org.jboss.netty.channel.socket.nio.AbstractNioWorker.run(AbstractNioWorker.java:90)
at org.jboss.netty.channel.socket.nio.NioWorker.run(NioWorker.java:178)
at org.jboss.netty.util.ThreadRenamingRunnable.run(ThreadRenamingRunnable.java:108)
at org.jboss.netty.util.internal.DeadLockProofWorker$1.run(DeadLockProofWorker.java:42)
at java.util.concurrent.ThreadPoolExecutor.runWorker(ThreadPoolExecutor.java:1142)
at java.util.concurrent.ThreadPoolExecutor$Worker.run(ThreadPoolExecutor.java:617)
at java.lang.Thread.run(Thread.java:745)
```

### Answer

After a large number of znodes are created in a single parent directory and the client tries to fetch all the child znodes in a single request, the server will fail to return because the results exceed the data size that can be stored in a znode.

To avoid this problem, set **jute.maxbuffer** to a larger value based on the client application.

**jute.maxbuffer** can only be set to a Java system property without the Zookeeper prefix. To set **jute.maxbuffer** to *X*, set **Djute.maxbuffer** to *X* when starting the ZooKeeper client or the service.

For example, set the parameter to 4 MB: **-Djute.maxbuffer=0x400000**.

**Table 20-11** Parameters

| Parameter      | Description                                                                                                                                                                                                                                                                      | Default Value |
|----------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------|
| jute.maxbuffer | Specifies the maximum length of data that can be stored in znode. The unit is byte. Default value: 0xfffff, which is less than 1 MB.<br><br><b>NOTE</b><br>If this option is changed, the system property must be set on all servers and clients, otherwise problems will arise. | 0xfffff       |

### 20.13.3 Why Four Letter Commands Don't Work With Linux netcat Command When Secure Netty Configurations Are Enabled at Zookeeper Server?

#### Question

Why four letter commands do not work with linux netcat command when secure netty configurations are enabled at Zookeeper server?

For example,

***echo stat /netcat host port***

#### Answer

Linux **netcat** command does not have option to communicate Zookeeper server securely, so it cannot support Zookeeper four letter commands when secure netty configurations are enabled.

To avoid this problem, user can use below Java API to execute four letter commands.

```
org.apache.zookeeper.client.FourLetterWordMain
```

For example,

```
String[] args = new String[]{host, port, "stat"};
org.apache.zookeeper.client.FourLetterWordMain.main(args);
```

#### NOTE

**netcat** command should be used only with non secure netty configuration.

## 20.13.4 How Do I Check Which ZooKeeper Instance Is a Leader?

### Question

How to check whether the role of a ZooKeeper instance is a leader or follower.

### Answer

Log in to Manager and choose **Cluster** > *Name of the desired cluster* > **Service** > **ZooKeeper** > **Instance**. On the displayed page, click the name of the quorumpeer instance. On the displayed instance details page, view the server status of the instance.

## 20.13.5 Why Cannot the Client Connect to ZooKeeper using the IBM JDK?

### Question

When the IBM JDK is used, the client fails to connect to ZooKeeper.

### Answer

The possible cause is that the **jaas.conf** file format of the IBM JDK is different from that of the common JDK.

If IBM JDK is used, use the following **jaas.conf** template. The **useKeytab** file path must start with **file://**, followed by an absolute path.

```
Client {  
  com.ibm.security.auth.module.Krb5LoginModule required  
  useKeytab="file://D:/install/HbaseClientSample/conf/user.keytab"  
  principal="hbaseuser1"  
  credsType="both";  
};
```

## 20.13.6 What Should I Do When the ZooKeeper Client Fails to Refresh a TGT?

### Question

The ZooKeeper client fails to refresh a TGT and therefore ZooKeeper cannot be accessed. The error message is as follows:

```
Login: Could not renew TGT due to problem running shell command: '*/kinit -R'; exception  
was:org.apache.zookeeper.Shell$ExitCodeException: kinit: Ticket expired while renewing credentials
```

### Answer

ZooKeeper uses the system command **kinit - R** to refresh a ticket. In the current version of MRS, the function of this command is canceled. If a long-term task needs to be executed, you are advised to implement the authentication function in keytab mode.

In the `jaas.conf` configuration file, set `useTicketCache` to `false`, `useKeyTab` to `true`, and specify the keytab path.

## 20.13.7 Why Is Message "Node does not exist" Displayed when A Large Number of Znodes Are Deleted Using the `deleteall` Command

### Question

When the client connects to a non-leader instance, run the `deleteall` command to delete a large number of znodes, the error message "Node does not exist" is displayed, but run the `stat` command, the node status can be obtained.

### Answer

The leader and follower data is not synchronized due to network problems or large data volume. To solve this problem, connect the client to the leader instance and delete the instance. To delete the leader node, view the IP address of the node where the leader resides by referring to [How Do I Check Which ZooKeeper Instance Is a Leader?](#), run the `zkCli.sh -server leader node IP address 2181` command to connect to the client, and then run the `deleteall` command to delete the leader node. For details, see [Using a ZooKeeper Client](#).

# 21 Appendix

---

## 21.1 Modifying Cluster Service Configuration Parameters

Modify the configuration parameters of each service on FusionInsight Manager.

**Step 1** You have logged in to FusionInsight Manager.

**Step 2** Choose **Cluster** > *Name of the desired cluster* > **Service**.

**Step 3** Click the specified service name on the service management page.

**Step 4** Click **Configuration**.

The **Basic Configuration** tab page is displayed by default. To modify more parameters, click the **All Configurations** tab. The navigation tree displays all configuration parameters of the service. The level-1 nodes in the navigation tree are service names or role names. The parameter category is displayed after the level-1 node is expanded.

**Step 5** In the navigation tree, select the specified parameter category and change the parameter values on the right.

If you are not sure about the location of a parameter, you can enter the parameter name in search box in the upper right corner. The system searches for the parameter in real time and displays the result.

**Step 6** Click **Save**. In the confirmation dialog box, click **OK**.

**Step 7** Wait until the message **Operation successful** is displayed. Click **Finish**.

The configuration is modified.

Check whether there is any service whose configuration has expired in the cluster. If yes, restart the corresponding service or role instance for the configuration to take effect.

----**End**

Modify the configuration parameters of each service on the cluster management page of the MRS management console.

**Step 1** Log in to the MRS console. In the left navigation pane, choose **Clusters > Active Clusters**, and click a cluster name.

**Step 2** Choose **Components > Name of the desired service > Service Configuration**.

The **Basic Configuration** tab page is displayed by default. To modify more parameters, click the **All Configurations** tab. The navigation tree displays all configuration parameters of the service. The level-1 nodes in the navigation tree are service names or role names. The parameter category is displayed after the level-1 node is expanded.

**Step 3** In the navigation tree, select the specified parameter category and change the parameter values on the right.

If you are not sure about the location of a parameter, you can enter the parameter name in search box in the upper right corner. The system searches for the parameter in real time and displays the result.

**Step 4** Click **Save Configuration**. In the displayed dialog box, click **OK**.

**Step 5** Wait until the message **Operation successful** is displayed. Click **Finish**.

The configuration is modified.

Check whether there is any service whose configuration has expired in the cluster. If yes, restart the corresponding service or role instance for the configuration to take effect.

----End

## 21.2 Accessing FusionInsight Manager

### Scenario

FusionInsight Manager is used to monitor, configure, and manage clusters. After the cluster is installed, you can use the account to log in to FusionInsight Manager.

Currently, you can access FusionInsight Manager using the following methods:

- [Accessing FusionInsight Manager Using EIP](#)
- [Accessing FusionInsight Manager Using Direct Connect](#)
- [Accessing FusionInsight Manager from an ECS](#)

You can switch the access methods between **EIP** and **Direct Connect** on the MRS console by performing the following steps:

Log in to the MRS console and click the target cluster to go its details page. In the **Basic Information** area, click ⇌ on the right of **Access Manager**.

#### NOTE

If you cannot log in to the WebUI of the component, access FusionInsight Manager by referring to [Accessing FusionInsight Manager from an ECS](#).

## Accessing FusionInsight Manager Using EIP

- Step 1** Log in to the MRS management console.
- Step 2** In the navigation pane, choose **Clusters > Active Clusters**. Click the target cluster name to access the cluster details page.
- Step 3** Click **Manager** next to **MRS Manager**. In the displayed dialog box, configure the EIP information.
1. If no EIP is bound during MRS cluster creation, select an available EIP from the EIP drop-down list or click **Manage EIP** to create an EIP. If you have bound an EIP when creating a cluster, go to [Step 3.2](#).
  2. Select the security group to which the security group rule to be added belongs. The security group is configured when the cluster is created.
  3. Add a security group rule. By default, the filled-in rule is used to access the EIP. To enable multiple IP address segments to access Manager, see steps [Step 6](#) to [Step 9](#). If you want to view, modify, or delete a security group rule, click **Manage Security Group Rule**.
  4. Select the information to be confirmed and click **OK**.
- Step 4** Click **OK**. The Manager login page is displayed.
- Step 5** Enter the default username **admin** and the password set during cluster creation, and click **Log In**. The Manager page is displayed.
- Step 6** On the MRS management console, choose **Clusters > Active Clusters**. Click the target cluster name to access the cluster details page.

### NOTE

To grant other users the permission to access Manager, perform [Step 6](#) to [Step 9](#) to add the users' public IP addresses to the trusted IP address range.

- Step 7** Click **Add Security Group Rule** on the right of **EIP**.
- Step 8** On the **Add Security Group Rule** page, add the IP address segment for users to access the public network and select **I confirm that the authorized object is a trusted public IP address range. Do not use 0.0.0.0/0. Otherwise, security risks may arise.**

By default, the IP address used for accessing the public network is filled. You can change the IP address segment as required. To enable multiple IP address segments, repeat steps [Step 6](#) to [Step 9](#). If you want to view, modify, or delete a security group rule, click **Manage Security Group Rule**.

- Step 9** Click **OK**.

----End

## Accessing FusionInsight Manager by Using Direct Connect

When **Direct Connect** is enabled in the environment, you can access FusionInsight Manager by using Direct Connect as an MRS cluster administrator.

- Step 1** Log in to the MRS management console.

- Step 2** In the navigation pane, choose **Clusters > Active Clusters**. Click the target cluster name to access the cluster details page.
- Step 3** Click **Access Manager** next to **MRS Manager**. In the displayed dialog box, select **Direct Connect**.
- Step 4** Click **OK**. The Manager login page is displayed.
- Step 5** Enter the default username **admin** and the password set during cluster creation, and click **Log In**. The Manager page is displayed.
- End

## Accessing FusionInsight Manager from an ECS

- Step 1** On the MRS management console, click **Clusters**.
- Step 2** On the **Active Clusters** page, click the name of the specified cluster.  
Record the **AZ, VPC, MRS ManagerSecurity Group** of the cluster.
- Step 3** On the homepage of the management console, choose **Service List > Elastic Cloud Server** to switch to the ECS management console and create an ECS.
- The **AZ, VPC, and Security Group** of the ECS must be the same as those of the cluster to be accessed.
  - Select a Windows public image. For example, a standard image **Windows Server 2012 R2 Standard 64bit(40GB)**.
  - For details about other configuration parameters, see .

### NOTE

If the security group of the ECS is different from **Default Security Group** of the Master node, you can modify the configuration using either of the following methods:

- Change the security group of the ECS to the default security group of the Master node. For details, see **Elastic Cloud Server > User Guide > Security Group > Changing a Security Group**.
- Add two security group rules to the security groups of the Master and Core nodes to enable the ECS to access the cluster. Set **Protocol** to **TCP**, **Ports** of the two security group rules to **28443** and **20009**, respectively. For details, see .

- Step 4** On the VPC management console, apply for an EIP and bind it to the ECS.  
For details, see **Virtual Private Cloud > User Guide > Elastic IP > Assigning an EIP and Binding It to an ECS**.
- Step 5** Log in to the ECS.  
The Windows system account, password, EIP, and the security group rules are required for logging in to the ECS. For details, see **Elastic Cloud Server > User Guide > Instances > Logging In to a Windows ECS**.
- Step 6** On the Windows remote desktop, use your browser to access Manager.  
For example, you can use Internet Explorer 11 in the Windows 2012 OS.  
The address for accessing Manager is the address of the **MRS Manager** page. Enter the name and password of the cluster user, for example, user **admin**.

 NOTE

- If you access Manager with other cluster usernames, change the password upon your first access. The new password must meet the requirements of the current password complexity policies. For details, contact the MRS cluster administrator.
- By default, a user is locked after inputting an incorrect password five consecutive times. The user is automatically unlocked after 5 minutes.

----End

## 21.3 Using an MRS Client

### 21.3.1 Using an MRS Client on Nodes Inside a MRS Cluster

#### Scenario

Before using the client, you need to install the client. For example, the installation directory is **/opt/hadoopclient**.

#### Procedure

**Step 1** Log in to the Master node in the cluster as user **root**.

**Step 2** Run the **sudo su - omm** command to switch the current user.

**Step 3** Run the following command to go to the client directory:

```
cd /opt/hadoopclient
```

**Step 4** Run the following command to configure environment variables:

```
source bigdata_env
```

**Step 5** If the Kerberos authentication is enabled for the current cluster, run the following command to authenticate the user. If Kerberos authentication is disabled for the current cluster, skip this step:

```
kinit MRS cluster user
```

Example: **kinit admin**

 NOTE

User **admin** is created by default for MRS clusters with Kerberos authentication enabled and is used for MRS cluster administrators to maintain the clusters.

**Step 6** Run the client command of a component directly.

For example, run the **hdfs dfs -ls /** command to view files in the HDFS root directory.

----End

## 21.3.2 Using an MRS Client on Nodes Outside a MRS Cluster

### Scenario

After a client is installed, you can use the client on a node outside an MRS cluster.

### Prerequisites

- A Linux ECS has been prepared. For details about the OS and its version of the ECS, see [Table 21-1](#).

**Table 21-1** Reference list

| CPU Architecture        | Operating System (OS) | Supported Version                               |
|-------------------------|-----------------------|-------------------------------------------------|
| x86 computing           | Euler                 | Euler OS 2.5                                    |
|                         | SLES                  | SUSE Linux Enterprise Server 12 SP4 (SUSE 12.4) |
|                         | RedHat                | Red Hat-7.5-x86_64 (Red Hat 7.5)                |
|                         | CentOS                | CentOS-7.6                                      |
| Kunpeng computing (Arm) | Euler                 | Euler OS 2.8                                    |
|                         | CentOS                | CentOS-7.6                                      |

In addition, sufficient disk space is allocated for the ECS, for example, **40GB**.

- The ECS and the MRS cluster are in the same VPC.
- The security group of the ECS must be the same as that of the Master node in an MRS cluster.
- The NTP service has been installed on the ECS OS and is running properly.  
If the NTP service is not installed, run the **yum install ntp -y** command to install it when the **yum** source is configured.
- A user can log in to the Linux ECS using the password (in SSH mode).

### Procedure

**Step 1** Create an ECS that meets the requirements.

**Step 2** Perform NTP time synchronization to synchronize the time of nodes outside the cluster with the time of the MRS cluster.

1. Run the **vi /etc/ntp.conf** command to edit the NTP client configuration file, add the IP address of the Master node in the MRS cluster, and comment out the IP addresses of other servers.

```
server master1_ip prefer  
server master2_ip
```

Figure 21-1 Adding the Master node IP addresses

```
# Use public servers from the pool.ntp.org project.
# Please consider joining the pool (http://www.pool.ntp.org/join.html).
#server 0.centos.pool.ntp.org iburst
#server 1.centos.pool.ntp.org iburst
#server 2.centos.pool.ntp.org iburst
#server 3.centos.pool.ntp.org iburst
#server 7.pool.ntp.org iburst
server 10.9.2.38 prefer
server 10.9.2.39
#broadcast 192.168.1.255 autokey # broadcast server
#broadcastclient # broadcast client
#broadcast autokey # multicast server
#multicastclient # multicast client
#manycastserver autokey # manycast server
#manycastclient autokey # manycast client
```

2. Run the **service ntpd stop** command to stop the NTP service.
3. Run the **/usr/sbin/ntpdate IP address of the active Master node** command to manually synchronize the time.
4. Run the **service ntpd start** or **systemctl restart ntpd** command to start the NTP service.
5. Run the **ntpstat** command to check the time synchronization result:

**Step 3** Perform the following steps to download the cluster client software package from FusionInsight Manager, copy the package to the ECS node, and install the client:

1. Log in to FusionInsight Manager and download the cluster client to the specified directory on the active management node.
2. Log in to the active management node as user **root**.

**sudo su - omm**

3. Run the following command to copy the client to the node where the client is to be installed:

```
scp -p /tmp/FusionInsight-Client/  
FusionInsight_Cluster_1_Services_Client.tar IP address of the node where  
the client is to be installed:/tmp
```

4. Log in to a node on which the client is to be installed as the client user.  
Run the following command to install the client. If you do not have the file operation permission, change the file permission as user **root**.

```
cd /tmp  
tar -xvf FusionInsight_Cluster_1_Services_Client.tar  
tar -xvf FusionInsight_Cluster_1_Services_ClientConfig.tar  
cd /tmp/FusionInsight_Cluster_1_Services_ClientConfig  
./install.sh /opt/mrsclient
```

5. Run the following commands to switch to the client directory and configure environment variables:

```
cd /opt/mrsclient  
source bigdata_env
```

6. If the Kerberos authentication is enabled for the current cluster, run the following command to authenticate the user. If Kerberos authentication is disabled for the current cluster, skip this step:

**kinit** *MRS cluster user*

Example: **kinit admin**

7. Run the client command of a component directly.

For example, run the **hdfs dfs -ls /** command to view files in the HDFS root directory.

----**End**