Elastic Volume Service

Getting Started

Issue 01

Date 2025-06-09





Copyright © Huawei Technologies Co., Ltd. 2025. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions

HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd. All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Security Declaration

Vulnerability

Huawei's regulations on product vulnerability management are subject to the *Vul. Response Process.* For details about this process, visit the following web page:

https://www.huawei.com/en/psirt/vul-response-process

For vulnerability information, enterprise customers can visit the following web page:

https://securitybulletin.huawei.com/enterprise/en/security-advisory

Contents

| 1 | Buying a | and P | reparing | an EVS | Disk for a | Linux Server1 | |
|---|-----------------|-------|----------|--------|------------|------------------|---|
| 2 | Buving a | and P | reparing | an EVS | Disk for a | Windows Server10 | 1 |

Buying and Preparing an EVS Disk for a Linux Server

Scenarios

You can use EVS disks as system disks or data disks. System disks are purchased together with servers, while data disks can be purchased together with servers or separately. If you have purchased data disks separately, you must attach and initialize them before they can be used.

This section describes how a non-shared data disk can be purchased on the EVS console, attached to a Linux server, and initialized on the server.

Operation Process

| Procedure | Description | |
|---------------------------------|---|--|
| Preparations | Sign up for a HUAWEI ID, enable Huawei Cloud services, and top up your account. | |
| Step 1: Purchase an EVS Disk | Buy a data disk on the EVS console. | |
| Step 2: Attach the EVS Disk | Attach the data disk to a Linux server. | |
| Step 3: Initialize the EVS Disk | Initialize the data disk on the server. | |


Preparations

- 1. Sign up with Huawei Cloud.
 - To sign up for a HUAWEI ID and enable Huawei Cloud services, see
 Signing Up for a HUAWEI ID and Enabling Huawei Cloud Services.
 - To complete real-name authentication, see Getting Authenticated.
- 2. Top up your account.

- To learn more about EVS pricing, see Billing.
- To top up an account, see Topping Up an Account.

Step 1: Purchase an EVS Disk

- **Step 1** Go to the **Buy Disk** page.
- **Step 2** Configure mandatory parameters based on the following table and retain the default settings for other parameters.



| Paramete r | Example Value | Description |
|---------------|------------------------|---|
| Region | CN South- Guangzhou | Resources are region-specific and cannot be used across regions through internal network connections. For low network latency and quick resource access, select the nearest region. |
| AZ | AZ1 | You can only attach EVS disks to servers in the same AZ. After a disk is purchased, its AZ cannot be changed. |

| Paramete r | Example Value | Description |
|----------------------|---|---|
| | Later | You can attach the disk after it is purchased. |
| Billing Mode | Pay-per-use | To learn more about EVS pricing, see Billing . |
| Data Source | Do not configure it. | If you want to create an empty data disk, do not configure a data source. |
| Disk Type | Ultra-high I/O | To learn more about disk types, see Disk Types and Performance. |
| Capacity | 100 GiB | Enter a disk capacity. |
| Automatic Backup | Do not use | Automatic backup allows you to back up the disk data to ensure your data security and integrity. |
| More > Share | Do not selection this option. | A non-shared disk can only be attached to one server. The sharing attribute of a disk cannot be changed after the disk has been purchased. |
| More > SCSI | Select this option. | A SCSI disk allows the server OS to directly access the underlying storage media and send SCSI commands to the disk. The device type of a disk cannot be changed after the disk has been purchased. |
| More > Encryption | Select this option and use the default key. | EVS uses the industry-standard XTS-AES-256 cryptographic algorithm and keys to encrypt EVS disks. The encryption attribute of a disk cannot be changed after the disk has been purchased. |
| Disk Name | volume-0001 | Enter a disk name. |
| Quantity | 1 | The preset disk quantity is 1 , which means only one disk is created. |

Step 3 Click Next.

Step 4 Go back to the disk list page. When the status of the **volume-0001** disk changes to **In-use**, the disk is successfully created.


----End

Step 2: Attach the EVS Disk

EVS disks cannot be used alone. You need to attach them to cloud servers first.

Step 1 In the disk list, find the **volume-0001** disk and click **Attach** in the **Operation** column.

Step 2 Attach the **volume-0001** disk to your desired server. Ensure that the server and disk are in the same AZ.



Step 3 Click **OK** to go back to the disk list page. When the status of the **volume-0001** disk changes to **In-use**, the disk is successfully attached.

----End

Step 3: Initialize the EVS Disk

After attaching the **volume-0001** disk, you need to initialize it before it can be used. The following example uses fdisk to format the disk into two primary MBR partitions, with one 40 GiB and the other 60 GiB.

Step 1 Log in to the server.

For how to log in to an ECS, see Logging In to an ECS.

For how to log in to a BMS, see Logging In to a BMS.

- Step 2 Create two primary partitions, /dev/vdb1 and /dev/vdb2 for data disk /dev/vdb.
 - 1. Check that the capacity of the /dev/vdb data disk is 100 GiB.

lsblk

```
[root@ecs-centos76 ~]# lsblk
NAME MAJ:MIN RM SIZE RO TYPE MOUNTPOINT
vda 253:0 0 40G 0 disk
—vda1 253:1 0 40G 0 part /
vdb 253:16 0 100G 0 disk
```

The command output shows that there are two EVS disks. /dev/vda is the system disk, and /dev/vdb is the new data disk, whose 100 GiB is not partitioned.

2. Run the following commands in sequence to create the first primary partition /dev/vdb1. Replace /dev/vdb1 with your desired partition name.

fdisk /dev/vdb

n

p

[root@ecs-test-0001 ~]# fdisk /dev/vdb

Welcome to fdisk (util-linux 2.23.2).

Changes will remain in memory only, until you decide to write them. Be careful before using the write command.

Device does not contain a recognized partition table Building a new DOS disklabel with disk identifier 0x38717fc1. Command (m for help): n Partition type: p primary (0 primary, 0 extended, 4 free) e extended Select (default p): p Partition number (1-4, default 1): 1

- Entering **p** for **Partition type** creates a primary partition, and entering **e** creates an extended partition.
- Partition number indicates the partition serial number. Enter a value ranging from
- Set First sector to 2048 and Last sector to 83886079 for partition /dev/vdb1 (40 GiB).

First and last sectors of the partitions in this example are calculated as follows:

Value of sectors = Capacity/512 bytes, 1 GiB = 1073741824 bytes

First sector (2048-209715199, default 2048) shows the sector value range of the /dev/vdb data disk (100 GiB).

First sector = 2048

Last sector = Value of sectors - 1 = (100 x 1073741824/512) - 1 = 209715200 -1=209715199

For the first partition /dev/vdb1 (40 GiB) of the /dev/vdb data disk:

First sector = 2048 (The first sector of the /dev/vdb data disk is used.)

Last sector = Value of sectors - 1 = (40 x 1073741824/512) - 1 = 83886079

For the second partition /dev/vdb2 (60 GiB) of the /dev/vdb data disk: First sector = Last sector of /dev/vdb1 + 1 = 83886079 + 1 = 83886080 Last sector = First sector + Value of sectors -1 = 83886080 + (60 x)1073741824/512) - 1 = 209715199

First sector (2048-209715199, default 2048): 2048 Last sector, +sectors or +size{K,M,G} (2048-209715199, default 209715199):83886079 Partition 1 of type Linux and of size 40 GB is set

Run the following commands in sequence to create the second primary partition /dev/vdb2. Replace /dev/vdb2 with your desired partition name.

p

2

Command (m for help): n

Partition type:

- p primary (0 primary, 0 extended, 4 free)
- e extended

Select (default p): p

Partition number (1-4, default 2): 2

Set the First sector to 83886080 and Last sector to 209715199 for partition /dev/vdb2.

First sector (83886080-209715199, default 83886080): 83886080 Last sector, +sectors or +size{K,M,G} (83886080-209715199, default 209715199):209715199 Partition 2 of type Linux and of size 60 GB is set

Check the sizes and partition styles of the new partitions.

Command (m for help): p

Disk /dev/vdb: 107.4 GB, 107374182400 bytes, 209715200 sectors

Units = sectors of 1 * 512 = 512 bytes

Sector size (logical/physical): 512 bytes / 512 bytes I/O size (minimum/optimal): 512 bytes / 512 bytes

Disk label type: dosDisk identifier: 0x994727e5

 Device Boot
 Start
 End
 Blocks
 Id
 System

 /dev/vdb1
 2048
 83886079
 41942016
 83
 Linux

 /dev/vdb2
 83886080
 209715199
 62914560
 83
 Linux

Command (m for help):

◯ NOTE

Disk label type: dos indicates the MBR partition style.

In case that you want to discard the changes made before, you can exit fdisk by entering **q** and press **Enter**. Then, re-create the partitions by referring to step 1 and step 2.

Step 3 Write the changes to the partition table.

w

Command (m for help): w
The partition table has been altered!

Calling ioctl() to re-read partition table. Syncing disks.

The partition is created.

Ⅲ NOTE

If error message **-bash**: **partprobe**: **command not found** is returned, the system cannot identify the command. In this case, run **yum install -y parted** to install the command. Then, run the command again.

Step 4 Synchronize the new partition table to the OS.

partprobe

Step 5 Create ext4 file systems for partitions /dev/vdb1 (40 GiB) and /dev/vdb2 (60 GiB).

mkfs -t ext4 /dev/vdb1

mkfs -t ext4 /dev/vdb2

◯ NOTE

It takes some time to create file systems. Do not exit before the system returns the following information:

[root@ecs-test-0001 ~]# mkfs -t ext4 /dev/vdb1 mke2fs 1.42.9 (28-Dec-2013)
Filesystem label=
OS type: Linux
Block size=4096 (log=2)
Fragment size=4096 (log=2)
Stride=0 blocks, Stripe width=0 blocks
2621440 inodes, 10485504 blocks
524275 blocks (5.00%) reserved for the super user

First data block=0

Maximum filesystem blocks=2157969408

Check whether the file system format is ext4.

blkid

```
[root@ecs-test-0001 ~]# blkid /dev/vdb
/dev/vdb1: UUID="0b3040e2-1367-4abb-841d-ddb0b92693df" TYPE="ext4"
/dev/vdb2: UUID="0d6769k2-1745-9dsf-453d-hgd0b34267dj" TYPE="ext4"
```

Step 6 Create directories (mount points) and mount the new partitions on the created mount points.

1. Mount /dev/vdb1 on /mnt/sdc.

mkdir -p /mnt/sdc mount /dev/vdb1 /mnt/sdc

2. Mount /dev/vdb2 on /mnt/sdd.

mkdir -p /mnt/sdd mount /dev/vdb2 /mnt/sdd

3. View the mount results.

lsblk

```
[root@ecs-test-0001 ~]# lsblk

NAME MAI:MIN RM SIZE RO TYPE MOUNTPOINT

vda 253:0 0 40G 0 disk

|-vda1 253:1 0 40G 0 part /

vdb 253:16 0 100G 0 disk

|-vdb1 253:17 0 40G 0 part /mnt/sdc

-vdb2 253:18 0 60G 0 part /mnt/sdd
```

You should now see that partitions /dev/vdb1 and /dev/vdb2 are mounted on /mnt/sdc and /mnt/sdd.

Step 7 Use the partition UUIDs to configure auto mount at startup.

∩ NOTE

- Mounts become invalid after a system reboot. You can configure auto mount at startup by adding information of the new partitions into the /etc/fstab file.
- You are advised not to use device names to identify disks in the /etc/fstab file because device names are assigned dynamically and may change (for example, from /dev/vdb1 to /dev/vdb2) after a server stop or start. This can even prevent your server from booting up.
- UUIDs are the unique character strings for identifying partitions in Linux.
- This operation will not affect the existing data on the ECS.
- Query the partition UUIDs.

blkid /dev/vdb1 blkid /dev/vdb2 [root@ecs-test-0001 ~]# **blkid /dev/vdb** /dev/vdb1: UUID="0b3040e2-1367-4abb-841d-ddb0b92693df" TYPE="ext4" /dev/vdb2: UUID="0d6769k2-1745-9dsf-453d-hgd0b34267dj" TYPE="ext4"

Take note of the UUIDs of partitions /dev/vdb1 and /dev/vdb2: 0b3040e2-1367-4abb-841d-ddb0b92693df and 0d6769k2-1745-9dsf-453d-hgd0b34267dj

2. Configure auto mount at startup.

vi /etc/fstab

Press i to enter the editing mode, move the cursor to the end of the file, press **Enter**, and add the following content:

UUID=0b3040e2-1367-4abb-841d-ddb0b92693df /mnt/sdc ext4 defaults 0 2 UUID=0d6769k2-1745-9dsf-453d-hgd0b34267dj /mnt/sdd ext4 defaults 0 2

Press **Esc**, enter :wq, and press **Enter** to save the settings and exit the vi editor.

Table 1-1 Content description

| Example Value | Description | |
|---|---|--|
| UUID=0b3040e2-1367 -4abb-841d- ddb0b92693df | The UUID of the partition. | |
| /mnt/sdc | The mount point of the partition. | |
| ext4 | The file system format of the partition. | |
| defaults | The partition mount option. Normally, this parameter is set to defaults . | |
| 0 | – The Linux dump backup option. | |
| | 0: Linux dump backup is not used. Usually, dump backup is not used, and you can set this parameter to 0. | |
| | ■ 1: Linux dump backup is used. | |
| 2 | The fsck option, which means whether to use fsck to check the disk during startup. | |
| | 2: The check starts from the partitions whose mount points are non-root directories. / is the root directory. | |
| | 1: The check starts from the partitions whose mount points are root directories. | |
| | ■ 0 : The fsck option is not used. | |

Step 8 Verify that auto mount takes effect.

umount /dev/vdb1 umount /dev/vdb2

mount -a

The system reloads all the content in the /etc/fstab file.

Query the file system mount information.

mount | grep /mnt/sdc

mount | grep /mnt/sdd

If information similar to the following is displayed, auto mount has taken effect:

root@ecs-test-0001 ~]# mount | grep /mnt/sdc /dev/vdb1 on /mnt/sdc type ext4 (rw,relatime,data=ordered) root@ecs-test-0001 ~]# mount | grep /mnt/sdd /dev/vdb2 on /mnt/sdd type ext4 (rw,relatime,data=ordered)

----End

You can use the disk after it is initialized.

2 Buying and Preparing an EVS Disk for a Windows Server

Scenarios

You can use EVS disks as system disks or data disks. System disks are purchased together with servers, while data disks can be purchased together with servers or separately. If you have purchased data disks separately, you must attach and initialize them before they can be used.

This section describes how a non-shared data disk can be purchased on the EVS console, attached to a Windows server, and initialized on the server.

Operation Process

| Procedure | Description | |
|---------------------------------|---|--|
| Preparations | Sign up for a HUAWEI ID, enable Huawei Cloud services, and top up your account. | |
| Step 1: Purchase an EVS Disk | Buy a data disk on the EVS console. | |
| Step 2: Attach the EVS Disk | Attach the data disk to a Windows server. | |
| Step 3: Initialize the EVS Disk | Initialize the data disk on the server. | |


Preparations

- 1. Sign up with Huawei Cloud.
 - To sign up for a HUAWEI ID and enable Huawei Cloud services, see
 Signing Up for a HUAWEI ID and Enabling Huawei Cloud Services.
 - To complete real-name authentication, see Getting Authenticated.
- 2. Top up your account.

- To learn more about EVS pricing, see Billing.
- To top up an account, see Topping Up an Account.

Step 1: Purchase an EVS Disk

- **Step 1** Go to the **Buy Disk** page.
- **Step 2** Configure mandatory parameters based on the following table and retain the default settings for other parameters.



| Paramete r | Example Value | Description |
|---------------|------------------------|---|
| Region | CN South- Guangzhou | Resources are region-specific and cannot be used across regions through internal network connections. For low network latency and quick resource access, select the nearest region. |
| AZ | AZ1 | You can only attach EVS disks to servers in the same AZ. After a disk is purchased, its AZ cannot be changed. |

| Paramete r | Example Value | Description |
|----------------------|---|---|
| | Later | You can attach the disk after it is purchased. |
| Billing Mode | Pay-per-use | To learn more about EVS pricing, see Billing . |
| Data Source | Do not configure it. | If you want to create an empty data disk, do not configure a data source. |
| Disk Type | Ultra-high I/O | To learn more about disk types, see Disk Types and Performance. |
| Capacity | 100 GiB | Enter a disk capacity. |
| Automatic Backup | Do not use | Automatic backup allows you to back up the disk data to ensure your data security and integrity. |
| More > Share | Do not selection this option. | A non-shared disk can only be attached to one server. The sharing attribute of a disk cannot be changed after the disk has been purchased. |
| More > SCSI | Select this option. | A SCSI disk allows the server OS to directly access the underlying storage media and send SCSI commands to the disk. The device type of a disk cannot be changed after the disk has been purchased. |
| More > Encryption | Select this option and use the default key. | EVS uses the industry-standard XTS-AES-256 cryptographic algorithm and keys to encrypt EVS disks. The encryption attribute of a disk cannot be changed after the disk has been purchased. |
| Disk Name | volume-0001 | Enter a disk name. |
| Quantity | 1 | The preset disk quantity is 1 , which means only one disk is created. |

Step 3 Click Next.

Step 4 Go back to the disk list page. When the status of the **volume-0001** disk changes to **In-use**, the disk is successfully created.


----End

Step 2: Attach the EVS Disk

EVS disks cannot be used alone. You need to attach them to cloud servers first. In the following example, the **volume-0001** disk is attached.

Step 1 In the disk list, find the **volume-0001** disk and click **Attach** in the **Operation** column.

Step 2 Attach the **volume-0001** disk to your desired server. Ensure that the server and disk are in the same AZ.



Step 3 Click **OK** to go back to the disk list page. When the status of the **volume-0001** disk changes to **In-use**, the disk is successfully attached.

----End

Step 3: Initialize the EVS Disk

After attaching the **volume-0001** disk, you need to initialize it before it can be used. In the following example, the disk is formatted into a 100 GiB GPT partition with the NTFS file system.

Step 1 Log in to the server.

For how to log in to an ECS, see Logging In to an ECS.

For how to log in to a BMS, see Logging In to a BMS.

Step 2 On the desktop of the server, click the start icon in the lower left corner.

The Windows Server window is displayed.

Step 3 Click Server Manager.

The Server Manager window is displayed.

Windows PowerShell

Windows PowerShell (x86)

Windows PowerShell ISE

Windows PowerShell ISE (x86) Windows Server Backup

П Server Manager > Dashboard Computer Management WELCOME TO SERVER MANAGER Defragment and Optimize Drives I Local Server Disk Cleanup All Servers Event Viewe 1) Configure this local server iSCSI Initiator File and Storage Services D Local Security Policy Microsoft Azure Services 2 Add roles and features ODBC Data Sources (32-bit) ODBC Data Sources (64-bit) 3 Add other servers to manage Performance Monitor 4 Create a server group Print Management 5 Connect this server to cloud serv Services System Configuration System Information Task Scheduler Windows Firewall with Advanced Security ROLES AND SERVER GROUPS Windows Memory Diagnostic

Local Server

Manageability

Services

Performance BPA results

Figure 2-1 Server Manager

Step 4 In the upper right corner, choose **Tools** > **Computer Management**.


File and Storage


Services

Manageability

Performance

BPA results





Step 5 Choose Storage > Disk Management.


Disks are displayed in the right pane. If there is a disk that is not initialized, the system will prompt you with the Initialize Disk dialog box.

In the **Initialize Disk** dialog box, the to-be-initialized disk is selected. Select a partition style and click **OK**. In this example, **GPT (GUID Partition Table)** is selected.

NOTICE

The maximum disk size supported by MBR is 2 TiB, and that supported by GPT is 18 EiB. Because an EVS data disk currently supports up to 32 TiB, use GPT if your disk size is greater than 2 TiB.

If the partition style of an in-use disk is changed, all data on the disk will be lost, so take care to select an appropriate partition style when initializing the disk. If you must change the partition style to GPT, it is recommended that you back up the disk data before the change.




Step 6 In the **Unallocated** area of **Disk 1**, right-click the blank area and choose **New Simple Volume**.

- 🗆 Computer Management File Action View Help 👉 📦 🖄 📆 🛭 🖸 📆 🜆 Computer Management (Local Volume Layout Type File System Status C Actions Healthy (Boot, Page File, Crash Dump, Primary Partition) Healthy (System, Active, Primary Partition) Disk Management Task Scheduler > [a] Event Viewer
> ai Shared Folders
> ai Local Users and Groups > Secol Users and Groups
> So Performance
 Device Manager
> Storage
> Mondows Server Backup
 Disk Management
> Services and Applications New Simple Volume... Disk 0 New Spanned Volume.. Basic 40.00 GB System Reserved 500 MB NTFS 39.51 GB NTFS Healthy (Boot, Pa New Striped Volume... Online Healthy (System, Active, Prir New Mirrored Volume.. New RAID-5 Volume... Disk 1 Basic 99.88 GB Online Properties 99.88 GB Help Unallocated > Unallocated Primary partition

Figure 2-4 Computer Management

The New Simple Volume Wizard window is displayed.

Figure 2-5 New Simple Volume Wizard



Step 7 Click Next to go to the Specify Volume Size page.


_ _ File Action View Help 🜆 Computer Management (Local Volume Layout Type File System Status C Actions System Tools Partition) Disk Management Task Scheduler More Actions Rvent Viewer Specify Volume Size > 🗟 Shared Folders
> 🜆 Local Users and Groups Choose a volume size that is between the maximum and minimum sizes 102270 Disk Management

Services and Applications 8 102270 < Back Next > Cancel Disk 1 99.88 GB Unallocated

Figure 2-6 Specify Volume Size

Step 8 Specify the volume size and click **Next**. The system selects the maximum volume size by default. You can specify the volume size as required. In this example, the default setting is used.





Step 9 Assign a drive letter or path to your partition and click **Next**. The system assigns drive letter D by default. In this example, the default setting is used.

File Action View Help 🦛 📦 | 🚈 🔚 🛭 🕞 🗩 🗹 🖂 🜆 Computer Management (Local Volume Layout | Type | File System | Status C Actions System Tools Partition) Disk Management ⚠ Task Scheduler
Event Viewer More Actions Format Partition Shared Folders
Local Users and Groups To store data on this partition, you must format it first Performance

Device Manager Choose whether you want to format this volume, and if so, what settings you want to use ✓ 🤮 Storage

> 🐿 Windows Server Backup O Do not format this volume Disk Management

Services and Applications () Format this volume with the following settings: New Volume Perform a quick format Enable file and folder comp < Back Next > Cancel Disk 1 Basic 99.88 GB 99.88 GB Unallocated Online > Unallocated Primary partition

Figure 2-8 Format Partition

Step 10 Specify format settings and click **Next**. The system selects the NTFS file system by default. You can specify a file system format as required. In this example, the default setting is used.




Figure 2-9 Completing the New Simple Volume Wizard


NOTICE

The partition sizes supported by file systems vary. Choose an appropriate file system format based on your service requirements.

Step 11 Click Finish.

Wait for the initialization to complete. When the volume status changes to **Healthy**, the initialization has succeeded.

Figure 2-10 Disk initialized



Step 12 After the volume is created, click on the task bar and check whether a new volume appears in the File Explorer. In this example, New Volume (D:) is the new volume.

If New Volume (D:) appears, the disk is successfully initialized and no further action is required.

💻 | 🛂 📗 🖚 | This PC File Computer View v ? ← → · ↑ 🛂 > This PC ∨ o Search This PC ∨ Folders (6) ♣ Ouick access Desktop Downloads Desktop Documents Downloads Documents Videos Pictures This PC ∨ Devices and drives (2) Desktop Local Disk (C:) 18.7 GB free of 39.5 GB New Volume (D:) Documents 99.7 GB free of 99.8 GB Downloads Music Pictures Videos Local Disk (C:) New Volume (D:) Network

Figure 2-11 File Explorer

----End

8 items

You can use the disk after it is initialized.

B== 🖃