

Distributed Message Service for Kafka

User Guide

Issue 01
Date 2025-02-13



Copyright © Huawei Cloud Computing Technologies Co., Ltd. 2025. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Cloud Computing Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are the property of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei Cloud and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Contents

1 Process of Using Kafka.....	1
2 Permissions Management.....	3
2.1 Creating an IAM User and Granting DMS for Kafka Permissions.....	3
3 Buying a Kafka Instance.....	7
4 Configuring Topics.....	27
4.1 Creating a Kafka Topic.....	27
4.2 Configuring Kafka Topic Permissions.....	33
4.3 Managing Topics.....	36
4.3.1 Viewing Kafka Topic Details.....	36
4.3.2 Modifying Kafka Topic Configurations.....	37
4.3.3 Changing Kafka Partition Quantity.....	39
4.3.4 Modifying Kafka Topic Replicas.....	43
4.3.5 Exporting the Kafka Topic List.....	47
4.3.6 Reassigning Kafka Partitions.....	48
4.3.7 Configuring Automatic Topic Creation.....	60
4.3.8 Deleting a Kafka Topic.....	61
5 Connecting to an Instance.....	64
5.1 Configuring Kafka Network Connections.....	64
5.1.1 Kafka Network Connection Conditions.....	64
5.1.2 Configuring Kafka Public Access.....	66
5.1.3 Accessing Kafka Using a VPC Endpoint Across VPCs.....	74
5.1.4 Accessing Kafka in a Public Network Using DNAT.....	79
5.2 Configuring Kafka Access Control.....	83
5.2.1 Configuring Plaintext or Ciphertext Access to Kafka Instances.....	83
5.2.2 Generating and Replacing an SSL Kafka Certificate in JKS Format.....	89
5.2.3 Obtaining and Using An SSL Kafka Certificate in PEM Format.....	95
5.2.4 Configuring Mutual SSL Authentication for Kafka.....	96
5.2.5 Configuring Kafka ACL Users.....	104
5.3 Configuring the Kafka Client.....	108
5.3.1 Setting Parameters for Kafka Clients.....	108
5.3.2 Suggestions on Using the Kafka Client.....	114
5.4 Connecting to Kafka Using the Client (SASL Disabled).....	116


5.5 Connecting to Kafka Using the Client (SASL Enabled).....	118
5.6 Connecting to Kafka on the Console.....	123
6 Managing Messages.....	125
6.1 Viewing Kafka Messages.....	125
6.2 Changing Kafka Message Retention Period.....	127
6.3 Deleting Kafka Messages.....	128
6.4 Diagnosing Kafka Message Accumulation.....	130
7 Managing Consumer Groups.....	134
7.1 Creating a Kafka Consumer Group.....	134
7.2 Querying the Kafka Consumer Group List.....	136
7.3 Viewing Kafka Consumer Information.....	138
7.4 Viewing and Resetting Kafka Consumption Offsets.....	142
7.5 Viewing Kafka Rebalancing Logs.....	147
7.6 Modifying Kafka Consumer Group Description.....	150
7.7 Exporting Kafka Consumer Groups.....	150
7.8 Deleting a Kafka Consumer Group.....	151
8 Managing Quotas.....	154
8.1 Configuring Kafka Quotas.....	154
8.2 Monitoring Kafka Quotas.....	159
9 Managing Instances.....	161
9.1 Viewing and Modifying Basic Information of a Kafka Instance.....	161
9.2 Viewing Kafka Disk Usage.....	167
9.3 Viewing Kafka Background Tasks.....	168
9.4 Viewing Sample Code of Kafka Production and Consumption.....	169
9.5 Modifying Kafka Instance Configuration Parameters.....	170
9.6 Configuring Kafka Instance Tags.....	176
9.7 Configuring Kafka Recycling Policies.....	177
9.8 Upgrading the Kafka Instance Kernel.....	180
9.9 Exporting the Kafka Instance List.....	182
9.10 Restarting a Kafka Instance.....	183
9.11 Deleting Kafka Instances.....	184
9.12 Using Kafka Manager.....	184
9.12.1 Accessing Kafka Manager.....	184
9.12.2 Resetting Kafka Manager Password.....	191
9.12.3 Restarting Kafka Manager.....	192
9.12.4 Disabling Kafka Manager.....	193
10 Modifying Instance Specifications.....	195
10.1 Modifying Cluster Kafka Instance Specifications.....	195
11 Migrating Data.....	203
11.1 Kafka Data Migration Overview.....	203

11.2 Migrating Data Using Smart Connect.....	206
11.2.1 Enabling Smart Connect.....	206
11.2.2 Replicating Kafka Instance Data.....	208
11.2.3 Dumping Kafka Data to Object Storage Service (OBS).....	215
11.2.4 Managing Smart Connect Tasks.....	217
11.2.5 Disabling Smart Connect.....	219
12 Testing Instance Performance.....	221
12.1 Kafka Production Rate and CPU Usage.....	221
12.2 Kafka Instance TPS.....	236
13 Applying for Increasing Kafka Quotas.....	242
14 Monitoring and Alarms.....	244
14.1 Viewing Kafka Metrics.....	244
14.2 Kafka Metrics.....	246
14.3 Configuring a Kafka Alarm Rule.....	259
15 Viewing Kafka Audit Logs.....	266

1 Process of Using Kafka

Distributed Message Service for Kafka is a message queuing service that is based on the open-source Apache Kafka. It provides Kafka instances with isolated computing, storage, and bandwidth resources. The following figure shows the process of message production and consumption using a Kafka instance.

Figure 1-1 Process of using Kafka



1. **Creating an IAM User and Granting DMS for Kafka Permissions**
Create IAM users and grant them only the DMS for Kafka permissions required to perform a given task based on their job responsibilities.
2. **Buying a Kafka Instance**
Kafka instances are tenant-exclusive, and physically isolated in deployment.
3. **Creating a Kafka Topic**
Create a topic for storing messages so that producers can produce messages and consumers can subscribe to messages.

4. **Connecting to an Instance**

The client uses commands to connect to Kafka instances in a private or public network, and produces and consumes messages.

2 Permissions Management

2.1 Creating an IAM User and Granting DMS for Kafka Permissions

This section describes how to use [Identity and Access Management \(IAM\)](#) for fine-grained permissions control for your Distributed Message Service (DMS) for Kafka resources. With IAM, you can:

- Create IAM users for personnel based on your enterprise's organizational structure. Each IAM user has their own identity credentials for accessing DMS for Kafka resources.
- Grant users only the permissions required to perform a given task based on their job responsibilities.
- Entrust another HUAWEI ID or cloud service to perform efficient O&M on your DMS for Kafka resources.

If your HUAWEI ID meets your permissions requirements, you can skip this section.


This section describes the procedure for granting permissions (see [Figure 2-1](#)).

Prerequisites

Learn about the permissions (see [System-defined roles and policies supported by DMS for Kafka](#)) supported by DMS for Kafka and choose policies according to your requirements. For the permissions of other services, see [System Permissions](#).

Process Flow

Figure 2-1 Process for granting DMS for Kafka permissions



1. For the following example, **create a user group on the IAM console** and assign the **DMS ReadOnlyAccess** policy to the group.
2. **Create an IAM user and add it to the created user group.**
3. **Log in as the IAM user** and verify permissions.

In the authorized region, perform the following operations:

- Choose **Service List > Distributed Message Service (for Kafka)**. Then click **Buy Instance** on the console of DMS for Kafka. If a message appears indicating that you cannot perform the operation, the **DMS ReadOnlyAccess** policy is in effect.
- Choose **Service List > Elastic Volume Service**. If a message appears indicating that you have insufficient permissions, the **DMS ReadOnlyAccess** policy is in effect.
- Choose **Service List > Distributed Message Service for Kafka**. If the Kafka instance list can be displayed, the **DMS ReadOnlyAccess** policy is in effect.

Example Custom Policies

You can create custom policies to supplement the system-defined policies of DMS for Kafka. For details about actions supported in custom policies, see [Permissions and Supported Actions](#)

To create a custom policy, choose either visual editor or JSON.

- Visual editor: Select cloud services, actions, resources, and request conditions. This does not require knowledge of policy syntax.
- JSON: Create a JSON policy or edit an existing one.

For details, see [Creating a Custom Policy](#). The following lists examples of common DMS for Kafka custom policies.

NOTE

- DMS for Kafka permissions policies are based on DMS. Therefore, when assigning permissions, select DMS permissions policies.
- Due to data caching, a policy involving Object Storage Service (OBS) actions will take effect five minutes after it is attached to a user, user group, or project.
- Example 1: Grant permission to delete and restart instances.

```
{
  "Version": "1.1",
  "Statement": [
    {
      "Effect": "Allow",
      "Action": [
        "dms:instance:modifyStatus",
        "dms:instance:delete"
      ]
    }
  ]
}
```

- Example 2: Grant permission to deny instance deletion.

A policy with only "Deny" permissions must be used together with other policies. If the permissions granted to an IAM user contain both "Allow" and "Deny", the "Deny" permissions take precedence over the "Allow" permissions.

Assume that you want to grant the permissions of the **DMS FullAccess** policy to a user but want to prevent them from deleting instances. You can create a custom policy for denying instance deletion, and attach this policy together with the **DMS FullAccess** policy to the user. As an explicit deny in any policy overrides any allows, the user can perform all operations on DMS for Kafka excepting deleting instances.

Example policy denying instance deletion:

```
{
  "Version": "1.1",
  "Statement": [
    {
      "Effect": "Deny",
      "Action": [
        "dms:instance:delete"
      ]
    }
  ]
}
```

DMS for Kafka Resources

A resource is an object that exists within a service. DMS for Kafka resources include **kafka**. To select these resources, specify their paths.

Table 2-1 DMS for Kafka resources and their paths

Resource	Resource Name	Path
kafka	Instance	<p>[Format] DMS:*:*: kafka:<i>instance ID</i></p> <p>[Notes] For instance resources, IAM automatically generates the prefix (DMS:*:*:kafka:) of the resource path. For the path of a specific resource, add the <i>instance ID</i> to the end. You can also use an asterisk * to indicate any resource. For example: DMS:*:*:kafka:* indicates any Kafka instance.</p>

DMS for Kafka Request Conditions

Request conditions are useful in determining when a custom policy is in effect. A request condition consists of condition keys and operators. Condition keys are either global or service-level and are used in the Condition element of a policy statement. **Global condition keys** (starting with **g:**) are available for operations of all services, while service-specific condition keys (starting with a service name such as **dms:**) are available only for operations of specific services. An operator must be used together with a condition key to form a complete condition statement.

DMS for Kafka has a group of predefined condition keys that can be used in IAM. For example, to define an "Allow" permission, use the condition `dms:ssl` to filter instances by SASL configurations. The following table lists the DMS for Kafka predefined condition keys.

Table 2-2 Predefined condition keys of DMS for Kafka

Condition Key	Operator	Description
<code>dms:connector</code>	Bool Null	Whether Smart Connect is enabled
<code>dms:publicIP</code>	Bool Null	Whether public access is enabled
<code>dms:ssl</code>	Bool Null	Whether SSL is enabled

3 Buying a Kafka Instance

Kafka instances are tenant-exclusive, and physically isolated in deployment. You can customize the computing capabilities and storage space of a Kafka instance as required.

Preparing Instance Dependencies

Before creating a Kafka instance, prepare the resources listed in [Table 3-1](#).

Table 3-1 Kafka resources

Resource	Requirement	Operations
VPC and subnet	<p>You need to configure a VPC and subnet for the Kafka instance as required. You can use the current account's existing VPC and subnet or shared ones, or create new ones.</p> <p>VPC owners can share the subnets in a VPC with one or multiple accounts through Resource Access Manager (RAM). Through VPC sharing, you can easily configure, operate, and manage multiple accounts' resources at low costs. For more information about VPC and subnet sharing, see VPC Sharing.</p> <p>Note when creating a VPC and a subnet:</p> <ul style="list-style-type: none"> • The VPC must be created in the same region as the Kafka instance. • The Kafka instance supports IPv6 after it is enabled for the subnet. The instance with IPv6 enabled can be accessed on a client using IPv6 addresses. 	<p>For details on how to create a VPC and a subnet, see Creating a VPC. If you need to create and use a new subnet in an existing VPC, see Creating a Subnet for the VPC.</p>
Security group	<p>Different Kafka instances can use the same or different security groups.</p> <p>The security group must be in the same region as the Kafka instance.</p> <p>Before accessing a Kafka instance, configure security groups based on the access mode. For details, see Table 5-2.</p>	<p>For details on how to create a security group, see Creating a Security Group. For details on how to add rules to a security group, see Adding a Security Group Rule.</p>

Resource	Requirement	Operations
EIP	<p>To access a Kafka instance on a client over a public network, create EIPs in advance.</p> <p>Note the following when creating EIPs:</p> <ul style="list-style-type: none"> • The EIPs must be created in the same region as the Kafka instance. • The number of EIPs must be the same as the number of Kafka instance brokers. • The Kafka console cannot identify IPv6 EIPs. 	<p>For details about how to create an EIP, see Assigning an EIP.</p>

Notes and Constraints

- SASL_SSL cannot be manually configured for instances with IPv6 enabled.
- Ciphertext access and Smart Connect are unavailable for single-node instances.

Quick Config of a Kafka Instance

Step 1 Go to the [Buy Instance](#) page.

Step 2 Set basic instance configurations on the **Quick Config** page.

Table 3-2 Basic instance configuration parameters

Parameter	Description
Billing Mode	<ul style="list-style-type: none"> • Yearly/Monthly is a prepaid mode. You need to pay first, and will be billed for your subscription period. • Pay-per-use is a postpaid mode. You can pay after using the service, and will be billed for your usage duration. The fees are calculated in seconds and settled by hour.
Region	DMS for Kafka instances in different regions cannot communicate with each other over an intranet. Select a nearest location for low latency and fast access.
AZ	<p>An AZ is a physical region where resources use independent power supply and networks. AZs are physically isolated but interconnected through an internal network.</p> <p>Select one AZ or at least three AZs. The AZ setting is fixed once the instance is created.</p>

Step 3 Select the bundle.


- **Recommended:** Select a preset DMS for Kafka bundle as required. Specify the disk type and capacity as required. **The disk type cannot be changed once the Kafka instance is created.**

The storage space is consumed by message replicas, logs, and metadata. Specify the storage space based on the expected service message size, the number of replicas, and the reserved disk space. Each Kafka broker reserves 33 GB disk space for storing logs and metadata.

Disks are formatted when an instance is created. As a result, the actual available disk space is 93% to 95% of the total disk space.


The disk supports high I/O, ultra-high I/O, Extreme SSD, and General Purpose SSD types. For more information, see [Disk Types and Performance](#).

Figure 3-1 Recommended



- **Custom:** The system calculates **Brokers** and **Storage Space per Broker**, and provides **Recommended Specifications** based on your selected version and specified parameters: **Peak Creation Traffic**, **Retrieval Traffic**, **Replicas per Topic**, **Total Partitions**, and **Messages Created During Retention Period**.

Figure 3-2 Specification calculation



Step 4 Set the network information.

Table 3-3 Instance network parameters

Parameter	Description
VPC	<p>Select a created or shared VPC.</p> <p>A VPC provides an isolated virtual network for your Kafka instances. You can configure and manage the network as required. You can click Manage VPCs on the right to go to the VPC console, and view or create VPCs.</p> <p>After the Kafka instance is created, its VPC cannot be changed.</p>
Subnet	<p>Select a created or shared subnet.</p> <p>After the Kafka instance is created, its subnet cannot be changed.</p> <p>The Kafka instance supports IPv6 after it is enabled for the subnet.</p>
IPv6	<p>This parameter is displayed after IPv6 is enabled for the subnet. The instance with IPv6 enabled can be accessed on a client using IPv6 addresses.</p> <p>SASL_SSL cannot be manually configured for instances with IPv6 enabled.</p> <p>The IPv6 setting is fixed once the instance is created.</p> <p>This function is available only in the CN East2 region.</p>
Security Group	<p>Select a created security group.</p> <p>A security group is a set of rules for accessing a Kafka instance. You can click Manage Security Group to view or create security groups on the network console.</p> <p>Before accessing a Kafka instance on the client, configure security group rules based on the access mode. For details about security group rules, see Table 5-2.</p>

Step 5 Configure the instance access mode.

Table 3-4 Instance access mode parameters

Parameter	Sub-Parameter	Description
Private Network Access	Access Method	<p>There are two methods:</p> <ul style="list-style-type: none"> • Plaintext access: Clients connect to the Kafka instance without SASL authentication. • Ciphertext access: Clients connect to the Kafka instance with SASL authentication. Enabling Ciphertext Access requires the Kafka security protocol, SSL username, password, and SASL PLAIN. <p>Once enabled, private network access cannot be disabled. Enable plaintext or ciphertext access, or both.</p>
	Cross-VPC Access Protocol	<ul style="list-style-type: none"> • When Plaintext Access is enabled and Ciphertext Access is disabled, PLAINTEXT is used for Cross-VPC Access Protocol. • When Ciphertext Access is enabled and Security Protocol is SASL_SSL, SASL_SSL is used for Cross-VPC Access Protocol. • When Ciphertext Access is enabled and Security Protocol is SASL_PLAINTEXT, SASL_PLAINTEXT is used for Cross-VPC Access Protocol. <p>Fixed once the instance is created.</p>
	Private IP Addresses	<p>Select Auto or Manual.</p> <ul style="list-style-type: none"> • Auto: The system automatically assigns an IP address from the subnet. • Manual: Select IP addresses from the drop-down list. If the number of selected IP addresses is less than the number of brokers, the remaining IP addresses will be automatically assigned.
Public Network Access	Access Method	<p>There are two methods:</p> <ul style="list-style-type: none"> • Plaintext access: Clients connect to the Kafka instance without SASL authentication. • Ciphertext access: Clients connect to the Kafka instance with SASL authentication. Enabling Ciphertext Access requires the Kafka security protocol, SSL username, password, and SASL PLAIN. <p>After public access is enabled, enable plaintext or ciphertext access, or both.</p>



Parameter	Sub-Parameter	Description
	Public IP Addresses	Select the number of public IP addresses as required. If EIPs are insufficient, click Create Elastic IP to create EIPs. Then, return to the Kafka console and click  next to Public IP Address to refresh the public IP address list. Kafka instances only support IPv4 EIPs.

Figure 3-3 Instance access mode



The Kafka security protocol, SSL username, password, and SASL/PLAIN mechanism are described as follows.

Table 3-5 Ciphertext access parameters

Parameter	Value	Description
Security Protocol	SASL_SSL	SASL is used for authentication. Data is encrypted with SSL certificates for high-security transmission.

Parameter	Value	Description
	SASL_PLAINTEXT	SASL is used for authentication. Data is transmitted in plaintext for high performance. SCRAM-SHA-512 authentication is recommended for plaintext transmission.
SSL Username	-	Username for a client to connect to a Kafka instance. A username should contain 4 to 64 characters, start with a letter, and contain only letters, digits, hyphens (-), and underscores (_). The username cannot be changed once ciphertext access is enabled.
Password	-	Password for a client to connect to a Kafka instance. A password must meet the following requirements: <ul style="list-style-type: none"> • Contains 8 to 32 characters. • Contains at least three types of the following characters: uppercase letters, lowercase letters, digits, and special characters `~!@#\$%^&*()-_+=\ []{};:","<.>?` and spaces, and cannot start with a hyphen (-). • Cannot be the username spelled forward or backward.
SASL/PLAIN	-	<ul style="list-style-type: none"> • If SASL/PLAIN is disabled, the SCRAM-SHA-512 mechanism is used for username and password authentication. • If SASL/PLAIN is enabled, both the SCRAM-SHA-512 and PLAIN mechanisms are supported. You can select either of them as required. <p>The SASL/PLAIN setting cannot be changed once ciphertext access is enabled.</p> <p>What are SCRAM-SHA-512 and PLAIN mechanisms?</p> <ul style="list-style-type: none"> • SCRAM-SHA-512: uses the hash algorithm to generate credentials for usernames and passwords to verify identities. SCRAM-SHA-512 is more secure than PLAIN. • PLAIN: a simple username and password verification mechanism.

Step 6 Configure advanced settings.**Table 3-6** Advanced configuration parameters

Parameter	Description
Instance Name	You can customize a name that complies with the rules: 4–64 characters; starts with a letter; can contain only letters, digits, hyphens (-), and underscores (_).
Enterprise Project	This parameter is for enterprise users. Enterprise projects facilitate project-level management and grouping of cloud resources and users. The default project is default .
Capacity Threshold Policy	Specify how messages are processed when the disk usage threshold (95%) is reached. <ul style="list-style-type: none">• Automatically delete: Messages can be produced and consumed, but 10% of the earliest messages will be deleted to ensure sufficient disk space. This policy is suitable for scenarios where no service interruption can be tolerated. Data may be lost.• Stop production: New messages cannot be produced, but existing messages can still be consumed. This policy is suitable for scenarios where no data loss can be tolerated.
Smart Connect	Configure Smart Connect . Smart Connect is used for data synchronization between heterogeneous systems. You can configure Smart Connect tasks to synchronize data between Kafka and another cloud service or between two Kafka instances. Enabling Smart Connect creates two brokers.
Automatic Topic Creation	Enable automatic Kafka topic creation if needed. If this option is enabled, a topic will be automatically created when a message is produced in or consumed from a topic that does not exist. The default topic parameters are listed in Table 3-7 . <ul style="list-style-type: none">• For cluster instances, after you change the value of the log.retention.hours (retention period), default.replication.factor (replica quantity), or num.partitions (partition quantity) parameter, the value will be used in later topics that are automatically created. For example, assume that num.partitions is changed to 5, an automatically created topic has parameters listed in Table 3-7.• Unavailable for single-node instances.

Parameter	Description
Tags	<p>Tags are used to identify cloud resources. When you have multiple cloud resources of the same type, you can use tags to classify them based on usage, owner, or environment.</p> <p>If your organization has configured tag policies for DMS for Kafka, add tags to Kafka instances based on the policies. If a tag does not comply with the policies, Kafka instance creation may fail. Contact your organization administrator to learn more about tag policies.</p> <ul style="list-style-type: none"> If you have predefined tags, select a predefined pair of tag key and value. You can click Create predefined tags to go to the Tag Management Service (TMS) console and view or create tags. You can also create new tags by specifying Tag key and Tag value. <p>Up to 20 tags can be added to each Kafka instance. For details about the requirements on tags, see Configuring Kafka Instance Tags.</p>
Description	Enter a Description of the instance for 0–1024 characters.

Table 3-7 Topic parameters

Parameter	Default Value (Single-node)	Default Value (Cluster)	Modified To (Cluster)
Partitions	1	3	5
Replicas	1	3	3
Aging Time (h)	72	72	72
Synchronous Replication	Disabled	Disabled	Disabled
Synchronous Flushing	Disabled	Disabled	Disabled
Message Timestamp	CreateTime	CreateTime	CreateTime
Max. Message Size (bytes)	10,485,760	10,485,760	10,485,760

Step 7 Specify the required duration.

This parameter is displayed only if the billing mode is yearly/monthly. If **Auto-renew** is selected, the instance will be renewed automatically.

- Monthly subscriptions auto-renew for 1 month every time.

- Yearly subscriptions auto-renew for 1 year every time.

Step 8 Click **Confirm**.

Step 9 Confirm the instance information, and read and agree to the *Huawei Cloud Customer Agreement*. If you have selected the yearly/monthly billing mode, click **Pay Now** and make the payment as prompted. If you have selected the pay-per-use mode, click **Submit**.

Step 10 Return to the instance list and check whether the Kafka instance has been created.

It takes 3 to 15 minutes to create an instance. During this period, the instance status is **Creating**.

- If the instance is created successfully, its status changes to **Running**.
- If the instance is in the **Failed** state, delete it by referring to [Deleting Kafka Instances](#) and try creating another one. If the instance creation fails again, contact customer service.

 **NOTE**

Instances that fail to be created do not occupy other resources.

----End

Standard Config of a Single-node/Cluster Kafka Instance

Step 1 Go to the [Buy Instance](#) page.

Step 2 Set basic instance configurations on the **Standard Config** page.

Table 3-8 Basic instance configuration parameters

Parameter	Description
Billing Mode	<ul style="list-style-type: none">• Yearly/Monthly is a prepaid mode. You need to pay first, and will be billed for your subscription period.• Pay-per-use is a postpaid mode. You can pay after using the service, and will be billed for your usage duration. The fees are calculated in seconds and settled by hour.
Region	DMS for Kafka instances in different regions cannot communicate with each other over an intranet. Select a nearest location for low latency and fast access.
AZ	An AZ is a physical region where resources use independent power supply and networks. AZs are physically isolated but interconnected through an internal network. Select one AZ or at least three AZs. The AZ setting is fixed once the instance is created.

Step 3 Configure the following instance specifications:

Table 3-9 Instance specifications parameters

Parameter	Description
Version	Kafka version, which can be 1.1.0, 2.7, or 3.x. The version is fixed once the instance is created.
Architecture	Select Single-node or Cluster as required. Single-node instances are available only in v2.7. See Comparing Single-node and Cluster Kafka Instances .
Broker Flavor	Select a broker flavor as required. Maximum number of partitions per broker × Number of brokers = Maximum number of partitions of an instance. If the total number of partitions of all topics exceeds the upper limit of partitions, topic creation fails.
Brokers	Specify the broker quantity.
Storage space per broker	Select the disk type and specify the disk size. The disk type is fixed once the Kafka instance is created. The storage space is consumed by message replicas, logs, and metadata. Specify the storage space based on the expected service message size, the number of replicas, and the reserved disk space. Each Kafka broker reserves 33 GB disk space for storing logs and metadata. Disks are formatted when an instance is created. As a result, the actual available disk space is 93% to 95% of the total disk space. The disk supports high I/O, ultra-high I/O, Extreme SSD, and General Purpose SSD types. For more information, see Disk Types and Performance .

Figure 3-4 Instance flavor

Custom

Specifications

Default

Version

3.x 2.7 1.1.0

Software version of the instance. [Version Support Notes](#) [Release Notes](#) This setting is fixed once the instance is created. Ideally, use server and client with the same version.

Instance Type

Default

Architecture

Cluster

Broker Flavor

Flavor Name	TPS Limit per Broker	Maximum Partitions per Broker	Recommended Consumer Grou...	Traffic per Broker (MB/s)
<input checked="" type="radio"/> kafka.2u4g.cluster.small	20,000	100	15	40
<input type="radio"/> kafka.2u4g.cluster	30,000	250	20	100
<input type="radio"/> kafka.4u8g.cluster	100,000	500	100	200
<input type="radio"/> kafka.8u16g.cluster	150,000	1,000	150	375
<input type="radio"/> kafka.12u24g.cluster	200,000	1,500	200	625
<input type="radio"/> kafka.16u32g.cluster	250,000	2,000	200	750

Specifications Flavor Name kafka.2u4g.cluster.small | TPS Limit per Broker 20,000 | Maximum Partitions per Broker 100 | Recommended Consumer Groups per Broker 15 | Traffic per Broker (MB/s) 40

Brokers

Note
For more about total traffic and service traffic, see [Learn more](#). Reserve 30% of traffic to accommodate for fluctuations. Total network bandwidth: 120 MB/s; Recommended service bandwidth: 20 MB/s for read and 20 MB/s for write.

Storage space per broker

The system disk type and size **cannot be changed**. The storage space **cannot be decreased**. Select a disk type for your required service I/O. [Learn more](#)

Type Capacity

Total storage space = 300 GB (3 brokers × 100 GB per broker) Disk bandwidth per broker = 170 MB/s. Total disk bandwidth = 510 MB/s (Disk bandwidth per broker × Number of brokers)

Step 4 Set the network information.

Table 3-10 Instance network parameters

Parameter	Description
VPC	Select a created or shared VPC. A VPC provides an isolated virtual network for your Kafka instances. You can configure and manage the network as required. You can click Manage VPCs on the right to go to the VPC console, and view or create VPCs. After the Kafka instance is created, its VPC cannot be changed.
Subnet	Select a created or shared subnet. After the Kafka instance is created, its subnet cannot be changed. The Kafka instance supports IPv6 after it is enabled for the subnet.

Parameter	Description
IPv6	<p>This parameter is displayed after IPv6 is enabled for the subnet. The instance with IPv6 enabled can be accessed on a client using IPv6 addresses.</p> <p>SASL_SSL cannot be manually configured for instances with IPv6 enabled.</p> <p>The IPv6 setting is fixed once the instance is created.</p> <p>This function is available only in the CN East2 region.</p>
Security Group	<p>Select a created security group.</p> <p>A security group is a set of rules for accessing a Kafka instance. You can click Manage Security Group to view or create security groups on the network console.</p> <p>Before accessing a Kafka instance on the client, configure security group rules based on the access mode. For details about security group rules, see Table 5-2.</p>

Step 5 Configure the instance access mode.

Table 3-11 Instance access mode parameters

Parameter	Sub-Parameter	Description
Private Network Access	Access Method	<p>There are two methods:</p> <ul style="list-style-type: none"> • Plaintext access: Clients connect to the Kafka instance without SASL authentication. • Ciphertext access: Clients connect to the Kafka instance with SASL authentication. Enabling Ciphertext Access requires the Kafka security protocol, SSL username, password, and SASL PLAIN. <p>Once enabled, private network access cannot be disabled. Enable plaintext or ciphertext access, or both.</p> <p>Ciphertext access is unavailable for single-node instances.</p>



Parameter	Sub-Parameter	Description
	Cross-VPC Access Protocol	<ul style="list-style-type: none"> When Plaintext Access is enabled and Ciphertext Access is disabled, PLAINTEXT is used for Cross-VPC Access Protocol. When Ciphertext Access is enabled and Security Protocol is SASL_SSL, SASL_SSL is used for Cross-VPC Access Protocol. When Ciphertext Access is enabled and Security Protocol is SASL_PLAINTEXT, SASL_PLAINTEXT is used for Cross-VPC Access Protocol. <p>Fixed once the instance is created.</p>
	Private IP Addresses	<p>Select Auto or Manual.</p> <ul style="list-style-type: none"> Auto: The system automatically assigns an IP address from the subnet. Manual: Select IP addresses from the drop-down list. If the number of selected IP addresses is less than the number of brokers, the remaining IP addresses will be automatically assigned.
Public Network Access	Access Method	<p>There are two methods:</p> <ul style="list-style-type: none"> Plaintext access: Clients connect to the Kafka instance without SASL authentication. Ciphertext access: Clients connect to the Kafka instance with SASL authentication. Enabling Ciphertext Access requires the Kafka security protocol, SSL username, password, and SASL PLAIN. <p>After public access is enabled, enable plaintext or ciphertext access, or both.</p> <p>Ciphertext access is unavailable for single-node instances.</p>
	Public IP Addresses	<p>Select the number of public IP addresses as required.</p> <p>If EIPs are insufficient, click Create Elastic IP to create EIPs. Then, return to the Kafka console and click  next to Public IP Address to refresh the public IP address list.</p> <p>Kafka instances only support IPv4 EIPs.</p>

Figure 3-5 Instance access mode



The Kafka security protocol, SSL username, password, and SASL/PLAIN mechanism are described as follows.

Table 3-12 Ciphertext access parameters

Parameter	Value	Description
Security Protocol	SASL_SSL	SASL is used for authentication. Data is encrypted with SSL certificates for high-security transmission.
	SASL_PLAINTEXT	SASL is used for authentication. Data is transmitted in plaintext for high performance. SCRAM-SHA-512 authentication is recommended for plaintext transmission.
SSL Username	-	Username for a client to connect to a Kafka instance. A username should contain 4 to 64 characters, start with a letter, and contain only letters, digits, hyphens (-), and underscores (_). The username cannot be changed once ciphertext access is enabled.

Parameter	Value	Description
Password	-	<p>Password for a client to connect to a Kafka instance.</p> <p>A password must meet the following requirements:</p> <ul style="list-style-type: none"> • Contains 8 to 32 characters. • Contains at least three types of the following characters: uppercase letters, lowercase letters, digits, and special characters `~!@#\$%^&*()-_+=\ []{};:'",<.>?` and spaces, and cannot start with a hyphen (-). • Cannot be the username spelled forward or backward.
SASL/PLAIN	-	<ul style="list-style-type: none"> • If SASL/PLAIN is disabled, the SCRAM-SHA-512 mechanism is used for username and password authentication. • If SASL/PLAIN is enabled, both the SCRAM-SHA-512 and PLAIN mechanisms are supported. You can select either of them as required. <p>The SASL/PLAIN setting cannot be changed once ciphertext access is enabled.</p> <p>What are SCRAM-SHA-512 and PLAIN mechanisms?</p> <ul style="list-style-type: none"> • SCRAM-SHA-512: uses the hash algorithm to generate credentials for usernames and passwords to verify identities. SCRAM-SHA-512 is more secure than PLAIN. • PLAIN: a simple username and password verification mechanism.

Step 6 Configure advanced settings.

Table 3-13 Advanced configuration parameters

Parameter	Description
Instance Name	You can customize a name that complies with the rules: 4–64 characters; starts with a letter; can contain only letters, digits, hyphens (-), and underscores (_).
Enterprise Project	This parameter is for enterprise users. Enterprise projects facilitate project-level management and grouping of cloud resources and users. The default project is default .

Parameter	Description
Capacity Threshold Policy	<p>Specify how messages are processed when the disk usage threshold (95%) is reached.</p> <ul style="list-style-type: none"> • Automatically delete: Messages can be produced and consumed, but 10% of the earliest messages will be deleted to ensure sufficient disk space. This policy is suitable for scenarios where no service interruption can be tolerated. Data may be lost. • Stop production: New messages cannot be produced, but existing messages can still be consumed. This policy is suitable for scenarios where no data loss can be tolerated.
Smart Connect	<p>Configure Smart Connect.</p> <p>Smart Connect is used for data synchronization between heterogeneous systems. You can configure Smart Connect tasks to synchronize data between Kafka and another cloud service or between two Kafka instances.</p> <p>Enabling Smart Connect creates two brokers.</p> <p>Single-node instances do not have this parameter.</p>
Automatic Topic Creation	<p>Enable automatic Kafka topic creation if needed.</p> <p>If this option is enabled, a topic will be automatically created when a message is produced in or consumed from a topic that does not exist. The default topic parameters are listed in Table 3-14.</p> <ul style="list-style-type: none"> • For cluster instances, after you change the value of the log.retention.hours (retention period), default.replication.factor (replica quantity), or num.partitions (partition quantity) parameter, the value will be used in later topics that are automatically created. For example, assume that num.partitions is changed to 5, an automatically created topic has parameters listed in Table 3-14. • Unavailable for single-node instances.

Parameter	Description
Tags	<p>Tags are used to identify cloud resources. When you have multiple cloud resources of the same type, you can use tags to classify them based on usage, owner, or environment.</p> <p>If your organization has configured tag policies for DMS for Kafka, add tags to Kafka instances based on the policies. If a tag does not comply with the policies, Kafka instance creation may fail. Contact your organization administrator to learn more about tag policies.</p> <ul style="list-style-type: none"> If you have predefined tags, select a predefined pair of tag key and value. You can click View predefined tags to go to the Tag Management Service (TMS) console and view or create tags. You can also create new tags by specifying Tag key and Tag value. <p>Up to 20 tags can be added to each Kafka instance. For details about the requirements on tags, see Configuring Kafka Instance Tags.</p>
Description	Enter a Description of the instance for 0–1024 characters.

Table 3-14 Topic parameters

Parameter	Default Value (Single-node)	Default Value (Cluster)	Modified To (Cluster)
Partitions	1	3	5
Replicas	1	3	3
Aging Time (h)	72	72	72
Synchronous Replication	Disabled	Disabled	Disabled
Synchronous Flushing	Disabled	Disabled	Disabled
Message Timestamp	CreateTime	CreateTime	CreateTime
Max. Message Size (bytes)	10,485,760	10,485,760	10,485,760

Step 7 Specify the required duration.

This parameter is displayed only if the billing mode is yearly/monthly. If **Auto-renew** is selected, the instance will be renewed automatically.

- Monthly subscriptions auto-renew for 1 month every time.

- Yearly subscriptions auto-renew for 1 year every time.

Step 8 In **Summary** on the right, view the selected instance configuration.

Step 9 Click **Confirm**.

Step 10 Confirm the instance information, and read and agree to the *Huawei Cloud Customer Agreement*. If you have selected the yearly/monthly billing mode, click **Pay Now** and make the payment as prompted. If you have selected the pay-per-use mode, click **Submit**.

Step 11 Return to the instance list and check whether the Kafka instance has been created.

It takes 3 to 15 minutes to create an instance. During this period, the instance status is **Creating**.

- If the instance is created successfully, its status changes to **Running**.
- If the instance is in the **Failed** state, delete it by referring to [Deleting Kafka Instances](#) and try creating another one. If the instance creation fails again, contact customer service.

 **NOTE**

Instances that fail to be created do not occupy other resources.

----**End**

4 Configuring Topics

4.1 Creating a Kafka Topic

Topics store messages created by producers and subscribed by consumers. If **Automatic Topic Creation** is not enabled during Kafka instance creation, you need to manually create topics. If **Automatic Topic Creation** has been enabled for the instance, this operation is optional.

Automatic Topic Creation indicates that a topic will be automatically created when a message is produced in or consumed from a topic that does not exist. The default topic parameters are listed in [Table 4-1](#).

The following parameters of cluster instances can be changed on the **Parameters** page: **log.retention.hours** (retention period), **default.replication.factor** (replica quantity), or **num.partitions** (partition quantity). The value will be used in later topics that are automatically created.

For example, assume that **num.partitions** is changed to **5**, an automatically created topic has parameters listed in [Table 4-1](#).

Table 4-1 Topic parameters

Parameter	Default Value (Single-node)	Default Value (Cluster)	Modified To (Cluster)
Partitions	1	3	5
Replicas	1	3	3
Aging Time (h)	72	72	72
Synchronous Replication	Disabled	Disabled	Disabled
Synchronous Flushing	Disabled	Disabled	Disabled
Message Timestamp	CreateTime	CreateTime	CreateTime

Parameter	Default Value (Single-node)	Default Value (Cluster)	Modified To (Cluster)
Max. Message Size (bytes)	10,485,760	10,485,760	10,485,760

Methods that can be used to manually create a topic:


- [Creating a Topic on the Console](#)
- [Creating a Topic on Kafka Manager](#)
- [Creating a Topic on the Client](#)


Notes and Constraints

- The partition quantity of topics of a single-node or cluster Kafka instance is limited. **When the partition quantity limit is reached, you can no longer create topics.** The quantity varies with instance specifications. For details, see [Cluster Kafka Instances](#) and [Single-node Kafka Instances](#).
- Instances created since May 17, 2023 do not have Kafka Manager. You cannot create topics for these instances using Kafka Manager.
- For an instance with ciphertext access enabled, if **allow.everyone.if.no.acl.found** is set to **false**, topics can be created on the client only for the initial user (set when ciphertext access is enabled for the first time).
- If a topic name starts with a special character, for example, a number sign (#), monitoring data cannot be displayed.
- Due to the limitation of the Kafka kernel, topics whose names contain only period or underscore difference cannot be created. For example, assume that the **Topic_1** topic is created, creating a topic named **Topic.1** will fail and throw the **Topic 'topic.1' collides with existing topics: topic_1** exception.

Creating a Topic on the Console

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired Kafka instance to view the instance details.

Step 6 In the navigation pane, choose **Topics**. Then click **Create Topic**.

Step 7 Enter a topic name, specify other parameters, and click **OK**.

Figure 4-1 Creating a topic (cluster instance)

×

Create Topic

Topic Name	<input type="text" value="topic-01"/>
Partitions ?	<input type="text" value="3"/> Value range: 1 to 200 Cannot be decreased once the topic is created.
Replicas ?	<input type="text" value="3"/> Value range: 1 to 3 queue_term_fenBenCount_suggest_label Cannot be greater than the broker quantity.
Aging Time (h) ?	<input type="text" value="72"/> Value range: 1 to 720 How long messages will be preserved in the topic. Messages older than this period will be deleted and cannot be consumed.
Synchronous Replication ?	<input type="checkbox"/>
Synchronous Flushing ?	<input type="checkbox"/>
Message Timestamp ?	<input type="text" value="CreateTime"/>
Max.Message Size (bytes) ?	<input type="text" value="10,485,760"/>
Description	<div style="border: 1px solid #ccc; height: 80px; width: 100%;"></div> 0/200

Table 4-2 Topic parameters

Parameter	Description
Topic Name	<p>Customize a name that contains 3 to 200 characters, starts with a letter or underscore (_), and contains only letters, digits, periods (.), hyphens (-), and underscores (_).</p> <p>The name must be different from preset topics:</p> <ul style="list-style-type: none"> • __consumer_offsets • __transaction_state • __trace • __connect-status • __connect-configs • __connect-offsets <p>Once the topic is created, you cannot modify its name.</p> <p>Due to the limitation of the Kafka kernel, topics whose names contain only period or underscore difference cannot be created. For example, assume that the Topic_1 topic is created, creating a topic named Topic.1 will fail and throw the Topic 'topic.1' collides with existing topics: topic_1 exception.</p>
Partitions	<p>Number of partitions in the topic.</p> <p>If the number of partitions is the same as that of consumers, the larger the partitions, the higher the consumption concurrency.</p> <p>If this parameter is set to 1, messages will be retrieved in the FIFO order.</p> <p>Value range: 1–200</p>
Replicas	<p>A higher number of replicas delivers higher reliability. Data is automatically backed up on each replica. When one Kafka broker becomes faulty, data is still available on other brokers.</p> <p>If this parameter is set to 1, only one set of data is available.</p> <p>Value range: 1 to number of brokers</p> <p>NOTE If an instance node is faulty, an internal service error may be reported when you query messages in a topic with only one replica. Therefore, you are not advised using a topic with only one replica.</p>
Aging Time (h)	<p>The period that messages are retained for. Consumers must retrieve messages before this period ends. Otherwise, the messages will be deleted and can no longer be consumed.</p> <p>Value range: 1–720</p>


Parameter	Description
Synchronous Replication	A message is returned to the client only after the message creation request has been received and the message has been acknowledged by all replicas. After enabling this, set the parameter acks to all or -1 in the configuration file or production code on the producer client. If there is only one replica, synchronous replication cannot be enabled.
Synchronous Flushing	A message is immediately flushed to disk once it is produced, bringing higher reliability. When this option is disabled, a message is stored in the memory instead of being immediately flushed to disk once produced.
Message Timestamp	Timestamp type of a message. Options: <ul style="list-style-type: none"> • CreateTime: time when the producer created the message. • LogAppendTime: time when the broker appended the message to the log.
Max. Message Size (bytes)	Maximum batch processing size allowed by Kafka. If message compression is enabled in the client configuration file or code of producers, this parameter indicates the size after compression. If this is increased and there are consumers older than 0.10.2, the consumers' fetch size must also be increased so that they can fetch record batches this large. Value range: 0 to 10,485,760
Description	0–200 characters.

----End

Creating a Topic on Kafka Manager

[Log in to Kafka Manager](#), choose **Topic > Create**, and set parameters as prompted. To ensure performance, a partition number within 200 is recommended for each topic.

Figure 4-2 Creating a topic on Kafka Manager



Creating a Topic on the Client

If your client is v2.2 or later, you can use **kafka-topics.sh** to create topics and manage topic parameters.

- For a Kafka instance with ciphertext access disabled, run the following command in the **/bin** directory of the Kafka client:

```
./kafka-topics.sh --create --topic ${topic-name} --bootstrap-server ${connection-address} --partitions $
{number-of-partitions} --replication-factor ${number-of-replicas}
```

Parameter description:

- **topic-name**: topic name, which can be customized.
- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **number-of-partitions**: number of partitions in a topic. To ensure performance, a partition number within 200 is recommended for each topic.
- **number-of-replicas**: number of replicas in a topic.

Example:

```
[root@ecs-kafka bin]# ./kafka-topics.sh --create --topic topic-01 --bootstrap-server
192.168.xx.xx:9092,192.168.xx.xx:9092,192.168.xx.xx:9092 --partitions 3 --replication-factor 3
Created topic topic-01.
[root@ecs-kafka bin]#
```

- For a Kafka instance with ciphertext access enabled, do as follows:
 - (Optional) Modify the client configuration file.
View **Security Protocol** in the **Connection** area on the **Basic Information** page on the Kafka console. The configuration settings vary depending on the protocol.

- **SASL_PLAINTEXT**: Skip this step and go to **b** if the username and password are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_PLAINTEXT
# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
# If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description: **username** and **password** are the ones you set when enabling ciphertext access for the first time or when creating a user.

- **SASL_SSL**: Skip this step and go to **b** if the username, password, and SSL certificate are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_SSL
ssl.truststore.location={ssl_truststore_path}
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
# If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
```

```
username="*****" \  
password="*****";  
sasl.mechanism=PLAIN
```

Parameter description:

- **ssl.truststore.location**: path for storing the **client.jks** certificate. Even in Windows, you need to use slashes (/) for the certificate path. Do not use backslashes (\), which are used by default for paths in Windows. Otherwise, the client will fail to obtain the certificate.
 - **ssl.truststore.password** is certified by the server, which must be set to **dms@kafka** and cannot be changed.
 - **ssl.endpoint.identification.algorithm**: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**
 - **username** and **password**: username and password you set when enabling ciphertext access for the first time or when creating a user.
- b. Run the following command in the **/bin** directory of the Kafka client:
- ```
./kafka-topics.sh --create --topic {topic-name} --bootstrap-server {connection-address} --
partitions {number-of-partitions} --replication-factor {number-of-replicas} --command-
config ../config/ssl-user-config.properties
```

Parameter description:

- **topic-name**: topic name, which can be customized.
- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **number-of-partitions**: number of partitions in a topic. To ensure performance, a partition number within 200 is recommended for each topic.
- **number-of-replicas**: number of replicas in a topic.

Example:

```
[root@ecs-kafka bin]# ./kafka-topics.sh --create --topic topic-01 --bootstrap-server
192.168.xx.xx:9093,192.168.xx.xx:9093,192.168.xx.xx:9093 --partitions 3 --replication-factor 3 --
command-config ../config/ssl-user-config.properties
Created topic topic-01.
[root@ecs-kafka bin]#
```

## 4.2 Configuring Kafka Topic Permissions

Kafka instances with ciphertext access enabled support access control list (ACL) for topics. You can differentiate user permissions by granting users different permissions in a topic.

This section describes how to grant topic permissions to users after ciphertext access is enabled for a Kafka instance.

### Notes and Constraints

- If parameter **allow.everyone.if.no.acl.found** is set to **true** and no topic is granted for a user, all users can subscribe to or publish messages to the topic.

If permissions for a topic have been granted to one or more users, only these users can subscribe to or publish messages to the topic. The value of **allow.everyone.if.no.acl.found** can be **modified**.


- If **allow.everyone.if.no.acl.found** is set to **false**, only the initial user (set when ciphertext access is enabled for the first time) and other authorized users have the permission to subscribe to or publish messages to topics. The value of **allow.everyone.if.no.acl.found** can be **modified**.
- If both the default and individual user permissions are configured for a topic, the union of the permissions is used.
- Unavailable for single-node instances.


## Prerequisites

- **Ciphertext has been enabled** for the Kafka instance.
- **A user is created**.

## Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired Kafka instance to view the instance details.

**Step 6** In the navigation pane, choose **Topics**.

**Step 7** In the row containing the desired topic, click **Grant User Permission**.

**Step 8** Grant topic permissions to users.

- To grant the same permissions to all users, select **Default permissions** and then select permissions. As shown in the following figure, all users have the permission to publish messages to this topic.

**Figure 4-3** Granting the same permissions to all users


**Default permissions** Grants the same permissions to all users. These permissions will take effect together with the permissions you configure for individual users.

Effect

Publish 


- To grant different permissions to different users, do not select **Default permissions**. In the **Users** area of the **Grant User Permission** dialog box, select target users. If there are many users, enter the username in the search box for a quick search. In the **Selected** area, configure permissions (**Subscribe**, **Publish**, or **Publish/Subscribe**) for the users. As shown in the following figure, only the **test**, **send**, and **receive** users can subscribe to or publish messages to this topic. The **send\_receive** user cannot subscribe to or publish messages to this topic.

**Figure 4-4** Granting permissions to individual users




If both the default and individual user permissions are configured for a topic, the union of the permissions is used. As shown in the following figure, the test and receive users can subscribe to and publish messages to this topic, while other users can only publish messages to this topic.


**Figure 4-5** Granting topic permissions to users



**Step 9** Click **OK**.

On the **Topics** tab page, click  next to the topic name to view the authorized users and their permissions.



**Figure 4-6** Viewing authorized users and their permissions



----End



## Deleting Topic Permissions

- Step 1** Log in to the console.
  - Step 2** Click  in the upper left corner to select the region where your instance is located.
  - Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
  - Step 4** In the navigation pane, choose **Kafka Instances**.
  - Step 5** Click the desired Kafka instance to view the instance details.
  - Step 6** In the navigation pane, choose **Topics**.
  - Step 7** In the row containing the desired topic, click **Grant User Permission**.
  - Step 8** In the **Selected** area of the displayed **Grant User Permission** dialog box, locate the row that contains the user whose permissions are to be removed, click **Delete**, and click **OK**.
- End

## 4.3 Managing Topics



### 4.3.1 Viewing Kafka Topic Details

On the Kafka console, you can view basic information, partition and producer information, and subscriptions of a topic.

#### Notes and Constraints

- If an instance contains more than 10,000 consumer groups, the subscribed topics cannot be queried.
- The producer information is displayed only when a producer is producing messages into topics.

#### Procedure

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose **Topics**.

**Step 7** Click a topic to view its details.

The general information, subscriptions, partitions, and producers are displayed.

- General information: topic name, brokers, partitions, and creation time  
The topic creation time is not displayed on the topic details page in any of the following cases:
  - The topics were created on or before July 10, 2023.
  - The topics were created automatically, by commands or code in clients, or with Kafka Manager.
- Subscriptions: consumer group name and status, Coordinator (ID), and accumulated messages

Click the name of a consumer group name.

If an instance contains more than **10,000** consumer groups, the subscribed topics **cannot** be queried.

**Figure 4-7** Subscriptions

| Consumer Group Name | Status | Coordinator(ID) | Accumulated Messages |
|---------------------|--------|-----------------|----------------------|
| group-test          | EMPTY  | 2               | 1                    |

- Partitions: partition ID, minimum offset, earliest update time, maximum offset, latest update time, and number of messages

**First Updated** and **Last Updated** display -- when all messages in the partition are aged or no message is produced, as shown in the following figure.

**Figure 4-8** Partitions

| Partition | Minimum Offset | First Updated               | Maximum Offset | Last Updated                | Messages |
|-----------|----------------|-----------------------------|----------------|-----------------------------|----------|
| 0         | 0              | Jan 02, 2025 09:59:12 GM... | 0              | Jan 02, 2025 09:59:12 GM... | 1        |
| 1         | 0              | --                          | 0              | --                          | 0        |
| 2         | 0              | --                          | 0              | --                          | 0        |

- Producers: broker address, producer address, and producer connected time  
For topics created on or before Jul 10, 2023, **Producers** is not displayed on the topic details page.

**Figure 4-9** Producers

| Broker Address     | Producer Address   | Producer Connected              |
|--------------------|--------------------|---------------------------------|
| 192.168.0.178:9092 | 192.168.0.21:35224 | May 17, 2024 14:37:06 GMT+08:00 |

----End

### 4.3.2 Modifying Kafka Topic Configurations

This section describes how to modify configurations in [Table 4-3](#) of a Kafka topic on the console.


Modifying **Synchronous Replication**, **Synchronous Flushing**, **Message Timestamp**, **Max. Message Size**, or **Description** does not require an instance restart.


**Table 4-3** Kafka topic configuration parameters

| Parameter               | Description                                                                                                                                                                                                                                                                                                                |
|-------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Partitions              | Number of partitions in a topic. For details about how to change, see <a href="#">Changing Kafka Partition Quantity</a> .                                                                                                                                                                                                  |
| Aging Time (h)          | Maximum message retention. For details about how to change, see <a href="#">Changing Kafka Message Retention Period</a> .                                                                                                                                                                                                  |
| Replicas                | Number of replicas of each topic partition. To modify it, see <a href="#">Modifying Kafka Topic Replicas</a> .                                                                                                                                                                                                             |
| Synchronous Replication | A message is returned to the client only after the message creation request has been received and the message has been acknowledged by all replicas.                                                                                                                                                                       |
| Synchronous Flushing    | <ul style="list-style-type: none"> <li>Enabled: A message is immediately flushed to disk once it is created, bringing higher reliability.</li> <li>Disabled: A message is stored in the memory instead of being immediately flushed to disk once created.</li> </ul>                                                       |
| Message Timestamp       | Timestamp type of a message. Options: <ul style="list-style-type: none"> <li><b>CreateTime</b>: time when the producer created the message.</li> <li><b>LogAppendTime</b>: time when the broker appended the message to the log.</li> </ul>                                                                                |
| Max. Message Size       | Maximum size of messages to be processed in batches. If message compression is enabled, this parameter indicates the size after compression.<br><br>If this value is increased and the consumer version is earlier than 0.10.2, the consumers' fetch size must also be increased so that they can obtain the latest value. |
| Description             | Topic description.                                                                                                                                                                                                                                                                                                         |

## Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Topics**.

**Step 7** Modify topic configurations in either of the following ways:

- Select one or more topics and click **Edit Topic** above the topic list.
- In the row containing the desired topic, click **Edit**.

**Step 8** In the **Edit Topic** dialog box, change configurations and click **OK**.

Note:

- If there is only one replica, **Synchronous Replication** cannot be enabled.
- After enabling synchronous replication, set **acks** to **all** or **-1** on the client. Otherwise, this function will not take effect.

----End

### 4.3.3 Changing Kafka Partition Quantity

After creating a topic, you can change the number of partitions as required. Changing the number of partitions does **not** restart the instance or affect services.

Methods for changing the partition quantity:


- [Modifying Topic Partitions on the Console](#)
- [Modifying Topic Partitions on Kafka Manager](#)
- [Modifying Topic Partitions on the Client](#)


#### Notes and Constraints

- The number of partitions can only be increased.
- Instances created since May 17, 2023 do not have Kafka Manager. You cannot modify topic partitions for these instances using Kafka Manager.
- The partition quantity of topics of a single-node or cluster Kafka instance is limited. **When the partition quantity limit is reached, you can no longer create topics.** The quantity varies with instance specifications. For details, see [Cluster Kafka Instances](#) and [Single-node Kafka Instances](#).
- For an instance with ciphertext access enabled, if **allow.everyone.if.no.acl.found** is set to **false**, the topic partition quantity can be modified on the client only by the initial user (set in first ciphertext access enablement).

#### Modifying Topic Partitions on the Console

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Topics**.

**Step 7** Modify the number of partitions using either of the following methods:

- Select one or more topics and click **Edit Topic** in the upper left corner.
- In the row containing the desired topic, click **Edit**.

**Step 8** In the **Edit Topic** dialog box, enter the number of partitions and click **OK**.

To ensure performance, a maximum of 200 partitions is allowed for each topic on the Kafka console.

----End

## Modifying Topic Partitions on Kafka Manager

**Step 1** [Log in to Kafka Manager](#).

**Step 2** Choose **Topic > List** to view the list of topics.

**Step 3** Click a topic to view its details.

**Step 4** Click **Add Partitions**.

**Figure 4-10** Topic details page

| Topic Summary               |     |
|-----------------------------|-----|
| Replication                 | 3   |
| Number of Partitions        | 1   |
| Sum of partition offsets    | 0   |
| Total number of Brokers     | 3   |
| Number of Brokers for Topic | 3   |
| Preferred Replicas %        | 100 |
| Brokers Skewed %            | 0   |
| Brokers Leader Skewed %     | 0   |
| Brokers Spread %            | 100 |
| Under-replicated %          | 0   |

| Partitions by Broker |                 |             |            |         |        |
|----------------------|-----------------|-------------|------------|---------|--------|
| Broker               | # of Partitions | # as Leader | Partitions | Skewed? | Leader |
| 0                    | 1               | 0           | (0)        | false   | false  |
| 1                    | 1               | 0           | (0)        | false   | false  |
| 2                    | 1               | 1           | (0)        | false   | false  |

**Step 5** Enter the number of partitions and click **Add Partitions**.

To ensure performance, 200 or less partitions are recommended for each topic.

**Figure 4-11** Adding partitions

If "Done" is displayed, the partitions are added successfully.

**Figure 4-12** Partitions added

----End

## Modifying Topic Partitions on the Client

If your Kafka client version is later than 2.2, you can use **kafka-topics.sh** to change the partition quantity.

- For a Kafka instance with ciphertext access disabled, run the following command in the **/bin** directory of the Kafka client:  

```
./kafka-topics.sh --bootstrap-server ${connection-address} --topic ${topic-name} --alter --partitions $
{number-of-partitions}
```

Parameter description:

- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **topic-name**: topic name.
- **number-of-partitions**: number of partitions in a topic. To ensure performance, a partition number within 200 is recommended for each topic.

Example:

```
[root@ecs-kafka bin]# ./kafka-topics.sh --bootstrap-server
192.168.xx.xx:9092,192.168.xx.xx:9092,192.168.xx.xx:9092 --topic topic-01 --alter --partitions 6
[root@ecs-kafka bin]#
```

- For a Kafka instance with ciphertext access enabled, do as follows:
  - a. (Optional) Modify the client configuration file.

View **Security Protocol** in the **Connection** area on the **Basic Information** page on the Kafka console. The configuration settings vary depending on the protocol.

- **SASL\_PLAINTEXT**: Skip this step and go to **b** if the username and password are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_PLAINTEXT
If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description: **username** and **password** are the ones you set when enabling ciphertext access for the first time or when creating a user.

- **SASL\_SSL**: Skip this step and go to **b** if the username, password, and SSL certificate are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_SSL
ssl.truststore.location={ssl_truststore_path}
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description:

- **ssl.truststore.location**: path for storing the **client.jks** certificate. Even in Windows, you need to use slashes (/) for the certificate path. Do not use backslashes (\), which are used by default for paths in Windows. Otherwise, the client will fail to obtain the certificate.
- **ssl.truststore.password** is certified by the server, which must be set to **dms@kafka** and cannot be changed.
- **ssl.endpoint.identification.algorithm**: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**
- **username** and **password**: username and password you set when enabling ciphertext access for the first time or when creating a user.

- b. Run the following command in the **/bin** directory of the Kafka client:

```
./kafka-topics.sh --bootstrap-server ${connection-address} --topic ${topic-name} --alter --partitions ${number-of-partitions} --command-config ../config/ssl-user-config.properties
```

Parameter description:

- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **topic-name**: topic name.
- **number-of-partitions**: number of partitions in a topic. To ensure performance, a partition number within 200 is recommended for each topic.

Example:

```
[root@ecs-kafka bin]# ./kafka-topics.sh --bootstrap-server 192.168.xx.xx:9093,192.168.xx.xx:9093,192.168.xx.xx:9093 --topic topic-01 --alter --partitions 6 --command-config ../config/ssl-user-config.properties
[root@ecs-kafka bin]#
```

## 4.3.4 Modifying Kafka Topic Replicas

The replicas of a Kafka topic can be modified as required.

Reassigning partitions can modify replicas automatically or manually on the Kafka console. For more information, see [Modifying Replicas by Automatic Reassignment](#) and [Modifying Replicas by Manual Reassignment](#).

### Notes and Constraints

- Unavailable for single-node instances.
- Reassignment tasks cannot be manually stopped. Please wait until they complete.
- If partition reassignment has been scheduled, reassignment cannot be scheduled again for any topic in this instance until this reassignment is executed.

### Operation Impact

- Partition reassignment on topics with a large amount of data consumes a large amount of network and storage bandwidth. As a result, service requests may time out or the latency may increase. Therefore, you are advised to perform reassignment during off-peak hours. Compare the current instance load based on the instance specifications to decide whether the remaining instance capacity can support partition reassignment. Do not reassign partitions when there is insufficient bandwidth or when the CPU usage is greater than 90%. To view data volume and CPU usage of a topic, see **Message Size** and **CPU Usage** on the monitoring page. For details, see [Viewing Kafka Metrics](#).
- A throttle refers to the upper limit of the bandwidth for replication of a topic, to ensure that other topics on the instance are not affected. Note that throttles apply to replication triggered by both normal message production and partition reassignment. If the throttle is too small, normal message production may be affected, and partition reassignment may never complete. If partitions are continuously reassigned, contact customer service.




- You cannot delete topics whose reassignment tasks have started. Otherwise, the tasks will never complete.
- After partition reassignment, the metadata of the topic changes. If the producer does not support the retry mechanism, a few requests will fail, causing some messages to fail to be produced.
- Reassignment takes longer for a topic with a large data volume. To check the volume, see the **Message Size** metric on the monitoring page by referring to [Viewing Kafka Metrics](#). To reduce the amount of data to be migrated, **decrease the topic aging time** without affecting services and wait for messages to age. After the reassignment is complete, you can restore the aging time.


## Prerequisite

The target broker should have sufficient disk space. To check available disk space of each broker, see [Viewing Kafka Disk Usage](#). If the remaining disk capacity of the target broker is close to the amount of data to be migrated to the broker, **expand the disk capacity** before the reassignment.

## Modifying Replicas by Automatic Reassignment

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Topics**.

**Step 7** Go to the **Auto** page in either of the following ways:

- Select one or more topics and choose **Reassign > Auto** above the topic list.
- In the row containing the desired topic, choose **More > Reassign > Auto**.

**Step 8** Modify the replicas.

**Table 4-4** Parameters of automatic reassignment

| Parameter   | Description                                                                                    |
|-------------|------------------------------------------------------------------------------------------------|
| Broker Name | Select the brokers to assign the topic's partition replicas to.                                |
| Replicas    | Enter the number of replicas. This number must be less than or equal to the number of brokers. |

| Parameter      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Max. Bandwidth | Specify <b>throttle</b> . The default value is <b>-1</b> , indicating that there is no throttle.<br><br>If the instance has low workload (for example, only 30/300 MB/s is used), you are not advised to limit the bandwidth. Otherwise, you are advised to set it to a value greater than or equal to the total production bandwidth of the to-be-reassigned topic multiplied by the maximum number of replicas of the to-be-reassigned topic.<br><br>For details, see <a href="#">Calculating a Throttle</a> . |
| Execute        | Specify when to execute the reassignment. <ul style="list-style-type: none"> <li>• <b>Now</b> means to execute it immediately.</li> <li>• <b>As scheduled</b> means to execute it at the scheduled time.</li> </ul>                                                                                                                                                                                                                                                                                              |

**Step 9** (Optional) Click **Calculate**. **Time Required** indicates how long automatic balancing will take.

The one-click calculation function does not affect the performance of Kafka instances.

**Step 10** Click **OK**.

The following table lists how to check whether reassignment is complete (scheduled and non-scheduled tasks):


**Table 4-5** Checking the reassignment result


| Task Type        | Reassignment Result                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Background tasks | In the upper left corner of the topic list, click <b>View details</b> and the <b>Background Tasks &gt; Background tasks</b> page is displayed. The reassignment task is complete when it is in the <b>Successful</b> state, which means that the replicas are modified.                                                                                                                                                                                                                                                                                                                                                                                                                                  |
| Scheduled tasks  | <ol style="list-style-type: none"> <li>1. The <b>Background Tasks &gt; Scheduled tasks</b> page is displayed. This page only shows whether scheduled tasks start to execute instead of whether they are successful. <ul style="list-style-type: none"> <li>- When the task status is <b>Pending</b>, reassignment has not been executed.</li> <li>- When the task status is <b>Successful</b>, reassignment has started.</li> <li>- When the task status is <b>Cancel</b>, reassignment has been canceled.</li> </ul> </li> <li>2. Click <b>Background tasks</b> tab page. When the task status is <b>Successful</b>, reassignment has completed, which means that the replicas are modified.</li> </ol> |

----End

## Modifying Replicas by Manual Reassignment

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.


**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Topics**.

**Step 7** Go to the **Manual** page in either of the following ways:

- Select a topic and choose **Reassign > Manual** above the topic list. Manual reassignment does not support batch operations.
- In the row containing the desired topic, choose **More > Reassign > Manual**.

**Step 8** Modify the replicas.

- In the upper right corner of the **Manual** dialog box, click **Delete Replica** or **Add Replica** to reduce or increase the number of replicas for each partition of the topic.
- Under the name of the replica to be reassigned, click the broker name or  and select the target broker to migrate the replica to. Assign replicas of the same partition to different brokers.
- Specify **throttle**. The default value is **-1**, indicating that there is no throttle. If the instance has low workload (for example, only 30/300 MB/s is used), you are not advised to limit the bandwidth. Otherwise, you are advised to set it to a value greater than or equal to the total production bandwidth of the to-be-reassigned topic multiplied by the maximum number of replicas of the to-be-reassigned topic. For details, see [Calculating a Throttle](#).
- For **Execute**, specify when to execute the reassignment. **Now** means to execute it immediately. **As scheduled** means to execute it at the scheduled time.

**Step 9** (Optional) Click **Calculate**. **Time Required** indicates how long manual balancing will take.

The one-click calculation function does not affect the performance of Kafka instances.

**Step 10** Click **OK**.

The following table lists how to check whether reassignment is complete (scheduled and non-scheduled tasks):

**Table 4-6** Checking the reassignment result

| Task Type        | Reassignment Result                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
|------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Background tasks | In the upper left corner of the topic list, click <b>View details</b> and the <b>Background Tasks &gt; Background tasks</b> page is displayed. The reassignment task is complete when it is in the <b>Successful</b> state, which means that the replicas are modified.                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Scheduled tasks  | <ol style="list-style-type: none"> <li>The <b>Background Tasks &gt; Scheduled tasks</b> page is displayed. This page only shows whether scheduled tasks start to execute instead of whether they are successful. <ul style="list-style-type: none"> <li>When the task status is <b>Pending</b>, reassignment has not been executed.</li> <li>When the task status is <b>Successful</b>, reassignment has started.</li> <li>When the task status is <b>Cancel</b>, reassignment has been canceled.</li> </ul> </li> <li>Click <b>Background tasks</b> tab page. When the task status is <b>Successful</b>, reassignment has completed, which means that the replicas are modified.</li> </ol> |

----End

### 4.3.5 Exporting the Kafka Topic List


Export the topic list on the console. Batch export is supported.


#### Prerequisites

**A topic** has been created.

#### Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Topics**.

**Step 7** Export the topic list in either of the following ways:

- Select the desired topics and choose **Export > Export selected data to an XLSX file** to export specified topics.

- Choose **Export** > **Export all data to an XLSX file** to export all topics.

The topic list contains the following information: topic name, number of partitions, number of replicas, aging time, message timestamp, max. message size, description, and whether synchronous replication and flushing are enabled.

----End

### 4.3.6 Reassigning Kafka Partitions

Partition reassignment is to reassign replicas of a partition to different brokers to solve the problem of unbalanced broker load.

Partition reassignment is required in the following scenarios:

- After you add brokers to an instance, new topics are created on new brokers, and the original topics are still on the original brokers, resulting in unbalanced partitions. To migrate the replicas of the original topic partitions to the new brokers, reassign partitions.
- The leader partition is degraded to be a follower on a heavily loaded broker.
- The replica quantity of a topic can be changed during partition reassignment.

The DMS for Kafka console provides **automatic** and **manual** reassignment. Automatic reassignment is recommended because it ensures that leaders are evenly distributed.

#### Notes and Constraints

- Unavailable for single-node instances.
- You cannot modify the partition quantity of topics whose reassignment tasks have started.
- Reassignment tasks cannot be manually stopped. Please wait until they complete.
- If partition reassignment has been scheduled, reassignment cannot be scheduled again for any topic in this instance until this reassignment is executed.

#### Operation Impact

- Partition reassignment on topics with a large amount of data consumes a large amount of network and storage bandwidth. As a result, service requests may time out or the latency may increase. Therefore, you are advised to perform reassignment during off-peak hours. Compare the current instance load based on the instance specifications to decide whether the remaining instance capacity can support partition reassignment. Do not reassign partitions when there is insufficient bandwidth or when the CPU usage is greater than 90%. To view data volume and CPU usage of a topic, see **Message Size** and **CPU Usage** on the monitoring page. For details, see [Viewing Kafka Metrics](#).
- A throttle refers to the upper limit of the bandwidth for replication of a topic, to ensure that other topics on the instance are not affected. Note that throttles apply to replication triggered by both normal message production and partition reassignment. If the throttle is too small, normal message

production may be affected, and partition reassignment may never complete. If partitions are continuously reassigned, contact customer service.


- You cannot delete topics whose reassignment tasks have started. Otherwise, the tasks will never complete.
- After partition reassignment, the metadata of the topic changes. If the producer does not support the retry mechanism, a few requests will fail, causing some messages to fail to be produced.
- Reassignment takes longer for a topic with a large data volume. To check the volume, see the **Message Size** metric on the monitoring page by referring to [Viewing Kafka Metrics](#). To reduce the amount of data to be migrated, **decrease the topic aging time** without affecting services and wait for messages to age. After the reassignment is complete, you can restore the aging time.


## Prerequisite

The target broker should have sufficient disk space. To check available disk space of each broker, see [Viewing Kafka Disk Usage](#). If the remaining disk capacity of the target broker is close to the amount of data to be migrated to the broker, **expand the disk capacity** before the reassignment.

## Auto Reassignment

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Topics**.

**Step 7** Reassign partitions using either of the following methods:

- Select one or more topics and choose **Reassign > Auto** above the topic list.
- In the row that contains the desired topic, choose **More > Reassign > Auto**.

**Step 8** Set automatic reassignment parameters.


**Table 4-7** Parameters of automatic reassignment

| Parameter   | Description                                                                                                                              |
|-------------|------------------------------------------------------------------------------------------------------------------------------------------|
| Broker Name | Select the brokers to assign the topic's partition replicas to.                                                                          |
| Replicas    | Enter the number of replicas to be automatically reassigned. The number of replicas must be less than or equal to the number of brokers. |

| Parameter      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
|----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Max. Bandwidth | Specify <b>throttle</b> . The default value is <b>-1</b> , indicating that there is no throttle.<br><br>If the instance has low workload (for example, only 30/300 MB/s is used), you are not advised to limit the bandwidth. Otherwise, you are advised to set it to a value greater than or equal to the total production bandwidth of the to-be-reassigned topic multiplied by the maximum number of replicas of the to-be-reassigned topic.<br><br>For details, see <a href="#">Calculating a Throttle</a> . |
| Execute        | Specify when to execute the reassignment.<br><ul style="list-style-type: none"> <li>• <b>Now</b> means to execute it immediately.</li> <li>• <b>As scheduled</b> means to execute it at the scheduled time.</li> </ul>                                                                                                                                                                                                                                                                                           |

**Figure 4-13** Setting automatic reassignment parameters

Auto



**Step 9** (Optional) Click **Calculate**. **Time Required** indicates how long automatic balancing will take.

The one-click calculation function does not affect the performance of Kafka instances.


**Step 10** Click **OK**.

The following table lists how to check whether reassignment is complete (scheduled and non-scheduled tasks):

**Table 4-8** Checking the reassignment result

| Task Type        | Reassignment Result                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Background tasks | In the upper left corner of the topic list, click <b>View details</b> and the <b>Background Tasks &gt; Background tasks</b> page is displayed. The reassignment task is complete when it is in the <b>Successful</b> state.                                                                                                                                                                                                                                                                                                                                                                                                                      |
| Scheduled tasks  | <ol style="list-style-type: none"> <li>The <b>Background Tasks &gt; Scheduled tasks</b> page is displayed. This page only shows whether scheduled tasks start to execute instead of whether they are successful. <ul style="list-style-type: none"> <li>When the task status is <b>Pending</b>, reassignment has not been executed.</li> <li>When the task status is <b>Successful</b>, reassignment has started.</li> <li>When the task status is <b>Cancel</b>, reassignment has been canceled.</li> </ul> </li> <li>Click <b>Background tasks</b> tab page. When the task status is <b>Successful</b>, reassignment has completed.</li> </ol> |

**Figure 4-14** Background Tasks page



**NOTE**


- You cannot delete topics whose reassignment tasks have started. Otherwise, the tasks will never complete.
- You cannot modify the partition quantity of topics whose reassignment tasks have started.
- Reassignment tasks cannot be manually stopped. Please wait until they complete.
- If partition reassignment has been scheduled, reassignment cannot be scheduled again for any topic in this instance until this reassignment is executed.


----End



## Manual Reassignment

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.


**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Topics**.


**Step 7** Reassign partitions using either of the following methods:

- Select a topic and choose **Reassign > Manual** above the topic list. Manual reassignment does not support batch operations.
- In the row that contains the desired topic, choose **More > Reassign > Manual**.

**Step 8** Set manual reassignment parameters.

- In the upper right corner of the **Manual** dialog box, click **Delete Replica** or **Add Replica** to reduce or increase the number of replicas for each partition of the topic.
- Under the name of the replica to be reassigned, click the broker name or  and select the target broker to migrate the replica to. Assign replicas of the same partition to different brokers.
- Specify **throttle**. The default value is **-1**, indicating that there is no throttle. If the instance has low workload (for example, only 30/300 MB/s is used), you are not advised to limit the bandwidth. Otherwise, you are advised to set it to a value greater than or equal to the total production bandwidth of the to-be-reassigned topic multiplied by the maximum number of replicas of the to-be-reassigned topic. For details, see [Calculating a Throttle](#).
- For **Execute**, specify when to execute the reassignment. **Now** means to execute it immediately. **As scheduled** means to execute it at the scheduled time.

**Figure 4-15** Setting manual reassignment parameters



**Step 9** (Optional) Click **Calculate**. **Time Required** indicates how long manual balancing will take.

The one-click calculation function does not affect the performance of Kafka instances.

**Step 10** Click **OK**.


The following table lists how to check whether reassignment is complete (scheduled and non-scheduled tasks):

**Table 4-9** Checking the reassignment result

| Task Type        | Reassignment Result                                                                                                                                                                                                         |
|------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Background tasks | In the upper left corner of the topic list, click <b>View details</b> and the <b>Background Tasks &gt; Background tasks</b> page is displayed. The reassignment task is complete when it is in the <b>Successful</b> state. |

| Task Type       | Reassignment Result                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Scheduled tasks | <ol style="list-style-type: none"> <li>The <b>Background Tasks &gt; Scheduled tasks</b> page is displayed. This page only shows whether scheduled tasks start to execute instead of whether they are successful. <ul style="list-style-type: none"> <li>When the task status is <b>Pending</b>, reassignment has not been executed.</li> <li>When the task status is <b>Successful</b>, reassignment has started.</li> <li>When the task status is <b>Cancel</b>, reassignment has been canceled.</li> </ul> </li> <li>Click <b>Background tasks</b> tab page. When the task status is <b>Successful</b>, reassignment has completed.</li> </ol> |

Figure 4-16 Background Tasks page



**NOTE**


- You cannot delete topics whose reassignment tasks have started. Otherwise, the tasks will never complete.
- You cannot modify the partition quantity of topics whose reassignment tasks have started.
- Reassignment tasks cannot be manually stopped. Please wait until they complete.
- If partition reassignment has been scheduled, reassignment cannot be scheduled again for any topic in this instance until this reassignment is executed.

----End

## Re-scheduling Partition Reassignment

**Step 1** On the **Scheduled tasks** tab page on the **Background Tasks** page, click the drop-down box in the upper left corner, select a time period, enter the desired topic name in the search box, and press **Enter**.

Figure 4-17 Querying reassignment schedules




**Step 2** In the row that contains the desired task, click **Modify**.

**Step 3** In the **Change Schedule** dialog box, change the schedule or cancel the scheduled task.

- To change the schedule, select a time and click **OK**.
- To cancel the task, select **Cancel** (as shown in [Figure 4-18](#)) and click **OK**.

**Figure 4-18** Canceling a reassignment schedule



----End

## Calculating a Throttle

Throttles are affected by the execution duration of the reassignment, leader/follower distribution of partition replicas, and message production rate.

- A throttle limits the replication traffic of all partitions in a broker.
- Replicas added after the assignment are regarded as followers, and existing replicas are regarded as leaders. Throttles on leaders and followers are separated.
- Throttles do not distinguish between replication caused by normal message production and that caused by partition reassignment. Therefore, the traffic generated in both cases is throttled.

Assume that the partition reassignment task needs to be completed within 200s and each replica has 100 MB data. Calculate the throttle in the following scenarios:

**Scenario 1: Topic 1 has two partitions and two replicas, and Topic 2 has one partition and one replica. All leader replicas are on the same broker, as shown in [Table 4-10](#). One replica needs to be added for Topic 1 and Topic 2 respectively, as shown in [Table 4-11](#).**


**Table 4-10** Replica distribution before reassignment

| Topic Name | Partition Name | Broker of Leader Replica | Broker of Follower Replica |
|------------|----------------|--------------------------|----------------------------|
| Topic 1    | 0              | 0                        | 0, 1                       |
| Topic 1    | 1              | 0                        | 0, 2                       |
| Topic 2    | 0              | 0                        | 0                          |

**Table 4-11** Replica distribution after reassignment

| Topic Name | Partition Name | Broker of Leader Replica | Broker of Follower Replica |
|------------|----------------|--------------------------|----------------------------|
| Topic 1    | 0              | 0                        | 0, 1, 2                    |
| Topic 1    | 1              | 0                        | 0, 1, 2                    |
| Topic 2    | 0              | 0                        | 0, 2                       |

**Figure 4-19** Reassignment scenario 1



As shown in [Figure 4-19](#), three replicas fetch data from Broker 0. Each replica on Broker 0 has 100 MB data. Broker 0 has only leader replicas, and Broker 1 and Broker 2 have only follower replicas.

- Bandwidth required by Broker 0 to complete partition reassignment within 200s =  $(100\text{ MB} + 100\text{ MB} + 100\text{ MB})/200\text{s} = 1.5\text{ MB/s}$
- Bandwidth required by Broker 1 to complete partition reassignment within 200s =  $100\text{ MB}/200\text{s} = 0.5\text{ MB/s}$

- Bandwidth required by Broker 2 to complete partition reassignment within 200s =  $(100 \text{ MB} + 100 \text{ MB})/200\text{s} = 1 \text{ MB/s}$

In conclusion, to complete the partition reassignment task within 200s, set the throttle to a value greater than or equal to 1.5 MB/s. The bandwidth should be set to be greater than or equal to 2 MB/s because the limit on it on the console must be an integer.

**Scenario 2: Topic 1 has two partitions and one replica, and Topic 2 has two partitions and one replica. Leader replicas are on different brokers, as shown in [Table 4-12](#). One replica needs to be added for Topic 1 and Topic 2 respectively, as shown in [Table 4-13](#).**


**Table 4-12** Replica distribution before reassignment

| Topic Name | Partition Name | Broker of Leader Replica | Broker of Follower Replica |
|------------|----------------|--------------------------|----------------------------|
| Topic 1    | 0              | 0                        | 0                          |
| Topic 1    | 1              | 1                        | 1                          |
| Topic 2    | 0              | 1                        | 1                          |
| Topic 2    | 1              | 2                        | 2                          |

**Table 4-13** Replica distribution after reassignment

| Topic Name | Partition Name | Broker of Leader Replica | Broker of Follower Replica |
|------------|----------------|--------------------------|----------------------------|
| Topic 1    | 0              | 0                        | 0, 2                       |
| Topic 1    | 1              | 1                        | 1, 2                       |
| Topic 2    | 0              | 1                        | 1, 2                       |
| Topic 2    | 1              | 2                        | 2, 0                       |

**Figure 4-20** Reassignment scenario 2



As shown in [Figure 4-20](#), Broker 1 has only leader replicas, and Broker 0 and Broker 2 have both leader and follower replicas. Leader and follower replicas on Broker 0 and Broker 2 are throttled separately.

- Bandwidth required by Broker 0 (leader) to complete partition reassignment within 200s =  $100 \text{ MB}/200\text{s} = 0.5 \text{ MB/s}$
- Bandwidth required by Broker 0 (follower) to complete partition reassignment within 200s =  $100 \text{ MB}/200\text{s} = 0.5 \text{ MB/s}$
- Bandwidth required by Broker 1 to complete partition reassignment within 200s =  $(100 \text{ MB} + 100 \text{ MB})/200\text{s} = 1 \text{ MB/s}$
- Bandwidth required by Broker 2 (leader) to complete partition reassignment within 200s =  $100 \text{ MB}/200\text{s} = 0.5 \text{ MB/s}$
- Bandwidth required by Broker 2 (follower) to complete partition reassignment within 200s =  $(100 \text{ MB} + 100 \text{ MB} + 100 \text{ MB})/200\text{s} = 1.5 \text{ MB/s}$

In conclusion, to complete the partition reassignment task within 200s, set the throttle to a value greater than or equal to 1.5 MB/s. The bandwidth should be set to be greater than or equal to 2 MB/s because the limit on it on the console must be an integer.

**Scenario 3: Both Topic 1 and Topic 2 have one partition and two replicas. All leader replicas are on the same broker. One replica needs to be added to Topic 1, as shown in [Table 4-14](#). Messages are produced on Topic 1, causing replication, as shown in [Table 4-15](#).**


**Table 4-14** Replica distribution before reassignment

| Topic Name | Partition Name | Broker of Leader Replica | Broker of Follower Replica |
|------------|----------------|--------------------------|----------------------------|
| Topic 1    | 0              | 0                        | 0, 1                       |
| Topic 2    | 0              | 0                        | 0, 1                       |

**Table 4-15** Replica distribution after reassignment

| Topic Name | Partition Name | Broker of Leader Replica | Broker of Follower Replica |
|------------|----------------|--------------------------|----------------------------|
| Topic 1    | 0              | 0                        | 0, 1, 2                    |
| Topic 2    | 0              | 0                        | 0, 1                       |

**Figure 4-21** Reassignment scenario 3



As shown in [Figure 4-21](#), one replica needs to fetch data from Broker 0 for partition reassignment, and the other replica needs to fetch data from Broker 0 for message production. Since the throttle does not distinguish between message production and partition reassignment, the traffic caused by both is limited and counted.

- Bandwidth required by Broker 0 to complete partition reassignment within 200s =  $(100 \text{ MB} + 700 \text{ KB/s} \times 200\text{s}) / 200\text{s} + 700 \text{ KB/s} = 1.9 \text{ MB/s}$
- Bandwidth required by Broker 2 to complete partition reassignment within 200s =  $100 \text{ MB} / 200\text{s} = 0.5 \text{ MB/s}$

In conclusion, to complete the partition reassignment task within 200s, set the throttle to a value greater than or equal to 1.9 MB/s. The bandwidth should be set



to be greater than or equal to 2 MB/s because the limit on it on the console must be an integer.

### 4.3.7 Configuring Automatic Topic Creation

**Automatic Topic Creation** indicates that a topic will be automatically created when a message is produced in or consumed from a topic that does not exist. By default, the topic has parameters listed in [Table 4-16](#).

The following parameters of cluster instances can be changed on the **Parameters** page: **log.retention.hours** (retention period), **default.replication.factor** (replica quantity), or **num.partitions** (partition quantity). The value will be used in later topics that are automatically created.

For example, assume that **num.partitions** is changed to **5**, an automatically created topic has parameters listed in [Table 4-16](#).

**Table 4-16** Topic parameters


| Parameter                 | Default Value (Single-node) | Default Value (Cluster) | Modified To (Cluster) |
|---------------------------|-----------------------------|-------------------------|-----------------------|
| Partitions                | 1                           | 3                       | 5                     |
| Replicas                  | 1                           | 3                       | 3                     |
| Aging Time (h)            | 72                          | 72                      | 72                    |
| Synchronous Replication   | Disabled                    | Disabled                | Disabled              |
| Synchronous Flushing      | Disabled                    | Disabled                | Disabled              |
| Message Timestamp         | CreateTime                  | CreateTime              | CreateTime            |
| Max. Message Size (bytes) | 10,485,760                  | 10,485,760              | 10,485,760            |


### Notes and Constraints

Enabling or disabling automatic topic creation may restart the instance.

### Procedure



**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired Kafka instance to view its details.

**Step 6** In the **Instance Information** area, click  or  next to **Automatic Topic Creation**. The **Confirm** dialog box is displayed.

**Step 7** Click **OK**. The **Background Tasks** page is displayed. Automatic topic creation has been configured when the task is in the **Successful** state.

----End

## 4.3.8 Deleting a Kafka Topic

This section describes how to delete a topic.

- [Deleting a Kafka Topic \(Console\)](#)
- [Deleting a Kafka Topic on the Client](#)

### Notes and Constraints


- Deleting a topic clears the topic data permanently.
- For an instance with ciphertext access enabled, if **allow.everyone.if.no.acl.found** is set to **false**, the topic can be deleted on the client only by the initial user (set in first ciphertext access enablement).


### Prerequisite

The instance is in the **Running** state.

### Deleting a Kafka Topic (Console)

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Topics**.

**Step 7** Delete topics using either of the following methods:

- Select one or more topics and click **Delete Topic** in the upper left corner.
- In the row containing the topic you want to delete, choose **More > Delete**.

**Step 8** In the **Delete Topic** dialog box that is displayed, click **OK** to delete the topic.

----End

## Deleting a Kafka Topic on the Client

If your Kafka client version is later than 2.2, you can use **kafka-topics.sh** to delete topics.

- For a Kafka instance with ciphertext access disabled, run the following command in the **/bin** directory of the Kafka client:

```
./kafka-topics.sh --bootstrap-server ${connection-address} --delete --topic ${topic-name}
```

Parameter description:

- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **topic-name**: topic name.

Example:

```
[root@ecs-kafka bin]# ./kafka-topics.sh --bootstrap-server
192.168.xx.xx:9092,192.168.xx.xx:9092,192.168.xx.xx:9092 --delete --topic topic-01
[root@ecs-kafka bin]#
```

- For a Kafka instance with ciphertext access enabled, do as follows:

- a. (Optional) Modify the client configuration file.

View **Security Protocol** in the **Connection** area on the **Basic Information** page on the Kafka console. The configuration settings vary depending on the protocol.

- **SASL\_PLAINTEXT**: Skip this step and go to **b** if the username and password are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_PLAINTEXT
If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description: **username** and **password** are the ones you set when enabling ciphertext access for the first time or when creating a user.

- **SASL\_SSL**: Skip this step and go to **b** if the username, password, and SSL certificate are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_SSL
ssl.truststore.location={ssl_truststore_path}
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description:

- **ssl.truststore.location**: path for storing the **client.jks** certificate. Even in Windows, you need to use slashes (/) for the certificate path. Do not use backslashes (\), which are used by default for paths in Windows. Otherwise, the client will fail to obtain the certificate.
  - **ssl.truststore.password** is certified by the server, which must be set to **dms@kafka** and cannot be changed.
  - **ssl.endpoint.identification.algorithm**: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**
  - **username** and **password**: username and password you set when enabling ciphertext access for the first time or when creating a user.
- b. Run the following command in the **/bin** directory of the Kafka client:
- ```
./kafka-topics.sh --bootstrap-server ${connection-address} --delete --topic ${topic-name} --  
command-config ../config/ssl-user-config.properties
```

Parameter description:

- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **topic-name**: topic name.

Example:

```
[root@ecs-kafka bin]# ./kafka-topics.sh --bootstrap-server  
192.168.xx.xx:9093,192.168.xx.xx:9093,192.168.xx.xx:9093 --delete --topic topic-01 --command-  
config ../config/ssl-user-config.properties  
[root@ecs-kafka bin]#
```

5 Connecting to an Instance

5.1 Configuring Kafka Network Connections

5.1.1 Kafka Network Connection Conditions

A client can connect to a Kafka instance over a public or private network. Notes before using a private network:

- By default, a client and a Kafka instance are interconnected when they are deployed in a VPC.
- If they are not, you need to interconnect them because of isolation among VPCs.

[Table 5-1](#) lists how to access a Kafka instance on a client.

Table 5-1 Access modes

Mode	How To Do	Reference
Public access	<ul style="list-style-type: none"> • To access a Kafka instance on a client using IPv4 addresses: Enable public access on the Kafka console and configure elastic IPs (EIPs). A client can connect to the Kafka instance through the EIPs. • To access a Kafka instance on a client using IPv6 addresses: Enable IPv6 on the Kafka console and add the IPv6 addresses into the shared bandwidth. A client can connect to the Kafka instance over a public network. 	Configuring Kafka Public Access
	Configure port mapping using DNAT. The client can connect to the Kafka instance in a public network.	Accessing Kafka in a Public Network Using DNAT

Mode	How To Do	Reference
Private access	A client and a Kafka instance are interconnected when they are deployed in a VPC.	-
	When a client and a Kafka instance are deployed in different VPCs of the same region, connect the client and the Kafka instance across VPCs using a VPC endpoint.	Accessing Kafka Using a VPC Endpoint Across VPCs
	When a client and a Kafka instance are deployed in different VPCs of the same region, interconnect two VPCs using a VPC peering connection.	VPC Peering Connection

Before accessing a Kafka instance on a client, configure the following rules in the security group of the instance.

 **NOTE**

After a security group is created, its default inbound rule allows communication among ECSs within the security group and its default outbound rule allows all outbound traffic. In this case, you can access a Kafka instance within a VPC, and do not need to add rules according to [Table 5-2](#).

Table 5-2 Security group rules

Direction	Protocol	Type	Port	Source	Description
Inbound	TCP	IPv4	9094	IP address or IP address group of the Kafka client	Accessing a Kafka instance over a public network (in plaintext)
Inbound	TCP	IPv4	9092	IP address or IP address group of the Kafka client	<ul style="list-style-type: none"> Accessing a Kafka instance over a private network within a VPC (in plaintext) Accessing a Kafka instance using a peering connection across VPCs (in plaintext)

Direction	Protocol	Type	Port	Source	Description
Inbound	TCP	IPv6	9192	IP address or IP address group of the Kafka client	Accessing a Kafka instance using IPv6 addresses (without SSL) (private or public network)
Inbound	TCP	IPv4	9095	IP address or IP address group of the Kafka client	Accessing a Kafka instance over a public network (in ciphertext)
Inbound	TCP	IPv4	9093	IP address or IP address group of the Kafka client	<ul style="list-style-type: none">• Accessing a Kafka instance over a private network within a VPC (in ciphertext)• Accessing a Kafka instance using a peering connection across VPCs (in ciphertext)
Inbound	TCP	IPv6	9193	IP address or IP address group of the Kafka client	Accessing a Kafka instance using IPv6 addresses (with SSL) (private or public network)
Inbound	TCP	IPv4	9011	198.19.128.0/17	Accessing a Kafka instance using a VPC endpoint across VPCs (in cipher- or plaintext)
Inbound	TCP	IPv4	9011	IP address or IP address group of the Kafka client	Accessing a Kafka instance using DNAT (in cipher- or plaintext)

5.1.2 Configuring Kafka Public Access

Clients can use IPv4 or IPv6 addresses to access a Kafka instance over a public network.

- By IPv4: On the Kafka console, enable public access and configure EIPs for the instance.
- By IPv6: Enable IPv6 in Kafka instance creation and add IPv6 addresses to the shared bandwidth to support both private and public IPv6 access.

On the Kafka console, the procedures for configuring public IPv4 access vary depending on the content displayed in the **Connection** area on the **Basic Information** page.

- When IPv6 is disabled, refer to [Enabling Public IPv4 Access \(Plaintext or Ciphertext Access Can Be Changed\)](#) and [Disabling Public IPv4 Access \(Plaintext or Ciphertext Access Can Be Changed\)](#).
- When IPv6 is enabled, refer to [Enabling Public IPv4 Access \(SASL Cannot Be Changed\)](#) and [Disabling Public IPv4 Access \(SASL Cannot Be Changed\)](#).

Notes and Constraints


Kafka instances only support IPv4 EIPs. IPv6 EIPs are not supported.


Prerequisites

- You can change the public access setting only when the Kafka instance is in the **Running** state.
- (Optional) To access a Kafka instance using IPv6 addresses, ensure that IPv6 is enabled for the Kafka instance.

Enabling Public IPv4 Access (SASL Cannot Be Changed)


Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click a Kafka instance to go to the **Basic Information** page.

Step 6 Click  next to **Public Access** to enable public access. For **Elastic IP Address**, select an EIP for each broker.

If the EIPs are insufficient, do as follows to set them.




1. Click **Create Elastic IP** to go to the **Buy EIP** page and purchase EIPs. For details, see [Assigning an EIP](#).
2. After the purchase is complete, return to the public access enabling page.
3. Click  after **Elastic IP Address**, select an EIP for each broker and then click .
4. You can view the operation progress on the **Background Tasks** page. If the task status is **Successful**, the modification has succeeded.

Figure 5-1 Enabling public access



After public access is enabled, configure security group rules listed in [Table 5-3](#) before attempting to access Kafka. For details about accessing Kafka, see [Connecting to an Instance](#).


Table 5-3 Kafka instance security group rules (public IPv4 access)


Direction	Protocol	Type	Port	Source	Description
Inbound	TCP	IPv4	9094	IP address or IP address group of the Kafka client	Accessing Kafka over a public network (without SSL)
Inbound	TCP	IPv4	9095	IP address or IP address group of the Kafka client	Accessing Kafka over a public network (with SSL)

----End

Disabling Public IPv4 Access (SASL Cannot Be Changed)

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click a Kafka instance to go to the **Basic Information** page.

Step 6 Click  next to **Public Access**.

You can view the operation progress on the **Background Tasks** page. If the task status is **Successful**, the modification has succeeded.

After public access is disabled, configure security group rules listed in [Table 5-4](#) before attempting to access Kafka in a VPC. For details about accessing Kafka, see [Connecting to an Instance](#).

Table 5-4 Kafka instance security group rules (private access)

Direction	Protocol	Type	Port	Source	Description
Inbound	TCP	IPv4	9092	IP address or IP address group of the Kafka client	Accessing a Kafka instance over a private network within a VPC (without SSL)
Inbound	TCP	IPv4	9093	IP address or IP address group of the Kafka client	Accessing a Kafka instance over a private network within a VPC (with SSL)


 **NOTE**


After a security group is created, its default inbound rule allows communication among ECSs within the security group and its default outbound rule allows all outbound traffic. In this case, you can access a Kafka instance within a VPC, and do not need to add rules according to [Table 5-4](#).

----End

Enabling Public IPv4 Access (Plaintext or Ciphertext Access Can Be Changed)


Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.



Step 3 Click  and choose Middleware > Distributed Message Service for Kafka to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click a Kafka instance to go to the **Basic Information** page.


Step 6 Click  next to **Public Access** to enable public access. For **Elastic IP Address**, select an EIP for each broker.

If the EIPs are insufficient, do as follows to set them.

1. Click **Create Elastic IP** to go to the **Buy EIP** page and purchase EIPs. For details, see [Assigning an EIP](#).
2. After the purchase is complete, return to the public access enabling page.
3. Click  after **Elastic IP Address**, select an EIP for each broker and then click . The **Background Tasks** page is displayed.

- If the status of the task turns to **Successful**, public access is successfully enabled.

Figure 5-2 Enabling public access






After public access is enabled, configure the **access mode (plaintext or ciphertext)** and security group rules listed in **Table 5-5** before attempting to access Kafka. For details about accessing Kafka, see **Connecting to an Instance**.

Table 5-5 Kafka instance security group rules (public IPv4 access)

Direction	Protocol	Type	Port	Source	Description
Inbound	TCP	IPv4	9094	IP address or IP address group of the Kafka client	Public plaintext access to Kafka
Inbound	TCP	IPv4	9095	IP address or IP address group of the Kafka client	Public ciphertext access to Kafka

----End

Disabling Public IPv4 Access (Plaintext or Ciphertext Access Can Be Changed)

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose Middleware > Distributed Message Service for Kafka to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click a Kafka instance to go to the **Basic Information** page.
- Step 6** Before disabling public access, disable **Plaintext Access** and **Ciphertext Access** next to **Public Network Access**. Then click  next to **Public Access**.

Step 7 Click **OK**. The **Background Tasks** page is displayed. If the status of the task turns to **Successful**, public access is successfully disabled.

After public access is disabled, configure security group rules listed in **Table 5-6** before attempting to access Kafka in a VPC. For details about accessing Kafka, see **Connecting to an Instance**.

 **NOTE**

After a security group is created, its default inbound rule allows communication among ECSs within the security group and its default outbound rule allows all outbound traffic. In this case, you can access a Kafka instance within a VPC, and do not need to add rules according to **Table 5-6**.


Table 5-6 Kafka instance security group rules (private access)

Direction	Protocol	Type	Port	Source	Description
Inbound	TCP	IPv4	9092	IP address or IP address group of the Kafka client	Accessing a Kafka instance over a private network within a VPC (in plaintext)
Inbound	TCP	IPv4	9093	IP address or IP address group of the Kafka client	Accessing a Kafka instance over a private network within a VPC (in ciphertext)

----End

Enabling IPv6 Public Network Access

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.


Step 3 Click  and choose **Middleware > Distributed Message Service for Kafka** to open the console of DMS for Kafka.


Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click a Kafka instance to go to the **Basic Information** page.

Step 6 In the **Connection** area, obtain **IPv6 Instance Address (Private Network)**. In the **Network** area, view and record the VPC and subnet.

Figure 5-3 Instance details page



Step 7 Click  in the upper left corner of the management console and choose **Network > Elastic IP**. The **EIPs** page is displayed.

Step 8 Choose **Shared Bandwidths** in the navigation pane.

Step 9 Apply for a shared bandwidth. For details, see [Assigning a Shared Bandwidth](#).

If a shared bandwidth already exists, you do not need to apply for one again.


Step 10 In the row containing the shared bandwidth, click **Add Public IP Address**.

Step 11 Set the parameters as described in [Table 5-7](#) and click **OK**.

Table 5-7 Adding public IP parameters

Parameter	Description
Public IP Address	Select IPv6 Address .
VPC	Select the VPC in Step 6 from the drop-down list.
Subnet	Select the subnet in Step 6 from the drop-down list. Select all IPv6 addresses in Step 6 .

Figure 5-4 Adding public IPs



Step 12 After the shared bandwidth is configured, set a Kafka instance security group with the rules described in [Table 5-8](#).

Table 5-8 Kafka instance security group rules (IPv6 access)

Direction	Protocol	Type	Port	Source	Description
Inbound	TCP	IPv6	9192	::/0	Accessing a Kafka instance using IPv6 addresses (without SSL encryption)
Inbound	TCP	IPv6	9193	::/0	Accessing a Kafka instance using IPv6 addresses (with SSL encryption)

When a client is connected to a Kafka instance over an IPv6 public network:

- The Kafka connection addresses are the IPv6 addresses in **Instance Address (Private Network)**.
- The client NIC must be added to shared bandwidth. Shared bandwidth is using a connected network. The shared bandwidth of the client NIC and that of the Kafka instance can be different.

----End

Disabling IPv6 Public Access

Remove the IPv6 addresses of a Kafka instance from the shared bandwidth. For details, see [Removing EIPs from a Shared Bandwidth](#).

5.1.3 Accessing Kafka Using a VPC Endpoint Across VPCs

VPCs are logically isolated from each other. If a Kafka instance and a Kafka client are in different VPCs within a region, they cannot communicate with each other. In this case, you can use one of the following methods to access a Kafka instance across VPCs:


- Establish a VPC peering connection to allow two VPCs to communicate with each other. For details, see [VPC Peering Connection](#).
- Use VPC Endpoint (VPCEP) to establish a cross-VPC connection.

The following describes how to use VPCEP to implement cross-VPC access.

VPCEP provides two types of resources: VPC endpoint services and VPC endpoints.

- A VPC endpoint service can be a Kafka instance which is accessed using VPC endpoints.
- A VPC endpoint is a secure and private channel for connecting a VPC to a VPC endpoint service.

Figure 5-5 Working principle of accessing a Kafka instance across VPCs



Is Plaintext Access or Ciphertext Access Used When a Client Accesses Kafka Across VPCs Using A VPC Endpoint?

It depends on **Cross-VPC Access Protocol**. The cross-VPC access protocol can be configured when you create a Kafka instance. After an instance is created, the setting cannot be changed.

Options:

- **PLAINTEXT**: There is no authentication required in such a connection and data is transmitted in plaintext.
- **SASL_SSL**: Clients can connect to a Kafka instance with SASL and the data will be encrypted using the SSL certificate.
- **SASL_PLAINTEXT**: Clients can connect to a Kafka instance with SASL and the data will be transmitted in plaintext.

Creating a VPC Endpoint Service

Step 1 Log in to the console.




- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the **Advanced Settings** section on the **Basic Information** tab page, obtain the listeners IP addresses and port IDs of the instance for **Cross-VPC Access**.

Figure 5-6 Cross-VPC access-related listeners IP addresses and corresponding port IDs of the Kafka instance



listeners IP Address	advertised.listeners IP Address/Domain Name	Port	Port ID
192.168.0.25	192.168.0.25	9011	cbdf4...a105
192.168.0.174	192.168.0.174	9011	29e3f...c61d18
192.168.0.70	192.168.0.70	9011	52f256...f1003

- Step 7** In the **Network** section on the **Basic Information** tab page, view the VPC to which the Kafka instance belongs.


Figure 5-7 Viewing the VPC to which the Kafka instance belongs

Network

AZ	AZ1,AZ3,AZ2
VPC	vpc-kafka
Subnet	subnet-kafka
Security Group	sg-kafka
IPv6	Disabled

- Step 8** Click the VPC to obtain the VPC ID on the VPC console.

Figure 5-8 Obtaining the VPC ID



VPC Information			
Name	vpc-kafka	ID	ea...72c
Created	Apr 24, 2022 09:59:50 GMT+08:00	Status	Available
CIDR Block	192.168.0.0/16 Edit CIDR Block	Enterprise Project	default
Description	- Edit		

Step 9 Call the VPC Endpoint API to create a VPC endpoint service. For details, see [Creating a VPC Endpoint Service](#).

```
POST https://{{endpoint}}/v1/{{project_id}}/vpc-endpoint-services
```

Set the following request parameter to the specified values, and other parameters as required.

- **port_id**: one of the port IDs obtained in [Step 6](#).
- **vpc_id**: VPC ID obtained in [Step 8](#).
- **server_type**: VM
- **client_port**: 9011
- **server_port**: 9011
- **protocol**: TCP
- **approval_enabled**: false
- **service_type**: interface
- **endpoint**: VPCEP endpoint obtained from [Regions and Endpoints](#). The region must be the same as that of the Kafka instance.
- **project_id**: project ID obtained from [Obtaining a Project ID](#). The region must be the same as that of the Kafka instance.

Record the value of **service_name** in the response. This parameter indicates the name of the VPC endpoint service.

Step 10 Repeat [Step 9](#) to create VPC endpoint services for other port IDs obtained in [Step 6](#) and record the VPC endpoint service names.


----End

(Optional) Adding a Whitelist

The VPC endpoint service can be used across accounts through a whitelist.

If the Kafka client and Kafka instance belong to different accounts, add the ID of the account to which the Kafka client belongs to the whitelist of the endpoint service. For details, see [Add a Whitelist Record](#).

Buying a VPC Endpoint

Step 1 Click  in the upper left corner of the console. Then choose **Network > VPC Endpoint**.

Step 2 Click **Buy VPC Endpoint**.

Step 3 Set the following parameters:

- **Region**: Select the region that the Kafka instance is in.
- **Service Category**: Select **Find a service by name**.
- **VPC Endpoint Service Name**: Enter the VPC endpoint service name recorded in [Step 9](#) and click **Verify**. If **Service name found** is displayed, proceed with subsequent operations.
- **VPC**: Select the VPC that the Kafka client is in.

- **Subnet:** Select the subnet that the Kafka client is in.
- **IPv4 Address:** Select **Automatically assign IP address**.

Retain the default values for other parameters. For details, see [Buying a VPC Endpoint](#).

Figure 5-9 VPC endpoint parameters

Region: [Region]

Billing Mode: Pay-per-use

Service Category: Cloud service

VPC Endpoint Service Name: 21560-efd2-4bb8-84ed-5d707302

VPC: vpc-kafka(192.168.0.0/16)

Subnet: subnet-kafka(192.168.0.0/...)

IPv4 Address: Automatically assign IP address

Access Control: [Off]

Tag: [Empty]

Description: [Empty]

Step 4 Click **Next**.

Step 5 Confirm the configurations and submit the request.

Step 6 Go back to the VPC endpoint list and check whether the status of the created VPC endpoint has changed to **Accepted**. The **Accepted** state means that the VPC endpoint has been connected to the VPC endpoint service.


Figure 5-10 Checking the VPC endpoint status

ID	Monit...	VPC	Status	VPC Endpoint ...	Type	IP Addr...	Created
5f285b1e-bee4-4bc8...		vpc-kafka	Accepted	21560...	Interface	192.168.0.74	May 20, 202...

Step 7 Click the VPC endpoint ID. On the **Summary** tab page, obtain the private IP address.

You can use the private IP address to access the VPC endpoint service.


Figure 5-11 Viewing the private IP address



Step 8 Repeat [Step 1](#) to [Step 7](#) to buy a VPC endpoint for each VPC endpoint service created in [Step 10](#), and view and record the private IP addresses of the VPC endpoint services.

----End


Modifying Parameter advertised.listeners IP

Step 1 Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 2 Click the desired Kafka instance to view its details.

Step 3 On the **Advanced Settings** section of the **Basic Information** tab page, click **Modify** for **Cross-VPC Access** to change the value of **advertised.listeners IP address** to the private IP addresses recorded in [Step 7](#) and [Step 8](#). **Each IP address must match the corresponding port ID. Otherwise, the network will be disconnected.** After the modification, click **Save**.

Figure 5-12 Changing the advertised.listeners IP addresses



----End

Verifying Connectivity

Check whether messages can be created and retrieved by referring to [Connecting to Kafka Using the Client \(SASL Disabled\)](#) or [Connecting to Kafka Using the Client \(SASL Enabled\)](#).

Notes:

- The address for connecting to a Kafka instance is in the format of "*advertised.listeners IP:9011*". For example, the addresses for connecting to the Kafka instance shown in [Figure 5-12](#) are **192.168.0.71:9011,192.168.0.11:9011,192.168.0.21:9011**.
- Configure inbound rules for the security group of the Kafka instance to allow access from **198.19.128.0/17** over port **9011**.

- If a network access control list (ACL) has been configured for the subnet of this instance, configure inbound rules for the network ACL to allow access from **198.19.128.0/17** and from the subnet used by the VPC endpoint.

 **NOTE**

198.19.128.0/17 is the network segment allocated to the VPCEP service. To use VPCEP, allow access from this network segment.

5.1.4 Accessing Kafka in a Public Network Using DNAT

Enable public access in either of the following ways:

- On the Kafka console, access Kafka instances using EIPs. For details, see [Configuring Kafka Public Access](#).
- Configure port mapping from EIPs to specified instance ports using destination NAT (DNAT).


This section describes how to access Kafka over a public network using DNAT.


Prerequisites

You have purchased EIPs of a quantity equal to the number of brokers in the Kafka instance. For details about how to purchase an EIP, see [Assigning an EIP](#).

Step 1: Obtain Information About the Kafka Instance

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.


Step 3 Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.


Step 6 In the **Connection** area on the **Basic Information** tab page, view and record the private network access addresses of the Kafka instance. In the **Network** area, view and record the VPC and subnet where the Kafka instance is located.

Figure 5-13 Kafka instance information



----End

Step 2: Buy a Public NAT Gateway

Step 1 Click  in the upper left corner of the management console and choose **Network > NAT Gateway**. The **Public NAT Gateways** page is displayed.


Step 2 Click **Buy Public NAT Gateway**.

Step 3 Set the following parameters:

- **Region:** Select the region that the Kafka instance is in.
- **Name:** Enter a name for the public NAT gateway.
- **VPC:** Select the VPC recorded in [Step 6](#).
- **Subnet:** Select the subnet recorded in [Step 6](#).
- **Enterprise Project:** Select an enterprise project as required.

Set other parameters as required. For details, see [Buying a Public NAT Gateway](#).

Figure 5-14 Buying a public NAT gateway



Step 4 Click **Next**.

Step 5 Confirm the specifications and click **Submit**.


----End

Step 3: Add a DNAT Rule

Step 1 On **Public NAT Gateways** page, locate the row containing the newly purchased public NAT gateway and click **Configure Rules** in the **Operation** column.

Step 2 On the **DNAT Rules** tab page, click **Add DNAT Rule**.

Figure 5-15 Public NAT gateway details



Step 3 Set the following parameters:

- **Scenario:** Select **VPC**.
- **Port Type:** Select **Specific port**.
- **Protocol:** Select **TCP**.
- **Public IP Address Type:** Select **EIP** and select an EIP.
- **Outside Port:** Enter **9011**.
- **Instance Type:** Select **Custom**.
- **Private IP Address:** Enter one of the private network addresses of the Kafka instance recorded in [Step 6](#).
- **Inside Port:** Enter **9011**.

For details about more parameters, see [Adding a DNAT Rule](#).

Figure 5-16 Adding a DNAT rule

Add DNAT Rule

Public NAT Gateway Name: nat-kafka

* Scenario: **VPC** Direct Connect/Cloud Connect

* Port Type: **Specific port** All ports

* Protocol: TCP

* Public IP Address Type: **EIP** Global EIP

1.2.3.4(1 Mbit/s | Pay-per-use | default) [View EIP](#) [?](#)

Bandwidth: 1 Mbit/s Billing Mode: Pay-per-use Enterprise Project: default

* Outside Port: 9011

* Instance Type: Server Virtual IP address **Custom**

* Private IP Address: . . .

* Inside Port: 9011

Description:

Step 4 Click **OK**.

View the DNAT rule status in the DNAT rule list. If **Status** is **Running**, the rule has been added successfully.

Step 5 Create DNAT rules for other private network addresses of the Kafka instance recorded in **Step 6**. **Configure a unique EIP for each DNAT rule.**

For details about how to create a DNAT rule, see **Step 2** to **Step 4**.


Step 6 After all DNAT rules are created, click the **DNAT Rules** tab to view the created DNAT rules and record the EIPs corresponding to the private IP addresses.

Figure 5-17 DNAT rule list

ID	Status	Scenario	Public IP Address	Outsid...	Private IP Address	Inside ...	Protocol
2bed5dc1-2954-466...	Running	VPC	1.2.3.4	9011	192.168.0.96	9011	TCP
198139a8-b66b-48...	Running	VPC	1.2.3.5	9011	192.168.0.64	9011	TCP
8d9feaf8-8aa9-47d...	Running	VPC	1.2.3.254	9011	192.168.0.235	9011	TCP

----End

Step 4: Map EIPs to the Port 9011 of Private IP Addresses


Step 1 Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 2 Click the desired Kafka instance to view its details.

Step 3 In the **Advanced Settings** section on the **Basic Information** tab page, click **Modify** next to **Cross-VPC Access**.

Step 4 Change the values of **advertised.listeners IP Address/Domain Name** to the EIPs in the DNAT rules. Ensure that the mapping between the private network addresses and the EIPs is consistent with that recorded in [Step 6](#). Then click **Save**.

Figure 5-18 Changing the advertised.listeners IP address (for DNAT access)



----End

Step 5: Verify Connectivity

Check whether messages can be created and retrieved by referring to [Connecting to Kafka Using the Client \(SASL Disabled\)](#) or [Connecting to Kafka Using the Client \(SASL Enabled\)](#).

Notes:

- The address for connecting to a Kafka instance is in the format of "*advertised.listeners IP:9011*". For example, the addresses for connecting to the Kafka instance shown in [Figure 5-18](#) are **124.xxx.xxx.167:9011,124.xxx.xxx.174:9011,124.xxx.xxx.57:9011**.
- Configure security group rules for the Kafka instance to allow inbound access over port **9011**.
- Public access must be enabled on the client connected to the Kafka instance.

5.2 Configuring Kafka Access Control

5.2.1 Configuring Plaintext or Ciphertext Access to Kafka Instances

You can access a Kafka instance in plaintext or ciphertext. This section describes how to change the access mode on the console.

- Plaintext access: Clients connect to the Kafka instance without SASL authentication.
- Ciphertext access: Clients connect to the Kafka instance with SASL authentication.

Notes and Constraints

- When you change the access mode for the first time, some instances will restart. You can see the actual situation on the console. The restart takes

about 75–80s. The instance will not be restarted when the access mode is changed again.


- For a single-node instance, you can only enable or disable plaintext for public network access.
- The access mode cannot be changed for instances with IPv6 enabled.


Prerequisites

You can change the access mode of a Kafka instance only when the instance is in the **Running** state.

Enabling Plaintext Access

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.



Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click a Kafka instance to go to the **Basic Information** page.

Step 6 An instance can be accessed in plaintext over the private network and public network. For details about how to enable plaintext access, see [Table 5-9](#).

Table 5-9 Enabling plaintext access

Access Method	Enabling Plaintext Access
Private network plaintext access	<ol style="list-style-type: none"> 1. Click  next to Plaintext Access in the Private Network Access area. A confirmation dialog box is displayed. 2. Click OK. The Background Tasks page is displayed. If the status of the task turns to Successful, plaintext access is successfully enabled.
Public network plaintext access	<ol style="list-style-type: none"> 1. Check that Public Access is enabled. If it is not enabled, enable it. For details, see Configuring Kafka Public Access. 2. Click  next to Plaintext Access in the Public Network Access area. A confirmation dialog box is displayed. 3. Click OK. The Background Tasks page is displayed. If the status of the task turns to Successful, plaintext access is successfully enabled.

----End

Enabling Ciphertext Access





- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click a Kafka instance to go to the **Basic Information** page.
- Step 6** An instance can be accessed in ciphertext over the private network and public network. For details about how to enable ciphertext access, see [Table 5-10](#).

Table 5-10 Enabling ciphertext access

Access Method	Enabling Ciphertext Access
Private network ciphertext access	<ol style="list-style-type: none"> 1. Click  next to Ciphertext Access in the Private Network Access area. The Private Network Ciphertext Access dialog box is displayed. 2. Set the Kafka security protocol, SASL/PLAIN mechanism, username, and password, and click OK. The Background Tasks page is displayed. If the status of the task turns to Successful, ciphertext access is successfully enabled. <p>NOTE When enabling ciphertext access for the first time (including through private network and public network), you need to set the Kafka security protocol, SASL/PLAIN mechanism, username, and password. Next time when you enable ciphertext access, you only need to set the Kafka security protocol.</p>

Access Method	Enabling Ciphertext Access
Public network ciphertext access	<ol style="list-style-type: none"> 1. Check that Public Access is enabled. If it is not enabled, enable it. For details, see Configuring Kafka Public Access. 2. Click  next to Ciphertext Access in the Public Network Access area. The Public Network Ciphertext Access dialog box is displayed. 3. Set the Kafka security protocol, SASL/PLAIN mechanism, username, and password, and click OK. The Background Tasks page is displayed. If the status of the task turns to Successful, ciphertext access is successfully enabled. <p>NOTE When enabling ciphertext access for the first time (including through private network and public network), you need to set the Kafka security protocol, SASL/PLAIN mechanism, username, and password. Next time when you enable ciphertext access, you only need to set the Kafka security protocol.</p>

The Kafka security protocol, SASL/PLAIN mechanism, username, and password are described as follows.

Table 5-11 Ciphertext access parameters

Parameter	Value	Description
Security Protocol	SASL_SSL	SASL is used for authentication. Data is encrypted with SSL certificates for high-security transmission.
	SASL_PLAINTEXT	SASL is used for authentication. Data is transmitted in plaintext for high performance. SCRAM-SHA-512 authentication is recommended for plaintext transmission.
Cross-VPC Access Protocol	-	<ul style="list-style-type: none"> • When Plaintext Access is enabled and Ciphertext Access is disabled, PLAINTEXT is used for Cross-VPC Access Protocol. • When Ciphertext Access is enabled and Security Protocol is SASL_SSL, SASL_SSL is used for Cross-VPC Access Protocol. • When Ciphertext Access is enabled and Security Protocol is SASL_PLAINTEXT, SASL_PLAINTEXT is used for Cross-VPC Access Protocol. <p>Fixed once the instance is created.</p>

Parameter	Value	Description
SASL/PLAIN	-	<ul style="list-style-type: none"> If SASL/PLAIN is disabled, the SCRAM-SHA-512 mechanism is used for username and password authentication. If SASL/PLAIN is enabled, both the SCRAM-SHA-512 and PLAIN mechanisms are supported. You can select either of them as required. <p>The SASL/PLAIN setting cannot be changed once ciphertext access is enabled.</p> <p>What are SCRAM-SHA-512 and PLAIN mechanisms?</p> <ul style="list-style-type: none"> SCRAM-SHA-512: uses the hash algorithm to generate credentials for usernames and passwords to verify identities. SCRAM-SHA-512 is more secure than PLAIN. PLAIN: a simple username and password verification mechanism.
Username and Password	-	<p>Username and password used by the client to connect to the Kafka instance.</p> <p>A username should contain 4 to 64 characters, start with a letter, and contain only letters, digits, hyphens (-), and underscores (_).</p> <p>A password must meet the following requirements:</p> <ul style="list-style-type: none"> Contains 8 to 32 characters. Contains at least three types of the following characters: uppercase letters, lowercase letters, digits, and special characters <code>~!@#%&*()-_+=\ [{]};:","<.>?</code> and spaces, and cannot start with a hyphen (-). Cannot be the username spelled forward or backward. <p>The username cannot be changed once ciphertext access is enabled.</p>

The Kafka security protocol, SASL/PLAIN mechanism, username, and password are required when the client accesses a Kafka instance with ciphertext access enabled. For details, see [Connecting to Kafka Using the Client \(SASL Enabled\)](#).

----End

Disabling Plaintext Access







- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click a Kafka instance to go to the **Basic Information** page.
- Step 6** An instance can be accessed in plaintext over the private network and public network. For details about how to disable plaintext access, see [Table 5-12](#).

Table 5-12 Disabling plaintext access

Access Method	Disabling Plaintext Access
Private network plaintext access	<p>Once enabled, private network access cannot be disabled. Enable plaintext or ciphertext access, or both. If ciphertext access is disabled, plaintext access cannot be disabled.</p> <ol style="list-style-type: none"> Click  next to Plaintext Access in the Private Network Access area. Click OK. The Background Tasks page is displayed. If the status of the task turns to Successful, plaintext access is successfully disabled.
Public network plaintext access	<ol style="list-style-type: none"> Click  next to Plaintext Access in the Public Network Access area. Click OK. The Background Tasks page is displayed. If the status of the task turns to Successful, plaintext access is successfully disabled.



----End

Disabling Ciphertext Access

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click a Kafka instance to go to the **Basic Information** page.

- Step 6** An instance can be accessed in ciphertext over the private network and public network. For details about how to disable ciphertext access, see [Table 5-13](#).

Table 5-13 Disabling ciphertext access

Access Method	Disabling Plaintext Access
Private network ciphertext access	<ol style="list-style-type: none">1. Click  next to Ciphertext Access in the Private Network Access area.2. Click OK. The Background Tasks page is displayed. If the status of the task turns to Successful, ciphertext access is successfully disabled.
Public network ciphertext access	<ol style="list-style-type: none">1. Click  next to Ciphertext Access in the Public Network Access area.2. Click OK. The Background Tasks page is displayed. If the status of the task turns to Successful, ciphertext access is successfully disabled.

After you disable ciphertext access, the created users will not be deleted. You do not need to create users again when you enable ciphertext access next time.

----End

5.2.2 Generating and Replacing an SSL Kafka Certificate in JKS Format

The SSL certificate secures data transmission through encryption between a client and an instance.

When connecting a Kafka client to a Kafka instance that has ciphertext access enabled and SASL_SSL as the security protocol, use either the certificate provided by DMS for Kafka or your own certificate. This section describes how to generate your own certificate and use it to replace the one provided by DMS for Kafka.

To generate and replace certificates, contact background support personnel to enable the function for you. This function is available on a whitelist basis in all regions.

Notes and Constraints

Replacing the certificate will restart the instance. Exercise caution.

Prerequisites

- A Linux server is available. The server must install [Java Development Kit 1.8.111 or later](#) and **JAVA_HOME** and **PATH** environment variables are configured.
- Kafka SASL_SSL has been enabled for the instance.

Enter **y** when the following information is displayed:

Trust this certificate?

4. Import the signed server certificate to the server keystore.
keytool -keystore server.keystore.jks -alias localhost -import -file server.cert-signed

Enter the keystore password set in **Step 1** as prompted.

- Step 6** Export the **server.keystore.jks**, **server.truststore.jks**, and **client.truststore.jks** certificates to the local PC.

The **server.keystore.jks** and **server.truststore.jks** files are used to replace the keystore and truststore files in subsequent step **Replacing a Certificate**. **client.truststore.jks** is required to be stored on the client. Record the storage path and it is the value of **ssl.truststore.location** in the configuration file used by the client to connect to the Kafka instance.


Figure 5-19 Certificate directory


```
total 44
drwxr-xr-x  2 root root 4096 Aug 10 15:20 ./
drwxr-xr-x 10 root root 4096 Aug  8 17:04 ../
-rw-r--r--  1 root root 1322 Aug  8 17:07 ca-cert
-rw-r--r--  1 root root   41 Aug  8 17:09 ca-cert.srl
-rw-----  1 root root 1854 Aug  8 17:07 ca-key
-rw-r--r--  1 root root 1226 Aug  8 17:08 client.truststore.jks
-rw-r--r--  1 root root 1055 Aug  8 17:09 server.cert-file
-rw-r--r--  1 root root 1176 Aug  8 17:09 server.cert-signed
-rw-r--r--  1 root root 4693 Aug  8 17:10 server.keystore.jks
-rw-r--r--  1 root root 1226 Aug  8 17:08 server.truststore.jks
```

----End

Step 2: Replacing a Certificate

- Step 1** Log in to the console.

- Step 2** Click  in the upper left corner to select the region where your instance is located.

- Step 3** Click  and choose **Middleware > Distributed Message Service for Kafka** to open the console of DMS for Kafka.

- Step 4** In the navigation pane, choose **Kafka Instances**.

- Step 5** Click the desired instance to view its details.

- Step 6** In the **Connection** area, click **Re-upload** next to **SSL Certificate**.

Figure 5-20 Connection information

Connection

Username: root [Reset Password](#)

Private Network Access

- Plaintext Access:
- Address (Private Network, Plaintext): 192.168.79.91:9... [Copy](#)
- Ciphertext Access:

Public Access [?](#) Enabled

- Plaintext Access:
- Address (Public Network, Plaintext): 100.128.204... [Copy](#)
- Ciphertext Access:
- Address (Public Network, Ciphertext): 100.128.204... [Copy](#)
- Security Protocol: SASL_SSL

SASL Mechanism: SCRAM-SHA-512

Mutual SSL Authentication: Disabled

SSL Certificate: [Download](#) | [Re-upload](#)

Step 7 Set the parameters for replacing the SSL certificate by referring to [Table 5-14](#).

Figure 5-21 Replacing the SSL certificate

Replace SSL certificate

i Replacing the certificate will restart the instance. ×

Key Password	<input style="border: 1px solid #ccc; border-radius: 4px;" type="password"/>
Keystore Password	<input style="border: 1px solid #ccc; border-radius: 4px;" type="password"/>
Keystore File	<div style="border: 1px solid #ccc; border-radius: 15px; padding: 5px; display: inline-block; margin-bottom: 5px;">Select File</div> <p style="font-size: 0.9em; color: #666; margin-top: 5px;">Select a JKS file under 100 KB.</p>
Truststore Password	<input style="border: 1px solid #ccc; border-radius: 4px;" type="password"/>
Truststore File	<div style="border: 1px solid #ccc; border-radius: 15px; padding: 5px; display: inline-block; margin-bottom: 5px;">Select File</div> <p style="font-size: 0.9em; color: #666; margin-top: 5px;">Select a JKS file under 100 KB.</p>

Table 5-14 Parameters for replacing the SSL certificate

Parameter	Description
Key Password	Enter the keystore password set in Step 1 .
Keystore Password	Enter the keystore password set in Step 1 .
Keystore File	Import the server.keystore.jks certificate.
Truststore Password	Enter the server truststore password set in Step 3 .
Truststore File	Import the server.truststore.jks certificate.

Step 8 Click **OK**.

Step 9 Click **OK**.

On the **Background Tasks** page, if the certificate replacement task is **Successful**, the certificate is successfully replaced.

After the original certificate is successfully replaced, you will download the certificate provided by DMS for Kafka rather than your own certificate by clicking **Download** on the **Basic Information** tab page.

----End

Step 3: Modifying Client Configuration Files

After a certificate is replaced, modify the `ssl.truststore.location` and `ssl.truststore.password` parameters in the `consumer.properties` and `producer.properties` files on the client, respectively.

```
security.protocol=SASL_SSL
ssl.truststore.location=/opt/kafka_2.12-2.7.2/config/client.truststore.jks
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
```

- `ssl.truststore.location`: path for storing the [client.truststore.jks certificate](#).
- `ssl.truststore.password`: [truststore password of the client certificate](#)
- `ssl.endpoint.identification.algorithm`: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**

5.2.3 Obtaining and Using An SSL Kafka Certificate in PEM Format


This section describes how to obtain an SSL certificate in PEM format and use it to access a Kafka instance.


Prerequisite

SASL_SSL has been enabled for the Kafka instance.

Obtaining a PEM SSL Certificate

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 Click **Download** next to **Connection > SSL Certificate**.

Step 7 Decompress the Zip package to obtain the PEM SSL certificate **client.pem**.

----End

Accessing a Kafka Instance Using a PEM Certificate

The following section demonstrates how to access a Kafka instance using a PEM certificate on a Java client.

Access a Kafka instance to produce and consume messages by referring to [Configuring Kafka Clients in Java](#). Modify the SASL setting of the message production and consumption configuration files as follows:

```
# If the SASL mechanism is PLAIN, configure as follows:
sasl.mechanism=PLAIN
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="username" \
password="password";

# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.mechanism=SCRAM-SHA-512
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="username" \
password="password";

#Set the Kafka security protocol.
security.protocol=SASL_SSL
# ssl truststore.location is the path for storing the SSL certificate. The following code uses the path format
in Windows as an example. Change the path format based on the actual running environment.
ssl.truststore.location=E:\temp\client.pem
# ssl.truststore.password is the server certificate password. To access a Kafka instance using a PEM
certificate, skip this parameter.
#ssl.truststore.password=dms@kafka
# ssl.endpoint.identification.algorithm indicates whether to verify the certificate domain name. This
parameter must be left blank, which indicates disabling domain name verification.
ssl.endpoint.identification.algorithm=
# Add the ssl.truststore.type parameter to specify the client certificate type to PEM.
ssl.truststore.type=PEM
```

5.2.4 Configuring Mutual SSL Authentication for Kafka


Mutual SSL authentication verifies the certificates of both the client and server during communication. This ensures that both parties involved in the communication are trusted.

Enable mutual SSL authentication to achieve high security.

To use mutual SSL authentication, contact background support personnel to enable it for you.

Figure 5-22 shows the overall procedure for configuring mutual SSL authentication.

Figure 5-22 Overall procedure for configuring mutual SSL authentication



Notes and Constraints

Configuring mutual SSL authentication will restart the instance. Exercise caution.

Prerequisites

- A Linux server is available. The server must install [Java Development Kit 1.8.111 or later](#) and `JAVA_HOME` and `PATH` environment variables are configured.
- Kafka SASL_SSL has been enabled for the instance.

Step 1: Generate Certificates for the Client to Verify the Server

Step 1 Log in to the Linux server and run the following command to generate a keystore for the `server.keystore.jks` certificate:

```
keytool -genkey -keystore server.keystore.jks -alias localhost -validity 3650 -keyalg RSA
```

Enter the keystore password as prompted and record the password for later use.

The password must meet the following requirements:

- Contains 8 to 32 characters.
- Contains at least three of the following character types: letters, digits, spaces, and special characters ``-!@# $ % ^ & * () - _ = + \ | [{ } : " ' ; < , > / ?` and does not start with a hyphen (-).

- Cannot be a weak password. To check whether a password is weak, enter it in [Step 7](#).

Enter the information about the certificate owner as prompted, such as the name, company, organization, city, and country or region.

```
[root@ecs-kafka ~]# keytool -genkey -keystore server.keystore.jks -alias localhost -validity 3650 -keyalg RSA
Enter keystore password:
Re-enter new password:
What is your first and last name?
  [Unknown]: Tom
What is the name of your organizational unit?
  [Unknown]: test
What is the name of your organization?
  [Unknown]: test01
What is the name of your City or Locality?
  [Unknown]: nj
What is the name of your State or Province?
  [Unknown]: js
What is the two-letter country code for this unit?
  [Unknown]: xx
Is CN=Tom, OU=test, O=test01, L=nj, ST=js, C=xx correct?
  [no]: y
```

Step 2 Run the following command to generate a CA:

```
openssl req -new -x509 -keyout ca-key -out ca-cert -days 3650
```

Enter the PEM password as prompted and record the password for later use.

The password must meet the following requirements: 4 to 1024 characters.

Enter the information about the certificate owner as prompted, such as the country or region, city, organization, company, name, and email.

```
[root@ecs-kafka ~]# openssl req -new -x509 -keyout ca-key -out ca-cert -days 3650
Generating a RSA private key
.....+++++
.....+++++
writing new private key to 'ca-key'
Enter PEM pass phrase:
Verifying - Enter PEM pass phrase:
-----
You are about to be asked to enter information that will be incorporated into your certificate request.
What you are about to enter is what is called a Distinguished Name or a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
-----
Country Name (2 letter code) [XX]:xx
State or Province Name (full name) []:js
Locality Name (eg, city) [Default City]:nj
Organization Name (eg, company) [Default Company Ltd]:test01
Organizational Unit Name (eg, section) []:test
Common Name (eg, your name or your server's hostname) []:Tom
Email Address []:xx
[root@ecs-kafka ~]#
```

Step 3 Run the following command to export the certificate from the **server.keystore.jks** file generated in [Step 1](#) and name the certificate **server.crt**:

```
keytool -keystore server.keystore.jks -alias localhost -certreq -file server.crt
```

Enter the keystore password in [Step 1](#) as prompted.

Step 4 Run the following command to use the CA private key to sign **server.crt** and name the signed certificate **server-signed.crt**:

```
openssl x509 -req -CA ca-cert -CAkey ca-key -in server.crt -out server-signed.crt -days 3650 -CAcreateserial
```

Enter the PEM password set in [Step 2](#) as prompted.

Step 5 Run the following command to import the CA certificate and **server-signed.crt** to the keystore:

```
keytool -keystore server.keystore.jks -alias CARoot -import -file ca-cert  
keytool -keystore server.keystore.jks -alias localhost -import -file server-signed.crt
```

Enter the keystore password in [Step 1](#) as prompted.

Enter **y** when the following information is displayed:

```
Trust this certificate?
```

Step 6 Run the following command to enable the client to trust the server certificate:

```
keytool -keystore client.truststore.jks -alias CARoot -import -file ca-cert
```

Enter the password of **client.truststore.jks** as required and record the password for later use.

The password must meet the following requirements:

- Contains 8 to 32 characters.
- Contains at least three of the following character types: letters, digits, spaces, and special characters `~!@#\$%^&*()-_+=\|[]{}:~<.>/? and does not start with a hyphen (-).
- Cannot be a weak password. To check whether a password is weak, enter it in [Step 7](#).

Enter **y** when the following information is displayed:

```
Trust this certificate?
```

Step 7 Export the **client.truststore.jks** and **server.keystore.jks** certificates to the local PC.

The **server.keystore.jks** file is used to replace the **keystore** file in the later step **Enable Mutual SSL Authentication**. **client.truststore.jks** is required to be stored on the client. Record the storage path and it is the value of **ssl.truststore.location** in the configuration file used by the client to connect to the Kafka instance.

----End

Step 2: Generate Certificates for the Server to Verify the Client

Step 1 Log in to the Linux server and run the following command to generate a keystore for the **client.keystore.jks** certificate:

```
keytool -genkey -keystore client.keystore.jks -alias localhost -validity 3650 -keyalg RSA
```

Enter the keystore password as prompted and record the password for later use.

The password must meet the following requirements:

- Contains 8 to 32 characters.
- Contains at least three of the following character types: letters, digits, spaces, and special characters `~!@#\$%^&*()-_+=\|[]{}:~<.>/? and does not start with a hyphen (-).
- Cannot be a weak password. To check whether a password is weak, enter it in [Step 7](#).

Enter the information about the certificate owner as prompted, such as the name, company, organization, city, and country or region.


```
[root@ecs-kafka ~]# keytool -genkey -keystore client.keystore.jks -alias localhost -validity 3650 -keyalg RSA
Enter keystore password:
Re-enter new password:
What is your first and last name?
  [Unknown]: Tom
What is the name of your organizational unit?
  [Unknown]: test
What is the name of your organization?
  [Unknown]: test01
What is the name of your City or Locality?
  [Unknown]: nj
What is the name of your State or Province?
  [Unknown]: js
What is the two-letter country code for this unit?
  [Unknown]: xx
Is CN=Tom, OU=test, O=test01, L=nj, ST=js, C=xx correct?
  [no]: y
```

Step 2 Run the following command to generate a CA:

```
openssl req -new -x509 -keyout ca-key -out ca-cert -days 3650
```

Enter the PEM password as prompted and record the password for later use.

The password must meet the following requirements: 4 to 1024 characters.

Enter the information about the certificate owner as prompted, such as the country or region, city, organization, company, name, and email.

```
[root@ecs-kafka ~]# openssl req -new -x509 -keyout ca-key -out ca-cert -days 3650
Generating a RSA private key
.....+++++
.....+++++
writing new private key to 'ca-key'
Enter PEM pass phrase:
Verifying - Enter PEM pass phrase:
-----
You are about to be asked to enter information that will be incorporated into your certificate request.
What you are about to enter is what is called a Distinguished Name or a DN.
There are quite a few fields but you can leave some blank
For some fields there will be a default value,
If you enter '.', the field will be left blank.
-----
Country Name (2 letter code) [XX]:xx
State or Province Name (full name) []:js
Locality Name (eg, city) [Default City]:nj
Organization Name (eg, company) [Default Company Ltd]:test01
Organizational Unit Name (eg, section) []:test
Common Name (eg, your name or your server's hostname) []:Tom
Email Address []:xx
[root@ecs-kafka ~]#
```

Step 3 Run the following command to export the certificate from the **client.keystore.jks** file generated in **Step 1** and name the certificate **client.crt**:

```
keytool -keystore client.keystore.jks -alias localhost -certreq -file client.crt
```

Enter the keystore password in **Step 1** as prompted.

Step 4 Run the following command to use the CA private key to sign **client.crt** and name the signed certificate **client-signed.crt**:

```
openssl x509 -req -CA ca-cert -CAkey ca-key -in client.crt -out client-signed.crt -days 3650 -CAcreateserial
```

Enter the PEM password set in **Step 2** as prompted.

Step 5 Run the following command to import the CA certificate and **client-signed.crt** to the keystore:

```
keytool -keystore client.keystore.jks -alias CARoot -import -file ca-cert
keytool -keystore client.keystore.jks -alias localhost -import -file client-signed.crt
```

Enter the keystore password in [Step 1](#) as prompted.

Enter **y** when the following information is displayed:
Trust this certificate?

Step 6 Run the following command to enable the server to trust the client certificate:

```
keytool -keystore server.truststore.jks -alias CARoot -import -file ca-cert
```

Enter the password of **server.truststore.jks** as prompted and record the password for later use.

The password must meet the following requirements:

- Contains 8 to 32 characters.
- Contains at least three of the following character types: letters, digits, spaces, and special characters `~!@#\$%^&*()-_+=\|{}:~";<.>/?` and does not start with a hyphen (-).
- Cannot be a weak password. To check whether a password is weak, enter it in [Step 7](#).

Enter **y** when the following information is displayed:
Trust this certificate?


Step 7 Export the **server.truststore.jks** and **client.keystore.jks** certificates to the local PC.

The **server.truststore.jks** file is used to replace the **truststore** file in the later step **Enable Mutual SSL Authentication**. **client.keystore.jks** is required to be stored on the client. Record the storage path and it is the value of **ssl.keystore.location** in the configuration file used by the client to connect to the Kafka instance.

----End

Step 3: Enable Mutual SSL Authentication

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service for Kafka** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired Kafka instance to go to the instance details page.

Step 6 In the **Connection** area, click  next to **Mutual SSL Authentication**.

Step 7 In the displayed **Mutual SSL Authentication** dialog box, set the parameters by referring to [Table 5-15](#).

Enabling mutual SSL authentication will restart the instance. Exercise caution.

Figure 5-23 Enabling mutual SSL authentication

Mutual SSL Authentication

i 1. Modifying this setting will restart the instance. ✕
 2. The protocol will change to SSL once you enable mutual SSL authentication.

Key Password	<input style="border: 1px solid #ccc; border-radius: 4px;" type="password"/>
Keystore Password	<input style="border: 1px solid #ccc; border-radius: 4px;" type="password"/>
Keystore File	<div style="border: 1px solid #ccc; border-radius: 15px; padding: 5px; display: inline-block; margin-bottom: 5px;">Select File</div> <small>Select a JKS file under 100 KB.</small>
Truststore Password	<input style="border: 1px solid #ccc; border-radius: 4px;" type="password"/>
Truststore File	<div style="border: 1px solid #ccc; border-radius: 15px; padding: 5px; display: inline-block; margin-bottom: 5px;">Select File</div> <small>Select a JKS file under 100 KB.</small>

Table 5-15 Parameters for enabling mutual SSL authentication

Parameter	Description
Key Password	Enter the password of server.keystore.jks .
Keystore Password	Enter the password of server.keystore.jks .
Keystore File	Import the server.keystore.jks certificate.
Truststore Password	Enter the password of server.truststore.jks .
Truststore File	Import the server.truststore.jks certificate.

Step 8 Click **OK**.

----End

Step 4: Modifying Client Configuration Files

After enabling mutual SSL authentication, modify the server certificate configuration and add the client certificate configurations in the **consumer.properties** and **producer.properties** files on the client.


```
security.protocol=SSL
ssl.truststore.location=/opt/kafka_2.12-2.7.2/config/client.truststore.jks
```

```
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
# Add the following client certificate configurations:
ssl.keystore.location=/var/private/ssl/kafka/client.keystore.jks
ssl.keystore.password=txxx3
ssl.key.password=txxx3
```

- **security.protocol**: certificate protocol type. When enabling mutual SSL authentication, set this parameter to **SSL**.
- **ssl.truststore.location**: path for storing the **client.truststore.jks** certificate.
- **ssl.truststore.password**: **password of client.truststore.jks**.
- **ssl.endpoint.identification.algorithm**: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**
- **ssl.keystore.location**: path for storing the **client.keystore.jks** certificate.
- **ssl.keystore.password**: **password of client.keystore.jks**.
- **ssl.key.password**: **password of client.keystore.jks**.

Disabling Mutual SSL Authentication

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service for Kafka** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired Kafka instance.

Step 6 In the **Connection** area, click  next to **Mutual SSL Authentication**.

Disabling mutual SSL authentication will restart the instance. Exercise caution.

Step 7 After disabling mutual SSL authentication, modify the server certificate protocol and delete the client certificate configurations in the **consumer.properties** and **producer.properties** files on the client.

```
security.protocol=SASL_SSL
ssl.truststore.location=/opt/kafka_2.12-2.7.2/config/client.truststore.jks
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
# Delete the following client certificate configurations:
ssl.keystore.location=/var/private/ssl/kafka.client.keystore.jks
ssl.keystore.password=txxx3
ssl.key.password=txxx3
```

security.protocol: certificate protocol type. When disabling mutual SSL authentication, set this parameter to **SASL_SSL**. You do not need to change the values of **ssl.truststore.location**, **ssl.truststore.password**, and **ssl.endpoint.identification.algorithm**.

----End

5.2.5 Configuring Kafka ACL Users

Kafka instances with ciphertext access enabled support access control list (ACL) for topics. You can differentiate user permissions by granting users different permissions in a topic.

This section describes how to create users, reset the password, modify user information, and delete users with ciphertext access enabled. For details about how to grant topic permissions for users, see [Configuring Kafka Topic Permissions](#).

There are two ways to create a user on the console. Accordingly, there are two ways to reset the user's password:

- Initial user: The user set when ciphertext access is enabled for the first time. If you forget your password, reset it by referring to [Resetting the Password \(for the Initial User\)](#).
- Non-initial users: Users created on the **Users** page. If you forget your password, reset it by referring to [Resetting the Password \(for Non-initial Users\)](#).

Notes and Constraints


- Single-node instances do not support user creation, user password reset, user information modification, or user deletion.
- The initial user set when ciphertext access is enabled for the first time cannot be deleted.
- Resetting a user password will interrupt services. Change the user password in the client configuration file or code as soon as possible.
- The maximum number of users that can be created for a Kafka instance is 20 or 500. Check the console for the actual limit.


Prerequisites

- Ciphertext access has been enabled for the Kafka instance.
- Kafka users can be configured only for Kafka instances in the **Running** state.

Creating a User

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 On the **Users** page, click **Create User**.

Step 7 Set user information by referring to [Configuring Kafka ACL Users](#).

Table 5-16 User creation parameters

Parameter	Description
Username	The username used to access a Kafka instance, you can customize a name that complies with the rules: 4–64 characters; starts with a letter; can contain only letters, digits, hyphens (-), and underscores (_).
Password	The password used to access a Kafka instance. A password must meet the following requirements: <ul style="list-style-type: none"> • Contains 8 to 32 characters. • Contains at least three types of the following characters: uppercase letters, lowercase letters, digits, and special characters `~!@#\$%^&*()-_+=\ [{}];:~<.>? and spaces, and cannot start with a hyphen (-). • Cannot be the username spelled forward or backward.
Description	The description of a user. 0–200 characters.


Step 8 Click **OK**.


After the user is created, grant permissions to the user by referring to [Configuring Kafka Topic Permissions](#).

----End

Resetting the Password (for the Initial User)

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Reset the password for the initial user in either of the following ways.

- Choose **More > Reset Kafka Password** in the row containing the desired Kafka instance.
- Click the desired Kafka instance to go to the instance details page. Choose **More > Reset Kafka Password** in the upper left corner.
- Click the desired Kafka instance to go to the instance details page. On the **Basic Information** page, click **Reset Password** next to **Username** in the **Connection** section.
- Click the desired Kafka instance to go to the instance details page. On the **Users** page, click **Reset Password** in the row containing the desired user.

Step 6 Enter and confirm a new password, and click **OK**.

- If the password is successfully reset, a success message is displayed.
- If the password fails to be reset, a failure message is displayed. In this case, reset the password again. If you still fail to reset the password after multiple attempts, contact customer service.


 **NOTE**


The system will display a success message only after the password is successfully reset on all brokers.

----End

Resetting the Password (for Non-initial Users)

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired Kafka instance to go to the instance details page.

Step 6 On the **Users** page, click **Reset Password** in the row containing the desired user.

Step 7 Enter and confirm a new password, and click **OK**.

- If the password is successfully reset, a success message is displayed.
- If the password fails to be reset, a failure message is displayed. In this case, reset the password again. If you still fail to reset the password after multiple attempts, contact customer service.


 **NOTE**


The system will display a success message only after the password is successfully reset on all brokers.

----End

Modifying User Information

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Users**.

Step 7 In the row containing the desired user, click **Edit**.


Step 8 Modify the description and click **OK**.


After the modification is successful, you can view the new description in the **Description** column.

----End

Deleting a User

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Users**.

Step 7 Delete a user in either of the following ways:


- In the row containing the desired user, click **Delete**.
- Select one or more users and click **Delete** above the list.


Step 8 In the displayed **Delete User** dialog box, click **OK** to delete the user.

----End

Exporting the User List

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Users**.

Step 7 Export the user list in either of the following ways:

- Select the desired users and choose **Export > Export selected data to an XLSX file** to export specified users.
- Choose **Export > Export all data to an XLSX file** to export all users.

Note: The initial user cannot be selected manually. To export the initial user, choose **Export all data to an XLSX file**.

----End

5.3 Configuring the Kafka Client

5.3.1 Setting Parameters for Kafka Clients

This section provides recommendations on configuring common parameters for Kafka producers and consumers. Kafka clients in different versions may have different parameter names. The following parameters are supported in v1.1.0 and later. For details about other parameters and versions, see [Kafka Configuration](#).

Table 5-17 Producer parameters

Parameter	Default Value	Recommended Value	Description
acks	1	all or -1 (if high reliability mode is selected) 1 (if high throughput mode is selected)	<p>Number of acknowledgments the producer requires the server to return before considering a request complete. This controls the durability of records that are sent. The value of this parameter can be any of the following:</p> <p>0: The producer will not wait for any acknowledgment from the server at all. The record will be immediately added to the socket buffer and considered sent. No guarantee can be made that the server has received the record, and the retries configuration will not take effect (as the client generally does not know of any failures). The offset given back for each record will always be set to -1.</p> <p>1: The leader will write the record to its local log but will respond without waiting until receiving full acknowledgement from all followers. If the leader fails immediately after acknowledging the record but before the followers have replicated it, the record will be lost.</p> <p>all or -1: The leader needs to wait until all backups in the ISR are written into logs. As long as any backup survives, data will not be lost. min.insync.replicas specifies the minimum number of replicas that must acknowledge a write for the write to be considered successful.</p>

Parameter	Default Value	Recommended Value	Description
retries	0	/	<p>Number of times that the client resends a message. Setting this parameter to a value greater than zero will cause the client to resend any record that failed to be sent.</p> <p>Note that this retry is no different than if the client re-sent the record upon receiving the error. Allowing retries will potentially change the ordering of records because if two batches are sent to the same partition, and the first fails and is retried but the second succeeds, then the records in the second batch may appear first.</p> <p>You are advised to configure producers so that they can be able to retry in case of network disconnections. Set retries to 3 and the retry interval retry.backoff.ms to 1000.</p>
request.timeout.ms	30,000	/	<p>Maximum amount of time (in ms) the client will wait for the response of a request. If the response is not received before the timeout elapses, the client will throw a timeout exception.</p> <p>Setting this parameter to a large value, for example, 127000 (127s), can prevent records from failing to be sent in high-concurrency scenarios.</p>
block.on.buffer.full	TRUE	TRUE	<p>Setting this parameter to TRUE indicates that when buffer memory is exhausted, the producer must stop receiving new message records or throw an exception.</p> <p>By default, this parameter is set to TRUE. However, in some cases, non-blocking usage is desired and it is better to throw an exception immediately. Setting this parameter to FALSE will cause the producer to instead throw "BufferExhaustedException" when buffer memory is exhausted.</p>

Parameter	Default Value	Recommended Value	Description
batch.size	16,384	262,144	<p>Default maximum number of bytes of messages that can be processed at a time. The producer will attempt to batch records together into fewer requests whenever multiple records are being sent to the same partition. This helps improve performance of both the client and the server. No attempt will be made to batch records larger than this size.</p> <p>Requests sent to brokers will contain multiple batches, one for each partition with data available to be sent.</p> <p>A smaller batch size will make batching less common and may reduce throughput (a batch size of zero will disable batching entirely). A larger batch size may use more memory as a buffer of the specified batch size will always be allocated in anticipation of additional records.</p>
buffer.memory	33,554,432	67,108,864	<p>Total bytes of memory the producer can use to buffer records waiting to be sent to the server. If records are sent faster than they can be delivered to the broker, the producer will stop sending records or throw a "block.on.buffer.full" exception.</p> <p>This setting should correspond roughly to the total memory the producer will use, but is not a rigid bound since not all memory the producer uses is used for buffering. Some additional memory will be used for compression (if compression is enabled) as well as for maintaining in-flight requests.</p>

Parameter	Default Value	Recommended Value	Description
enable.idempotence	<ul style="list-style-type: none"> Earlier than v3.0: false v3.0 and later: true 	If idempotence is not required, you are advised to set this parameter to false .	If you have enabled idempotence on the producer client, and produced messages, message offsets are not continuous on the consumer client or on the Message Query page on the Kafka console. This is because enabling idempotence generates some metadata control messages during message production. These control messages are produced to topics, and are invisible to consumers.

Table 5-18 Consumer parameters

Parameter	Default Value	Recommended Value	Description
auto.commit.enable	TRUE	FALSE	<p>If this parameter is set to TRUE, the offset of messages already fetched by the consumer will be periodically committed to ZooKeeper. This committed offset will be used when the process fails as the position from which the new consumer will begin.</p> <p>Constraints: If this parameter is set to FALSE, to avoid message loss, an offset must be committed to ZooKeeper after the messages are successfully consumed.</p>

Parameter	Default Value	Recommended Value	Description
auto.offset.reset	latest	earliest	<p>Indicates what to do when there is no initial offset in ZooKeeper or if the current offset has been deleted. Options:</p> <ul style="list-style-type: none"> • earliest: Automatically reset to the smallest offset. • latest: Automatically reset to the largest offset. • none: The system throws an exception to the consumer if no offset is available. • anything else: The system throws an exception to the consumer. <p>If this parameter is set to latest, the producer may start to send messages to new partitions (if any) before the consumer resets to the initial offset. As a result, some messages will be lost.</p>
connections.max.idle.ms	600,000	30,000	<p>Timeout interval (in ms) for an idle connection. The server closes the idle connection after this period of time ends. Setting this parameter to 30000 can reduce the server response failures when the network condition is poor.</p>
max.poll.records	500	Must be less than the value of max.poll.interval.ms .	<p>The maximum number of messages that a consumer can pull from a broker at a time.</p>
max.poll.interval.ms	300,000	Increase this parameter if complex and time-consuming logic exists between two polls.	<p>The maximum interval between consumer polls, in milliseconds. If this parameter is exceeded, the consumption fails and the consumer is removed from the consumer group, triggering rebalance.</p>
heartbeat.interval.ms	3,000	≥ 3000	<p>Heartbeat interval between a consumer and Kafka, in milliseconds.</p>

Parameter	Default Value	Recommended Value	Description
session.timeout.ms	10,000	Set this parameter to at least 3 times the value of heartbeat.interval.ms .	The consumer-broker session timeout when the offset is managed by consumer group, in milliseconds.
fetch.max.bytes	1,000,000	max.request.size < message.max.bytes < fetch.max.bytes	The maximum bytes of a message that a consumer can pull from a broker at a time.

5.3.2 Suggestions on Using the Kafka Client

Consumers

1. Ensure that the owner thread does not exit abnormally. Otherwise, the client may fail to initiate consumption requests and the consumption will be blocked.
2. Commit messages only after they have been processed. Otherwise, the messages may fail to be processed and cannot be polled again.
3. Generally, do not commit every message. Otherwise, there will be many **OFFSET_COMMIT** requests, causing high CPU usage. For example, if a consumption request pulls 1000 messages and commits every one of them, TPS of the commit requests is 1000 times that of consumption. The smaller the message size, the larger the ratio. You can commit a specific number of messages in batches or enable **enable.auto.commit**. However, if the client is faulty, some cached consumption offset may be lost, resulting in repeated consumption. Therefore, you are advised to commit messages in batches based on service requirements.
4. A consumer cannot frequently join or leave a group. Otherwise, the consumer will frequently perform rebalancing, which blocks consumption.
5. The number of consumers in a consumer group must be within the total partitions subscribed by the consumer group. Otherwise, some consumers cannot pull messages.
6. Ensure that the consumer polls at regular intervals to keep sending heartbeats to the server. If the consumer stops sending heartbeats for long enough, the consumer session will time out and the consumer will be considered to have stopped. This will also block consumption.
7. Ensure that there is a limitation on the size of messages buffered locally to avoid an out-of-memory (OOM) situation.
8. Set the timeout for the consumer session to 30 seconds:
session.timeout.ms=30000.
9. Kafka supports exactly-once delivery. Therefore, ensure the idempotency of processing messages for services.

10. Always close the consumer before exiting. Otherwise, consumers in the same group may be blocked within the timeout set by **session.timeout.ms**.
11. Do not start a consumer group name with a special character, such as a number sign (#). Otherwise, monitoring data of the consumer group cannot be displayed.

Producers

1. Synchronous replication: Set **acks** to **all**.
2. Retry message sending: Set **retries** to **3**.
3. Optimize message sending: For latency-sensitive messages, set **linger.ms** to **0**. For latency-insensitive messages, set **linger.ms** to a value ranging from **100** to **1000**.
4. Ensure that the producer has sufficient JVM memory to avoid blockages.
5. Set the timestamp to the local time. Messages will fail to age if the timestamp is a future time.
6. Try reusing producers. Do not create producers frequently. When idempotence is enabled (default for producer clients 3.0 and later), producing messages creates producer state objects on the server. Frequent creation results in too many objects to be reclaimed in time, causing server memory surges and performance deterioration. Set **enable.idempotence** to **false** if the idempotence is not required.

Topics

Recommended topic configurations: Use 3 replicas, enable synchronous replication, and set the minimum number of in-sync replicas to 2. The number of in-sync replicas cannot be the same as the number of replicas of the topic. Otherwise, if one replica is unavailable, messages cannot be produced.

You can enable or disable automatic topic creation. Enabling this function automatically creates a topic when a message is produced in or consumed from a topic that does not exist.

Others

Maximum number of connections: 3000

Maximum size of a message: 10 MB

Access Kafka using SASL_SSL. Ensure that your DNS service is capable of resolving an IP address to a domain name. Alternatively, map all Kafka broker IP addresses to host names in the **hosts** file. Prevent Kafka clients from performing reverse resolution. Otherwise, connections may fail to be established.

Apply for a disk space size that is more than twice the size of service data multiplied by the number of replicas. In other words, keep 50% of the disk space idle.

Avoid frequent full GC in JVM. Otherwise, message production and consumption will be blocked.

5.4 Connecting to Kafka Using the Client (SASL Disabled)

This section describes how to access a Kafka instance with SASL disabled on an open-source Kafka client. With SASL disabled, there is no authentication required in such a connection and data is transmitted in plaintext, which is friendly to performance.

Notes and Constraints

For instances purchased in July 2020 and later, each Kafka broker allows a maximum of 1000 connections from each IP address by default. For instances purchased before July 2020, each Kafka broker allows a maximum of 200 connections from each IP address by default. Excess connections will be rejected. You can change the limit by referring to [Modifying Kafka Instance Configuration Parameters](#), that is, to modify parameter `max.connections.per.ip`.

Prerequisites

- The network between the client and the Kafka instance has been established. For details about the network requirements, see [Kafka Network Connection Conditions](#).
- Security group rules have been properly configured.
Before accessing a Kafka instance with SASL disabled on a client, configure proper security group rules for the instance. For details, see [Table 5-2](#).
- The Kafka instance addresses have been obtained.


Obtain the instance connection addresses in the **Connection** area on the **Basic Information** page on the Kafka console. The addresses are displayed in two types on the Kafka console. The one is **Private Network Access** or **Public Network Access** and the other is **Address (Private Network, Plaintext)** or **Address (Public Network, Plaintext)**.

- For private access within a VPC, the Kafka connection addresses are shown as follows.

Figure 5-24 Kafka instance addresses for private access within a VPC (Instance Address (Private Network))

Instance Address (Private Network) IPv4 192.168.0.24:9092,192.168.0.224:9092,192.168.0.197:9092 

Figure 5-25 Kafka instance addresses for private access within a VPC (Address (Private Network, Plaintext))

Address (Private Network, Plaintext)	192.168.4.103:9092,192.168.4.74:9092,192.168.4.167:9092 
--------------------------------------	---

- For public access, the Kafka connection addresses are shown as follows.

Figure 5-26 Kafka instance addresses for public access (**Instance Address (Public Network)**)

Instance Address (Public Network) 139:9094,122:9094,119:9094,100:9094

Figure 5-27 Kafka instance addresses for public access (**Address (Public Network, Plaintext)**)

Address (Public Network, Plaintext) 100:9094,100:9094,100:9094,100:9094

- If automatic topic creation is not enabled for the Kafka instance, [create a topic](#) before connecting to the instance.
- Kafka CLI [v1.1.0](#), [v2.3.0](#), [v2.7.2](#), or [v3.4.0](#) is available. Ensure that the Kafka instance and the CLI use the same version.
- [JDK v1.8.111 or later](#) has been installed on the server, and the `JAVA_HOME` and `PATH` environment variables have been configured as follows:

Add the following lines to the `.bash_profile` file in the home directory as an authorized user. In this command, `/opt/java/jdk1.8.0_151` is the JDK installation path. Change it to the path where you install JDK.

```
export JAVA_HOME=/opt/java/jdk1.8.0_151
export PATH=$JAVA_HOME/bin:$PATH
```

Run the `source .bash_profile` command for the modification to take effect.

Accessing the Instance Using CLI

The following uses Linux as an example.

Step 1 Decompress the Kafka CLI package.

Access the directory where the CLI package is stored and run the following command to decompress the package:

```
tar -zxf [kafka_tar]
```

In the preceding command, `[kafka_tar]` indicates the name of the CLI package.

For example:

```
tar -zxf kafka_2.12-2.7.2.tgz
```

Step 2 Access the `/bin` directory of the Kafka CLI.

In Windows, you need to access the `/bin/windows` directory.

Step 3 Run the following command to produce messages:

```
./kafka-console-producer.sh --broker-list ${connection-address} --topic ${topic-name}
```

Parameter description:

- `{connection-address}`: the address obtained in [Prerequisites](#).
- `{topic-name}`: the name of the topic created for the Kafka instance. If automatic topic creation has enabled for the Kafka instance, set this parameter to the name of a created topic or a topic that has not been created.

The following example uses connection addresses **10.xx.xx.45:9094,10.xx.xx.127:9094,10.xx.xx.103:9094**. After running the preceding command, you can send a message to the Kafka instance by writing it and pressing **Enter**. Each line of content is sent as a message.

```
[root@ecs-kafka bin]# ./kafka-console-producer.sh --broker-list
10.xx.xx.45:9094,10.xx.xx.127:9094,10.xx.xx.103:9094 --topic topic-demo
>Hello
>DMS
>Kafka!
>^C[root@ecs-kafka bin]#
```

To stop producing messages, press **Ctrl+C** to exit.

Step 4 Run the following command to consume messages:

```
./kafka-console-consumer.sh --bootstrap-server ${connection-address} --topic ${topic-name} --group $
{consumer-group-name} --from-beginning
```

Parameter description:

- *{connection-address}*: the address obtained in [Prerequisites](#).
- *{topic-name}*: the name of the topic created for the Kafka instance.
- *{consumer-group-name}*: the consumer group name set based on your service requirements. **If a consumer group name has been specified in the configuration file, ensure that you use the same name in the command line. Otherwise, consumption may fail.** If a consumer group name starts with a special character, such as a number sign (#), the monitoring data cannot be displayed.

Example:

```
[root@ecs-kafka bin]# ./kafka-console-consumer.sh --bootstrap-server
10.xx.xx.45:9094,10.xx.xx.127:9094,10.xx.xx.103:9094 --topic topic-demo --group order-test --from-beginning
Kafka!
DMS
Hello
^CProcessed a total of 3 messages
[root@ecs-kafka bin]#
```

To stop consuming messages, press **Ctrl+C** to exit.

----End

5.5 Connecting to Kafka Using the Client (SASL Enabled)

This section describes how to access a Kafka instance in ciphertext on an open-source Kafka client. The client connects to the Kafka instance with SASL authentication. If the security protocol **SASL_SSL** is used, the client communicates with the Kafka instance in encryption, improving security.

Notes and Constraints

- For security purposes, **TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA256**, **TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256**, and **TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256** are supported for instances created on and before March 20, 2021.

TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256 is also supported for instances created after March 20, 2021.

- For instances purchased in July 2020 and later, each Kafka broker allows a maximum of 1000 connections from each IP address by default. For instances purchased before July 2020, each Kafka broker allows a maximum of 200 connections from each IP address by default. Excess connections will be rejected. You can change the limit by referring to [Modifying Kafka Instance Configuration Parameters](#), that is, to modify parameter `max.connections.per.ip`.

Prerequisites

- The network between the client and the Kafka instance has been established. For details about the network requirements, see [Kafka Network Connection Conditions](#).
- Security group rules have been properly configured.
Before accessing a Kafka instance with ciphertext access enabled on a client, configure proper security group rules for the instance. For details, see [Table 5-2](#).
- The Kafka instance addresses have been obtained.


Obtain the instance connection addresses in the **Connection** area on the **Basic Information** page on the Kafka console. The addresses are displayed in two types on the Kafka console. The one is **Private Network Access** or **Public Network Access** and the other is **Address (Private Network, Ciphertext)** or **Address (Public Network, Ciphertext)**.

- For private access within a VPC, the Kafka connection addresses are shown as follows.

Figure 5-28 Kafka instance addresses for private access within a VPC (**Instance Address (Private Network)**)

Instance Address (Private Network) IPv4 192.168.0.239:9093,192.168.0.182:9093,192.168.0.57:9093 

Figure 5-29 Kafka instance addresses for private access within a VPC (**Address (Private Network, Plaintext)**)

Address (Private Network, Plaintext)	192.0.0.238:9093,192.0.0.32:9093,192.0.0.236:9093 
--------------------------------------	---

- For public access, the Kafka connection addresses are shown as follows.

Figure 5-30 Kafka instance addresses for public access (**Instance Address (Public Network)**)



Instance Address (Public Network) 139.145.9095,122.145.9095,119.145.9095 

Figure 5-31 Kafka instance addresses for public access (**Address (Public Network, Ciphertext)**)



- The SASL mechanism in use is known.
In the **Connection** area on the Kafka instance details page, view **SASL Mechanism**. If both SCRAM-SHA-512 and PLAIN are enabled, use either of them in connection configurations. For instances that were created much earlier, if **SASL Mechanism** is not displayed on the instance details page, PLAIN is used by default.

Figure 5-32 SASL mechanism in use



- The security protocol in use is known.
In the **Connection** area on the Kafka instance details page, view **Security Protocol**. For instances that were created much earlier, if **Security Protocol** is not displayed on the instance details page, SASL_SSL is used by default.
- If automatic topic creation is not enabled for the Kafka instance, [create a topic](#) before connecting to the instance.
- The **client.jks** certificate has been downloaded. Click the Kafka instance to go to the **Basic Information** tab page. Click **Download** next to **SSL Certificate** in the **Connection** area. Download and decompress the package to obtain the client certificate file **client.jks**.
- Kafka CLI [v1.1.0](#), [v2.3.0](#), [v2.7.2](#), or [v3.4.0](#) is available. Ensure that the Kafka instance and the CLI use the same version.
- [JDK v1.8.111 or later](#) has been installed on the server, and the **JAVA_HOME** and **PATH** environment variables have been configured as follows:

Add the following lines to the **.bash_profile** file in the home directory as an authorized user. In this command, **/opt/java/jdk1.8.0_151** is the JDK installation path. Change it to the path where you install JDK.

```
export JAVA_HOME=/opt/java/jdk1.8.0_151
export PATH=$JAVA_HOME/bin:$PATH
```

Run the **source .bash_profile** command for the modification to take effect.

Accessing the Instance Using CLI

The following uses Linux as an example.

- Step 1** Map hosts to IP addresses in the **/etc/hosts** file on the host where the client is located, so that the client can quickly parse the instance brokers.

Set IP addresses to the instance connection addresses obtained in [Prerequisites](#). Set hosts to the names of instance hosts. Specify a unique name for each host.

For example:

```
10.154.48.120 server01
10.154.48.121 server02
10.154.48.122 server03
```

Step 2 Decompress the Kafka CLI package.

Access the directory where the CLI package is stored and run the following command to decompress the package:

```
tar -zxf [kafka_tar]
```

In the preceding command, *[kafka_tar]* indicates the name of the CLI package.

For example:

```
tar -zxf kafka_2.12-2.7.2.tgz
```

Step 3 Modify the Kafka CLI configuration file based on the [SASL mechanism](#).

- **If PLAIN is used**, find the **consumer.properties** and **producer.properties** files in the **/config** directory of the Kafka CLI and add the following content to the files:

```
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description:

username and **password**: username and password you set when enabling ciphertext access for the first time or when creating a user.

- **If SCRAM-SHA-512 is used**, find the **consumer.properties** and **producer.properties** files in the **/config** directory of the Kafka CLI and add the following content to the files:

```
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
```

Parameter description:

username and **password**: username and password you set when enabling ciphertext access for the first time or when creating a user.

Step 4 Modify the Kafka CLI configuration file based on the [security protocol](#).

- **SASL_SSL**: Find the **consumer.properties** and **producer.properties** files in the **/config** directory of the Kafka CLI and add the following content to the files:

```
security.protocol=SASL_SSL
ssl.truststore.location={ssl_truststore_path}
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
```

Parameter description:

- **ssl.truststore.location**: path for storing the **client.jks** certificate. Even in Windows, you need to use slashes (/) for the certificate path. Do not use backslashes (\), which are used by default for paths in Windows. Otherwise, the client will fail to obtain the certificate.
- **ssl.truststore.password**: server certificate password, which must be set to **dms@kafka** and cannot be changed.
- **ssl.endpoint.identification.algorithm**: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**

- **SASL_PLAINTEXT**: Find the **consumer.properties** and **producer.properties** files in the **/config** directory of the Kafka CLI and add the following content to the files:
security.protocol=SASL_PLAINTEXT

Step 5 Access the **/bin** directory of the Kafka CLI.

In Windows, you need to access the **/bin/windows** directory.

Step 6 Run the following command to create messages:

```
./kafka-console-producer.sh --broker-list ${connection addr} --topic ${topic name} --producer.config ../config/producer.properties
```

Parameter description:

- *{connection-address}*: the address obtained in [Prerequisites](#).
- *{topic-name}*: the name of the topic created for the Kafka instance. If automatic topic creation has enabled for the Kafka instance, set this parameter to the name of a created topic or a topic that has not been created.

The following example uses connection addresses **10.xx.xx.45:9095,10.xx.xx.127:9095,10.xx.xx.103:9095**.

After running the preceding command, you can send a message to the Kafka instance by writing it and pressing **Enter**. Each line of content is sent as a message.

```
[root@ecs-kafka bin]# ./kafka-console-producer.sh --broker-list
10.xx.xx.45:9095,10.xx.xx.127:9095,10.xx.xx.103:9095 --topic topic-demo --producer.config ../config/
producer.properties
>Hello
>DMS
>Kafka!
>^C[root@ecs-kafka bin]#
```

To stop producing messages, press **Ctrl+C** to exit.

Step 7 Run the following command to retrieve messages:

```
./kafka-console-consumer.sh --bootstrap-server ${connection-address} --topic ${topic-name} --group $
{consumer-group-name} --from-beginning --consumer.config ../config/consumer.properties
```

Parameter description:

- *{connection-address}*: the address obtained in [Prerequisites](#).
- *{topic-name}*: the name of the topic created for the Kafka instance.
- *{consumer-group-name}*: the consumer group name set based on your service requirements. **If a consumer group name has been specified in the configuration file, ensure that you use the same name in the command line. Otherwise, consumption may fail.** If a consumer group name starts with a special character, such as a number sign (**#**), the monitoring data cannot be displayed.

Example:

```
[root@ecs-kafka bin]# ./kafka-console-consumer.sh --bootstrap-server
10.xx.xx.45:9095,10.xx.xx.127:9095,10.xx.xx.103:9095 --topic topic-demo --group order-test --from-beginning
--consumer.config ../config/consumer.properties
Hello
DMS
Kafka!
```

```
^CProcessed a total of 3 messages
[root@ecs-kafka bin]#
```

To stop consuming messages, press **Ctrl+C** to exit.

----End

5.6 Connecting to Kafka on the Console


This section describes how a Kafka instance produces messages on the console. Specified messages can be sent to a Kafka instance to verify service logic.


Prerequisites

- Messages can be produced in a topic only when the instance is in the **Running** state.
- [A topic](#) has been created.

Producing Messages on the Console

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Topics**.

Step 7 In the row containing the desired topic, choose **More > Create Message** or click **Create Message** (see the console). The **Create Message** dialog box is displayed.

Step 8 Set message parameters by referring to [Table 5-19](#).

Table 5-19 Message parameters

Parameter	Description
Message Body	Message content. 0–128,000 bytes.
Message Key	Message key.
Specify Partition	Indicates whether to enable the function of sending messages to a specified partition. <ul style="list-style-type: none"> • Off: Messages are sent to partitions based on their key hash. • On: Messages are sent to specified partitions. Requires the partition ID.

Step 9 Click **OK**.

You can view the sent messages on the **Message Query** page.

----**End**

6 Managing Messages

6.1 Viewing Kafka Messages


You can view the offset of different partitions, the message size, creation time, and body of messages in topics.


Notes and Constraints

- If a topic contains a large amount of data, an internal service error may be reported when you query messages in a topic with only one replica. You can shorten the time range for query based on the data volume.
- To query with content, due to resource and performance restrictions, a total of 200 MB and 10,000 messages can be queried, and a maximum of 10 messages can be returned.
- The console displays messages smaller than 4 KB. To view messages larger than 4 KB, click **Download Message**.

Procedure

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the left navigation pane, choose **Message Query**.

Step 7 Messages can be queried by creation time or offset. For details, see [Table 6-1](#) and [Table 6-2](#).

Table 6-1 Querying messages by creation time

Parameter	Description
Topic Name	Name of the topic to be queried.
Partition	Partition where the message is located. If no partition is specified, messages in all partitions of the topic are displayed in the query result.
Content	Enter a keyword in the message body. NOTE Due to resource and performance restrictions, query with content is limited to 10 results. Each search covers at most 10,000 records, or 200 MB. For large records (> 20 KB per message) or a long period, dump messages for offline query.
Created	A time range to be queried. NOTE If a topic contains a large amount of data, an internal service error may be reported when you query messages in a topic with only one replica. You can shorten the time range for query based on the data volume.

Table 6-2 Querying messages by offset

Parameter	Description
Topic Name	Name of the topic to be queried.
Partition	Partition where the message is located.
Offset	Offset of the message.

Step 8 Click **Search** to query messages.

The query result is as follows.

Figure 6-1 Querying topic messages

Topic Name	Partition	Offset	Message Size (Bytes)	Created	Operation
topic-1081992957	0	1	8	May 20, 2024 14:12:08 GMT+08:00	View Message Body
topic-1081992957	0	0	9	May 20, 2024 14:11:57 GMT+08:00	View Message Body

Parameter description:

- **Topic Name:** name of the topic where the message is located
- **Partition:** partition where the message is located
- **Offset:** position of the message in the partition
- **Message Size (Byte)** size of the message
- **Created:** time when the message is created. The message creation time is specified by **CreateTime** when a producer creates messages. If this parameter

is not set during message creation, the message creation time is year 1970 by default.

Step 9 Click **View Message Body**. In the displayed **View Message Body** dialog box, view the message content, including the topic name, partition, offset, creation time, and message body.

The console displays messages smaller than 4 KB. To view messages larger than 4 KB, click **Download Message**.

Step 10 (Optional) To restore the default settings, click **Reset**.

----End

6.2 Changing Kafka Message Retention Period

Aging time is a period that messages in a topic are retained for. Consumers must consume messages before this period ends. Otherwise, the messages will be deleted and can no longer be consumed.

The topic retention period is 72 hours by default, and can be changed later as required. Changing the aging time does not affect services.

You can change the aging time in either of the following ways:

- By editing the topic on the **Topics** tab page
- By changing the value of the **log.retention.hours** parameter on the **Parameters** tab page. For details, see [Modifying Kafka Instance Configuration Parameters](#).


The **log.retention.hours** parameter takes effect only for topics that have no aging time configured. If there is aging time configured for a topic, it overrides the **log.retention.hours** parameter. For example, if the aging time of Topic01 is set to 60 hours and **log.retention.hours** is set to 72 hours, the actual aging time of Topic01 is 60 hours.


Notes and Constraints

The retention period of single-node instances can be modified only on the **Topics** page.

Procedure

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Topics**.

Step 7 Modify the topic aging time using either of the following methods:

- Select one or more topics and click **Edit Topic** in the upper left corner.
- In the row containing the desired topic, click **Edit**.

Step 8 In the **Edit Topic** dialog box, enter the aging time and click **OK**.

----End

6.3 Deleting Kafka Messages

This section describes how to delete messages stored in a topic on the console.

Notes and Constraints

Deleting messages takes effect permanently.

Prerequisite


Before deleting a message, set the **auto.offset.reset** parameter in the code of consumption. **auto.offset.reset** specifies the consumption policy of a consumer when there is no initial offset in Kafka or the current offset does not exist (for example, the current offset has been deleted). Options:


- **latest**: The offset is automatically reset to the latest offset.
- **earliest**: The offset is automatically reset to the earliest offset.
- **none**: The system throws an exception to the consumer.

If this parameter is set to **latest**, the producer may start to send messages to new partitions (if any) before the consumer resets to the initial offset. As a result, some messages will be lost.

Procedure

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Topics**.

Step 7 In the row that contains the topic whose messages you want to delete, choose **More > Delete Messages**. The **Delete Messages** dialog box is displayed.

Step 8 Set the parameters for deleting messages, as shown in [Table 6-3](#).

Figure 6-2 Deleting messages





Table 6-3 Parameters for deleting a message

Parameter	Description
Partition	Select the ID of the partition where the message is located.
Offset	Enter an offset. The data after the earliest offset and before this offset will be deleted. For example, if the earliest offset is 2 and the entered offset is 5, the messages whose offset ranges from 2 to 4 will be deleted. Note: <ul style="list-style-type: none"> If Offset is set to -1, all messages in the partition will be deleted. If the offset you entered is not between the earliest offset and the latest offset of the specified partition, no messages will be deleted.

To delete messages from multiple partitions, click **Add Partition** and specify the partition and offset for the messages to be deleted. 10 partitions can be deleted at most at a time.

Step 9 Click **OK**. The **Deletion Result** dialog box is displayed. Click **OK** to delete the messages.

Figure 6-3 Deletion result



The screenshot shows a dialog box titled "Deletion Result" with a close button (X) in the top right corner. Below the title is a table with three columns: "Partition", "Offset", and "Deletion Result". The table contains one row with the following data: "Partition0", "-1", and "Successful" (with a green checkmark icon). At the bottom right of the dialog box is an "OK" button.

Partition	Offset	Deletion Result
Partition0	-1	✓ Successful

----End

6.4 Diagnosing Kafka Message Accumulation

Unprocessed messages accumulate if the client's consumption is slower than the server's sending. Accumulated messages cannot be consumed in time.


DMS for Kafka provides the message accumulation diagnosis function on the console. If there are accumulated messages, you can learn about the possible causes, affected partitions or brokers, and handling suggestions of the accumulation by viewing the diagnosis record.

Prerequisites

- A Kafka instance has been created, and a consumer group is consuming messages in non-assign mode.
- When a consumer group is being diagnosed, other consumer groups and other topics in the consumer group cannot be diagnosed.


Process Flow


Figure 6-4 Process of accumulation diagnosis



Step 1: Pre-check

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.


Step 5 Click the desired instance to go to the instance details page.

Step 6 In the left navigation pane, choose **Analysis & Diagnosis > Accumulation Diagnosis**.

Step 7 Select the consumer groups and topics to be diagnosed, and click **Pre-check**.

If the check is successful, the message "Pre-checked" is displayed in the upper part of the page, and the check results of the memory usage, CPU usage, partition subscription relationships, accumulated messages, and traffic burst are displayed.

Figure 6-5 Pre-check



If there is no risk shown in the **Accumulated Messages** area, message accumulation diagnosis cannot be performed. If there are any risks in the **Accumulated Messages** area and the consumer group is not consuming message in the assign mode, you can perform [message accumulation diagnosis](#).

----End

Step 2: Diagnosis


Step 1 Click **Start Diagnosis**. In the **Diagnosis Records** area, a record in the **Diagnosing** state is displayed.

If the status changes to **Successful**, the diagnosis is complete.

Step 2 Locate the row that contains the target diagnosis record, and click **View Details**. The **Diagnosis Details** page is displayed.

Step 3 View the number of abnormal, failed, and normal items in the upper part of the page. In the **Diagnosed Item** area, click an abnormal item, such as **Rebalancing**, and view the possible causes, affected partitions or brokers, and handling suggestions.

Figure 6-6 Diagnosis details




----End

7 Managing Consumer Groups

7.1 Creating a Kafka Consumer Group

A consumer subscribes to a topic. A consumer group consists of one or more consumers. Within a consumer group, each consumer can consume multiple partitions at the same time. Each partition can be consumed by one consumer at a time.

Figure 7-1 Example consumption



auto.create.groups.enable: a consumer group is automatically created when a consumer attempts to enter a group that does not exist.

- A consumer group is required before consuming messages when **auto.create.groups.enable** is **false** in [Configuring Parameters](#). Otherwise, consumption will fail.
- A consumer group is created automatically before consuming messages when **auto.create.groups.enable** is **true** in [Configuring Parameters](#).


This section describes how to create a consumer group on the console. This operation does not restart the Kafka instance.


Notes and Constraints

- For instances created on and after April 25, 2023, consumer groups can be created on the console.
- If **auto.create.groups.enable** is set to **true**, the consumer group status is **EMPTY**, and no offset has been submitted, the system automatically deletes the consumer group 10 minutes later.
- If **auto.create.groups.enable** is set to **false**, the system does not automatically delete consumer groups. You can manually delete them.
- If a consumer group has never committed an offset, the group will be deleted after the Kafka instance restarts.

Procedure

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Consumer Groups**.

Step 7 Click **Create Consumer Group**.

Step 8 Set consumer group parameters by referring to [Table 7-1](#) and click **OK**.

Table 7-1 Consumer group parameters

Parameter	Description
Consumer Group Name	Enter 3 to 64 characters, starting with a letter or underscore (_). Use only letters, digits, periods (.), hyphens (-), and underscores (_). If a consumer group name starts with a special character, for example, a number sign (#), monitoring data cannot be displayed.
Description	Enter 0 to 200 characters.

View the new consumer group in the consumer group list.


----End


7.2 Querying the Kafka Consumer Group List

After a consumer group is created, you can view its configuration and status.

Viewing the Consumer Group List (Console)

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose the **Consumer Groups** tab.


The consumer group name, status, Coordinator (ID), and description are displayed. Coordinator (ID) indicates the broker where the coordinator component is located. The consumer group status can be:

- **DEAD:** The consumer group has no member or metadata.
- **EMPTY:** The consumer group has metadata but has no member.
- **PREPARING_REBALANCE:** The consumer group is to be rebalanced.
- **COMPLETING_REBALANCE:** All members have joined the consumer group.
- **STABLE:** Members in the consumer group can consume messages normally.

Figure 7-2 Consumer group list

Consumer Group Name	Status	Coordinator (ID)	Description	Operation
<input type="checkbox"/> test	EMPTY	2	--	Edit Delete

Step 7 (Optional) To query a consumer group, enter a consumer group name or status, Coordinator (ID), number of accumulated messages, description, or keyword, then press **Enter**.

Step 8 (Optional) To refresh the consumer group list, click  in the upper right corner.

----End

Viewing the Consumer Group List (Kafka CLI)

- For a Kafka instance with ciphertext access disabled, run the following command in the **/bin** directory of the Kafka client:

```
./kafka-consumer-groups.sh --bootstrap-server ${connection-address} --list
```

Parameter description: **connection-address** indicates the Kafka instance address, which can be obtained in the **Connection** area on the **Basic Information** page on the Kafka console.

Example:

```
[root@ecs-kafka bin]# ./kafka-consumer-groups.sh --bootstrap-server
192.168.xx.xx:9092,192.xx.xx.212:9092,192.xx.xx.147:9092 --list
test
__consumer-group-dial-test
[root@ecs-kafka bin]#
```

- For a Kafka instance with ciphertext access enabled, do as follows:
 - a. (Optional) Modify the client configuration file.

View **Security Protocol** in the **Connection** area on the **Basic Information** page on the Kafka console. The configuration settings vary depending on the protocol.

- **SASL_PLAINTEXT**: Skip this step and go to **b** if the username and password are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_PLAINTEXT
# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
# If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description: **username** and **password** are the ones you set when enabling ciphertext access for the first time or when creating a user.

- **SASL_SSL**: Skip this step and go to **b** if the username, password, and SSL certificate are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_SSL
ssl.truststore.location={ssl_truststore_path}
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
# If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description:

- **ssl.truststore.location**: path for storing the **client.jks** certificate. Even in Windows, you need to use slashes (/) for the certificate path. Do not use backslashes (\), which are used by default for paths in Windows. Otherwise, the client will fail to obtain the certificate.

- **ssl.truststore.password** is certified by the server, which must be set to **dms@kafka** and cannot be changed.
 - **ssl.endpoint.identification.algorithm**: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**
 - **username** and **password**: username and password you set when enabling ciphertext access for the first time or when creating a user.
- b. Run the following command in the **/bin** directory of the Kafka client:
- ```
./kafka-consumer-groups.sh --bootstrap-server ${connection-address} --list --command-config ../config/ssl-user-config.properties
```

Parameter description: **connection-address** indicates the Kafka instance address, which can be obtained in the **Connection** area on the **Basic Information** page on the Kafka console.

Example:

```
[root@ecs-kafka bin]# ./kafka-consumer-groups.sh --bootstrap-server
192.168.xx.xx:9093,192.168.xx.xx:9093,192.168.xx.xx:9093 --list --command-config ../config/ssl-
user-config.properties
test
__consumer-group-dial-test
[root@ecs-kafka bin]#
```

## 7.3 Viewing Kafka Consumer Information

If a consumer group has consumers who are accessing a Kafka instance, you can view their connection information.

### Notes and Constraints


- Due to cache reasons, the consumer connection addresses displayed on Kafka Manager may have expired. In this case, restart Kafka Manager.
- Instances created on or after May 17, 2023 do not have Kafka Manager. You cannot view consumer addresses of these instances using Kafka Manager.


### Prerequisites

The consumer list and connection address can be viewed only when consumers in a consumer group are connected to the Kafka instance (that is, the consumer group is in the **STABLE** state).

### Viewing the Consumer List (Console)

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Consumer Groups**.

**Step 7** Click the name of the desired consumer group.

**Step 8** On the **Consumers** tab page, view the consumer list.

In the consumer list, you can view the consumer ID, consumer address, and client ID.

**Step 9** (Optional) To query a specific consumer, enter the consumer ID in the search box and press **Enter**.

----End

## Viewing the Consumer List (Kafka CLI)

- For a Kafka instance with ciphertext access disabled, run the following command in the **/bin** directory of the Kafka client:

```
./kafka-consumer-groups.sh --bootstrap-server ${connection-address} --group ${group-name} --members --describe
```

Parameter description:

- connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- group-name**: consumer group name.

Example:

```
[root@ecs-kafka bin]# ./kafka-consumer-groups.sh --bootstrap-server
192.168.xx.xx:9092,192.168.xx.xx:9092,192.168.xx.xx:9092 --group test --members --describe
GROUP CONSUMER-ID HOST CLIENT-ID
#PARTITIONS
test console-consumer-571a64fe-b0c4-47ce-833d-9e0da5a88d14 /192.168.0.215 console-
consumer 3
[root@ecs-kafka bin]#
```

- For a Kafka instance with ciphertext access enabled, do as follows:
  - (Optional) Modify the client configuration file.

View **Security Protocol** in the **Connection** area on the **Basic Information** page on the Kafka console. The configuration settings vary depending on the protocol.

- SASL\_PLAINTEXT**: Skip this step and go to **b** if the username and password are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_PLAINTEXT
If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```



Parameter description: **username** and **password** are the ones you set when enabling ciphertext access for the first time or when creating a user.

- **SASL\_SSL**: Skip this step and go to **b** if the username, password, and SSL certificate are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_SSL
ssl.truststore.location={ssl_truststore_path}
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description:

- **ssl.truststore.location**: path for storing the **client.jks** certificate. Even in Windows, you need to use slashes (/) for the certificate path. Do not use backslashes (\), which are used by default for paths in Windows. Otherwise, the client will fail to obtain the certificate.
  - **ssl.truststore.password** is certified by the server, which must be set to **dms@kafka** and cannot be changed.
  - **ssl.endpoint.identification.algorithm**: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**
  - **username** and **password**: username and password you set when enabling ciphertext access for the first time or when creating a user.
- b. Run the following command in the **/bin** directory of the Kafka client:
- ```
./kafka-consumer-groups.sh --bootstrap-server ${connection-address} --group ${group-name} --members --describe --command-config ../config/ssl-user-config.properties
```

Parameter description:

- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **group-name**: consumer group name.

Example:

```
[root@ecs-kafka bin]# ./kafka-consumer-groups.sh --bootstrap-server
192.168.xx.xx:9093,192.168.xx.xx:9093,192.168.xx.xx:9093 --group test --members --describe --
command-config ../config/ssl-user-config.properties
```

GROUP	CONSUMER-ID	HOST	CLIENT-ID
#PARTITIONS			
test	console-consumer-566d0c82-07d3-4d87-9a6e-f57a9bc9fc69	/192.168.0.215	console-consumer 3

```
[root@ecs-kafka bin]#
```

Viewing Consumer Connection Addresses (Console)




- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose **Consumer Groups**.
- Step 7** Click the desired consumer group.
- Step 8** On the **Consumers** tab page, view the consumer addresses.

Figure 7-3 Consumer list




ID	Address	Client ID
console-consumer-8b13d9f2-d958-403f-adcd-90f60601a57c	/192.168.0.88	console-consumer

----End

Viewing Consumer Connection Addresses (Kafka Manager)

- Step 1** [Log in to Kafka Manager](#).
- Step 2** Click **kafka_cluster** to go to the cluster details page.
- Step 3** On the top menu bar, choose **Consumers**.

Figure 7-4 Navigation bar



- Step 4** Click the desired consumer group to view the topics that the group has subscribed to.

Figure 7-5 Consumer group list

Consumers			
Show 10 entries			
Consumer	Type	Topics it consumes from	
group01	KF	topic-01: (100% coverage, 180016 lag) topic-02: (0% coverage, 0 lag)	
group02	KF	topic-02: (0% coverage, 0 lag)	
group11	KF	topic-01: (100% coverage, 363016 lag)	

Step 5 Click the desired topic to go to the topic details page.

Figure 7-6 Topics that the consumer group has subscribed to

Consumed Topic Information	
Topic	Partitions Covered %
topic-01	100
topic-02	0

Step 6 In the **Consumer Instance Owner** column, view the consumer connection address.

Figure 7-7 Topic details page

Partition	LogSize	Consumer Offset	Lag	Consumer Instance Owner
0	33,333	0	33,333	consumer-1-5d096c5f-159d-468d-8b10-7961dc6f49d1/10.224.177.100
1	33,334	0	33,334	consumer-1-5d096c5f-159d-468d-8b10-7961dc6f49d1/10.224.177.100
2	33,333	0	33,333	consumer-1-5d096c5f-159d-468d-8b10-7961dc6f49d1/10.224.177.100

----End

7.4 Viewing and Resetting Kafka Consumption Offsets

A consumption offset indicates the consumption progress of a consumer. This section describes how to view and reset consumption offsets.

Notes and Constraints


Messages may be consumed more than once after the offset is reset. Exercise caution when performing this operation.


Prerequisites

The consumer offset cannot be reset on the fly. You must first stop consumption of the desired consumer group. After a client is stopped, the server considers the client offline only after the time period specified in **ConsumerConfig.SESSION_TIMEOUT_MS_CONFIG** (1000 ms by default).

Viewing Consumer Offsets (Console)

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.


Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Consumer Groups**.

Step 7 Click the name of the desired consumer group.

Step 8 On the **Consumer Offset** tab page, view the list of topics that the consumer group has subscribed to, total number of messages accumulated in the topic, consumption progress in each partition of the topic (number of accumulated messages, offset, latest offset, consumer ID, consumer address, and client ID).

Figure 7-8 Consumer offsets



Topic Name	Partitions	Accumulated Messages	Operation
topic-ldp	3	1	Reset Consumer Offset

Partition	Accumulated Mes...	Offset	Latest Offset	ID	Address	Client ID	Operation
0	0	98	98	--	--	--	Reset Consumer Offset
1	1	101	102	--	--	--	Reset Consumer Offset
2	0	60	60	--	--	--	Reset Consumer Offset

Step 9 (Optional) To query the consumer offsets of a specific topic, enter the topic name in the search box and press **Enter**.

----End

Viewing Consumer Offsets (Kafka CLI)

- For a Kafka instance with ciphertext access disabled, run the following command in the **/bin** directory of the Kafka client:

```
./kafka-consumer-groups.sh --bootstrap-server ${connection-address} --offsets --describe --all-groups
```

Parameter description: **connection-address** indicates the Kafka instance address, which can be obtained in the **Connection** area on the **Basic Information** page on the Kafka console.

Example:

```
[root@ecs-kafka bin]# ./kafka-consumer-groups.sh --bootstrap-server
192.168.xx.xx:9092,192.168.xx.xx:9092,192.168.xx.xx:9092 --offsets --describe --all-groups
```

Consumer group '__consumer-group-dial-test' has no active members.

GROUP	TOPIC	PARTITION	CURRENT-OFFSET	LOG-END-OFFSET	LAG
CONSUMER-ID	HOST	CLIENT-ID			
__consumer-group-dial-test	__dms_dial_test	0	350	350	0
-	-	-	-	-	-
__consumer-group-dial-test	__dms_dial_test	1	350	350	0
-	-	-	-	-	-
__consumer-group-dial-test	__dms_dial_test	2	350	350	0
-	-	-	-	-	-

Consumer group 'test' has no active members.

GROUP	TOPIC	PARTITION	CURRENT-OFFSET	LOG-END-OFFSET	LAG
CONSUMER-ID	HOST	CLIENT-ID			
test	topic-01	0	5	5	0
test	topic-01	1	3	3	0
test	topic-01	2	10	10	0

```
[root@ecs-kafka bin]#
```

- For a Kafka instance with ciphertext access enabled, do as follows:
 - (Optional) Modify the client configuration file.

View **Security Protocol** in the **Connection** area on the **Basic Information** page on the Kafka console. The configuration settings vary depending on the protocol.

- SASL_PLAINTEXT**: Skip this step and go to **b** if the username and password are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_PLAINTEXT
# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
# If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description: **username** and **password** are the ones you set when enabling ciphertext access for the first time or when creating a user.

- SASL_SSL**: Skip this step and go to **b** if the username, password, and SSL certificate are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```

security.protocol=SASL_SSL
ssl.truststore.location={ssl_truststore_path}
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sas.l.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sas.l.mechanism=SCRAM-SHA-512
# If the SASL mechanism is PLAIN, configure as follows:
sas.l.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sas.l.mechanism=PLAIN
    
```

Parameter description:

- **ssl.truststore.location:** path for storing the **client.jks** certificate. Even in Windows, you need to use slashes (/) for the certificate path. Do not use backslashes (\), which are used by default for paths in Windows. Otherwise, the client will fail to obtain the certificate.
 - **ssl.truststore.password** is certified by the server, which must be set to **dms@kafka** and cannot be changed.
 - **ssl.endpoint.identification.algorithm:** whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**
 - **username** and **password:** username and password you set when enabling ciphertext access for the first time or when creating a user.
- b. Run the following command in the **/bin** directory of the Kafka client:

```
./kafka-consumer-groups.sh --bootstrap-server ${connection-address} --offsets --describe --all-groups --command-config ../config/ssl-user-config.properties
```

Parameter description: **connection-address** indicates the Kafka instance address, which can be obtained in the **Connection** area on the **Basic Information** page on the Kafka console.

Example:

```
[root@ecs-kafka bin]# ./kafka-consumer-groups.sh --bootstrap-server
192.168.xx.xx:9093,192.168.xx.xx:9093,192.168.xx.xx:9093 --offsets --describe --all-groups --
command-config ../config/ssl-user-config.properties
```

Consumer group ' __consumer-group-dial-test' has no active members.

GROUP	TOPIC	PARTITION	CURRENT-OFFSET	LOG-END-OFFSET	
LAG	CONSUMER-ID	HOST	CLIENT-ID		
__consumer-group-dial-test	__dms_dial_test	0	347	347	0
-	-	-	-	-	-
__consumer-group-dial-test	__dms_dial_test	1	347	347	0
-	-	-	-	-	-
__consumer-group-dial-test	__dms_dial_test	2	347	347	0
-	-	-	-	-	-

Consumer group 'test' has no active members.

GROUP	TOPIC	PARTITION	CURRENT-OFFSET	LOG-END-OFFSET	LAG
CONSUMER-ID	HOST	CLIENT-ID			
test	topic-01	0	5	5	0
test	topic-01	1	3	3	0
test	topic-01	2	10	10	0

[root@ecs-kafka bin]#

Resetting Consumer Offsets



- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose the **Consumer Groups** tab.
- Step 7** Click the name of the desired consumer group.
- Step 8** On the **Consumer Offset** tab page, you can perform the following operations:
- To reset the consumer offset of all partitions of a single topic, click **Reset Consumer Offset** in the row containing the desired topic.
 - To reset the consumer offset of a single partition of a single topic, click **Reset Consumer Offset** in the row containing the desired partition.
 - To reset the consumer offset in all partitions of all topics, click **Reset Consumer Offset**.
- Step 9** In the displayed **Reset Consumer Offset** dialog box, set the parameters by referring to [Table 7-2](#).

Table 7-2 Parameters for resetting the consumer offset

Parameter	Description
Reset By	You can reset an offset by: <ul style="list-style-type: none"> • Time: Reset the offset to the specified time. • Offset: Reset the offset to the specified position. If you reset offsets in batches, they can only be reset to the specified time.
Time	Set this parameter if Reset By is set to Time . Select a time point. After the reset is complete, retrieval starts from this time point. <ul style="list-style-type: none"> • Earliest: earliest offset • Custom: a custom time point • Latest: latest offset
Offset	Set this parameter if Reset By is set to Offset . Enter an offset, which is greater than or equal to 0. After the reset is complete, retrieval starts from this offset.

- Step 10** Click **OK**.

Step 11 Click **Yes** in the confirmation dialog box. The consumer offset is reset.

----End

7.5 Viewing Kafka Rebalancing Logs

Rebalancing is to reallocate subscription relationships between consumers and topic partitions in a consumer group. During rebalancing, all consumers in the consumer group stop consuming messages until rebalancing completes.

Possible causes of rebalancing:

- The number of consumer group members changes. For example, a new consumer joins the group or a consumer quits the group.
- The number of topics subscribed to by a consumer group changes.
- The number of topic partitions subscribed to by a consumer group changes.

Rebalancing logs record rebalancing details, including the time, reason, and triggering client of rebalancing. This section describes how to view rebalancing logs on the console.

Rebalancing logs are stored and can be queried in Log Tank Service (LTS).

Notes and Constraints


- Rebalancing logging is not available for instances created before April 6, 2023.
- Unavailable for single-node instances.
- Rebalancing logs are stored for seven days by default. To retain them longer, see [Modifying a Log Group](#).
- Enabling rebalancing logging will create a log group, log stream, and dashboard in LTS. Fees are generated based on the log volume. For details, see [LTS pricing details](#).


Prerequisites

- Ensure that you have permissions to create log groups and log streams in LTS.
- Rebalancing logging can be enabled or disabled only when the Kafka instance is in the **Running** state.

Enabling Rebalancing Logging

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.



Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

- Step 6** In the navigation pane, choose **Rebalancing Logs**.
 - Step 7** Click **Enable Logging**. The **Enable Logging** dialog box is displayed.
 - Step 8** Click **OK**. The **Background Tasks** page is displayed. The rebalancing log function is enabled when the rebalancing logging task is in the **Successful** state.
- Enabling rebalancing logging will create a log group and log stream in LTS.
- End

Viewing Rebalancing Logs

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose **Rebalancing Logs**.
- Step 7** On the **Dashboard** tab page, view the number of consumer group rebalancing times and reasons. On the **Logs** tab page, view rebalancing logs.

To search for logs, see [Log Search](#).

An example rebalancing log:

```
{
  "level": "INFO",
  "timestamp": "2023-03-23 17:23:22,906",
  "message": {
    "leaderId": "consumer-1-177817b6-1f29-4717-8a83-dda8eaab1635",
    "generationId": "1",
    "reason": "Assignment received from leader for group KMSocketCache-dms-vm-fa3cf9d6-manager-shared-server-0 for generation 1",
    "groupId": "KMSocketCache-dms-vm-fa3cf9d6-manager-shared-server-0",
    "coordinatorId": "0",
    "type": "END_REBALANCE",
    "group": "GroupMetadata(groupId=KMSocketCache-dms-vm-fa3cf9d6-manager-shared-server-0, generation=1, protocolType=Some(consumer), currentState=CompletingRebalance, members=Map(consumer-1-177817b6-1f29-4717-8a83-dda8eaab1635 -&gt; MemberMetadata(memberId=consumer-1-177817b6-1f29-4717-8a83-dda8eaab1635, clientId=consumer-1, clientHost=/172.31.2.168, sessionTimeoutMs=10000, rebalanceTimeoutMs=300000, supportedProtocols=List(range, )))"
  }
}
```

[Table 7-3](#) describes the parameters.

Table 7-3 Rebalancing parameters


Parameter	Description
level	Level of the rebalancing logs. The only value is INFO .


Parameter	Description
timestamp	Time of rebalancing.
leaderId	Leader consumer ID.
generationId	Generation ID of the consumer group. Generation is the number of times that a consumer group performs rebalancing. It is incremented by 1 each time a rebalancing is complete.
reason	Reason for triggering rebalancing.
groupId	Consumer group ID.
coordinatorId	Broker where the Coordinator component is.
type	Operation that triggered rebalancing. Values: <ul style="list-style-type: none"> ● JOIN_GROUP: A new consumer is added to a consumer group. ● OVER_CAPACITY: The group limit is exceeded. ● UPDATE_MEMBER: The consumer metadata is updated. ● PROTOCOL_CHANGE: The protocol is changed. ● HEARTBEAT_EXPIRED: The consumer heartbeat timed out. ● SYNC_GROUP: The reassignment plan is synchronized. ● END_REBALANCE: Rebalancing ended. ● LEAVE_GROUP: A consumer left a consumer group.
group	Information about consumers in the consumer group.

----End

Disabling Rebalancing Logging

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Rebalancing Logs**.

Step 7 Click **Disable Logging** in the upper right corner. The **Disable Logging** dialog box is displayed.

Step 8 Click **OK**. The **Background Tasks** page is displayed. The rebalancing log function is disabled when the rebalancing logging task is in the **Successful** state.

This only disables the rebalancing logging function. The log groups and log streams on LTS are retained and still generate fees. If you no longer need the logs, delete the **log groups** and **log streams** on LTS.


----End


7.6 Modifying Kafka Consumer Group Description

After creating a consumer group, you can modify its description based on service requirements.

Procedure

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

Step 4 In the navigation pane, choose **Kafka Instances**.

Step 5 Click the desired instance to go to the instance details page.

Step 6 In the navigation pane, choose **Consumer Groups**.

Step 7 In the row containing the consumer group to be edited, click **Edit**.

Step 8 Modify the description and click **OK**.

After the modification is successful, you can view the new description in the **Description** column.


----End


7.7 Exporting Kafka Consumer Groups

You can export a list of consumer groups in a Kafka instance.

Procedure

Step 1 Log in to the console.

Step 2 Click  in the upper left corner to select the region where your instance is located.

Step 3 Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose **Consumer Groups**.
- Step 7** Export consumer groups in either of the following ways:
- Select the desired consumer groups and choose **Export > Export selected data to an XLSX file** to export specified consumer groups.
 - Choose **Export > Export all data to an XLSX file** to export all consumer groups.
- End

7.8 Deleting a Kafka Consumer Group

You can delete a consumer group in either of the following ways:

- On the console.
- Use **Kafka CLI**. (Ensure that the Kafka instance version is the same as the CLI version.)



Notes and Constraints

- If **auto.create.groups.enable** is set to **true**, the consumer group status is **EMPTY**, and no offset has been submitted, the system automatically deletes the consumer group 10 minutes later.
- If **auto.create.groups.enable** is set to **false**, the system does not automatically delete consumer groups. You can manually delete them.
- If a consumer group has never committed an offset, the group will be deleted after the Kafka instance restarts.
- Deleting a consumer group loses the consumption offset. Re-consumption or repeated consumption may occur.

Prerequisite

The status of the consumer group to be deleted is **EMPTY**.

Deleting a Consumer Group on the Console

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose the **Consumer Groups** tab.

Step 7 Delete consumer groups using either of the following methods:

- Select one or more consumer groups and click **Delete Consumer Group** above the consumer group list.
- In the row containing the consumer group to be deleted, click **Delete**.
- Click the consumer group to be deleted. The consumer group details page is displayed. Click **Delete** in the upper right corner.

Step 8 In the displayed **Delete Consumer Group** dialog box, click **OK**.

----End

Using the CLI to Delete a Consumer Group

The following uses Linux as an example.

- For a Kafka instance with ciphertext access disabled, run the following command in the **/bin** directory of the Kafka client:

```
./kafka-consumer-groups.sh --bootstrap-server ${connection-address} --delete --group ${consumer-group-name}
```

Parameter description:

- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **consumer-group-name**: consumer group name.

Example:

```
[root@ecs-kafka bin]# ./kafka-consumer-groups.sh --bootstrap-server 192.168.xx.xx:9092,192.168.xx.xx:9092,192.168.xx.xx:9092 --delete --group group-01
Deletion of requested consumer groups ('group-01') was successful.
[root@ecs-kafka bin]#
```

- For a Kafka instance with ciphertext access enabled, do as follows:

a. (Optional) Modify the client configuration file.

View **Security Protocol** in the **Connection** area on the **Basic Information** page on the Kafka console. The configuration settings vary depending on the protocol.

- **SASL_PLAINTEXT**: Skip this step and go to **b** if the username and password are already set. Otherwise, create the **ssl-user-config.properties** file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_PLAINTEXT
# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
# If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description: **username** and **password** are the ones you set when enabling ciphertext access for the first time or when creating a user.

- **SASL_SSL**: Skip this step and go to **b** if the username, password, and SSL certificate are already set. Otherwise, create the **ssl-user-**

config.properties file in the **/config** directory on the Kafka client and add the following content to the file:

```
security.protocol=SASL_SSL
ssl.truststore.location={ssl_truststore_path}
ssl.truststore.password=dms@kafka
ssl.endpoint.identification.algorithm=
# If the SASL mechanism is SCRAM-SHA-512, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.scram.ScramLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=SCRAM-SHA-512
# If the SASL mechanism is PLAIN, configure as follows:
sasl.jaas.config=org.apache.kafka.common.security.plain.PlainLoginModule required \
username="*****" \
password="*****";
sasl.mechanism=PLAIN
```

Parameter description:

- **ssl.truststore.location**: path for storing the **client.jks** certificate. Even in Windows, you need to use slashes (/) for the certificate path. Do not use backslashes (\), which are used by default for paths in Windows. Otherwise, the client will fail to obtain the certificate.
 - **ssl.truststore.password** is certified by the server, which must be set to **dms@kafka** and cannot be changed.
 - **ssl.endpoint.identification.algorithm**: whether to verify the certificate domain name. **This parameter must be left blank, which indicates disabling domain name verification.**
 - **username** and **password**: username and password you set when enabling ciphertext access for the first time or when creating a user.
- b. In the **/bin** directory of the Kafka client, run the following command:
- ```
./kafka-consumer-groups.sh --bootstrap-server ${connection-address} --delete --group $
{consumer-group-name} --command-config ../config/ssl-user-config.properties
```

Parameter description:

- **connection-address**: can be obtained from the **Connection** area on the **Basic Information** page on the Kafka console.
- **consumer-group-name**: consumer group name.

Example:

```
[root@ecs-kafka bin]# ./kafka-consumer-groups.sh --bootstrap-server
192.168.xx.xx:9093,192.168.xx.xx:9093,192.168.xx.xx:9093 --delete --group group-02 --command-
config ../config/ssl-user-config.properties
Deletion of requested consumer groups ('group-02') was successful.
[root@ecs-kafka bin]#
```

# 8 Managing Quotas

---

## 8.1 Configuring Kafka Quotas

Kafka quotas can be configured for users, clients, or topics to limit the message production or consumption rate.

Rate limits for users and clients work on the entire broker, while topic rate limits work on a specific topic.

### Notes and Constraints

- Available for instances created on or after November 10, 2022.
- This function is unavailable for single-node instances.



### Operation Impact

- When the quota is reached, production/consumption latency increases.
- If the quota is small and the production rate is high, production may time out and messages may be lost. As a result, some messages fail to be produced.
- If the initial production/consumption traffic is heavy, and a small quota is set, the production/consumption latency increases and some messages fail to be produced. To ensure stable production and consumption, you are advised to first set the quota to half the traffic, and then half the quota each time you set it until the target quota is reached. For example, if the initial production traffic is 100 MB/s, you can set the production limit to 50 MB/s first. After production becomes stable, change the production limit to 25 MB/s until the target limit is reached.

### Prerequisites




- To configure user quotas, [enable ciphertext access](#) on the Kafka details page and then obtain the username on the **Users** page on the console.
- To control client traffic, obtain the client ID from the client configuration.
- To control topic traffic, obtain the topic name from the **Topics** page.

## Creating a User or Client Quota

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose **Kafka Quotas > Quotas**.
- Step 7** Click the **User/Client** tab.
- Step 8** In the upper left, click **Create Quota**. The **Create Quota** slide panel is displayed.
- Step 9** Set quota parameters.

**Figure 8-1** Creating a user/client quota

### Create Quota

 Configuring quotas may result in higher request latency, production timeout, and message losses. [Learn more](#) 

Username and client ID cannot be both empty.

Username  [Use Default](#)  
Use Default: The quota applies to all users.

Client ID  [Use Default](#)  
Use Default: The quota applies to all clients.

---

Leave empty to apply no rate limit. However, the production limit and consumption limit cannot be both empty.

Production Limit  (MB/s)

Consumption Limit  (MB/s)



**Table 8-1** Quota parameters

| Parameter         | Description                                                                                                                                                                                                         |
|-------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Username          | Enter the name obtained in <a href="#">Prerequisites</a> . To apply the quota to all users, click <b>Use Default</b> next to <b>Username</b> . After the quota is created, the username cannot be changed.          |
| Client ID         | Enter the client ID obtained in <a href="#">Prerequisites</a> . To apply the quota to all clients, click <b>Use Default</b> next to <b>Client ID</b> . After the quota is created, the client ID cannot be changed. |
| Production Limit  | Set an upper limit on the production rate. The unit is MB/s. If this parameter is left blank, no limit is set.                                                                                                      |
| Consumption Limit | Set an upper limit on the consumption rate. The unit is MB/s. If this parameter is left blank, no limit is set.                                                                                                     |

**NOTE**


- **Username** is not displayed in the **Create Quota** dialog box for instances with ciphertext access disabled.
- **Username** and **Client ID** cannot be both empty.
- **Production Limit** and **Consumption Limit** cannot be both empty.

**Step 10** Click **OK**. The **Background Tasks** page is displayed. If the status of the quota creation task is **Successful**, the quota has been created.

Go to the **Kafka Quotas > Quotas** page. On the **User/Client** tab page, view the created quota in either of the following ways.



- For instances with ciphertext access disabled: Enter the name of the created quota in the search box and press **Enter**.
- For instances with ciphertext access enabled: Click **User quotas**, **Client quotas**, or **User and client quotas** in the upper left corner, select the type of the new quota, enter the quota name in the search box, and press **Enter**.

**Figure 8-2** Viewing the new quota



----End

## Creating a Topic Quota

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose **Kafka Quotas > Quotas**.
- Step 7** Click the **Topic** tab.
- Step 8** In the upper left, click **Create Quota**. The **Create Quota** slide panel is displayed.
- Step 9** Set quota parameters.

**Figure 8-3** Creating a topic quota

### Create Quota

⚠ Configuring quotas may result in higher request latency, production timeout, and message losses. [Learn more](#) ✕

★ Topic Name

---

Leave empty to apply no rate limit. However, the production limit and consumption limit cannot be both empty.

Production Limit  (MB/s)

Consumption Limit  (MB/s)

**Table 8-2** Quota parameters

| Parameter         | Description                                                                                                     |
|-------------------|-----------------------------------------------------------------------------------------------------------------|
| Topic Name        | Enter the name of the topic to apply the quota to. After the quota is created, the topic cannot be changed.     |
| Production Limit  | Set an upper limit on the production rate. The unit is MB/s. If this parameter is left blank, no limit is set.  |
| Consumption Limit | Set an upper limit on the consumption rate. The unit is MB/s. If this parameter is left blank, no limit is set. |

 NOTE

**Production Limit** and **Consumption Limit** cannot be both empty.


**Step 10** Click **OK**. The **Background Tasks** page is displayed. If the status of the quota creation task is **Successful**, the quota has been created.


Go to the **Kafka Quotas > Quotas** page. On the **Topic** tab page, enter the name of the new quota in the search box, then press **Enter** to view the created quota.

----End

## Modifying a Quota

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Kafka Quotas > Quotas**.

**Step 7** In the row containing the desired quota, click **Edit**.

**Step 8** Change the production limit or consumption limit, and click **OK**. The **Background Tasks** page is displayed. If the status of the quota modification task is **Successful**, the quota has been modified.

Choose **Kafka Quotas > Quotas** and view the new production or consumption rate limit.


 NOTE


**Production Limit** and **Consumption Limit** cannot be both empty.

----End

## Exporting Quotas

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Kafka Quotas > Quotas**.


**Step 7** Export quotas.


- For specified user/client quotas: On the **User/Client** tab page, select desired user/client quotas and choose **Export > Export selected data to an XLSX file**.
- For all user/client quotas: On the **User/Client** tab page, choose **Export > Export all data to an XLSX file**.
- For specified topic quotas: On the **Topic** tab page, select desired topic quotas and choose **Export > Export selected data to an XLSX file**.
- For all topic quotas: On the **Topic** tab page, choose **Export > Export all data to an XLSX file**.

----End

## Deleting a Quota

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Kafka Quotas > Quotas**.

**Step 7** In the row containing the desired quota, click **Delete**.

**Step 8** Click **OK**. The **Background Tasks** page is displayed. If the status of the quota deletion task is **Successful**, the quota has been deleted.

----End

## 8.2 Monitoring Kafka Quotas


If quotas have been configured for a Kafka instance, the bandwidth usage by user/client/topic of each broker under certain quota policies can be viewed on the console.


### Notes and Constraints

Unavailable for single-node instances.

### Viewing Bandwidth Usage

**Step 1** Log in to the console.


**Step 2** Click  in the upper left corner to select the region where your instance is located.

- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose **Kafka Quotas > Quota Monitoring**.
- Step 7** Set the parameters to query bandwidth usage.

**Table 8-3** Bandwidth usage query parameters

| Parameter      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Search By      | Specify the criteria by which the bandwidth usage is to be searched. <ul style="list-style-type: none"> <li>● <b>Ranked:</b> Show the specified number of users, clients, or topics that have used the most bandwidth.</li> <li>● <b>Bandwidth:</b> Show users, clients, or topics whose bandwidth rate is higher than your specified value.</li> <li>● <b>Bandwidth usage:</b> Show users, clients, or topics whose bandwidth usage is higher than your specified percentage.</li> </ul> |
| Bandwidth From | Specify the bandwidth usage data source. <ul style="list-style-type: none"> <li>● <b>Production:</b> Count production bandwidth usage.</li> <li>● <b>Consumption:</b> Count consumption bandwidth usage.</li> </ul>                                                                                                                                                                                                                                                                       |
| Dimension      | Specify the bandwidth usage data dimension. <ul style="list-style-type: none"> <li>● <b>User/Client:</b> Count user/client bandwidth usage.</li> <li>● <b>Topic:</b> Count topic bandwidth usage.</li> </ul>                                                                                                                                                                                                                                                                              |

**Figure 8-4** Bandwidth usage parameters



- Step 8** Click **Search** to view the bandwidth usage of users, clients, and topics of each broker.

----End

# 9 Managing Instances

---

## 9.1 Viewing and Modifying Basic Information of a Kafka Instance

After creating a Kafka instance, you can view the details or modify some parameters of it on the console as required. These parameters include the instance name, description, security group, and capacity threshold policy.

### Notes and Constraints


Single-node instances do not support reconfiguration of Smart Connect and private network access.


### Prerequisite

You can modify basic information of a Kafka instance when the instance is in the **Running** state.

### Viewing Kafka Instance Details

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** You can filter Kafka instances by tag, status, name, version, flavor, used/available storage space, maximum partitions, billing mode, and enterprise project. Only enterprise users can filter instances by enterprise projects. For Kafka instance statuses, see [Table 9-1](#).

**Table 9-1** Kafka instance status description

| Status          | Description                                                                                                                                                                                          |
|-----------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Creating        | The instance is being created.                                                                                                                                                                       |
| Creation failed | The instance failed to be created.                                                                                                                                                                   |
| Running         | The instance is running properly.<br>Only instances in the <b>Running</b> state can provide services.                                                                                                |
| Faulty          | The instance is not running properly.                                                                                                                                                                |
| Starting        | The status between <b>Frozen</b> and <b>Running</b> .                                                                                                                                                |
| Restarting      | The instance is being restarted.                                                                                                                                                                     |
| Changing        | The instance specifications or public access configurations are being modified.                                                                                                                      |
| Change failed   | The instance specifications or public access configurations failed to be modified.<br>You cannot restart, delete, or modify an instance in the <b>Change failed</b> state. Contact customer service. |
| Frozen          | The instance is frozen.                                                                                                                                                                              |
| Freezing        | The status between <b>Running</b> and <b>Frozen</b> .                                                                                                                                                |
| Upgrading       | The instance is being upgraded.                                                                                                                                                                      |
| Rolling back    | The instance is being rolled back.                                                                                                                                                                   |
| Binning         | The instance is being moved to the recycle bin.                                                                                                                                                      |
| Binned          | The instance is in the recycle bin.                                                                                                                                                                  |
| Recovering      | The instance is being recovered from the recycle bin.                                                                                                                                                |

**Step 6** Click the name of the desired Kafka instance and view detailed information about the instance on the **Basic Information** tab page.

**Table 9-2** and **Table 9-3** describe the parameters for connecting to a Kafka instance. For details about other parameters, see the **Basic Information** tab page of the Kafka instance on the console.

**Table 9-2** Connection parameters (SASL\_SSL cannot be changed)

| Section    | Parameter | Description                                                |
|------------|-----------|------------------------------------------------------------|
| Connection | Username  | Username for accessing the instance with SASL_SSL enabled. |

| Section | Parameter                          | Description                                                                                                                                                                                                 |
|---------|------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|         | Kafka SASL_SSL                     | Whether SASL_SSL is enabled.<br>This function is unavailable for single-node instances.                                                                                                                     |
|         | Security Protocol                  | Security protocol used by the instance with SASL_SSL enabled.                                                                                                                                               |
|         | SASL Mechanism                     | SASL mechanism used by the instance with SASL_SSL enabled.                                                                                                                                                  |
|         | SSL Certificate                    | Click <b>Download</b> to download the SSL certificate for accessing the instance.                                                                                                                           |
|         | Instance Address (Private Network) | Address for connecting to the instance when public access is disabled.<br>The number of connection addresses is the same as that of brokers.                                                                |
|         | Manager Address (Private Network)  | Address for connecting to Kafka Manager when public access is disabled.<br>Instances created since May 17, 2023 do not have this address.                                                                   |
|         | Manager Username                   | Username for connecting to Kafka Manager.<br>Instances created since May 17, 2023 do not have this username.                                                                                                |
|         | Public Access                      | Indicates whether public access has been enabled for the instance.                                                                                                                                          |
|         | Instance Address (Public Network)  | Address for connecting to the instance when public access is enabled.<br>This parameter is displayed only when public access is enabled.                                                                    |
|         | Manager Address (Public Network)   | Address for connecting to Kafka Manager when public access is enabled.<br>This parameter is displayed only when public access is enabled.<br>Instances created since May 17, 2023 do not have this address. |
|         | Intra-VPC Plaintext Access         | Whether intra-VPC plaintext access is enabled.                                                                                                                                                              |





**Table 9-3** Connection parameters (plaintext and ciphertext access)

| Section    | Parameter              | Sub-Parameter                         | Description                                                         |                                                                                                                                                                                      |
|------------|------------------------|---------------------------------------|---------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Connection | Username               | -                                     | Username for accessing the instance with ciphertext access enabled. |                                                                                                                                                                                      |
|            | Private Network Access | Plaintext Access                      |                                                                     | Indicates whether plaintext access is enabled.                                                                                                                                       |
|            |                        | Address (Private Network, Plaintext)  |                                                                     | This parameter is displayed only after you enable <b>Plaintext Access</b> .                                                                                                          |
|            |                        | Ciphertext Access                     |                                                                     | Indicates whether ciphertext access is enabled.<br>This function is unavailable for single-node instances.                                                                           |
|            |                        | Address (Private Network, Ciphertext) |                                                                     | This parameter is displayed only after you enable <b>Ciphertext Access</b> .                                                                                                         |
|            |                        | Security Protocol                     |                                                                     | This parameter is displayed only after you enable <b>Ciphertext Access</b> .                                                                                                         |
|            | Public Network Access  | Toggle switch                         |                                                                     | Indicates whether public access has been enabled.                                                                                                                                    |
|            |                        | Plaintext Access                      |                                                                     | This parameter is displayed only when <b>Public Access</b> is enabled.<br>Indicates whether plaintext access is enabled.                                                             |
|            |                        | Address (Public Network, Plaintext)   |                                                                     | This parameter is displayed only after you enable <b>Plaintext Access</b> .                                                                                                          |
|            |                        | Ciphertext Access                     |                                                                     | This parameter is displayed only when <b>Public Access</b> is enabled.<br>Indicates whether ciphertext access is enabled.<br>This function is unavailable for single-node instances. |
|            |                        | Address (Public Network, Ciphertext)  |                                                                     | This parameter is displayed only after you enable <b>Ciphertext Access</b> .                                                                                                         |





| Section | Parameter       | Sub-Parameter     | Description                                                                                                                                     |
|---------|-----------------|-------------------|-------------------------------------------------------------------------------------------------------------------------------------------------|
|         |                 | Security Protocol | This parameter is displayed only after you enable <b>Ciphertext Access</b> .                                                                    |
|         | SASL Mechanism  | -                 | This parameter is displayed only after you enable <b>Ciphertext Access</b> .                                                                    |
|         | SSL Certificate | -                 | This parameter is displayed only when SASL_SSL is enabled.<br>Click <b>Download</b> to download the SSL certificate for accessing the instance. |





----End

## Modifying Basic Information of a Kafka Instance

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** Modify the following parameters if needed:

**Table 9-4** Modifiable Kafka parameters

| Parameter     | How to Modify                                                                                                                                                                                                                                                                                                                             | Result                                                                                        |
|---------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------|
| Instance Name | Click  , enter a new name, and click  .<br>Naming rules: 4–64 characters; starts with a letter; can contain only letters, digits, hyphens (-), and underscores (_). | The modification result is displayed in the upper right corner of the page.                   |
| Smart Connect | See <a href="#">Enabling Smart Connect</a> and <a href="#">Disabling Smart Connect</a> .                                                                                                                                                                                                                                                  | To check the progress and result of the current task, go to the <b>Background Tasks</b> page. |
| Description   | Click  , enter a new description, and click  .<br>0 to 1024 characters.                                                                                             | The modification result is displayed in the upper right corner of the page.                   |

| Parameter                 | How to Modify                                                                                                                                                                                                                                                                                                                                   | Result                                                                                                           |
|---------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------|
| Enterprise Project        | <p>Click , select a new enterprise project from the drop-down list, and click .</p> <p>Only for enterprise users. Modifying this parameter does not restart the instance.</p> | The modification result is displayed in the upper right corner of the page.                                      |
| Security Group            | <p>Click , select a new security group from the drop-down list, and click .</p> <p>Modifying this parameter does not restart the instance.</p>                                | The modification result is displayed in the upper right corner of the page.                                      |
| Private Network Access    | See <a href="#">Configuring Plaintext or Ciphertext Access to Kafka Instances</a> .                                                                                                                                                                                                                                                             | You will be redirected to the <b>Background Tasks</b> page, which displays the modification progress and result. |
| Public Access             | See <a href="#">Configuring Kafka Public Access</a> .                                                                                                                                                                                                                                                                                           | You will be redirected to the <b>Background Tasks</b> page, which displays the modification progress and result. |
| Capacity Threshold Policy | <p>Click the desired policy. In the displayed <b>Confirm</b> dialog box, click <b>OK</b>.</p> <p>Modifying this parameter does not restart the instance.</p> <p>When the policies are triggered, messages may be deleted or cannot be produced.</p>                                                                                             | You will be redirected to the <b>Background Tasks</b> page, which displays the modification progress and result. |
| Automatic Topic Creation  | <p>Enable/Disable this <b>Automatic Topic Creation</b>. In the displayed <b>Confirm</b> dialog box, click <b>OK</b>.</p> <p>Changing this option may restart the instance.</p>                                                                                                                                                                  | You will be redirected to the <b>Background Tasks</b> page, which displays the modification progress and result. |
| Cross-VPC Access          | See <a href="#">Accessing Kafka Using a VPC Endpoint Across VPCs</a> and <a href="#">Accessing Kafka in a Public Network Using DNAT</a> .                                                                                                                                                                                                       | The modification result is displayed in the upper right corner of the page.                                      |

----End



## 9.2 Viewing Kafka Disk Usage

This section describes how to view the disk usage of each broker of a Kafka instance on the console.

### Notes and Constraints

Unavailable for single-node instances.


### Procedure

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click a Kafka instance to go to the **Basic Information** page.
- Step 6** Go to the **Disk Usage Statistics** page.

You can query topics that use the most disk space or topics that have used a specified amount or percentage of disk space.

In the upper right corner of the page, click **View Metric**. On the displayed Cloud Eye page, you can view metrics of Kafka instances.

**Figure 9-1** Viewing disk usage



----End



## 9.3 Viewing Kafka Background Tasks

After you initiate certain instance operations listed in [Table 9-5](#), a background task will start for each operation. On the console, you can view the background task status and clear task information by deleting task records.


**Table 9-5** Backend task list

| Task Name                        | Description                                                                                                                                                                                                           |
|----------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Creating an instance             | Creates a Kafka instance.                                                                                                                                                                                             |
| Restart Instance                 | Restarts a Kafka instance.                                                                                                                                                                                            |
| Modifying Kafka parameters       | <ul style="list-style-type: none"><li>• Modifies configuration parameters of Kafka.</li><li>• Enables/Disables automatic topic creation.</li></ul>                                                                    |
| Change capacity threshold policy | Changes capacity threshold policies for a Kafka instance.                                                                                                                                                             |
| Enabling or disabling SSL        | Switches between plaintext and ciphertext access.                                                                                                                                                                     |
| Configure public network access  | Enables/Disables public access.                                                                                                                                                                                       |
| Enable Smart Connect             | Enables Smart Connect.                                                                                                                                                                                                |
| Disable Smart Connect            | Disables Smart Connect.                                                                                                                                                                                               |
| Modify Specifications            | <ul style="list-style-type: none"><li>• Expands the storage space.</li><li>• Adds brokers.</li><li>• Increases the bandwidth.</li><li>• Increases the broker flavor.</li><li>• Decreases the broker flavor.</li></ul> |
| Create Quota                     | Creates user/client/topic quotas.                                                                                                                                                                                     |
| Modify Quota                     | Modifies quotas.                                                                                                                                                                                                      |
| Delete Quota                     | Deletes user/client/topic quotas.                                                                                                                                                                                     |
| Kafka partition reassignment     | Reassigns partitions of a topic.                                                                                                                                                                                      |
| Enable logging                   | Enables rebalancing logging.                                                                                                                                                                                          |
| Disable logging                  | Disables rebalancing logging.                                                                                                                                                                                         |
| Configure topic permission       | Grants permissions to users in a topic.                                                                                                                                                                               |

## Procedure

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click a Kafka instance to go to the **Basic Information** page.
- Step 6** In the navigation pane, choose **Background Tasks**.
- Step 7** On the Background Tasks or Scheduled Tasks tab page, click the time drop-down list, specify a time range, enter a keyword in the search box, and press **Enter**. The tasks started within the specified time range are displayed.

On the **Background Tasks** page, you can also perform the following operations:

- Click  to refresh the task status.
- Click **Delete**. In the displayed **Delete Task** dialog box, click **OK** to clear the task information.



You can only delete the records of tasks in the **Successful**, **Failed**, or **Canceled** state.

----End

## 9.4 Viewing Sample Code of Kafka Production and Consumption

Distributed Message Service for Kafka allows you to view sample Java, Go, and Python code of producing and consuming messages on the console. You can quickly complete Kafka client integration.

### Procedure

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Click the desired instance to go to the instance details page.
- Step 6** In the navigation pane, choose **Topics**.
- Step 7** Click **View Sample Code**. The **Sample Code** dialog box is displayed.

The sample code is available in Java, Go, and Python, and PlainText, SASL\_SSL, and SASL\_PLAINTEXT access modes.

- PlainText: Accessing the Kafka instance in plaintext.
- SASL\_SSL: Accessing the Kafka instance in ciphertext with SASL authentication. SASL authentication uses PLAIN or SCRAM-SHA-512.
- SASL\_PLAINTEXT: Accessing the Kafka instance in plaintext with SASL authentication. SASL authentication uses PLAIN or SCRAM-SHA-512.

----End

## 9.5 Modifying Kafka Instance Configuration Parameters

Your Kafka instances, topics, and consumers come with default configuration parameter settings. You can modify common parameters on the Kafka console. For details about parameters that are not listed on the console, see the [Kafka official website](#).

Kafka instances have dynamic and static parameters:

- Dynamic parameters: Modifying dynamic parameters will not restart the instance.
- Static parameters: After static parameters are modified, you must manually restart the instance.

### Notes and Constraints


- Configuration parameters of some old instances cannot be modified. Check whether your instance parameters can be modified on the console. If they cannot be modified, contact customer service.
- This function is not available for single-node instances.


### Prerequisites

You can modify configuration parameters of a Kafka instance when the instance is in the **Running** state.

### Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** On the **Parameters** page, click **Edit** in the row containing the parameter to modify.

Parameters of v1.1.0 instances are described in [Table 9-6](#) and [Table 9-7](#).

Parameters of v2.3.0/v2.7/v3.x instances are described in [Table 9-8](#) and [Table 9-9](#).

**Table 9-6** Dynamic parameters (v1.1.0 instances)

| Parameter                 | Description                                                                                                                                                                                                                                                                                                                          | Value Range                  | Default Value |
|---------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------|---------------|
| auto.create.groups.enable | Whether to automatically create consumer groups.<br>You can modify this parameter on the console only for instances created on or after April 25, 2023. For instances created before April 25, 2023, the function of automatically creating consumer groups is enabled by default and cannot be disabled on the console.             | true or false                | true          |
| offsets.retention.minutes | The longest period a consumption position can be retained starts from the time of submission. Positions retained beyond this duration will be deleted. Each time a consumption position is submitted to a topic partition, its retention period resets to 0.<br>This is a static parameter for instances created before May 1, 2023. | 1,440–30,240<br>Unit: minute | 20,160        |

**Table 9-7** Static parameters (v1.1.0 instances)

| Parameter           | Description                                                                                                                                                                                                                     | Value Range                | Default Value |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------|---------------|
| min.insync.replicas | If a producer sets the acks parameter to <b>all</b> (or <b>-1</b> ), the <b>min.insync.replicas</b> parameter specifies the minimum number of replicas that must acknowledge a write for the write to be considered successful. | 1–3                        | 1             |
| message.max.bytes   | Maximum length of a single message.                                                                                                                                                                                             | 0–10,485,760<br>Unit: byte | 10,485,760    |



| Parameter                      | Description                                                                                                                                                                                               | Value Range                          | Default Value |
|--------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------|---------------|
| unclean.leader.election.enable | Indicates whether to allow replicas not in the ISR set to be elected as the leader as a last resort, even though doing so may result in data loss.                                                        | <b>true</b> or <b>false</b>          | false         |
| connections.max.idle.ms        | Idle connection timeout (in ms). Connections that are idle for the duration specified by this parameter will be closed.                                                                                   | 5,000–600,000<br>Unit: millisecond   | 600,000       |
| log.retention.hours            | Maximum duration for storing log files.<br><br>This parameter takes effect only for topics that have no aging time configured. If there is aging time configured for topics, it overrides this parameter. | 1–168<br>Unit: hour                  | 72            |
| max.connections.per.ip         | The maximum number of connections allowed from each IP address. Request for new connections will be rejected once the limit is reached.                                                                   | 100–20,000                           | 1000          |
| group.max.session.timeout.ms   | Maximum session timeout for consumers. A longer timeout gives consumers more time to process messages between heartbeats but results in a longer time to detect failures.                                 | 6,000–1,800,000<br>Unit: millisecond | 1,800,000     |
| default.replication.factor     | The default number of replicas configured for an automatically created topic.                                                                                                                             | 1–3                                  | 3             |

| Parameter                      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | Value Range                        | Default Value |
|--------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------|---------------|
| allow.everyone.if.no.acl.found | <ul style="list-style-type: none"> <li>When this parameter is set to <b>true</b>, all users can access resources without ACL rules.</li> <li>When this parameter is set to <b>false</b>, the initial user has all the permissions and other users require authorization. All the permissions cover modifying a topic, creating and deleting a topic, and changing the number of topic partitions.</li> </ul> <p>This parameter is displayed only when ciphertext access is enabled for the instance.</p> <p>This parameter cannot be modified for instances created before September 15, 2023.</p> | <b>true</b> or <b>false</b>        | true          |
| num.partitions                 | The default number of partitions configured for each automatically created topic.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  | 1–200                              | 3             |
| group.min.session.timeout.ms   | Minimum session timeout for consumers. A shorter timeout enables quicker failure detection but results in more frequent consumer heartbeating, which can overwhelm broker resources.                                                                                                                                                                                                                                                                                                                                                                                                               | 6,000–300,000<br>Unit: millisecond | 6,000         |

**Table 9-8** Dynamic parameters (v2.3.0/v2.7/v3.x)

| Parameter           | Description                                                                                                                                                                                                                     | Value Range                | Default Value |
|---------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------|---------------|
| min.insync.replicas | If a producer sets the acks parameter to <b>all</b> (or <b>-1</b> ), the <b>min.insync.replicas</b> parameter specifies the minimum number of replicas that must acknowledge a write for the write to be considered successful. | 1–3                        | 1             |
| message.max.bytes   | Maximum length of a single message.                                                                                                                                                                                             | 0–10,485,760<br>Unit: byte | 10,485,760    |

| Parameter                      | Description                                                                                                                                                                                                                                                                                                                          | Value Range                  | Default Value |
|--------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------|---------------|
| auto.create.groups.enable      | Whether to automatically create consumer groups.<br>You can modify this parameter on the console only for instances created on or after April 25, 2023. For instances created before April 25, 2023, the function of automatically creating consumer groups is enabled by default and cannot be disabled on the console.             | true or false                | true          |
| max.connections.per.ip         | The maximum number of connections allowed from each IP address. Request for new connections will be rejected once the limit is reached.                                                                                                                                                                                              | 100–20,000                   | 1000          |
| unclean.leader.election.enable | Indicates whether to allow replicas not in the ISR set to be elected as the leader as a last resort, even though doing so may result in data loss.                                                                                                                                                                                   | true or false                | false         |
| offsets.retention.minutes      | The longest period a consumption position can be retained starts from the time of submission. Positions retained beyond this duration will be deleted. Each time a consumption position is submitted to a topic partition, its retention period resets to 0.<br>This is a static parameter for instances created before May 1, 2023. | 1,440–30,240<br>Unit: minute | 20,160        |

**Table 9-9** Static parameters (v2.3.0/v2.7/v3.x)

| Parameter               | Description                                                                                                             | Value Range                        | Default Value |
|-------------------------|-------------------------------------------------------------------------------------------------------------------------|------------------------------------|---------------|
| connections.max.idle.ms | Idle connection timeout (in ms). Connections that are idle for the duration specified by this parameter will be closed. | 5,000–600,000<br>Unit: millisecond | 600,000       |

| Parameter                      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        | Value Range                          | Default Value |
|--------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------|---------------|
| log.retention.hours            | Maximum duration for storing log files.<br><br>This parameter takes effect only for topics that have no aging time configured. If there is aging time configured for topics, it overrides this parameter.                                                                                                                                                                                                                                                                                                                                                                                          | 1–168<br>Unit: hour                  | 72            |
| group.max.session.timeout.ms   | Maximum session timeout for consumers. A longer timeout gives consumers more time to process messages between heartbeats but results in a longer time to detect failures.                                                                                                                                                                                                                                                                                                                                                                                                                          | 6,000–1,800,000<br>Unit: millisecond | 1,800,000     |
| default.replication.factor     | The default number of replicas configured for an automatically created topic.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      | 1–3                                  | 3             |
| allow.everyone.if.no.acl.found | <ul style="list-style-type: none"> <li>When this parameter is set to <b>true</b>, all users can access resources without ACL rules.</li> <li>When this parameter is set to <b>false</b>, the initial user has all the permissions and other users require authorization. All the permissions cover modifying a topic, creating and deleting a topic, and changing the number of topic partitions.</li> </ul> <p>This parameter is displayed only when ciphertext access is enabled for the instance.</p> <p>This parameter cannot be modified for instances created before September 15, 2023.</p> | <b>true</b> or <b>false</b>          | true          |
| num.partitions                 | The default number of partitions configured for each automatically created topic.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  | 1–200                                | 3             |
| group.min.session.timeout.ms   | Minimum session timeout for consumers. A shorter timeout enables quicker failure detection but results in more frequent consumer heartbeating, which can overwhelm broker resources.                                                                                                                                                                                                                                                                                                                                                                                                               | 6,000–300,000<br>Unit: millisecond   | 6,000         |

 **NOTE**

- To modify multiple dynamic or static parameters at a time, click **Modify** above the parameter list.
- If you want to restore the default values, click **Restore Default** in the row containing the desired parameter.

**Step 7** Click **Save**.

Modifying dynamic parameters will not restart the instance. Static parameter modification requires **manual restart** of the instance.

----End

## 9.6 Configuring Kafka Instance Tags

Tags facilitate Kafka instance identification and management.

You can add tags to a Kafka instance when creating the instance or add tags on the **Tags** tab page of the created instance. Up to 20 tags can be added to an instance. Tags can be deleted.

If your organization has configured tag policies for DMS for Kafka, add tags to Kafka instances based on the tag policies. If a tag added on the **Tags** page does not comply with the tag policies, the tag fails to be added.


A tag consists of a tag key and a tag value. [Table 9-10](#) lists the tag key and value requirements.


**Table 9-10** Tag key and value requirements

| Parameter | Requirements                                                                                                                                                                                                                                                                                                                                                           |
|-----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Tag key   | <ul style="list-style-type: none"> <li>• Cannot be left blank.</li> <li>• Must be unique for the same instance.</li> <li>• Can contain 1 to 128 characters.</li> <li>• Can contain letters, digits, spaces, and special characters <code>_ . : = + - @</code></li> <li>• Cannot start or end with a space.</li> <li>• Cannot start with <code>_sys_</code>.</li> </ul> |
| Tag value | <ul style="list-style-type: none"> <li>• Can contain 0 to 255 characters.</li> <li>• Can contain letters, digits, spaces, and special characters <code>_ . : = + - @</code></li> <li>• Cannot start or end with a space in instance creation.</li> </ul>                                                                                                               |

## Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.


**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane on the left, choose **Tags**.

View the tags of the instance.

**Step 7** Perform the following operations as required:

- Add a tag
  - a. Click **Create/Delete Tag**.
  - b. Enter a tag key and a tag value, and click **Add**.  
If you have predefined tags, select a predefined pair of tag key and value, and click **Add**.
  - c. Click **OK**.
- Delete a tag  
Delete a tag using either of the following methods:
  - In the row containing the tag to be deleted, click **Delete**. In the **Delete Tag** dialog box, click **Yes**.
  - Click **Create/Delete Tag**. In the dialog box that is displayed, click  next to the tag to be deleted and click **OK**.  
You can delete up to **19** tags in this way.
  - Select one or more tags and click **Delete** above. The **Delete Tag** dialog box is displayed. Click **OK**.

----End

## 9.7 Configuring Kafka Recycling Policies

If recycling is enabled, deleted instances and their data are retained in Recycle Bin, and can be recovered during the retention period. Once the retention period expires, instances in Recycle Bin will be deleted permanently.

Recycling is disabled by default.


### Notes and Constraints


- Pay-per-use instance in Recycle Bin will not generate fees, but their storage will.
- Yearly/Monthly instances will be moved to Recycle Bin upon unsubscription. After that, they will not generate fees, but their storage will.

- Yearly/Monthly instances will be changed to pay-per-use ones upon successful recovery.
- Removing or unsubscribing instances in the grace or retention period deletes them permanently.
- Available in the CN North-Beijing4, CN East-Shanghai1, and CN South-Guangzhou regions.

## Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Recycle Bin**.


**Step 5** Click **Modify Recycling Policy** and the **Modify Recycling Policy** dialog box is displayed.


**Step 6** Enable **Recycle Bin**, specify **Retention Days** (1–7), and click **OK**.

----End

## Recovering Kafka Instances

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Recycle Bin**.

**Step 5** Recover Kafka instances using either of the following methods:

- Select one or more Kafka instances and click **Recover** in the upper left corner.
- In the row containing the desired Kafka instance, click **Recover**.

**Step 6** In the displayed **Recover Instance** dialog box, click **OK**.

It takes 3 to 10 minutes to recover an instance. You can view recovered instances on the DMS for Kafka page.


### NOTE


Yearly/Monthly instances will be changed to pay-per-use ones upon successful recovery.

----End

## Modifying Retention Days

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Recycle Bin**.

**Step 5** Click **Modify Recycling Policy** and the **Modify Recycling Policy** dialog box is displayed.


**Step 6** Modify the retention days (1-7) and click **OK**.


Changes to the retention period apply only to instances deleted after the changes.

----End

## Exporting Instances in the Recycle Bin

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Recycle Bin**.


**Step 5** Export the instance list using either of the following methods:


- Select the desired instances and choose **Export > Export selected data to an XLSX file** to export specified instances.
- Choose **Export > Export all data to an XLSX file** to export all instances.

----End

## Deleting Instances Permanently

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Recycle Bin**.

**Step 5** Delete instances using either of the following methods:

- Select one or more Kafka instances and click **Delete** in the upper left corner.



- In the row containing the Kafka instance to be deleted, click **Delete**.


**Step 6** In the displayed **Delete Instance** dialog box, enter **DELETE** and click **OK**.


Deleting a Kafka instance in the recycle bin will **clear the instance data without any backup**. Exercise caution.

----End

## Disabling Recycling

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Recycle Bin**.

**Step 5** Click **Modify Recycling Policy** and the **Modify Recycling Policy** dialog box is displayed.

**Step 6** Disable **Recycle Bin** and click **OK**.

----End

## 9.8 Upgrading the Kafka Instance Kernel

Upgrade your Kafka instance kernel to use the latest kernel version. A kernel upgrade adds certain new features and resolves certain earlier issues. For example, new features may include consumer group creation on the console and topic details viewing.

Kafka instance kernel upgrades have no impact on the Kafka version. For example, if you use Kafka 2.7, you will still be using it after a kernel upgrade.

### Impact of Kernel Upgrades

- Single-replica topics do not support message production and consumption during an upgrade, which will cause service interruptions.
- If a topic has multiple replicas, such upgrades will not interrupt services, but may cause disorder of partition messages. Evaluate this impact and avoid peak hours.
- Brokers will be upgraded one by one. The software package and data of each broker will be updated. Upgrading the software package takes about 5 minutes. Synchronizing the data takes longer as the data volume of other brokers' leader replica becomes larger. Total upgrade duration = Software package upgrade duration of each broker + Data synchronization duration
- The monitoring process is restarted and the monitoring data is lost for each broker during the upgrade. The monitoring continues after the restart is complete.

- During an upgrade, broker restarts will cause partition leader switches, interrupting connections in seconds. The switch takes less than a minute when networks are stable. For multi-replica topics, configure retries on the producer client. To do so:
  - Open-source Kafka client: Set the **retries** parameter to 3, 4, or 5.
  - Flink: Configure the retry policy by referring to the following code:
 


```
StreamExecutionEnvironment env = StreamExecutionEnvironment.getExecutionEnvironment();
env.setRestartStrategy(RestartStrategies.fixedDelayRestart(3, Time.seconds(20)));
```


## Prerequisites

The instance must be in the **Running** state.

## Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Choose **More > Upgrade** in the row containing the desired instance.

**Step 6** Set **Execute** to **Now** or **As scheduled**.

If you select **As scheduled**, specify date and time.

**Step 7** In the **Risk Check** area, check whether the items are normal.

If any risk is found, handle it as prompted and click **Recheck**. If the risk does not need to be handled, select **I understand the risks**.

**Step 8** Click **OK**.

The method of checking the upgrade result depends on when the upgrade is executed.

**Table 9-11** Checking the upgrade result

| Execution | Check Method                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|-----------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Now       | <ol style="list-style-type: none"> <li>1. Click an instance name to go to the instance details page.</li> <li>2. Choose <b>Background Tasks</b> in the navigation pane.</li> <li>3. Check the upgrade task status on the <b>Background Tasks</b> tab page.                             <ul style="list-style-type: none"> <li>– The upgrade is complete when the task is in the <b>Successful</b> state.</li> <li>– The upgrade failed when the task is in the <b>Failed</b> state. Contact customer service.</li> </ul> </li> </ol> |

| Execution    | Check Method                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|--------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| As scheduled | <ol style="list-style-type: none"> <li>1. Click an instance name to go to the instance details page.</li> <li>2. Choose <b>Background Tasks</b> in the navigation pane.</li> <li>3. On the <b>Scheduled tasks</b> tab page, check whether the upgrade task is started.                             <ul style="list-style-type: none"> <li>- The task has not been started when it is in the <b>Pending</b> state.</li> <li>- The task has been started when it is in the <b>Successful</b> state.</li> </ul> </li> <li>4. Check the upgrade task status on the <b>Background Tasks</b> tab page.                             <ul style="list-style-type: none"> <li>- The upgrade is complete when the task is in the <b>Successful</b> state.</li> <li>- The upgrade failed when the task is in the <b>Failed</b> state. Contact customer service.</li> </ul> </li> </ol> |

----End

## Modifying Scheduled Upgrade Tasks

**Step 1** Go to the **Scheduled tasks** tab page on the **Background Tasks** page, click the drop-down box in the upper left corner and select a period. Enter "upgrade" in the search box and press **Enter**.

**Step 2** Click **Modify** in the row containing the desired task.

**Step 3** In the **Change Schedule** dialog box, reschedule or cancel the task.

- To reschedule: Specify a new time and click **OK**.
- To cancel: Select **Cancel** and click **OK**.


----End


## 9.9 Exporting the Kafka Instance List

You can export a list of instances on the DMS for Kafka console.

### Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Export the instance list in either of the following ways:

- Select the desired instances and choose **Export > Export selected data to an XLSX file** to export specified instances.
- Choose **Export > Export all data to an XLSX file** to export all instances.

----End

## 9.10 Restarting a Kafka Instance

You can restart one or more Kafka instances in batches on the DMS for Kafka console.

### Notes and Constraints


- When a Kafka instance is being restarted, message consumption and production requests of clients will be rejected.
- To maintain service connections during instance restart, configure the retry mechanism on the client.


### Prerequisite

The status of the Kafka instance you want to restart is either **Running** or **Faulty**.

### Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Restart Kafka instances using one of the following methods:

- Select one or more Kafka instances and click **Restart** in the upper left corner.
- In the row containing the desired instance, click **Restart**.
- Click the desired Kafka instance to go to the instance details page. In the upper right corner, click **Restart**.

**Step 6** In the **Restart Instance** dialog box, click **Yes** to restart the Kafka instance.

It takes 3 to 15 minutes to restart a Kafka instance. After the instance is successfully restarted, its status should be **Running**.

#### NOTE

Restarting a Kafka instance only restarts the instance process and does not restart the VM where the instance is located.

----End

## 9.11 Deleting Kafka Instances

For pay-per-use Kafka instances, you can delete one or more of them in batches on the console. For yearly/monthly Kafka instances, if you no longer need them, choose **More > Unsubscribe** in the **Operation** column. Kafka instances will be automatically deleted upon unsubscription.


Manage deleted instances using recycle bin policies. Deleting instances when no recycle bin policies are enabled clears instance data permanently. Recycle bin policies are disabled by default. To enable them, see [Procedure](#).


### Prerequisites

The status of the Kafka instance you want to delete is **Running**, **Faulty**, or **Frozen**.

### Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Delete pay-per-use Kafka instances in either of the following ways:

- Select one or more Kafka instances and click **Delete** in the upper left corner.
- In the row containing the Kafka instance to be deleted, choose **More > Delete**.
- Click the desired Kafka instance to go to the instance details page. In the upper right corner, choose **More > Delete**.

**Step 6** In the **Delete Instance** dialog box, enter **DELETE** and click **OK** to delete the Kafka instance.

It takes 1 to 60 seconds to delete a Kafka instance.

----End

## 9.12 Using Kafka Manager

### 9.12.1 Accessing Kafka Manager

Kafka Manager is an open-source tool for managing Kafka. It can be used only through a web browser. In Kafka Manager, you can view the monitoring statistics and broker information of your Kafka clusters.

**Instances created since May 17, 2023 do not have Kafka Manager. Kafka Manager's functions are provided on the Kafka console.**

**Table 9-12** Kafka Manager functions on the Kafka console

| Kafka Manager                                 | Kafka Console                                                                                                                                                                                                                                                                                |
|-----------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Viewing topics about an instance              | View the topic list on the <b>Topics</b> page.                                                                                                                                                                                                                                               |
| Viewing basic information about a topic       | View the basic information (including the number of replicas, number of partitions, and aging time) about each topic on the <b>Topics</b> page.                                                                                                                                              |
| Reassigning topic partitions                  | Reassign partitions automatically or manually on the <b>Topics</b> page.                                                                                                                                                                                                                     |
| Updating topic configurations                 | Modify topic configuration parameters on the <b>Topics</b> page.                                                                                                                                                                                                                             |
| Viewing the consumer group list               | View the consumer group list on the <b>Consumer Groups</b> page.                                                                                                                                                                                                                             |
| Viewing details about a specific consumer     | On the <b>Consumer Groups</b> page, click a consumer group name to go to the consumer group details page and view consumers and their progress.                                                                                                                                              |
| Viewing details of topics in a consumer group | On the <b>Consumer Groups</b> page, click a consumer group name to go to the consumer group details page. On the <b>Consumer Offset</b> tab page, view the topic list of the consumer group, the number of messages accumulated in each topic, and the consumption status of each partition. |
| Monitoring the cluster or topics              | View monitoring information on the <b>Monitoring</b> page.                                                                                                                                                                                                                                   |

## Prerequisites

Security group rules have been configured by referring to [Table 9-13](#).

**Table 9-13** Security group rule

| Direction | Protocol | Port | Source                                             | Description           |
|-----------|----------|------|----------------------------------------------------|-----------------------|
| Inbound   | TCP      | 9999 | IP address or IP address group of the Kafka client | Access Kafka Manager. |

## Logging In to Kafka Manager


**Step 1** Create a Windows ECS with the same VPC and security group configurations as the Kafka instance. For details, see [Purchasing a Custom ECS](#).

If public access has been enabled, this step is optional. You can access the instance using the local browser. You do not need to create a Windows ECS.

**Step 2** Obtain the Kafka Manager address on the instance details page.

- If public network access has been disabled, the Kafka Manager address is **Manager Address (Private Network)**.

**Figure 9-2** Kafka Manager address (private network)

Manager Address (Private Network) `https://192.168.0.224:9999,https://192.168.0.24:9999` 

- If public network access has been enabled, the Kafka Manager address is **Manager Address (Public Network)**.

**Figure 9-3** Kafka Manager address (public network)

Manager Address (Public Network) `https://122.1.1.50:9999,https://122.1.1.36:9999` 

**Step 3** Enter the Kafka Manager address in the web browser in the Windows ECS.

If public access is enabled, enter the Kafka Manager address in the address bar of the browser on the local PC. If public access is not enabled, log in to the ECS prepared in [Step 1](#) and enter the Kafka Manager address in the address bar of the browser on the ECS.

**Step 4** Enter the username and password for logging in to Kafka Manager, which you set when creating the instance.

----End


## Viewing Information in Kafka Manager

In Kafka Manager, you can view the monitoring statistics and broker information of your Kafka clusters.

- Information about clusters
  - Click **Clusters** to view the information about clusters. [Figure 9-4](#) shows an example of the cluster information.
    - The top navigation bar provides the following functions, as shown in the red box 1 in the figure.
      - **Cluster:** viewing the list of clusters and cluster information.
      - **Brokers:** viewing information about brokers of a cluster.
      - **Topic:** viewing information about topics in a cluster.
      - **Preferred Replica Election:** electing the leader (preferred replica) of a topic. This operation is not recommended.
      - **Reassign Partitions:** reassigning partitions. This operation is not recommended.

- **Consumers:** viewing the status of consumer groups in a cluster.
- Red box 2 shows an example of the cluster information summary, including the number of topics and brokers in the cluster.


**Figure 9-4** Information about clusters



- Combined information about all brokers of a cluster  
This page shows statistics of brokers of a cluster. **Figure 9-5** shows an example of the storage configuration.
  - Red box 1 shows the list of brokers, including number of incoming and outgoing bytes of different brokers.
  - Red box 2 shows the monitoring metrics of the cluster.




**Figure 9-5** Viewing the combined information about all brokers in a cluster



- Information about a specific broker
  - Click the ID of a broker to view its statistics. **Figure 9-6** shows an example of the storage configuration.
    - Red box 1 shows the statistics of the broker, including the numbers of topics, partitions, and leaders, and percentages of messages, incoming traffic, and outgoing traffic.
    - Red box 2 shows the monitoring metrics of the broker.

**Figure 9-6** Viewing information about a broker



- Topics of an instance

In the navigation bar, choose **Topic > List**. The displayed page shows the list of topics and information about the topics, as shown in **Figure 9-7**.

Topics starting with "\_\_" are internal topics. To avoid service faults, do not perform any operation on these topics.

**Figure 9-7** Topics of an instance

Kafka Manager **kafka\_cluster** Cluster ▾ Brokers Topic ▾ Preferred Replica Election Reassign Partitions Consumers

Clusters / kafka\_cluster / Topics

Operations

Generate Partition Assignments Run Partition Assignments Add Partitions

Topics

Show 10 entries Search:

| Topic              | # Partitions | # Brokers | Brokers Spread % | Brokers Skew % | Brokers Leader Skew % | # Replicas | Under Replicated % | Producer Message/Sec | Summed Recent Offsets |
|--------------------|--------------|-----------|------------------|----------------|-----------------------|------------|--------------------|----------------------|-----------------------|
| __consumer_offsets | 50           | 3         | 100              | 0              | 0                     | 3          | 0                  | 0.00                 | 3                     |
| __trace            | 9            | 3         | 100              | 66             | 66                    | 1          | 0                  | 0.00                 | 0                     |
| topic-test         | 3            | 3         | 100              | 0              | 0                     | 3          | 0                  | 0.00                 | 0                     |


Showing 1 to 3 of 3 entries Previous 1 Next

- Details of a topic

Click the name of a topic to view its details on the displayed page, as shown in **Figure 9-8**.

- Red box 1: basic information about the topic, including **Replication**, **Number of Partitions**, and **Sum of Partition Offsets**.
- Red box 2: information about partitions of different brokers.
- Red box 3: consumer groups of the topic. Click the name of a consumer group name to view its details.
- Red box 4: configurations of the topic. See **Topic Configs**.
- Red box 5: monitoring metrics of the topic.
- Red box 6: information about partitions in the topic, including **Latest Offset**, **Leader** of a partition, **Replicas**, and **In Sync Replicas**.


**Figure 9-8** Details of a topic



- List of consumers

Click **Consumers** to view the list of consumers in a cluster. Only consumer groups that have consumed messages in the last 14 days are displayed on this page.


**Figure 9-9** Viewing the list of consumers



- Details of a specific consumer


Click the name of a consumer to view its details, including the list of topics in the consumer and the number of messages that can be retrieved in each topic (**Total Lag**).

**Figure 9-10** Viewing consumer details



- Details of topics in a consumer  
Click the name of a topic to view consumption details of different partitions in the topic, including **Partition**, the number of messages in a partition (**LogSize**), progress of the retrieval (**Consumer Offset**), number of remaining messages in the partition that can be retrieved (**Lag**), and the latest consumer that retrieved from the partition (**Consumer Instance Owner**).

**Figure 9-11** Viewing details of a topic



## 9.12.2 Resetting Kafka Manager Password


You can reset the password of Kafka Manager of a Kafka instance if you forget it. This function is not available for instances created since May 17, 2023.


### Prerequisites

A Kafka instance has been created and is in the **Running** state.

## Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Reset the Kafka Manager password using either of the following methods:

- In the row containing the desired Kafka instance, choose **More > Reset Manager Password**.
- Click the desired Kafka instance to go to the instance details page. In the upper right corner, choose **More > Reset Manager Password**.
- Click the desired Kafka instance to go to the instance details page. On the **Basic Information** page, click **Reset Manager Password** next to **Manager Username** in the **Connection** section.

**Step 6** Enter and confirm a new password, and click **OK**.

- If the password is successfully reset, a success message is displayed.
- If the password fails to be reset, a failure message is displayed. Reset the password again. If you still fail to reset the password after multiple attempts, contact customer service.

### NOTE


The system will display a success message only after the password is successfully reset on all brokers.

----End

## 9.12.3 Restarting Kafka Manager

Restart Kafka Manager when you fail to log in to it or it cannot provide services as usual.

**Figure 9-12** Error information




This function is not available for instances created since May 17, 2023.


## Notes and Constraints

Restarting Kafka Manager does not affect services.

## Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Restart Kafka Manager using either of the following methods:

- In the row containing the desired Kafka instance, choose **More > Restart Kafka Manager**.
- Click the desired Kafka instance to go to the instance details page. In the upper right corner, choose **More > Restart Kafka Manager**.

**Step 6** Click **Yes**.

You can view the operation progress on the **Background Tasks** page. If the task status is **Successful**, the restart has succeeded.

----End

## 9.12.4 Disabling Kafka Manager


Kafka Manager consumes memory and CPU. To free some resources, disable this function. This section describes how to disable Kafka Manager on the console.


### Notes and Constraints

- Once disabled, Kafka Manager cannot be enabled.
- Disabling Kafka Manager does not restart the instance.

## Procedure


**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired Kafka instance to go to the instance details page.

**Step 6** On the **Basic Information** tab page, click  next to **Kafka Manager** in the **Connection** area.

After Kafka Manager is disabled, the Kafka Manager connection address will not be displayed on the console, the Kafka Manager password cannot be reset, and Kafka Manager cannot be restarted.

**----End**

# 10 Modifying Instance Specifications

## 10.1 Modifying Cluster Kafka Instance Specifications

After creating a Kafka instance, you can increase or decrease its specifications. [Table 10-1](#) lists available modification options. Only one object can be modified per operation: broker quantity, bandwidth, storage space, or broker flavor.

**Table 10-1** Specification modification options

| Old/New Flavor | Modified Object | Increase | Decrease |
|----------------|-----------------|----------|----------|
| New flavor     | Broker quantity | √        | ×        |
|                | Storage space   | √        | ×        |
|                | Broker flavor   | √        | √        |
| Old flavor     | Bandwidth       | √        | ×        |
|                | Storage space   | √        | ×        |
|                | Broker flavor   | ×        | ×        |

### Distinguishing Between Old and New Specifications

- Old specifications: In the instance list, the instance specification is displayed as bandwidth (for example, **100 MB/s**).
- New specifications: In the instance list, the instance specification is displayed as the ECS flavor multiplied by the number of brokers (for example, **kafka.2u4g.cluster\*3 brokers**).

**Figure 10-1** Instance list

| Name                                         | Status  | Version | Flavor                        | Used/Available Storage Spa... |
|----------------------------------------------|---------|---------|-------------------------------|-------------------------------|
| kafka-test<br>a0af5cb3-c7fd-4f2d-ac1f-fe9... | Running | 2.7     | kafka.2u4g.cluster * 3 broker | 0/186                         |
| kafka-01<br>252b248f-501e-41ed-983...        | Running | 2.3.0   | 100 MB/s                      | 0/186                         |



## Notes and Constraints

Unavailable for single-node instances.

## Impact of Specification Modification

**Table 10-2** Impact of specification modification

| Modified Object              | Impact                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                  |
|------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Bandwidth or broker quantity | <ul style="list-style-type: none"> <li>• Increasing the bandwidth or adding brokers does not affect the original brokers or services.</li> <li>• When you increase the bandwidth or change the broker quantity, the storage space is proportionally expanded based on the current disk space. For example, assume that the original number of brokers of an instance is 3 and the disk size of each broker is 200 GB. If the broker quantity changes to 10 and the disk size of each broker is still 200 GB, the total disk size becomes 2,000 GB.</li> <li>• New topics are created on new brokers, and the original topics are still on the original brokers, resulting in unbalanced partitions. You can <a href="#">reassign partitions</a> to migrate the replicas of the original topic partitions to the new brokers.</li> </ul> |
| Storage space                | <ul style="list-style-type: none"> <li>• You can expand the storage space 20 times.</li> <li>• Storage space expansion does not affect services.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |


| Modified Object | Impact                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|-----------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Broker flavor   | <ul style="list-style-type: none"> <li>● Single-replica topics do not support message production and consumption during this period. Services will be interrupted.</li> <li>● If a topic has multiple replicas, modifying the broker flavor does not interrupt services, but may cause disorder of partition messages. Evaluate this impact and avoid peak hours.</li> <li>● Broker rolling restarts will cause partition leader changes, interrupting connections for less than a minute when the network is stable. For multi-replica topics, configure the retry mechanism on the producer client. To do so: <ul style="list-style-type: none"> <li>– If you use an open-source Kafka client, configure the <b>retries</b> parameter to a value in the range from 3 to 5.</li> <li>– If you use Flink, configure the retry policy by referring to the following code: <pre style="background-color: #f0f0f0; padding: 5px;">StreamExecutionEnvironment env = StreamExecutionEnvironment.getExecutionEnvironment(); env.setRestartStrategy(RestartStrategies.fixedDelayRestart(3, Time.seconds(20)));</pre> </li> </ul> </li> <li>● If the total number of partitions created for an instance is greater than the upper limit allowed by a new flavor, scale-down cannot be performed. The maximum number of partitions varies with instance specifications. For details, see <a href="#">Specifications</a>.<br/>For example, if 800 partitions have been created for a <b>kafka.4u8g.cluster*3</b> instance, you can no longer scale down the instance to <b>kafka.2u4g.cluster*3</b> because this flavor allows only 750 partitions.</li> <li>● It takes 5 to 10 minutes to modify specifications on one broker. The more brokers, the longer time the modification takes.</li> </ul> |

## Process of Increasing or Decreasing Broker Flavors



When you scale up or down the broker flavor, a rolling restart is performed on brokers. The following process takes three brokers as an example:

1. Stop the Kafka process on Broker 0.
2. Scale up or down the flavor of Broker 0.
3. Restart the Kafka process on Broker 0.
4. Repeat **1** to **3** to scale up or down the flavor of Broker 1.
5. Repeat **1** to **3** to scale up or down the flavor of Broker 2.









**Figure 10-2** Process of modifying a broker flavor



## Procedure

- Step 1** Log in to the console.
- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** In the row containing the desired instance, choose **More > Modify Specifications** in the **Operation** column.
- Step 6** Specify the required storage space, broker flavor, or bandwidth.
  - **Increase the bandwidth (for earlier instances).**
    - a. Specify a new bandwidth and click **Next**.
    - b. Confirm the configurations and click **Submit**.
    - c. Return to the instance list and check whether the change succeeded.

**Figure 10-3** Viewing the increased bandwidth

| <input type="checkbox"/> Name                                                                                                                                                                                                                       | Status  | Version  | Flavor  |
|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------|-----------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------|
| <input type="checkbox"/> kafka-1674331489  <br>5b0ac100-aa24-4461-8950-dc...  |  Running  | 2.3.0                                                                                         | 300 MB/s                                                                                     |

- If the instance status has changed from **Changing** to **Change failed**, the change failed. Move the cursor over **Change failed** to check the failure cause.  
Instances in the **Change failed** state cannot be restarted, modified, or deleted. After the instance status automatically changes from **Change failed** to **Running**, you can continue to perform operations on the instance. If the status does not change to **Running**, contact customer service.

- d. After increasing the bandwidth, add the IP address of the new broker to the client connection configuration to improve reliability.
- **Expand the storage space (for earlier instances).**
  - a. Specify a new storage space and click **Next**.
  - b. Confirm the configurations and click **Submit**.
  - c. Return to the instance list and check whether the change succeeded.
    - If the instance status has changed from **Changing** to **Running**, the change succeeded. View the new storage space in the **Used/Available Storage Space (GB)** column in the instance list.

**Figure 10-4** Viewing the increased storage space

| Name                                       | Status  | Version | Flavor   | Used/Available St... |
|--------------------------------------------|---------|---------|----------|----------------------|
| kafka-1674331489<br>5b0ac100-aa24-4461-... | Running | 2.3.0   | 100 MB/s | 0/558 (0%)           |

- If the instance status has changed from **Changing** to **Change failed**, the change failed. Move the cursor over **Change failed** to check the failure cause.
 

Instances in the **Change failed** state cannot be restarted, modified, or deleted. After the instance status automatically changes from **Change failed** to **Running**, you can continue to perform operations on the instance. If the status does not change to **Running**, contact customer service.
- **Expand the storage space (for later instances).**
  - a. Select **Storage** for **Change By**. For **Storage space per broker**, enter a value. Storage spaces vary by instance specifications. For details, see [Specifications](#). Click **Next**.
  - b. Confirm the configurations and click **Submit**.
  - c. Check the modification progress and estimated remaining time.
    - i. In the instance list, click the instance to go to the instance details page.
    - ii. In the navigation pane, choose **Background Tasks**.
    - iii. Click the task whose name is **Modify Specifications**. The **Specification Modification Task Details** dialog box is displayed.
    - iv. Check the progress and estimated remaining time. In **Steps**, check the steps, start time, and end time.
  - d. Check whether the modification is successful.
    - If the task is in the **Successful** state, the modification is successful. View the new storage space (Storage space per broker × Number of brokers) in the **Used/Available Storage Space (GB)** column in the instance list.
    - If the task is in the **Failed** state, the modification is not successful. Move the cursor over **Failed** or check the cause in **Steps**.
 

After the modification fails, the instance is in the **Change failed** state, and cannot be restarted, modified, or deleted. After the

instance status automatically changes from **Change failed** to **Running**, you can continue to perform operations. If the status does not change to **Running**, contact customer service.

**Figure 10-5** Expanding the storage space

Change By: **Storage** | Brokers | Broker Flavor

The storage cannot be reduced.

Storage space per broker: High I/O  GB

Total disk bandwidth: 390 MB/s = Disk bandwidth per broker x Broker quantity  
Disk bandwidth per broker: 130 MB/s

New Specifications: Total storage: 600 GB | Storage space per broker: High I/O 200 GB | Brokers: 3

- **Increase the broker quantity (for later instances).**
  - a. For **Change By**, select **Brokers**.
  - b. For **Brokers**, specify the broker quantity. The broker quantity range varies by instance specifications. For details, see [Specifications](#).
  - c. If public access has been enabled, configure EIPs for the new brokers.
  - d. For **Subnet**, retain the default settings.
  - e. For **Private IP Addresses**, select **Auto** or **Manual**.
    - **Auto**: The system assigns an IP address from the subnet automatically.
    - **Manual**: Select the IP addresses for the new brokers from the drop-down list. If the number of selected IP addresses is less than the number of brokers, the remaining IP addresses will be automatically assigned.
  - f. Click **Next**.
  - g. Confirm the configurations and click **Submit**.
  - h. Check the modification progress and estimated remaining time.
    - i. In the instance list, click the instance to go to the instance details page.
    - ii. In the navigation pane, choose **Background Tasks**.
    - iii. Click the task whose name is **Modify Specifications**. The **Specification Modification Task Details** dialog box is displayed.
    - iv. Check the progress and estimated remaining time. In **Steps**, check the steps, start time, and end time.
  - i. Check whether the modification is successful.
    - If the task is in the **Successful** state, the modification is successful. View the number of brokers in the **Flavor** column in the instance list.
    - If the task is in the **Failed** state, the modification is not successful. Move the cursor over **Failed** or check the cause in **Steps**.  
After the modification fails, the instance is in the **Change failed** state, and cannot be restarted, modified, or deleted. After the

instance status automatically changes from **Change failed** to **Running**, you can continue to perform operations. If the status does not change to **Running**, contact customer service.

- j. After adding brokers, add the IP addresses of the new brokers to the client connection configuration to improve reliability.

**Figure 10-6** Adding brokers

Change By: Storage, **Brokers**, Broker Flavor

The broker quantity cannot be decreased. Partitions can be reassigned.

Brokers: - 4 +

Total disk bandwidth: 460 MB/s = Disk bandwidth per broker x Broker quantity  
Disk bandwidth per broker: 115 MB/s

Subnet: subnet-... (192.168.0.0/24) (available IP addresses: ...)

Private IP Addresses: **Auto**, Manual

New Specifications: Total storage: 400 GB | Storage space per broker: High I/O 100 GB | Brokers: 4

- **Modifying broker flavors (for later instances).**
  - a. For **Change By**, select **Broker Flavor**.
  - b. Specify a new broker flavor.
  - c. In the **Risk Check** area, check for risks.

If any risk is found, handle it as prompted and click **Recheck**. If the risks do not need to be handled, select **I understand the risks**.
  - d. Click **Next**, confirm the information, and click **Submit**.
  - e. Check the scaling progress and estimated remaining time.
    - i. In the instance list, click the instance to go to the instance details page.
    - ii. In the navigation pane, choose **Background Tasks**.
    - iii. Click the task whose name is **Modify Specifications**. The **Specification Modification Task Details** dialog box is displayed.
    - iv. Check the progress and estimated remaining time. In **Steps**, check the steps, start time, and end time.
  - f. Check whether the modification is successful.
    - If the task is in the **Successful** state, the modification is successful. View the broker flavor in the **Flavor** column in the instance list.
    - If the task is in the **Failed** state, the modification is not successful. Move the cursor over **Failed** or check the cause in **Steps**.

After the modification fails, the instance is in the **Change failed** state, and cannot be restarted, modified, or deleted. After the instance status automatically changes from **Change failed** to **Running**, you can continue to perform operations. If the status does not change to **Running**, contact customer service.

**Figure 10-7** Increasing or decreasing a broker flavor

Change By: Storage Brokers Broker Flavor

Modifying the broker flavor will restart brokers and may cause disconnections. Single-replica topics cannot provide message creation and retrieval during this time.

| Broker Flavor                    | Flavor Name          | TPS Limit per Broker | Maximum Partitions per Bro... | Recommended Consumer G... | Traffic per Broker (MB/s) |
|----------------------------------|----------------------|----------------------|-------------------------------|---------------------------|---------------------------|
| <input checked="" type="radio"/> | kafka.2u4g.cluster   | 30,000               | 250                           | 20                        | 100                       |
| <input type="radio"/>            | kafka.4u8g.cluster   | 100,000              | 500                           | 100                       | 200                       |
| <input type="radio"/>            | kafka.8u16g.cluster  | 150,000              | 1,000                         | 150                       | 375                       |
| <input type="radio"/>            | kafka.12u24g.cluster | 200,000              | 1,500                         | 200                       | 625                       |
| <input type="radio"/>            | kafka.16u32g.cluster | 250,000              | 2,000                         | 200                       | 750                       |

Total traffic: 300 MB/s (Total traffic = Traffic per broker x Broker quantity)

Service traffic:

- \* Recommended read traffic: 50 MB/s
- \* Recommended write traffic: 50 MB/s

[Learn more](#) about total traffic and service traffic.

Tip: Reserve 30% of traffic to accommodate traffic fluctuations.

New Specifications: **kafka.2u4g.cluster**

----End

# 11 Migrating Data

---

## 11.1 Kafka Data Migration Overview

You can migrate Kafka services to connect message producers and consumers to a new Kafka instance and can even migrate persisted message data to the new Kafka instance. Kafka services can be migrated in the following two scenarios:

- Migrating services to the cloud without downtime  
Services that have high requirements on continuity must be smoothly migrated to the cloud because they cannot afford a long downtime.
- Re-deploying services on the cloud  
A Kafka instance deployed within an AZ is not capable of cross-AZ disaster recovery. For higher reliability, you can re-deploy services to an instance that is deployed across AZs.

### Constraints

- When Smart Connect is used to migrate services, it consumes the source Kafka messages and produces messages to the target Kafka instance, occupying the bandwidth of the source and the target Kafka.
- To maintain performance, Smart Connect only synchronizes the source and target data in real time. The consumption progress is synchronized in batches, so the consumption progress on the source and target partitions may vary from 0 to 100.

### Preparation

1. Configure the network environment.  
A Kafka instance can be accessed within a VPC or over a public network. For public network access, the producer and consumer must have public access permissions, and the following security group rules must be configured.



**Table 11-1** Security group rules

| Direction | Protocol | Port | Source                                             | Description                                                    |
|-----------|----------|------|----------------------------------------------------|----------------------------------------------------------------|
| Inbound   | TCP      | 9094 | IP address or IP address group of the Kafka client | Accessing a Kafka instance in a public network (in plaintext)  |
| Inbound   | TCP      | 9095 | IP address or IP address group of the Kafka client | Accessing a Kafka instance in a public network (in ciphertext) |

2. Create the target Kafka instance.  
The specifications of the target instance cannot be lower than the original specifications. For more information, see [Buying a Kafka Instance](#).
3. Create a topic in the target Kafka instance.  
Create a topic with the same configurations as the original Kafka instance, including the topic name, number of replicas, number of partitions, message aging time, and whether to enable synchronous replication and flushing. For more information, see [Creating a Kafka Topic](#).

## Migration Scheme 1: Migrating the Production First

Migrate the message production service to the new Kafka instance. After migration, the original Kafka instance will no longer produce messages. After all messages of the original Kafka instance are consumed, migrate the message consumption service to the new Kafka instance to consume messages of this instance.

This is a common migration scheme. It is simple and easy to control on the service side. During the migration, the message sequence is ensured, so this scheme is **suitable for scenarios with strict requirements on the message sequence**. However, latency may occur because there is a period when you have to wait for all data to be consumed.

- Step 1** Change the Kafka connection address of the producer to that of the new Kafka instance.
- Step 2** Restart the production service so that the producer can send new messages to the new Kafka instance.
- Step 3** Check the consumption progress of each consumer group in the original Kafka instance until all data in the original Kafka instance is consumed.
- Step 4** Change the Kafka connection addresses of the consumers to those of the new Kafka instance.

**Step 5** Restart the consumption service so that consumers can consume messages from the new Kafka instance.

**Step 6** Check whether consumers consume messages properly from the new Kafka instance.

**Step 7** The migration is complete.

----End

## Migration Scheme 2: Migrating the Production Later

Use multiple consumers for the consumption service. Some consume messages from the original Kafka instance, and others consume messages from the new Kafka instances. Then, migrate the production service to the new Kafka instance so that all messages can be consumed in time.

For a certain period of time, the consumption service consumes messages from both the original and new Kafka instances. Before the migration, message consumption from the new Kafka instance has already started, so there is no latency. However, early on in the migration, data is consumed from both the original and new Kafka instances, so the messages may not be consumed in the order that they are produced. This scheme is **suitable for services that require low latency but do not require strict message sequence**.

**Step 1** Start new consumer clients, set the Kafka connection addresses to that of the new Kafka instance, and consume data from the new Kafka instance.

Original consumer clients must continue running. Messages are consumed from both the original and new Kafka instances.

**Step 2** Change the Kafka connection address of the producer to that of the new Kafka instance.

**Step 3** Restart the producer client to migrate the production service to the new Kafka instance.

**Step 4** After the production service is migrated, check whether the consumption service connected to the new Kafka instance is normal.

**Step 5** After all data in the original Kafka is consumed, close the original consumption clients.

**Step 6** The migration is complete.

----End

## Migration Scheme 3: Migrating the Consumption First

Use Smart Connect to synchronize the two Kafka instances, migrate the consumer first and then the producer to the new Kafka instance.

This scheme uses Smart Connect to synchronize the source and target data in real time. However, the consumption progress is synchronized in batches. The consumption progress on the source and target partition may vary from 0 to 100. As a result, some messages are repeatedly consumed. This scheme applies to services where the message production must continue, end-to-end latency must be low, and repeated consumption can be tolerated.

- Step 1** Create a Smart Connect task for Kafka data replication. For details, see [Replicating Kafka Instance Data](#).
- Step 2** On the **Message Query** page of the Kafka console, check whether the latest messages and the synchronization progress of both Kafka instances are consistent. For details, see [Viewing Kafka Messages](#).
- Yes: Go to [Step 3](#).
  - No: Check whether the synchronized data per minute of both Kafka instances is normal. If yes, wait for the synchronization progress of both Kafka instances to be consistent, then go to [Step 3](#).
- Step 3** Change the Kafka connection addresses of the consumers to those of the new Kafka instance.
- Step 4** Restart the consumption service so that consumers can consume messages from the new Kafka instance.
- Step 5** Check whether consumers consume messages properly from the new Kafka instance.
- Step 6** Change the Kafka connection address of the producer to that of the new Kafka instance.
- Step 7** Restart the producer client to migrate the production service to the new Kafka instance.
- Step 8** After the production service is migrated, check whether the consumption service connected to the new Kafka instance is normal.
- Step 9** The migration is complete.

----End

## How Do I Migrate Persisted Data Along with Services?

You can migrate consumed data from the original instance to a new instance by using Smart Connect. This tool mirrors the original Kafka producer and consumer into new ones and migrates data to the new Kafka instance. For details, see [Replicating Kafka Instance Data](#).

Note that each cloud Kafka instance stores data in three replicas. Therefore, the storage space of the new instance should be three times that of the original single-replica message storage.

## 11.2 Migrating Data Using Smart Connect

### 11.2.1 Enabling Smart Connect

Smart Connect synchronizes data between Kafka and other cloud services (such as OBS) or between two Kafka instances for backup or migration.

Procedure for using Smart Connect:

1. Enable Smart Connect.

2. Create a Smart Connect task.

This section describes how to enable Smart Connect.

## Notes and Constraints


- Enabling Smart Connect incurs additional broker fees.  
For example, if you enable Smart Connect for a kafka.4u8g.cluster instance, at least two more kafka.4u8g brokers will be created for Smart Connect and you need to pay for them.
- Unavailable for single-node instances.


## Prerequisites

- [A Kafka instance has been created](#) and is in the **Running** state.
- `auto.create.groups.enable` is set to **true**. If no, modify it by referring to [Modifying Kafka Instance Configuration Parameters](#).

## Procedure


**Step 1** Log in to the console.


**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Enable Smart Connect using one of the following methods:

- In the row containing the desired Kafka instance, choose **More > Enable Smart Connect**.
- Click the desired Kafka instance to go to the instance details page. In the upper right corner, choose **More > Enable Smart Connect**.
- Click the desired Kafka instance to go to the instance details page. Click  next to **Smart Connect**.
- Click the desired Kafka instance to go to the instance details page. In the navigation pane, choose **Smart Connect**. Click **Enable Smart Connect**.

**Step 6** Click , enable **Smart Connect**, set 2–16 brokers as required, and click **Next**.

### NOTE

By default, two brokers will be used. If synchronization traffic between two Kafka instances is estimated to be large, for example, greater than 50 MB/s, use more brokers.

**Step 7** On the displayed **Enabling Smart Connect for Kafka Instance** page, ensure that **Smart Connect** is enabled and click **Submit**.

----End

## Follow-up Operations

Proceed to [Replicating Kafka Instance Data, Dumping Kafka Data to Object Storage Service \(OBS\)](#), to synchronize data between DMS for Kafka and other cloud services.

### 11.2.2 Replicating Kafka Instance Data

Create a Smart Connect task to copy data unidirectionally or bidirectionally between two Kafka instances.

Data in the source Kafka instance is synchronized to the target Kafka instance in real time.

#### Notes and Constraints


- This function is unavailable for single-node Kafka instances.
- A maximum of 18 Smart Connect tasks can be created for an instance.
- When you copy Kafka data, the two Kafka instances must be connected through the intranet. If they are in different VPCs, connect the network by referring to [Accessing Kafka Using a VPC Endpoint Across VPCs](#) or [VPC Peering Connection](#).
- After a Smart Connect task is created, task parameters cannot be modified.
- If you have enabled Smart Connect for an instance before July 1, 2022 and Kafka data replication is not available, [disable Smart Connect](#) and then enable it again.
- Data can be synchronized only when **Max. Message Size** of the target topic is greater than or equal to **524,288** bytes. If no topic is available in the target Kafka instance, a topic will be automatically created with the same **Max. Message Size** as that of the source Kafka instance topic during data synchronization. In this case, ensure the **Max. Message Size** to be used is greater than or equal to **524,288** bytes. To modify **Max. Message Size**, see [Modifying Kafka Topic Configurations](#).


#### Prerequisites

- You have [enabled Smart Connect](#).
- A Kafka instance has been created and is in the **Running** state.

#### Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

- Step 6** In the navigation pane, choose **Smart Connect**.
- Step 7** On the displayed page, click **Create Task**.
- Step 8** For **Task Name**, enter a unique Smart Connect task name. Naming rules: 4–64 characters and only letters, digits, hyphens (-), or underscores (\_).
- Step 9** For **Task Type**, select **Copy Kafka data**.
- Step 10** For **Start Immediately**, specify whether to execute the task immediately after the task is created. By default, the task is executed immediately. If you disable this option, you can enable it later in the task list.
- Step 11** In the **Current Kafka** area, set the instance alias. Naming rules: 1–20 characters and only letters, digits, hyphens (-), or underscores (\_).

The instance alias is used in the following scenarios:

- If you enable **Rename Topics** and select **Push** or **Both** for **Sync Direction**, the alias of the current Kafka instance will be added to the topic names of the peer end Kafka instance. For example, if the alias of the current Kafka instance is **A** and the topic name of the peer end Kafka instance is **test**, the renamed topic will be **A.test**.
- After a Smart Connect task of Kafka data replication is created, a topic named **mm2-offset-syncs.peer end Kafka instance alias.internal** is generated for the current Kafka instance. If the task has **Sync Consumer Offset** enabled and uses **Pull** or **Both** for **Sync Direction**, a topic named *peer end Kafka instance alias.checkpoints.internal* is also created for the current Kafka instance. The two topics are used to store internal data. If they are deleted, data replication will fail.

- Step 12** In the **Peer Kafka** area, configure the following parameters.

**Table 11-2** Peer Kafka parameters

| Parameter      | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|----------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Instance Alias | <p>Naming rules: 1–20 characters and only letters, digits, hyphens (-), or underscores (_).</p> <p>The instance alias is used in the following scenarios:</p> <ul style="list-style-type: none"> <li>• If you enable <b>Rename Topics</b> and select <b>Pull</b> or <b>Both</b> for <b>Sync Direction</b>, the alias of the peer end Kafka instance will be added to the topic names of the current Kafka instance. For example, if the alias of the peer end Kafka instance is <b>B</b> and the topic name of the current Kafka instance is <b>test01</b>, the renamed topic will be <b>B.test01</b>.</li> <li>• After a Smart Connect task of Kafka data replication is created, if the task has <b>Sync Consumer Offset</b> enabled and uses <b>Push</b> or <b>Both</b> for <b>Sync Direction</b>, a topic named <i>current Kafka instance alias.checkpoints.internal</i> is also created for the peer end Kafka instance. This topic is used to store internal data. If it is deleted, data replication will fail.</li> </ul> |
| Config Type    | <p>Options:</p> <ul style="list-style-type: none"> <li>• <b>Kafka address</b>: Enter Kafka instance addresses. To replicate data to a target Kafka instance in <b>another</b> VPC, use this type.</li> <li>• <b>Instance name</b>: Select an existing Kafka instance. To replicate data to a target Kafka instance in the <b>same</b> VPC, use this type.</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Instance Name  | <p>Mandatory when <b>Instance name</b> is used for <b>Config Type</b> and the Kafka instances are within a VPC.</p> <p>Select an existing Kafka instance from the drop-down list.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| Kafka Address  | <p>Set this parameter when <b>Config Type</b> is set to <b>Kafka address</b>.</p> <p>Enter the IP addresses and port numbers for connecting to the Kafka instance.</p> <p>When you copy Kafka data, the two Kafka instances must be connected through the intranet. If they are in different VPCs, connect the network by referring to <a href="#">Accessing Kafka Using a VPC Endpoint Across VPCs</a> or <a href="#">VPC Peering Connection</a>.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |

| Parameter                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|--------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Authentication           | Options: <ul style="list-style-type: none"> <li>• <b>SASL_SSL</b>: The Kafka instance has enabled SASL_SSL, clients can connect to it with SASL and the data will be encrypted using the SSL certificate.</li> <li>• <b>SASL_PLAINTEXT</b>: The Kafka instance has enabled SASL_PLAINTEXT, clients can connect to it with SASL and the data will be transmitted in plaintext.</li> <li>• <b>PLAINTEXT</b>: The instance is not using authentication.</li> </ul> |
| Authentication Mechanism | Set this parameter when <b>Authentication</b> is set to <b>SASL_SSL/SASL_PLAINTEXT</b> . <ul style="list-style-type: none"> <li>• <b>SCRAM-SHA-512</b>: uses the hash algorithm to generate credentials for usernames and passwords to verify identities. SCRAM-SHA-512 is more secure than PLAIN.</li> <li>• <b>PLAIN</b>: a simple username and password verification mechanism.</li> </ul>                                                                   |
| Username                 | Set this parameter when <b>Authentication</b> is set to <b>SASL_SSL/SASL_PLAINTEXT</b> .<br>Set in instance creation or user creation.                                                                                                                                                                                                                                                                                                                          |
| Password                 | Set this parameter when <b>Authentication</b> is set to <b>SASL_SSL/SASL_PLAINTEXT</b> .<br>Set in instance creation or user creation.                                                                                                                                                                                                                                                                                                                          |

After a Smart Connect task is created, modifying the **authentication method or mechanism, or password** of the peer end instance causes the synchronization task to **fail**. In this case, delete the current Smart Connect task and create another one.

**Step 13** In the **Rules** area, configure the following parameters.

**Table 11-3** Parameters for configuring data replication rules

| Parameter      | Description                                                                                                                                                                                                                                                                                                                                                                         |
|----------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Sync Direction | There are three synchronization directions: <ul style="list-style-type: none"> <li>• <b>Pull</b>: Replicates data from the peer Kafka instance to the current Kafka instance.</li> <li>• <b>Push</b>: Replicates data from the current Kafka instance to the peer Kafka instance.</li> <li>• <b>Both</b>: Bidirectional replication of Kafka instance data on both ends.</li> </ul> |



| Parameter         | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                |
|-------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Topics            | <p>Specify the topics whose data is to be replicated.</p> <ul style="list-style-type: none"> <li>• <b>Regular expression:</b> Use a regular expression to match topics.</li> <li>• <b>Enter/Select:</b> Enter topic names. To enter multiple topic names, press <b>Enter</b> after entering each topic name. You can also select topics from the drop-down list. <b>A maximum of 20 topics can be entered or selected.</b></li> </ul> <p>Data of topics whose names end with "internal" (for example, <b>topic.internal</b>) will not be synchronized.</p> |
| Tasks             | <p>Number of data replication tasks. The default value is 2. You are advised to use the default value.</p> <p>If <b>Sync Direction</b> is set to <b>Both</b>, the actual number of tasks will be twice the number of tasks you configure here.</p>                                                                                                                                                                                                                                                                                                         |
| Rename Topics     | <p>Add the alias of the source Kafka instance before the target topic name to form a new name of the target topic. For example, if the alias of the source instance is <b>A</b> and the target topic name is <b>test</b>, the renamed target topic will be <b>A.test</b>.</p> <p>If you select <b>Both</b> for <b>Sync Direction</b>, enable <b>Rename Topics</b> to prevent infinite replication.</p>                                                                                                                                                     |
| Add Source Header | <p>The target topic receives the replicated messages. The message header contains the message source.</p> <p>If you select <b>Both</b> for <b>Sync Direction</b>, <b>Add Source Header</b> is enabled by default to prevent infinite replication.</p>                                                                                                                                                                                                                                                                                                      |


| Parameter            | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |
|----------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Sync Consumer Offset | <p>Enable this option to synchronize the consumer offset to the target Kafka instance.</p> <p>After enabling <b>Sync Consumer Offset</b>, pay attention to the following:</p> <ul style="list-style-type: none"> <li>• The source and target Kafka instances cannot consume messages at the same time. Otherwise, the synchronized consumer offset will be abnormal.</li> <li>• The consumer offset is synchronized every minute. As a result, the consumer offset on the target end may be slightly smaller than that on the source end, and some messages are repeatedly consumed. The service logic of the consumer client must be able to handle repeated consumption.</li> <li>• The offset synchronized from the source end is not the same as the offset on the target end. Instead, there is a mapping relationship. If the consumer offset is maintained by the consumer client, the consumer client does not obtain the consumer offset from the target Kafka instance after switching consumption from the source Kafka instance to the target Kafka instance. As a result, the offset may be incorrect or the consumer offset may be reset.</li> </ul> |
| Replicas             | <p>Number of topic replicas when a topic is automatically created in the peer instance. The value of this parameter cannot exceed the number of brokers in the peer instance.</p> <p>This parameter takes precedence over the <b>default.replication.factor</b> parameter set in the peer instance.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                            |
| Start Offset         | <p>Options:</p> <ul style="list-style-type: none"> <li>• <b>Minimum offset</b>: dumping the earliest data</li> <li>• <b>Maximum offset</b>: dumping the latest data</li> </ul>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
| Compression          | <p>Compression algorithm to use for copying messages.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                          |
| Topic Mapping        | <p>Customize the target topic name.</p> <p>Maximum mappings: 20. <b>Rename Topic</b> and <b>Topic Mapping</b> cannot be configured at the same time.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |

Precautions:

- When creating a bidirectional replication task, you must enable **Rename Topics** or **Add Source Header** to prevent infinite replication. If you specify the same topic for a pull task and a push task between two instances (forming bidirectional replication), and **Rename Topics** and **Add Source Header** are not enabled for the two tasks, data will be replicated infinitely.

- If you create two or more tasks with the same configuration and enable **Sync Consumer Offset** for them, data will be repeatedly replicated and the consumer offset of the target topic will be abnormal.

**Figure 11-1** Configuring data replication rules



**Step 14** (Optional) In the lower right corner of the page, click **Check** to test the connectivity between the Kafka instances.

If "Connectivity check passed." is displayed, the Kafka instances are connected.

**Step 15** Click **Create**. The Smart Connect task list page is displayed. The message "Task xxx was created successfully." is displayed in the upper right corner of the page.

After a Smart Connect task of Kafka data replication is created, Kafka automatically creates the following topics:

- A topic named **mm2-offset-syncs.peer end Kafka instance alias.internal** is generated for the current Kafka instance. If the task has **Sync Consumer Offset** enabled and uses **Pull** or **Both** for **Sync Direction**, a topic named *peer end Kafka instance alias.checkpoints.internal* is also created for the current

Kafka instance. **The two topics are used to store internal data. If they are deleted, data replication will fail.**

- After a Smart Connect task of Kafka data replication is created, if the task has **Sync Consumer Offset** enabled and uses **Push** or **Both** for **Sync Direction**, a topic named *current Kafka instance alias.checkpoints.internal* is also created for the peer end Kafka instance. **This topic is used to store internal data. If it is deleted, data replication will fail.**

----End

## 11.2.3 Dumping Kafka Data to Object Storage Service (OBS)

Create a Smart Connect task to dump Kafka instance data to OBS for message data backup.

Data in the source Kafka instance is synchronized to the dumping file in real time.

### Notes and Constraints


- This function is unavailable for single-node instances.
- A maximum of 18 Smart Connect tasks can be created for an instance.
- After a Smart Connect task is created, task parameters cannot be modified.


### Prerequisites

- You have [enabled Smart Connect](#).
- A Kafka instance has been created and is in the **Running** state.
- The OBS bucket must be created in the same region as the Kafka instance.

### Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Smart Connect**.

**Step 7** On the displayed page, click **Create Task**.

**Step 8** For **Task Name**, enter a unique Smart Connect task name. Naming rules: 4–64 characters and only letters, digits, hyphens (-), or underscores (\_).

**Step 9** For **Task Type**, select **Dumping**.

**Step 10** For **Start Immediately**, specify whether to execute the task immediately after the task is created. By default, the task is executed immediately. If you disable this option, you can enable it later in the task list.

**Step 11** In the **Source** area, retain the default setting.

**Step 12** In the **Topics** area, set parameters based on the following table.

**Table 11-4** Topic parameters

| Parameter          | Description                                                                                                                                    |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------|
| Regular expression | A regular expression is used to subscribe to topics whose messages you want to dump.                                                           |
| Enter/Select       | Enter or select the names of the topics to be dumped. Separate them with commas (,). <b>A maximum of 20 topics can be entered or selected.</b> |

**Step 13** In the **Target** area, set parameters based on the following table.

**Table 11-5** Target parameters

| Parameter          | Description                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|--------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Offset             | Options: <ul style="list-style-type: none"> <li>• <b>Minimum offset:</b> dumping the earliest data</li> <li>• <b>Maximum offset:</b> dumping the latest data</li> </ul>                                                                                                                                                                                                                                                                                           |
| Dumping Period (s) | Interval for periodically dumping data. The time unit is second and the default interval is 300 seconds.<br>No package files will be generated if there is no data within an interval.                                                                                                                                                                                                                                                                            |
| AK                 | Access key ID.<br>For details about how to obtain the AK, see <a href="#">Access Keys</a> .                                                                                                                                                                                                                                                                                                                                                                       |
| SK                 | Secret access key used together with the access key ID.<br>For details about how to obtain the SK, see <a href="#">Access Keys</a> .                                                                                                                                                                                                                                                                                                                              |
| Dumping Address    | The OBS bucket used to store the topic data. <ul style="list-style-type: none"> <li>• <b>Select:</b> You can select an existing OBS bucket from the drop-down list or click <b>Create Dumping Address</b> to create an OBS bucket.</li> <li>• <b>Enter:</b> You can enter an existing OBS bucket or click <b>Create Dumping Address</b> to create an OBS bucket. <b>The OBS bucket to be entered must be in the same region as the Kafka instance.</b></li> </ul> |
| Dumping Directory  | Directory for storing topic files dumped to OBS. Use slashes (/) to separate directory levels.                                                                                                                                                                                                                                                                                                                                                                    |

| Parameter             | Description                                                                                                                                                                                                               |
|-----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Time Directory Format | Data is saved to a hierarchical time directory in the dumping directory. For example, if the time directory is accurate to day, the directory will be in the format of <i>bucket name/file directory/year/month/day</i> . |
| Record Separator      | Select a separator to separate OBS dumping records.                                                                                                                                                                       |
| Use Storage Key       | Specifies whether to dump keys.                                                                                                                                                                                           |

 **NOTE**

Do not use the key of a message as the dumping file name.

**Step 14** Click **Create**. The Smart Connect task list page is displayed. The message "Task xxx was created successfully." is displayed in the upper right corner of the page.

----End

## 11.2.4 Managing Smart Connect Tasks

View, delete, start, pause, or restart a Smart Connect task.

### Notes and Constraints


Unavailable for single-node instances.


### Prerequisite

A Smart Connect task has been **created**.

### Viewing Smart Connect Tasks

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Smart Connect**.

**Step 7** Click a Smart Connect task name to go to the details page.

**Step 8** View the basic information, source, and target of the Smart Connect task.


 **NOTE**


The source and target are displayed on the task details page only when they have been configured for the Smart Connect task.

----End

## Deleting a Smart Connect Task

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Smart Connect**.

**Step 7** In the row containing the Smart Connect task to be deleted, click **Delete**.


**Step 8** Click **OK**.


----End

## Starting or Pausing a Smart Connect Task

After a task of a Kafka instance is paused, data of the instance will not be synchronized to another Kafka instance or other cloud services.

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Smart Connect**.


**Step 7** Perform the required operation:


- To start a Smart Connect task, click **Start** in the row that contains the task.
- To pause a Smart Connect task, click **Pause** in the row containing the task, then click **OK** in the dialog box that is displayed.

----End

## Restarting a Smart Connect Task

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.

**Step 6** In the navigation pane, choose **Smart Connect**.

**Step 7** In the row containing the desired Smart Connect task, click **Restart**.

Precautions:

- Modifying the source or target parameters after a Smart Connect task is created may cause the restart to fail.
- Restarting a Smart Connect task resets the synchronization progress and the synchronization task will be restarted.

**Step 8** Click **OK**.

Once the task is restarted, a success message is displayed in the upper left area of the page.

----End

## 11.2.5 Disabling Smart Connect

Disable Smart Connect and resources can be freed.

Disabling Smart Connect does not affect services.

### Notes and Constraints

- Brokers related to Smart Connect are automatically deleted, and no longer generate fees.
- If you disable Smart Connect and then enable it again, deleted Smart Connect tasks cannot be retrieved and need to be created again.
- Unavailable for single-node instances.




### Prerequisites

- A Kafka instance has been created and is in the **Running** state.
- **All Smart Connect tasks must be deleted**. This is to prevent running Smart Connect tasks from being lost after Smart Connect is disabled.

### Procedure

**Step 1** Log in to the console.



- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  in the upper left corner and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.
- Step 4** In the navigation pane, choose **Kafka Instances**.
- Step 5** Disable Smart Connect using either of the following methods:
- In the row containing the desired Kafka instance, choose **More > Disable Smart Connect**.
  - Click the desired Kafka instance to go to the instance details page. In the upper right corner, choose **More > Disable Smart Connect**.
- Step 6** Click  to disable Smart Connect. Then click **Next**.
- Step 7** Ensure that **Smart Connect** is disabled and click **Submit**.
- End

# 12 Testing Instance Performance

## 12.1 Kafka Production Rate and CPU Usage

This section describes performance tests on Distributed Message Service (DMS) for Kafka. The performance is measured by the message production rate on the client side and CPU usage on the server side. The tests cover the following scenarios:

- Scenario 1 (batch size): same Kafka instance, same topics, different message size settings
- Scenario 2 (cross-AZ or intra-AZ production): same Kafka instance, same topics, different AZ settings for the client and server
- Scenario 3 (number of replicas): same Kafka instance, different numbers of replicas
- Scenario 4 (synchronous or asynchronous replication): same Kafka instance, topics with different replication settings

**Table 12-1** Test parameters

| Partitions | Replicas | Synchronous Replication | batch.size | Cross-AZ Production |
|------------|----------|-------------------------|------------|---------------------|
| 3          | 1        | No                      | 1 KB       | No                  |
| 3          | 1        | No                      | 16 KB      | No                  |
| 3          | 1        | No                      | 1 KB       | Yes                 |
| 3          | 3        | Yes                     | 1 KB       | No                  |
| 3          | 3        | No                      | 1 KB       | No                  |


### Environment

Perform the following steps to set up the test environment.

1. Purchase a Kafka instance with parameters specified as follows and retain the default settings for other ones. For details about how to purchase one, see [Buying a Kafka Instance](#).
  - **Region:** CN-Hong Kong
  - **AZ:** Select 1.
  - **Version:** Select 2.7.
  - **Architecture:** Select **Cluster**.
  - **Broker Flavor:** Select **kafka.2u4g.cluster**.
  - **Brokers:** Enter 3.
  - **Storage Space per Broker:** Select **Ultra-high I/O** and enter 200.
  - **VPC:** Select a VPC.
  - **Subnet:** Select a subnet.
  - **Security Group:** Select a security group.
  - **Access Mode:** Retain the default settings.
  - **Instance Name:** Enter "kafka-test".
  - **Enterprise Project:** Select **default**.

After the purchase, obtain **Address (Private Network, Plaintext)** on the instance details page.

**Connection**



2. Create three topics with parameters specified as follows for the purchased Kafka instance. For details, see [Creating a Kafka Topic](#).
  - Topic-01: 3 partitions, 1 replica, asynchronous replication
  - Topic-02: 3 partitions, 3 replicas, asynchronous replication
  - Topic-03: 3 partitions, 3 replicas, synchronous replication
3. Obtain the test tool.  
Obtain [Kafka CLI 2.7.2](#).
4. Purchase a server for the client.  
Buy two ECSs with the following configurations. For details about how to purchase an ECS, see [Purchasing a Custom ECS](#).
  - One ECS is 4 vCPUs | 8 GB, runs Linux, and is configured with the same region, AZ, VPC, subnet, and security group as the Kafka instance.

- The other ECS is 4 vCPUs | 8 GB, runs Linux, and is configured with the same region, VPC, subnet, and security group but a different AZ from the Kafka instance.

Perform the following operations on the ECSs:

- Install **Java JDK** and configure the environment variables **JAVA\_HOME** and **PATH**.

```
export JAVA_HOME=/root/jdk1.8.0_231
export PATH=$JAVA_HOME/bin:$PATH
```

- Download **Kafka CLI 2.7.2** and decompress it.

```
tar -zxvf kafka_2.12-2.7.2.tgz
```

## Script

```
./kafka-producer-perf-test.sh --producer-props bootstrap.servers=${connection address} acks=1 batch.size=${batch.size} linger.ms=0 --topic ${topic name} --num-records ${num-records} --record-size 1024 --throughput 102400
```

- **bootstrap.servers**: address of the Kafka instance obtained in [1](#).
- **acks**: message synchronization policy. acks=1 indicates asynchronous replication, and acks=-1 indicates synchronous replication.
- **batch.size**: size of messages sent in each batch, in bytes.
- **linger.ms**: interval between two batches.
- **topic**: topic name set in [2](#).
- **num-records**: total number of messages to be sent.
- **record-size**: size of each message.
- **throughput**: number of messages sent per second.

## Procedure

### Scenario 1: Varied Batch Sizes

- Step 1** Log in to the client server, go to the **kafka\_2.12-2.7.2/bin** directory, and run the following scripts.

Set **batch.size** to 1 KB, and run the following script:

```
./kafka-producer-perf-test.sh --producer-props
bootstrap.servers=192.168.0.69:9092,192.168.0.42:9092,192.168.0.66:9092 acks=1 batch.size=1024
linger.ms=0 --topic Topic-01 --num-records 8000000 --record-size 1024 --throughput 102400
```

Result:

```
8000000 records sent, 34128.673632 records/sec (33.33 MB/sec), 879.91 ms avg latency, 4102.00 ms max
latency, 697 ms 50th, 2524 ms 95th, 2888 ms 99th, 4012 ms 99.9th.
```

Message production rate: 34,128 records/second

Set **batch.size** to 16 KB, and run the following script:

```
./kafka-producer-perf-test.sh --producer-props
bootstrap.servers=192.168.0.69:9092,192.168.0.42:9092,192.168.0.66:9092 acks=1 batch.size=16384
linger.ms=0 --topic Topic-01 --num-records 100000000 --record-size 1024 --throughput 102400
```

Result:

```
100000000 records sent, 102399.318430 records/sec (100.00 MB/sec), 4.72 ms avg latency, 914.00 ms max
latency, 1 ms 50th, 5 ms 95th, 162 ms 99th, 398 ms 99.9th.
```

Message production rate: 102,399 records/second

- Step 2** Log in to the Kafka console and click the name of the test instance.
- Step 3** In the navigation pane, choose **Monitoring**.
- Step 4** On the **Brokers** tab page, view the CPU usage of the server nodes.

**Figure 12-1** broker-0 CPU usage (batch.size = 1 KB)



CPU usage: 58.10%

**Figure 12-2** broker-0 CPU usage (batch.size = 16 KB)



CPU usage: 24.10%

**Figure 12-3** broker-1 CPU usage (batch.size = 1 KB)



CPU usage: 56.70%

**Figure 12-4** broker-1 CPU usage (batch.size = 16 KB)



CPU usage: 25%

**Figure 12-5** broker-2 CPU usage (batch.size = 1 KB)



CPU usage: 53.30%

**Figure 12-6** broker-2 CPU usage (batch.size = 16 KB)



CPU usage: 23.30%

----End

### Scenario 2: Cross-AZ or Intra-AZ Production

**Step 1** Log in to the client server, go to the `kafka_2.12-2.7.2/bin` directory, and run the following scripts.

**Configure the same AZ for the client and the instance**, and run the following script:

```
./kafka-producer-perf-test.sh --producer-props
bootstrap.servers=192.168.0.69:9092,192.168.0.42:9092,192.168.0.66:9092 acks=1 batch.size=1024
linger.ms=0 --topic Topic-01 --num-records 8000000 --record-size 1024 --throughput 102400
```

Result:

```
8000000 records sent, 34128.673632 records/sec (33.33 MB/sec), 879.91 ms avg latency, 4102.00 ms max latency, 697 ms 50th, 2524 ms 95th, 2888 ms 99th, 4012 ms 99.9th.
```

Message production rate: 34,128 records/second

**Configure different AZs for the client and the instance**, and run the following script:

```
./kafka-producer-perf-test.sh --producer-props
bootstrap.servers=192.168.0.69:9092,192.168.0.42:9092,192.168.0.66:9092 acks=1 batch.size=1024
linger.ms=0 --topic Topic-01 --num-records 4000000 --record-size 1024 --throughput 102400
```

Result:

```
4000000 records sent, 8523.042044 records/sec (8.32 MB/sec), 3506.20 ms avg latency, 11883.00 ms max latency, 1817 ms 50th, 10621 ms 95th, 11177 ms 99th, 11860 ms 99.9th.
```

Message production rate: 8523 records/second

**Step 2** Log in to the Kafka console and click the name of the test instance.

**Step 3** In the navigation pane, choose **Monitoring**.

**Step 4** On the **Brokers** tab page, view the CPU usage of the server nodes.


**Figure 12-7** broker-0 CPU usage (same AZ)



CPU usage: 58.10%



**Figure 12-8** broker-0 CPU usage (different AZs)



CPU usage: 17.20%

**Figure 12-9** broker-1 CPU usage (same AZ)




CPU usage: 56.70%

**Figure 12-10** broker-1 CPU usage (different AZs)



CPU usage: 16.70%

**Figure 12-11** broker-2 CPU usage (same AZ)



CPU usage: 53.30%

**Figure 12-12** broker-2 CPU usage (different AZs)



CPU usage: 18.80%

----End

### Scenario 3: Varied Numbers of Replicas

**Step 1** Log in to the client server, go to the `kafka_2.12-2.7.2/bin` directory, and run the following scripts.

For the **one-replica** topic, run the following script:

```
./kafka-producer-perf-test.sh --producer-props
bootstrap.servers=192.168.0.69:9092,192.168.0.42:9092,192.168.0.66:9092 acks=1 batch.size=1024
linger.ms=0 --topic Topic-01 --num-records 8000000 --record-size 1024 --throughput 102400
```

Result:

```
8000000 records sent, 34128.673632 records/sec (33.33 MB/sec), 879.91 ms avg latency, 4102.00 ms max
latency, 697 ms 50th, 2524 ms 95th, 2888 ms 99th, 4012 ms 99.9th.
```

Message production rate: 34,128 records/second

For the **three-replica** topic, run the following script:

```
./kafka-producer-perf-test.sh --producer-props
bootstrap.servers=192.168.0.69:9092,192.168.0.42:9092,192.168.0.66:9092 acks=1 batch.size=1024
linger.ms=0 --topic Topic-02 --num-records 4000000 --record-size 1024 --throughput 102400
```

Result:

```
4000000 records sent, 14468.325219 records/sec (14.13 MB/sec), 2069.99 ms avg latency, 7911.00 ms max
latency, 846 ms 50th, 6190 ms 95th, 6935 ms 99th, 7879 ms 99.9th.
```


Message production rate: 14,468 records/second

**Step 2** Log in to the Kafka console and click the name of the test instance.

**Step 3** In the navigation pane, choose **Monitoring**.

**Step 4** On the **Brokers** tab page, view the CPU usage of the server nodes.

**Figure 12-13** broker-0 CPU usage (one replica)



CPU usage: 58.10%

**Figure 12-14** broker-0 CPU usage (three replicas)



CPU usage: 86.70%

**Figure 12-15** broker-1 CPU usage (one replica)



CPU usage: 56.70%

**Figure 12-16** broker-1 CPU usage (three replicas)




CPU usage: 80.60%

**Figure 12-17** broker-2 CPU usage (one replica)



CPU usage: 53.30%

**Figure 12-18** broker-2 CPU usage (three replicas)



CPU usage: 86.20%

----End

#### Scenario 4: Synchronous/Asynchronous Replication

**Step 1** Log in to the client server, go to the `kafka_2.12-2.7.2/bin` directory, and run the following scripts.

For **asynchronous replication**, run the following script:

```
./kafka-producer-perf-test.sh --producer-props
bootstrap.servers=192.168.0.69:9092,192.168.0.42:9092,192.168.0.66:9092 acks=1 batch.size=1024
linger.ms=0 --topic Topic-02 --num-records 4000000 --record-size 1024 --throughput 102400
```

Result:

```
4000000 records sent, 14468.325219 records/sec (14.13 MB/sec), 2069.99 ms avg latency, 7911.00 ms max
latency, 846 ms 50th, 6190 ms 95th, 6935 ms 99th, 7879 ms 99.9th.
```

Message production rate: 14,468 records/second

For **synchronous replication**, run the following script:

```
./kafka-producer-perf-test.sh --producer-props
bootstrap.servers=192.168.0.69:9092,192.168.0.42:9092,192.168.0.66:9092 acks=-1 batch.size=1024
linger.ms=0 --topic Topic-03 --num-records 1000000 --record-size 1024 --throughput 102400
```

Result:

1000000 records sent, 3981.937930 records/sec (3.89 MB/sec), 7356.98 ms avg latency, 19013.00 ms max latency, 6423 ms 50th, 14381 ms 95th, 18460 ms 99th, 18975 ms 99.9th.


Message production rate: 3981 records/second

**Step 2** Log in to the Kafka console and click the name of the test instance.

**Step 3** In the navigation pane, choose **Monitoring**.


**Step 4** On the **Brokers** tab page, view the CPU usage of the server nodes.

**Figure 12-19** broker-0 CPU usage (asynchronous replication)




CPU usage: 86.70%

**Figure 12-20** broker-0 CPU usage (synchronous replication)




CPU usage: 60%

**Figure 12-21** broker-1 CPU usage (asynchronous replication)




CPU usage: 80.60%

**Figure 12-22** broker-1 CPU usage (synchronous replication)




CPU usage: 55.20%

**Figure 12-23** broker-2 CPU usage (asynchronous replication)



CPU usage: 86.20%

**Figure 12-24** broker-2 CPU usage (synchronous replication)



CPU usage: 50%

----End

## Result

**Table 12-2** Testing results

| Partitions | Replicas | Synchronous Replication | batch.size | Cross-AZ Production | Message Production Rate on the Client Side (Records/Second) | CPU Usage on the Server Side (broker-0) | CPU Usage on the Server Side (broker-1) | CPU Usage on the Server Side (broker-2) |
|------------|----------|-------------------------|------------|---------------------|-------------------------------------------------------------|-----------------------------------------|-----------------------------------------|-----------------------------------------|
| 3          | 1        | No                      | 1 KB       | No                  | 34,128                                                      | 58.10%                                  | 56.70%                                  | 53.30%                                  |
| 3          | 1        | No                      | 16 KB      | No                  | 102,399                                                     | 24.10%                                  | 25.00%                                  | 23.30%                                  |
| 3          | 1        | No                      | 1 KB       | Yes                 | 8,523                                                       | 17.20%                                  | 16.70%                                  | 18.80%                                  |
| 3          | 3        | Yes                     | 1 KB       | No                  | 3981                                                        | 60.00%                                  | 55.20%                                  | 50.00%                                  |
| 3          | 3        | No                      | 1 KB       | No                  | 14,468                                                      | 86.70%                                  | 80.60%                                  | 86.20%                                  |

Based on the test results, the following conclusions are drawn (for reference only):

- When the **batch.size** of production requests is 16 times larger, the message production rate increases, and the CPU usage decreases.
- Compared with cross-AZ production, intra-AZ production significantly increases message production rate and CPU usage.



- When the number of replicas changes from 1 to 3, the message production rate decreases significantly, and the CPU usage increases.
- Compared with synchronous replication, asynchronous replication increases the message production rate and the CPU usage.

## 12.2 Kafka Instance TPS

TPS tests can be performed in the following scenarios:

- Scenario 1 (whether SASL is enabled): same topic, different SASL settings
- Scenario 2 (synchronous or asynchronous replication): same instance, topics with different replication settings
- Scenario 3 (synchronous or asynchronous flushing): same instance, topics with different flushing settings
- Scenario 4 (disk type): same topic, instances with different disk types
- Scenario 5 (number of partitions): same instance, topics with different number of partitions

### Environment

Perform the following steps to set up the test environment.

1. Purchase Kafka instances with parameters specified in [Table 12-3](#). For more information, see [Buying a Kafka Instance](#).

**Table 12-3** Instance parameters

| Instance Name | Brokers | Broker Flavor        | SASL | Storage space per broker |
|---------------|---------|----------------------|------|--------------------------|
| kafka-01      | 3       | kafka.2u4g.cluster   | Yes  | Ultra-high I/O           |
| kafka-02      | 3       | kafka.4u8g.cluster   | Yes  | Ultra-high I/O           |
| kafka-03      | 3       | kafka.8u16g.cluster  | Yes  | Ultra-high I/O           |
| kafka-04      | 3       | kafka.12u24g.cluster | Yes  | Ultra-high I/O           |
| kafka-05      | 3       | kafka.16u32g.cluster | Yes  | Ultra-high I/O           |
| kafka-06      | 3       | kafka.2u4g.cluster   | No   | Ultra-high I/O           |
| kafka-07      | 3       | kafka.4u8g.cluster   | No   | Ultra-high I/O           |

| Instance Name | Brokers | Broker Flavor        | SASL | Storage space per broker |
|---------------|---------|----------------------|------|--------------------------|
| kafka-08      | 3       | kafka.8u16g.cluster  | No   | Ultra-high I/O           |
| kafka-09      | 3       | kafka.12u24g.cluster | No   | Ultra-high I/O           |
| kafka-10      | 3       | kafka.16u32g.cluster | No   | Ultra-high I/O           |
| kafka-11      | 3       | kafka.2u4g.cluster   | No   | High I/O                 |
| kafka-12      | 3       | kafka.4u8g.cluster   | No   | High I/O                 |
| kafka-13      | 3       | kafka.8u16g.cluster  | No   | High I/O                 |
| kafka-14      | 3       | kafka.12u24g.cluster | No   | High I/O                 |
| kafka-15      | 3       | kafka.16u32g.cluster | No   | High I/O                 |

After the purchase, obtain **Address (Private Network, Plaintext)** on the instance details page.

**Connection**

Username --

Private Network Access

Plaintext Access

Address (Private Network, Plaintext) IPv4 192.168.0...

Ciphertext Access

Public Network Access

Disabled

Only for IPv4.

2. Create topics with parameters specified in [Table 12-4](#) for each instance purchased above. For details about how to create topics, see [Creating a Kafka Topic](#).

**Table 12-4** Topic parameters

| Topic Name | Synchronous Replication | Synchronous Flushing | Replicas | Partitions |
|------------|-------------------------|----------------------|----------|------------|
| topic-01   | No                      | No                   | 3        | 30         |
| topic-02   | Yes                     | No                   | 3        | 30         |
| topic-03   | No                      | Yes                  | 3        | 30         |
| topic-04   | No                      | No                   | 3        | 3          |
| topic-05   | No                      | No                   | 3        | 12         |
| topic-06   | No                      | No                   | 3        | 100        |

3. Obtain the test tool.

Obtain [Kafka CLI v2.7.2](#).

4. Purchase a server for the client.

Buy a Linux ECS (with the same region, AZ, VPC, subnet, and security group as the Kafka instance). For details about how to purchase an ECS, see [Purchasing a Custom ECS](#).

Perform the following operations on the ECSs:

- Install [Java JDK](#) and configure the environment variables **JAVA\_HOME** and **PATH**.  

```
export JAVA_HOME=/root/jdk1.8.0_231
export PATH=$JAVA_HOME/bin:$PATH
```
- Download [Kafka CLI v2.7.2](#) and decompress it.  

```
tar -zxf kafka_2.12-2.7.2.tgz
```

## Script

```
./kafka-producer-perf-test.sh --producer-props bootstrap.servers=${connection address} acks=1
batch.size=16384 linger.ms=10 --topic ${topic name} --num-records 1000000 --record-size 1024 --
throughput -1 --producer.config ../config/producer.properties
```

- **bootstrap.servers**: address of the Kafka instance obtained in [1](#).
- **acks**: message synchronization policy. `acks=1` indicates asynchronous replication, and `acks=-1` indicates synchronous replication.
- **batch.size**: size of messages sent in each batch, in bytes.
- **linger.ms**: interval between two batches.
- **topic**: topic name set in [2](#).
- **num-records**: total number of messages to be sent.
- **record-size**: size of each message.
- **throughput**: number of messages sent per second.

## Result

**Scenario 1 (whether SASL is enabled): same topic (30 partitions, 3 replicas, asynchronous replication, and asynchronous flushing), instances with SASL enabled or disabled. The test result is as follows.**

**Table 12-5** Test results

| Instance Flavor      | Storage space per broker | Brokers | TPS (SASL Enabled) | TPS (SASL Disabled) |
|----------------------|--------------------------|---------|--------------------|---------------------|
| kafka.2u4g.cluster   | Ultra-high I/O           | 3       | 100,000            | 280,000             |
| kafka.4u8g.cluster   | Ultra-high I/O           | 3       | 170,000            | 496,000             |
| kafka.8u16g.cluster  | Ultra-high I/O           | 3       | 200,000            | 730,000             |
| kafka.12u24g.cluster | Ultra-high I/O           | 3       | 320,000            | 790,000             |
| kafka.16u32g.cluster | Ultra-high I/O           | 3       | 360,000            | 1,000,000           |

Conclusion: When messages are produced to Kafka instances with the same flavor and topic but different access modes, instances without SASL show higher TPS than those with SASL.

**Scenario 2 (synchronous/asynchronous replication): same instance (ultra-high I/O, three brokers, SASL disabled), topics with different replication settings, and number of producer processes is three. The test result is as follows.**

**Table 12-6** Test results

| Instance Flavor      | Synchronous Flushing | Replicas | Partitions | TPS (Synchronous Replication) | TPS (Asynchronous Replication) |
|----------------------|----------------------|----------|------------|-------------------------------|--------------------------------|
| kafka.2u4g.cluster   | No                   | 3        | 30         | 100,000                       | 280,000                        |
| kafka.4u8g.cluster   | No                   | 3        | 30         | 230,000                       | 496,000                        |
| kafka.8u16g.cluster  | No                   | 3        | 30         | 342,000                       | 730,000                        |
| kafka.12u24g.cluster | No                   | 3        | 30         | 383,000                       | 790,000                        |
| kafka.16u32g.cluster | No                   | 3        | 30         | 485,000                       | 1,000,000                      |

Conclusion: When messages are produced to different topics of a Kafka instance, topics with asynchronous replication show higher TPS than those with synchronous replication when other topic parameters are the same.

**Scenario 3 (synchronous/asynchronous replication flushing): same instance (ultra-high I/O, three brokers, SASL disabled), topics with different flushing settings. The test result is as follows.**

**Table 12-7** Test results

| Instance Flavor      | Synchronous Replication | Replicas | Partitions | TPS (Synchronous Flushing) | TPS (Asynchronous Flushing) |
|----------------------|-------------------------|----------|------------|----------------------------|-----------------------------|
| kafka.2u4g.cluster   | No                      | 3        | 30         | 30,000                     | 280,000                     |
| kafka.4u8g.cluster   | No                      | 3        | 30         | 32,500                     | 496,000                     |
| kafka.8u16g.cluster  | No                      | 3        | 30         | 36,100                     | 730,000                     |
| kafka.12u24g.cluster | No                      | 3        | 30         | 37,400                     | 790,000                     |
| kafka.16u32g.cluster | No                      | 3        | 30         | 40,400                     | 1,000,000                   |

Conclusion: When messages are produced to different topics of a Kafka instance, topics with asynchronous flushing show significantly higher TPS than those with synchronous flushing when other topic parameters are the same.

**Scenario 4 (different disk types): same topic (30 partitions, 3 replicas, asynchronous replication, and asynchronous flushing) with different disk types. The test result is as follows.**

**Table 12-8** Test results

| Instance Flavor      | Brokers | SASL | TPS (High I/O) | TPS (Ultra-High I/O) |
|----------------------|---------|------|----------------|----------------------|
| kafka.2u4g.cluster   | 3       | No   | 110,000        | 250,000              |
| kafka.4u8g.cluster   | 3       | No   | 135,000        | 380,000              |
| kafka.8u16g.cluster  | 3       | No   | 213,000        | 480,000              |
| kafka.12u24g.cluster | 3       | No   | 240,000        | 577,000              |

| Instance Flavor      | Brokers | SASL | TPS (High I/O) | TPS (Ultra-High I/O) |
|----------------------|---------|------|----------------|----------------------|
| kafka.16u32g.cluster | 3       | No   | 280,000        | 840,000              |

Conclusion: When messages are produced to the same topics of Kafka instances with the same flavor but different disk types, instances with ultra-high I/O disks show higher TPS than those with high I/O disks.

**Scenario 5 (different numbers of partitions): same instance (ultra-high I/O, three brokers, SASL disabled), topics with different number of partitions. The test result is as follows.**

**Table 12-9** Test results

| Instance Flavor      | Synchronous Flushing | Synchronous Replication | Replicas | TPS (3 Partitions) | TPS (12 Partitions) | TPS (100 Partitions) |
|----------------------|----------------------|-------------------------|----------|--------------------|---------------------|----------------------|
| kafka.2u4g.cluster   | No                   | No                      | 3        | 250,000            | 260,000             | 250,000              |
| kafka.4u8g.cluster   | No                   | No                      | 3        | 330,000            | 280,000             | 260,000              |
| kafka.8u16g.cluster  | No                   | No                      | 3        | 480,000            | 410,000             | 340,000              |
| kafka.12u24g.cluster | No                   | No                      | 3        | 570,000            | 750,000             | 520,000              |
| kafka.16u32g.cluster | No                   | No                      | 3        | 840,000            | 1,000,000           | 630,000              |

Conclusion: When messages are produced to topics with different partition quantities of a Kafka instance, instances with more partitions show higher performance when other parameters are the same. However, performance reaches a peak and then deteriorates when partitions continue to increase.

# 13 Applying for Increasing Kafka Quotas

---

## What Is a Quota?

A quota is a limit on the quantity or capacity of a certain type of service resources that you can use, for example, the maximum number of Kafka instances that you can create.

If a quota cannot meet your needs, apply for a higher quota.

## How Do I View My Quota?



1. Log in to the console.
2. Click  in the upper left corner to select a region and a project.
3. In the upper right corner of the page, choose **Resources** > **My Quotas**.  
The **Quotas** page is displayed.

Figure 13-1 My Quotas



4. On the **Quotas** page, view the used and total quotas of resources.  
If a quota cannot meet your needs, apply for a higher quota by performing the following operations.

## How Do I Increase My Quota?

1. Log in to the console.
2. In the upper right corner of the page, choose **Resources > My Quotas**.  
The **Service Quota** page is displayed.
3. Click **Increase Quota**.
4. On the **Create Service Ticket** page, set the parameters.  
In the **Problem Description** area, enter the required quota and the reason for the quota adjustment.
5. Read the agreements and confirm that you agree to them, and then click **Submit**.



# 14 Monitoring and Alarms

---

## 14.1 Viewing Kafka Metrics


Cloud Eye monitors Kafka instance metrics in real time. You can view each and key metrics on the Cloud Eye console.


### Prerequisite

At least one Kafka instance has been created. The instance has at least one available message.

### Procedure

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** View the instance metrics in either of the following ways:

- In the row containing the desired instance, click **View Metric**. On the Cloud Eye console, view the metrics. Metric data is reported to Cloud Eye every minute.
- Click the desired instance to go to the instance details page. In the navigation pane, choose **Monitoring and Alarms > Monitoring Details**. On the displayed page, view the monitoring data. The data is updated every minute.

Click the following dimensions to view monitoring data:


- Single-node instance: **By Instance, By Broker, By Topic, or By Consumer Group**.


- Cluster instance: **By Instance, By Broker, By Topic, By Consumer Group, or By Smart Connect.**

----End

## Viewing Top Kafka KPI Data

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired instance to go to the instance details page.


**Step 6** In the navigation pane, choose **Monitoring and Alarms > Monitoring Overview**.

**Step 7** In the **KPI Rankings** area, check the top 5, top 10, and top 20 data by consumer group, topic, and broker.

**Table 14-1** KPI list

| Dimension         | Key Metric                                                                                                                                              |
|-------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------|
| By Consumer Group | <ul style="list-style-type: none"> <li>• Accumulated Messages</li> <li>• Consumer Retrieved Messages</li> </ul>                                         |
| By Topic          | <ul style="list-style-type: none"> <li>• Total Messages</li> <li>• Message Creation</li> <li>• Message Retrieval</li> </ul>                             |
| Broker            | <ul style="list-style-type: none"> <li>• CPU Usage</li> <li>• Network Bandwidth Usage</li> <li>• Disk Read Speed</li> <li>• Disk Write Speed</li> </ul> |

**Figure 14-1** KPI ranking



----End

## 14.2 Kafka Metrics

### Introduction

This section describes metrics reported by DMS for Kafka to Cloud Eye as well as their namespaces and dimensions. You can use the Cloud Eye console or [APIs](#) to query the Kafka metrics and alarms, or view Kafka instance metrics on the **Monitoring** page of the DMS for Kafka console.

For example, you can call the [API](#) to query the monitoring data of the **Disk Capacity Usage** metric.

### Namespace

SYS.DMS

### Instance Metrics

**Table 14-2** Instance metrics

| Metric ID          | Metric Name | Description                                              | Value Range | Monitored Object | Monitoring Period (Raw Data) |
|--------------------|-------------|----------------------------------------------------------|-------------|------------------|------------------------------|
| current_partitions | Partitions  | Number of used partitions in the instance<br>Unit: Count | 0–100,000   | Kafka instance   | 1 minute                     |

| Metric ID                | Metric Name          | Description                                                                                                                                                                                                    | Value Range     | Monitored Object | Monitoring Period (Raw Data) |
|--------------------------|----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------|------------------|------------------------------|
| current_topics           | Topics               | Number of created topics in the instance<br>Unit: Count                                                                                                                                                        | 0–100,000       | Kafka instance   | 1 minute                     |
| group_msgs               | Accumulated Messages | Total number of accumulated messages in all consumer groups of the instance<br>Unit: Count                                                                                                                     | 0–1,000,000,000 | Kafka instance   | 1 minute                     |
| instance_bytes_in_rate   | Message Production   | Number of bytes produced in the instance per second<br>Unit: Byte/s, KiB/s, MiB/s, GiB/s, TiB/s, PiB/s<br>Some instances do not support this metric. Check whether your instance supports it on the console.   | 0–1,000,000     | Kafka instance   | 1 minute                     |
| instance_bytes_out_rate  | Message Consumption  | Number of bytes consumed from the instance per second<br>Unit: Byte/s, KiB/s, MiB/s, GiB/s, TiB/s, PiB/s<br>Some instances do not support this metric. Check whether your instance supports it on the console. | 0–1,000,000     | Kafka instance   | 1 minute                     |
| current_partitions_usage | Partition Usage      | Partition usage<br>Unit: %<br>Some instances do not support this metric. Check whether your instance supports it on the console.                                                                               | 0–100           | Kafka instance   | 1 minute                     |

## Broker Metrics

Enabling Smart Connect for a Kafka instance creates two or more brokers. On the **By Broker** tab page, select "connector" for **Node Type** for Smart Connect broker metrics, or select "broker" for **Node Type** for Kafka instance broker metrics.

Metrics of Smart Connect brokers: disk capacity usage, memory usage, JVM heap memory usage, node alive status, and connections.

**Table 14-3** Broker metrics

| Metric ID               | Metric Name                                   | Description                                                                           | Value Range         | Monitor Object        | Monitoring Period (Raw Data) |
|-------------------------|-----------------------------------------------|---------------------------------------------------------------------------------------|---------------------|-----------------------|------------------------------|
| broker_data_size        | Message Size                                  | Total size of messages in the broker<br>Unit: byte, KB, MB, GB, TB or PB              | 0–5,000,000,000,000 | Kafka instance broker | 1 minute                     |
| broker_messages_in_rate | Message Creation Rate                         | Number of messages created per second<br>Unit: count/s                                | 0–500,000           | Kafka instance broker | 1 minute                     |
| broker_bytes_out_rate   | Message Retrieval                             | Number of bytes retrieved per second<br>Unit: byte/s, KB/s, MB/s, or GB/s             | 0–500,000,000       | Kafka instance broker | 1 minute                     |
| broker_bytes_in_rate    | Message Creation                              | Number of bytes created per second<br>Unit: byte/s, KB/s, MB/s, or GB/s               | 0–500,000,000       | Kafka instance broker | 1 minute                     |
| broker_fetch_mean       | Average Message Retrieval Processing Duration | Average time that the broker spends processing message retrieval requests<br>Unit: ms | 0–10,000            | Kafka instance broker | 1 minute                     |

| Metric ID            | Metric Name                                  | Description                                                                                                      | Value Range                                                                                        | Monitored Object      | Monitoring Period (Raw Data) |
|----------------------|----------------------------------------------|------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------|-----------------------|------------------------------|
| broker_produce_mean  | Average Message Creation Processing Duration | Average time that the broker spends processing message creation requests<br>Unit: ms                             | 0-10,000                                                                                           | Kafka instance broker | 1 minute                     |
| broker_cpu_core_load | Average Load per CPU Core                    | Average load of each CPU core of the Kafka VM<br>Unit: %                                                         | 0-20                                                                                               | Kafka instance broker | 1 minute                     |
| broker_disk_usage    | Disk Capacity Usage                          | Disk usage of the Kafka VM<br>Unit: %                                                                            | 0-100                                                                                              | Kafka instance broker | 1 minute                     |
| broker_memory_usage  | Memory Usage                                 | Memory usage of the Kafka VM<br>Unit: %                                                                          | 0-100                                                                                              | Kafka instance broker | 1 minute                     |
| broker_heap_usage    | JVM Heap Memory Usage of Kafka               | Heap memory usage of the Kafka JVM<br>Unit: %                                                                    | 0-100                                                                                              | Kafka instance broker | 1 minute                     |
| broker_alive         | Broker Alive                                 | Whether the Kafka broker is alive<br><br>This metric is supported by instances purchased in April 2020 or later. | <ul style="list-style-type: none"> <li>● <b>1</b>: alive</li> <li>● <b>0</b>: not alive</li> </ul> | Kafka instance broker | 1 minute                     |

| Metric ID                  | Metric Name             | Description                                                                                                                                          | Value Range     | Monitored Object      | Monitoring Period (Raw Data) |
|----------------------------|-------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------|-----------------------|------------------------------|
| broker_connections         | Connections             | Total number of TCP connections on the Kafka broker<br>Unit: count<br>This metric is supported by instances purchased in April 2020 or later.        | 0-65,535        | Kafka instance broker | 1 minute                     |
| broker_cpu_usage           | CPU Usage               | CPU usage of the Kafka VM<br>Unit: %<br>This metric is supported by instances purchased in April 2020 or later.                                      | 0-100           | Kafka instance broker | 1 minute                     |
| broker_disk_read_await     | Average Disk Read Time  | Average time for each disk I/O read in the monitoring period<br>Unit: ms<br>This metric is supported for instances purchased in June 2020 or later.  | > 0             | Kafka instance broker | 1 minute                     |
| broker_disk_write_await    | Average Disk Write Time | Average time for each disk I/O write in the monitoring period<br>Unit: ms<br>This metric is supported for instances purchased in June 2020 or later. | > 0             | Kafka instance broker | 1 minute                     |
| broker_total_bytes_in_rate | Inbound Traffic         | Inbound traffic per second<br>Unit: byte/s<br>This metric is supported for instances purchased in June 2020 or later.                                | 0-1,000,000,000 | Kafka instance broker | 1 minute                     |

| Metric ID                   | Metric Name             | Description                                                                                                                                                                                                                                                                                      | Value Range     | Monitored Object      | Monitoring Period (Raw Data) |
|-----------------------------|-------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------|-----------------------|------------------------------|
| broker_total_bytes_out_rate | Outbound Traffic        | Outbound traffic per second<br>Unit: byte/s<br>This metric is supported for instances purchased in June 2020 or later.                                                                                                                                                                           | 0–1,000,000,000 | Kafka instance broker | 1 minute                     |
| broker_disk_read_rate       | Disk Read Speed         | Read traffic on the disk<br>Unit: byte/s, KB/s, MB/s, or GB/s<br>This metric is supported for instances purchased on or after May 16, 2022.                                                                                                                                                      | ≥ 0             | Kafka instance broker | 1 minute                     |
| broker_disk_write_rate      | Disk Write Speed        | Write traffic on the disk<br>Unit: byte/s, KB/s, MB/s, or GB/s<br>This metric is supported for instances purchased on or after May 16, 2022.                                                                                                                                                     | ≥ 0             | Kafka instance broker | 1 minute                     |
| network_bandwidth_usage     | Network Bandwidth Usage | Network bandwidth usage<br>Unit: %<br>This metric is supported only: <ul style="list-style-type: none"> <li>For instances purchased since July 9 2023.</li> <li>For instances purchased before July 9 2023, this metric is supported for brokers if they are added since July 9 2023.</li> </ul> | 0–100           | Kafka instance broker | 1 minute                     |



## Topic Metrics

**Table 14-4** Topic metrics

| Metric ID            | Metric Name       | Description                                                                                                                                                                                               | Value Range         | Monitored Object          | Monitoring Period (Raw Data) |
|----------------------|-------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------|---------------------------|------------------------------|
| topic_bytes_in_rate  | Message Creation  | Number of bytes created per second<br>Unit: byte/s, KB/s, MB/s, or GB/s<br>This metric is available only when <b>Monitoring Type</b> is set to <b>Basic monitoring</b> on the <b>By Topic</b> tab page.   | 0–500,000,000       | Topic in a Kafka instance | 1 minute                     |
| topic_bytes_out_rate | Message Retrieval | Number of bytes retrieved per second<br>Unit: byte/s, KB/s, MB/s, or GB/s<br>This metric is available only when <b>Monitoring Type</b> is set to <b>Basic monitoring</b> on the <b>By Topic</b> tab page. | 0–500,000,000       | Topic in a Kafka instance | 1 minute                     |
| topic_data_size      | Message Size      | Total size of messages in the queue<br>Unit: byte, KB, MB, GB, TB or PB<br>This metric is available only when <b>Monitoring Type</b> is set to <b>Basic monitoring</b> on the <b>By Topic</b> tab page.   | 0–5,000,000,000,000 | Topic in a Kafka instance | 1 minute                     |
| topic_messages       | Total Messages    | Total number of messages in the queue<br>Unit: count<br>This metric is available only when <b>Monitoring Type</b> is set to <b>Basic monitoring</b> on the <b>By Topic</b> tab page.                      | ≥ 0                 | Topic in a Kafka instance | 1 minute                     |

| Metric ID              | Metric Name           | Description                                                                                                                                                                                  | Value Range | Monitored Object          | Monitoring Period (Raw Data) |
|------------------------|-----------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------|---------------------------|------------------------------|
| topic_messages_in_rate | Message Creation Rate | Number of messages created per second<br>Unit: count/s<br>This metric is available only when <b>Monitoring Type</b> is set to <b>Basic monitoring</b> on the <b>By Topic</b> tab page.       | 0-500,000   | Topic in a Kafka instance | 1 minute                     |
| partition_messages     | Partition Messages    | Total number of messages in the partition<br>Unit: count<br>This metric is available only when <b>Monitoring Type</b> is set to <b>Partition monitoring</b> on the <b>By Topic</b> tab page. | $\geq 0$    | Topic in a Kafka instance | 1 minute                     |
| produced_messages      | Created Messages      | Number of messages that have been created<br>Unit: count<br>This metric is available only when <b>Monitoring Type</b> is set to <b>Partition monitoring</b> on the <b>By Topic</b> tab page. | $\geq 0$    | Topic in a Kafka instance | 1 minute                     |

## Consumer Group Metrics

Table 14-5 Consumer group metrics

| Metric ID                 | Metric Name                | Description                                                                                                                                                                                                                                                                                                    | Value Range     | Monitor ed Object                   | Mo nitor ing Peri od (Ra w Dat a) |
|---------------------------|----------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------|-------------------------------------|-----------------------------------|
| messag es_cons umed       | Retriev ed Messag es       | Number of messages that have been retrieved in the consumer group<br>Unit: count<br><br>This metric is available only when <b>Topic</b> is set to a specific topic name and <b>Monitoring Type</b> is set to <b>Partition monitoring</b> on the <b>By Consumer Group</b> tab page.                             | $\geq 0$        | Consum er group of a Kafka instance | 1 min ute                         |
| messag es_rem ained       | Availab le Messag es       | Number of messages that can be retrieved in the consumer group<br>Unit: count<br><br>This metric is available only when <b>Topic</b> is set to a specific topic name and <b>Monitoring Type</b> is set to <b>Partition monitoring</b> on the <b>By Consumer Group</b> tab page.                                | $\geq 0$        | Consum er group of a Kafka instance | 1 min ute                         |
| topic_messag es_rem ained | Topic Availab le Messag es | Number of remaining messages that can be retrieved from the specified topic in the consumer group<br>Unit: Count<br><br>This metric is available only when <b>Topic</b> is set to a specific topic name and <b>Monitoring Type</b> is set to <b>Basic monitoring</b> on the <b>By Consumer Group</b> tab page. | 0 to $2^{63}-1$ | Consum er group of a Kafka instance | 1 min ute                         |

| Metric ID                   | Metric Name                                        | Description                                                                                                                                                                                                                                                                                             | Value Range     | Monitored Object                   | Monitoring Period (Raw Data) |
|-----------------------------|----------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------|------------------------------------|------------------------------|
| topic_messages_consumed     | Topic Retrieved Messages                           | Number of messages that have been retrieved from the specified topic in the consumer group<br>Unit: Count<br><br>This metric is available only when <b>Topic</b> is set to a specific topic name and <b>Monitoring Type</b> is set to <b>Basic monitoring</b> on the <b>By Consumer Group</b> tab page. | 0 to $2^{63}-1$ | Consumer group of a Kafka instance | 1 minute                     |
| consumer_messages_remaining | Accumulated Messages (Consumer Available Messages) | Number of remaining messages that can be retrieved in the consumer group<br>Unit: Count<br><br>This metric is available only when <b>Topic</b> is set to <b>All topics</b> on the <b>By Consumer Group</b> tab page.                                                                                    | 0 to $2^{63}-1$ | Consumer group of a Kafka instance | 1 minute                     |
| consumer_messages_consumed  | Consumer Retrieved Messages                        | Number of messages that have been retrieved in the consumer group<br>Unit: Count<br><br>This metric is available only when <b>Topic</b> is set to <b>All topics</b> on the <b>By Consumer Group</b> tab page.                                                                                           | 0 to $2^{63}-1$ | Consumer group of a Kafka instance | 1 minute                     |

| Metric ID                          | Metric Name                | Description                                                                                                                                                                                                                                                                                                                                                                                                                                    | Value Range  | Monitored Object                   | Monitoring Period (Raw Data) |
|------------------------------------|----------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------|------------------------------------|------------------------------|
| messages_consumed_per_minute       | Partition Consumption Rate | <p>Number of messages consumed from the specified queue partition in the consumer group every minute</p> <p>Unit: count/minute</p> <p>This metric is available only when <b>Topic</b> is set to a specific topic name and <b>Monitoring Type</b> is set to <b>Partition monitoring</b> on the <b>By Consumer Group</b> tab page.</p> <p>Some instances do not support this metric. Check whether your instance supports it on the console.</p> | 0–30,000,000 | Consumer group of a Kafka instance | 1 minute                     |
| topic_messages_consumed_per_minute | Queue Consumption Rate     | <p>Number of messages consumed from the specified queue in the consumer group every minute</p> <p>Unit: count/minute</p> <p>This metric is available only when <b>Topic</b> is set to a specific topic name and <b>Monitoring Type</b> is set to <b>Basic monitoring</b> on the <b>By Consumer Group</b> tab page.</p> <p>Some instances do not support this metric. Check whether your instance supports it on the console.</p>               | 0–30,000,000 | Consumer group of a Kafka instance | 1 minute                     |

| Metric ID                          | Metric Name                     | Description                                                                                                                                                                                                                                                                                                                              | Value Range  | Monitored Object                   | Monitoring Period (Raw Data) |
|------------------------------------|---------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------|------------------------------------|------------------------------|
| consumer_messages_consumed_per_min | Consumer Group Consumption Rate | <p>Number of messages consumed from the consumer group every minute</p> <p>Unit: count/minute</p> <p>This metric is available only when <b>Topic</b> is set to <b>All topics</b> on the <b>By Consumer Group</b> tab page.</p> <p>Some instances do not support this metric. Check whether your instance supports it on the console.</p> | 0–30,000,000 | Consumer group of a Kafka instance | 1 minute                     |

## Smart Connect Metrics

Smart Connect metrics are only available for cluster instances.

**Table 14-6** Smart Connect metrics

| Metric ID                   | Metric Name                  | Description                                                                        | Value Range | Monitored Object                       | Monitoring Period (Raw Data) |
|-----------------------------|------------------------------|------------------------------------------------------------------------------------|-------------|----------------------------------------|------------------------------|
| kafka_wait_synchronize_data | Kafka Data to Sync           | <p>Data to synchronize in the Kafka migration task</p> <p>Unit: count</p>          | $\geq 0$    | Smart Connect task of a Kafka instance | 1 minute                     |
| kafka_synchronize_rate      | Kafka Data Synced per Minute | <p>Data synchronized per minute in the Kafka migration task</p> <p>Unit: count</p> | $\geq 0$    | Smart Connect task of a Kafka instance | 1 minute                     |

| Metric ID     | Metric Name   | Description                                                                                        | Value Range                                                                          | Monitored Object                       | Monitoring Period (Raw Data) |
|---------------|---------------|----------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------|----------------------------------------|------------------------------|
| task_status   | Task Status   | Status of the current task                                                                         | <ul style="list-style-type: none"> <li>• 0: abnormal</li> <li>• 1: normal</li> </ul> | Smart Connect task of a Kafka instance | 1 minute                     |
| message_delay | Message Delay | Time elapsed between when a message is sent from the source and received by the target<br>Unit: ms | ≥ 0                                                                                  | Smart Connect task of a Kafka instance | 1 minute                     |

Precautions:

- A Smart Connect task that bidirectionally copies Kafka data is split into two tasks for monitoring: *Smart Connect task name\_source\_0* and *Smart Connect task name\_source\_1*.
- If all messages in a topic have aged before the next synchronization, there is no Kafka data to be synchronized. However, since the Kafka data synchronization metric uses the offset value that contains aged data, **Kafka Data Synced per Minute** will display the number of aged messages.

## Dimension

| Key                     | Value                                        |
|-------------------------|----------------------------------------------|
| kafka_instance_id       | Kafka instance                               |
| kafka_broker            | Kafka instance broker                        |
| kafka_topics            | Kafka instance topic                         |
| kafka_partitions        | Partition in a Kafka instance                |
| kafka_groups-partitions | Partition consumer group in a Kafka instance |
| kafka_groups_topics     | Topic consumer group in a Kafka instance     |
| kafka_groups            | Consumer group of a Kafka instance           |
| connector_task          | Smart Connect task of a Kafka instance       |

## 14.3 Configuring a Kafka Alarm Rule

This section describes the alarm rules of some metrics and how to configure them. In actual services, you are advised to configure alarm rules for metrics based on the following alarm policies:

**Table 14-7** Alarm policies and handling of Kafka instances

| Metric ID            | Metric                    | Monitored Object | Alarm Policy                                                                                          | Description                                    | Handling Suggestion                                                                                                                                                                                                                          |
|----------------------|---------------------------|------------------|-------------------------------------------------------------------------------------------------------|------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| broker_disk_usage    | Disk Capacity Usage       | Broker           | Alarm threshold: original value > 80%<br>Number of consecutive periods: 1<br>Alarm severity: critical | Disk usage of the Kafka VM                     | Modify the instance <b>storage space</b> . For details, see <a href="#">Modifying Instance Specifications</a> .                                                                                                                              |
| broker_cpu_core_load | Average Load per CPU Core | Broker           | Alarm threshold: original value > 2<br>Number of consecutive periods: 3<br>Alarm severity: major      | Average load of each CPU core of the Kafka VM. | Check whether the metric has been approaching or exceeding the alarm threshold for a long time. If yes, modify the instance <b>bandwidth or the number of brokers</b> . For details, see <a href="#">Modifying Instance Specifications</a> . |
| broker_memory_usage  | Memory Usage              | Broker           | Alarm threshold: original value > 90%<br>Number of consecutive periods: 3<br>Alarm severity: critical | Memory usage of the Kafka VM.                  | Modify the instance <b>bandwidth or the number of brokers</b> . For details, see <a href="#">Modifying Instance Specifications</a> .                                                                                                         |




| Metric ID          | Metric     | Monitored Object | Alarm Policy                                                                                                                                                                                                                                                                         | Description                                | Handling Suggestion                                                                                                                                                                                                                                                              |
|--------------------|------------|------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| current_partitions | Partitions | Instance         | <p>Alarm threshold: original value &gt; 90% of the maximum allowed number of partitions. The partition limit varies depending on instance specifications. For details, see <a href="#">Specification s</a>.</p> <p>Number of consecutive periods: 1</p> <p>Alarm severity: major</p> | Number of used partitions in the instance. | If new topics are required, modify the instance <b>bandwidth or the number of brokers</b> , or split the service to multiple instances. For details about how to modify the instance bandwidth or the number of brokers, see <a href="#">Modifying Instance Specifications</a> . |
| broker_cpu_usage   | CPU Usage  | Broker           | <p>Alarm threshold: original value &gt; 90%</p> <p>Number of consecutive periods: 3</p> <p>Alarm severity: major</p>                                                                                                                                                                 | CPU usage of the Kafka VM.                 | Check whether the metric has been approaching or exceeding the alarm threshold for a long time. If yes, modify the instance <b>bandwidth or the number of brokers</b> . For details, see <a href="#">Modifying Instance Specifications</a> .                                     |


| Metric ID              | Metric                   | Monitored Object | Alarm Policy                                                                                                                                          | Description                                                                                        | Handling Suggestion                                                                                                                                                                                                                                                                                                        |
|------------------------|--------------------------|------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| group_msgs             | Accumulated Messages     | Instance         | Alarm threshold: original value > 90% of the upper limit. The upper limit is customized.<br>Number of consecutive periods: 1<br>Alarm severity: major | Total number of accumulated messages in all consumer groups of the instance                        | Delete idle consumer groups, if any. You can also accelerate message retrieval, for example, by increasing the number of consumers.                                                                                                                                                                                        |
| topic_messages_remaind | Topic Available Messages | Consumer group   | Alarm threshold: original value > 90% of the upper limit. The upper limit is customized.<br>Number of consecutive periods: 1<br>Alarm severity: major | Number of remaining messages that can be retrieved from the specified topic in the consumer group. | Check whether the consumer code logic is correct, for example, by checking whether the consumer stops consuming messages due to an exception. You can also accelerate message retrieval, for example, by adding topic consumers. Ensure that the number of partitions is greater than or equal to the number of consumers. |

## Configuring Kafka Alarm Rules

The following section describes how to configure alarm rules for a specified Kafka instance.

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.

**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Go to the monitoring page in either of the following ways:

- Click **View Metric** in the row containing the desired Kafka instance.
- Click the desired Kafka instance to go to the instance details page. Choose **Monitoring and Alarms > Monitoring Details** in the navigation pane.

**Step 6** Hover the mouse pointer over a metric and click **+** to create an alarm rule for the metric. The **Create Alarm Rule** page is displayed.


**Step 7** Specify the alarm details.

For more information about creating alarm rules, see [Creating an Alarm Rule](#).

1. Set the alarm name and description.
2. Set the alarm policy.

As shown in the following figure, if the original disk capacity usage is equal to or higher than 80% for consecutive once, an alarm is generated. If the alarm is not handled on time, an alarm notification is sent.

**Figure 14-2** Setting the alarm policy



3. Set the alarm notification configurations.

If you enable **Alarm Notification**, specify **Notification Recipient** and **Notification Policies**.


4. Click **Create**.


----End

## Enabling One-Click Monitoring

The following section describes how to enable alarm rules for key metrics of all Kafka instances in a region.

**Step 1** Log in to the console.

**Step 2** Click  in the upper left corner to select the region where your instance is located.

**Step 3** Click  and choose **Middleware > Distributed Message Service (for Kafka)** to open the console of DMS for Kafka.


**Step 4** In the navigation pane, choose **Kafka Instances**.

**Step 5** Click the desired Kafka instance to go to the instance details page.


**Step 6** In the navigation pane, choose **Monitoring and Alarms > Alarms**. The **One-Click Monitoring** tab page is displayed.

**Step 7** By default, the alarm rules are in the **Disable** state. Click **Config** and the **One-Click Monitoring** page is displayed on the Cloud Eye console.

**Figure 14-3** One-click monitoring




**Step 8** Left-click the search box, select **Resource Type**, select **Distributed Message Service** from the drop-down list, and click **OK**.

**Step 9** In the row containing **Distributed Message Service**, click . The **Enable Alarm Rule** dialog box is displayed.

**Step 10** A Kafka instance has two preset alarm rules. See [Table 14-8](#). Enable the alarm rules as required and click **OK**.

**Figure 14-4** Enabling alarm rules



**Table 14-8** Alarm rules

| Alarm Rule                            | Dimension | Policy                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|---------------------------------------|-----------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| alarm-dms-kafka_broker-metric-default | Instance  | <ul style="list-style-type: none"> <li>A major alarm is generated once a day when the raw number of partitions is greater than or equal to 750 for three consecutive periods.</li> <li>A major alarm is generated once a day when the raw number of topics is greater than or equal to 200 for three consecutive periods.</li> <li>A major alarm is generated once a day when the raw number of stacked messages is greater than or equal to 100,000,000 for three consecutive periods.</li> </ul> |

| Alarm Rule                                 | Dimension | Policy                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                           |
|--------------------------------------------|-----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| alarm-dms-kafka_instance_id-metric-default | Broker    | <ul style="list-style-type: none"> <li>● A critical alarm is generated every 10 minutes when the raw average duration per disk write is greater than 5,000 ms for three consecutive periods.</li> <li>● A critical alarm is generated every 10 minutes when the raw average duration per disk read is greater than 5,000 ms for three consecutive periods.</li> <li>● A major alarm is generated every hour when the raw average duration for processing consumption requests is greater than 60,000 ms for three consecutive periods.</li> <li>● A critical alarm is generated every 10 minutes when the raw JVM heap memory usage is greater than 85% for three consecutive periods.</li> <li>● A critical alarm is generated every 10 minutes when the raw disk usage is greater than 85% for three consecutive periods.</li> <li>● A critical alarm is generated every 10 minutes when the raw CPU usage is greater than 85% for three consecutive periods.</li> <li>● A critical alarm is generated every 10 minutes when the raw active status of a broker is less than 1 for three consecutive periods.</li> <li>● A critical alarm is generated every 10 minutes when the raw memory usage is greater than 85% for three consecutive periods.</li> </ul> |

Alarm policies can be modified after one-click monitoring is enabled. For details, see [One-Click Monitoring](#).

**Step 11** Go back to the **One-Click Monitoring** page, click . The alarm rule is in the **Enable** state.



If other Kafka instances are available in this region, their alarm rules are enabled, too.

----End

## Viewing Alarm Rules of a Kafka Instance

The following procedure describes how to query all alarm rules of a specified Kafka instance.

**Step 1** Log in to the console.

- Step 2** Click  in the upper left corner to select the region where your instance is located.
- Step 3** Click  in the upper left corner of the console, choose **Management & Governance > Cloud Eye**.
- Step 4** In the navigation pane, choose **Cloud Service Monitoring**.
- Step 5** Search for "Distributed Message Service" and press **Enter**.
- Step 6** Click **Distributed Message Service DMS**. The **Details** page is displayed.
- Step 7** In the row containing the desired Kafka instance, choose **More > View Alarm Rule**. All alarm rules of this Kafka instance are displayed in the **View Alarm Rule** dialog box.
- End

# 15 Viewing Kafka Audit Logs

With Cloud Trace Service (CTS), you can record operations associated with DMS for Kafka for later query, audit, and backtrack operations.

## Prerequisite

CTS has been enabled.

## DMS for Kafka Operations Supported by CTS

**Table 15-1** DMS for Kafka operations that can be recorded by CTS

| Operation                                                   | Resource Type | Trace Name                             |
|-------------------------------------------------------------|---------------|----------------------------------------|
| Successfully creating an order for creating an instance     | kafka         | createDMSInstanceOrderSuccess          |
| Successfully creating an instance                           | kafka         | createDMSInstanceTaskSuccess           |
| Failing to create an order for creating an instance         | kafka         | createDMSInstanceOrderFailure          |
| Failing to create an instance                               | kafka         | createDMSInstanceTaskFailure           |
| Successfully deleting an instance that failed to be created | kafka         | deleteDMSCreateFailureInstancesSuccess |
| Failing to delete an instance that failed to be created     | kafka         | deleteDMSCreateFailureInstancesFailure |
| Successfully deleting an instance                           | kafka         | deleteDMSInstanceTaskSuccess           |

| Operation                                                                | Resource Type | Trace Name                         |
|--------------------------------------------------------------------------|---------------|------------------------------------|
| Failing to delete an instance                                            | kafka         | deleteDMSInstanceTaskFailure       |
| Deleting multiple instance tasks at a time                               | kafka         | batchDeleteDMSInstanceTask         |
| Successfully submitting a request to delete multiple instances at a time | kafka         | batchDeleteDMSInstanceSuccess      |
| Successfully deleting multiple instances at a time                       | kafka         | batchDeleteDMSInstanceTask-Success |
| Failing to submit a request to delete multiple instances at a time       | kafka         | batchDeleteDMSInstanceFailure      |
| Failing to delete multiple instances at a time                           | kafka         | batchDeleteDMSInstanceTask-Failure |
| Successfully submitting a request to modify an instance order            | kafka         | modifyDMSInstanceOrderSuccess      |
| Failing to submit a request to modify an instance order                  | kafka         | modifyDMSInstanceOrderFailure      |
| Successfully submitting a request to scale up an instance                | kafka         | extendDMSInstanceSuccess           |
| Successfully scaling up an instance                                      | kafka         | extendDMSInstanceTaskSuccess       |
| Failing to submit a request to scale up an instance                      | kafka         | extendDMSInstanceFailure           |
| Failing to scale up an instance                                          | kafka         | extendDMSInstanceTaskFailure       |
| Successfully submitting a request to reset instance password             | kafka         | resetDMSInstancePasswordSuccess    |



| Operation                                                                 | Resource Type | Trace Name                         |
|---------------------------------------------------------------------------|---------------|------------------------------------|
| Failing to submit a request to reset instance password                    | kafka         | resetDMSInstancePasswordFailure    |
| Successfully submitting a request to restart an instance                  | kafka         | restartDMSInstanceSuccess          |
| Successfully restarting an instance                                       | kafka         | restartDMSInstanceTaskSuccess      |
| Failing to submit a request to restart an instance                        | kafka         | restartDMSInstanceFailure          |
| Failing to restart an instance                                            | kafka         | restartDMSInstanceTaskFailure      |
| Successfully submitting a request to restart multiple instances at a time | instance      | batchRestartDMSInstanceSuccess     |
| Successfully restarting multiple instances at a time                      | kafka         | batchRestartDMSInstanceTaskSuccess |
| Failing to submit a request to restart multiple instances at a time       | instance      | batchRestartDMSInstanceFailure     |
| Failing to restart multiple instances at a time                           | kafka         | batchRestartDMSInstanceTaskFailure |
| Successfully submitting a request to modify instance information          | kafka         | modifyDMSInstanceInfoSuccess       |
| Successfully modifying instance information                               | kafka         | modifyDMSInstanceInfoTaskSuccess   |
| Failing to submit a request to modify instance information                | kafka         | modifyDMSInstanceInfoFailure       |
| Failing to modify instance information                                    | kafka         | modifyDMSInstanceInfoTaskFailure   |
| Successfully deleting a background task                                   | kafka         | deleteDMSBackendJobSuccess         |

| Operation                                           | Resource Type | Trace Name                     |
|-----------------------------------------------------|---------------|--------------------------------|
| Failing to delete a background task                 | kafka         | deleteDMSBackendJobFailure     |
| Successfully enabling Smart Connect                 | kafka         | createConnectorTaskSuccess     |
| Successfully creating a Smart Connect task          | kafka         | createConnectorSinkTaskSuccess |
| Failing to enable Smart Connect                     | kafka         | createConnectorTaskFailure     |
| Failing to create a Smart Connect task              | kafka         | createConnectorSinkTaskFailure |
| Successfully freezing an instance                   | kafka         | freezeDMSInstanceTaskSuccess   |
| Failing to freeze an instance                       | kafka         | freezeDMSInstanceTaskFailure   |
| Successfully unfreezing an instance                 | kafka         | unfreezeDMSInstanceTaskSuccess |
| Failing to unfreeze an instance                     | kafka         | unfreezeDMSInstanceTaskFailure |
| Successfully creating a topic for a Kafka instance  | kafka         | Kafka_create_topicSuccess      |
| Failing to create a topic for a Kafka instance      | kafka         | Kafka_create_topicFailure      |
| Successfully deleting a topic from a Kafka instance | kafka         | Kafka_delete_topicsSuccess     |
| Failing to delete a topic for a Kafka instance      | kafka         | Kafka_delete_topicsFailure     |
| Successfully enabling automatic topic creation      | kafka         | enable_auto_topicSuccess       |
| Failing to enable automatic topic creation          | kafka         | enable_auto_topicFailure       |
| Successfully modifying a topic                      | kafka         | Kafka_alter_topicsSuccess      |

| Operation                                                | Resource Type | Trace Name                         |
|----------------------------------------------------------|---------------|------------------------------------|
| Failing to modify a topic                                | kafka         | Kafka_alter_topicsFailure          |
| Successfully reassigning partitions                      | kafka         | kafka_reassignmentTaskSuccess      |
| Failing to reassign partitions                           | kafka         | kafka_reassignmentTaskFailure      |
| Successfully submitting a partition reassignment request | kafka         | kafka_reassignmentSuccess          |
| Failing to submit a partition reassignment request       | kafka         | kafka_reassignmentFailure          |
| Successfully resetting the consumer offset               | kafka         | Kafka_reset_consumer_offsetSuccess |
| Failing to reset the consumer offset                     | kafka         | Kafka_reset_consumer_offsetFailure |
| Successfully deleting consumer groups in batches         | kafka         | Kafka_batch_delete_groupSuccess    |
| Failing to delete consumer groups in batches             | kafka         | Kafka_batch_delete_groupFailure    |
| Successfully creating a user                             | kafka         | createUserSuccess                  |
| Failing to create a user                                 | kafka         | createUserFailure                  |
| Successfully deleting a user                             | kafka         | deleteUserSuccess                  |
| Failing to delete a user                                 | kafka         | deleteUserFailure                  |
| Successfully updating user policies                      | kafka         | updateUserPoliciesTaskSuccess      |
| Failing to update user policies                          | kafka         | updateUserPoliciesTaskFailure      |
| Successfully recovering an instance from Recycle Bin     | kafka         | out_recycleTaskSuccess             |

| Operation                                       | Resource Type | Trace Name             |
|-------------------------------------------------|---------------|------------------------|
| Failing to recover an instance from Recycle Bin | kafka         | out_recycleTaskFailure |

## Viewing Audit Logs

See [Querying Real-Time Traces](#).