

EventGrid

Getting Started

Issue 01
Date 2023-05-06



Copyright © Huawei Cloud Computing Technologies Co., Ltd. 2023. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Cloud Computing Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are the property of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei Cloud and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Huawei Cloud Computing Technologies Co., Ltd.

Address: Huawei Cloud Data Center Jiaoxinggong Road
Qianzhong Avenue
Gui'an New District
Gui Zhou 550029
People's Republic of China

Website: <https://www.huaweicloud.com/intl/en-us/>

Contents

1 Enabling EG and Authorizing Permissions.....	1
2 Sending a Huawei Cloud Service Event.....	3
3 Sending a Custom Event.....	8

1 Enabling EG and Authorizing Permissions

Before using EventGrid (EG), ensure that:

1. You have [registered a Huawei Cloud account and enabled Huawei Cloud services](#).
2. Your account has permission to use EG. For details about how to authorize an account, see [Creating a User and Granting EG Permissions](#).

If you use an IAM user account, contact the Huawei Cloud account administrator to authorize you to use the EG service.

Logging In to the EG Console

Step 1 Log in to Huawei Cloud console.

Step 2 Click  and select a region.



Step 3 Click  in the upper left, and choose EventGrid from the service list to go to the EG console.

Figure 1-1 EG console



----End

2 Sending a Huawei Cloud Service Event

This section describes how to send a Huawei Cloud service event.

Huawei Cloud Object Storage Service (OBS) sends the generated cloud service events to EG. The EG service filters and converts the events based on the filter rule, and triggers the event target (a function in FunctionGraph).

Prerequisites

- You have completed the operations in [1 Enabling EG and Authorizing Permissions](#).
- You have obtained the permission to access OBS and FunctionGraph.

Step 1: Create an Event Target (Create a Function)

Step 1 Log in to the FunctionGraph console.

Step 2 Choose **Functions > Function List** in the navigation pane.

Step 3 Click **Create Function**.

Step 4 Set function parameters, as shown in [Figure 2-1](#). For details about the function parameters, see .

- **Function Type:** Select **Event Function**.
- **Region:** Select the region as required.
- **Function Name:** Enter **test**.
- **Agency:** Select **Use no agency**.
- **Runtime:** Select **Python 2.7**.

Figure 2-1 Creating a function

Basic Information

* Function Type

Event Function HTTP Function

* Region

Regions are geographic areas isolated from each other. Resources are region-specific and cannot be used across regions through internal network connections. For low network latency and quick resource access, select the nearest region.

* Function Name

Enter a function name.

Enter 1 to 60 characters, starting with a letter and ending with a letter or digit. Only letters, digits, hyphens (-), and underscores (_) are allowed.

Agency ?

Use no agency Create Agency

* Enterprise Project ?

default View Enterprise Project

Runtime ?

Python 2.7

Step 5 Click **Create**.

Step 6 On the **Code** tab page of the function details page, enter the following code and click **Deploy**.

```
# -*- coding:utf-8 -*-
import json
def handler (event, context):
    print(json.dumps(event))
    return {
        "statusCode": 200,
        "isBase64Encoded": False,
        "body": json.dumps(event),
        "headers": {
            "Content-Type": "application/json"
        }
    }
```

----End


Step 2: Create an Event Subscription

Subscriptions bind event sources, channels, and targets. Events of sources are routed to targets based on specified rules.

Step 1 Log in to the EG console.

Step 2 In the navigation pane, choose **Event Subscriptions**.

Step 3 Click **Create Event Subscription**.


Step 4 Click  next to the default subscription name.

Step 5 Enter **OfficialEvent** in **Subscription Name**, and click **OK**.

Step 6 Configure an event source.

1. Click **Event Source**, and set event source parameters as shown in [Figure 2-2](#).
 - **Provider**: Select Huawei Cloud.
 - **Event Source**: Select **Object Storage Service (OBS)**.
 - **Filter Rule**: Use the default rule.

Figure 2-2 Setting event source parameters



2. Click **OK**.

Step 7 Configure an event target.

1. Click **Event Target**, and set event target parameters as shown in [Figure 2-3](#).
 - **Provider**: Select **Huawei Cloud**.
 - **Event Target**: Select **FunctionGraph (function computing)**.
 - **Function**: Select **test** (created in [Step 1](#)).
 - **Version**: Select **latest**.
 - **Transform Type**: Select **Pass-through**.

Figure 2-3 Setting event target parameters

The screenshot shows the 'Event Target' configuration page. At the top, there's a header with a globe icon and the text 'Event Target'. Below this, the 'Provider' section has two buttons: 'Huawei Cloud' (selected) and 'Custom'. The 'Event Target' section contains three dropdown menus: 'Event Target' (FunctionGraph (function computing)), 'Function' (test), and 'Version' (latest). The 'Rule' section has three tabs: 'Pass-through' (selected), 'Variables', and 'Constants'. Below the tabs, there's a question mark icon and the text 'Route all content of events to the target.'

2. Click **OK**.

Step 8 Click **Save**.

----End

Step 3: Generate an OBS Event (Create an OBS Bucket)

Step 1 Log in to the OBS console.


Step 2 Click **Create Bucket**.

Step 3 Set bucket parameters, as shown in [Figure 2-4](#). For details about the bucket parameters, see [Creating a Bucket](#).

- **Region:** The value must be the same as the region of the EG service.
- **Bucket Name:** Enter **eg-test**.
- **Default Storage Class:** Select **Standard**.
- **Bucket Policy:** Select **Private**.
- **Default Encryption:** Leave it unselected.

- **Direct Reading:** Select **Disable**.
- **Enterprise Project:** Select **default**.

Figure 2-4 Creating a bucket



Step 4 Click **Create Now** and create a bucket as prompted.

----End

Step 4: View Results


Step 1 Log in to the FunctionGraph console.

Step 2 Choose **Functions > Function List** in the navigation pane.

Step 3 Click the **test** function to go to the function details page.

Step 4 On the **Metrics** tab page, view the number of invocations and running duration.

Figure 2-5 Viewing metrics



----End

3 Sending a Custom Event

This section describes how to send a custom event.

The custom events generated by custom event sources are sent to EG. The EG service filters and converts the custom events based on the filter rule, and triggers the event target (a function in FunctionGraph).

Prerequisites

- You have completed the operations in [1 Enabling EG and Authorizing Permissions](#).
- You have obtained the permission to access FunctionGraph.

Step 1: Create a Custom Channel

Step 1 Log in to the EG console.

Step 2 In the navigation pane, choose **Event Channels**.

Step 3 Click **Create Event Channel**.

Step 4 Enter **channel** in **Name**, and click **OK**.

View the created channel in the **Custom** area, and record the channel ID.

Figure 3-1 Event channel ID



----End

Step 2: Create an Event Source

- Step 1** Log in to the EG console.
- Step 2** In the navigation pane, choose **Event Sources**.
- Step 3** Click **Create Event Source**.
- Step 4** Set event source parameters, as shown in [Figure 3-2](#).
 - **Type:** Select **Existing**.
 - **Channel:** Select the channel created in [Step 1](#).
 - **Name:** Enter **egsdk-source**.

Figure 3-2 Create a source for the custom event

Create Event Source ×

Channel

Type Existing New ?

* Channel C

Basic

* Name

Description

* Type

- Step 5** Click **OK**.
- View this event source on the **Custom** tab.
- End

Step 3: Create an Event Target (Create a Function)

- Step 1** Log in to the FunctionGraph console.
- Step 2** Choose **Functions > Function List** in the navigation pane.
- Step 3** Click **Create Function**.
- Step 4** Set function parameters, as shown in [Figure 3-3](#). For details about the function parameters, see .
 - **Function Type:** Select **Event Function**.

- **Region:** Select the region as required.
- **Function Name:** Enter **test**.
- **Agency:** Select **Use no agency**.
- **Runtime:** Select **Python 2.7**.

Figure 3-3 Creating a function

Basic Information

* Function Type

Event Function HTTP Function

* Region

Regions are geographic areas isolated from each other. Resources are region-specific and cannot be used across regions through internal network connections. For low network latency and quick resource access, select the nearest region.

* Function Name

Enter a function name.

Enter 1 to 60 characters, starting with a letter and ending with a letter or digit. Only letters, digits, hyphens (-), and underscores (_) are allowed.

Agency ?

Use no agency Create Agency

* Enterprise Project ?

default View Enterprise Project

Runtime ?

Python 2.7

Step 5 Click **Create**.

Step 6 On the **Code** tab page of the function details page, enter the following code and click **Deploy**.

```
# -*- coding:utf-8 -*-
import json
def handler (event, context):
    print(json.dumps(event))
    return {
        "statusCode": 200,
        "isBase64Encoded": False,
        "body": json.dumps(event),
        "headers": {
            "Content-Type": "application/json"
        }
    }
```

----End


Step 4: Create an Event Subscription

Subscriptions bind event sources, channels, and targets. Events of sources are routed to targets based on specified rules.

Step 1 Log in to the EG console.

Step 2 In the navigation pane, choose **Event Subscriptions**.

Step 3 Click **Create Event Subscription**.

Step 4 Click  next to the default subscription name.

Step 5 Enter **CustomEvent** in **Subscription Name**, and click **OK**.

Step 6 Configure an event source.

1. Click **Event Source**, and set event source parameters as shown in [Figure 3-4](#).
 - **Provider**: Select **Custom**.
 - **Channel type**: Select **Existing** for **Type**.
 - **Channel configuration**: Select the channel created in [Step 1](#) from **Channel**.
 - **Event source type**: Select **Existing** for **Type**.
 - **Event source configuration**: Select **egsdk-source** (created in [Step 2](#)) from **Event Source**.
 - **Filter Rule**: Retain the default value and record the value of **values**, for example, **egsdk-source** in [Figure 3-4](#).

Figure 3-4 Setting event source parameters

Event Source

Provider

Huawei Cloud Custom

Channel

Type Existing New ?

* Channel channel C

Event Source

Type Existing New ?

* Event Source egsdk-source

* Filter Rule ? [Learn how to configure a filter rule.](#)

```
1 {
2   "source": [
3     {
4       "op": "StringIn",
5       "values": [
6         "egsdk-source"
7       ]
8     }
9   ]
10 }
```

OK Cancel

2. Click **OK**.

Step 7 Configure an event target.

1. Click **Event Target**, and set event target parameters as shown in [Figure 3-5](#).
 - **Provider:** Select **Huawei Cloud**.
 - **Event Target:** Select **FunctionGraph (function computing)**.
 - **Function:** Select **test** (created in [Step 3](#)).
 - **Version:** Select **latest**.
 - **Transform Type:** Select **Pass-through**.

Figure 3-5 Setting event target parameters

The screenshot shows the 'Event Target' configuration page. At the top, there's a title 'Event Target' with a globe icon. Below it, the 'Provider' section has two buttons: 'Huawei Cloud' (selected) and 'Custom'. The 'Event Target' section contains three dropdown menus: 'Event Target' (FunctionGraph (function computing)), 'Function' (test), and 'Version' (latest). The 'Rule' section has three tabs: 'Pass-through' (selected), 'Variables', and 'Constants'. Below the tabs, there's a question mark icon and the text 'Route all content of events to the target.'

2. Click **OK**.

Step 8 Click **Save**.

----End

Step 5: Send a Custom Event

Step 1 Configure a custom event. For details, see [CloudEvents SDK](#).

Modify the following parameters in the sample code for publishing an event:

- **NAME:** IAM username.
- **PASSWORD:** IAM user password.
- **DOMAIN_NAME:** Account name.
- **IAM_ENDPOINT:** IAM endpoint. For details, see "Regions and Endpoints".
- **PROJECT_ID:** Project ID. For details about how to obtain a project ID, see [API Credentials](#)
- **CHANNEL_ID:** Change the value to the channel ID recorded in [Step 1](#).

- **ENDPOINT:** EG [endpoint](#).
- **SOURCE:** Event source name. Change it to the value of **values** in **Filter** recorded in [Step 4](#).

★ Filter Rule ⓘ Learn how to configure a filter rule.

```
1 {
2   "source": [
3     {
4       "op": "StringIn",
5       "values": [
6         "egsdk-source"
7       ]
8     }
9   ]
10 }
```

- **TIME:** Time when the event is generated.
- **DATA:** Event content that complies with the [CloudEvents 1.0](#) specifications. Modify this parameter based on service requirements.

Step 2 Run the main function to publish the event.

----End

Step 6: View Results


Step 1 Log in to the FunctionGraph console.

Step 2 Choose **Functions > Function List** in the navigation pane.

Step 3 Click the **test** function to go to the function details page.

Step 4 On the **Metrics** tab page, view the number of invocations and running duration.

Figure 3-6 Viewing metrics



----End