

**IAM Identity Center**

# Getting Started

<b>Issue</b>	01
<b>Date</b>	2025-08-25



**Copyright © Huawei Technologies Co., Ltd. 2025. All rights reserved.**

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

## **Trademarks and Permissions**



HUAWEI and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

## **Notice**

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

# Security Declaration

## Vulnerability

Huawei's regulations on product vulnerability management are subject to the *Vul. Response Process*. For details about this process, visit the following web page:

<https://www.huawei.com/en/psirt/vul-response-process>

For vulnerability information, enterprise customers can visit the following web page:

<https://securitybulletin.huawei.com/enterprise/en/security-advisory>

---

# Contents

1 Overview.....

2 Making Preparations.....

3 Creating Users and Permission Sets.....

4 Associating Accounts with Users and Permission Sets.....

5 Logging In as an IAM Identity Center User and Accessing Resources.....

1

3

5

11

15


# 1 Overview

---

Read this chapter if you are using IAM Identity Center for the first time. It helps you quickly familiarize yourself with the main functions of IAM Identity Center.

The following figure shows how to use IAM Identity Center.

Figure 1-1 Flowchart



# 2 Making Preparations

---

Before using IAM Identity Center, you need to prepare as described in the following sections:

- [Registering a HUAWEI ID, Enabling Huawei Cloud, and Completing Real-Name Authentication](#)
- [Enabling the Organizations Service and Creating an Organization](#)

## Registering a HUAWEI ID, Enabling Huawei Cloud, and Completing Real-Name Authentication

If you already have a Huawei Cloud account, skip this part. If you do not have a Huawei Cloud account:

1. Access the [Huawei Cloud official website](#), and click **Sign Up** in the upper right corner.
2. Register a HUAWEI ID as prompted.
3. Read and agree to the terms, and click **Enable**.  
For details, see [Signing Up for a HUAWEI ID and Enabling Huawei Cloud Services](#).
4. Complete real-name authentication by following the instructions in [Enterprise Real-Name Authentication](#).

### NOTE

IAM Identity Center is a free service. You do not need to top up your account.

## Enabling the Organizations Service and Creating an Organization

IAM Identity Center obtains member account information from organizations defined in the Organizations service. Before using IAM Identity Center, you must enable the Organizations service and create an organization. Then, you can log in to IAM Identity Center using the organization's management account.

Before using the Organizations service, you need to enable the [Enterprise Center](#) function. You must use the master account of Enterprise Center to create an organization.

**Step 1** Access the Enterprise Center console.

**Step 2** Click **Enable for Free**.

The **Enable Enterprise Center** dialog box is displayed.

**Step 3** Select **I have read and agree to Huawei Cloud Management Service Agreement** and click **Enable Now**. Your account will become an enterprise master account. For details, see [Enabling Enterprise Center](#).

**Step 4** Go to the Organizations console.

**Step 5** Click **Enable Organizations** to enable the Organizations service.

**Step 6** After the Organizations service is enabled, your organization and the root are automatically created, and your login account is defined as the management account.

**Step 7** Invite an account to join your organization. .

----End




# 3 Creating Users and Permission Sets

## Creating Users

After IAM Identity Center is enabled, you need to create Identity Center users.


**Step 1** Log in to the Huawei Cloud management console.

**Step 2** Click  in the upper left corner of the page and choose **Management & Governance > IAM Identity Center**.

**Step 3** In the navigation pane, choose **Users**.

**Step 4** Click **Create User** in the upper right corner of the page.

**Figure 3-1** Creating users



**Step 5** Configure basic information about the user. After the configuration is complete, click **Next** in the lower right corner of the page.

The user details are mandatory. The contact methods, job-related information, and address are optional and can be set as needed.

Figure 3-2 Configuring basic information

The screenshot shows the 'Create User' interface. At the top, there's a progress bar with three steps: 1. Set User Details (active), 2. (Optional) Add User to Groups, and 3. Confirm. Below the progress bar, the 'User Details' section is expanded, showing input fields for Username, Given Name, Email Address, Password, Family Name, Display Name, and Confirm Email Address. There are also checkboxes for 'Send an email to this user with password setup instructions' and 'Generate a one-time password that you can share with this user'. The form is divided into sections: User Details, Contact Methods - Optional, Job-related Information - Optional, and Address - Optional. The 'Next' button is visible at the bottom right.


Table 3-1 User details

Parameter	Description
Username	IAM Identity Center username. The value is user-defined and must be unique.
Password	Select a password generation method. <ul style="list-style-type: none"><li>● <b>Send an email to this user with password setup instructions:</b> The system will send a password reset instruction email to the user. The user can set a password as instructed.</li><li>● <b>Generate a one-time password that you can share with this user:</b> An automatically generated one-time password will be displayed on the page indicating that the user is created. The administrator copies the information and sends it to the user. When the user uses the one-time password to log in through the user portal URL, the system prompts the user to change the password. The user can only log in to the console using the new password.</li></ul> <b>CAUTION</b> If the page is closed, the one-time password generated by the system will no longer be displayed again. To obtain the password again, you need to <a href="#">reset the password</a> .
Email Address	Email address of a user. The value is user-defined and must be unique. It can be used to authenticate the user and reset the password.
Confirm Email Address	Enter the email address again for confirmation. The email address and confirm email address must be the same.
Family Name	Family name of the user.

Parameter	Description
Given Name	Given name of the user.
Display Name	Display name of an IAM Identity Center user. The value is user-defined and can be the same as the display name of another IAM Identity Center user. Generally, the value is the real name of the user.

**Step 6** (Optional) In the **(Optional) Add User to Groups** step, select groups. The user will have the permissions assigned to the group. Click **Next**.


**Figure 3-3** (Optional) Adding a user to groups



**Step 7** In the **Confirm** step, confirm the configuration and click **OK** in the lower right corner of the page. The IAM Identity Center user is created and displayed in the user list.

- If **Send an email to this user with password setup instructions.** is selected for **Password** in step **Step 5**, the user list will be displayed, showing the newly created IAM Identity Center user.
- If **Generate a one-time password that you can share with this user.** is selected for **Password** in step **Step 5**, a page that contains detailed information about the one-time password will be displayed. You can copy the information and send it to the user. The user can use the username and one-time password to log in through the user portal URL.

Figure 3-4 Confirming user creation



----End

Creating a Permission Set

A permission set defines a collection of one or more IAM policies and controls the permissions of IAM Identity Center users to access resources. Creating permission sets is mandatory. When logging in to the management console as an IAM Identity Center user to access resources of multiple accounts, you must associate the user with permission sets. Otherwise, the user cannot access any resources after login.


- Step 1
- Log in to the Huawei Cloud management console.
- Step 2
- Click  in the upper left corner of the page and choose **Management & Governance > IAM Identity Center**.
- Step 3
- In the navigation pane, choose **Multi-Account Permissions > Permission Sets**.
- Step 4
- Click **Create Permission Set** in the upper right corner of the page.

Figure 3-5 Creating a permission set



- Step 5
- In the **Set Permission Set Details** step, configure details about the permission set and click **Next**.

Figure 3-6 Setting permission set details

Create Permission Set

A permission set contains policies that determine a user's permissions to access a Huawei Cloud account. When you associate a user or group with a permission set for a Huawei Cloud account, IAM Identity Center creates an IAM agency in the account and attaches the policies specified in the permission set to that agency. [Learn More](#)

1 Specify Details

2 Set Policy

3 Confirm

Name

123

Session Duration

1h

4h

8h

12h

Custom

Custom duration

9

Initial Access Page

Enter the initial access page URL.

Description

Enter a description.

0/1,024

Table 3-2 Permission set details

Parameter	Description
Name	Name of a permission set. The value is user-defined and must be unique.
Session Duration	The length of time a user can be logged in to the console. When the login time exceeds the configured session duration, the user is automatically logged out. To continue the access, the user needs to log in again.
Initial Access Page	Initial page that a user accesses after logging in to the console using the user portal URL. For example, if you enter the IAM console URL, users will access the IAM console after login.
Description	Description of a permission set.

**Step 6** In the **Set Policy** step, configure system-defined policies, custom identity policies, and custom policies for the permission set and click **Next**.

If you enable **Identity Policy**, only system-defined policies and custom identity policies are displayed.


- System-defined policies: You can select system-defined policies preconfigured in IAM Identity Center, including policies and identity policies.
- Custom identity policies: You can create custom identity policies in visual editor or JSON view to supplement system-defined identity policies.
- Custom policies: You can create custom policies only in JSON view to supplement system-defined policies.

Issue 01 (2025-08-25)

Copyright © Huawei Technologies Co., Ltd.


9

Figure 3-7 Setting policies



**Step 7** In the **Confirm** step, confirm the configuration and click **OK** in the lower right corner.

Figure 3-8 Confirming configurations



**NOTE**

By default, newly created permission sets are not attached to any accounts. Their status will change to **Attached** after you attach them to accounts.

----End


# 4 Associating Accounts with Users and Permission Sets

---


After IAM Identity Center users/groups and permission sets are created, you can associate one or more member accounts in your organization with the created users/groups and permission sets. This way, the IAM Identity Center users can access resources under the associated accounts after logging in to the system, and permissions included in the associated permission set can be granted to the resources.


## Procedure

**Step 1** Log in to the Huawei Cloud management console.

**Step 2** Click  in the upper left corner of the page and choose **Management & Governance > IAM Identity Center**.

**Step 3** In the navigation pane, choose **Multi-Account Permissions > Accounts**.

By default, accounts are displayed in an organizational hierarchy structure. You can click  to switch to the list view.

**Figure 4-1** Account view

**Step 4** Select one or more accounts from the account list and click **Assign User/Group** in the upper left corner.


Alternatively, locate a target account and click **Assign User/Group** in the **Operation** column.

**Figure 4-2** Selecting accounts

**Step 5** In the **Select User/Group** step on the displayed page, select one or more users/groups and click **Next**.




Figure 4-3 Assigning users/groups




**Step 6** In the **Select Permission Set** step, select one or more permission sets and click **Next**.

Figure 4-4 Selecting one or more permission sets



**Step 7** In the **Confirm** step, confirm the configurations and click **OK**.

Figure 4-5 Confirming configurations



----End


# 5

## Logging In as an IAM Identity Center User and Accessing Resources

After associating member accounts of an organization with an IAM Identity Center user and permission sets, you can use the IAM Identity Center username and password to log in to the console through the user portal URL and access resources according to the permissions included in the associated permission sets.

### Procedure


**Step 1** Log in to the Huawei Cloud management console.

**Step 2** Click  in the upper left corner of the page and choose **Management & Governance > IAM Identity Center**.

**Step 3** In the navigation pane, choose **Dashboard**. On the displayed page, obtain the user portal URL.

The user portal URL can also be obtained from the password setting instruction email sent to the user or from the one-time password page displayed when the user was created.


**Figure 5-1** User portal URL



**Step 4** Open a browser and access the user portal URL. Enter the IAM Identity Center username, and click **Next**.


The IAM Identity Center username and password for logging in to the portal are obtained during user creation. For details, see [Creating Users](#). If the password is forgotten or needs to be changed, the administrator can use the [password resetting](#) function to allow the system to resend a password setting instruction email to the user or generate a one-time password.

**Figure 5-2** User login



- Step 5** Enter the password, and click **Log In**.
- Step 6** Under a specific account, locate your desired permission set and click **Access Console** in the **Operation** column to access resources according to the permissions included in the permission set.

**Figure 5-3** Accessing resources



----End