

Cloud Container Engine

API Reference

Issue 01
Date 2025-03-04



Copyright © Huawei Cloud Computing Technologies Co., Ltd. 2025. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Cloud Computing Technologies Co., Ltd.

Trademarks and Permissions



HUAWEI and other Huawei trademarks are the property of Huawei Technologies Co., Ltd.

All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei Cloud and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Huawei Cloud Computing Technologies Co., Ltd.

Address: Huawei Cloud Data Center Jiaoxinggong Road
 Qianzhong Avenue
 Gui'an New District
 Gui Zhou 550029
 People's Republic of China

Website: <https://www.huaweicloud.com/intl/en-us/>

Contents

1 Before You Start.....	1
2 API Overview.....	4
3 Calling APIs.....	23
3.1 Making an API Request.....	23
3.2 Authentication.....	27
3.3 Response.....	28
4 APIs.....	31
4.1 API URL.....	31
4.2 Cluster Management.....	32
4.2.1 Creating a Cluster.....	32
4.2.2 Reading a Specified Cluster.....	75
4.2.3 Listing Clusters in a Specified Project.....	92
4.2.4 Updating a Specified Cluster.....	111
4.2.5 Deleting a Cluster.....	132
4.2.6 Hibernating a Cluster.....	152
4.2.7 Waking Up a Cluster.....	154
4.2.8 Obtaining a Cluster Certificate.....	155
4.2.9 Modifying Cluster Specifications.....	160
4.2.10 Querying a Job.....	164
4.2.11 Binding/Unbinding Public API Server Address.....	168
4.2.12 Obtaining Cluster Access Address.....	173
4.3 Node Management.....	176
4.3.1 Creating a Node.....	176
4.3.2 Reading a Specified Node.....	223
4.3.3 Listing All Nodes in a Cluster.....	245
4.3.4 Updating a Specified Node.....	267
4.3.5 Deleting a Node.....	289
4.3.6 Accepting a Node.....	311
4.3.7 Resetting a Node.....	327
4.3.8 Removing a Node.....	344
4.3.9 Migrating a Node.....	349
4.4 Node Pool Management.....	359

4.4.1 Creating a Node Pool.....	360
4.4.2 Reading a Specified Node Pool.....	412
4.4.3 Listing All Node Pools in a Specified Cluster.....	435
4.4.4 Updating a Specified Node Pool.....	459
4.4.5 Deleting a Node Pool.....	490
4.5 Add-on Management.....	513
4.5.1 Installing an Add-on Instance.....	514
4.5.2 Listing Add-on Templates.....	523
4.5.3 Updating an Add-on Instance.....	529
4.5.4 Rolling Back an Add-on Instance.....	540
4.5.5 Deleting an Add-on Instance.....	549
4.5.6 Querying an Add-on Instance.....	550
4.5.7 Listing Add-on Instances.....	556
4.6 Quota Management.....	562
4.6.1 Querying Resource Quotas.....	562
4.7 API Versions.....	564
4.7.1 Obtaining API Versions.....	564
4.8 Tag Management.....	566
4.8.1 Adding Resource Tags to a Specified Cluster in Batches.....	566
4.8.2 Deleting Resource Tags of a Specified Cluster in Batches.....	568
4.9 Configuration Management.....	571
4.9.1 Obtaining the Parameters That Can Be Configured for a Node Pool.....	571
4.9.2 Obtaining the List of Parameters That Can Be Configured for a Cluster.....	572
4.9.3 Obtaining the Parameters That Can Be Configured for a Node Pool.....	574
4.9.4 Changing the Values of Configuration Parameters of a Node Pool.....	577
4.10 Chart Management.....	583
4.10.1 Uploading a Chart.....	583
4.10.2 Obtaining a Chart List.....	585
4.10.3 Obtaining a Release List.....	587
4.10.4 Updating a Chart.....	590
4.10.5 Creating a Release.....	593
4.10.6 Deleting a Chart.....	596
4.10.7 Updating a Release.....	598
4.10.8 Obtaining a Chart.....	601
4.10.9 Deleting a Release.....	603
4.10.10 Downloading a Chart.....	605
4.10.11 Obtaining a Release.....	606
4.10.12 Obtaining Chart Values.....	608
4.10.13 Obtaining Historical Records of a Release.....	610
4.10.14 Obtaining the Quota of a User Chart.....	613
4.11 Add-on Instance Parameters.....	614
4.11.1 CoreDNS.....	615

4.11.2 CCE Container Storage (Everest).....	619
4.11.3 CCE Node Problem Detector.....	624
4.11.4 Kubernetes Dashboard.....	627
4.11.5 CCE Cluster Autoscaler.....	630
4.11.6 NGINX Ingress Controller.....	635
4.11.7 Kubernetes Metrics Server.....	639
4.11.8 CCE Advanced HPA.....	642
4.11.9 CCE AI Suite (NVIDIA GPU).....	646
4.11.10 Volcano Scheduler.....	649
4.11.11 CCE Secrets Manager for DEW.....	654
4.11.12 NodeLocal DNSCache.....	655
5 Kubernetes APIs.....	660
6 Permissions and Supported Actions.....	663
7 Appendix.....	669
7.1 Status Code.....	669
7.2 Error Codes.....	673
7.3 Obtaining a Project ID.....	679
7.4 Obtaining an Account ID.....	680
7.5 Specifying Add-ons to Be Installed During Cluster Creation.....	680
7.6 How to Obtain Parameters in the API URI.....	683
7.7 Creating a VPC and Subnet.....	684
7.8 Creating a Key Pair.....	684
7.9 Node Flavor Description.....	685
7.10 Adding a Salt in the password Field When Creating a Node.....	685
7.11 Maximum Number of Pods That Can Be Created on a Node.....	687
7.12 Node OS.....	690
7.13 Space Allocation of a Data Disk.....	691
7.14 Attaching Disks to a Node.....	695

1

Before You Start

Cloud Container Engine (CCE) is a container service that allows you to run containers efficiently in the cloud. CCE provides highly scalable, high-performance, enterprise-class Kubernetes clusters and supports Docker containers. With CCE, you can easily deploy, manage, and scale containerized applications in the cloud.

This document describes how to use APIs for performing operations on CCE, such as creating or deleting CCE resources, modifying resource specifications, or adding NICs. For details about all supported operations, see [API Overview](#).

If you plan to access CCE resources through an API, ensure that you are familiar with CCE concepts.

CCE supports both Kubernetes-native APIs and proprietary APIs. With these APIs, you can use all functions of CCE.

- CCE has opened APIs through API gateways to support operations on cloud service infrastructures (for example, creating a node). Operations on cluster resources (such as [creating a workload](#)) are also supported.
- Kubernetes-native APIs: You can perform operations on cluster resources (such as [creating a workload](#)) using the Kubernetes-native API server. However, operations on cloud service infrastructures (such as creating a node) are not supported.

For details about Kubernetes-native API versions, see <https://kubernetes.io/docs/concepts/overview/kubernetes-api/>.

NOTE

- The Kubernetes-native APIs called in the current version do not support HTTP persistent connections.
- The Kubernetes-native APIs in the current version include Beta APIs, whose version names include **beta**, for example, **v1beta1**. This type of APIs varies according to Kubernetes-native APIs. Therefore, you are advised to use this type of APIs in unimportant scenarios, for example, short-term test clusters.

CCE supports Representational State Transfer (REST) APIs, allowing you to call APIs using HTTPS. For details about API calling, see [3 Calling APIs](#).

Endpoints

An endpoint is the **request address** for calling an API. Endpoints vary depending on services and regions. An endpoint can be obtained from [Regions and Endpoints](#).

You need to select an endpoint based on your service requirements.

- The URL format for cluster, node, node pool, add-on, and quota management is **https://Endpoint/uri**. *uri* indicates the resource path, that is, the API access path.
- The URL format for Kubernetes APIs, storage management, and add-on management is **https://{clusterid}.Endpoint/uri**. In the URL, *{clusterid}* indicates the cluster ID, and *uri* indicates the resource path, that is, the path for API access.

NOTE

- The format of the URL called by the add-on management APIs is **https:// {clusterid}.Endpoint/uri**. However, *{clusterid}* is used only for the domain name and is not verified or used by the APIs. Set *{clusterid}* in the query or body. For details about *{clusterid}*, see the add-on management sections.
- *{clusterid}* is required for Kubernetes APIs and storage management, which indicates the cluster that needs to be accessed by calling the API.

Table 1-1 URL parameters

Parameter	Description
{clusterid}	Cluster ID. After a cluster is created, call the API for obtaining a cluster in a specified project to obtain the cluster ID.
Endpoint	Entry (URL) for a web service. Endpoints vary depending on services and regions.
uri	Access path of an API for performing an operation. Obtain the path from the URI of an API. For example, the resource-path of the API used to obtain a user token is v3/auth/tokens .

Notes and Constraints

- CCE imposes a quota on the number and capacity of resources that a user can access. By default, you can create a maximum of five clusters in each region and a cluster can have a maximum of 50 nodes.
- For more constraints, see API description.

Basic Concepts

- Domain

A domain is created upon successful registration. The domain has full access permissions for all of its cloud services and resources. It can be used to reset user passwords and grant user permissions. The domain user is a payment

entity, which should not be used directly to perform routine management. For security purposes, create users and grant them permissions for routine management.

- User

An IAM user is created using an account to use cloud services. Each IAM user has their own identity credentials (password and access keys).

The account name, username, and password will be required for API authentication.

- Region

A region is a geographic area in which cloud resources are deployed.

Availability zones (AZs) in the same region can communicate with each other over an intranet, while AZs in different regions are isolated from each other.

Deploying cloud resources in different regions can better suit certain user requirements or comply with local laws or regulations.


- AZ

An AZ comprises of one or more physical data centers equipped with independent ventilation, fire, water, and electricity facilities. Computing, network, storage, and other resources in an AZ are logically divided into multiple clusters. AZs within a region are interconnected using high-speed optical fibers to allow you to build cross-AZ high-availability systems.

- Project

A project corresponds to a region. Default projects are defined to group and physically isolate resources (including compute, storage, and network resources) across regions. Users can be granted permissions in a default project to access all resources under their accounts in the region associated with the project. If you need more refined access control, create subprojects under a default project and create resources in subprojects. Then you can assign users the permissions required to access only the resources in the specific subprojects.

Figure 1-1 Project isolation model



2 API Overview

APIs provided by CCE are classified into two types: proprietary APIs and Kubernetes-native APIs. By using these two types of APIs, you can use all functions provided by CCE, including creating clusters and nodes, using the Kubernetes-native APIs to create workloads, and using the proprietary CCE APIs to monitor application data.

Type	Subtype	Description
Proprietary CCE APIs	Cluster-related APIs	Manage clusters, including creating and deleting clusters. You can use APIs in this category to create clusters and obtain information about created clusters.
	Node-related APIs	Manage nodes, including creating and deleting nodes. You can use these APIs in this category to add nodes to clusters and obtain information about created nodes.
	Node Pool-related APIs	Manage node pools, including creating and deleting node pools. You can use APIs in this category to create node pools and obtain information about created node pools.
	Add-on-related APIs	Manage add-ons, including querying AddonTemplates and creating, updating, deleting, and obtaining AddonInstances.
	Quota-related API	Obtain quotas of CCE resources.
Kubernetes-native APIs	N/A	For details about how to call Kubernetes-native APIs, see Kubernetes APIs .

Cluster-related APIs

Table 2-1 Cluster-related APIs

API	Description
Creating a Cluster	Create an empty cluster, which has only master nodes but do not have worker nodes.
Reading a Specified Cluster	Obtain details about a specified cluster.
Listing Clusters in a Specified Project	Obtain details about all clusters in a specified project.
Updating a Specified Cluster	Update information about a specified cluster.
Deleting a Cluster	Delete a specified cluster.
Hibernating a Cluster	Hibernate a specified cluster.
Waking Up a Cluster	Wake up a hibernated cluster.
Obtaining Cluster Certificates	Obtain certificates of a specified cluster.
Obtaining Job Information	Obtain the progress of a job with a specified job ID returned after a job request is issued.

Node-related APIs

Table 2-2 Node-related APIs

API	Description
Creating a Node	Create a node in a specified cluster.
Reading a Specified Node	Obtain details about a node with a specified node ID.
Reading all Nodes in a Cluster	Obtain details about all nodes in a cluster with a specified cluster ID.
Updating a Specified Node	Update information about a specified node.
Deleting a Node	Delete a specified node
Accepting a Node	Accept a node into a specified cluster.
Resetting a Node	Reset a node in a specified cluster.

API	Description
Removing a Node	Remove a node from a specified cluster.
Migrating a Node	Migrate a node from a specified cluster to another cluster.

Node Pool-related APIs

Table 2-3 Node pool-related APIs

API	Description
Creating a Node Pool	Create a node pool in a specified cluster.
Reading a Specified Node Pool	Obtain details about a node with a specified node ID.
Listing All Node Pools in a Specified Cluster	Obtain details about all node pools in a cluster with a specified cluster ID.
Updating a Specified Node Pool	Update information about a specified node pool.
Deleting a Node Pool	Delete a specified node pool.

Add-on-related APIs

Table 2-4 Add-on-related APIs

API	Description
Installing an Add-on Instance	Install an add-on by using the add-on template.
Listing Add-on Templates	Query add-on information.
Updating an Add-on Instance	Update an add-on instance.
Deleting an Add-on Instance	Delete an add-on instance.
Reading an Add-on Instance	Obtain details about an add-on instance.
Listing Add-on Instances	List all add-on instances in the cluster.

Quota-related API

Table 2-5 Quota-related API

API	Description
Querying Resource Quotas	Query resource quotas.

Kubernetes APIs

API	Function	URI
Node	Reading a specified node	GET /api/v1/nodes/{name}
	Listing all nodes	GET /api/v1/nodes
	Updating a specified node	PATCH /api/v1/nodes/{name}
Namespace	Creating a namespace	POST /api/v1/namespaces
	Deleting a namespace	DELETE /api/v1/namespaces/{name}
	Querying a specified namespace	GET /api/v1/namespaces/{name}
	Replacing a specified namespace	PUT /api/v1/namespaces/{name}
	Replacing the status of a specified namespace	PUT /api/v1/namespaces/{name}/status
	Replacing the finalize values of a specified namespace	PUT /api/v1/namespaces/{name}/finalize
	Listing namespaces	GET /api/v1/namespaces
	Updating a specified namespace	PATCH /api/v1/namespaces/{name}
Resource quotas	Querying resource quotas	GET /api/v1/resourcequotas
	Creating a resource quota	POST /api/v1/namespaces/{namespace}/resourcequotas
	Updating a resource quota	PUT /api/v1/namespaces/{namespace}/resourcequotas/{name}
	Deleting a resource quota	DELETE /api/v1/namespaces/{namespace}/resourcequotas/{name}

API	Function	URI
Pod	Creating a pod	POST /api/v1/namespaces/{namespace}/pods
	Deleting a pod	DELETE /api/v1/namespaces/{namespace}/pods/{name}
	Deleting all pods	DELETE /api/v1/namespaces/{namespace}/pods
	Reading a specified pod	GET /api/v1/namespaces/{namespace}/pods/{name}
	Replacing a specified pod	PUT /api/v1/namespaces/{namespace}/pods/{name}
	Replacing the status of a specified pod	PUT /api/v1/namespaces/{namespace}/pods/{name}/status
	Listing all pods in a specified namespace	GET /api/v1/namespaces/{namespace}/pods
	Listing pods	GET /api/v1/pods
	Updating a specified pod	PATCH /api/v1/namespaces/{namespace}/pods/{name}
Deployment	Creating a Deployment	POST /apis/apps/v1/namespaces/{namespace}/deployments
	Rolling back a Deployment	PATCH /apis/apps/v1/namespaces/{namespace}/deployments/{name} (for clusters of v1.17 or later) POST /apis/apps/v1beta1/namespaces/{namespace}/deployments/{name}/rollback (for clusters of v1.15 and earlier) POST /apis/extensions/v1beta1/namespaces/{namespace}/deployments/{name}/rollback (for clusters of v1.15 and earlier)
	Deleting a Deployment	DELETE /apis/apps/v1/namespaces/{namespace}/deployments/{name}
	Deleting all Deployments	DELETE /apis/apps/v1/namespaces/{namespace}/deployments
	Reading a specified Deployment	GET /apis/apps/v1/namespaces/{namespace}/deployments/{name}
	Reading the status of a specified Deployment	GET /apis/apps/v1/namespaces/{namespace}/deployments/{name}/status

API	Function	URI
Deployment	Reading the scaling operation of a specified Deployment	GET /apis/apps/v1/namespaces/{namespace}/deployments/{name}/scale
	Replacing a specified Deployment	PUT /apis/apps/v1/namespaces/{namespace}/deployments/{name}
	Replacing the status of a specified Deployment	PUT /apis/apps/v1/namespaces/{namespace}/deployments/{name}/status
	Replacing the scaling operation of a specified Deployment	PUT /apis/apps/v1/namespaces/{namespace}/deployments/{name}/scale
	Listing Deployments in a specified namespace	GET /apis/apps/v1/namespaces/{namespace}/deployments
	Listing all Deployments	GET /apis/apps/v1/deployments
	Updating a specified Deployment	PATCH /apis/apps/v1/namespaces/{namespace}/deployments/{name}
	Updating the status of a specified Deployment	PATCH /apis/apps/v1/namespaces/{namespace}/deployments/{name}/status
	Updating the scaling operation of a specified Deployment	PATCH /apis/apps/v1/namespaces/{namespace}/deployments/{name}/scale
StatefulSet	Creating a StatefulSet	POST /apis/apps/v1/namespaces/{namespace}/statefulsets
	Deleting a specified StatefulSet	DELETE /apis/apps/v1/namespaces/{namespace}/statefulsets/{name}
	Deleting all StatefulSets	DELETE /apis/apps/v1/namespaces/{namespace}/statefulsets
	Reading a specified StatefulSet	GET /apis/apps/v1/namespaces/{namespace}/statefulsets/{name}
	Reading the status of a specified StatefulSet	GET /apis/apps/v1/namespaces/{namespace}/statefulsets/{name}/status
	Replacing a specified StatefulSet	PUT /apis/apps/v1/namespaces/{namespace}/statefulsets/{name}
	Replacing the status of a specified StatefulSet	PUT /apis/apps/v1/namespaces/{namespace}/statefulsets/{name}/status
	Listing StatefulSets in a specified namespace	GET /apis/apps/v1/namespaces/{namespace}/statefulsets
	Listing all StatefulSets	GET /apis/apps/v1/statefulsets

API	Function	URI
	Updating a specified StatefulSet	PATCH /apis/apps/v1/namespaces/{namespace}/statefulsets/{name}
	Updating the status of a specified StatefulSet	PATCH /apis/apps/v1/namespaces/{namespace}/statefulsets/{name}/status
Daemon Set	Creating a DaemonSet	POST /apis/apps/v1/namespaces/{namespace}/daemonsets
	Deleting a specified DaemonSet	DELETE /apis/apps/v1/namespaces/{namespace}/daemonsets/{name}
	Deleting all DaemonSets	DELETE /apis/apps/v1/namespaces/{namespace}/daemonsets
	Reading a specified DaemonSet	GET /apis/apps/v1/namespaces/{namespace}/daemonsets/{name}
	Reading the status of a specified DaemonSet	GET /apis/apps/v1/namespaces/{namespace}/daemonsets/{name}/status
	Updating a specified DaemonSet	PATCH /apis/apps/v1/namespaces/{namespace}/daemonsets/{name}
	Updating the status of a specified DaemonSet	PATCH /apis/apps/v1/namespaces/{namespace}/daemonsets/{name}/status
	Listing all DaemonSets	GET /apis/apps/v1/daemonsets
	Listing DaemonSets in a specified namespace	GET /apis/apps/v1/namespaces/{namespace}/daemonsets
	Replacing a specified DaemonSet	PUT /apis/apps/v1/namespaces/{namespace}/daemonsets/{name}
	Replacing the status of a specified DaemonSet	PUT /apis/apps/v1/namespaces/{namespace}/daemonsets/{name}/status
Job	Creating a job	POST /apis/batch/v1/namespaces/{namespace}/jobs
	Deleting a job	DELETE /apis/batch/v1/namespaces/{namespace}/jobs/{name}
	Deleting all jobs	DELETE /apis/batch/v1/namespaces/{namespace}/jobs
	Reading a specified job	GET /apis/batch/v1/namespaces/{namespace}/jobs/{name}
	Reading the status of a specified job	GET /apis/batch/v1/namespaces/{namespace}/jobs/{name}/status
	Replacing a specified job	PUT /apis/batch/v1/namespaces/{namespace}/jobs/{name}

API	Function	URI
	Replacing the status of a specified job	PUT /apis/batch/v1/namespaces/{namespace}/jobs/{name}/status
	Listing jobs in a specified namespace	GET /apis/batch/v1/namespaces/{namespace}/jobs
	Listing all jobs	GET /apis/batch/v1/jobs
	Updating the status of a specified job	PATCH /apis/batch/v1/namespaces/{namespace}/jobs/{name}/status
	Updating a specified job	PATCH /apis/batch/v1/namespaces/{namespace}/jobs/{name}
CronJob	Creating a cron job	POST /apis/batch/v1/namespaces/{namespace}/cronjobs (only for clusters of v1.25 or later) POST /apis/batch/v1beta1/namespaces/{namespace}/cronjobs (only for clusters of v1.23 or earlier)
	Deleting a cron job	DELETE /apis/batch/v1/namespaces/{namespace}/cronjobs/{name} (only for clusters of v1.25 or later) DELETE /apis/batch/v1beta1/namespaces/{namespace}/cronjobs/{name} (only for clusters of v1.23 or earlier)
	Deleting all cron jobs	DELETE /apis/batch/v1/namespaces/{namespace}/cronjobs (only for clusters of v1.25 or later) DELETE /apis/batch/v1beta1/namespaces/{namespace}/cronjobs (only for clusters of v1.23 or earlier)
	Reading a specified cron job	GET /apis/batch/v1/namespaces/{namespace}/cronjobs/{name} (only for clusters of v1.25 or later) GET /apis/batch/v1beta1/namespaces/{namespace}/cronjobs/{name} (only for clusters of v1.23 or earlier)
	Reading the status of a specified cron job	GET /apis/batch/v1/namespaces/{namespace}/cronjobs/{name}/status (only for clusters of v1.25 or later) GET /apis/batch/v1beta1/namespaces/{namespace}/cronjobs/{name}/status (only for clusters of v1.23 or earlier)

API	Function	URI
	Replacing a specified cron job	PUT /apis/batch/v1/namespaces/{namespace}/cronjobs/{name} (only for clusters of v1.25 or later) PUT /apis/batch/v1beta1/namespaces/{namespace}/cronjobs/{name} (only for clusters of v1.23 or earlier)
	Replacing the status of a specified cron job	PUT /apis/batch/v1/namespaces/{namespace}/cronjobs/{name}/status (only for clusters of v1.25 or later) PUT /apis/batch/v1beta1/namespaces/{namespace}/cronjobs/{name}/status (only for clusters of v1.23 or earlier)
	Listing cron jobs under a specified namespace	GET /apis/batch/v1/namespaces/{namespace}/cronjobs (only for clusters of v1.25 or later) GET /apis/batch/v1beta1/namespaces/{namespace}/cronjobs (only for clusters of v1.23 or earlier)
	Listing all cron jobs	GET /apis/batch/v1/cronjobs (only for clusters of v1.25 or later) GET /apis/batch/v1beta1/cronjobs (only for clusters of v1.23 or earlier)
	Updating the status of a specified cron job	PATCH /apis/batch/v1/namespaces/{namespace}/cronjobs/{name}/status (only for clusters of v1.25 or later) PATCH /apis/batch/v1beta1/namespaces/{namespace}/cronjobs/{name}/status (only for clusters of v1.23 or earlier)
	Updating a specified cron job	PATCH /apis/batch/v1/namespaces/{namespace}/cronjobs/{name} (only for clusters of v1.25 or later) PATCH /apis/batch/v1beta1/namespaces/{namespace}/cronjobs/{name} (only for clusters of v1.23 or earlier)
ReplicaSet	Listing ReplicaSets	GET /apis/apps/v1/namespaces/{namespace}/replicasets
	Reading a specified ReplicaSet	GET /apis/apps/v1/namespaces/{namespace}/replicasets/{name}
	Listing all ReplicaSets	GET /apis/apps/v1/replicasets
ReplicationController	Creating a ReplicationController	POST /api/v1/namespaces/{namespace}/replicationcontrollers

API	Function	URI
ReplicationController	Deleting a ReplicationController	DELETE /api/v1/namespaces/{namespace}/replicationcontrollers/{name}
	Deleting all ReplicationControllers	DELETE /api/v1/namespaces/{namespace}/replicationcontrollers
	Reading a ReplicationController under a specified namespace	GET /api/v1/namespaces/{namespace}/replicationcontrollers/{name}
	Replacing a ReplicationController under a specified namespace	PUT /api/v1/namespaces/{namespace}/replicationcontrollers/{name}
	Replacing the status of a ReplicationController under a specified namespace	PUT /api/v1/namespaces/{namespace}/replicationcontrollers/{name}/status
	Listing ReplicationControllers in a specified namespace	GET /api/v1/namespaces/{namespace}/replicationcontrollers
	Listing ReplicationControllers	GET /api/v1/replicationcontrollers
	Updating a specified ReplicationController	PATCH /api/v1/namespaces/{namespace}/replicationcontrollers/{name}
Endpoints	Creating an endpoint	POST /api/v1/namespaces/{namespace}/endpoints
	Deleting an endpoint	DELETE /api/v1/namespaces/{namespace}/endpoints/{name}
	Deleting all endpoints	DELETE /api/v1/namespaces/{namespace}/endpoints
	Querying a specified endpoint	GET /api/v1/namespaces/{namespace}/endpoints/{name}
	Replacing a specified endpoint	PUT /api/v1/namespaces/{namespace}/endpoints/{name}
	Listing endpoints	GET /api/v1/endpoints
	Listing endpoints in a specified namespace	GET /api/v1/namespaces/{namespace}/endpoints
	Updating a specified endpoint	PATCH /api/v1/namespaces/{namespace}/endpoints/{name}

API	Function	URI
Service	Creating a Service	POST /api/v1/namespaces/{namespace}/services
	Deleting a specified Service	DELETE /api/v1/namespaces/{namespace}/services/{name}
	Obtaining a specified Service	GET /api/v1/namespaces/{namespace}/services/{name}
	Replacing a specified Service	PUT /api/v1/namespaces/{namespace}/services/{name}
	Listing Services in a specified namespace	GET /api/v1/namespaces/{namespace}/services
	Listing Services	GET /api/v1/services
	Updating a specified Service	PATCH /api/v1/namespaces/{namespace}/services/{name}
Ingress	Creating an ingress	POST /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses (for clusters of v1.21 and later) POST /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses (for clusters from v1.15 to v1.21) POST /apis/extensions/v1beta1/namespaces/{namespace}/ingresses (for clusters earlier than v1.15)
	Updating a specified ingress	PATCH /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses/{name} (for clusters of v1.21 and later) PATCH /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses/{name} (for clusters from v1.15 to v1.21) PATCH /apis/extensions/v1beta1/namespaces/{namespace}/ingresses/{name} (for clusters earlier than v1.15)
	Replacing a specified ingress	PUT /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses/{name} (for clusters of v1.21 and later) PUT /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses/{name} (for clusters from v1.15 to v1.21) PUT /apis/extensions/v1beta1/namespaces/{namespace}/ingresses/{name} (for clusters earlier than v1.15)

API	Function	URI
	Deleting an ingress	DELETE /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses/{name} (for clusters of v1.21 and later) DELETE /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses/{name} (for clusters from v1.15 to v1.21) DELETE /apis/extensions/v1beta1/namespaces/{namespace}/ingresses/{name} (for clusters earlier than v1.15)
	Deleting all ingresses	DELETE /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses (for clusters of v1.21 and later) DELETE /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses (for clusters from v1.15 to v1.21) DELETE /apis/extensions/v1beta1/namespaces/{namespace}/ingresses (for clusters earlier than v1.15)
	Obtaining a specified ingress	GET /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses/{name} (for clusters of v1.21 and later) GET /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses/{name} (for clusters from v1.15 to v1.21) GET /apis/extensions/v1beta1/namespaces/{namespace}/ingresses/{name} (for clusters earlier than v1.15)
	Listing ingresses in a specified namespace	GET /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses (for clusters of v1.21 and later) GET /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses (for clusters from v1.15 to v1.21) GET /apis/extensions/v1beta1/namespaces/{namespace}/ingresses (for clusters earlier than v1.15)
	Listing ingresses	GET /apis/networking.k8s.io/v1/ingresses (for clusters of v1.21 and later) GET /apis/networking.k8s.io/v1beta1/ingresses (for clusters from v1.15 to v1.21) GET /apis/extensions/v1beta1/ingresses (for clusters earlier than v1.15)

API	Function	URI
	Obtaining the status of an ingress in a specified namespace	GET /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses/{name}/status (for clusters of v1.21 and later) GET /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses/{name}/status (for clusters from v1.15 to v1.21) GET /apis/extensions/v1beta1/namespaces/{namespace}/ingresses/{name}/status (for clusters earlier than v1.15)
	Replacing the status of an ingress in a specified namespace	PUT /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses/{name}/status (for clusters of v1.21 and later) PUT /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses/{name}/status (for clusters from v1.15 to v1.21) PUT /apis/extensions/v1beta1/namespaces/{namespace}/ingresses/{name}/status (for clusters earlier than v1.15)
	Updating the status of an ingress in a specified namespace	PATCH /apis/networking.k8s.io/v1/namespaces/{namespace}/ingresses/{name}/status (for clusters of v1.21 and later) PATCH /apis/networking.k8s.io/v1beta1/namespaces/{namespace}/ingresses/{name}/status (for clusters from v1.15 to v1.21) PATCH /apis/extensions/v1beta1/namespaces/{namespace}/ingresses/{name}/status (for clusters earlier than v1.15)
Network Policy	Creating a network policy	POST /apis/networking.k8s.io/v1/namespaces/{namespace}/networkpolicies
	Updating a specified network policy	PATCH /apis/networking.k8s.io/v1/namespaces/{namespace}/networkpolicies/{name}
	Replacing a specified network policy	PUT /apis/networking.k8s.io/v1/namespaces/{namespace}/networkpolicies/{name}

API	Function	URI
	Deleting a specified network policy	DELETE /apis/networking.k8s.io/v1/namespaces/{namespace}/networkpolicies/{name}
	Deleting network policies in batches	DELETE /apis/networking.k8s.io/v1/namespaces/{namespace}/networkpolicies
	Reading a specified network policy	GET /apis/networking.k8s.io/v1/namespaces/{namespace}/networkpolicies/{name}
	Listing network policies in a specified namespace	GET /apis/networking.k8s.io/v1/namespaces/{namespace}/networkpolicies
	Listing all network policies	GET /apis/networking.k8s.io/v1/networkpolicies
PersistentVolume	Creating a PersistentVolume	POST /api/v1/persistentvolumes
	Deleting a specified PersistentVolume	DELETE /api/v1/persistentvolumes/{name}
	Deleting all PersistentVolumes	DELETE /api/v1/persistentvolumes
	Reading a specified PersistentVolume	GET /api/v1/persistentvolumes/{name}
	Replacing a specified PersistentVolume	PUT /api/v1/persistentvolumes/{name}
	Replacing the status of a specified PersistentVolume	PUT /api/v1/persistentvolumes/{name}/status
	Listing all PersistentVolumes	GET /api/v1/persistentvolumes
	Updating a specified PersistentVolume	PATCH /api/v1/persistentvolumes/{name}
PersistentVolumeClaim	Creating a PersistentVolumeClaim	POST /api/v1/namespaces/{namespace}/persistentvolumeclaims
	Deleting a specified PersistentVolumeClaim	DELETE /api/v1/namespaces/{namespace}/persistentvolumeclaims/{name}
	Deleting all PersistentVolume-Claims	DELETE /api/v1/namespaces/{namespace}/persistentvolumeclaims
	Reading a specified PersistentVolumeClaim	GET /api/v1/namespaces/{namespace}/persistentvolumeclaims/{name}

API	Function	URI
PersistentVolumeClaim	Replacing a specified PersistentVolumeClaim	PUT /api/v1/namespaces/{namespace}/persistentvolumeclaims/{name}
	Replacing the status of a specified PersistentVolumeClaim	PUT /api/v1/namespaces/{namespace}/persistentvolumeclaims/{name}/status
	Listing PersistentVolume-Claims in a specified namespace	GET /api/v1/namespaces/{namespace}/persistentvolumeclaims
	Listing all PersistentVolume-Claims	GET /api/v1/persistentvolumeclaims
	Updating a specified PersistentVolumeClaim	PATCH /api/v1/namespaces/{namespace}/persistentvolumeclaims/{name}
ConfigMap	Creating a ConfigMap	POST /api/v1/namespaces/{namespace}/configmaps
	Deleting a ConfigMap	DELETE /api/v1/namespaces/{namespace}/configmaps/{name}
	Deleting all ConfigMaps	DELETE /api/v1/namespaces/{namespace}/configmaps
	Reading a specified ConfigMap	GET /api/v1/namespaces/{namespace}/configmaps/{name}
	Replacing a specified ConfigMap	PUT /api/v1/namespaces/{namespace}/configmaps/{name}
	Listing ConfigMaps in a specified namespace	GET /api/v1/namespaces/{namespace}/configmaps
	Listing all ConfigMaps	GET /api/v1/configmaps
	Updating a specified ConfigMap	PATCH /api/v1/namespaces/{namespace}/configmaps/{name}
Secret	Creating a secret	POST /api/v1/namespaces/{namespace}/secrets
	Deleting a secret	DELETE /api/v1/namespaces/{namespace}/secrets/{name}
	Deleting all secrets in a specified namespace	DELETE /api/v1/namespaces/{namespace}/secrets
	Reading a specified secret	GET /api/v1/namespaces/{namespace}/secrets/{name}
	Replacing a specified secret	PUT /api/v1/namespaces/{namespace}/secrets/{name}

API	Function	URI
	Listing the secrets in a namespace	GET /api/v1/namespaces/{namespace}/secrets
	Listing secrets in a cluster	GET /api/v1/secrets
RBAC/ ClusterRole	Creating a ClusterRole	POST /apis/rbac.authorization.k8s.io/v1/clusterroles
	Updating a specified ClusterRole	PATCH /apis/rbac.authorization.k8s.io/v1/clusterroles/{name}
	Replacing a specified ClusterRole	PUT /apis/rbac.authorization.k8s.io/v1/clusterroles/{name}
	Deleting a specified ClusterRole	DELETE /apis/rbac.authorization.k8s.io/v1/clusterroles/{name}
	Deleting ClusterRoles in batches	DELETE /apis/rbac.authorization.k8s.io/v1/clusterroles
	Reading a specified ClusterRole	GET /apis/rbac.authorization.k8s.io/v1/clusterroles/{name}
	Listing ClusterRoles	GET /apis/rbac.authorization.k8s.io/v1/clusterroles
RBAC/ ClusterRoleBinding	Creating a ClusterRoleBinding	POST /apis/rbac.authorization.k8s.io/v1/clusterrolebindings
	Updating a specified ClusterRoleBinding	PATCH /apis/rbac.authorization.k8s.io/v1/clusterrolebindings/{name}
	Replacing a specified ClusterRoleBinding	PUT /apis/rbac.authorization.k8s.io/v1/clusterrolebindings/{name}
	Deleting a specified ClusterRoleBinding	DELETE /apis/rbac.authorization.k8s.io/v1/clusterrolebindings/{name}
	Deleting ClusterRoleBindings in batches	DELETE /apis/rbac.authorization.k8s.io/v1/clusterrolebindings
	Reading a specified ClusterRoleBinding	GET /apis/rbac.authorization.k8s.io/v1/clusterrolebindings/{name}
	Listing ClusterRoleBindings	GET /apis/rbac.authorization.k8s.io/v1/clusterrolebindings
RBAC/ Role	Creating a Role	POST /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/roles
	Updating a specified Role	PATCH /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/roles/{name}

API	Function	URI
	Replacing a specified Role	PUT /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/roles/{name}
	Deleting a specified Role	DELETE /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/roles/{name}
	Deleting Roles in batches	DELETE /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/roles
	Reading a specified Role	GET /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/roles/{name}
	Listing Roles in a specified namespace	GET /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/roles
	Listing all Roles	GET /apis/rbac.authorization.k8s.io/v1/roles
RBAC/ RoleBinding	Creating a RoleBinding	POST /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/rolebindings
	Updating a specified RoleBinding	PATCH /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/rolebindings/{name}
	Replacing a specified RoleBinding	PUT /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/rolebindings/{name}
	Deleting a specified RoleBinding	DELETE /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/rolebindings/{name}
	Deleting RoleBindings in batches	DELETE /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/rolebindings
	Reading a specified RoleBinding	GET /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/rolebindings/{name}
	Listing RoleBindings in a specified namespace	GET /apis/rbac.authorization.k8s.io/v1/namespaces/{namespace}/rolebindings
	Listing all RoleBindings	GET /apis/rbac.authorization.k8s.io/v1/rolebindings
API groups	Listing APIVersions	GET /api
	Listing APIGroups	GET /apis
	listing APIResources of GroupVersion apiregistration.k8s.io/v1beta1	GET /apis/apiregistration.k8s.io/v1beta1

API	Function	URI
	listing APIResources of GroupVersion extensions/v1beta1	GET /apis/extensions/v1beta1
	listing APIResources of GroupVersion apps/v1&apps/v1beta1	GET /apis/apps/v1 (for clusters later than v1.15) GET /apis/apps/v1beta1 (for clusters of v1.15 and earlier)
	listing APIResources of GroupVersion authentication.k8s.io/v1	GET /apis/authentication.k8s.io/v1
	listing APIResources of GroupVersion authentication.k8s.io/v1beta1	GET /apis/authentication.k8s.io/v1beta1
	listing APIResources of GroupVersion authorization.k8s.io/v1	GET /apis/authorization.k8s.io/v1
	listing APIResources of GroupVersion authorization.k8s.io/v1beta1	GET /apis/authorization.k8s.io/v1beta1
	listing APIResources of GroupVersion autoscaling/v1	GET /apis/autoscaling/v1
	listing APIResources of GroupVersion batch/v1	GET /apis/batch/v1
	listing APIResources of GroupVersion certificates.k8s.io/v1beta1	GET /apis/certificates.k8s.io/v1beta1
	listing APIResources of GroupVersion networking.k8s.io/v1	GET /apis/networking.k8s.io/v1
	listing APIResources of GroupVersion policy/v1beta1	GET /apis/policy/v1beta1
	listing APIResources of GroupVersion rbac.authorization.k8s.io/v1beta1	GET /apis/rbac.authorization.k8s.io/v1beta1

API	Function	URI
	listing APIResources of GroupVersion storage.k8s.io/v1	GET /apis/storage.k8s.io/v1
	listing APIResources of GroupVersion storage.k8s.io/v1beta1	GET /apis/storage.k8s.io/v1beta1
	listing APIResources of GroupVersion apiextensions.k8s.io/v1beta1	GET /apis/apiextensions.k8s.io/v1beta1
	listing APIResources of GroupVersion v1	GET /api/v1
Event	Reading events	GET /api/v1/events
	Listing events in a specified namespace	GET /api/v1/namespaces/{namespace}/events

3 Calling APIs

3.1 Making an API Request

This section describes the structure of a REST API request, and uses the IAM API for obtaining a user token as an example to demonstrate how to call an API. The obtained token can then be used to authenticate the calling of other APIs.

Request URI

A request URI is in the following format:

{URI-scheme}://{Endpoint}/{resource-path}?{query-string}

Although a request URI is included in the request header, most programming languages or frameworks require the request URI to be transmitted separately.

Table 3-1 URI parameters

Parameter	Description
URI-scheme	Protocol used to transmit requests. All APIs use HTTPS.
Endpoint	Domain name or IP address of the server bearing the REST service. The endpoint varies between services in different regions. It can be obtained from Regions and Endpoints .
resource-path	Access path of an API for performing an operation. Obtain the path from the URI of an API. For example, the resource-path of the API used to obtain a user token is /v3/auth/tokens .
query-string	Query parameter, which is optional. Ensure that a question mark (?) is included before each query parameter that is in the format of <i>Parameter name=Parameter value</i> . For example, ? limit=10 indicates that a maximum of 10 data records will be displayed.

 NOTE

To simplify the URI display in this document, each API is provided only with a **resource-path** and a request method. The **URI-scheme** of all APIs is **HTTPS**, and the endpoints of all APIs in the same region are identical.

Request Methods

The HTTP protocol defines the following request methods that can be used to send a request to the server.

Table 3-2 HTTP methods

Method	Description
GET	Requests the server to return specified resources.
PUT	Requests the server to update specified resources.
POST	Requests the server to add resources or perform special operations.
DELETE	Requests the server to delete specified resources, for example, an object.
HEAD	Requests the server to return the response header.
PATCH	Requests the server to update partial content of a specified resource. If the resource does not exist, a new resource will be created.

For example, in the case of the API used to obtain a user token, the request method is **POST**. The request is as follows:

```
POST https://{{endpoint}}/v3/auth/tokens
```

Request Header

You can also add additional header fields to a request, such as the fields required by a specified URI or HTTP method. For example, to request for the authentication information, add **Content-Type**, which specifies the request body type.

Table 3-3 lists common request header fields.

Table 3-3 Common request header fields

Parameter	Description	Mandatory	Example Value
Host	Specifies the server domain name and port number of the resources being requested. The value can be obtained from the URL of the service API. The value is in the format of <i>Hostname:Port number</i> . If the port number is not specified, the default port is used. The default port number for https is 443 .	No This field is mandatory for AK/SK authentication.	code.test.com or code.test.com:443
Content-Type	Specifies the type (or format) of the message body. The default value application/json is recommended. Other values of this field will be provided for specific APIs if any.	Yes	application/json
Content-Length	Specifies the length of the request body. The unit is byte.	No	3495
X-Project-Id	Specifies the project ID. Obtain the project ID by following the instructions in Obtaining a Project ID .	No	e9993fc787d94b6c886cb aa340f9c0f4

Parameter	Description	Mandatory	Example Value
X-Auth-Token	<p>Specifies the user token.</p> <p>It is a response to the API for obtaining a user token (This is the only API that does not require authentication).</p> <p>After the request is processed, the value of X-Subject-Token in the response header is the token value.</p>	No This field is mandatory for token authentication.	The following is part of an example token: MIIPAgYJKoZIhvcNAQc-Co...ggg1BBIINPXsidG9rZ

NOTE

In addition to supporting authentication using tokens, APIs support authentication using AK/SK, which uses SDKs to sign a request. During the signature, the **Authorization** (signature authentication) and **X-Sdk-Date** (time when a request is sent) headers are automatically added in the request.

For more details, see "Authentication Using AK/SK" in [Authentication](#).

The API used to obtain a user token does not require authentication. Therefore, only the **Content-Type** field needs to be added to requests for calling the API. An example of such requests is as follows:

```
POST https://{{endpoint}}/v3/auth/tokens
Content-Type: application/json
```

(Optional) Request Body

This part is optional. The body of a request is often sent in a structured format as specified in the **Content-Type** header field. The request body transfers content except the request header.

The request body varies between APIs. Some APIs do not require the request body, such as the APIs requested using the GET and DELETE methods.

In the case of the API used to obtain a user token, the request parameters and parameter details can be obtained from the API request. The following provides an example request with a body included. Replace **username**, **domainname**, ********* (login password), and **xxxxxxxxxxxxxxxxxx** (project name) with the actual values. You can obtain a project name from [Regions and Endpoints](#).

NOTE

The **scope** parameter specifies where a token takes effect. You can set **scope** to an account or a project under an account. In the following example, the token takes effect only for the resources in a specified project. For more information about this API, see [Obtaining a User Token](#).

```
POST https://{{endpoint}}/v3/auth/tokens
Content-Type: application/json

{
  "auth": {
    "identity": {
      "methods": [
        "password"
      ],
      "password": {
        "user": {
          "name": "username",
          "password": "*****",
          "domain": {
            "name": "domainname"
          }
        }
      }
    },
    "scope": {
      "project": {
        "name": "xxxxxxxxxxxxxxxxxx"
      }
    }
  }
}
```

If all data required for the API request is available, you can send the request to call the API through [curl](#), [Postman](#), or coding. In the response to the API used to obtain a user token, **x-subject-token** is the desired user token. This token can then be used to authenticate the calling of other APIs.

3.2 Authentication

Requests for calling an API can be authenticated using either of the following methods:

- Token authentication: Requests are authenticated using tokens.
- AK/SK authentication: Requests are encrypted using an AK/SK. AK/SK-based authentication is recommended because it is more secure than token-based authentication.

Token-based Authentication



NOTE

The validity period of a token is 24 hours. When using a token for authentication, cache it to prevent frequently calling the IAM API used to obtain a user token.

A token specifies temporary permissions in a computer system. During API authentication using a token, the token is added to requests to get permissions for calling the API.

You can obtain a token by calling the Obtaining a User Token API. When you call the API, set **auth.scope** in the request body to **project**.

```
{
  "auth": {
    "identity": {
      "methods": [
        "password"
      ],
      "password": {
        "user": {
          "name": "username",
          "password": "*****",
          "domain": {
            "name": "domainname"
          }
        }
      }
    },
    "scope": {
      "project": {
        "name": "xxxxxxxxxxxxxxxxxx"
      }
    }
  }
}
```

```
        "password"
    ],
    "password": {
        "user": {
            "name": "username",
            "password": "*****",
            "domain": {
                "name": "domainname"
            }
        }
    }
},
"scope": {
    "project": {
        "name": "xxxxxxx"
    }
}
}
```

After a token is obtained, the **X-Auth-Token** header field must be added to requests to specify the token when calling other APIs. For example, if the token is **ABCDEFJ....**, **X-Auth-Token: ABCDEFJ....** can be added to a request as follows:

```
POST https://{{endpoint}}/v3/auth/projects
Content-Type: application/json
X-Auth-Token: ABCDEFJ....
```

AK/SK Authentication



AK/SK authentication supports API requests with a body not larger than 12 MB. For API requests with a larger body, token authentication is recommended.

In AK/SK authentication, AK/SK is used to sign requests and the signature is then added to the requests for authentication.

- AK: access key ID, which is a unique identifier used in conjunction with a secret access key to sign requests cryptographically.
- SK: secret access key, which is used in conjunction with an AK to sign requests cryptographically. It identifies a request sender and prevents the request from being modified.

In AK/SK authentication, you can use an AK/SK to sign requests based on the signature algorithm or using the signing SDK. For details about how to sign requests and use the signing SDK, see [API Request Signing Guide](#).



The signing SDK is only used for signing requests and is different from the SDKs provided by services.

3.3 Response

Status Code

After sending a request, you will receive a response, including a status code, response header, and response body.

A status code is a group of digits, ranging from 1xx to 5xx. It indicates the status of a request. For more information, see [Status Code](#).

For example, if status code **201** is returned for calling the API used to obtain a user token, the request is successful.

Response Header

Similar to a request, a response also has a header, for example, **Content-Type**.

Figure 3-1 shows the response header fields for the API used to obtain a user token. The **x-subject-token** header field is the desired user token. This token can then be used to authenticate the calling of other APIs.

Figure 3-1 Header fields of the response to the request for obtaining a user token

```
connection → keep-alive
content-type → application/json
date → Tue, 12 Feb 2019 06:52:13 GMT
server → Web Server
strict-transport-security → max-age=31536000; includeSubdomains;
transfer-encoding → chunked
via → proxy A
x-content-type-options → nosniff
x-download-options → noopener
x-frame-options → SAMEORIGIN
x-lam-trace-id → 218d45ab-d674-4995-af3a-2d0255ba41b5
x-subject-token
x-xss-protection → 1; mode=block;
```



Response Body

The body of a response is often returned in structured format as specified in the **Content-Type** header field. The response body transfers content except the response header.

The following is part of the response body for the API used to obtain a user token.

```
{
  "token": {
    "expires_at": "2019-02-13T06:52:13.855000Z",
    "methods": [
      "password"
    ],
    "catalog": [
      {
        "endpoints": [
          {
            "region_id": "eu-west-0",
            ....
```

If an error occurs during API calling, an error code and a message will be displayed. The following shows an error response body.

```
{  
    "error_msg": "The format of message is error",  
    "error_code": "AS.0001"  
}
```

In the response body, **error_code** is an error code, and **error_msg** provides information about the error.

4 APIs

4.1 API URL

- The URL format for cluster, node, node pool, add-on, and quota management is **https://Endpoint/uri**. *uri* indicates the resource path, that is, the API access path.
- The URL format for Kubernetes APIs, storage management, and add-on management is **https://{clusterid}.Endpoint/uri**. In the URL, *{clusterid}* indicates the cluster ID, and *uri* indicates the resource path, that is, the path for API access.

NOTE

- The format of the URL called by the add-on management APIs is **https://*{clusterid}*.Endpoint/uri**. However, *{clusterid}* is used only for the domain name and is not verified or used by the APIs. Set *{clusterid}* in the query or body. For details about *{clusterid}*, see the add-on management sections.
- *{clusterid}* is required for Kubernetes APIs and storage management, which indicates the cluster that needs to be accessed by calling the API.

Table 4-1 URL parameters

Parameter	Description
{clusterid}	Cluster ID. After a cluster is created, call the API for obtaining a cluster in a specified project to obtain the cluster ID.
Endpoint	URL that is the entry point for a web service. You can obtain it from Endpoints .
uri	Access path of an API for performing an operation. Obtain the path from the URI of an API. For example, the resource-path of the API used to obtain a user token is v3/auth/tokens .

4.2 Cluster Management

4.2.1 Creating a Cluster

Function

This API is used to create an empty cluster, which has only master nodes but no worker nodes. After creating a cluster by calling this API, you can add nodes by [creating nodes](#).

NOTE

- The URL for cluster management is in the format of `https://Endpoint/uri`, in which `uri` indicates the resource path, that is, the path for API access.
- By default, ICAgent is not installed when you call this API to create a cluster. If you need to install ICAgent, add `"cluster.install.addons.external/install": [{"addonTemplateName": "icagent"}]` to **annotations** in the request body. ICAgent will be automatically installed during cluster creation. ICAgent is an O&M data collection agent used by Application Performance Management (APM). It runs on each server to collect data from probes in real time. ICAgent is the prerequisite for achieving application O&M. If ICAgent is not installed, the application O&M functions cannot be used.

Constraints

Before calling the CCE API to create a cluster, ensure that the following conditions are met:

- A **VPC** is available.
- CIDR blocks have been properly set for containers and Services. They are not editable after cluster creation, unless you create a new cluster.
- An agency has been correctly created and is not deleted. If the agency verification fails, the cluster fails to be created. You can log in to the CCE console. If no agency is created, the system prompts you to create one. If an agency has been created, no message is displayed.
- By default, an account can create a maximum of five clusters in each region. If you need to create more clusters, you can submit an application to increase the quota.

URI

POST /api/v3/projects/{project_id}/clusters

Table 4-2 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-3 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-4 Request body parameters

Parameter	Mandatory	Type	Description
kind	Yes	String	API type. The value is fixed at Cluster or cluster and cannot be changed.
apiVersion	Yes	String	API version. The value is fixed at v3 and cannot be changed.
metadata	Yes	ClusterMetadata object	Basic information about a cluster. Metadata is a collection of attributes.
spec	Yes	ClusterSpec object	Detailed description of the cluster. CCE creates or updates objects by defining or updating spec .
status	No	ClusterStatus object	Cluster status and job ID of the cluster creation job.

Table 4-5 ClusterMetadata

Parameter	Mandatory	Type	Description
name	Yes	String	<p>Cluster name.</p> <p>Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.</p>
uid	No	String	<p>Cluster ID, which uniquely identifies a cluster. This ID is automatically generated after a cluster is created. Only the automatically generated ID will take effect.</p>
alias	No	String	<p>Alias of a cluster name displayed on the CCE console, and the name can be changed.</p> <p>Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.</p> <p>A cluster alias must be unique. In the request body for creating or updating a cluster, if the cluster alias is not specified or set to null, the cluster name will be used as the cluster alias. In the response body for obtaining a cluster, the cluster alias is returned. If it is not configured, the cluster name will be returned.</p>

Parameter	Mandatory	Type	Description
annotations	No	Map<String, String>	<p>Cluster annotations, in the format of key-value pairs.</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations: Does not label or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This field is not stored in the database and is used only to specify the add-ons to be installed in the cluster.• Install ICAgent during cluster creation by adding the key-value pair "cluster.install.addons.external / install": "[{"addonTemplateName": "icagent"}]".
labels	No	Map<String, String>	<p>Cluster labels, in the format of key-value pairs.</p> <p>NOTE</p> <p>The value of this field is automatically generated by the system and is used by the frontend to identify the features supported by the cluster during the upgrade. Customized values are invalid.</p>
creationTimestamp	No	String	Time when the cluster was created.
updateTimestamp	No	String	Time when the cluster was updated.

Table 4-6 ClusterSpec

Parameter	Mandatory	Type	Description
category	No	String	Cluster type. Options: <ul style="list-style-type: none">• CCE: CCE cluster. CCE cluster supports hybrid deployment of VMs and BMSs, and heterogeneous nodes such as GPU and NPU nodes, allowing you to run your containers in a secure and stable container runtime environment based on a high-performance network model.
type	No	String	Master node architecture: <ul style="list-style-type: none">• VirtualMachine: x86

Parameter	Mandatory	Type	Description
flavor	Yes	String	<p>Cluster specifications. Specifications of clusters of 1.15 or later versions can be changed after they are created. For details, see Modifying Cluster Specifications.</p> <p>Options:</p> <ul style="list-style-type: none">• cce.s1.small: a small-scale CCE cluster with one master node and a maximum of 50 worker nodes• cce.s1.medium: a medium-scale CCE cluster with one master node and a maximum of 200 worker nodes• cce.s2.small: a small-scale CCE cluster with three master nodes and a maximum of 50 worker nodes• cce.s2.medium: a medium-scale CCE cluster with three master nodes and a maximum of 200 worker nodes• cce.s2.large: a large-scale CCE cluster with three master nodes and a maximum of 1,000 worker nodes• cce.s2.xlarge: an ultra-large-scale CCE cluster with three master nodes and a maximum of 2,000 worker nodes

Parameter	Mandatory	Type	Description
			<p>NOTE</p> <p>The fields in the parameters are described as follows:</p> <ul style="list-style-type: none">• s1: specifies a cluster with one master node. If the master node is faulty, the cluster will become unavailable, but running workloads in the cluster are not affected.• s2: specifies an HA cluster with three master nodes. If one of the master nodes is faulty, the cluster is still available.• small: specifies that a cluster can manage a maximum of 50 worker nodes.• medium: specifies that a cluster can manage a maximum of 200 worker nodes.• large: specifies that a cluster can manage a maximum of 1,000 worker nodes.• xlarge: specifies that a cluster can manage a maximum of 2,000 worker nodes.

Parameter	Mandatory	Type	Description
version	No	String	<p>Cluster version, which mirrors the baseline version of the Kubernetes community. The latest version is recommended. You can create clusters of two latest versions on the CCE console. To learn which cluster versions are available, log in to the CCE console, create a cluster, and check the Cluster Version parameter. You can call APIs to create clusters of other versions. However, these cluster versions will be gradually terminated. For details about the support policy, see the CCE announcement.</p> <p>NOTE</p> <ul style="list-style-type: none">• If not specified, a cluster of the latest version will be created.• If a baseline cluster version is specified but the R version is not specified, a cluster of the latest R version will be created by default. It is a good practice not to specify the R version.

Parameter	Mandatory	Type	Description
platformVersion	No	String	<p>CCE cluster platform version, indicating the internal version under the cluster version (version). Platform versions are used to trace iterations in a major cluster version. They are unique within a major cluster version and recounted when the major cluster version changes. This parameter cannot be customized. When you create a cluster, the latest corresponding platform version is automatically selected.</p> <p>The format of platformVersion is cce.X.Y.</p> <ul style="list-style-type: none">• X: internal feature version, indicating changes in features, patches, or OS support in the cluster version. The value starts from 1 and increases monotonically.• Y: patch version of an internal feature version. It is used only for software package update after the feature version is brought online. No other modification is involved. The value starts from 0 and increases monotonically.
description	No	String	Cluster description, for example, which purpose the cluster is intended to serve. By default, this field is left unspecified. To modify cluster description after the cluster is created, call the API for updating cluster information or go to the cluster details page on the CCE console. Only UTF-8 encoding is supported.

Parameter	Mandatory	Type	Description
customSan	No	Array of strings	<p>Custom SAN field in the server certificate of the cluster API server, which must comply with the SSL and X509 format specifications.</p> <ol style="list-style-type: none">1. Duplicate names are not allowed.2. Must comply with the IP address and domain name formats. <p>Example:</p> <p>SAN 1: DNS Name=example.com SAN 2: DNS Name=www.example.com SAN 3: DNS Name=example.net SAN 4: IP Address=93.184.216.34</p>
ipv6enable	No	Boolean	Whether the cluster supports IPv6 addresses. This field is supported in clusters of v1.15 and later versions.
hostNetwork	Yes	HostNetwork object	Node networking parameters, including VPC and subnet ID. This field is mandatory because nodes in a cluster communicate with each other by using a VPC.
containerNetwork	Yes	ContainerNetwork object	Container networking parameters, including the container network model and container CIDR block.
serviceNetwork	No	ServiceNetwork object	Service CIDR block, including IPv4 CIDR blocks.
authentication	No	Authentication object	Configurations of the cluster authentication mode.
billingMode	No	Integer	Billing mode of a cluster. <ul style="list-style-type: none">• 0: pay-per-use Defaults to pay-per-use.
masters	No	Array of MasterSpec objects	Advanced configurations of master nodes

Parameter	Mandatory	Type	Description
kubernetesSvcIpRange	No	String	Service CIDR blocks for Kubernetes clusterIPs. This field is available only for clusters of v1.11.7 and later. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used. This parameter is deprecated. Use serviceNetwork instead. The new field contains the IPv4 CIDR blocks.
clusterTags	No	Array of ResourceTag objects	Cluster resource tags.
kubeProxyMode	No	String	Service forwarding mode. Options: <ul style="list-style-type: none">• iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.• ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. NOTE iptables is used by default.
az	No	String	AZ. This field is returned only for a query.

Parameter	Mandatory	Type	Description
extendParam	No	ClusterExtendedParam object	Extended field to decide whether the cluster will span across AZs or belong to a specified enterprise project, or whether a dedicated CCE cluster is to be created.
supportIstio	No	Boolean	Whether Istio is supported.
configurationsOverride	No	Array of PackageConfiguration objects	Whether to overwrite the default component configurations of the cluster. If a component or a parameter that is not supported by the component is specified, this configuration is ignored.

Table 4-7 HostNetwork

Parameter	Mandatory	Type	Description
vpc	Yes	String	ID of the VPC used to create a master node. Obtain the public address by performing the following steps: <ul style="list-style-type: none">Method 1: Log in to the VPC console, and click the name of a VPC to view the VPC ID on the displayed details page.Method 2: Use the VPC API to query the VPC ID.
subnet	Yes	String	Network ID of the subnet used to create a master node. Methods: <ul style="list-style-type: none">Method 1: Log in to VPC console and click the target subnet on the Subnets tab page. You can view the network ID on the displayed page.Method 2: Use the VPC API for querying subnets. . .

Parameter	Mandatory	Type	Description
SecurityGroup	No	String	Default worker node security group ID of the cluster. If specified, the cluster will be bound to the target security group. Otherwise, the system will automatically create a default worker node security group for you. The default worker node security group needs to allow access from certain ports to ensure normal communications.

Table 4-8 ContainerNetwork

Parameter	Mandatory	Type	Description
mode	Yes	String	Container network model. Select one of the following possible values: <ul style="list-style-type: none">• overlay_l2: an overlay_l2 network (container tunnel network) built for containers by using OpenVSwitch (OVS).• vpc-router: an underlay_l2 network built for containers by using IPvlan and custom VPC routes.
cidr	No	String	Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, or 192.168.0.0/16-19. If the selected CIDR block conflicts with existing ones, an error will be reported. Not editable after the cluster is created. (deprecated. A specified cids will make cidr invalid.)

Parameter	Mandatory	Type	Description
cids	No	Array of ContainerCID R objects	List of container CIDR blocks. In clusters of v1.21 or later, the cids field is used. When the cluster network type is vpc-router , you can configure a maximum of 20 container CIDR blocks. In cluster versions earlier than v1.21, if the cids field is used, the first CIDR element in the array is used as the container CIDR block. The configuration cannot be modified after the cluster is created.

Table 4-9 ContainerCIDR

Parameter	Mandatory	Type	Description
cidr	Yes	String	Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, and 192.168.0.0/16-19

Table 4-10 EniNetwork

Parameter	Mandatory	Type	Description
eniSubnetId	Yes	String	IPv4 subnet ID of ENI subnet. (IPv6 is not supported and is being discarded.) You can obtain it in either of the following ways: <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.
eniSubnetCIDR	No	String	ENI subnet CIDR (being discarded)

Parameter	Mandatory	Type	Description
subnets	Yes	Array of NetworkSubnet objects	List of IPv4 subnet IDs

Table 4-11 NetworkSubnet

Parameter	Mandatory	Type	Description
subnetID	Yes	String	<p>IPv4 subnet ID of the subnet for creating master nodes. Currently, IPv6 is not supported. You can obtain it in either of the following ways:</p> <ul style="list-style-type: none"> Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page. Method 2: Use the VPC API for querying subnets.

Table 4-12 ServiceNetwork

Parameter	Mandatory	Type	Description
IPv4CIDR	No	String	<p>Value range of the Kubernetes clusterIP IPv4 CIDR blocks. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used.</p>

Table 4-13 Authentication

Parameter	Mandatory	Type	Description
mode	No	String	Cluster authentication mode. <ul style="list-style-type: none">● Clusters of Kubernetes v1.11 or earlier support x509, rbac, and authenticating_proxy. Defaults to x509.● Clusters of Kubernetes v1.13 or later support rbac and authenticating_proxy. Defaults to rbac.
authenticatin gProxy	No	Authenticati ngProxy object	Configuration related to the authenticating_proxy mode. This field is mandatory when the authentication mode is authenticating_proxy .

Table 4-14 AuthenticatingProxy

Parameter	Mandatory	Type	Description
ca	No	String	X509 CA certificate (Base64-encoded) configured in authenticating_proxy mode. This field is mandatory when the cluster authentication mode is authenticating_proxy . Maximum size: 1 MB
cert	No	String	Client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .

Parameter	Mandatory	Type	Description
privateKey	No	String	Private key of the client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. The private key used by the Kubernetes cluster does not support password encryption. Use an unencrypted private key. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .

Table 4-15 MasterSpec

Parameter	Mandatory	Type	Description
availabilityZone	No	String	AZ

Table 4-16 ResourceTag

Parameter	Mandatory	Type	Description
key	No	String	<p>Key.</p> <ul style="list-style-type: none">• Cannot be null. Max characters: 128.• Use letters, digits, and spaces in UTF-8 format.• Can contain the following special characters: _.:=/=+-@.• Cannot start with <code>_sys_</code>.

Parameter	Mandatory	Type	Description
value	No	String	<p>Value.</p> <ul style="list-style-type: none">• Can be null but not the default. Max characters: 255.• Use letters, digits, and spaces in UTF-8 format.• Can contain the following special characters: _.:;/=-+@.

Table 4-17 ClusterExtendParam

Parameter	Mandatory	Type	Description
clusterAZ	No	String	<p>AZ of master nodes in a cluster.</p> <ul style="list-style-type: none">• multi_az: (Optional) The cluster will span across AZs. Multiple AZs can be configured only for a cluster with multiple master nodes is used.• <i>AZ of the dedicated cloud computing pool.</i> The cluster will be deployed in the AZ of Dedicated Cloud (DeC). It is mandatory for dedicated CCE clusters.

Parameter	Mandatory	Type	Description
dssMasterVolumes	No	String	<p>Whether the system and data disks of a master node use dedicated distributed storage. If this parameter is omitted or left unspecified, EVS disks are used by default.</p> <p>This parameter is mandatory for dedicated CCE clusters. It is in the following format: <code><rootVol.dssPoolID>.<rootVol.volType>;<dataVol.dssPoolID>.<dataVol.volType></code></p> <p>Field description:</p> <ul style="list-style-type: none"> • rootVol is the system disk. dataVol is the data disk. • dssPoolID indicates the ID of the DSS storage pool. • volType indicates the storage volume type of the DSS storage pool, such as SAS and SSD. <p>Example: <code>c950ee97-587c-4f24-8a74-3367e3da570f.sas;6edbc2f4-1507-44f8-ac0d-eed1d2608d38.ssd</code></p> <p>NOTE This field cannot be configured for non-dedicated CCE clusters.</p>
enterpriseProjectId	No	String	<p>ID of the enterprise project that a cluster belongs to.</p> <p>NOTE</p> <ul style="list-style-type: none"> • An enterprise project can be configured only after the enterprise project function is enabled. • The enterprise project to which the cluster belongs must be the same as that to which other cloud service resources associated with the cluster belong.

Parameter	Mandatory	Type	Description
kubeProxyMode	No	String	<p>Service forwarding mode. Two modes are available:</p> <ul style="list-style-type: none">• iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.• ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE This parameter has been deprecated. If this parameter and kubeProxyMode in ClusterSpec are specified at the same time, the latter is used.</p>
clusterExternalIP	No	String	EIP of the master node

Parameter	Mandatory	Type	Description
alpha.cce/ fixPoolMask	No	String	<p>Number of mask bits of the fixed IP address pool of the container network model. This field is supported only for the VPC network model (vpc-router).</p> <p>This parameter determines the number of container IP addresses that can be allocated to a node. The maximum number of pods that can be created on a node is decided by this parameter and maxPods set during node creation. For details, see Maximum Number of Pods That Can Be Created on a Node.</p> <p>For integer characters, the value ranges from 24 to 28.</p>
decMasterFlavor	No	String	Specifications of the master node in the dedicated hybrid cluster.
dockerUmaskMode	No	String	Default UmaskMode configuration of Docker in a cluster. The value can be secure or normal . If this parameter is not specified, normal is used by default.
kubernetes.io/ cpuManagerPolicy	No	String	<p>Cluster CPU management policy. The value can be none (or null) or static. The default value is none (or null).</p> <ul style="list-style-type: none">• none or null: disables pods from exclusively occupying CPUs. Select this option if you want a large pool of shareable CPU cores.• static: enables pods to exclusively occupy CPUs. Select this option if your workload is sensitive to CPU cache and scheduling latency.

Parameter	Mandatory	Type	Description
upgradefrom	No	String	Records of how the cluster is upgraded to the current version

Table 4-18 PackageConfiguration

Parameter	Mandatory	Type	Description
name	No	String	Component name.
configurations	No	Array of ConfigurationItem objects	Component configuration item.

Table 4-19 ConfigurationItem

Parameter	Mandatory	Type	Description
name	No	String	Component configuration item name.
value	No	Object	Component configuration item value.

Table 4-20 ClusterStatus

Parameter	Mandatory	Type	Description
phase	No	String	<p>Cluster status. Options:</p> <ul style="list-style-type: none">• Available: The cluster is running properly.• Unavailable: The cluster is exhibiting unexpected behavior. Manually delete it.• ScalingUp: Nodes are being added to the cluster.• ScalingDown: The cluster is being downsized to fewer nodes.• Creating: The cluster is being created.• Deleting: The cluster is being deleted.• Upgrading: The cluster is being upgraded.• Resizing: Cluster specifications are being changed.• RollingBack: The cluster is being rolled back.• RollbackFailed: The cluster rollback is abnormal.• Hibernating: The cluster is being hibernated.• Hibernation: The cluster is in hibernation.• Awaking: The cluster is being woken up from hibernation.• Empty: The cluster does not have any resources. This field is discarded.• Error: Resources in the cluster are abnormal. Manually delete the cluster.

Parameter	Mandatory	Type	Description
jobID	No	String	<p>ID of the task associated with the cluster in the current state. Options:</p> <ul style="list-style-type: none">• ID of the associated task returned when creating a cluster. You can use it to obtain the auxiliary tasks for creating a cluster.• ID of the associated task returned when a cluster fails to be deleted or is deleted. If this parameter is not empty, you can use the task ID to obtain the auxiliary tasks for deleting a cluster. <p>NOTE Tasks are short-lived. Do not use task information in scenarios such as cluster status determination.</p>
reason	No	String	Reason of cluster state change. This parameter is returned if the cluster is not in the Available state.
message	No	String	Detailed information about why the cluster changes to the current state. This parameter is returned if the cluster is not in the Available state.
endpoints	No	Array of ClusterEndpo ints objects	Access address of kube-apiserver in the cluster.
deleteOption	No	Object	Whether to delete configurations. This parameter is contained only in the response to the deletion request.
deleteStatus	No	Object	Whether to delete the status information. This parameter is contained only in the response to the deletion request.

Table 4-21 ClusterEndpoints

Parameter	Mandatory	Type	Description
url	No	String	Access address of kube-apiserver in the cluster.
type	No	String	Type of the cluster access address. <ul style="list-style-type: none">• Internal: address for internal network access• External: address for external network access

Response Parameters

Status code: 201

Table 4-22 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Cluster or cluster and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	ClusterMetadata object	Basic information about a cluster. Metadata is a collection of attributes.
spec	ClusterSpec object	Detailed description of the cluster. CCE creates or updates objects by defining or updating spec .
status	ClusterStatus object	Cluster status and job ID of the cluster creation job.

Table 4-23 ClusterMetadata

Parameter	Type	Description
name	String	Cluster name. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.

Parameter	Type	Description
uid	String	Cluster ID, which uniquely identifies a cluster. This ID is automatically generated after a cluster is created. Only the automatically generated ID will take effect.
alias	String	<p>Alias of a cluster name displayed on the CCE console, and the name can be changed. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.</p> <p>A cluster alias must be unique.</p> <p>In the request body for creating or updating a cluster, if the cluster alias is not specified or set to null, the cluster name will be used as the cluster alias. In the response body for obtaining a cluster, the cluster alias is returned. If it is not configured, the cluster name will be returned.</p>
annotations	Map<String, String>	<p>Cluster annotations, in the format of key-value pairs.</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations: Does not label or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This field is not stored in the database and is used only to specify the add-ons to be installed in the cluster.• Install ICAgent during cluster creation by adding the key-value pair "cluster.install.addons.external/install":"[{"addonTemplateName":"icagent"}]" .
labels	Map<String, String>	<p>Cluster labels, in the format of key-value pairs.</p> <p>NOTE</p> <p>The value of this field is automatically generated by the system and is used by the frontend to identify the features supported by the cluster during the upgrade. Customized values are invalid.</p>
creationTimestamp	String	Time when the cluster was created.
updateTimestamp	String	Time when the cluster was updated.

Table 4-24 ClusterSpec

Parameter	Type	Description
category	String	Cluster type. Options: <ul style="list-style-type: none">• CCE: CCE cluster CCE cluster supports hybrid deployment of VMs and BMSs, and heterogeneous nodes such as GPU and NPU nodes, allowing you to run your containers in a secure and stable container runtime environment based on a high-performance network model.
type	String	Master node architecture: <ul style="list-style-type: none">• VirtualMachine: x86

Parameter	Type	Description
flavor	String	<p>Cluster specifications. Specifications of clusters of 1.15 or later versions can be changed after they are created. For details, see Modifying Cluster Specifications. Options:</p> <ul style="list-style-type: none">• cce.s1.small: a small-scale CCE cluster with one master node and a maximum of 50 worker nodes• cce.s1.medium: a medium-scale CCE cluster with one master node and a maximum of 200 worker nodes• cce.s2.small: a small-scale CCE cluster with three master nodes and a maximum of 50 worker nodes• cce.s2.medium: a medium-scale CCE cluster with three master nodes and a maximum of 200 worker nodes• cce.s2.large: a large-scale CCE cluster with three master nodes and a maximum of 1,000 worker nodes• cce.s2.xlarge: an ultra-large-scale CCE cluster with three master nodes and a maximum of 2,000 worker nodes <p>NOTE The fields in the parameters are described as follows:</p> <ul style="list-style-type: none">• s1: specifies a cluster with one master node. If the master node is faulty, the cluster will become unavailable, but running workloads in the cluster are not affected.• s2: specifies an HA cluster with three master nodes. If one of the master nodes is faulty, the cluster is still available.• small: specifies that a cluster can manage a maximum of 50 worker nodes.• medium: specifies that a cluster can manage a maximum of 200 worker nodes.• large: specifies that a cluster can manage a maximum of 1,000 worker nodes.• xlarge: specifies that a cluster can manage a maximum of 2,000 worker nodes.

Parameter	Type	Description
version	String	<p>Cluster version, which mirrors the baseline version of the Kubernetes community. The latest version is recommended.</p> <p>You can create clusters of two latest versions on the CCE console. To learn which cluster versions are available, log in to the CCE console, create a cluster, and check the Cluster Version parameter. You can call APIs to create clusters of other versions. However, these cluster versions will be gradually terminated. For details about the support policy, see the CCE announcement.</p> <p>NOTE</p> <ul style="list-style-type: none">• If not specified, a cluster of the latest version will be created.• If a baseline cluster version is specified but the R version is not specified, a cluster of the latest R version will be created by default. It is a good practice not to specify the R version.
platformVersion	String	<p>CCE cluster platform version, indicating the internal version under the cluster version (version). Platform versions are used to trace iterations in a major cluster version. They are unique within a major cluster version and recounted when the major cluster version changes. This parameter cannot be customized. When you create a cluster, the latest corresponding platform version is automatically selected.</p> <p>The format of platformVersion is cce.X.Y.</p> <ul style="list-style-type: none">• X: internal feature version, indicating changes in features, patches, or OS support in the cluster version. The value starts from 1 and increases monotonically.• Y: patch version of an internal feature version. It is used only for software package update after the feature version is brought online. No other modification is involved. The value starts from 0 and increases monotonically.
description	String	<p>Cluster description, for example, which purpose the cluster is intended to serve. By default, this field is left unspecified. To modify cluster description after the cluster is created, call the API for updating cluster information or go to the cluster details page on the CCE console. Only UTF-8 encoding is supported.</p>

Parameter	Type	Description
customSan	Array of strings	<p>Custom SAN field in the server certificate of the cluster API server, which must comply with the SSL and X509 format specifications.</p> <ol style="list-style-type: none">1. Duplicate names are not allowed.2. Must comply with the IP address and domain name formats. <p>Example:</p> <p>SAN 1: DNS Name=example.com SAN 2: DNS Name=www.example.com SAN 3: DNS Name=example.net SAN 4: IP Address=93.184.216.34</p>
ipv6enable	Boolean	Whether the cluster supports IPv6 addresses. This field is supported in clusters of v1.15 and later versions.
hostNetwork	HostNetwork object	Node networking parameters, including VPC and subnet ID. This field is mandatory because nodes in a cluster communicate with each other by using a VPC.
containerNetwork	ContainerNetwork object	Container networking parameters, including the container network model and container CIDR block.
serviceNetwork	ServiceNetwork object	Service CIDR block, including IPv4 CIDR blocks.
authentication	Authentication object	Configurations of the cluster authentication mode.
billingMode	Integer	Billing mode of a cluster. <ul style="list-style-type: none">• 0: pay-per-use Defaults to pay-per-use.
masters	Array of MasterSpec objects	Advanced configurations of master nodes
kubernetesSvcIpRange	String	Service CIDR blocks for Kubernetes clusterIPs. This field is available only for clusters of v1.11.7 and later. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used. This parameter is deprecated. Use serviceNetwork instead. The new field contains the IPv4 CIDR blocks.
clusterTags	Array of ResourceTag objects	Cluster resource tags.

Parameter	Type	Description
kubeProxyMode	String	<p>Service forwarding mode. Options:</p> <ul style="list-style-type: none">• iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.• ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE iptables is used by default.</p>
az	String	AZ. This field is returned only for a query.
extendParam	ClusterExtendedParam object	Extended field to decide whether the cluster will span across AZs or belong to a specified enterprise project, or whether a dedicated CCE cluster is to be created.
supportIstio	Boolean	Whether Istio is supported.
configurationsOverride	Array of PackageConfiguration objects	Whether to overwrite the default component configurations of the cluster. If a component or a parameter that is not supported by the component is specified, this configuration is ignored.

Table 4-25 HostNetwork

Parameter	Type	Description
vpc	String	<p>ID of the VPC used to create a master node. Obtain the public address by performing the following steps:</p> <ul style="list-style-type: none">• Method 1: Log in to the VPC console, and click the name of a VPC to view the VPC ID on the displayed details page.• Method 2: Use the VPC API to query the VPC ID.

Parameter	Type	Description
subnet	String	<p>Network ID of the subnet used to create a master node. Methods:</p> <ul style="list-style-type: none">Method 1: Log in to VPC console and click the target subnet on the Subnets tab page. You can view the network ID on the displayed page.Method 2: Use the VPC API for querying subnets. . .
SecurityGroup	String	Default worker node security group ID of the cluster. If specified, the cluster will be bound to the target security group. Otherwise, the system will automatically create a default worker node security group for you. The default worker node security group needs to allow access from certain ports to ensure normal communications.

Table 4-26 ContainerNetwork

Parameter	Type	Description
mode	String	<p>Container network model. Select one of the following possible values:</p> <ul style="list-style-type: none">overlay_l2: an overlay_l2 network (container tunnel network) built for containers by using OpenVSwitch (OVS).vpc-router: an underlay_l2 network built for containers by using IPvlan and custom VPC routes.
cidr	String	<p>Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, or 192.168.0.0/16-19. If the selected CIDR block conflicts with existing ones, an error will be reported.</p> <p>Not editable after the cluster is created. (deprecated. A specified cids will make cidr invalid.)</p>

Parameter	Type	Description
cids	Array of ContainerCIDR objects	List of container CIDR blocks. In clusters of v1.21 or later, the cids field is used. When the cluster network type is vpc-router , you can configure a maximum of 20 container CIDR blocks. In cluster versions earlier than v1.21, if the cids field is used, the first CIDR element in the array is used as the container CIDR block. The configuration cannot be modified after the cluster is created.

Table 4-27 ContainerCIDR

Parameter	Type	Description
cidr	String	Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, and 192.168.0.0/16-19

Table 4-28 EniNetwork

Parameter	Type	Description
eniSubnetId	String	IPv4 subnet ID of ENI subnet. (IPv6 is not supported and is being discarded.) You can obtain it in either of the following ways: <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.
eniSubnetCIDR	String	ENI subnet CIDR (being discarded)
subnets	Array of NetworkSubnet objects	List of IPv4 subnet IDs

Table 4-29 NetworkSubnet

Parameter	Type	Description
subnetID	String	<p>IPv4 subnet ID of the subnet for creating master nodes. Currently, IPv6 is not supported. You can obtain it in either of the following ways:</p> <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.

Table 4-30 ServiceNetwork

Parameter	Type	Description
IPv4CIDR	String	Value range of the Kubernetes clusterIP IPv4 CIDR blocks. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used.

Table 4-31 Authentication

Parameter	Type	Description
mode	String	<p>Cluster authentication mode.</p> <ul style="list-style-type: none">Clusters of Kubernetes v1.11 or earlier support x509, rbac, and authenticating_proxy. Defaults to x509.Clusters of Kubernetes v1.13 or later support rbac and authenticating_proxy. Defaults to rbac.
authenticatin gProxy	Authenticati ngProxy object	Configuration related to the authenticating_proxy mode. This field is mandatory when the authentication mode is authenticating_proxy .

Table 4-32 AuthenticatingProxy

Parameter	Type	Description
ca	String	X509 CA certificate (Base64-encoded) configured in authenticating_proxy mode. This field is mandatory when the cluster authentication mode is authenticating_proxy . Maximum size: 1 MB
cert	String	Client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .
privateKey	String	Private key of the client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. The private key used by the Kubernetes cluster does not support password encryption. Use an unencrypted private key. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .

Table 4-33 MasterSpec

Parameter	Type	Description
availabilityZone	String	AZ

Table 4-34 ResourceTag

Parameter	Type	Description
key	String	Key. <ul style="list-style-type: none">● Cannot be null. Max characters: 128.● Use letters, digits, and spaces in UTF-8 format.● Can contain the following special characters: _.:;/=-@.● Cannot start with _sys_.

Parameter	Type	Description
value	String	<p>Value.</p> <ul style="list-style-type: none"> Can be null but not the default. Max characters: 255. Use letters, digits, and spaces in UTF-8 format. Can contain the following special characters: _.:/=+-@.

Table 4-35 ClusterExtendParam

Parameter	Type	Description
clusterAZ	String	<p>AZ of master nodes in a cluster.</p> <ul style="list-style-type: none"> multi_az: (Optional) The cluster will span across AZs. Multiple AZs can be configured only for a cluster with multiple master nodes is used. <i>AZ of the dedicated cloud computing pool.</i> The cluster will be deployed in the AZ of Dedicated Cloud (DeC). It is mandatory for dedicated CCE clusters.
dssMasterVolumes	String	<p>Whether the system and data disks of a master node use dedicated distributed storage. If this parameter is omitted or left unspecified, EVS disks are used by default.</p> <p>This parameter is mandatory for dedicated CCE clusters. It is in the following format: <code><rootVol.dssPoolID>.<rootVol.volType>;<dataVol.dssPoolID>.<dataVol.volType></code></p> <p>Field description:</p> <ul style="list-style-type: none"> rootVol is the system disk. dataVol is the data disk. dssPoolID indicates the ID of the DSS storage pool. volType indicates the storage volume type of the DSS storage pool, such as SAS and SSD. <p>Example: <code>c950ee97-587c-4f24-8a74-3367e3da570f.sas;6e dbc2f4-1507-44f8-ac0d-eed1d2608d38.ssd</code></p> <p>NOTE This field cannot be configured for non-dedicated CCE clusters.</p>

Parameter	Type	Description
enterpriseProjectId	String	<p>ID of the enterprise project that a cluster belongs to.</p> <p>NOTE</p> <ul style="list-style-type: none">An enterprise project can be configured only after the enterprise project function is enabled.The enterprise project to which the cluster belongs must be the same as that to which other cloud service resources associated with the cluster belong.
kubeProxyMode	String	<p>Service forwarding mode. Two modes are available:</p> <ul style="list-style-type: none">iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE This parameter has been deprecated. If this parameter and kubeProxyMode in ClusterSpec are specified at the same time, the latter is used.</p>
clusterExternalIP	String	EIP of the master node
alpha.cce/fixPoolMask	String	<p>Number of mask bits of the fixed IP address pool of the container network model. This field is supported only for the VPC network model (vpc-router).</p> <p>This parameter determines the number of container IP addresses that can be allocated to a node. The maximum number of pods that can be created on a node is decided by this parameter and maxPods set during node creation. For details, see Maximum Number of Pods That Can Be Created on a Node.</p> <p>For integer characters, the value ranges from 24 to 28.</p>
decMasterFlavor	String	Specifications of the master node in the dedicated hybrid cluster.

Parameter	Type	Description
dockerUmaskMode	String	Default UmaskMode configuration of Docker in a cluster. The value can be secure or normal . If this parameter is not specified, normal is used by default.
kubernetes.io/cpuManagerPolicy	String	<p>Cluster CPU management policy. The value can be none (or null) or static. The default value is none (or null).</p> <ul style="list-style-type: none">• none or null: disables pods from exclusively occupying CPUs. Select this option if you want a large pool of shareable CPU cores.• static: enables pods to exclusively occupy CPUs. Select this option if your workload is sensitive to CPU cache and scheduling latency.
upgradefrom	String	Records of how the cluster is upgraded to the current version

Table 4-36 PackageConfiguration

Parameter	Type	Description
name	String	Component name.
configurations	Array of ConfigurationItem objects	Component configuration item.

Table 4-37 ConfigurationItem

Parameter	Type	Description
name	String	Component configuration item name.
value	Object	Component configuration item value.

Table 4-38 ClusterStatus

Parameter	Type	Description
phase	String	<p>Cluster status. Options:</p> <ul style="list-style-type: none">• Available: The cluster is running properly.• Unavailable: The cluster is exhibiting unexpected behavior. Manually delete it.• ScalingUp: Nodes are being added to the cluster.• ScalingDown: The cluster is being downsized to fewer nodes.• Creating: The cluster is being created.• Deleting: The cluster is being deleted.• Upgrading: The cluster is being upgraded.• Resizing: Cluster specifications are being changed.• RollingBack: The cluster is being rolled back.• RollbackFailed: The cluster rollback is abnormal.• Hibernating: The cluster is being hibernated.• Hibernation: The cluster is in hibernation.• Awaking: The cluster is being woken up from hibernation.• Empty: The cluster does not have any resources. This field is discarded.• Error: Resources in the cluster are abnormal. Manually delete the cluster.
jobID	String	<p>ID of the task associated with the cluster in the current state. Options:</p> <ul style="list-style-type: none">• ID of the associated task returned when creating a cluster. You can use it to obtain the auxiliary tasks for creating a cluster.• ID of the associated task returned when a cluster fails to be deleted or is deleted. If this parameter is not empty, you can use the task ID to obtain the auxiliary tasks for deleting a cluster. <p>NOTE Tasks are short-lived. Do not use task information in scenarios such as cluster status determination.</p>
reason	String	Reason of cluster state change. This parameter is returned if the cluster is not in the Available state.

Parameter	Type	Description
message	String	Detailed information about why the cluster changes to the current state. This parameter is returned if the cluster is not in the Available state.
endpoints	Array of ClusterEndpoints objects	Access address of kube-apiserver in the cluster.
deleteOption	Object	Whether to delete configurations. This parameter is contained only in the response to the deletion request.
deleteStatus	Object	Whether to delete the status information. This parameter is contained only in the response to the deletion request.

Table 4-39 ClusterEndpoints

Parameter	Type	Description
url	String	Access address of kube-apiserver in the cluster.
type	String	Type of the cluster access address. <ul style="list-style-type: none">• Internal: address for internal network access• External: address for external network access

Example Requests

- Create an HA CCE cluster of v1.19 with three master nodes and a maximum of 50 worker nodes.

/api/v3/projects/{project_id}/clusters

```
{  
  "kind": "Cluster",  
  "apiVersion": "v3",  
  "metadata": {  
    "name": "cluster"  
  },  
  "spec": {  
    "category": "CCE",  
    "flavor": "cce.s2.small",  
    "version": "v1.19",  
    "hostNetwork": {  
      "vpc": "030bfb19-5fa7-42ad-8a0d-c0721d268867",  
      "subnet": "ca964acf-8468-4735-8229-97940ef6c881"  
    },  
    "containerNetwork": {  
      "mode": "vpc-router",  
      "cidr": "10.0.0.0/16"  
    },  
    "kubernetesSvclpRange": "10.247.0.0/16",  
  }  
}
```

```
"description" : "",  
"billingMode" : 0,  
"extendParam" : {  
    "kubeProxyMode" : "iptables",  
    "alpha.cce/fixPoolMask" : "25",  
    "enterpriseProjectId" : "0"  
},  
"authentication" : {  
    "mode" : "rbac"  
},  
"ipv6enable" : false  
}
```

- Create an HA CCE cluster of v1.19 with three master nodes and a maximum of 50 worker nodes and install ICAgent in the cluster.

/api/v3/projects/{project_id}/clusters

```
{  
    "kind" : "Cluster",  
    "apiVersion" : "v3",  
    "metadata" : {  
        "name" : "cluster",  
        "annotations" : {  
            "cluster.install.addons.external/install" : "[{\\"addonTemplateName\\":\\"icagent\\"}]"  
        }  
    },  
    "spec" : {  
        "category" : "CCE",  
        "flavor" : "cce.s2.small",  
        "version" : "v1.19",  
        "hostNetwork" : {  
            "vpc" : "030fbf19-5fa7-42ad-8a0d-c0721d268867",  
            "subnet" : "ca964acf-8468-4735-8229-97940ef6c881"  
        },  
        "containerNetwork" : {  
            "mode" : "vpc-router",  
            "cidr" : "10.0.0.0/16"  
        },  
        "kubernetesSvclpRange" : "10.247.0.0/16",  
        "description" : "",  
        "billingMode" : 0,  
        "extendParam" : {  
            "kubeProxyMode" : "iptables",  
            "alpha.cce/fixPoolMask" : "25",  
            "enterpriseProjectId" : "0"  
        },  
        "authentication" : {  
            "mode" : "rbac"  
        },  
        "ipv6enable" : false  
    }  
}
```

- Create an HA CCE cluster of v1.19 with three master nodes and a maximum of 50 worker nodes and configure the default security group for custom nodes in the cluster.

/api/v3/projects/{project_id}/clusters

```
{  
    "kind" : "Cluster",  
    "apiVersion" : "v3",  
    "metadata" : {  
        "name" : "cluster"  
    },  
    "spec" : {  
        "category" : "CCE",  
        "flavor" : "cce.s2.small",  
        "version" : "v1.19",  
        "defaultSecurityGroup" : "cce-sg-00000000"  
    }  
}
```

```
"hostNetwork" : {  
    "vpc" : "030bfb19-5fa7-42ad-8a0d-c0721d268867",  
    "subnet" : "ca964acf-8468-4735-8229-97940ef6c881",  
    "SecurityGroup" : "a4ef108c-2ec6-492f-a6c4-7b64e25ae490"  
},  
"containerNetwork" : {  
    "mode" : "vpc-router",  
    "cidr" : "10.0.0.0/16"  
},  
"kubernetesSvclpRange" : "10.247.0.0/16",  
"description" : "",  
"billingMode" : 0,  
"extendParam" : {  
    "kubeProxyMode" : "iptables",  
    "alpha.cce/fixPoolMask" : "25",  
    "enterpriseProjectId" : "0"  
},  
"authentication" : {  
    "mode" : "rbac"  
},  
"ipv6enable" : false  
}
```

- Create an HA CCE cluster of v1.25 with three master nodes and a maximum of 50 worker nodes.

/api/v3/projects/{project_id}/clusters

```
{  
    "kind" : "Cluster",  
    "apiVersion" : "v3",  
    "metadata" : {  
        "name" : "cluster"  
    },  
    "spec" : {  
        "category" : "Turbo",  
        "flavor" : "cce.s2.small",  
        "version" : "v1.25",  
        "type" : "VirtualMachine",  
        "hostNetwork" : {  
            "vpc" : "030bfb19-5fa7-42ad-8a0d-c0721d268867",  
            "subnet" : "ca964acf-8468-4735-8229-97940ef6c881"  
        },  
        "containerNetwork" : {  
            "mode" : "eni"  
        },  
        "eniNetwork" : {  
            "eniSubnetId" : "861fb11d-2f0e-4c10-a98a-166dc26e4ff7",  
            "eniSubnetCIDR" : "192.168.0.0/24",  
            "subnets" : [ {  
                "subnetID" : "861fb11d-2f0e-4c10-a98a-166dc26e4ff7"  
            } ]  
        },  
        "serviceNetwork" : {  
            "IPv4CIDR" : "10.247.0.0/16"  
        },  
        "description" : "",  
        "billingMode" : 0,  
        "extendParam" : {  
            "kubeProxyMode" : "iptables",  
            "enterpriseProjectId" : "0"  
        },  
        "authentication" : {  
            "mode" : "rbac"  
        },  
        "ipv6enable" : false  
    }  
}
```

Example Responses

Status code: 201

The cluster creation job is successfully delivered.

```
{  
    "kind" : "Cluster",  
    "apiVersion" : "v3",  
    "metadata" : {  
        "alias" : "cluster",  
        "name" : "cluster",  
        "uid" : "bce956e1-87f3-11ec-b5e5-0255ac101514",  
        "creationTimestamp" : "2022-02-07 08:55:45.785425492 +0000 UTC",  
        "updateTimestamp" : "2022-02-07 08:55:45.78542824 +0000 UTC",  
        "annotations" : {  
            "jobid" : "bd42f724-87f3-11ec-b5e5-0255ac101514",  
            "resourceJobId" : "bce99f78-87f3-11ec-b5e5-0255ac101514"  
        }  
    },  
    "spec" : {  
        "category" : "CCE",  
        "type" : "VirtualMachine",  
        "flavor" : "cce.s2.small",  
        "version" : "v1.19.10-r0",  
        "platformVersion" : "cce.5.0",  
        "hostNetwork" : {  
            "vpc" : "030fbfb19-5fa7-42ad-8a0d-c0721d268867",  
            "subnet" : "ca964acf-8468-4735-8229-97940ef6c881"  
        },  
        "containerNetwork" : {  
            "mode" : "vpc-router",  
            "cidr" : "10.0.0.0/16",  
            "cidrs" : [ {  
                "cidr" : "10.0.0.0/16"  
            } ]  
        },  
        "eniNetwork" : { },  
        "authentication" : {  
            "mode" : "rbac",  
            "authenticatingProxy" : { }  
        },  
        "billingMode" : 0,  
        "kubernetesSvclpRange" : "10.247.0.0/16",  
        "kubeProxyMode" : "iptables",  
        "extendParam" : {  
            "alpha.cce/fixPoolMask" : "25",  
            "enterpriseProjectId" : "0",  
            "kubeProxyMode" : "iptables",  
            "orderID" : ""  
        },  
        "status" : {  
            "phase" : "Creating",  
            "jobID" : "bd42f724-87f3-11ec-b5e5-0255ac101514"  
        }  
}
```

Status Codes

Status Code	Description
201	The cluster creation job is successfully delivered.

Error Codes

See [Error Codes](#).

4.2.2 Reading a Specified Cluster

Function

This API is used to obtain details about a specified cluster.



The URL for cluster management is in the format of https://Endpoint/uri. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

GET /api/v3/projects/{project_id}/clusters/{cluster_id}

Table 4-40 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Table 4-41 Query Parameters

Parameter	Mandatory	Type	Description
detail	No	String	Whether the details about a cluster are queried. If this parameter is set to true , the total number of nodes (totalNodesNumber), number of normal nodes (activeNodesNumber), total CPUs (totalNodesCPU), total memory size (totalNodesMemory), and installed add-ons (installedAddonInstances) will be added to the annotation. The details of installed add-ons include the add-on name (addonTemplateName), version (version), and status (status).

Request Parameters

Table 4-42 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-43 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Cluster or cluster and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	ClusterMetadata object	Basic information about a cluster. Metadata is a collection of attributes.
spec	ClusterSpec object	Detailed description of the cluster. CCE creates or updates objects by defining or updating spec .
status	ClusterStatus object	Cluster status.

Table 4-44 ClusterMetadata

Parameter	Type	Description
name	String	Cluster name. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.
uid	String	Cluster ID, which uniquely identifies a cluster. This ID is automatically generated after a cluster is created. Only the automatically generated ID will take effect.
alias	String	Alias of a cluster name displayed on the CCE console, and the name can be changed. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. A cluster alias must be unique. In the request body for creating or updating a cluster, if the cluster alias is not specified or set to null, the cluster name will be used as the cluster alias. In the response body for obtaining a cluster, the cluster alias is returned. If it is not configured, the cluster name will be returned.

Parameter	Type	Description
annotations	Map<String, String>	<p>Cluster annotations, in the format of key-value pairs.</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations: Does not label or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This field is not stored in the database and is used only to specify the add-ons to be installed in the cluster.• Install ICAgent during cluster creation by adding the key-value pair "cluster.install.addons.external/install":"[{"addonTemplateName":"icagent"}]".
labels	Map<String, String>	<p>Cluster labels, in the format of key-value pairs.</p> <p>NOTE</p> <p>The value of this field is automatically generated by the system and is used by the frontend to identify the features supported by the cluster during the upgrade. Customized values are invalid.</p>
creationTimestamp	String	Time when the cluster was created.
updateTimestamp	String	Time when the cluster was updated.

Table 4-45 ClusterSpec

Parameter	Type	Description
category	String	<p>Cluster type. Options:</p> <ul style="list-style-type: none">• CCE: CCE cluster CCE cluster supports hybrid deployment of VMs and BMSs, and heterogeneous nodes such as GPU and NPU nodes, allowing you to run your containers in a secure and stable container runtime environment based on a high-performance network model.
type	String	<p>Master node architecture:</p> <ul style="list-style-type: none">• VirtualMachine: x86

Parameter	Type	Description
flavor	String	<p>Cluster specifications. Specifications of clusters of 1.15 or later versions can be changed after they are created. For details, see Modifying Cluster Specifications. Options:</p> <ul style="list-style-type: none">• cce.s1.small: a small-scale CCE cluster with one master node and a maximum of 50 worker nodes• cce.s1.medium: a medium-scale CCE cluster with one master node and a maximum of 200 worker nodes• cce.s2.small: a small-scale CCE cluster with three master nodes and a maximum of 50 worker nodes• cce.s2.medium: a medium-scale CCE cluster with three master nodes and a maximum of 200 worker nodes• cce.s2.large: a large-scale CCE cluster with three master nodes and a maximum of 1,000 worker nodes• cce.s2.xlarge: an ultra-large-scale CCE cluster with three master nodes and a maximum of 2,000 worker nodes <p>NOTE The fields in the parameters are described as follows:</p> <ul style="list-style-type: none">• s1: specifies a cluster with one master node. If the master node is faulty, the cluster will become unavailable, but running workloads in the cluster are not affected.• s2: specifies an HA cluster with three master nodes. If one of the master nodes is faulty, the cluster is still available.• small: specifies that a cluster can manage a maximum of 50 worker nodes.• medium: specifies that a cluster can manage a maximum of 200 worker nodes.• large: specifies that a cluster can manage a maximum of 1,000 worker nodes.• xlarge: specifies that a cluster can manage a maximum of 2,000 worker nodes.

Parameter	Type	Description
version	String	<p>Cluster version, which mirrors the baseline version of the Kubernetes community. The latest version is recommended.</p> <p>You can create clusters of two latest versions on the CCE console. To learn which cluster versions are available, log in to the CCE console, create a cluster, and check the Cluster Version parameter. You can call APIs to create clusters of other versions. However, these cluster versions will be gradually terminated. For details about the support policy, see the CCE announcement.</p> <p>NOTE</p> <ul style="list-style-type: none">• If not specified, a cluster of the latest version will be created.• If a baseline cluster version is specified but the R version is not specified, a cluster of the latest R version will be created by default. It is a good practice not to specify the R version.
platformVersion	String	<p>CCE cluster platform version, indicating the internal version under the cluster version (version). Platform versions are used to trace iterations in a major cluster version. They are unique within a major cluster version and recounted when the major cluster version changes. This parameter cannot be customized. When you create a cluster, the latest corresponding platform version is automatically selected.</p> <p>The format of platformVersion is cce.X.Y.</p> <ul style="list-style-type: none">• X: internal feature version, indicating changes in features, patches, or OS support in the cluster version. The value starts from 1 and increases monotonically.• Y: patch version of an internal feature version. It is used only for software package update after the feature version is brought online. No other modification is involved. The value starts from 0 and increases monotonically.
description	String	<p>Cluster description, for example, which purpose the cluster is intended to serve. By default, this field is left unspecified. To modify cluster description after the cluster is created, call the API for updating cluster information or go to the cluster details page on the CCE console. Only UTF-8 encoding is supported.</p>

Parameter	Type	Description
customSan	Array of strings	<p>Custom SAN field in the server certificate of the cluster API server, which must comply with the SSL and X509 format specifications.</p> <ol style="list-style-type: none">1. Duplicate names are not allowed.2. Must comply with the IP address and domain name formats. <p>Example:</p> <p>SAN 1: DNS Name=example.com SAN 2: DNS Name=www.example.com SAN 3: DNS Name=example.net SAN 4: IP Address=93.184.216.34</p>
ipv6enable	Boolean	Whether the cluster supports IPv6 addresses. This field is supported in clusters of v1.15 and later versions.
hostNetwork	HostNetwork object	Node networking parameters, including VPC and subnet ID. This field is mandatory because nodes in a cluster communicate with each other by using a VPC.
containerNetwork	ContainerNetwork object	Container networking parameters, including the container network model and container CIDR block.
serviceNetwork	ServiceNetwork object	Service CIDR block, including IPv4 CIDR blocks.
authentication	Authentication object	Configurations of the cluster authentication mode.
billingMode	Integer	Billing mode of a cluster. <ul style="list-style-type: none">• 0: pay-per-use Defaults to pay-per-use.
masters	Array of MasterSpec objects	Advanced configurations of master nodes
kubernetesSvcIpRange	String	Service CIDR blocks for Kubernetes clusterIPs. This field is available only for clusters of v1.11.7 and later. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used. This parameter is deprecated. Use serviceNetwork instead. The new field contains the IPv4 CIDR blocks.
clusterTags	Array of ResourceTag objects	Cluster resource tags.

Parameter	Type	Description
kubeProxyMode	String	<p>Service forwarding mode. Options:</p> <ul style="list-style-type: none">• iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.• ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE iptables is used by default.</p>
az	String	AZ. This field is returned only for a query.
extendParam	ClusterExtendedParam object	Extended field to decide whether the cluster will span across AZs or belong to a specified enterprise project, or whether a dedicated CCE cluster is to be created.
supportIstio	Boolean	Whether Istio is supported.
configurationsOverride	Array of PackageConfiguration objects	Whether to overwrite the default component configurations of the cluster. If a component or a parameter that is not supported by the component is specified, this configuration is ignored.

Table 4-46 HostNetwork

Parameter	Type	Description
vpc	String	<p>ID of the VPC used to create a master node. Obtain the public address by performing the following steps:</p> <ul style="list-style-type: none">• Method 1: Log in to the VPC console, and click the name of a VPC to view the VPC ID on the displayed details page.• Method 2: Use the VPC API to query the VPC ID.

Parameter	Type	Description
subnet	String	<p>Network ID of the subnet used to create a master node. Methods:</p> <ul style="list-style-type: none">Method 1: Log in to VPC console and click the target subnet on the Subnets tab page. You can view the network ID on the displayed page.Method 2: Use the VPC API for querying subnets. . .
SecurityGroup	String	Default worker node security group ID of the cluster. If specified, the cluster will be bound to the target security group. Otherwise, the system will automatically create a default worker node security group for you. The default worker node security group needs to allow access from certain ports to ensure normal communications.

Table 4-47 ContainerNetwork

Parameter	Type	Description
mode	String	<p>Container network model. Select one of the following possible values:</p> <ul style="list-style-type: none">overlay_l2: an overlay_l2 network (container tunnel network) built for containers by using OpenVSwitch (OVS).vpc-router: an underlay_l2 network built for containers by using IPvlan and custom VPC routes.
cidr	String	<p>Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, or 192.168.0.0/16-19. If the selected CIDR block conflicts with existing ones, an error will be reported.</p> <p>Not editable after the cluster is created. (deprecated. A specified cids will make cidr invalid.)</p>

Parameter	Type	Description
cids	Array of ContainerCIDR objects	List of container CIDR blocks. In clusters of v1.21 or later, the cids field is used. When the cluster network type is vpc-router , you can configure a maximum of 20 container CIDR blocks. In cluster versions earlier than v1.21, if the cids field is used, the first CIDR element in the array is used as the container CIDR block. The configuration cannot be modified after the cluster is created.

Table 4-48 ContainerCIDR

Parameter	Type	Description
cidr	String	Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, and 192.168.0.0/16-19

Table 4-49 EniNetwork

Parameter	Type	Description
eniSubnetId	String	IPv4 subnet ID of ENI subnet. (IPv6 is not supported and is being discarded.) You can obtain it in either of the following ways: <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.
eniSubnetCIDR	String	ENI subnet CIDR (being discarded)
subnets	Array of NetworkSubnet objects	List of IPv4 subnet IDs

Table 4-50 NetworkSubnet

Parameter	Type	Description
subnetID	String	<p>IPv4 subnet ID of the subnet for creating master nodes. Currently, IPv6 is not supported. You can obtain it in either of the following ways:</p> <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.

Table 4-51 ServiceNetwork

Parameter	Type	Description
IPv4CIDR	String	Value range of the Kubernetes clusterIP IPv4 CIDR blocks. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used.

Table 4-52 Authentication

Parameter	Type	Description
mode	String	<p>Cluster authentication mode.</p> <ul style="list-style-type: none">Clusters of Kubernetes v1.11 or earlier support x509, rbac, and authenticating_proxy. Defaults to x509.Clusters of Kubernetes v1.13 or later support rbac and authenticating_proxy. Defaults to rbac.
authenticatin gProxy	Authenticati ngProxy object	Configuration related to the authenticating_proxy mode. This field is mandatory when the authentication mode is authenticating_proxy .

Table 4-53 AuthenticatingProxy

Parameter	Type	Description
ca	String	X509 CA certificate (Base64-encoded) configured in authenticating_proxy mode. This field is mandatory when the cluster authentication mode is authenticating_proxy . Maximum size: 1 MB
cert	String	Client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .
privateKey	String	Private key of the client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. The private key used by the Kubernetes cluster does not support password encryption. Use an unencrypted private key. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .

Table 4-54 MasterSpec

Parameter	Type	Description
availabilityZone	String	AZ

Table 4-55 ResourceTag

Parameter	Type	Description
key	String	Key. <ul style="list-style-type: none">● Cannot be null. Max characters: 128.● Use letters, digits, and spaces in UTF-8 format.● Can contain the following special characters: _.:;/=-@.● Cannot start with _sys_.

Parameter	Type	Description
value	String	<p>Value.</p> <ul style="list-style-type: none"> Can be null but not the default. Max characters: 255. Use letters, digits, and spaces in UTF-8 format. Can contain the following special characters: _.:/=+-@.

Table 4-56 ClusterExtendParam

Parameter	Type	Description
clusterAZ	String	<p>AZ of master nodes in a cluster.</p> <ul style="list-style-type: none"> multi_az: (Optional) The cluster will span across AZs. Multiple AZs can be configured only for a cluster with multiple master nodes is used. <i>AZ of the dedicated cloud computing pool.</i> The cluster will be deployed in the AZ of Dedicated Cloud (DeC). It is mandatory for dedicated CCE clusters.
dssMasterVolumes	String	<p>Whether the system and data disks of a master node use dedicated distributed storage. If this parameter is omitted or left unspecified, EVS disks are used by default.</p> <p>This parameter is mandatory for dedicated CCE clusters. It is in the following format: <code><rootVol.dssPoolID>.<rootVol.volType>;<dataVol.dssPoolID>.<dataVol.volType></code></p> <p>Field description:</p> <ul style="list-style-type: none"> rootVol is the system disk. dataVol is the data disk. dssPoolID indicates the ID of the DSS storage pool. volType indicates the storage volume type of the DSS storage pool, such as SAS and SSD. <p>Example: <code>c950ee97-587c-4f24-8a74-3367e3da570f.sas;6e dbc2f4-1507-44f8-ac0d-eed1d2608d38.ssd</code></p> <p>NOTE This field cannot be configured for non-dedicated CCE clusters.</p>

Parameter	Type	Description
enterpriseProjectId	String	<p>ID of the enterprise project that a cluster belongs to.</p> <p>NOTE</p> <ul style="list-style-type: none">An enterprise project can be configured only after the enterprise project function is enabled.The enterprise project to which the cluster belongs must be the same as that to which other cloud service resources associated with the cluster belong.
kubeProxyMode	String	<p>Service forwarding mode. Two modes are available:</p> <ul style="list-style-type: none">iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE This parameter has been deprecated. If this parameter and kubeProxyMode in ClusterSpec are specified at the same time, the latter is used.</p>
clusterExternalIP	String	EIP of the master node
alpha.cce/fixPoolMask	String	<p>Number of mask bits of the fixed IP address pool of the container network model. This field is supported only for the VPC network model (vpc-router).</p> <p>This parameter determines the number of container IP addresses that can be allocated to a node. The maximum number of pods that can be created on a node is decided by this parameter and maxPods set during node creation. For details, see Maximum Number of Pods That Can Be Created on a Node.</p> <p>For integer characters, the value ranges from 24 to 28.</p>
decMasterFlavor	String	Specifications of the master node in the dedicated hybrid cluster.

Parameter	Type	Description
dockerUmaskMode	String	Default UmaskMode configuration of Docker in a cluster. The value can be secure or normal . If this parameter is not specified, normal is used by default.
kubernetes.io/cpuManagerPolicy	String	<p>Cluster CPU management policy. The value can be none (or null) or static. The default value is none (or null).</p> <ul style="list-style-type: none">• none or null: disables pods from exclusively occupying CPUs. Select this option if you want a large pool of shareable CPU cores.• static: enables pods to exclusively occupy CPUs. Select this option if your workload is sensitive to CPU cache and scheduling latency.
upgradefrom	String	Records of how the cluster is upgraded to the current version

Table 4-57 PackageConfiguration

Parameter	Type	Description
name	String	Component name.
configurations	Array of ConfigurationItem objects	Component configuration item.

Table 4-58 ConfigurationItem

Parameter	Type	Description
name	String	Component configuration item name.
value	Object	Component configuration item value.

Table 4-59 ClusterStatus

Parameter	Type	Description
phase	String	<p>Cluster status. Options:</p> <ul style="list-style-type: none">• Available: The cluster is running properly.• Unavailable: The cluster is exhibiting unexpected behavior. Manually delete it.• ScalingUp: Nodes are being added to the cluster.• ScalingDown: The cluster is being downsized to fewer nodes.• Creating: The cluster is being created.• Deleting: The cluster is being deleted.• Upgrading: The cluster is being upgraded.• Resizing: Cluster specifications are being changed.• RollingBack: The cluster is being rolled back.• RollbackFailed: The cluster rollback is abnormal.• Hibernating: The cluster is being hibernated.• Hibernation: The cluster is in hibernation.• Awaking: The cluster is being woken up from hibernation.• Empty: The cluster does not have any resources. This field is discarded.• Error: Resources in the cluster are abnormal. Manually delete the cluster.
jobID	String	<p>ID of the task associated with the cluster in the current state. Options:</p> <ul style="list-style-type: none">• ID of the associated task returned when creating a cluster. You can use it to obtain the auxiliary tasks for creating a cluster.• ID of the associated task returned when a cluster fails to be deleted or is deleted. If this parameter is not empty, you can use the task ID to obtain the auxiliary tasks for deleting a cluster. <p>NOTE Tasks are short-lived. Do not use task information in scenarios such as cluster status determination.</p>
reason	String	Reason of cluster state change. This parameter is returned if the cluster is not in the Available state.

Parameter	Type	Description
message	String	Detailed information about why the cluster changes to the current state. This parameter is returned if the cluster is not in the Available state.
endpoints	Array of ClusterEndpoints objects	Access address of kube-apiserver in the cluster.
deleteOption	Object	Whether to delete configurations. This parameter is contained only in the response to the deletion request.
deleteStatus	Object	Whether to delete the status information. This parameter is contained only in the response to the deletion request.

Table 4-60 ClusterEndpoints

Parameter	Type	Description
url	String	Access address of kube-apiserver in the cluster.
type	String	Type of the cluster access address. <ul style="list-style-type: none">• Internal: address for internal network access• External: address for external network access

Example Requests

None

Example Responses

Status code: 200

Information about the specified cluster is successfully obtained.

```
{  
    "kind" : "Cluster",  
    "apiVersion" : "v3",  
    "metadata" : {  
        "alias" : "mycluster",  
        "name" : "mycluster",  
        "uid" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",  
        "creationTimestamp" : "2018-08-02 03:48:58.968214406 +0000 UTC",  
        "updateTimestamp" : "2018-08-02 04:05:29.386391813 +0000 UTC"  
    },  
    "spec" : {  
        "type" : "VirtualMachine",  
        "flavor" : "cce.s1.small",  
        "imageRef" : "centos7",  
        "keyPair" : "cce-keypair",  
        "securityGroups" : ["cce-sg"],  
        "volume" : {  
            "size" : 10,  
            "type" : "VolumeType",  
            "volumeType" : "VirtualMachineDisk",  
            "volumeTypeRef" : "VirtualMachineDiskType",  
            "volumeTypeRefName" : "VirtualMachineDiskType",  
            "volumeTypeRefUid" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",  
            "volumeTypeRefCreationTimestamp" : "2018-08-02 03:48:58.968214406 +0000 UTC",  
            "volumeTypeRefUpdateTimestamp" : "2018-08-02 04:05:29.386391813 +0000 UTC"  
        },  
        "nodeSelector" : {  
            "node-role.k8s.io/master" : "true"  
        },  
        "nodeAffinity" : {  
            "labelSelector" : {  
                "node-role.k8s.io/master" : "true"  
            },  
            "prefer": true  
        },  
        "nodeTaints" : [{}],  
        "nodeTolerations" : [{}],  
        "nodeLabels" : {  
            "node-role.k8s.io/master" : "true"  
        },  
        "nodeAnnotations" : {}  
    }  
}
```

```
"version" : "v1.7.3-r13",
"description" : "this is a demo cluster",
"customSan" : [ "192.168.1.0", "example.com" ],
"hostNetwork" : {
    "vpc" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",
    "subnet" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb"
},
"containerNetwork" : {
    "mode" : "overlay_l2",
    "cidr" : "172.16.0.0/16"
},
"authentication" : {
    "mode" : "x509",
    "authenticatingProxy" : { }
},
"billingMode" : 0
},
"status" : {
    "phase" : "Available",
    "endpoints" : [ {
        "url" : "https://192.168.0.11:5443",
        "type" : "Internal"
    } ]
}
```

Status Codes

Status Code	Description
200	Information about the specified cluster is successfully obtained.

Error Codes

See [Error Codes](#).

4.2.3 Listing Clusters in a Specified Project

Function

This API is used to obtain details about all clusters in a specified project.

URI

GET /api/v3/projects/{project_id}/clusters

Table 4-61 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Table 4-62 Query Parameters

Parameter	Mandatory	Type	Description
detail	No	String	Whether the details about a cluster are queried. If this parameter is set to true , the total number of nodes (totalNodesNumber), number of normal nodes (activeNodesNumber), total CPUs (totalNodesCPU), total memory size (totalNodesMemory), and installed add-ons (installedAddonInstances) will be added to the annotation. The details of installed add-ons include the add-on name (addonTemplateName), version (version), and status (status).

Parameter	Mandatory	Type	Description
status	No	String	<p>Cluster status. Options:</p> <ul style="list-style-type: none">• Available: The cluster is running properly.• Unavailable: The cluster is exhibiting unexpected behavior. Manually delete it.• ScalingUp: Nodes are being added to the cluster.• ScalingDown: The cluster is being downsized to fewer nodes.• Creating: The cluster is being created.• Deleting: The cluster is being deleted.• Upgrading: The cluster is being upgraded.• Resizing: Cluster specifications are being changed.• RollingBack: The cluster is being rolled back.• RollbackFailed: The cluster rollback is abnormal.• Hibernating: The cluster is being hibernated.• Hibernation: The cluster is in hibernation.• Awaking: The cluster is being woken up from hibernation.• Empty: The cluster does not have any resources. This field is discarded.• Error: Resources in the cluster are abnormal. Manually delete the cluster.
type	No	String	<p>Cluster type. Options:</p> <ul style="list-style-type: none">• VirtualMachine: CCE cluster• ARM64: Kunpeng cluster
version	No	String	Cluster version filtering.

Request Parameters

Table 4-63 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-64 Response body parameters

Parameter	Type	Description
kind	String	Api type
apiVersion	String	API version
items	Array of Cluster objects	A list of details for all clusters in the current project. You can filter clusters by items.metadata.name .

Table 4-65 Cluster

Parameter	Type	Description
kind	String	API type. The value is fixed at Cluster or cluster and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	ClusterMetadata object	Basic information about a cluster. Metadata is a collection of attributes.

Parameter	Type	Description
spec	ClusterSpec object	Detailed description of the cluster. CCE creates or updates objects by defining or updating spec .
status	ClusterStatus object	Cluster status and job ID of the cluster creation job.

Table 4-66 ClusterMetadata

Parameter	Type	Description
name	String	Cluster name. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.
uid	String	Cluster ID, which uniquely identifies a cluster. This ID is automatically generated after a cluster is created. Only the automatically generated ID will take effect.
alias	String	Alias of a cluster name displayed on the CCE console, and the name can be changed. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. A cluster alias must be unique. In the request body for creating or updating a cluster, if the cluster alias is not specified or set to null, the cluster name will be used as the cluster alias. In the response body for obtaining a cluster, the cluster alias is returned. If it is not configured, the cluster name will be returned.

Parameter	Type	Description
annotations	Map<String, String>	<p>Cluster annotations, in the format of key-value pairs.</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations: Does not label or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This field is not stored in the database and is used only to specify the add-ons to be installed in the cluster.• Install ICAgent during cluster creation by adding the key-value pair "cluster.install.addons.external/install":"[{"addonTemplateName":"icagent"}]".
labels	Map<String, String>	<p>Cluster labels, in the format of key-value pairs.</p> <p>NOTE</p> <p>The value of this field is automatically generated by the system and is used by the frontend to identify the features supported by the cluster during the upgrade. Customized values are invalid.</p>
creationTimestamp	String	Time when the cluster was created.
updateTimestamp	String	Time when the cluster was updated.

Table 4-67 ClusterSpec

Parameter	Type	Description
category	String	<p>Cluster type. Options:</p> <ul style="list-style-type: none">• CCE: CCE cluster CCE cluster supports hybrid deployment of VMs and BMSs, and heterogeneous nodes such as GPU and NPU nodes, allowing you to run your containers in a secure and stable container runtime environment based on a high-performance network model.
type	String	<p>Master node architecture:</p> <ul style="list-style-type: none">• VirtualMachine: x86

Parameter	Type	Description
flavor	String	<p>Cluster specifications. Specifications of clusters of 1.15 or later versions can be changed after they are created. For details, see Modifying Cluster Specifications. Options:</p> <ul style="list-style-type: none">• cce.s1.small: a small-scale CCE cluster with one master node and a maximum of 50 worker nodes• cce.s1.medium: a medium-scale CCE cluster with one master node and a maximum of 200 worker nodes• cce.s2.small: a small-scale CCE cluster with three master nodes and a maximum of 50 worker nodes• cce.s2.medium: a medium-scale CCE cluster with three master nodes and a maximum of 200 worker nodes• cce.s2.large: a large-scale CCE cluster with three master nodes and a maximum of 1,000 worker nodes• cce.s2.xlarge: an ultra-large-scale CCE cluster with three master nodes and a maximum of 2,000 worker nodes <p>NOTE The fields in the parameters are described as follows:</p> <ul style="list-style-type: none">• s1: specifies a cluster with one master node. If the master node is faulty, the cluster will become unavailable, but running workloads in the cluster are not affected.• s2: specifies an HA cluster with three master nodes. If one of the master nodes is faulty, the cluster is still available.• small: specifies that a cluster can manage a maximum of 50 worker nodes.• medium: specifies that a cluster can manage a maximum of 200 worker nodes.• large: specifies that a cluster can manage a maximum of 1,000 worker nodes.• xlarge: specifies that a cluster can manage a maximum of 2,000 worker nodes.

Parameter	Type	Description
version	String	<p>Cluster version, which mirrors the baseline version of the Kubernetes community. The latest version is recommended.</p> <p>You can create clusters of two latest versions on the CCE console. To learn which cluster versions are available, log in to the CCE console, create a cluster, and check the Cluster Version parameter. You can call APIs to create clusters of other versions. However, these cluster versions will be gradually terminated. For details about the support policy, see the CCE announcement.</p> <p>NOTE</p> <ul style="list-style-type: none">• If not specified, a cluster of the latest version will be created.• If a baseline cluster version is specified but the R version is not specified, a cluster of the latest R version will be created by default. It is a good practice not to specify the R version.
platformVersion	String	<p>CCE cluster platform version, indicating the internal version under the cluster version (version). Platform versions are used to trace iterations in a major cluster version. They are unique within a major cluster version and recounted when the major cluster version changes. This parameter cannot be customized. When you create a cluster, the latest corresponding platform version is automatically selected.</p> <p>The format of platformVersion is cce.X.Y.</p> <ul style="list-style-type: none">• X: internal feature version, indicating changes in features, patches, or OS support in the cluster version. The value starts from 1 and increases monotonically.• Y: patch version of an internal feature version. It is used only for software package update after the feature version is brought online. No other modification is involved. The value starts from 0 and increases monotonically.
description	String	<p>Cluster description, for example, which purpose the cluster is intended to serve. By default, this field is left unspecified. To modify cluster description after the cluster is created, call the API for updating cluster information or go to the cluster details page on the CCE console. Only UTF-8 encoding is supported.</p>

Parameter	Type	Description
customSan	Array of strings	<p>Custom SAN field in the server certificate of the cluster API server, which must comply with the SSL and X509 format specifications.</p> <ol style="list-style-type: none">1. Duplicate names are not allowed.2. Must comply with the IP address and domain name formats. <p>Example:</p> <p>SAN 1: DNS Name=example.com SAN 2: DNS Name=www.example.com SAN 3: DNS Name=example.net SAN 4: IP Address=93.184.216.34</p>
ipv6enable	Boolean	Whether the cluster supports IPv6 addresses. This field is supported in clusters of v1.15 and later versions.
hostNetwork	HostNetwork object	Node networking parameters, including VPC and subnet ID. This field is mandatory because nodes in a cluster communicate with each other by using a VPC.
containerNetwork	ContainerNetwork object	Container networking parameters, including the container network model and container CIDR block.
serviceNetwork	ServiceNetwork object	Service CIDR block, including IPv4 CIDR blocks.
authentication	Authentication object	Configurations of the cluster authentication mode.
billingMode	Integer	Billing mode of a cluster. <ul style="list-style-type: none">• 0: pay-per-use Defaults to pay-per-use.
masters	Array of MasterSpec objects	Advanced configurations of master nodes
kubernetesSvcIpRange	String	Service CIDR blocks for Kubernetes clusterIPs. This field is available only for clusters of v1.11.7 and later. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used. This parameter is deprecated. Use serviceNetwork instead. The new field contains the IPv4 CIDR blocks.
clusterTags	Array of ResourceTag objects	Cluster resource tags.

Parameter	Type	Description
kubeProxyMode	String	<p>Service forwarding mode. Options:</p> <ul style="list-style-type: none">• iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.• ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE iptables is used by default.</p>
az	String	AZ. This field is returned only for a query.
extendParam	ClusterExtendedParam object	Extended field to decide whether the cluster will span across AZs or belong to a specified enterprise project, or whether a dedicated CCE cluster is to be created.
supportIstio	Boolean	Whether Istio is supported.
configurationsOverride	Array of PackageConfiguration objects	Whether to overwrite the default component configurations of the cluster. If a component or a parameter that is not supported by the component is specified, this configuration is ignored.

Table 4-68 HostNetwork

Parameter	Type	Description
vpc	String	<p>ID of the VPC used to create a master node. Obtain the public address by performing the following steps:</p> <ul style="list-style-type: none">• Method 1: Log in to the VPC console, and click the name of a VPC to view the VPC ID on the displayed details page.• Method 2: Use the VPC API to query the VPC ID.

Parameter	Type	Description
subnet	String	<p>Network ID of the subnet used to create a master node. Methods:</p> <ul style="list-style-type: none">Method 1: Log in to VPC console and click the target subnet on the Subnets tab page. You can view the network ID on the displayed page.Method 2: Use the VPC API for querying subnets. . .
SecurityGroup	String	Default worker node security group ID of the cluster. If specified, the cluster will be bound to the target security group. Otherwise, the system will automatically create a default worker node security group for you. The default worker node security group needs to allow access from certain ports to ensure normal communications.

Table 4-69 ContainerNetwork

Parameter	Type	Description
mode	String	<p>Container network model. Select one of the following possible values:</p> <ul style="list-style-type: none">overlay_l2: an overlay_l2 network (container tunnel network) built for containers by using OpenVSwitch (OVS).vpc-router: an underlay_l2 network built for containers by using IPvlan and custom VPC routes.
cidr	String	<p>Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, or 192.168.0.0/16-19. If the selected CIDR block conflicts with existing ones, an error will be reported.</p> <p>Not editable after the cluster is created. (deprecated. A specified cids will make cidr invalid.)</p>

Parameter	Type	Description
cids	Array of ContainerCIDR objects	List of container CIDR blocks. In clusters of v1.21 or later, the cids field is used. When the cluster network type is vpc-router , you can configure a maximum of 20 container CIDR blocks. In cluster versions earlier than v1.21, if the cids field is used, the first CIDR element in the array is used as the container CIDR block. The configuration cannot be modified after the cluster is created.

Table 4-70 ContainerCIDR

Parameter	Type	Description
cidr	String	Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, and 192.168.0.0/16-19

Table 4-71 EniNetwork

Parameter	Type	Description
eniSubnetId	String	IPv4 subnet ID of ENI subnet. (IPv6 is not supported and is being discarded.) You can obtain it in either of the following ways: <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.
eniSubnetCIDR	String	ENI subnet CIDR (being discarded)
subnets	Array of NetworkSubnet objects	List of IPv4 subnet IDs

Table 4-72 NetworkSubnet

Parameter	Type	Description
subnetID	String	<p>IPv4 subnet ID of the subnet for creating master nodes. Currently, IPv6 is not supported. You can obtain it in either of the following ways:</p> <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.

Table 4-73 ServiceNetwork

Parameter	Type	Description
IPv4CIDR	String	Value range of the Kubernetes clusterIP IPv4 CIDR blocks. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used.

Table 4-74 Authentication

Parameter	Type	Description
mode	String	<p>Cluster authentication mode.</p> <ul style="list-style-type: none">Clusters of Kubernetes v1.11 or earlier support x509, rbac, and authenticating_proxy. Defaults to x509.Clusters of Kubernetes v1.13 or later support rbac and authenticating_proxy. Defaults to rbac.
authenticatin gProxy	Authenticati ngProxy object	Configuration related to the authenticating_proxy mode. This field is mandatory when the authentication mode is authenticating_proxy .

Table 4-75 AuthenticatingProxy

Parameter	Type	Description
ca	String	X509 CA certificate (Base64-encoded) configured in authenticating_proxy mode. This field is mandatory when the cluster authentication mode is authenticating_proxy . Maximum size: 1 MB
cert	String	Client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .
privateKey	String	Private key of the client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. The private key used by the Kubernetes cluster does not support password encryption. Use an unencrypted private key. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .

Table 4-76 MasterSpec

Parameter	Type	Description
availabilityZone	String	AZ

Table 4-77 ResourceTag

Parameter	Type	Description
key	String	Key. <ul style="list-style-type: none">● Cannot be null. Max characters: 128.● Use letters, digits, and spaces in UTF-8 format.● Can contain the following special characters: _.:;/=-@.● Cannot start with _sys_.

Parameter	Type	Description
value	String	<p>Value.</p> <ul style="list-style-type: none"> Can be null but not the default. Max characters: 255. Use letters, digits, and spaces in UTF-8 format. Can contain the following special characters: _.:/=+-@.

Table 4-78 ClusterExtendParam

Parameter	Type	Description
clusterAZ	String	<p>AZ of master nodes in a cluster.</p> <ul style="list-style-type: none"> multi_az: (Optional) The cluster will span across AZs. Multiple AZs can be configured only for a cluster with multiple master nodes is used. <i>AZ of the dedicated cloud computing pool.</i> The cluster will be deployed in the AZ of Dedicated Cloud (DeC). It is mandatory for dedicated CCE clusters.
dssMasterVolumes	String	<p>Whether the system and data disks of a master node use dedicated distributed storage. If this parameter is omitted or left unspecified, EVS disks are used by default.</p> <p>This parameter is mandatory for dedicated CCE clusters. It is in the following format: <code><rootVol.dssPoolID>.<rootVol.volType>;<dataVol.dssPoolID>.<dataVol.volType></code></p> <p>Field description:</p> <ul style="list-style-type: none"> rootVol is the system disk. dataVol is the data disk. dssPoolID indicates the ID of the DSS storage pool. volType indicates the storage volume type of the DSS storage pool, such as SAS and SSD. <p>Example: <code>c950ee97-587c-4f24-8a74-3367e3da570f.sas;6e dbc2f4-1507-44f8-ac0d-eed1d2608d38.ssd</code></p> <p>NOTE This field cannot be configured for non-dedicated CCE clusters.</p>

Parameter	Type	Description
enterpriseProjectId	String	<p>ID of the enterprise project that a cluster belongs to.</p> <p>NOTE</p> <ul style="list-style-type: none">An enterprise project can be configured only after the enterprise project function is enabled.The enterprise project to which the cluster belongs must be the same as that to which other cloud service resources associated with the cluster belong.
kubeProxyMode	String	<p>Service forwarding mode. Two modes are available:</p> <ul style="list-style-type: none">iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE This parameter has been deprecated. If this parameter and kubeProxyMode in ClusterSpec are specified at the same time, the latter is used.</p>
clusterExternalIP	String	EIP of the master node
alpha.cce/fixPoolMask	String	<p>Number of mask bits of the fixed IP address pool of the container network model. This field is supported only for the VPC network model (vpc-router).</p> <p>This parameter determines the number of container IP addresses that can be allocated to a node. The maximum number of pods that can be created on a node is decided by this parameter and maxPods set during node creation. For details, see Maximum Number of Pods That Can Be Created on a Node.</p> <p>For integer characters, the value ranges from 24 to 28.</p>
decMasterFlavor	String	Specifications of the master node in the dedicated hybrid cluster.

Parameter	Type	Description
dockerUmaskMode	String	Default UmaskMode configuration of Docker in a cluster. The value can be secure or normal . If this parameter is not specified, normal is used by default.
kubernetes.io/cpuManagerPolicy	String	<p>Cluster CPU management policy. The value can be none (or null) or static. The default value is none (or null).</p> <ul style="list-style-type: none">• none or null: disables pods from exclusively occupying CPUs. Select this option if you want a large pool of shareable CPU cores.• static: enables pods to exclusively occupy CPUs. Select this option if your workload is sensitive to CPU cache and scheduling latency.
upgradefrom	String	Records of how the cluster is upgraded to the current version

Table 4-79 PackageConfiguration

Parameter	Type	Description
name	String	Component name.
configurations	Array of ConfigurationItem objects	Component configuration item.

Table 4-80 ConfigurationItem

Parameter	Type	Description
name	String	Component configuration item name.
value	Object	Component configuration item value.

Table 4-81 ClusterStatus

Parameter	Type	Description
phase	String	<p>Cluster status. Options:</p> <ul style="list-style-type: none">• Available: The cluster is running properly.• Unavailable: The cluster is exhibiting unexpected behavior. Manually delete it.• ScalingUp: Nodes are being added to the cluster.• ScalingDown: The cluster is being downsized to fewer nodes.• Creating: The cluster is being created.• Deleting: The cluster is being deleted.• Upgrading: The cluster is being upgraded.• Resizing: Cluster specifications are being changed.• RollingBack: The cluster is being rolled back.• RollbackFailed: The cluster rollback is abnormal.• Hibernating: The cluster is being hibernated.• Hibernation: The cluster is in hibernation.• Awaking: The cluster is being woken up from hibernation.• Empty: The cluster does not have any resources. This field is discarded.• Error: Resources in the cluster are abnormal. Manually delete the cluster.
jobID	String	<p>ID of the task associated with the cluster in the current state. Options:</p> <ul style="list-style-type: none">• ID of the associated task returned when creating a cluster. You can use it to obtain the auxiliary tasks for creating a cluster.• ID of the associated task returned when a cluster fails to be deleted or is deleted. If this parameter is not empty, you can use the task ID to obtain the auxiliary tasks for deleting a cluster. <p>NOTE Tasks are short-lived. Do not use task information in scenarios such as cluster status determination.</p>
reason	String	Reason of cluster state change. This parameter is returned if the cluster is not in the Available state.

Parameter	Type	Description
message	String	Detailed information about why the cluster changes to the current state. This parameter is returned if the cluster is not in the Available state.
endpoints	Array of ClusterEndpoints objects	Access address of kube-apiserver in the cluster.
deleteOption	Object	Whether to delete configurations. This parameter is contained only in the response to the deletion request.
deleteStatus	Object	Whether to delete the status information. This parameter is contained only in the response to the deletion request.

Table 4-82 ClusterEndpoints

Parameter	Type	Description
url	String	Access address of kube-apiserver in the cluster.
type	String	Type of the cluster access address. <ul style="list-style-type: none">• Internal: address for internal network access• External: address for external network access

Example Requests

None

Example Responses

Status code: 200

The cluster list is successfully obtained.

```
{  
  "kind" : "Cluster",  
  "apiVersion" : "v3",  
  "items" : [ {  
    "kind" : "Cluster",  
    "apiVersion" : "v3",  
    "metadata" : {  
      "alias" : "mycluster",  
      "name" : "mycluster",  
      "uid" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",  
      "creationTimestamp" : "2018-08-02 03:48:58.968214406 +0000 UTC",  
      "updateTimestamp" : "2018-08-02 04:05:29.386391813 +0000 UTC"  
    },  
  },  
]
```

```
"spec" : {
    "type" : "VirtualMachine",
    "flavor" : "cce.s1.small",
    "version" : "v1.7.3-r13",
    "description" : "awesome cluster",
    "customSan" : [ "192.168.1.0", "example.com" ],
    "hostNetwork" : {
        "vpc" : "f0c12911-4fdb-4284-9230-7ffb0860826a",
        "subnet" : "ac274229-fd2e-4695-9f01-a0c1372b8006"
    },
    "containerNetwork" : {
        "mode" : "overlay_l2",
        "cidr" : "172.16.0.0/16"
    },
    "authentication" : {
        "mode" : "x509",
        "authenticatingProxy" : { }
    },
    "billingMode" : 0
},
"status" : {
    "phase" : "Available",
    "endpoints" : [ {
        "url" : "https://192.168.0.11:5443",
        "type" : "Internal"
    } ]
}
}
```

Status Codes

Status Code	Description
200	The cluster list is successfully obtained.

Error Codes

See [Error Codes](#).

4.2.4 Updating a Specified Cluster

Function

This API is used to update information about a specified cluster.



The URL for cluster management is in the format of https://Endpoint/uri. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

PUT /api/v3/projects/{project_id}/clusters/{cluster_id}

Table 4-83 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-84 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-85 Request body parameters

Parameter	Mandatory	Type	Description
spec	Yes	ClusterInformationSpec object	Detailed cluster parameters
metadata	No	ClusterMetadataForUpdate object	Basic cluster information, including name-related fields

Table 4-86 ClusterInformationSpec

Parameter	Mandatory	Type	Description
description	No	String	<p>Cluster description.</p> <p>1. A maximum of 200 characters are allowed. The value cannot contain the following special characters: ~\$%^&*<>[]{} ()'"#\`</p> <p>2. Only clusters in the Available, ScalingUp, and ScalingDown states can be modified.</p>
customSan	No	Array of strings	<p>Custom SAN field in the server certificate of the cluster API server, which must comply with the SSL and X509 format specifications.</p> <p>1. Duplicate names are not allowed.</p> <p>2. Must comply with the IP address and domain name formats.</p> <p>Example: SAN 1: DNS Name=example.com SAN 2: DNS Name=www.example.com SAN 3: DNS Name=example.net SAN 4: IP Address=93.184.216.34</p>
containerNetwork	No	ContainerNet workUpdate object	Container networking parameters, including information about the container CIDR block.
eniNetwork	No	EniNetworkU pdate object	Cloud Native Network 2.0 network configuration, including the container subnet information of the CCE Turbo cluster.
hostNetwork	No	hostNetwork object	Node network parameters, including the default security group settings.

Table 4-87 ContainerNetworkUpdate

Parameter	Mandatory	Type	Description
cidrs	No	Array of ContainerCIDR objects	List of container CIDR blocks. For a clusters of v1.21 or later, if it uses a VPC network, a maximum of 20 container CIDR blocks can be added incrementally. The configuration cannot be modified after the cluster is updated.

Table 4-88 ContainerCIDR

Parameter	Mandatory	Type	Description
cidr	Yes	String	Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, and 192.168.0.0/16-19

Table 4-89 EniNetworkUpdate

Parameter	Mandatory	Type	Description
subnets	No	Array of NetworkSubnet objects	List of IPv4 subnet IDs. CCE Turbo clusters of version 1.19.10 and later support multiple container subnets. In addition, the container subnet list can be incrementally updated. Subnets can be added, not deleted. Exercise caution when selecting a subnet. The request body must contain all existing subnets.

Table 4-90 NetworkSubnet

Parameter	Mandatory	Type	Description
subnetID	Yes	String	<p>IPv4 subnet ID of the subnet for creating master nodes. Currently, IPv6 is not supported. You can obtain it in either of the following ways:</p> <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.

Table 4-91 hostNetwork

Parameter	Mandatory	Type	Description
SecurityGroup	No	String	The default security group of the worker node in the cluster needs to allow traffic through some ports to ensure normal communication. The modified security group applies only to nodes newly created or accepted. For existing nodes, you need to manually modify the security group rules for them.

Table 4-92 ClusterMetadataForUpdate

Parameter	Mandatory	Type	Description
alias	No	String	<p>Alias of a cluster name. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.</p> <p>A cluster alias must be unique. If this parameter is left blank, the alias is not changed.</p>

Response Parameters

Status code: 200

Table 4-93 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Cluster or cluster and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	ClusterMetadata object	Basic information about a cluster. Metadata is a collection of attributes.
spec	ClusterSpec object	Detailed description of the cluster. CCE creates or updates objects by defining or updating spec .
status	ClusterStatus object	Cluster status and job ID of the cluster creation job.

Table 4-94 ClusterMetadata

Parameter	Type	Description
name	String	Cluster name. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.
uid	String	Cluster ID, which uniquely identifies a cluster. This ID is automatically generated after a cluster is created. Only the automatically generated ID will take effect.
alias	String	Alias of a cluster name displayed on the CCE console, and the name can be changed. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. A cluster alias must be unique. In the request body for creating or updating a cluster, if the cluster alias is not specified or set to null, the cluster name will be used as the cluster alias. In the response body for obtaining a cluster, the cluster alias is returned. If it is not configured, the cluster name will be returned.

Parameter	Type	Description
annotations	Map<String, String>	<p>Cluster annotations, in the format of key-value pairs.</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations: Does not label or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This field is not stored in the database and is used only to specify the add-ons to be installed in the cluster.• Install ICAgent during cluster creation by adding the key-value pair "cluster.install.addons.external/install":"[{"addonTemplateName":"icagent"}]".
labels	Map<String, String>	<p>Cluster labels, in the format of key-value pairs.</p> <p>NOTE</p> <p>The value of this field is automatically generated by the system and is used by the frontend to identify the features supported by the cluster during the upgrade. Customized values are invalid.</p>
creationTimestamp	String	Time when the cluster was created.
updateTimestamp	String	Time when the cluster was updated.

Table 4-95 ClusterSpec

Parameter	Type	Description
category	String	<p>Cluster type. Options:</p> <ul style="list-style-type: none">• CCE: CCE cluster CCE cluster supports hybrid deployment of VMs and BMSs, and heterogeneous nodes such as GPU and NPU nodes, allowing you to run your containers in a secure and stable container runtime environment based on a high-performance network model.
type	String	<p>Master node architecture:</p> <ul style="list-style-type: none">• VirtualMachine: x86

Parameter	Type	Description
flavor	String	<p>Cluster specifications. Specifications of clusters of 1.15 or later versions can be changed after they are created. For details, see Modifying Cluster Specifications. Options:</p> <ul style="list-style-type: none">• cce.s1.small: a small-scale CCE cluster with one master node and a maximum of 50 worker nodes• cce.s1.medium: a medium-scale CCE cluster with one master node and a maximum of 200 worker nodes• cce.s2.small: a small-scale CCE cluster with three master nodes and a maximum of 50 worker nodes• cce.s2.medium: a medium-scale CCE cluster with three master nodes and a maximum of 200 worker nodes• cce.s2.large: a large-scale CCE cluster with three master nodes and a maximum of 1,000 worker nodes• cce.s2.xlarge: an ultra-large-scale CCE cluster with three master nodes and a maximum of 2,000 worker nodes <p>NOTE The fields in the parameters are described as follows:</p> <ul style="list-style-type: none">• s1: specifies a cluster with one master node. If the master node is faulty, the cluster will become unavailable, but running workloads in the cluster are not affected.• s2: specifies an HA cluster with three master nodes. If one of the master nodes is faulty, the cluster is still available.• small: specifies that a cluster can manage a maximum of 50 worker nodes.• medium: specifies that a cluster can manage a maximum of 200 worker nodes.• large: specifies that a cluster can manage a maximum of 1,000 worker nodes.• xlarge: specifies that a cluster can manage a maximum of 2,000 worker nodes.

Parameter	Type	Description
version	String	<p>Cluster version, which mirrors the baseline version of the Kubernetes community. The latest version is recommended.</p> <p>You can create clusters of two latest versions on the CCE console. To learn which cluster versions are available, log in to the CCE console, create a cluster, and check the Cluster Version parameter. You can call APIs to create clusters of other versions. However, these cluster versions will be gradually terminated. For details about the support policy, see the CCE announcement.</p> <p>NOTE</p> <ul style="list-style-type: none">• If not specified, a cluster of the latest version will be created.• If a baseline cluster version is specified but the R version is not specified, a cluster of the latest R version will be created by default. It is a good practice not to specify the R version.
platformVersion	String	<p>CCE cluster platform version, indicating the internal version under the cluster version (version). Platform versions are used to trace iterations in a major cluster version. They are unique within a major cluster version and recounted when the major cluster version changes. This parameter cannot be customized. When you create a cluster, the latest corresponding platform version is automatically selected.</p> <p>The format of platformVersion is cce.X.Y.</p> <ul style="list-style-type: none">• X: internal feature version, indicating changes in features, patches, or OS support in the cluster version. The value starts from 1 and increases monotonically.• Y: patch version of an internal feature version. It is used only for software package update after the feature version is brought online. No other modification is involved. The value starts from 0 and increases monotonically.
description	String	<p>Cluster description, for example, which purpose the cluster is intended to serve. By default, this field is left unspecified. To modify cluster description after the cluster is created, call the API for updating cluster information or go to the cluster details page on the CCE console. Only UTF-8 encoding is supported.</p>

Parameter	Type	Description
customSan	Array of strings	<p>Custom SAN field in the server certificate of the cluster API server, which must comply with the SSL and X509 format specifications.</p> <ol style="list-style-type: none">1. Duplicate names are not allowed.2. Must comply with the IP address and domain name formats. <p>Example:</p> <p>SAN 1: DNS Name=example.com SAN 2: DNS Name=www.example.com SAN 3: DNS Name=example.net SAN 4: IP Address=93.184.216.34</p>
ipv6enable	Boolean	Whether the cluster supports IPv6 addresses. This field is supported in clusters of v1.15 and later versions.
hostNetwork	HostNetwork object	Node networking parameters, including VPC and subnet ID. This field is mandatory because nodes in a cluster communicate with each other by using a VPC.
containerNetwork	ContainerNetwork object	Container networking parameters, including the container network model and container CIDR block.
serviceNetwork	ServiceNetwork object	Service CIDR block, including IPv4 CIDR blocks.
authentication	Authentication object	Configurations of the cluster authentication mode.
billingMode	Integer	Billing mode of a cluster. <ul style="list-style-type: none">• 0: pay-per-use Defaults to pay-per-use.
masters	Array of MasterSpec objects	Advanced configurations of master nodes
kubernetesSvcIpRange	String	Service CIDR blocks for Kubernetes clusterIPs. This field is available only for clusters of v1.11.7 and later. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used. This parameter is deprecated. Use serviceNetwork instead. The new field contains the IPv4 CIDR blocks.
clusterTags	Array of ResourceTag objects	Cluster resource tags.

Parameter	Type	Description
kubeProxyMode	String	<p>Service forwarding mode. Options:</p> <ul style="list-style-type: none">• iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.• ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE iptables is used by default.</p>
az	String	AZ. This field is returned only for a query.
extendParam	ClusterExtendedParam object	Extended field to decide whether the cluster will span across AZs or belong to a specified enterprise project, or whether a dedicated CCE cluster is to be created.
supportIstio	Boolean	Whether Istio is supported.
configurationsOverride	Array of PackageConfiguration objects	Whether to overwrite the default component configurations of the cluster. If a component or a parameter that is not supported by the component is specified, this configuration is ignored.

Table 4-96 HostNetwork

Parameter	Type	Description
vpc	String	<p>ID of the VPC used to create a master node. Obtain the public address by performing the following steps:</p> <ul style="list-style-type: none">• Method 1: Log in to the VPC console, and click the name of a VPC to view the VPC ID on the displayed details page.• Method 2: Use the VPC API to query the VPC ID.

Parameter	Type	Description
subnet	String	<p>Network ID of the subnet used to create a master node. Methods:</p> <ul style="list-style-type: none">Method 1: Log in to VPC console and click the target subnet on the Subnets tab page. You can view the network ID on the displayed page.Method 2: Use the VPC API for querying subnets. . .
SecurityGroup	String	Default worker node security group ID of the cluster. If specified, the cluster will be bound to the target security group. Otherwise, the system will automatically create a default worker node security group for you. The default worker node security group needs to allow access from certain ports to ensure normal communications.

Table 4-97 ContainerNetwork

Parameter	Type	Description
mode	String	<p>Container network model. Select one of the following possible values:</p> <ul style="list-style-type: none">overlay_l2: an overlay_l2 network (container tunnel network) built for containers by using OpenVSwitch (OVS).vpc-router: an underlay_l2 network built for containers by using IPvlan and custom VPC routes.
cidr	String	<p>Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, or 192.168.0.0/16-19. If the selected CIDR block conflicts with existing ones, an error will be reported.</p> <p>Not editable after the cluster is created. (deprecated. A specified cids will make cidr invalid.)</p>

Parameter	Type	Description
cids	Array of ContainerCIDR objects	List of container CIDR blocks. In clusters of v1.21 or later, the cids field is used. When the cluster network type is vpc-router , you can configure a maximum of 20 container CIDR blocks. In cluster versions earlier than v1.21, if the cids field is used, the first CIDR element in the array is used as the container CIDR block. The configuration cannot be modified after the cluster is created.

Table 4-98 ContainerCIDR

Parameter	Type	Description
cidr	String	Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, and 192.168.0.0/16-19

Table 4-99 EniNetwork

Parameter	Type	Description
eniSubnetId	String	IPv4 subnet ID of ENI subnet. (IPv6 is not supported and is being discarded.) You can obtain it in either of the following ways: <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.
eniSubnetCIDR	String	ENI subnet CIDR (being discarded)
subnets	Array of NetworkSubnet objects	List of IPv4 subnet IDs

Table 4-100 NetworkSubnet

Parameter	Type	Description
subnetID	String	<p>IPv4 subnet ID of the subnet for creating master nodes. Currently, IPv6 is not supported. You can obtain it in either of the following ways:</p> <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.

Table 4-101 ServiceNetwork

Parameter	Type	Description
IPv4CIDR	String	Value range of the Kubernetes clusterIP IPv4 CIDR blocks. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used.

Table 4-102 Authentication

Parameter	Type	Description
mode	String	<p>Cluster authentication mode.</p> <ul style="list-style-type: none">Clusters of Kubernetes v1.11 or earlier support x509, rbac, and authenticating_proxy. Defaults to x509.Clusters of Kubernetes v1.13 or later support rbac and authenticating_proxy. Defaults to rbac.
authenticatin gProxy	Authenticati ngProxy object	Configuration related to the authenticating_proxy mode. This field is mandatory when the authentication mode is authenticating_proxy .

Table 4-103 AuthenticatingProxy

Parameter	Type	Description
ca	String	X509 CA certificate (Base64-encoded) configured in authenticating_proxy mode. This field is mandatory when the cluster authentication mode is authenticating_proxy . Maximum size: 1 MB
cert	String	Client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .
privateKey	String	Private key of the client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. The private key used by the Kubernetes cluster does not support password encryption. Use an unencrypted private key. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .

Table 4-104 MasterSpec

Parameter	Type	Description
availabilityZone	String	AZ

Table 4-105 ResourceTag

Parameter	Type	Description
key	String	Key. <ul style="list-style-type: none">● Cannot be null. Max characters: 128.● Use letters, digits, and spaces in UTF-8 format.● Can contain the following special characters: _.:;/=-@.● Cannot start with _sys_.

Parameter	Type	Description
value	String	<p>Value.</p> <ul style="list-style-type: none"> Can be null but not the default. Max characters: 255. Use letters, digits, and spaces in UTF-8 format. Can contain the following special characters: _:/=-@.

Table 4-106 ClusterExtendParam

Parameter	Type	Description
clusterAZ	String	<p>AZ of master nodes in a cluster.</p> <ul style="list-style-type: none"> multi_az: (Optional) The cluster will span across AZs. Multiple AZs can be configured only for a cluster with multiple master nodes is used. <i>AZ of the dedicated cloud computing pool.</i> The cluster will be deployed in the AZ of Dedicated Cloud (DeC). It is mandatory for dedicated CCE clusters.

dssMasterVolumes	String	<p>Whether the system and data disks of a master node use dedicated distributed storage. If this parameter is omitted or left unspecified, EVS disks are used by default.</p> <p>This parameter is mandatory for dedicated CCE clusters. It is in the following format: <code><rootVol.dssPoolID>.<rootVol.volType>;<dataVol.dssPoolID>.<dataVol.volType></code></p> <p>Field description:</p> <ul style="list-style-type: none"> rootVol is the system disk. dataVol is the data disk. dssPoolID indicates the ID of the DSS storage pool. volType indicates the storage volume type of the DSS storage pool, such as SAS and SSD. <p>Example: <code>c950ee97-587c-4f24-8a74-3367e3da570f.sas;6e dbc2f4-1507-44f8-ac0d-eed1d2608d38.ssd</code></p> <p>NOTE This field cannot be configured for non-dedicated CCE clusters.</p>
------------------	--------	---

Parameter	Type	Description
enterpriseProjectId	String	<p>ID of the enterprise project that a cluster belongs to.</p> <p>NOTE</p> <ul style="list-style-type: none">An enterprise project can be configured only after the enterprise project function is enabled.The enterprise project to which the cluster belongs must be the same as that to which other cloud service resources associated with the cluster belong.
kubeProxyMode	String	<p>Service forwarding mode. Two modes are available:</p> <ul style="list-style-type: none">iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE This parameter has been deprecated. If this parameter and kubeProxyMode in ClusterSpec are specified at the same time, the latter is used.</p>
clusterExternalIP	String	EIP of the master node
alpha.cce/fixPoolMask	String	<p>Number of mask bits of the fixed IP address pool of the container network model. This field is supported only for the VPC network model (vpc-router).</p> <p>This parameter determines the number of container IP addresses that can be allocated to a node. The maximum number of pods that can be created on a node is decided by this parameter and maxPods set during node creation. For details, see Maximum Number of Pods That Can Be Created on a Node.</p> <p>For integer characters, the value ranges from 24 to 28.</p>
decMasterFlavor	String	Specifications of the master node in the dedicated hybrid cluster.

Parameter	Type	Description
dockerUmaskMode	String	Default UmaskMode configuration of Docker in a cluster. The value can be secure or normal . If this parameter is not specified, normal is used by default.
kubernetes.io/cpuManagerPolicy	String	<p>Cluster CPU management policy. The value can be none (or null) or static. The default value is none (or null).</p> <ul style="list-style-type: none">• none or null: disables pods from exclusively occupying CPUs. Select this option if you want a large pool of shareable CPU cores.• static: enables pods to exclusively occupy CPUs. Select this option if your workload is sensitive to CPU cache and scheduling latency.
upgradefrom	String	Records of how the cluster is upgraded to the current version

Table 4-107 PackageConfiguration

Parameter	Type	Description
name	String	Component name.
configurations	Array of ConfigurationItem objects	Component configuration item.

Table 4-108 ConfigurationItem

Parameter	Type	Description
name	String	Component configuration item name.
value	Object	Component configuration item value.

Table 4-109 ClusterStatus

Parameter	Type	Description
phase	String	<p>Cluster status. Options:</p> <ul style="list-style-type: none">• Available: The cluster is running properly.• Unavailable: The cluster is exhibiting unexpected behavior. Manually delete it.• ScalingUp: Nodes are being added to the cluster.• ScalingDown: The cluster is being downsized to fewer nodes.• Creating: The cluster is being created.• Deleting: The cluster is being deleted.• Upgrading: The cluster is being upgraded.• Resizing: Cluster specifications are being changed.• RollingBack: The cluster is being rolled back.• RollbackFailed: The cluster rollback is abnormal.• Hibernating: The cluster is being hibernated.• Hibernation: The cluster is in hibernation.• Awaking: The cluster is being woken up from hibernation.• Empty: The cluster does not have any resources. This field is discarded.• Error: Resources in the cluster are abnormal. Manually delete the cluster.
jobID	String	<p>ID of the task associated with the cluster in the current state. Options:</p> <ul style="list-style-type: none">• ID of the associated task returned when creating a cluster. You can use it to obtain the auxiliary tasks for creating a cluster.• ID of the associated task returned when a cluster fails to be deleted or is deleted. If this parameter is not empty, you can use the task ID to obtain the auxiliary tasks for deleting a cluster. <p>NOTE Tasks are short-lived. Do not use task information in scenarios such as cluster status determination.</p>
reason	String	Reason of cluster state change. This parameter is returned if the cluster is not in the Available state.

Parameter	Type	Description
message	String	Detailed information about why the cluster changes to the current state. This parameter is returned if the cluster is not in the Available state.
endpoints	Array of ClusterEndpoints objects	Access address of kube-apiserver in the cluster.
deleteOption	Object	Whether to delete configurations. This parameter is contained only in the response to the deletion request.
deleteStatus	Object	Whether to delete the status information. This parameter is contained only in the response to the deletion request.

Table 4-110 ClusterEndpoints

Parameter	Type	Description
url	String	Access address of kube-apiserver in the cluster.
type	String	Type of the cluster access address. <ul style="list-style-type: none">• Internal: address for internal network access• External: address for external network access

Example Requests

- Updating only the description of a cluster

```
{  
  "spec": {  
    "description": "new description"  
  }  
}
```
- Updating only the custom SAN of the cluster certificate

```
{  
  "spec": {  
    "customSan": [ "192.168.1.0", "example.com" ]  
  }  
}
```
- Updating both the cluster description and custom certificate SAN

```
{  
  "spec": {  
    "description": "new description",  
    "customSan": [ "192.168.1.0", "example.com" ]  
  }  
}
```
- Configure a CIDR block for a cluster that uses VPCs and is of a version later than v1.21.

```
{  
  "spec" : {  
    "containerNetwork" : {  
      "cidrs" : [ {  
        "cidr" : "10.10.0.0/16"  
      }, {  
        "cidr" : "10.11.0.0/16"  
      } ]  
    }  
  }  
}
```

- Modify the default security group of a node in a cluster.

/api/v3/projects/{project_id}/clusters/{cluster_id}

```
{  
  "spec" : {  
    "hostNetwork" : {  
      "SecurityGroup" : "6ee29825-8f49-4796-b33a-fc76f84a59ae"  
    }  
  }  
}
```

Example Responses

Status code: 200

Information about the specified cluster is successfully updated.

```
{  
  "kind" : "Cluster",  
  "apiVersion" : "v3",  
  "metadata" : {  
    "alias" : "mycluster",  
    "name" : "mycluster",  
    "uid" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",  
    "creationTimestamp" : "2018-08-02 03:48:58.968214406 +0000 UTC",  
    "updateTimestamp" : "2018-08-02 06:39:36.844676088 +0000 UTC"  
  },  
  "spec" : {  
    "type" : "VirtualMachine",  
    "flavor" : "cce.s1.small",  
    "version" : "v1.7.3-r13",  
    "description" : "new description",  
    "customSan" : [ "192.168.1.0", "example.com" ],  
    "hostNetwork" : {  
      "vpc" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",  
      "subnet" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",  
      "SecurityGroup" : "6ee29825-8f49-4796-b33a-fc76f84a59ae"  
    },  
    "containerNetwork" : {  
      "mode" : "overlay_l2",  
      "cidr" : "172.17.0.0/16"  
    },  
    "authentication" : {  
      "mode" : "x509",  
      "authenticatingProxy" : { }  
    },  
    "billingMode" : 0  
  },  
  "status" : {  
    "phase" : "Available",  
    "endpoints" : [ {  
      "url" : "https://192.168.0.11:5443",  
      "type" : "Internal"  
    } ]  
  }  
}
```

Status Codes

Status Code	Description
200	Information about the specified cluster is successfully updated.

Error Codes

See [Error Codes](#).

4.2.5 Deleting a Cluster

Function

This API is used to delete a specified cluster.



The URL for cluster management is in the format of `https://Endpoint/uri`. In the URL, `uri` indicates the resource path, that is, the path for API access.

URI

`DELETE /api/v3/projects/{project_id}/clusters/{cluster_id}`

Table 4-111 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Table 4-112 Query Parameters

Parameter	Mandatory	Type	Description
delete_efs	No	String	Whether to delete SFS Turbo volumes. Value options: <ul style="list-style-type: none">• true or block (The system starts to delete the object. If the deletion fails, subsequent processes are blocked.)• try (The system starts to delete the object. If the deletion fails, no deletion retry is performed, and subsequent processes are not blocked.)• false or skip (The object is not deleted. These are the default value options.)
delete_evs	No	String	Whether to delete EVS disks. Value options: <ul style="list-style-type: none">• true or block (The system starts to delete the object. If the deletion fails, subsequent processes are blocked.)• try (The system starts to delete the object. If the deletion fails, no deletion retry is performed, and subsequent processes are not blocked.)• false or skip (The object is not deleted. These are the default value options.)

Parameter	Mandatory	Type	Description
delete_net	No	String	<p>Whether to delete cluster Service and ingress resources, such as ELB load balancers. Value options:</p> <ul style="list-style-type: none">• true or block (The system starts to delete the object. If the deletion fails, subsequent processes are blocked.)• try (The system starts to delete the object. If the deletion fails, no deletion retry is performed, and subsequent processes are not blocked.)• false or skip (Skip the deletion.)
delete_obs	No	String	<p>Whether to delete OBS volumes. Value options:</p> <ul style="list-style-type: none">• true or block (The system starts to delete the object. If the deletion fails, subsequent processes are blocked.)• try (The system starts to delete the object. If the deletion fails, no deletion retry is performed, and subsequent processes are not blocked.)• false or skip (The object is not deleted. These are the default value options.)

Parameter	Mandatory	Type	Description
delete_sfs	No	String	<p>Whether to delete SFS volumes. Value options:</p> <ul style="list-style-type: none">• true or block (The system starts to delete the object. If the deletion fails, subsequent processes are blocked.)• try (The system starts to delete the object. If the deletion fails, no deletion retry is performed, and subsequent processes are not blocked.)• false or skip (The object is not deleted. These are the default value options.)
delete_sfs30	No	String	<p>Whether to delete an SFS 3.0 volume. Example value:</p> <ul style="list-style-type: none">• true or block (The system starts to delete the object. If the deletion fails, subsequent processes are blocked.)• try (The system starts to delete the object. If the deletion fails, no deletion retry is performed, and subsequent processes are not blocked.)• false or skip (The object is not deleted. These are the default value options.)

Parameter	Mandatory	Type	Description
lts_reclaim_policy	No	String	<p>Whether to delete an LTS log stream. Options:</p> <ul style="list-style-type: none">• true or block (The system starts to delete the object. If the deletion fails, subsequent processes are blocked.)• try (The system starts to delete the object. If the deletion fails, no deletion retry is performed, and subsequent processes will proceed.)• false or skip (The deletion is skipped. This is the default option.)

Request Parameters

Table 4-113 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-114 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Cluster or cluster and cannot be changed.

Parameter	Type	Description
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	ClusterMetadata object	Basic information about a cluster. Metadata is a collection of attributes.
spec	ClusterSpec object	Detailed description of the cluster. CCE creates or updates objects by defining or updating spec .
status	ClusterStatus object	Cluster status and job ID of the cluster creation job.

Table 4-115 ClusterMetadata

Parameter	Type	Description
name	String	Cluster name. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.
uid	String	Cluster ID, which uniquely identifies a cluster. This ID is automatically generated after a cluster is created. Only the automatically generated ID will take effect.
alias	String	Alias of a cluster name displayed on the CCE console, and the name can be changed. Enter 4 to 128 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. A cluster alias must be unique. In the request body for creating or updating a cluster, if the cluster alias is not specified or set to null, the cluster name will be used as the cluster alias. In the response body for obtaining a cluster, the cluster alias is returned. If it is not configured, the cluster name will be returned.

Parameter	Type	Description
annotations	Map<String, String>	<p>Cluster annotations, in the format of key-value pairs.</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations: Does not label or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This field is not stored in the database and is used only to specify the add-ons to be installed in the cluster.• Install ICAgent during cluster creation by adding the key-value pair "cluster.install.addons.external/install":"[{"addonTemplateName":"icagent"}]".
labels	Map<String, String>	<p>Cluster labels, in the format of key-value pairs.</p> <p>NOTE</p> <p>The value of this field is automatically generated by the system and is used by the frontend to identify the features supported by the cluster during the upgrade. Customized values are invalid.</p>
creationTimestamp	String	Time when the cluster was created.
updateTimestamp	String	Time when the cluster was updated.

Table 4-116 ClusterSpec

Parameter	Type	Description
category	String	<p>Cluster type. Options:</p> <ul style="list-style-type: none">• CCE: CCE cluster CCE cluster supports hybrid deployment of VMs and BMSs, and heterogeneous nodes such as GPU and NPU nodes, allowing you to run your containers in a secure and stable container runtime environment based on a high-performance network model.
type	String	<p>Master node architecture:</p> <ul style="list-style-type: none">• VirtualMachine: x86

Parameter	Type	Description
flavor	String	<p>Cluster specifications. Specifications of clusters of 1.15 or later versions can be changed after they are created. For details, see Modifying Cluster Specifications. Options:</p> <ul style="list-style-type: none">• cce.s1.small: a small-scale CCE cluster with one master node and a maximum of 50 worker nodes• cce.s1.medium: a medium-scale CCE cluster with one master node and a maximum of 200 worker nodes• cce.s2.small: a small-scale CCE cluster with three master nodes and a maximum of 50 worker nodes• cce.s2.medium: a medium-scale CCE cluster with three master nodes and a maximum of 200 worker nodes• cce.s2.large: a large-scale CCE cluster with three master nodes and a maximum of 1,000 worker nodes• cce.s2.xlarge: an ultra-large-scale CCE cluster with three master nodes and a maximum of 2,000 worker nodes <p>NOTE The fields in the parameters are described as follows:</p> <ul style="list-style-type: none">• s1: specifies a cluster with one master node. If the master node is faulty, the cluster will become unavailable, but running workloads in the cluster are not affected.• s2: specifies an HA cluster with three master nodes. If one of the master nodes is faulty, the cluster is still available.• small: specifies that a cluster can manage a maximum of 50 worker nodes.• medium: specifies that a cluster can manage a maximum of 200 worker nodes.• large: specifies that a cluster can manage a maximum of 1,000 worker nodes.• xlarge: specifies that a cluster can manage a maximum of 2,000 worker nodes.

Parameter	Type	Description
version	String	<p>Cluster version, which mirrors the baseline version of the Kubernetes community. The latest version is recommended.</p> <p>You can create clusters of two latest versions on the CCE console. To learn which cluster versions are available, log in to the CCE console, create a cluster, and check the Cluster Version parameter. You can call APIs to create clusters of other versions. However, these cluster versions will be gradually terminated. For details about the support policy, see the CCE announcement.</p> <p>NOTE</p> <ul style="list-style-type: none">• If not specified, a cluster of the latest version will be created.• If a baseline cluster version is specified but the R version is not specified, a cluster of the latest R version will be created by default. It is a good practice not to specify the R version.
platformVersion	String	<p>CCE cluster platform version, indicating the internal version under the cluster version (version). Platform versions are used to trace iterations in a major cluster version. They are unique within a major cluster version and recounted when the major cluster version changes. This parameter cannot be customized. When you create a cluster, the latest corresponding platform version is automatically selected.</p> <p>The format of platformVersion is cce.X.Y.</p> <ul style="list-style-type: none">• X: internal feature version, indicating changes in features, patches, or OS support in the cluster version. The value starts from 1 and increases monotonically.• Y: patch version of an internal feature version. It is used only for software package update after the feature version is brought online. No other modification is involved. The value starts from 0 and increases monotonically.
description	String	<p>Cluster description, for example, which purpose the cluster is intended to serve. By default, this field is left unspecified. To modify cluster description after the cluster is created, call the API for updating cluster information or go to the cluster details page on the CCE console. Only UTF-8 encoding is supported.</p>

Parameter	Type	Description
customSan	Array of strings	<p>Custom SAN field in the server certificate of the cluster API server, which must comply with the SSL and X509 format specifications.</p> <ol style="list-style-type: none">1. Duplicate names are not allowed.2. Must comply with the IP address and domain name formats. <p>Example:</p> <p>SAN 1: DNS Name=example.com SAN 2: DNS Name=www.example.com SAN 3: DNS Name=example.net SAN 4: IP Address=93.184.216.34</p>
ipv6enable	Boolean	Whether the cluster supports IPv6 addresses. This field is supported in clusters of v1.15 and later versions.
hostNetwork	HostNetwork object	Node networking parameters, including VPC and subnet ID. This field is mandatory because nodes in a cluster communicate with each other by using a VPC.
containerNetwork	ContainerNetwork object	Container networking parameters, including the container network model and container CIDR block.
serviceNetwork	ServiceNetwork object	Service CIDR block, including IPv4 CIDR blocks.
authentication	Authentication object	Configurations of the cluster authentication mode.
billingMode	Integer	Billing mode of a cluster. <ul style="list-style-type: none">• 0: pay-per-use Defaults to pay-per-use.
masters	Array of MasterSpec objects	Advanced configurations of master nodes
kubernetesSvcIpRange	String	Service CIDR blocks for Kubernetes clusterIPs. This field is available only for clusters of v1.11.7 and later. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used. This parameter is deprecated. Use serviceNetwork instead. The new field contains the IPv4 CIDR blocks.
clusterTags	Array of ResourceTag objects	Cluster resource tags.

Parameter	Type	Description
kubeProxyMode	String	<p>Service forwarding mode. Options:</p> <ul style="list-style-type: none">• iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.• ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE iptables is used by default.</p>
az	String	AZ. This field is returned only for a query.
extendParam	ClusterExtendedParam object	Extended field to decide whether the cluster will span across AZs or belong to a specified enterprise project, or whether a dedicated CCE cluster is to be created.
supportIstio	Boolean	Whether Istio is supported.
configurationsOverride	Array of PackageConfiguration objects	Whether to overwrite the default component configurations of the cluster. If a component or a parameter that is not supported by the component is specified, this configuration is ignored.

Table 4-117 HostNetwork

Parameter	Type	Description
vpc	String	<p>ID of the VPC used to create a master node. Obtain the public address by performing the following steps:</p> <ul style="list-style-type: none">• Method 1: Log in to the VPC console, and click the name of a VPC to view the VPC ID on the displayed details page.• Method 2: Use the VPC API to query the VPC ID.

Parameter	Type	Description
subnet	String	<p>Network ID of the subnet used to create a master node. Methods:</p> <ul style="list-style-type: none">Method 1: Log in to VPC console and click the target subnet on the Subnets tab page. You can view the network ID on the displayed page.Method 2: Use the VPC API for querying subnets. . .
SecurityGroup	String	Default worker node security group ID of the cluster. If specified, the cluster will be bound to the target security group. Otherwise, the system will automatically create a default worker node security group for you. The default worker node security group needs to allow access from certain ports to ensure normal communications.

Table 4-118 ContainerNetwork

Parameter	Type	Description
mode	String	<p>Container network model. Select one of the following possible values:</p> <ul style="list-style-type: none">overlay_l2: an overlay_l2 network (container tunnel network) built for containers by using OpenVSwitch (OVS).vpc-router: an underlay_l2 network built for containers by using IPvlan and custom VPC routes.
cidr	String	<p>Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, or 192.168.0.0/16-19. If the selected CIDR block conflicts with existing ones, an error will be reported.</p> <p>Not editable after the cluster is created. (deprecated. A specified cids will make cidr invalid.)</p>

Parameter	Type	Description
cids	Array of ContainerCIDR objects	List of container CIDR blocks. In clusters of v1.21 or later, the cids field is used. When the cluster network type is vpc-router , you can configure a maximum of 20 container CIDR blocks. In cluster versions earlier than v1.21, if the cids field is used, the first CIDR element in the array is used as the container CIDR block. The configuration cannot be modified after the cluster is created.

Table 4-119 ContainerCIDR

Parameter	Type	Description
cidr	String	Container CIDR block. Recommended: 10.0.0.0/12-19, 172.16.0.0/16-19, and 192.168.0.0/16-19

Table 4-120 EniNetwork

Parameter	Type	Description
eniSubnetId	String	IPv4 subnet ID of ENI subnet. (IPv6 is not supported and is being discarded.) You can obtain it in either of the following ways: <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.
eniSubnetCIDR	String	ENI subnet CIDR (being discarded)
subnets	Array of NetworkSubnet objects	List of IPv4 subnet IDs

Table 4-121 NetworkSubnet

Parameter	Type	Description
subnetID	String	<p>IPv4 subnet ID of the subnet for creating master nodes. Currently, IPv6 is not supported. You can obtain it in either of the following ways:</p> <ul style="list-style-type: none">Method 1: Log in to the VPC console and click the target subnet on the Subnets page. You can view the IPv4 subnet ID on the displayed page.Method 2: Use the VPC API for querying subnets.

Table 4-122 ServiceNetwork

Parameter	Type	Description
IPv4CIDR	String	Value range of the Kubernetes clusterIP IPv4 CIDR blocks. If this parameter is not specified during cluster creation, the default value 10.247.0.0/16 will be used.

Table 4-123 Authentication

Parameter	Type	Description
mode	String	<p>Cluster authentication mode.</p> <ul style="list-style-type: none">Clusters of Kubernetes v1.11 or earlier support x509, rbac, and authenticating_proxy. Defaults to x509.Clusters of Kubernetes v1.13 or later support rbac and authenticating_proxy. Defaults to rbac.
authenticatin gProxy	Authenticati ngProxy object	Configuration related to the authenticating_proxy mode. This field is mandatory when the authentication mode is authenticating_proxy .

Table 4-124 AuthenticatingProxy

Parameter	Type	Description
ca	String	X509 CA certificate (Base64-encoded) configured in authenticating_proxy mode. This field is mandatory when the cluster authentication mode is authenticating_proxy . Maximum size: 1 MB
cert	String	Client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .
privateKey	String	Private key of the client certificate issued by the X509 CA certificate configured in authenticating_proxy mode, which is used for authentication from kube-apiserver to the extended API server. The private key used by the Kubernetes cluster does not support password encryption. Use an unencrypted private key. (The value must be Base64-encoded.) This field is mandatory when the cluster authentication mode is authenticating_proxy .

Table 4-125 MasterSpec

Parameter	Type	Description
availabilityZone	String	AZ

Table 4-126 ResourceTag

Parameter	Type	Description
key	String	Key. <ul style="list-style-type: none">● Cannot be null. Max characters: 128.● Use letters, digits, and spaces in UTF-8 format.● Can contain the following special characters: _.:;/=-@.● Cannot start with _sys_.

Parameter	Type	Description
value	String	<p>Value.</p> <ul style="list-style-type: none">Can be null but not the default. Max characters: 255.Use letters, digits, and spaces in UTF-8 format.Can contain the following special characters: _:/=-@.

Table 4-127 ClusterExtendParam

Parameter	Type	Description
clusterAZ	String	<p>AZ of master nodes in a cluster.</p> <ul style="list-style-type: none">multi_az: (Optional) The cluster will span across AZs. Multiple AZs can be configured only for a cluster with multiple master nodes is used.<i>AZ of the dedicated cloud computing pool.</i> The cluster will be deployed in the AZ of Dedicated Cloud (DeC). It is mandatory for dedicated CCE clusters.

dssMasterVolumes	String	<p>Whether the system and data disks of a master node use dedicated distributed storage. If this parameter is omitted or left unspecified, EVS disks are used by default.</p> <p>This parameter is mandatory for dedicated CCE clusters. It is in the following format: <rootVol.dssPoolID>.<rootVol.volType>;<dataVol.dssPoolID>.<dataVol.volType></p> <p>Field description:</p> <ul style="list-style-type: none">rootVol is the system disk. dataVol is the data disk.dssPoolID indicates the ID of the DSS storage pool.volType indicates the storage volume type of the DSS storage pool, such as SAS and SSD. <p>Example: c950ee97-587c-4f24-8a74-3367e3da570f.sas;6e dbc2f4-1507-44f8-ac0d-eed1d2608d38.ssd</p> <p>NOTE This field cannot be configured for non-dedicated CCE clusters.</p>
------------------	--------	---

Parameter	Type	Description
enterpriseProjectId	String	<p>ID of the enterprise project that a cluster belongs to.</p> <p>NOTE</p> <ul style="list-style-type: none">An enterprise project can be configured only after the enterprise project function is enabled.The enterprise project to which the cluster belongs must be the same as that to which other cloud service resources associated with the cluster belong.
kubeProxyMode	String	<p>Service forwarding mode. Two modes are available:</p> <ul style="list-style-type: none">iptables: Traditional kube-proxy uses iptables rules to implement Service load balancing. In this mode, too many iptables rules will be generated when many Services are deployed. In addition, non-incremental updates will cause latency and even tangible performance issues in the case of service traffic spikes.ipvs: Optimized kube-proxy mode with higher throughput and faster speed. This mode supports incremental updates and can keep connections uninterrupted during Service updates. It is suitable for large-sized clusters. <p>NOTE This parameter has been deprecated. If this parameter and kubeProxyMode in ClusterSpec are specified at the same time, the latter is used.</p>
clusterExternalIP	String	EIP of the master node
alpha.cce/fixPoolMask	String	<p>Number of mask bits of the fixed IP address pool of the container network model. This field is supported only for the VPC network model (vpc-router).</p> <p>This parameter determines the number of container IP addresses that can be allocated to a node. The maximum number of pods that can be created on a node is decided by this parameter and maxPods set during node creation. For details, see Maximum Number of Pods That Can Be Created on a Node.</p> <p>For integer characters, the value ranges from 24 to 28.</p>
decMasterFlavor	String	Specifications of the master node in the dedicated hybrid cluster.

Parameter	Type	Description
dockerUmaskMode	String	Default UmaskMode configuration of Docker in a cluster. The value can be secure or normal . If this parameter is not specified, normal is used by default.
kubernetes.io/cpuManagerPolicy	String	<p>Cluster CPU management policy. The value can be none (or null) or static. The default value is none (or null).</p> <ul style="list-style-type: none">• none or null: disables pods from exclusively occupying CPUs. Select this option if you want a large pool of shareable CPU cores.• static: enables pods to exclusively occupy CPUs. Select this option if your workload is sensitive to CPU cache and scheduling latency.
upgradefrom	String	Records of how the cluster is upgraded to the current version

Table 4-128 PackageConfiguration

Parameter	Type	Description
name	String	Component name.
configurations	Array of ConfigurationItem objects	Component configuration item.

Table 4-129 ConfigurationItem

Parameter	Type	Description
name	String	Component configuration item name.
value	Object	Component configuration item value.

Table 4-130 ClusterStatus

Parameter	Type	Description
phase	String	<p>Cluster status. Options:</p> <ul style="list-style-type: none">• Available: The cluster is running properly.• Unavailable: The cluster is exhibiting unexpected behavior. Manually delete it.• ScalingUp: Nodes are being added to the cluster.• ScalingDown: The cluster is being downsized to fewer nodes.• Creating: The cluster is being created.• Deleting: The cluster is being deleted.• Upgrading: The cluster is being upgraded.• Resizing: Cluster specifications are being changed.• RollingBack: The cluster is being rolled back.• RollbackFailed: The cluster rollback is abnormal.• Hibernating: The cluster is being hibernated.• Hibernation: The cluster is in hibernation.• Awaking: The cluster is being woken up from hibernation.• Empty: The cluster does not have any resources. This field is discarded.• Error: Resources in the cluster are abnormal. Manually delete the cluster.
jobID	String	<p>ID of the task associated with the cluster in the current state. Options:</p> <ul style="list-style-type: none">• ID of the associated task returned when creating a cluster. You can use it to obtain the auxiliary tasks for creating a cluster.• ID of the associated task returned when a cluster fails to be deleted or is deleted. If this parameter is not empty, you can use the task ID to obtain the auxiliary tasks for deleting a cluster. <p>NOTE Tasks are short-lived. Do not use task information in scenarios such as cluster status determination.</p>
reason	String	Reason of cluster state change. This parameter is returned if the cluster is not in the Available state.

Parameter	Type	Description
message	String	Detailed information about why the cluster changes to the current state. This parameter is returned if the cluster is not in the Available state.
endpoints	Array of ClusterEndpoints objects	Access address of kube-apiserver in the cluster.
deleteOption	Object	Whether to delete configurations. This parameter is contained only in the response to the deletion request.
deleteStatus	Object	Whether to delete the status information. This parameter is contained only in the response to the deletion request.

Table 4-131 ClusterEndpoints

Parameter	Type	Description
url	String	Access address of kube-apiserver in the cluster.
type	String	Type of the cluster access address. <ul style="list-style-type: none">• Internal: address for internal network access• External: address for external network access

Example Requests

None

Example Responses

Status code: 200

The job for deleting a cluster is successfully delivered.

```
{  
  "kind" : "Cluster",  
  "apiVersion" : "v3",  
  "metadata" : {  
    "alias" : "mycluster",  
    "name" : "mycluster",  
    "uid" : "fc563b3c-9552-11e8-8beb-0255ac106311",  
    "creationTimestamp" : "2018-08-01 06:20:28.81667161 +0000 UTC",  
    "updateTimestamp" : "2018-08-01 09:23:38.944333282 +0000 UTC"  
  },  
  "spec" : {  
    "type" : "VirtualMachine",  
    "flavor" : "cce.s1.small",  
  }  
}
```

```
"version" : "v1.7.3-r13",
"description" : "new description",
"hostNetwork" : {
    "vpc" : "cbed56e8-03e7-4304-a477-b54bef0857c3",
    "subnet" : "5de50062-2be2-4a52-893e-e0906e3e9c9d"
},
"containerNetwork" : {
    "mode" : "overlay_l2",
    "cidr" : "172.16.0.0/16"
},
"authentication" : {
    "mode" : "x509",
    "authenticatingProxy" : { }
},
"billingMode" : 0
},
"status" : {
    "phase" : "Available",
    "jobID" : "e8ebf96c-956d-11e8-a949-0255ac10575d",
    "endpoints" : [ {
        "url" : "https://192.168.0.16:5443",
        "type" : "Internal"
    } ]
}
```

Status Codes

Status Code	Description
200	The job for deleting a cluster is successfully delivered.

Error Codes

See [Error Codes](#).

4.2.6 Hibernating a Cluster

Function

This API is used to hibernate a running cluster. After a cluster is hibernated, master node resources stop being billed.

Constraints

- After a cluster is hibernated, resources such as workloads cannot be created or managed in the cluster.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/operation/hibernate

Table 4-132 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-133 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

None

Example Requests

None

Example Responses

None

Status Codes

Status Code	Description
200	The cluster hibernation job is successfully delivered. Keep querying the cluster status. When the cluster status changes to Hibernation , the cluster is hibernated.

Error Codes

See [Error Codes](#).

4.2.7 Waking Up a Cluster

Function

This API is used to wake up a hibernated cluster. After the cluster is woken up, master node resources continue to be billed.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/operation/awake

Table 4-134 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-135 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

None

Example Requests

None

Example Responses

None

Status Codes

Status Code	Description
200	The cluster wakeup job is successfully delivered. Keep querying the cluster status. When the cluster status changes to Available , the cluster is woken up successfully.

Error Codes

See [Error Codes](#).

4.2.8 Obtaining a Cluster Certificate

Function

This API is used to obtain a certificate of a specified cluster.

Constraints

This API is applicable to clusters of v1.13 and later.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/clustercert

Table 4-136 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-137 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-138 Request body parameters

Parameter	Mandatory	Type	Description
duration	Yes	Integer	Validity period of the cluster certificate. The minimum value is 1 day and the maximum value is 5 years. Therefore, the value ranges from 1 to 1827. (The unit is day. The actual limit depends on the number of leap years in the five years. For example, if there is a leap year in the five years, the upper limit is 1826 days.) If this parameter is set to -1, the maximum value is 5 years.

Response Parameters

Status code: 200

Table 4-139 Response header parameters

Parameter	Type	Description
Port-ID	String	Port ID of the cluster master node

Table 4-140 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Config and cannot be changed.
apiVersion	String	API version. The value is fixed at v1 .
preferences	Object	This field is not used currently and is left unspecified by default.
clusters	Array of Clusters objects	Cluster list
users	Array of Users objects	Certificate information and client key information of a specified user
contexts	Array of Contexts objects	Context list
current-context	String	Current context. If publicIp (VM EIP) exists, the value is external . If publicIp does not exist, the value is internal .

Table 4-141 Clusters

Parameter	Type	Description
name	String	Cluster name. <ul style="list-style-type: none">• If publicIp does not exist (that is, no VM EIP exists), there is only one cluster in the cluster list, and the value of this parameter is internalCluster.• If publicIp exists (that is, the EIP exists), there are at least two clusters in the cluster list, and the value of this parameter is externalCluster.

Parameter	Type	Description
cluster	ClusterCert object	Cluster information

Table 4-142 ClusterCert

Parameter	Type	Description
server	String	Server IP address
certificate-authority-data	String	Certificate authorization data
insecure-skip-tls-verify	Boolean	Whether to skip the server certificate verification. If the cluster type is <code>externalCluster</code> , the value is <code>true</code> .

Table 4-143 Users

Parameter	Type	Description
name	String	The value is fixed at <code>user</code> .
user	User object	Certificate information and client key information of a specified user

Table 4-144 User

Parameter	Type	Description
client-certificate-data	String	Client certificate
client-key-data	String	PEM encoding data from the TLS client key file

Table 4-145 Contexts

Parameter	Type	Description
name	String	Context name. <ul style="list-style-type: none">• If publicIp does not exist (that is, no VM EIP exists), there is only one cluster in the cluster list, and the value of this parameter is internal.• If publicIp exists (that is, the EIP exists), there are at least two clusters in the cluster list, and the value of this field for all extension contexts is external.
context	Context object	Context information

Table 4-146 Context

Parameter	Type	Description
cluster	String	Cluster context
user	String	User context

Example Requests

Applying for a cluster access certificate valid for 30 days

```
{  
    "duration" : 30  
}
```

Example Responses

Status code: 200

The certificate of the specified cluster is successfully obtained. For details about the certificate file format, see the Kubernetes v1.Config structure.

```
{  
    "kind" : "Config",  
    "apiVersion" : "v1",  
    "preferences" : { },  
    "clusters" : [ {  
        "name" : "internalCluster",  
        "cluster" : {  
            "server" : "https://192.168.1.7:5443",  
            "certificate-authority-data" : "Q2VydGlmaWNhdGU6*****FTkQgQ0VSVElGSUNBVEUtLS0tLQo="  
        }  
    } ],  
    "users" : [ {  
        "name" : "user",  
        "user" : {  
            "client-certificate-data" : "LS0tLS1CRUdJTiBDR*****QVRFLS0tLS0K",  
            "client-key-data" : "LS0tLS1CRUdJTi*****BLRVktLS0tLQo="  
        }  
    } ]  
}
```

```
        }
    },
    "contexts" : [ {
        "name" : "internal",
        "context" : {
            "cluster" : "internalCluster",
            "user" : "user"
        }
    }],
    "current-context" : "internal"
}
```

Status Codes

Status Code	Description
200	The certificate of the specified cluster is successfully obtained. For details about the certificate file format, see the Kubernetes v1.Config structure.

Error Codes

See [Error Codes](#).

4.2.9 Modifying Cluster Specifications

Function

This API is used to modify the specifications of a specified cluster.



NOTE

- The URL for cluster management is in the format of `https://Endpoint/uri`, where `uri` indicates the resource path for API access.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/operation/resize

Table 4-147 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-148 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-149 Request body parameters

Parameter	Mandatory	Type	Description
flavorResize	Yes	String	<p>The target flavor to be changed. You can only adjust the maximum number of worker nodes in a cluster. The number of master nodes is fixed and cannot be altered, and the cluster flavors cannot be downgraded. Suppose the original cluster flavor is cce.s2.medium. In that case, you can only upgrade it to cce.s2.large or higher, but you cannot downgrade it to cce.s2.small or cce.s1.medium.</p> <ul style="list-style-type: none">• cce.s1.small: a small-scale CCE cluster with one master node and a maximum of 50 worker nodes• cce.s1.medium: a medium-scale CCE cluster with one master node and a maximum of 200 worker nodes• cce.s2.small: a small-scale CCE cluster with three master nodes and a maximum of 50 worker nodes• cce.s2.medium: a medium-scale CCE cluster with three master nodes and a maximum of 200 worker nodes• cce.s2.large: a large-scale CCE cluster with three master nodes and a maximum of 1,000 worker nodes• cce.s2.xlarge: an ultra-large-scale CCE cluster with three master nodes and a maximum of 2,000 worker nodes

Parameter	Mandatory	Type	Description
			<p>NOTE The fields in the parameters are described as follows:</p> <ul style="list-style-type: none">• s1: specifies a cluster with one master node. If the master node is faulty, the cluster will become unavailable, but running workloads in the cluster are not affected.• s2: specifies an HA cluster with three master nodes. If one of the master nodes is faulty, the cluster is still available.• small: specifies that a cluster can manage a maximum of 50 worker nodes.• medium: specifies that a cluster can manage a maximum of 200 worker nodes.• large: specifies that a cluster can manage a maximum of 1,000 worker nodes.• xlarge: specifies that a cluster can manage a maximum of 2,000 worker nodes.
extendParam	No	extendParam object	-

Table 4-150 extendParam

Parameter	Mandatory	Type	Description
decMasterFlavor	No	String	Specifications of the master node in the dedicated hybrid cluster

Response Parameters

Status code: 201

Table 4-151 Response body parameters

Parameter	Type	Description
jobID	String	ID of the job

Example Requests

- Modifying the specifications of the pay-per-use cluster

```
POST /api/v3/projects/{project_id}/clusters/{cluster_id}/operation/resize

{
  "flavorResize" : "cce.s1.medium"
}
```

Example Responses

Status code: 201

The job for modifying the specifications of the pay-per-use cluster is delivered.

```
{
  "jobID" : "13b8d958-8fcf-11ed-aef3-0255ac1001bd"
}
```

Status Codes

Status Code	Description
201	The job for modifying the specifications of the pay-per-use cluster is delivered.

Error Codes

See [Error Codes](#).

4.2.10 Querying a Job

Function

This API is used to obtain information about a job via the job ID returned after a query request is delivered.

NOTE

- The URL for cluster management is in the format of **https://Endpoint/uri**. In the URL, **uri** indicates the resource path, that is, the path for API access.
- You can call this API when:
 - Creating or deleting a cluster
 - Creating or deleting a node

URI

GET /api/v3/projects/{project_id}/jobs/{job_id}

Table 4-152 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
job_id	Yes	String	Job ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-153 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-154 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Job and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	JobMetadata object	Job metadata
spec	JobSpec object	Detailed job parameters

Parameter	Type	Description
status	JobStatus object	Job status

Table 4-155 JobSpec

Parameter	Type	Description
type	String	Job type. An example value is CreateCluster .
clusterUID	String	ID of the cluster where the job runs.
resourceID	String	ID of the resource on which the job is executed.
resourceName	String	Name of the resource on which the job is executed.
extendParam	Map<String, String>	Extended parameters
subJobs	Array of Job objects	Subjob list. <ul style="list-style-type: none">• The list contains details about all subjobs.• Generally, a cluster/node creation job consists of multiple subjobs. The job is complete only after all subjobs are complete.

Table 4-156 Job

Parameter	Type	Description
kind	String	API type. The value is fixed at Job and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	JobMetadata object	Job metadata
spec	JobSpec object	Detailed job parameters
status	JobStatus object	Job status

Table 4-157 JobMetadata

Parameter	Type	Description
uid	String	Job ID
creationTimestamp	String	Time when the job was created
updateTimestamp	String	Time when the job was updated

Table 4-158 JobStatus

Parameter	Type	Description
phase	String	Job status. Possible values: <ul style="list-style-type: none">• JobPhaseInitializing JobPhase = "Initializing"• JobPhaseRunning JobPhase = "Running"• JobPhaseFailed JobPhase = "Failed"• JobPhaseSuccess JobPhase = "Success"
reason	String	Reason why the job is in the current state.

Example Requests

None

Example Responses

Status code: 200

The progress of the specified job is successfully obtained.

```
{  
    "kind" : "Job",  
    "apiVersion" : "v3",  
    "metadata" : {  
        "uid" : "354331b2c-229a-11e8-9c75-0255ac100ceb",  
        "creationTimestamp" : "2018-08-02 08:12:40.672772389 +0000 UTC",  
        "updateTimestamp" : "2018-08-02 08:21:50.478108569 +0000 UTC"  
    },  
    "spec" : {  
        "type" : "CreateCluster",  
        "clusterUID" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",  
        "resourceID" : "6f4dcbb2c-229a-11e8-9c75-0255ac100ceb",  
        "resourceName" : "cluster-name",  
        "extendParam" : {  
            "serverID" : "bc467e3a-2338-11e8-825b-0255ac100c13"  
        },  
        "subJobs" : [ {  
            "kind" : "Job",  
            "apiVersion" : "v3",  
            "metadata" : {  
                "uid" : "fd474fab-9606-11e8-baa9-0255ac10215d",  
                "creationTimestamp" : "2018-08-02 03:52:34.615819618 +0000 UTC",  
            }  
        }]  
    }  
}
```

```
        "updateTimestamp" : "2018-08-02 04:05:29.196243031 +0000 UTC"
    },
    "spec" : {
        "type" : "InstallMaster",
        "clusterUID" : "fcc72de0-9606-11e8-baa8-0255ac10215d",
        "resourceID" : "fd3b4ac0-9606-11e8-baa8-0255ac10215d",
        "extendParam" : {
            "serverID" : "fd3b4ac0-9606-11e8-baa8-0255ac10215d"
        }
    },
    "status" : {
        "phase" : "Success"
    }
}, {
    "kind" : "Job",
    "apiVersion" : "v3",
    "metadata" : {
        "uid" : "fd474f82-9606-11e8-baa8-0255ac10215d",
        "creationTimestamp" : "2018-08-02 03:52:33.859150791 +0000 UTC",
        "updateTimestamp" : "2018-08-02 03:52:34.615655429 +0000 UTC"
    },
    "spec" : {
        "type" : "CreatePSMCert",
        "clusterUID" : "fcc72de0-9606-11e8-baa8-0255ac10215d"
    },
    "status" : {
        "phase" : "Success"
    }
} ]
},
"status" : {
    "phase" : "Running",
    "reason" : ""
}
}
```

Status Codes

Status Code	Description
200	The progress of the specified job is successfully obtained.

Error Codes

See [Error Codes](#).

4.2.11 Binding/Unbinding Public API Server Address

Function

This API is used to bind or unbind the public API server address of the cluster by cluster ID.



NOTE

The URL for cluster management is in the format of `https://Endpoint/uri`. In the URL, `uri` indicates the resource path, that is, the path for API access.

URI

PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/mastereip

Table 4-159 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-160 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-161 Request body parameters

Parameter	Mandatory	Type	Description
spec	Yes	MasterEIPRequestSpec object	Parameters in the request for binding or unbinding the public APIServer address of a cluster

Table 4-162 MasterEIPRequestSpec

Parameter	Mandatory	Type	Description
action	No	String	Binding or unbinding. Mandatory. <ul style="list-style-type: none">• Binding: The value is fixed at {"action":"bind"}.• Unbinding: The value is fixed at {"action":"unbind"}.
spec	No	spec object	Configuration attributes of the elastic IP address to be bound
bandwidth	No	String	Bandwidth (This field has expired and is not recommended.)
elasticip	No	String	ENI IP (This field has expired and is not recommended.)

Table 4-163 spec

Parameter	Mandatory	Type	Description
id	No	String	Specifies the ENI ID. This parameter is mandatory for binding an ENI and is invalid for unbinding an ENI.

Response Parameters

Status code: 200

Table 4-164 Response body parameters

Parameter	Type	Description
metadata	Metadata object	Basic information about the object. Metadata is a collection of attributes.
spec	MasterEIPResponseSpec object	Configuration of the bound public API Server address of a cluster
status	status object	Status information

Table 4-165 Metadata

Parameter	Type	Description
uid	String	Unique ID.
name	String	Resource name
labels	Map<String, String>	Resource labels in key-value pairs. This is a reserved field and does not take effect.
annotations	Map<String, String>	Resource annotations in the format of key-value pairs.
updateTimestamp	String	Update time.
creationTimestamp	String	Creation time.

Table 4-166 MasterEIPResponseSpec

Parameter	Type	Description
action	String	A binding operation
spec	spec object	Configuration attributes of the elastic IP address to be bound
elasticip	String	EIP

Table 4-167 spec

Parameter	Type	Description
id	String	ENI ID
eip	EipSpec object	EIP details
IsDynamic	Boolean	Dynamic provisioning or not

Table 4-168 EipSpec

Parameter	Type	Description
bandwidth	bandwidth object	Bandwidth information

Table 4-169 bandwidth

Parameter	Type	Description
size	Integer	Bandwidth size
sharetype	String	Bandwidth type

Table 4-170 status

Parameter	Type	Description
privateEndpoint	String	Private IP for accessing the cluster (VIP in the case of an HA cluster)
publicEndpoint	String	Public IP for accessing the cluster

Example Requests

Bind the public API server address to a cluster.

```
{  
  "spec": {  
    "action": "bind",  
    "spec": {  
      "id": "a757a69e-f920-455a-b1ba-d7a22db0fd50"  
    }  
  }  
}
```

Example Responses

Status code: 200

This indicates that the public API server address of the cluster is successfully bound. No response body is returned if the unbinding is successful.

```
{  
  "metadata": { },  
  "spec": {  
    "action": "bind",  
    "spec": {  
      "id": "a757a69e-f920-455a-b1ba-d7a22db0fd50",  
      "eip": {  
        "bandwidth": {  
          "size": 5,  
          "sharetype": "PER"  
        }  
      },  
      "isDynamic": false  
    },  
    "elasticIp": "8.8.8.8"  
  },  
  "status": {  
    "privateEndpoint": "https://192.168.3.238:5443",  
    "publicEndpoint": "https://8.8.8.8:5443"  
  }  
}
```

Status Codes

Status Code	Description
200	This indicates that the public API server address of the cluster is successfully bound. No response body is returned if the unbinding is successful.

Error Codes

See [Error Codes](#).

4.2.12 Obtaining Cluster Access Address

Function

This API is used to obtain the cluster access addresses by cluster ID, including the private IP (VIP returned by an HA cluster) and public IP.



The URL for cluster management is in the format of https://Endpoint/uri. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

GET /api/v3/projects/{project_id}/clusters/{cluster_id}/openapi

Table 4-171 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-172 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-173 Response body parameters

Parameter	Type	Description
metadata	Metadata object	Basic information about the object. Metadata is a collection of attributes.
spec	OpenAPISpec object	Parameters for configuring the address for accessing the cluster
status	status object	Status information

Table 4-174 Metadata

Parameter	Type	Description
uid	String	Unique ID.
name	String	Resource name
labels	Map<String, String>	Resource labels in key-value pairs. This is a reserved field and does not take effect.
annotations	Map<String, String>	Resource annotations in the format of key-value pairs.
updateTimestamp	String	Update time.
creationTimestamp	String	Creation time.

Table 4-175 OpenAPISpec

Parameter	Type	Description
spec	spec object	Address for accessing the cluster

Table 4-176 spec

Parameter	Type	Description
eip	EipSpec object	EIP details
IsDynamic	Boolean	Dynamic provisioning or not

Table 4-177 EipSpec

Parameter	Type	Description
bandwidth	bandwidth object	Bandwidth information

Table 4-178 bandwidth

Parameter	Type	Description
size	Integer	Bandwidth size
sharetype	String	Bandwidth type

Table 4-179 status

Parameter	Type	Description
privateEndpoint	String	Private IP for accessing the cluster (VIP in the case of an HA cluster)
publicEndpoint	String	Public IP for accessing the cluster

Example Requests

None

Example Responses

Status code: 200

The cluster access address is obtained successfully.

```
{  
    "metadata": { },  
    "spec": {  
        "spec": {  
            "eip": {  
                "bandwidth": { }  
            },  
            "isDynamic": false  
        }  
    },  
    "status": {  
        "privateEndpoint": "https://192.168.3.238:5443",  
        "publicEndpoint": ""  
    }  
}
```

Status Codes

Status Code	Description
200	The cluster access address is obtained successfully.

Error Codes

See [Error Codes](#).

4.3 Node Management

4.3.1 Creating a Node

Function

This API is used to create a node in a specified cluster.



NOTE

- If there is no cluster, [create one](#).
- The URL for cluster management is in the format of <https://Endpoint/uri>. In the URL, **uri** indicates the resource path, that is, the path for API access.

Constraints

Only KVM nodes can be created. Non-KVM nodes cannot be used after being created.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes

Table 4-180 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Table 4-181 Query Parameters

Parameter	Mandatory	Type	Description
nodepoolScaleUp	No	String	Whether the request is delivered by the node pool. If the value is not NodepoolScaleUp , the number of pods in the corresponding node pool is automatically updated.

Request Parameters

Table 4-182 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-183 Request body parameters

Parameter	Mandatory	Type	Description
kind	Yes	String	API type. The value is fixed at Node and cannot be changed.
apiVersion	Yes	String	API version. The value is fixed at v3 and cannot be changed.
metadata	No	NodeMetadata object	Node metadata, which is a collection of attributes.
spec	Yes	NodeSpec object	Detailed description of the node. CCE creates or updates objects by defining or updating spec .

Table 4-184 NodeMetadata

Parameter	Mandatory	Type	Description
name	No	String	<p>Node name</p> <p>NOTE</p> <p>Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. If name is left empty or is not specified, the node name is generated based on the default rule, which is <i>Cluster name-Random characters</i>. Only the first 36 characters are kept for a long cluster name. If the number of nodes (count) is greater than 1, some random characters are added to the end of the entered node name according to the default rule, which is <i>User-defined name-Random characters</i>. Only the first 50 characters in the custom name are kept, followed by some random characters. Names of nodes running in clusters v1.28.1, v1.27.3, v1.25.6, v1.23.11, v1.21.12 or later support periods (.), but this configuration is not recommended.</p>
uid	No	String	Node ID, which is unique and automatically generated after the resource is created. A user-defined ID will not take effect.

Parameter	Mandatory	Type	Description
labels	No	Map<String, String>	<p>CCE node label (not the native Kubernetes label). Labels are used to select objects that meet certain criteria. A label is a key-value pair.</p> <p>Example:</p> <pre>"labels": { "key" : "value" }</pre>
annotations	No	Map<String, String>	<p>CCE node annotations, in key-value pairs (not the native Kubernetes annotations).</p> <p>Example:</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations are not used to identify or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
creationTimestamp	No	String	Time when the object was created. The value is automatically generated after the object is created. A user-defined value will not take effect.
updateTimestamp	No	String	Time when the object was updated. The value is automatically generated after the object is created. A user-defined value will not take effect.

Table 4-185 NodeSpec

Parameter	Mandatory	Type	Description
flavor	Yes	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	Yes	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	No	String	The OS type of the node. For details about the supported OSs, see Node OS . NOTE <ul style="list-style-type: none">The system automatically selects the supported OS based on the cluster version. If the current cluster does not support the OS, an error will be reported.If alpha.cce/NodeImageID in extendParam is specified during node creation, you do not need to configure this parameter.This parameter is mandatory when creating a node pool.
login	Yes	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Yes	Volume object	Information about disks on the node
dataVolumes	Yes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .

Parameter	Mandatory	Type	Description
storage	No	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	No	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	No	NodeNicSpec object	NIC of the node
count	No	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	No	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Mandatory	Type	Description
taints	No	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Mandatory	Type	Description
k8sTags	No	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"k8sTags": { "key": "value" }</pre>
ecsGroupId	No	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>

Parameter	Mandatory	Type	Description
dedicatedHostId	No	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>
userTags	No	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	No	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Mandatory	Type	Description
initializedConditions	No	Array of strings	<p>Custom initialization flag, which is left blank by default. Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.

Parameter	Mandatory	Type	Description
			<p>2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.</p> <ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).
extendParam	No	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	No	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-186 Login

Parameter	Mandatory	Type	Description
sshKey	No	String	Name of the key pair used for login.

Table 4-187 UserPassword

Parameter	Mandatory	Type	Description
username	No	String	Login account. Defaults to root .

Parameter	Mandatory	Type	Description
password	Yes	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@#\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-188 Volume

Parameter	Mandatory	Type	Description
size	Yes	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 - Value range for data disks: 100 to 32768
volumetype	Yes	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk SATA disks have been removed from EVS. You can find them attached only on existing nodes.

Parameter	Mandatory	Type	Description
extendParam	No	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	No	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	No	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	No	Boolean	<ul style="list-style-type: none"> Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created. If the node pool type is ElasticBMS, this field must be set to true. If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	No	VolumeMeta data object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-189 VolumeMetadata

Parameter	Mandatory	Type	Description
_system_encrypted	No	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.
_system_cm_kid	No	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-190 Storage

Parameter	Mandatory	Type	Description
storageSelectors	Yes	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
storageGroups	Yes	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-191 StorageSelectors

Parameter	Mandatory	Type	Description
name	Yes	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.

Parameter	Mandatory	Type	Description
storageType	Yes	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
matchLabels	No	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-192 matchLabels

Parameter	Mandatory	Type	Description
size	No	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
volumeType	No	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.
metadataEncrypted	No	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkid	No	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	No	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-193 StorageGroups

Parameter	Mandatory	Type	Description
name	Yes	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	No	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Yes	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Yes	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-194 VirtualSpace

Parameter	Mandatory	Type	Description
name	Yes	String	Name of a virtualSpace. <ul style="list-style-type: none">• Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.• runtime: runtime space configuration. runtimeConfig needs to be configured.• user: user space configuration. lvmConfig needs to be configured.
size	Yes	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	No	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	No	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-195 LVMConfig

Parameter	Mandatory	Type	Description
lvType	Yes	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Parameter	Mandatory	Type	Description
path	No	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-196 RuntimeConfig

Parameter	Mandatory	Type	Description
lvType	Yes	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-197 NodePublicIP

Parameter	Mandatory	Type	Description
ids	No	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	No	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	No	NodeEIPSpec object	EIP configuration.

Table 4-198 NodeEIPSpec

Parameter	Mandatory	Type	Description
iptype	Yes	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	No	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-199 NodeBandwidth

Parameter	Mandatory	Type	Description
chargemode	No	String	<p>Bandwidth billing mode.</p> <ul style="list-style-type: none">If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.If the field value is traffic, the billing is based on traffic.If the value is out of the preceding options, the cloud server will fail to be created. <p>NOTE</p> <ul style="list-style-type: none">Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.
size	No	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.

Parameter	Mandatory	Type	Description
sharetype	No	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-200 NodeNicSpec

Parameter	Mandatory	Type	Description
primaryNic	No	NicSpec object	Description of the primary NIC.
extNics	No	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-201 NicSpec

Parameter	Mandatory	Type	Description
subnetId	No	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	No	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.

Parameter	Mandatory	Type	Description
ipBlock	No	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-202 Taint

Parameter	Mandatory	Type	Description
key	Yes	String	Key.
value	No	String	Value.
effect	Yes	String	Effect.

Table 4-203 UserTag

Parameter	Mandatory	Type	Description
key	No	String	Key of the cloud server label. The value cannot start with CCE- or _type_baremetal .
value	No	String	Value of the cloud server label.

Table 4-204 Runtime

Parameter	Mandatory	Type	Description
name	No	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is docker.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is docker; for nodes running other OSs, the default container runtime is containerd.

Table 4-205 NodeExtendParam

Parameter	Mandatory	Type	Description
ecs:performancetype	No	String	ECS flavor types. This field is returned in the response.
maxPods	No	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256. This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>

Parameter	Mandatory	Type	Description
DockerLVMConfigOverride	No	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.)</p> <p>Example default configuration: "DockerLVMConfigOverride":"dockerThinpool=vgpaas/90%VG;kubernetesLV=vgpaas/10%VG;diskType=evs;lvType=linear"</p> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none">• userLV (optional): size of the user space, for example, vgpaas/20%VG.• userPath (optional): mount path of the user space, for example, /home/wqt-test.• diskType: disk type. Currently, only evs, hdd, and ssd are supported.• lvType: type of a logic volume. The value can be linear or striped.• dockerThinpool: Docker space size, for example, vgpaas/60%VG.• kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Mandatory	Type	Description
dockerBaseSize	No	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	No	String	Public key of a node.
alpha.cce/preInstall	No	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	No	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	No	String	This parameter is required when a custom image is used to create a BMS node.

Parameter	Mandatory	Type	Description
chargingMode	No	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	No	String	Name of an agency An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.
kubeReservedMem	No	Integer	Reserved node memory, which is reserved for Kubernetes components.
systemReservedMem	No	Integer	Reserved node memory, which is reserved for system components.
init-node-password	No	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-206 HostnameConfig

Parameter	Mandatory	Type	Description
type	Yes	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Response Parameters

Status code: 201

Table 4-207 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Node and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.

Parameter	Type	Description
metadata	NodeMetadata object	Node metadata, which is a collection of attributes.
spec	NodeSpec object	Detailed description of the node. CCE creates or updates objects by defining or updating spec .
status	NodeStatus object	Node status, which is dynamically recorded. A user-defined value will not function when a node is being created or modified.

Table 4-208 NodeMetadata

Parameter	Type	Description
name	String	<p>Node name</p> <p>NOTE</p> <p>Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. If name is left empty or is not specified, the node name is generated based on the default rule, which is <i>Cluster name-Random characters</i>. Only the first 36 characters are kept for a long cluster name. If the number of nodes (count) is greater than 1, some random characters are added to the end of the entered node name according to the default rule, which is <i>User-defined name-Random characters</i>. Only the first 50 characters in the custom name are kept, followed by some random characters. Names of nodes running in clusters v1.28.1, v1.27.3, v1.25.6, v1.23.11, v1.21.12 or later support periods (.), but this configuration is not recommended.</p>
uid	String	Node ID, which is unique and automatically generated after the resource is created. A user-defined ID will not take effect.
labels	Map<String, String>	<p>CCE node label (not the native Kubernetes label).</p> <p>Labels are used to select objects that meet certain criteria. A label is a key-value pair.</p> <p>Example:</p> <pre>"labels": { "key" : "value" }</pre>

Parameter	Type	Description
annotations	Map<String, String>	<p>CCE node annotations, in key-value pairs (not the native Kubernetes annotations). Example:</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations are not used to identify or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
creationTimestamp	String	Time when the object was created. The value is automatically generated after the object is created. A user-defined value will not take effect.
updateTimestamp	String	Time when the object was updated. The value is automatically generated after the object is created. A user-defined value will not take effect.

Table 4-209 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	String	The OS type of the node. For details about the supported OSs, see Node OS .

Parameter	Type	Description
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .
storage	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	NodeNicSpec object	NIC of the node
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Type	Description
taints	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"k8sTags": { "key": "value" }</pre>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-210 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-211 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-212 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-213 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-214 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-215 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-216 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-217 StorageGroups

Parameter	Type	Description
name	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-218 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">● Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.● runtime: runtime space configuration. runtimeConfig needs to be configured.● user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-219 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-220 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-221 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-222 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-223 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-224 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-225 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-226 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-227 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-228 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is <code>docker</code>.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-229 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/ 90%VG;kubernetesLV=vgpaas/ 10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none"> • userLV (optional): size of the user space, for example, vgpaas/20%VG. • userPath (optional): mount path of the user space, for example, /home/wqt-test. • diskType: disk type. Currently, only evs, hdd, and ssd are supported. • lvType: type of a logic volume. The value can be linear or striped. • dockerThinpool: Docker space size, for example, vgpaas/60%VG. • kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-230 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-231 NodeStatus

Parameter	Type	Description
phase	String	Node status, which is the status of a node during its lifecycle (such as installation and uninstallation) or the status of a node in a Kubernetes cluster. Options: <ul style="list-style-type: none">• Build: The node is being created.• Installing: The node is being managed.• Upgrading: The node is being upgraded.• Active: The node is running properly.• Abnormal: The node is abnormal.• Deleting: The node is being deleted.• Error: The node is faulty.
lastProbeTime	String	Last time when the node status was checked. If the cluster is in the abnormal, frozen, or intermediate state (for example, creating), the node status check may be affected. The node status that takes more than five minutes to check has no reference value.
jobID	String	ID of a creation or deletion job
serverId	String	ID of the underlying ECS or BMS node
privateIP	String	IP address in the private network segment of the primary NIC on the node
privateIPv6IP	String	IPv6 address in the private network segment of the primary NIC on the node
publicIP	String	Node EIP. If the ECS data is not synchronized in real time, you can click Sync Node Data on the console to manually update the data.
deleteStatus	DeleteStatus object	Resource status during resource deletion.

Table 4-232 DeleteStatus

Parameter	Type	Description
previous_total	Integer	Total number of existing cluster resource records when the cluster is deleted.
current_total	Integer	Latest number of resource records, which is generated based on the current cluster resource records.

Parameter	Type	Description
updated	Integer	Total number of resource records updated when the cluster is deleted.
added	Integer	Total number of resource records updated when the cluster is deleted.
deleted	Integer	Total number of resource records deleted when the cluster is deleted.

Example Requests

Create a node with the flavor of 2 vCPUs and 4 GiB of memory. The node runs EulerOS 2.5 for Docker containers. The sizes of the system disk and data disk of the node are 50 GB and 100 GB, respectively. Both the disks are of the high I/O type.

```
POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes
```

```
{
  "kind" : "Node",
  "apiVersion" : "v3",
  "metadata" : {
    "name" : "test-83790"
  },
  "spec" : {
    "flavor" : "c7.large.2",
    "az" : "*****",
    "os" : "EulerOS 2.5",
    "dataVolumes" : [ {
      "size" : 100,
      "volumetype" : "SAS"
    }],
    "billingMode" : 0,
    "extendParam" : {
      "maxPods" : 110
    },
    "nodeNicSpec" : {
      "primaryNic" : {
        "subnetId" : "ca964acf-8468-4735-8229-97940ef6c881"
      }
    },
    "rootVolume" : {
      "size" : 50,
      "volumetype" : "SAS"
    },
    "runtime" : {
      "name" : "docker"
    },
    "login" : {
      "sshKey" : "KeyPair-001"
    },
    "storage" : {
      "storageSelectors" : [ {
        "name" : "cceUse",
        "storageType" : "evs",
        "matchLabels" : {
          "size" : "100",
          "volumeType" : "SAS",
          "count" : "1"
        }
      }]
    }
}
```

```
"storageGroups" : [ {
  "name" : "vgpaas",
  "selectorNames" : [ "cceUse" ],
  "cceManaged" : true,
  "virtualSpaces" : [ {
    "name" : "runtime",
    "size" : "90%"
  }, {
    "name" : "kubernetes",
    "size" : "10%"
  } ]
},
"count" : 1
}
```

Example Responses

Status code: 201

The job for creating a node in a specified cluster is successfully delivered.

```
{
  "kind" : "Node",
  "apiVersion" : "v3",
  "metadata" : {
    "name" : "test-83790",
    "uid" : "5ecfddfe-87db-11ec-b5e5-0255ac101514",
    "annotations" : {
      "jobid" : "5ec1518c-87db-11ec-b5e5-0255ac101514",
      "resourceJobId" : "5ed0d692-87db-11ec-b5e5-0255ac101514"
    }
  },
  "spec" : {
    "flavor" : "c7.large.2",
    "az" : "*****",
    "os" : "EulerOS 2.5",
    "login" : {
      "sshKey" : "KeyPair-001"
    },
    "rootVolume" : {
      "volumetype" : "SAS",
      "size" : 50
    },
    "dataVolumes" : [ {
      "volumetype" : "SAS",
      "size" : 100
    }],
    "storage" : {
      "storageSelectors" : [ {
        "name" : "cceUse",
        "storageType" : "evs",
        "matchLabels" : {
          "count" : "1",
          "size" : "100",
          "volumeType" : "SAS"
        }
      }],
      "storageGroups" : [ {
        "name" : "vgpaas",
        "cceManaged" : true,
        "selectorNames" : [ "cceUse" ],
        "virtualSpaces" : [ {
          "name" : "runtime",
          "size" : "90%"
        }, {
          "name" : "kubernetes",
          "size" : "10%"
        } ]
      }]
    }
  }
}
```

```
        }
    }
},
"publicIP" : {
    "eip" : {
        "bandwidth" : { }
    }
},
"nodeNicSpec" : {
    "primaryNic" : {
        "subnetId" : "ca964acf-8468-4735-8229-97940ef6c881"
    }
},
"count" : 1,
"billingMode" : 0,
"runtime" : {
    "name" : "docker"
},
"extendParam" : {
    "chargingMode" : 0,
    "ecs:performancetype" : "computingv3",
    "init-node-password" : "*****",
    "maxPods" : 110,
    "publicKey" : ""
},
"status" : {
    "jobID" : "5ec1518c-87db-11ec-b5e5-0255ac101514"
}
}
```

Status Codes

Status Code	Description
201	The job for creating a node in a specified cluster is successfully delivered.

Error Codes

See [Error Codes](#).

4.3.2 Reading a Specified Node

Function

This API is used to obtain details about a specified node via the node ID.



The URL for cluster management is in the format of `https://Endpoint/uri`. In the URL, `uri` indicates the resource path, that is, the path for API access.

URI

`GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/{node_id}`

Table 4-233 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
node_id	Yes	String	Node ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-234 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-235 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Node and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.

Parameter	Type	Description
metadata	NodeMetadata object	Node metadata, which is a collection of attributes.
spec	NodeSpec object	Detailed description of the node. CCE creates or updates objects by defining or updating spec .
status	NodeStatus object	Node status, which is dynamically recorded. A user-defined value will not function when a node is being created or modified.

Table 4-236 NodeMetadata

Parameter	Type	Description
name	String	<p>Node name</p> <p>NOTE</p> <p>Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. If name is left empty or is not specified, the node name is generated based on the default rule, which is <i>Cluster name-Random characters</i>. Only the first 36 characters are kept for a long cluster name. If the number of nodes (count) is greater than 1, some random characters are added to the end of the entered node name according to the default rule, which is <i>User-defined name-Random characters</i>. Only the first 50 characters in the custom name are kept, followed by some random characters. Names of nodes running in clusters v1.28.1, v1.27.3, v1.25.6, v1.23.11, v1.21.12 or later support periods (.), but this configuration is not recommended.</p>
uid	String	Node ID, which is unique and automatically generated after the resource is created. A user-defined ID will not take effect.
labels	Map<String, String>	<p>CCE node label (not the native Kubernetes label).</p> <p>Labels are used to select objects that meet certain criteria. A label is a key-value pair.</p> <p>Example:</p> <pre>"labels": { "key" : "value" }</pre>

Parameter	Type	Description
annotations	Map<String, String>	<p>CCE node annotations, in key-value pairs (not the native Kubernetes annotations). Example:</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations are not used to identify or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
creationTimestamp	String	Time when the object was created. The value is automatically generated after the object is created. A user-defined value will not take effect.
updateTimestamp	String	Time when the object was updated. The value is automatically generated after the object is created. A user-defined value will not take effect.

Table 4-237 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	String	The OS type of the node. For details about the supported OSs, see Node OS .

Parameter	Type	Description
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .
storage	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	NodeNicSpec object	NIC of the node
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Type	Description
taints	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example: "k8sTags": { "key": "value" }</p>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-238 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-239 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-240 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-241 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-242 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-243 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-244 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-245 StorageGroups

Parameter	Type	Description
name	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-246 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">● Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.● runtime: runtime space configuration. runtimeConfig needs to be configured.● user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-247 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-248 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-249 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-250 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-251 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-252 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-253 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-254 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-255 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-256 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is <code>docker</code>.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-257 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/ 90%VG;kubernetesLV=vgpaas/ 10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none"> • userLV (optional): size of the user space, for example, vgpaas/20%VG. • userPath (optional): mount path of the user space, for example, /home/wqt-test. • diskType: disk type. Currently, only evs, hdd, and ssd are supported. • lvType: type of a logic volume. The value can be linear or striped. • dockerThinpool: Docker space size, for example, vgpaas/60%VG. • kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-258 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none"> • privatelp: The Kubernetes node is named after its IP address. • cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none"> • For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization. • For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-259 NodeStatus

Parameter	Type	Description
phase	String	Node status, which is the status of a node during its lifecycle (such as installation and uninstallation) or the status of a node in a Kubernetes cluster. Options: <ul style="list-style-type: none">• Build: The node is being created.• Installing: The node is being managed.• Upgrading: The node is being upgraded.• Active: The node is running properly.• Abnormal: The node is abnormal.• Deleting: The node is being deleted.• Error: The node is faulty.
lastProbeTime	String	Last time when the node status was checked. If the cluster is in the abnormal, frozen, or intermediate state (for example, creating), the node status check may be affected. The node status that takes more than five minutes to check has no reference value.
jobID	String	ID of a creation or deletion job
serverId	String	ID of the underlying ECS or BMS node
privateIP	String	IP address in the private network segment of the primary NIC on the node
privateIPv6IP	String	IPv6 address in the private network segment of the primary NIC on the node
publicIP	String	Node EIP. If the ECS data is not synchronized in real time, you can click Sync Node Data on the console to manually update the data.
deleteStatus	DeleteStatus object	Resource status during resource deletion.

Table 4-260 DeleteStatus

Parameter	Type	Description
previous_total	Integer	Total number of existing cluster resource records when the cluster is deleted.
current_total	Integer	Latest number of resource records, which is generated based on the current cluster resource records.

Parameter	Type	Description
updated	Integer	Total number of resource records updated when the cluster is deleted.
added	Integer	Total number of resource records updated when the cluster is deleted.
deleted	Integer	Total number of resource records deleted when the cluster is deleted.

Example Requests

None

Example Responses

Status code: 200

Information about the specified node is successfully obtained.

```
{
  "kind" : "Node",
  "apiVersion" : "v3",
  "metadata" : {
    "name" : "myhost",
    "uid" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",
    "creationTimestamp" : "2018-08-02 08:12:40.124294439 +0000 UTC",
    "updateTimestamp" : "2018-08-02 08:18:20.221871842 +0000 UTC",
    "annotations" : {
      "kubernetes.io/node-pool.id" : "az1.dc1#s1.medium#EulerOS 2.2"
    }
  },
  "spec" : {
    "flavor" : "s1.medium",
    "az" : "*****",
    "os" : "EulerOS 2.2",
    "login" : {
      "sshKey" : "KeyPair-001"
    },
    "rootVolume" : {
      "volumetype" : "SAS",
      "size" : 40
    },
    "dataVolumes" : [ {
      "volumetype" : "SAS",
      "size" : 100
    }],
    "publicIP" : {
      "eip" : {
        "bandwidth" : { }
      }
    },
    "billingMode" : 0
  },
  "status" : {
    "phase" : "Active",
    "serverId" : "456789abc-9368-46f3-8f29-d1a95622a568",
    "publicIP" : "10.34.56.78",
    "privateIP" : "192.168.1.23"
  }
}
```

Status Codes

Status Code	Description
200	Information about the specified node is successfully obtained.

Error Codes

See [Error Codes](#).

4.3.3 Listing All Nodes in a Cluster

Function

This API is used to obtain details about all nodes in a specified cluster with the cluster ID.



The URL for cluster management is in the format of https://Endpoint/uri. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes

Table 4-261 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-262 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-263 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at List .
apiVersion	String	API version. The value is fixed at v3 .
items	Array of Node objects	List of details for all nodes in the current cluster. You can filter nodes by items.metadata.name .

Table 4-264 Node

Parameter	Type	Description
kind	String	API type. The value is fixed at Node and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	NodeMetadata object	Node metadata, which is a collection of attributes.
spec	NodeSpec object	Detailed description of the node. CCE creates or updates objects by defining or updating spec .
status	NodeStatus object	Node status, which is dynamically recorded. A user-defined value will not function when a node is being created or modified.

Table 4-265 NodeMetadata

Parameter	Type	Description
name	String	<p>Node name</p> <p>NOTE</p> <p>Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. If name is left empty or is not specified, the node name is generated based on the default rule, which is <i>Cluster name-Random characters</i>. Only the first 36 characters are kept for a long cluster name. If the number of nodes (count) is greater than 1, some random characters are added to the end of the entered node name according to the default rule, which is <i>User-defined name-Random characters</i>. Only the first 50 characters in the custom name are kept, followed by some random characters. Names of nodes running in clusters v1.28.1, v1.27.3, v1.25.6, v1.23.11, v1.21.12 or later support periods (.), but this configuration is not recommended.</p>
uid	String	<p>Node ID, which is unique and automatically generated after the resource is created. A user-defined ID will not take effect.</p>
labels	Map<String, String>	<p>CCE node label (not the native Kubernetes label).</p> <p>Labels are used to select objects that meet certain criteria. A label is a key-value pair.</p> <p>Example:</p> <pre>"labels": { "key" : "value" }</pre>
annotations	Map<String, String>	<p>CCE node annotations, in key-value pairs (not the native Kubernetes annotations). Example:</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations are not used to identify or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
creationTimestamp	String	<p>Time when the object was created. The value is automatically generated after the object is created. A user-defined value will not take effect.</p>

Parameter	Type	Description
updateTimestamp	String	Time when the object was updated. The value is automatically generated after the object is created. A user-defined value will not take effect.

Table 4-266 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	String	The OS type of the node. For details about the supported OSs, see Node OS . NOTE <ul style="list-style-type: none"> The system automatically selects the supported OS based on the cluster version. If the current cluster does not support the OS, an error will be reported. If alpha.cce/NodeImageID in extendParam is specified during node creation, you do not need to configure this parameter. This parameter is mandatory when creating a node pool.
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .

Parameter	Type	Description
storage	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	NodeNicSpec object	NIC of the node
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Type	Description
taints	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"k8sTags": { "key": "value" }</pre>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none"> Clusters of v1.25 or earlier: docker. Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-267 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-268 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-269 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-270 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-271 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-272 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-273 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-274 StorageGroups

Parameter	Type	Description
name	String	<p>Name of a virtual storage group, which must be unique.</p> <p>NOTE</p> <ul style="list-style-type: none"> • If cceManaged is set to true, the name must be set to vgpass. • If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral. • If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-275 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">• Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.• runtime: runtime space configuration. runtimeConfig needs to be configured.• user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-276 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-277 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-278 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-279 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-280 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-281 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-282 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-283 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-284 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-285 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is <code>docker</code>.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-286 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/ 90%VG;kubernetesLV=vgpaas/ 10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none"> • userLV (optional): size of the user space, for example, vgpaas/20%VG. • userPath (optional): mount path of the user space, for example, /home/wqt-test. • diskType: disk type. Currently, only evs, hdd, and ssd are supported. • lvType: type of a logic volume. The value can be linear or striped. • dockerThinpool: Docker space size, for example, vgpaas/60%VG. • kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-287 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-288 NodeStatus

Parameter	Type	Description
phase	String	Node status, which is the status of a node during its lifecycle (such as installation and uninstallation) or the status of a node in a Kubernetes cluster. Options: <ul style="list-style-type: none">• Build: The node is being created.• Installing: The node is being managed.• Upgrading: The node is being upgraded.• Active: The node is running properly.• Abnormal: The node is abnormal.• Deleting: The node is being deleted.• Error: The node is faulty.
lastProbeTime	String	Last time when the node status was checked. If the cluster is in the abnormal, frozen, or intermediate state (for example, creating), the node status check may be affected. The node status that takes more than five minutes to check has no reference value.
jobID	String	ID of a creation or deletion job
serverId	String	ID of the underlying ECS or BMS node
privateIP	String	IP address in the private network segment of the primary NIC on the node
privateIPv6IP	String	IPv6 address in the private network segment of the primary NIC on the node
publicIP	String	Node EIP. If the ECS data is not synchronized in real time, you can click Sync Node Data on the console to manually update the data.
deleteStatus	DeleteStatus object	Resource status during resource deletion.

Table 4-289 DeleteStatus

Parameter	Type	Description
previous_total	Integer	Total number of existing cluster resource records when the cluster is deleted.
current_total	Integer	Latest number of resource records, which is generated based on the current cluster resource records.

Parameter	Type	Description
updated	Integer	Total number of resource records updated when the cluster is deleted.
added	Integer	Total number of resource records updated when the cluster is deleted.
deleted	Integer	Total number of resource records deleted when the cluster is deleted.

Example Requests

None

Example Responses

Status code: 200

Information about all the nodes in the specified cluster is successfully obtained.

```
{
  "kind" : "List",
  "apiVersion" : "v3",
  "items" : [ {
    "kind" : "Node",
    "apiVersion" : "v3",
    "metadata" : {
      "name" : "myhost",
      "uid" : "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",
      "creationTimestamp" : "2018-08-02 07:37:24.005071325 +0000 UTC",
      "updateTimestamp" : "2018-08-02 07:44:04.965500815 +0000 UTC",
      "annotations" : {
        "kubernetes.io/node-pool.id" : "az1.dc1#s1.medium#EulerOS 2.2"
      }
    },
    "spec" : {
      "flavor" : "s1.medium",
      "az" : "az1.dc1",
      "os" : "EulerOS 2.2",
      "login" : {
        "sshKey" : "KeyPair-001"
      },
      "rootVolume" : {
        "volumetype" : "SAS",
        "size" : 40
      },
      "dataVolumes" : [ {
        "volumetype" : "SAS",
        "size" : 100
      }],
      "publicIP" : {
        "eip" : {
          "bandwidth" : { }
        }
      },
      "billingMode" : 0
    },
    "status" : {
      "phase" : "Active",
      "serverId" : "456789abc-9368-46f3-8f29-d1a95622a568",
      "publicIP" : "10.34.56.78",
      "nodeIP" : "10.34.56.78"
    }
  }
}
```

```
        "privateIP" : "192.168.1.23"
    }
}
}
```

Status Codes

Status Code	Description
200	Information about all the nodes in the specified cluster is successfully obtained.

Error Codes

See [Error Codes](#).

4.3.4 Updating a Specified Node

Function

This API is used to update information about a specified node.



- Currently, only the **name** field in **metadata** can be updated. This field indicates the node name.
- The URL for cluster management is in the format of **https://Endpoint/uri**. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/{node_id}

Table 4-290 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
node_id	Yes	String	Node ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-291 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-292 Request body parameters

Parameter	Mandatory	Type	Description
metadata	Yes	ClusterNodeInformationMetadata object	Node metadata, which is a collection of attributes.

Table 4-293 ClusterNodeInformationMetadata

Parameter	Mandatory	Type	Description
name	Yes	String	<p>Node name</p> <p>NOTE</p> <p>After the node name is changed, the ECS name (VM name) will be changed accordingly. Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. Names of nodes running in clusters v1.28.1, v1.27.3, v1.25.6, v1.23.11, v1.21.12 or later support periods (.), but this configuration is not recommended.</p>

Response Parameters

Status code: 200

Table 4-294 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Node and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	NodeMetadata object	Node metadata, which is a collection of attributes.
spec	NodeSpec object	Detailed description of the node. CCE creates or updates objects by defining or updating spec .
status	NodeStatus object	Node status, which is dynamically recorded. A user-defined value will not function when a node is being created or modified.

Table 4-295 NodeMetadata

Parameter	Type	Description
name	String	<p>Node name</p> <p>NOTE</p> <p>Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. If name is left empty or is not specified, the node name is generated based on the default rule, which is <i>Cluster name-Random characters</i>. Only the first 36 characters are kept for a long cluster name. If the number of nodes (count) is greater than 1, some random characters are added to the end of the entered node name according to the default rule, which is <i>User-defined name-Random characters</i>. Only the first 50 characters in the custom name are kept, followed by some random characters. Names of nodes running in clusters v1.28.1, v1.27.3, v1.25.6, v1.23.11, v1.21.12 or later support periods (.), but this configuration is not recommended.</p>
uid	String	<p>Node ID, which is unique and automatically generated after the resource is created. A user-defined ID will not take effect.</p>
labels	Map<String, String>	<p>CCE node label (not the native Kubernetes label).</p> <p>Labels are used to select objects that meet certain criteria. A label is a key-value pair.</p> <p>Example:</p> <pre>"labels": { "key" : "value" }</pre>

Parameter	Type	Description
annotations	Map<String, String>	<p>CCE node annotations, in key-value pairs (not the native Kubernetes annotations). Example:</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations are not used to identify or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
creationTimestamp	String	Time when the object was created. The value is automatically generated after the object is created. A user-defined value will not take effect.
updateTimestamp	String	Time when the object was updated. The value is automatically generated after the object is created. A user-defined value will not take effect.

Table 4-296 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	String	The OS type of the node. For details about the supported OSs, see Node OS .

Parameter	Type	Description
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .
storage	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	NodeNicSpec object	NIC of the node
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Type	Description
taints	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example: "k8sTags": { "key": "value" }</p>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">• Clusters of v1.25 or earlier: docker.• Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-297 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-298 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-299 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-300 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-301 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-302 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-303 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-304 StorageGroups

Parameter	Type	Description
name	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-305 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">● Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.● runtime: runtime space configuration. runtimeConfig needs to be configured.● user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-306 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-307 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-308 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-309 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-310 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-311 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-312 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-313 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-314 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-315 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is <code>docker</code>.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-316 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/90%VG;kubernetesLV=vgpaas/10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none">• userLV (optional): size of the user space, for example, vgpaas/20%VG.• userPath (optional): mount path of the user space, for example, /home/wqt-test.• diskType: disk type. Currently, only evs, hdd, and ssd are supported.• lvType: type of a logic volume. The value can be linear or striped.• dockerThinpool: Docker space size, for example, vgpaas/60%VG.• kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-317 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-318 NodeStatus

Parameter	Type	Description
phase	String	Node status, which is the status of a node during its lifecycle (such as installation and uninstallation) or the status of a node in a Kubernetes cluster. Options: <ul style="list-style-type: none">• Build: The node is being created.• Installing: The node is being managed.• Upgrading: The node is being upgraded.• Active: The node is running properly.• Abnormal: The node is abnormal.• Deleting: The node is being deleted.• Error: The node is faulty.
lastProbeTime	String	Last time when the node status was checked. If the cluster is in the abnormal, frozen, or intermediate state (for example, creating), the node status check may be affected. The node status that takes more than five minutes to check has no reference value.
jobID	String	ID of a creation or deletion job
serverId	String	ID of the underlying ECS or BMS node
privateIP	String	IP address in the private network segment of the primary NIC on the node
privateIPv6IP	String	IPv6 address in the private network segment of the primary NIC on the node
publicIP	String	Node EIP. If the ECS data is not synchronized in real time, you can click Sync Node Data on the console to manually update the data.
deleteStatus	DeleteStatus object	Resource status during resource deletion.

Table 4-319 DeleteStatus

Parameter	Type	Description
previous_total	Integer	Total number of existing cluster resource records when the cluster is deleted.
current_total	Integer	Latest number of resource records, which is generated based on the current cluster resource records.

Parameter	Type	Description
updated	Integer	Total number of resource records updated when the cluster is deleted.
added	Integer	Total number of resource records updated when the cluster is deleted.
deleted	Integer	Total number of resource records deleted when the cluster is deleted.

Example Requests

Update the name of a specified node.

```
{
  "metadata": {
    "name": "new-hostname"
  }
}
```

Example Responses

Status code: 200

Information about the specified node is successfully updated.

```
{
  "kind": "Node",
  "apiVersion": "v3",
  "metadata": {
    "name": "new-hostname",
    "uid": "4d1ecb2c-229a-11e8-9c75-0255ac100ceb",
    "creationTimestamp": "2017-08-20T21:11:09Z",
    "updateTimestamp": "2017-08-20T21:11:09Z",
    "annotations": {
      "kubernetes.io/node-pool.id": "az1.dc1#s1.medium#EulerOS 2.2"
    }
  },
  "spec": {
    "flavor": "s1.medium",
    "az": "az1.dc1",
    "os": "EulerOS 2.2",
    "login": {
      "sshKey": "KeyPair-001"
    },
    "rootVolume": {
      "volumetype": "SAS",
      "size": 40
    },
    "dataVolumes": [ {
      "volumetype": "SAS",
      "size": 100
    }],
    "publicIP": {
      "eip": { }
    },
    "billingMode": 0
  },
  "status": {
    "phase": "Active",
    "serverId": "456789abc-9368-46f3-8f29-d1a95622a568",
    "publicIP": "10.34.56.78",
  }
}
```

```
        "privateIP" : "192.168.1.23"
    }
```

Status Codes

Status Code	Description
200	Information about the specified node is successfully updated.

Error Codes

See [Error Codes](#).

4.3.5 Deleting a Node

Function

This API is used to delete a specified node.



The URL for cluster management is in the format of https://Endpoint/uri. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

DELETE /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/{node_id}

Table 4-320 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
node_id	Yes	String	Node ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Table 4-321 Query Parameters

Parameter	Mandatory	Type	Description
nodepoolScaleDown	No	String	Whether the request is delivered by the node pool. If the value is not NoScaleDown , the number of pods in the corresponding node pool is automatically updated.

Request Parameters

Table 4-322 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-323 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Node and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	NodeMetadata object	Node metadata, which is a collection of attributes.
spec	NodeSpec object	Detailed description of the node. CCE creates or updates objects by defining or updating spec .

Parameter	Type	Description
status	NodeStatus object	Node status, which is dynamically recorded. A user-defined value will not function when a node is being created or modified.

Table 4-324 NodeMetadata

Parameter	Type	Description
name	String	<p>Node name</p> <p>NOTE</p> <p>Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. If name is left empty or is not specified, the node name is generated based on the default rule, which is <i>Cluster name-Random characters</i>. Only the first 36 characters are kept for a long cluster name. If the number of nodes (count) is greater than 1, some random characters are added to the end of the entered node name according to the default rule, which is <i>User-defined name-Random characters</i>. Only the first 50 characters in the custom name are kept, followed by some random characters. Names of nodes running in clusters v1.28.1, v1.27.3, v1.25.6, v1.23.11, v1.21.12 or later support periods (.), but this configuration is not recommended.</p>
uid	String	Node ID, which is unique and automatically generated after the resource is created. A user-defined ID will not take effect.
labels	Map<String, String>	<p>CCE node label (not the native Kubernetes label).</p> <p>Labels are used to select objects that meet certain criteria. A label is a key-value pair.</p> <p>Example:</p> <pre>"labels": { "key" : "value" }</pre>

Parameter	Type	Description
annotations	Map<String, String>	<p>CCE node annotations, in key-value pairs (not the native Kubernetes annotations). Example:</p> <pre>"annotations": { "key1" : "value1", "key2" : "value2" }</pre> <p>NOTE</p> <ul style="list-style-type: none">• annotations are not used to identify or select objects. The metadata in annotations may be small or large, structured or unstructured, and may include characters that are not allowed in labels.• This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
creationTimestamp	String	Time when the object was created. The value is automatically generated after the object is created. A user-defined value will not take effect.
updateTimestamp	String	Time when the object was updated. The value is automatically generated after the object is created. A user-defined value will not take effect.

Table 4-325 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	String	The OS type of the node. For details about the supported OSs, see Node OS .

Parameter	Type	Description
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .
storage	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	NodeNicSpec object	NIC of the node
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Type	Description
taints	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example: "k8sTags": { "key": "value" }</p>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none"> Clusters of v1.25 or earlier: docker. Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-326 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-327 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-328 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-329 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-330 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-331 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-332 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-333 StorageGroups

Parameter	Type	Description
name	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-334 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">● Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.● runtime: runtime space configuration. runtimeConfig needs to be configured.● user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-335 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-336 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-337 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-338 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-339 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-340 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-341 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-342 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-343 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-344 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">Clusters earlier than v1.25: The default value is <code>docker</code>.Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-345 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/ 90%VG;kubernetesLV=vgpaas/ 10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none"> • userLV (optional): size of the user space, for example, vgpaas/20%VG. • userPath (optional): mount path of the user space, for example, /home/wqt-test. • diskType: disk type. Currently, only evs, hdd, and ssd are supported. • lvType: type of a logic volume. The value can be linear or striped. • dockerThinpool: Docker space size, for example, vgpaas/60%VG. • kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-346 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-347 NodeStatus

Parameter	Type	Description
phase	String	Node status, which is the status of a node during its lifecycle (such as installation and uninstallation) or the status of a node in a Kubernetes cluster. Options: <ul style="list-style-type: none">• Build: The node is being created.• Installing: The node is being managed.• Upgrading: The node is being upgraded.• Active: The node is running properly.• Abnormal: The node is abnormal.• Deleting: The node is being deleted.• Error: The node is faulty.
lastProbeTime	String	Last time when the node status was checked. If the cluster is in the abnormal, frozen, or intermediate state (for example, creating), the node status check may be affected. The node status that takes more than five minutes to check has no reference value.
jobID	String	ID of a creation or deletion job
serverId	String	ID of the underlying ECS or BMS node
privateIP	String	IP address in the private network segment of the primary NIC on the node
privateIPv6IP	String	IPv6 address in the private network segment of the primary NIC on the node
publicIP	String	Node EIP. If the ECS data is not synchronized in real time, you can click Sync Node Data on the console to manually update the data.
deleteStatus	DeleteStatus object	Resource status during resource deletion.

Table 4-348 DeleteStatus

Parameter	Type	Description
previous_total	Integer	Total number of existing cluster resource records when the cluster is deleted.
current_total	Integer	Latest number of resource records, which is generated based on the current cluster resource records.

Parameter	Type	Description
updated	Integer	Total number of resource records updated when the cluster is deleted.
added	Integer	Total number of resource records updated when the cluster is deleted.
deleted	Integer	Total number of resource records deleted when the cluster is deleted.

Example Requests

None

Example Responses

Status code: 200

The job for deleting a node is successfully delivered.

```
{
  "kind" : "Node",
  "apiVersion" : "v3",
  "metadata" : {
    "name" : "new-hostname",
    "uid" : "cc697ad9-9563-11e8-8ea7-0255ac106311",
    "creationTimestamp" : "2018-08-01 08:20:49.944664515 +0000 UTC",
    "updateTimestamp" : "2018-08-01 09:20:05.644032347 +0000 UTC",
    "annotations" : {
      "kubernetes.io/node-pool.id" : "az1.dc1#s1.medium#EulerOS 2.2"
    }
  },
  "spec" : {
    "flavor" : "s1.medium",
    "az" : "az1.dc1",
    "os" : "EulerOS 2.2",
    "login" : {
      "sshKey" : "KeyPair-001"
    },
    "rootVolume" : {
      "volumetype" : "SAS",
      "size" : 40
    },
    "dataVolumes" : [ {
      "volumetype" : "SAS",
      "size" : 100
    }],
    "publicIP" : {
      "eip" : {
        "bandwidth" : { }
      }
    },
    "billingMode" : 0
  },
  "status" : {
    "phase" : "Active",
    "jobID" : "661f6f7d-956c-11e8-a916-0255ac10575d",
    "serverID" : "5b504f8d-33f1-4ab7-a600-b62dac967d72",
    "privateIP" : "192.168.0.69",
    "publicIP" : "10.154.194.59"
  }
}
```

Status Codes

Status Code	Description
200	The job for deleting a node is successfully delivered.

Error Codes

See [Error Codes](#).

4.3.6 Accepting a Node

Function

This API is used to accept a node into a specified cluster.



The URL for cluster management is in the format of https://Endpoint/uri. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/add

Table 4-349 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-350 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-351 Request body parameters

Parameter	Mandatory	Type	Description
apiVersion	Yes	String	API version. The value is fixed at v3 .
kind	Yes	String	API type. The value is fixed at List .
nodeList	Yes	Array of AddNode objects	List of nodes to be managed. A maximum of 200 nodes can be managed simultaneously.

Table 4-352 AddNode

Parameter	Mandatory	Type	Description
serverID	Yes	String	Server ID. For details about how to obtain the server ID, see the ECS or BMS documentation.
spec	Yes	ReinstallNodeSpec object	Node reinstallation configuration parameters. Currently, accepted nodes cannot be added into node pools.

Table 4-353 ReinstallNodeSpec

Parameter	Mandatory	Type	Description
os	Yes	String	Operating system. If you specify a custom image, the actual OS version in the IMS image is used. Select an OS version supported by the current cluster, for example, EulerOS 2.5, CentOS 7.6, or EulerOS 2.8.
login	Yes	Login object	Node login mode. Either the key pair or password must be used for login.
name	No	String	<p>Node name.</p> <p>NOTE</p> <p>Specifying this field during reinstallation will change the node name, and the server name will change accordingly. By default, the current server name is used as the node name. Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-).</p>
serverConfig	No	ReinstallServerConfig object	Server configuration.
volumeConfig	No	ReinstallVolumeConfig object	Volume management configuration.
runtimeConfig	No	ReinstallRuntimeConfig object	Container runtime configuration.
k8sOptions	No	ReinstallK8sOptionsConfig object	Kubernetes node configuration.
lifecycle	No	NodeLifecycleConfig object	Customized lifecycle configuration of a node.

Parameter	Mandatory	Type	Description
initializedConditions	No	Array of strings	<p>Custom initialization flag. Before CCE nodes are initialized, they are tainted with node.cloudprovider.kubernetes.io/uninitialized to prevent pods from being scheduled to them.</p> <p>CCE supports custom initialization flags. After receiving the initializedConditions parameter, CCE converts the parameter value into a node label and provisions the label with the node, for example, cloudprovider.openvessel.io/inject-initialized-conditions=CCEInitial_CustomedInitial.</p> <p>After the node is labeled, its status.Conditions is polled to check whether the type of conditions has a flag name, such as CCEInitial and CustomedInitial. If all input flags exist and their status is True, the node initialization is complete and the initialization taint is removed.</p> <ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.
extendParam	No	ReinstallExtendedParam object	Extended reinstallation parameter, which is discarded.
hostnameConfig	No	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-354 Login

Parameter	Mandatory	Type	Description
sshKey	No	String	Name of the key pair used for login.

Table 4-355 UserPassword

Parameter	Mandatory	Type	Description
username	No	String	Login account. Defaults to root .
password	Yes	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@#\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-356 ReinstallServerConfig

Parameter	Mandatory	Type	Description
userTags	No	Array of UserTag objects	Cloud server labels. The key of a label must be unique. The maximum number of user-defined labels supported by CCE depends on the region. In the region that supports the least number of labels, you can still create up to 5 labels for a cloud server.
rootVolume	No	ReinstallVolumeSpec object	System disk configurations used in reinstallation.

Table 4-357 UserTag

Parameter	Mandatory	Type	Description
key	No	String	Key of the cloud server label. The value cannot start with CCE- or _type_baremetal .
value	No	String	Value of the cloud server label.

Table 4-358 ReinstallVolumeSpec

Parameter	Mandatory	Type	Description
imageID	No	String	Custom image ID.
cmkID	No	String	User master key ID. If this parameter is left blank by default, the EVS disk is not encrypted.

Table 4-359 ReinstallVolumeConfig

Parameter	Mandatory	Type	Description
lvmConfig	No	String	<p>Docker data disk configurations.</p> <p>The following is an example default configuration: <code>"lvmConfig":"dockerThinpool=vgpaas/90%VG;kubernetesLV=vgpaas/10%VG;diskType=evs;lvType=linear"</code></p> <p>The following fields are included:</p> <ul style="list-style-type: none">• userLV: size of the user space, for example, vgpaas/20%VG.• userPath: mount path of the user space, for example, /home/wqt-test.• diskType: disk type. Currently, only evs, hdd, and ssd are supported.• lvType: type of a logic volume. The value can be linear or striped.• dockerThinpool: Docker space size, for example, vgpaas/60%VG.• kubernetesLV: kubelet space size, for example, vgpaas/20%VG.
storage	No	Storage object	<p>Disk initialization management parameter.</p> <p>This parameter is complex to configure. For details, see Attaching Disks to a Node.</p> <p>If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later.</p> <p>NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.</p>

Table 4-360 Storage

Parameter	Mandatory	Type	Description
storageSelectors	Yes	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
storageGroups	Yes	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-361 StorageSelectors

Parameter	Mandatory	Type	Description
name	Yes	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
storageType	Yes	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
matchLabels	No	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-362 matchLabels

Parameter	Mandatory	Type	Description
size	No	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100

Parameter	Mandatory	Type	Description
volumeType	No	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.
metadataEncrypted	No	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkid	No	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	No	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-363 StorageGroups

Parameter	Mandatory	Type	Description
name	Yes	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	No	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Yes	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.

Parameter	Mandatory	Type	Description
virtualSpaces	Yes	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-364 VirtualSpace

Parameter	Mandatory	Type	Description
name	Yes	String	Name of a virtualSpace. <ul style="list-style-type: none">• Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.• runtime: runtime space configuration. runtimeConfig needs to be configured.• user: user space configuration. lvmConfig needs to be configured.
size	Yes	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	No	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	No	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-365 LVMConfig

Parameter	Mandatory	Type	Description
lvType	Yes	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	No	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-366 RuntimeConfig

Parameter	Mandatory	Type	Description
lvType	Yes	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-367 ReinstallRuntimeConfig

Parameter	Mandatory	Type	Description
dockerBaseSize	No	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
runtime	No	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Table 4-368 Runtime

Parameter	Mandatory	Type	Description
name	No	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is docker.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is docker; for nodes running other OSs, the default container runtime is containerd.

Table 4-369 ReinstallK8sOptionsConfig

Parameter	Mandatory	Type	Description
labels	No	Map<String, String>	Defined in key-value pairs. A maximum of 20 key-value pairs are allowed. <ul style="list-style-type: none">• Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-key• Value: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. <p>Example:</p> <pre>"k8sTags": { "key": "value" }</pre>

Parameter	Mandatory	Type	Description
taints	No	Array of Taint objects	<p>Taints can be added for anti-affinity when creating nodes. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule"}, { "key": "looks", "value": "bad", "effect": "NoSchedule"}]</pre>
maxPods	No	Integer	Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256. This limit prevents the node from being overloaded of pods.

Table 4-370 Taint

Parameter	Mandatory	Type	Description
key	Yes	String	Key.

Parameter	Mandatory	Type	Description
value	No	String	Value.
effect	Yes	String	Effect.

Table 4-371 NodeLifecycleConfig

Parameter	Mandatory	Type	Description
preInstall	No	String	Pre-installation script. NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)
postInstall	No	String	Post-installation script. NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)

Table 4-372 ReinstallExtendParam

Parameter	Mandatory	Type	Description
alpha.cce/ NodeImageID	No	String	(Discarded) ID of the user image to run the target OS. Specifying this parameter is equivalent to specifying imageID in ReinstallVolumeSpec . The original value will be overwritten.

Table 4-373 HostnameConfig

Parameter	Mandatory	Type	Description
type	Yes	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Response Parameters

Status code: 200

Table 4-374 Response body parameters

Parameter	Type	Description
jobid	String	Job ID returned after the job is delivered. The job ID can be used to query the job execution status.

Example Requests

Add a node running EulerOS 2.5 to a cluster.

```
POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/add

{
  "kind" : "List",
  "apiVersion" : "v3",
  "nodeList" : [ {
    "serverID" : "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx",
    "spec" : {
      "name" : "my-ecs-0001",
      "os" : "EulerOS 2.5",
      "login" : {
        "sshKey" : "KeyPair-001"
      }
    }
  } ]
}
```

Example Responses

Status code: 200

The job for accepting a node into a specified cluster is successfully delivered.

```
{
  "jobid" : "2ec9b78d-9368-46f3-8f29-d1a95622a568"
}
```

Status Codes

Status Code	Description
200	The job for accepting a node into a specified cluster is successfully delivered.

Error Codes

See [Error Codes](#).

4.3.7 Resetting a Node

Function

This API is used to reset a node in a specified cluster.



NOTE

The URL for cluster management is in the format of `https://Endpoint/uri`. In the URL, `uri` indicates the resource path, that is, the path for API access.

URI

```
POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/reset
```

Table 4-375 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-376 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-377 Request body parameters

Parameter	Mandatory	Type	Description
apiVersion	Yes	String	API version. The value is fixed at v3 .
kind	Yes	String	API type. The value is fixed at List .
nodeList	Yes	Array of ResetNode objects	List of nodes to be reset. A maximum of 200 nodes can be reset at a time.

Table 4-378 ResetNode

Parameter	Mandatory	Type	Description
nodeID	Yes	String	Node ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
spec	Yes	ReinstallNodeSpec object	Node reinstallation configuration parameters. Nodes in a node pool cannot be specified externally. These nodes will be reinstalled based on the node pool settings. By default, this parameter is mandatory for nodes in a node pool.

Table 4-379 ReinstallNodeSpec

Parameter	Mandatory	Type	Description
os	Yes	String	Operating system. If you specify a custom image, the actual OS version in the IMS image is used. Select an OS version supported by the current cluster, for example, EulerOS 2.5, CentOS 7.6, or EulerOS 2.8.
login	Yes	Login object	Node login mode. Either the key pair or password must be used for login.
name	No	String	Node name. NOTE Specifying this field during reinstallation will change the node name, and the server name will change accordingly. By default, the current server name is used as the node name. Enter 1 to 56 characters starting with a letter and not ending with a hyphen (-).
serverConfig	No	ReinstallServerConfig object	Server configuration.

Parameter	Mandatory	Type	Description
volumeConfig	No	ReinstallVolumeConfig object	Volume management configuration.
runtimeConfig	No	ReinstallRuntimeConfig object	Container runtime configuration.
k8sOptions	No	ReinstallK8sOptionsConfig object	Kubernetes node configuration.
lifecycle	No	NodeLifecycleConfig object	Customized lifecycle configuration of a node.
initializedConditions	No	Array of strings	<p>Custom initialization flag. Before CCE nodes are initialized, they are tainted with node.cloudprovider.kubernetes.io/uninitialized to prevent pods from being scheduled to them.</p> <p>CCE supports custom initialization flags. After receiving the initializedConditions parameter, CCE converts the parameter value into a node label and provisions the label with the node, for example, cloudprovider.openvessel.io/inject-initialized-conditions=CCEInitial_CustomedInitial.</p> <p>After the node is labeled, its status.Conditions is polled to check whether the type of conditions has a flag name, such as CCEInitial and CustomedInitial. If all input flags exist and their status is True, the node initialization is complete and the initialization taint is removed.</p> <ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.

Parameter	Mandatory	Type	Description
extendParam	No	ReinstallExtendedParam object	Extended reinstallation parameter, which is discarded.
hostnameConfig	No	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-380 Login

Parameter	Mandatory	Type	Description
sshKey	No	String	Name of the key pair used for login.

Table 4-381 UserPassword

Parameter	Mandatory	Type	Description
username	No	String	Login account. Defaults to root .
password	Yes	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@#\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-382 ReinstallServerConfig

Parameter	Mandatory	Type	Description
userTags	No	Array of UserTag objects	Cloud server labels. The key of a label must be unique. The maximum number of user-defined labels supported by CCE depends on the region. In the region that supports the least number of labels, you can still create up to 5 labels for a cloud server.
rootVolume	No	ReinstallVolumeSpec object	System disk configurations used in reinstallation.

Table 4-383 UserTag

Parameter	Mandatory	Type	Description
key	No	String	Key of the cloud server label. The value cannot start with CCE- or _type_baremetal .
value	No	String	Value of the cloud server label.

Table 4-384 ReinstallVolumeSpec

Parameter	Mandatory	Type	Description
imageID	No	String	Custom image ID.
cmkID	No	String	User master key ID. If this parameter is left blank by default, the EVS disk is not encrypted.

Table 4-385 ReinstallVolumeConfig

Parameter	Mandatory	Type	Description
lvmConfig	No	String	<p>Docker data disk configurations.</p> <p>The following is an example default configuration: "lvmConfig":"dockerThinpool=vgpaas/90%VG;kubernetesLV=vgpaas/10%VG;diskType=evs;lvType=linear"</p> <p>The following fields are included:</p> <ul style="list-style-type: none">• userLV: size of the user space, for example, vgpaas/20%VG.• userPath: mount path of the user space, for example, /home/wqt-test.• diskType: disk type. Currently, only evs, hdd, and ssd are supported.• lvType: type of a logic volume. The value can be linear or striped.• dockerThinpool: Docker space size, for example, vgpaas/60%VG.• kubernetesLV: kubelet space size, for example, vgpaas/20%VG.
storage	No	Storage object	<p>Disk initialization management parameter.</p> <p>This parameter is complex to configure. For details, see Attaching Disks to a Node.</p> <p>If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later.</p> <p>NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.</p>

Table 4-386 Storage

Parameter	Mandatory	Type	Description
storageSelectors	Yes	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
storageGroups	Yes	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-387 StorageSelectors

Parameter	Mandatory	Type	Description
name	Yes	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
storageType	Yes	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
matchLabels	No	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-388 matchLabels

Parameter	Mandatory	Type	Description
size	No	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100

Parameter	Mandatory	Type	Description
volumeType	No	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.
metadataEncrypted	No	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkid	No	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	No	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-389 StorageGroups

Parameter	Mandatory	Type	Description
name	Yes	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	No	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Yes	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.

Parameter	Mandatory	Type	Description
virtualSpaces	Yes	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-390 VirtualSpace

Parameter	Mandatory	Type	Description
name	Yes	String	Name of a virtualSpace. <ul style="list-style-type: none">• Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.• runtime: runtime space configuration. runtimeConfig needs to be configured.• user: user space configuration. lvmConfig needs to be configured.
size	Yes	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	No	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	No	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-391 LVMConfig

Parameter	Mandatory	Type	Description
lvType	Yes	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	No	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-392 RuntimeConfig

Parameter	Mandatory	Type	Description
lvType	Yes	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-393 ReinstallRuntimeConfig

Parameter	Mandatory	Type	Description
dockerBaseSize	No	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
runtime	No	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Table 4-394 Runtime

Parameter	Mandatory	Type	Description
name	No	String	<p>Container runtime. Default value:</p> <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is docker.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is docker; for nodes running other OSs, the default container runtime is containerd.

Table 4-395 ReinstallK8sOptionsConfig

Parameter	Mandatory	Type	Description
labels	No	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">• Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-key• Value: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. <p>Example:</p> <pre>"k8sTags": { "key": "value" }</pre>

Parameter	Mandatory	Type	Description
taints	No	Array of Taint objects	<p>Taints can be added for anti-affinity when creating nodes. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule"}, { "key": "looks", "value": "bad", "effect": "NoSchedule"}]</pre>
maxPods	No	Integer	Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256. This limit prevents the node from being overloaded of pods.

Table 4-396 Taint

Parameter	Mandatory	Type	Description
key	Yes	String	Key.

Parameter	Mandatory	Type	Description
value	No	String	Value.
effect	Yes	String	Effect.

Table 4-397 NodeLifecycleConfig

Parameter	Mandatory	Type	Description
preInstall	No	String	Pre-installation script. NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)
postInstall	No	String	Post-installation script. NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)

Table 4-398 ReinstallExtendParam

Parameter	Mandatory	Type	Description
alpha.cce/ NodeImageID	No	String	(Discarded) ID of the user image to run the target OS. Specifying this parameter is equivalent to specifying imageID in ReinstallVolumeSpec . The original value will be overwritten.

Table 4-399 HostnameConfig

Parameter	Mandatory	Type	Description
type	Yes	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Response Parameters

Status code: 200

Table 4-400 Response body parameters

Parameter	Type	Description
jobid	String	Job ID returned after the job is delivered. The job ID can be used to query the job execution status.

Example Requests

- Reset the nodes running EulerOS 2.5 in the default node pool.

```
POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/reset
```

```
{  
    "kind" : "List",  
    "apiVersion" : "v3",  
    "nodeList" : [ {  
        "nodeID" : "yyyyyyyy-yyyy-yyyy-yyyy-yyyyyyyyyyyy",  
        "spec" : {  
            "name" : "my-ecs-0001",  
            "os" : "EulerOS 2.5",  
            "login" : {  
                "sshKey" : "KeyPair-001"  
            }  
        }  
    } ]  
}
```

- Reset a node in a node pool (invalid spec).

```
POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/reset
```

```
{  
    "kind" : "List",  
    "apiVersion" : "v3",  
    "nodeList" : [ {  
        "nodeID" : "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx",  
        "spec" : {  
            "name" : "my-ecs-0001",  
            "os" : "EulerOS 2.5",  
            "login" : {  
                "sshKey" : "KeyPair-001"  
            }  
        }  
    } ]  
}
```

Example Responses

Status code: 200

The job for resetting a node in a specified cluster is successfully delivered.

```
{  
    "jobid" : "2ec9b78d-9368-46f3-8f29-d1a95622a568"  
}
```

Status Codes

Status Code	Description
200	The job for resetting a node in a specified cluster is successfully delivered.

Error Codes

See [Error Codes](#).

4.3.8 Removing a Node

Function

This API is used to remove a node from a specified cluster.



The URL for cluster management is in the format of https://Endpoint/uri. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/operation/remove

Table 4-401 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-402 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-403 Request body parameters

Parameter	Mandatory	Type	Description
apiVersion	No	String	API version. The value is fixed at v3 .
kind	No	String	API type. The value is fixed at RemoveNodesTask .
spec	Yes	RemoveNodeSpec object	Configuration information.
status	No	TaskStatus object	Job status.

Table 4-404 RemoveNodesSpec

Parameter	Mandatory	Type	Description
login	Yes	Login object	Node login mode. Either the key pair or password must be used for login.
nodes	Yes	Array of NodeItem objects	List of nodes to be removed. A maximum of 200 nodes can be removed at a time.

Table 4-405 Login

Parameter	Mandatory	Type	Description
sshKey	No	String	Name of the key pair used for login.

Table 4-406 UserPassword

Parameter	Mandatory	Type	Description
username	No	String	Login account. Defaults to root .

Parameter	Mandatory	Type	Description
password	Yes	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@#\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-407 NodeItem

Parameter	Mandatory	Type	Description
uid	Yes	String	Node ID.

Table 4-408 TaskStatus

Parameter	Mandatory	Type	Description
jobID	No	String	Job ID, which is used by the caller to query the job progress.

Response Parameters

Status code: 200

Table 4-409 Response body parameters

Parameter	Type	Description
apiVersion	String	API version. The value is fixed at v3 .
kind	String	API type. The value is fixed at RemoveNodesTask .
spec	RemoveNodesSpec object	Configuration information.
status	TaskStatus object	Job status.

Table 4-410 RemoveNodesSpec

Parameter	Type	Description
login	Login object	Node login mode. Either the key pair or password must be used for login.
nodes	Array of NodeItem objects	List of nodes to be removed. A maximum of 200 nodes can be removed at a time.

Table 4-411 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-412 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .

Parameter	Type	Description
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:.,/?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-413 NodeItem

Parameter	Type	Description
uid	String	Node ID.

Table 4-414 TaskStatus

Parameter	Type	Description
jobID	String	Job ID, which is used by the caller to query the job progress.

Example Requests

Removing a Node

```
PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/operation/remove

{
  "spec": {
    "login": {
      "sshKey": "KeyPair-001"
    },
    "nodes": [
      {
        "uid": "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx"
      },
      {
        "uid": "yyyyyyyy-yyyy-yyyy-yyyy-yyyyyyyyyyyy"
      }
    ]
  }
}
```

Example Responses

Status code: 200

The job for removing a node in a specified cluster is successfully delivered.

```
{  
  "spec": {  
    "login": {  
      "sshKey": "KeyPair-001"  
    },  
    "nodes": [ {  
      "uid": "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxx"  
    }, {  
      "uid": "yyyyyyyy-yyyy-yyyy-yyyy-yyyyyyyyyy"  
    } ]  
  },  
  "status": {  
    "jobID": "2ec9b78d-9368-46f3-8f29-d1a95622a568"  
  }  
}
```

Status Codes

Status Code	Description
200	The job for removing a node in a specified cluster is successfully delivered.

Error Codes

See [Error Codes](#).

4.3.9 Migrating a Node

Function

This API is used to migrate a node from a specified cluster to another cluster. The node can be migrated only between different clusters in the same VPC and project, and the cluster types before and after the migration must be the same.



The URL for cluster management is in the format of **https://Endpoint/uri**, where **uri** indicates the resource path for API access.

Constraints

- Data can be migrated only between clusters in the same VPC and project.
- Data cannot be migrated between CCE Turbo clusters and CCE standard clusters.
- Data cannot be migrated between DEC and non-DEC clusters.
- Data cannot be migrated between clusters with IPv6 enabled and clusters without IPv6 enabled.

- Data can be migrated only to the default node pool of the target cluster.

URI

PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/operation/migrateto/{target_cluster_id}

Table 4-415 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
target_cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-416 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-417 Request body parameters

Parameter	Mandatory	Type	Description
apiVersion	No	String	API version. The value is fixed at v3 .

Parameter	Mandatory	Type	Description
kind	No	String	API type. The value is fixed at MigrateNodesTask .
spec	Yes	MigrateNodeSpec object	Configuration data.
status	No	TaskStatus object	Job status.

Table 4-418 MigrateNodesSpec

Parameter	Mandatory	Type	Description
os	Yes	String	Operating system type, which must be accurate to the version number. When alpha.cce/NodeImageID is specified, the value of os must be the same as the OS of the custom image.
extendParam	No	MigrateNodeExtendParam object	Extended parameters for node migration.
login	Yes	Login object	Node login mode. Either the key pair or password must be used for login.
runtime	No	Runtime object	Container runtime
nodes	Yes	Array of NodeItem objects	List of nodes to be migrated. A maximum of 200 nodes can be migrated at a time.

Table 4-419 MigrateNodeExtendParam

Parameter	Mandatory	Type	Description
maxPods	No	Integer	Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256. This limit prevents the node from being overloaded of pods.

Parameter	Mandatory	Type	Description
DockerLVMConfigOverride	No	String	<p>Docker data disk configurations.</p> <p>The disk type of the nodes to be migrated must be the same as that specified during node creation (that is, the value of diskType in DockerLVMConfigOverride must be the same as that specified during node creation). Ensure that the disk types of the nodes selected for a single API call are the same.</p> <p>The following is the default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/90%VG;kubernetesLV=vgpaas/10%VG;diskType=evs;lvType=linear"</pre> <p>The configuration contains the following fields:</p> <ul style="list-style-type: none">• userLV (optional): size of the user space, for example, vgpaas/20%VG.• (Optional) userPath: mount path of the user space, for example, /home/wqt-test.• diskType: specifies the disk type. Currently, only evs, hdd, and ssd are supported.• lvType: type of the logical volume. Currently, the value can be linear or striped. For example, striped.• dockerThinpool: Docker disk size, for example, vgpaas/60%VG.• kubernetesLV: Kubelet space size, for example, vgpaas/20%VG.
alpha.cce/preInstall	No	String	<p>Pre-installation script.</p> <p>NOTE</p> <p>The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>

Parameter	Mandatory	Type	Description
alpha.cce/ postInstall	No	String	Post-installation script. NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)
alpha.cce/ NodeImageID	No	String	ID of the user image to run the target OS. When alpha.cce/NodeImageID is specified, the value of os must be the same as the OS of the custom image.

Table 4-420 Login

Parameter	Mandatory	Type	Description
sshKey	No	String	Name of the key pair used for login.

Table 4-421 UserPassword

Parameter	Mandatory	Type	Description
username	No	String	Login account. Defaults to root .

Parameter	Mandatory	Type	Description
password	Yes	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@#\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-422 Runtime

Parameter	Mandatory	Type	Description
name	No	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is docker.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is docker; for nodes running other OSs, the default container runtime is containerd.

Table 4-423 NodeItem

Parameter	Mandatory	Type	Description
uid	Yes	String	Node ID.

Table 4-424 TaskStatus

Parameter	Mandatory	Type	Description
jobID	No	String	Job ID, which is used by the caller to query the job progress.

Response Parameters

Status code: 200

Table 4-425 Response body parameters

Parameter	Type	Description
apiVersion	String	API version. The value is fixed at v3 .
kind	String	API type. The value is fixed at MigrateNodesTask .
spec	MigrateNodesSpec object	Configuration data.
status	TaskStatus object	Job status.

Table 4-426 MigrateNodesSpec

Parameter	Type	Description
os	String	Operating system type, which must be accurate to the version number. When alpha.cce/NodeImageID is specified, the value of os must be the same as the OS of the custom image.
extendParam	MigrateNodesExtendParam object	Extended parameters for node migration.
login	Login object	Node login mode. Either the key pair or password must be used for login.

Parameter	Type	Description
runtime	Runtime object	Container runtime
nodes	Array of NodeItem objects	List of nodes to be migrated. A maximum of 200 nodes can be migrated at a time.

Table 4-427 MigrateNodeExtendParam

Parameter	Type	Description
maxPods	Integer	Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256. This limit prevents the node from being overloaded of pods.
DockerLVMConfigOverride	String	<p>Docker data disk configurations. The disk type of the nodes to be migrated must be the same as that specified during node creation (that is, the value of diskType in DockerLVMConfigOverride must be the same as that specified during node creation). Ensure that the disk types of the nodes selected for a single API call are the same.</p> <p>The following is the default configuration: "DockerLVMConfigOverride":"dockerThinpool=vgpaas/90%VG;kubernetesLV=vgpaas/10%VG;diskType=evs;lvType=linear"</p> <p>The configuration contains the following fields:</p> <ul style="list-style-type: none">• userLV (optional): size of the user space, for example, vgpaas/20%VG.• (Optional) userPath: mount path of the user space, for example, /home/wqt-test.• diskType: specifies the disk type. Currently, only evs, hdd, and ssd are supported.• lvType: type of the logical volume. Currently, the value can be linear or striped. For example, striped.• dockerThinpool: Docker disk size, for example, vgpaas/60%VG.• kubernetesLV: Kubelet space size, for example, vgpaas/20%VG.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>

Parameter	Type	Description
alpha.cce/ postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/ NodeImageID	String	<p>ID of the user image to run the target OS.</p> <p>When alpha.cce/NodeImageID is specified, the value of os must be the same as the OS of the custom image.</p>

Table 4-428 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-429 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_-=+[{}]:.,/?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-430 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">Clusters earlier than v1.25: The default value is docker.Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is docker; for nodes running other OSs, the default container runtime is containerd.

Table 4-431 NodeItem

Parameter	Type	Description
uid	String	Node ID.

Table 4-432 TaskStatus

Parameter	Type	Description
jobID	String	Job ID, which is used by the caller to query the job progress.

Example Requests

- Migrate a node running EulerOS 2.5 to another cluster.

```
PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/operation/migrateto/{target_cluster_id}

{
  "spec" : {
    "os" : "EulerOS 2.5",
    "login" : {
      "sshKey" : "KeyPair-001"
    },
    "nodes" : [ {
      "uid" : "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx"
    }, {
      "uid" : "yyyyyyyy-yyyy-yyyy-yyyy-yyyyyyyyyyyy"
    }
  }
}
```

- Migrate a node running EulerOS 2.5 and created using a specified image ID to another cluster.

```
PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/operation/migrateto/{target_cluster_id}

{
  "spec" : {
    "os" : "EulerOS 2.5",
    "extendParam" : {

```

```
        "alpha.cce/NodeImageID" : "cc697ad7-9563-11e8-8ea7-0255ac106311"
    },
    "login" : {
        "sshKey" : "KeyPair-001"
    },
    "nodes" : [ {
        "uid" : "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx"
    }, {
        "uid" : "yyyyyyyy-yyyy-yyyy-yyyy-yyyyyyyyyyyy"
    } ]
}
```

Example Responses

Status code: 200

The job for migrating a node from a specified cluster to another cluster is successfully delivered.

```
{
    "spec" : {
        "os" : "EulerOS 2.5",
        "login" : {
            "sshKey" : "KeyPair-001"
        },
        "runtime" : {
            "name" : "docker"
        },
        "nodes" : [ {
            "uid" : "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx"
        }, {
            "uid" : "yyyyyyyy-yyyy-yyyy-yyyy-yyyyyyyyyyyy"
        } ]
    },
    "status" : {
        "jobID" : "2ec9b78d-9368-46f3-8f29-d1a95622a568"
    }
}
```

Status Codes

Status Code	Description
200	The job for migrating a node from a specified cluster to another cluster is successfully delivered.

Error Codes

See [Error Codes](#).

4.4 Node Pool Management

4.4.1 Creating a Node Pool

Function

This API is used to create a node pool in a specified cluster. This API can be called only when the cluster is in the available, scaling-out, or scaling-in state.

When creating a node pool in a cluster of v1.21, you can bind security groups to the node pool. A maximum of five security groups can be bound to a node pool.

After the security groups of a node pool are updated, the update takes effect only for newly created pods. You are advised to evict the original pods on the node.

NOTE

If there is no cluster, [create one](#). The URL for cluster management is in the format of **https://Endpoint/uri**. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools

Table 4-433 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-434 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-435 Request body parameters

Parameter	Mandatory	Type	Description
kind	Yes	String	API type. The value is fixed at NodePool .
apiVersion	Yes	String	API version. The value is fixed at v3 .
metadata	Yes	NodePoolMetadata object	Metadata information of the node pool
spec	Yes	NodePoolSpec object	Node pool specifications
status	No	NodePoolStatus object	Node pool status

Table 4-436 NodePoolMetadata

Parameter	Mandatory	Type	Description
name	Yes	String	Node pool name. NOTE Naming rules: Enter 1 to 50 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. <ul style="list-style-type: none">• You cannot create node pools named DefaultPool.
uid	No	String	UID of the node pool. The value is automatically generated after the object is updated. A user-defined value will not take effect.
annotations	No	Map<String, String>	Annotations of a node pool in key-value pairs. This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
updateTimestamp	No	String	Update time.
creationTimestamp	No	String	Creation time.

Table 4-437 NodePoolSpec

Parameter	Mandatory	Type	Description
type	No	String	<p>Node pool type. If this parameter is left blank, the value vm is used by default.</p> <ul style="list-style-type: none">• vm: ECS• ElasticBMS: C6 general computing-plus BMS. An example flavor is c6.22xlarge.2.physical.• pm: BMS
nodeTemplate	Yes	NodeSpec object	Detailed parameters of the node pool template.
initialNodeCount	No	Integer	Initial number of nodes for the node pool. When queried, the value is the number of target nodes in the node pool.
autoscaling	No	NodePoolNodeAutoscaling object	Auto scaling parameters
nodeManagement	No	NodeManagement object	Node management configuration
podSecurityGroups	No	Array of SecurityID objects	Security group configuration. This parameter is available only for CCE Turbo clusters.
customSecurityGroups	No	Array of strings	<p>Custom security group settings for a node pool. New nodes scaled out in a node pool can be bound to a specified security group.</p> <ul style="list-style-type: none">• Specifying no security group ID will add the new nodes to the default security group of the worker nodes.• Specifying a valid security group ID will put new nodes in that security group.• When specifying a security group, do not modify the rules of the port on which CCE running depends.

Table 4-438 NodeSpec

Parameter	Mandatory	Type	Description
flavor	Yes	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	Yes	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	No	String	The OS type of the node. For details about the supported OSs, see Node OS . NOTE <ul style="list-style-type: none">The system automatically selects the supported OS based on the cluster version. If the current cluster does not support the OS, an error will be reported.If alpha.cce/NodeImageID in extendParam is specified during node creation, you do not need to configure this parameter.This parameter is mandatory when creating a node pool.
login	Yes	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Yes	Volume object	Information about disks on the node
dataVolumes	Yes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .

Parameter	Mandatory	Type	Description
storage	No	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	No	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	No	NodeNicSpec object	NIC of the node
count	No	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	No	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Mandatory	Type	Description
taints	No	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{"key": "status", "value": "unavailable", "effect": "NoSchedule"}, {"key": "looks", "value": "bad", "effect": "NoSchedule"}]</pre>

Parameter	Mandatory	Type	Description
k8sTags	No	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"k8sTags": { "key": "value" }</pre>
ecsGroupId	No	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>

Parameter	Mandatory	Type	Description
dedicatedHostId	No	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>
userTags	No	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	No	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Mandatory	Type	Description
initializedConditions	No	Array of strings	<p>Custom initialization flag, which is left blank by default. Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.

Parameter	Mandatory	Type	Description
			<p>2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.</p> <ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).
extendParam	No	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	No	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-439 Login

Parameter	Mandatory	Type	Description
sshKey	No	String	Name of the key pair used for login.

Table 4-440 UserPassword

Parameter	Mandatory	Type	Description
username	No	String	Login account. Defaults to root .

Parameter	Mandatory	Type	Description
password	Yes	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@#\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-441 Volume

Parameter	Mandatory	Type	Description
size	Yes	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 - Value range for data disks: 100 to 32768
volumetype	Yes	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk SATA disks have been removed from EVS. You can find them attached only on existing nodes.

Parameter	Mandatory	Type	Description
extendParam	No	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	No	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	No	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	No	Boolean	<ul style="list-style-type: none"> Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created. If the node pool type is ElasticBMS, this field must be set to true. If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	No	VolumeMeta data object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-442 VolumeMetadata

Parameter	Mandatory	Type	Description
_system_encrypted	No	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.
_system_cm_kid	No	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-443 Storage

Parameter	Mandatory	Type	Description
storageSelectors	Yes	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
storageGroups	Yes	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-444 StorageSelectors

Parameter	Mandatory	Type	Description
name	Yes	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.

Parameter	Mandatory	Type	Description
storageType	Yes	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
matchLabels	No	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-445 matchLabels

Parameter	Mandatory	Type	Description
size	No	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
volumeType	No	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.
metadataEncrypted	No	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkid	No	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	No	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-446 StorageGroups

Parameter	Mandatory	Type	Description
name	Yes	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	No	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Yes	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Yes	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-447 VirtualSpace

Parameter	Mandatory	Type	Description
name	Yes	String	Name of a virtualSpace. <ul style="list-style-type: none">• Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.• runtime: runtime space configuration. runtimeConfig needs to be configured.• user: user space configuration. lvmConfig needs to be configured.
size	Yes	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	No	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	No	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-448 LVMConfig

Parameter	Mandatory	Type	Description
lvType	Yes	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Parameter	Mandatory	Type	Description
path	No	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-449 RuntimeConfig

Parameter	Mandatory	Type	Description
lvType	Yes	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-450 NodePublicIP

Parameter	Mandatory	Type	Description
ids	No	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	No	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	No	NodeEIPSpec object	EIP configuration.

Table 4-451 NodeEIPSpec

Parameter	Mandatory	Type	Description
iptype	Yes	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	No	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-452 NodeBandwidth

Parameter	Mandatory	Type	Description
chargemode	No	String	<p>Bandwidth billing mode.</p> <ul style="list-style-type: none">If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.If the field value is traffic, the billing is based on traffic.If the value is out of the preceding options, the cloud server will fail to be created. <p>NOTE</p> <ul style="list-style-type: none">Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.
size	No	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.

Parameter	Mandatory	Type	Description
sharetype	No	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-453 NodeNicSpec

Parameter	Mandatory	Type	Description
primaryNic	No	NicSpec object	Description of the primary NIC.
extNics	No	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-454 NicSpec

Parameter	Mandatory	Type	Description
subnetId	No	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	No	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.

Parameter	Mandatory	Type	Description
ipBlock	No	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-455 Taint

Parameter	Mandatory	Type	Description
key	Yes	String	Key.
value	No	String	Value.
effect	Yes	String	Effect.

Table 4-456 UserTag

Parameter	Mandatory	Type	Description
key	No	String	Key of the cloud server label. The value cannot start with CCE- or _type_baremetal .
value	No	String	Value of the cloud server label.

Table 4-457 Runtime

Parameter	Mandatory	Type	Description
name	No	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is docker.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is docker; for nodes running other OSs, the default container runtime is containerd.

Table 4-458 NodeExtendParam

Parameter	Mandatory	Type	Description
ecs:performancetype	No	String	ECS flavor types. This field is returned in the response.
maxPods	No	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256. This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>

Parameter	Mandatory	Type	Description
DockerLVMConfigOverride	No	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.)</p> <p>Example default configuration: "DockerLVMConfigOverride":"dockerThinpool=vgpaas/90%VG;kubernetesLV=vgpaas/10%VG;diskType=evs;lvType=linear"</p> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none">• userLV (optional): size of the user space, for example, vgpaas/20%VG.• userPath (optional): mount path of the user space, for example, /home/wqt-test.• diskType: disk type. Currently, only evs, hdd, and ssd are supported.• lvType: type of a logic volume. The value can be linear or striped.• dockerThinpool: Docker space size, for example, vgpaas/60%VG.• kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Mandatory	Type	Description
dockerBaseSize	No	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	No	String	Public key of a node.
alpha.cce/preInstall	No	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	No	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	No	String	This parameter is required when a custom image is used to create a BMS node.

Parameter	Mandatory	Type	Description
chargingMode	No	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	No	String	Name of an agency An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.
kubeReservedMem	No	Integer	Reserved node memory, which is reserved for Kubernetes components.
systemReservedMem	No	Integer	Reserved node memory, which is reserved for system components.
init-node-password	No	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-459 HostnameConfig

Parameter	Mandatory	Type	Description
type	Yes	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-460 NodePoolNodeAutoscaling

Parameter	Mandatory	Type	Description
enable	No	Boolean	Whether to enable auto scaling.
minNodeCount	No	Integer	Minimum number of nodes allowed if auto scaling is enabled. The value cannot be greater than the maximum number of nodes allowed by the cluster specifications.

Parameter	Mandatory	Type	Description
maxNodeCount	No	Integer	Maximum number of nodes allowed if auto scaling is enabled. This value must be greater than or equal to the value of minNodeCount and cannot exceed the maximum number of nodes in the cluster specifications.
scaleDownCooldownTime	No	Integer	Interval between two scaling operations, in minutes. During this period, nodes added after a scale-up will not be deleted.
priority	No	Integer	Weight of a node pool. A node pool with a higher weight has a higher priority during scaling.

Table 4-461 NodeManagement

Parameter	Mandatory	Type	Description
serverGroupReference	No	String	Cloud server group ID. If this field is specified, all nodes in the node pool will be created in this group. The group ID can be specified only when you create the node pool and cannot be modified. When you specify a cloud server group, the number of nodes in the node pool cannot exceed the group quota.

Table 4-462 SecurityID

Parameter	Mandatory	Type	Description
id	No	String	Security group ID

Table 4-463 NodePoolStatus

Parameter	Mandatory	Type	Description
currentNode	No	Integer	Total number of nodes in the current node pool (excluding the nodes that are being deleted)
creatingNode	No	Integer	Number of nodes in the creation process in the node pool
deletingNode	No	Integer	Number of nodes being deleted in the current node pool.

Parameter	Mandatory	Type	Description
phase	No	String	<p>Node pool status.</p> <ul style="list-style-type: none">• Null: available (the number of current nodes in the node pool has reached the expected value, and no node scaling is being performed.)• Synchronizing: scaling in progress (the number of current nodes in the node pool does not reach the expected value and no node scaling is being performed.)• Synchronized: pending scaling (the number of current nodes in the node pool does not reach the expected value, or node scaling is being performed.)• SoldOut: The node pool cannot be scaled out. (This field is used in multiple scenarios, for example, resources in the node pool have been sold out or the resource quota is insufficient.) <p>NOTE</p> <p>This node pool status has been discarded and is reserved only for compatibility. You are not advised to use it. The replacements are as follows:</p> <ul style="list-style-type: none">• Node pool scaling status: You can obtain accurate status of the current node pool based on parameters such as currentNode, creatingNode, or deletingNode.• Node pool scale-out: You can use conditions to obtain the detailed status of a node pool. Scalable can replace SoldOut.• Deleting: The object is being deleted.• Error: An error occurs.

Parameter	Mandatory	Type	Description
jobId	No	String	ID of a job executed on the node pool. This field is available only when the node pool is being deleted.
conditions	No	Array of NodePoolCondition objects	Node pool status details. For details, see the definition of Condition .

Table 4-464 NodePoolCondition

Parameter	Mandatory	Type	Description
type	No	String	Condition type. The options are as follows: <ul style="list-style-type: none">• Scalable: whether a node pool can be scaled. If the status is False, node pool scaling will not be triggered again.• QuotaInsufficient: Quotas on which node pool scaling depends are insufficient, affecting the node pool scaling status.• ResourceInsufficient: Resources on which node pool scaling depends are insufficient, affecting the node pool scaling status.• UnexpectedError: The node pool fails to be scaled out due to unexpected reasons, affecting the node pool scaling status.• Error: A node pool error occurs. A common trigger is deletion failure.
status	No	String	Current status of Condition . The options are as follows: <ul style="list-style-type: none">• "True"• "False"
lastProbeTime	No	String	Time when the status was last checked

Parameter	Mandatory	Type	Description
lastTransitTime	No	String	Time when the status was last changed
reason	No	String	Reason why the status was last changed
message	No	String	Detailed condition description

Response Parameters

Status code: 201

Table 4-465 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at NodePool .
apiVersion	String	API version. The value is fixed at v3 .
metadata	NodePoolMetadata object	Metadata of the node pool.
spec	NodePoolSpec object	Node pool specifications.
status	CreateNodePoolStatus object	Node pool status.

Table 4-466 NodePoolMetadata

Parameter	Type	Description
name	String	Node pool name. NOTE Naming rules: Enter 1 to 50 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed. <ul style="list-style-type: none">• You cannot create node pools named DefaultPool.
uid	String	UID of the node pool. The value is automatically generated after the object is updated. A user-defined value will not take effect.

Parameter	Type	Description
annotations	Map<String, String>	Annotations of a node pool in key-value pairs. This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
updateTimestamp	String	Update time.
creationTimestamp	String	Creation time.

Table 4-467 NodePoolSpec

Parameter	Type	Description
type	String	Node pool type. If this parameter is left blank, the value vm is used by default. <ul style="list-style-type: none">• vm: ECS• ElasticBMS: C6 general computing-plus BMS. An example flavor is c6.22xlarge.2.physical.• pm: BMS
nodeTemplate	NodeSpec object	Detailed parameters of the node pool template.
initialNodeCount	Integer	Initial number of nodes for the node pool. When queried, the value is the number of target nodes in the node pool.
autoscaling	NodePoolNodeAutoscaling object	Auto scaling parameters
nodeManagement	NodeManagement object	Node management configuration
podSecurityGroups	Array of SecurityID objects	Security group configuration. This parameter is available only for CCE Turbo clusters.

Parameter	Type	Description
customSecurityGroups	Array of strings	<p>Custom security group settings for a node pool. New nodes scaled out in a node pool can be bound to a specified security group.</p> <ul style="list-style-type: none">Specifying no security group ID will add the new nodes to the default security group of the worker nodes.Specifying a valid security group ID will put new nodes in that security group.When specifying a security group, do not modify the rules of the port on which CCE running depends.

Table 4-468 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	String	The OS type of the node. For details about the supported OSs, see Node OS . NOTE <ul style="list-style-type: none">The system automatically selects the supported OS based on the cluster version. If the current cluster does not support the OS, an error will be reported.If alpha.cce/NodeImageID in extendParam is specified during node creation, you do not need to configure this parameter.This parameter is mandatory when creating a node pool.
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node

Parameter	Type	Description
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .
storage	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	NodeNicSpec object	NIC of the node
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Type	Description
taints	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example: "k8sTags": { "key": "value" }</p>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-469 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-470 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-471 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-472 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
__system_cm_kid	String	CMK ID, which indicates encryption in metadata . This field is used with __system_encrypted .

Table 4-473 Storage

Parameter	Type	Description
storageSelectors	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
storageGroups	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-474 StorageSelectors

Parameter	Type	Description
name	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
storageType	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
matchLabels	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-475 matchLabels

Parameter	Type	Description
size	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
volumeType	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-476 StorageGroups

Parameter	Type	Description
name	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-477 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">• Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.• runtime: runtime space configuration. runtimeConfig needs to be configured.• user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-478 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-479 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-480 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-481 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-482 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-483 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-484 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-485 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-486 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-487 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">Clusters earlier than v1.25: The default value is <code>docker</code>.Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-488 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/ 90%VG;kubernetesLV=vgpaas/ 10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none"> • userLV (optional): size of the user space, for example, vgpaas/20%VG. • userPath (optional): mount path of the user space, for example, /home/wqt-test. • diskType: disk type. Currently, only evs, hdd, and ssd are supported. • lvType: type of a logic volume. The value can be linear or striped. • dockerThinpool: Docker space size, for example, vgpaas/60%VG. • kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-489 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-490 NodePoolNodeAutoscaling

Parameter	Type	Description
enable	Boolean	Whether to enable auto scaling.
minNodeCount	Integer	Minimum number of nodes allowed if auto scaling is enabled. The value cannot be greater than the maximum number of nodes allowed by the cluster specifications.
maxNodeCount	Integer	Maximum number of nodes allowed if auto scaling is enabled. This value must be greater than or equal to the value of minNodeCount and cannot exceed the maximum number of nodes in the cluster specifications.

Parameter	Type	Description
scaleDownCooldownTime	Integer	Interval between two scaling operations, in minutes. During this period, nodes added after a scale-up will not be deleted.
priority	Integer	Weight of a node pool. A node pool with a higher weight has a higher priority during scaling.

Table 4-491 NodeManagement

Parameter	Type	Description
serverGroupReference	String	Cloud server group ID. If this field is specified, all nodes in the node pool will be created in this group. The group ID can be specified only when you create the node pool and cannot be modified. When you specify a cloud server group, the number of nodes in the node pool cannot exceed the group quota.

Table 4-492 SecurityID

Parameter	Type	Description
id	String	Security group ID

Table 4-493 CreateNodePoolStatus

Parameter	Type	Description
currentNode	Integer	Total number of nodes in the current node pool (excluding the nodes that are being deleted).
creatingNode	Integer	Number of nodes that are being created in the node pool.
deletingNode	Integer	Number of nodes that are being deleted in the current node pool.

Parameter	Type	Description
phase	String	<p>Node pool status. Options:</p> <ul style="list-style-type: none">• Null: The node pool is available. (The number of nodes in the current node pool has reached the expected value, and no node scaling is being performed.)• Synchronizing: The node pool is being scaled. (The number of nodes in the current node pool has not reached the expected value, and no node scaling is being performed.)• Synchronized: The node pool scaling is pending. (The number of nodes in the current node pool has not reached the expected value, or node scaling is being performed.)• SoldOut: The node pool cannot be scaled out. (This field is used in multiple scenarios, for example, resources in the node pool have been sold out or the resource quota is insufficient.) <p>NOTE This node pool status has been deprecated. It is reserved only for compatibility. Do not use it anymore. Use the following instead:</p> <ul style="list-style-type: none">• Node pool scaling status: You can obtain the status of the current node pool using parameters such as currentNode, creatingNode, or deletingNode.• Node pool scale-out: You can use conditions to obtain the detailed status of a node pool. Scalable can replace SoldOut.• Deleting: The node pool is being deleted.• Error: An error occurred in the node pool.
conditions	Array of NodePoolCondition objects	Node pool status details. For details, see the definition of Condition .

Table 4-494 NodePoolCondition

Parameter	Type	Description
type	String	Condition type. The options are as follows: <ul style="list-style-type: none">• Scalable: whether a node pool can be scaled. If the status is False, node pool scaling will not be triggered again.• QuotaInsufficient: Quotas on which node pool scaling depends are insufficient, affecting the node pool scaling status.• ResourceInsufficient: Resources on which node pool scaling depends are insufficient, affecting the node pool scaling status.• UnexpectedError: The node pool fails to be scaled out due to unexpected reasons, affecting the node pool scaling status.• Error: A node pool error occurs. A common trigger is deletion failure.
status	String	Current status of Condition . The options are as follows: <ul style="list-style-type: none">• "True"• "False"
lastProbeTime	String	Time when the status was last checked
lastTransitTime	String	Time when the status was last changed
reason	String	Reason why the status was last changed
message	String	Detailed condition description

Example Requests

Create a node pool with the following configurations: The number of nodes is 0. The node pool flavor is 2 vCPUs and 4 GiB of memory. The node OS is EulerOS 2.5. Docker containers are deployed. The sizes of the system disk and data disk of the node are 40 GB and 100 GB, respectively. Both the disks are of the high I/O type.

```
{  
  "kind": "NodePool",  
  "apiVersion": "v3",  
  "metadata": {  
    "name": "lc-it-nodepool-79796"  
  },  
  "spec": {  
    "initialNodeCount": 0,  
    "type": "vm",  
    "autoscaling": {  
      "enable": false,  
      "minNodeCount": 0,  
      "maxNodeCount": 1,  
      "scaleDownCooldownTime": 0,  
    },  
    "nodeConfig": {  
      "os": "euleros",  
      "flavor": {  
        "cpu": 2,  
        "memory": 4,  
        "disk": {  
          "size": 40,  
          "type": "highIOPerformance",  
          "category": "system",  
        },  
        "disk": {  
          "size": 100,  
          "type": "highIOPerformance",  
          "category": "data",  
        },  
      },  
      "image": "euleros-2.5",  
      "network": {  
        "type": "bridge",  
        "ip": "192.168.1.100",  
        "mask": "255.255.255.0",  
        "gw": "192.168.1.1",  
        "dns": ["8.8.8.8", "8.8.4.4"],  
      },  
      "securityGroups": ["default"],  
    },  
  },  
}
```

```
        "priority" : 0
    },
    "nodeManagement" : {
        "serverGroupReference" : ""
    },
    "nodeTemplate" : {
        "flavor" : "s6.large.2",
        "az" : "*****",
        "os" : "EulerOS 2.5",
        "login" : {
            "sshKey" : "KeyPair-001"
        },
        "rootVolume" : {
            "volumetype" : "SAS",
            "size" : 40
        },
        "dataVolumes" : [ {
            "volumetype" : "SAS",
            "size" : 100,
            "extendParam" : {
                "useType" : "docker"
            }
        }],
        "billingMode" : 0,
        "extendParam" : {
            "alpha.cce/preInstall" : "",
            "alpha.cce/postInstall" : "",
            "alpha.cce/NodeImageID" : "",
            "maxPods" : 110
        },
        "nodeNicSpec" : {
            "primaryNic" : {
                "subnetId" : "7e767d10-7548-4df5-ad72-aeac1d08bd8a"
            }
        },
        "podSecurityGroups" : [ {
            "id" : ""
        }]
    }
}
```

Example Responses

Status code: 201

The job for creating a node pool in a specified cluster is successfully delivered.

```
{
    "kind" : "NodePool",
    "apiVersion" : "v3",
    "metadata" : {
        "name" : "lc-it-nodepool-79796",
        "uid" : "99addaa2-69eb-11ea-a592-0255ac1001bb"
    },
    "spec" : {
        "type" : "vm",
        "nodeTemplate" : {
            "flavor" : "s6.large.2",
            "az" : "*****",
            "os" : "EulerOS 2.5",
            "login" : {
                "sshKey" : "KeyPair-001"
            },
            "rootVolume" : {
                "volumetype" : "SAS",
                "size" : 40
            },
            "dataVolumes" : [ {
```

```
"volumetype" : "SAS",
"size" : 100,
"extendParam" : [
    "useType" : "docker"
]
},
"publicIP" : {
    "eip" : {
        "bandwidth" : { }
    }
},
"nodeNicSpec" : {
    "primaryNic" : {
        "subnetId" : "7e767d10-7548-4df5-ad72-aeac1d08bd8a"
    }
},
"billingMode" : 0,
"extendParam" : [
    "alpha.cce/NodeImageID" : "",
    "alpha.cce/postInstall" : "",
    "alpha.cce/preInstall" : "",
    "maxPods" : 110
],
"k8sTags" : {
    "cce.cloud.com/cce-nodepool" : "lc-it-nodepool-79796"
}
},
"autoscaling" : {
    "maxNodeCount" : 1
},
"nodeManagement" : { }
},
"status" : {
    "phase" : ""
}
```

Status Codes

Status Code	Description
201	The job for creating a node pool in a specified cluster is successfully delivered.

Error Codes

See [Error Codes](#).

4.4.2 Reading a Specified Node Pool

Function

This API is used to obtain details about a specified node pool.

NOTE

The URL for cluster management is in the format of https://Endpoint/uri. In the URL, **uri** indicates the resource path, that is, the path for API access.

URI

GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}

Table 4-495 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
nodepool_id	Yes	String	Node pool ID.

Request Parameters

Table 4-496 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-497 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at NodePool .
apiVersion	String	API version. The value is fixed at v3 .
metadata	NodePoolMetadata object	Metadata of the node pool.

Parameter	Type	Description
spec	NodePoolSpec object	Node pool specifications.
status	NodePoolStatus object	Node pool status.

Table 4-498 NodePoolMetadata

Parameter	Type	Description
name	String	<p>Node pool name.</p> <p>NOTE</p> <p>Naming rules:</p> <p>Enter 1 to 50 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.</p> <ul style="list-style-type: none">• You cannot create node pools named DefaultPool.
uid	String	UID of the node pool. The value is automatically generated after the object is updated. A user-defined value will not take effect.
annotations	Map<String, String>	Annotations of a node pool in key-value pairs. This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
updateTimestamp	String	Update time.
creationTimestamp	String	Creation time.

Table 4-499 NodePoolSpec

Parameter	Type	Description
type	String	<p>Node pool type. If this parameter is left blank, the value vm is used by default.</p> <ul style="list-style-type: none">• vm: ECS• ElasticBMS: C6 general computing-plus BMS. An example flavor is c6.22xlarge.2.physical.• pm: BMS

Parameter	Type	Description
nodeTemplate	NodeSpec object	Detailed parameters of the node pool template.
initialNodeCount	Integer	Initial number of nodes for the node pool. When queried, the value is the number of target nodes in the node pool.
autoscaling	NodePoolNodeAutoscaling object	Auto scaling parameters
nodeManagement	NodeManagement object	Node management configuration
podSecurityGroups	Array of SecurityID objects	Security group configuration. This parameter is available only for CCE Turbo clusters.
customSecurityGroups	Array of strings	Custom security group settings for a node pool. New nodes scaled out in a node pool can be bound to a specified security group. <ul style="list-style-type: none">• Specifying no security group ID will add the new nodes to the default security group of the worker nodes.• Specifying a valid security group ID will put new nodes in that security group.• When specifying a security group, do not modify the rules of the port on which CCE running depends.

Table 4-500 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.

Parameter	Type	Description
os	String	<p>The OS type of the node. For details about the supported OSs, see Node OS.</p> <p>NOTE</p> <ul style="list-style-type: none">• The system automatically selects the supported OS based on the cluster version. If the current cluster does not support the OS, an error will be reported.• If <code>alpha.cce/NodeImageID</code> in <code>extendParam</code> is specified during node creation, you do not need to configure this parameter.• This parameter is mandatory when creating a node pool.
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for <code>rootVolume</code> .
storage	Storage object	<p>Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node.</p> <p>If this parameter retains its default, disks are managed based on the <code>DockerLVMConfigOverride</code> (discarded) parameter in <code>extendParam</code>. This parameter is supported by clusters of version 1.15.11 and later.</p> <p>NOTE</p> <p>If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.</p>
publicIP	NodePublicIP object	EIP of a node.
nodeNicSpec	NodeNicSpec object	NIC of the node

Parameter	Type	Description
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. • 0: pay-per-use
taints	Array of Taint objects	You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters: <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{"key": "status", "value": "unavailable", "effect": "NoSchedule"}, {"key": "looks", "value": "bad", "effect": "NoSchedule"}]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example: "k8sTags": { "key": "value" }</p>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-501 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-502 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-503 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none"> • SAS: high I/O SAS disk • SSD: ultra-high I/O SSD disk • SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none"> • Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created. • If the node pool type is ElasticBMS, this field must be set to true. • If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-504 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-505 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-506 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-507 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-508 StorageGroups

Parameter	Type	Description
name	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-509 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">● Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.● runtime: runtime space configuration. runtimeConfig needs to be configured.● user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-510 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-511 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-512 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-513 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-514 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-515 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-516 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-517 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-518 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-519 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">Clusters earlier than v1.25: The default value is <code>docker</code>.Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-520 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/ 90%VG;kubernetesLV=vgpaas/ 10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none"> • userLV (optional): size of the user space, for example, vgpaas/20%VG. • userPath (optional): mount path of the user space, for example, /home/wqt-test. • diskType: disk type. Currently, only evs, hdd, and ssd are supported. • lvType: type of a logic volume. The value can be linear or striped. • dockerThinpool: Docker space size, for example, vgpaas/60%VG. • kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-521 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none"> • privatelp: The Kubernetes node is named after its IP address. • cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none"> • For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization. • For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-522 NodePoolNodeAutoscaling

Parameter	Type	Description
enable	Boolean	Whether to enable auto scaling.
minNodeCount	Integer	Minimum number of nodes allowed if auto scaling is enabled. The value cannot be greater than the maximum number of nodes allowed by the cluster specifications.
maxNodeCount	Integer	Maximum number of nodes allowed if auto scaling is enabled. This value must be greater than or equal to the value of minNodeCount and cannot exceed the maximum number of nodes in the cluster specifications.

Parameter	Type	Description
scaleDownCooldownTime	Integer	Interval between two scaling operations, in minutes. During this period, nodes added after a scale-up will not be deleted.
priority	Integer	Weight of a node pool. A node pool with a higher weight has a higher priority during scaling.

Table 4-523 NodeManagement

Parameter	Type	Description
serverGroupReference	String	Cloud server group ID. If this field is specified, all nodes in the node pool will be created in this group. The group ID can be specified only when you create the node pool and cannot be modified. When you specify a cloud server group, the number of nodes in the node pool cannot exceed the group quota.

Table 4-524 SecurityID

Parameter	Type	Description
id	String	Security group ID

Table 4-525 NodePoolStatus

Parameter	Type	Description
currentNode	Integer	Total number of nodes in the current node pool (excluding the nodes that are being deleted)
creatingNode	Integer	Number of nodes in the creation process in the node pool
deletingNode	Integer	Number of nodes being deleted in the current node pool.

Parameter	Type	Description
phase	String	<p>Node pool status.</p> <ul style="list-style-type: none">• Null: available (the number of current nodes in the node pool has reached the expected value, and no node scaling is being performed.)• Synchronizing: scaling in progress (the number of current nodes in the node pool does not reach the expected value and no node scaling is being performed.)• Synchronized: pending scaling (the number of current nodes in the node pool does not reach the expected value, or node scaling is being performed.)• SoldOut: The node pool cannot be scaled out. (This field is used in multiple scenarios, for example, resources in the node pool have been sold out or the resource quota is insufficient.) <p>NOTE This node pool status has been discarded and is reserved only for compatibility. You are not advised to use it. The replacements are as follows:</p> <ul style="list-style-type: none">• Node pool scaling status: You can obtain accurate status of the current node pool based on parameters such as currentNode, creatingNode, or deletingNode.• Node pool scale-out: You can use conditions to obtain the detailed status of a node pool. Scalable can replace SoldOut.• Deleting: The object is being deleted.• Error: An error occurs.
jobId	String	ID of a job executed on the node pool. This field is available only when the node pool is being deleted.
conditions	Array of NodePoolCondition objects	Node pool status details. For details, see the definition of Condition .

Table 4-526 NodePoolCondition

Parameter	Type	Description
type	String	Condition type. The options are as follows: <ul style="list-style-type: none">• Scalable: whether a node pool can be scaled. If the status is False, node pool scaling will not be triggered again.• QuotaInsufficient: Quotas on which node pool scaling depends are insufficient, affecting the node pool scaling status.• ResourceInsufficient: Resources on which node pool scaling depends are insufficient, affecting the node pool scaling status.• UnexpectedError: The node pool fails to be scaled out due to unexpected reasons, affecting the node pool scaling status.• Error: A node pool error occurs. A common trigger is deletion failure.
status	String	Current status of Condition . The options are as follows: <ul style="list-style-type: none">• "True"• "False"
lastProbeTime	String	Time when the status was last checked
lastTransitTime	String	Time when the status was last changed
reason	String	Reason why the status was last changed
message	String	Detailed condition description

Example Requests

None

Example Responses

Status code: 200

Details about the specified node pool are obtained successfully.

```
{  
  "kind": "NodePool",  
  "apiVersion": "v3",  
  "metadata": {  
    "name": "lc-it-nodepool-79796",  
    "uid": "99addaa2-69eb-11ea-a592-0255ac1001bb"  
  },  
  "spec": {  
    "type": "vm",  
    "nodeTemplate": {  
      "image": "centos:7",  
      "cpu": 2,  
      "memory": 4096  
    }  
  }  
}
```

```
        "flavor" : "s6.large.2",
        "az" : "*****",
        "os" : "EulerOS 2.5",
        "login" : {
            "sshKey" : "KeyPair-001"
        },
        "rootVolume" : {
            "volumetype" : "SAS",
            "size" : 40
        },
        "dataVolumes" : [ {
            "volumetype" : "SAS",
            "size" : 100,
            "extendParam" : {
                "useType" : "docker"
            }
        }],
        "publicIP" : {
            "eip" : {
                "bandwidth" : { }
            }
        },
        "nodeNicSpec" : {
            "primaryNic" : {
                "subnetId" : "7e767d10-7548-4df5-ad72-aeac1d08bd8a"
            }
        },
        "billingMode" : 0,
        "extendParam" : {
            "maxPods" : 110
        },
        "k8sTags" : {
            "cce.cloud.com/cce-nodepool" : "lc-it-nodepool-79796"
        },
        "autoscaling" : { },
        "nodeManagement" : { }
    },
    "status" : {
        "phase" : "Deleting",
        "jobId" : "3281fa02-69ee-11ea-a592-0255ac1001bb"
    }
}
```

Status Codes

Status Code	Description
200	Details about the specified node pool are obtained successfully.

Error Codes

See [Error Codes](#).

4.4.3 Listing All Node Pools in a Specified Cluster

Function

This API is used to obtain information about all node pools in a specified cluster.

NOTE

- The URL for cluster management is in the format of `https://Endpoint/uri`. In the URL, `uri` indicates the resource path, that is, the path for API access.
- A node pool is a group of nodes within a cluster that all have the same configuration.

URI

GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools

Table 4-527 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Table 4-528 Query Parameters

Parameter	Mandatory	Type	Description
showDefaultNodePool	No	String	Whether to display the default node pool. By default, the default node pool is not displayed. If this parameter is set to <code>true</code> , the default node pool is displayed.

Request Parameters

Table 4-529 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-530 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed to List.
apiVersion	String	API version. The value is fixed to v3.
items	Array of NodePoolResp objects	/

Table 4-531 NodePoolResp

Parameter	Type	Description
kind	String	API type. The value is fixed at NodePool .
apiVersion	String	API version. The value is fixed at v3 .
metadata	NodePoolMetadata object	Metadata of the node pool.
spec	NodePoolSpec object	Node pool specifications.
status	NodePoolStatus object	Node pool status.

Table 4-532 NodePoolMetadata

Parameter	Type	Description
name	String	<p>Node pool name.</p> <p>NOTE</p> <p>Naming rules:</p> <p>Enter 1 to 50 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.</p> <ul style="list-style-type: none">• You cannot create node pools named DefaultPool.
uid	String	UID of the node pool. The value is automatically generated after the object is updated. A user-defined value will not take effect.
annotations	Map<String, String>	Annotations of a node pool in key-value pairs. This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
updateTimestamp	String	Update time.
creationTimestamp	String	Creation time.

Table 4-533 NodePoolSpec

Parameter	Type	Description
type	String	<p>Node pool type. If this parameter is left blank, the value vm is used by default.</p> <ul style="list-style-type: none">• vm: ECS• ElasticBMS: C6 general computing-plus BMS. An example flavor is c6.22xlarge.2.physical.• pm: BMS
nodeTemplate	NodeSpec object	Detailed parameters of the node pool template.
initialNodeCount	Integer	Initial number of nodes for the node pool. When queried, the value is the number of target nodes in the node pool.
autoscaling	NodePoolNodeAutoscaling object	Auto scaling parameters

Parameter	Type	Description
nodeManagement	NodeManagement object	Node management configuration
podSecurityGroups	Array of SecurityID objects	Security group configuration. This parameter is available only for CCE Turbo clusters.
customSecurityGroups	Array of strings	Custom security group settings for a node pool. New nodes scaled out in a node pool can be bound to a specified security group. <ul style="list-style-type: none">• Specifying no security group ID will add the new nodes to the default security group of the worker nodes.• Specifying a valid security group ID will put new nodes in that security group.• When specifying a security group, do not modify the rules of the port on which CCE running depends.

Table 4-534 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	String	The OS type of the node. For details about the supported OSs, see Node OS . NOTE <ul style="list-style-type: none">• The system automatically selects the supported OS based on the cluster version. If the current cluster does not support the OS, an error will be reported.• If alpha.cce/NodeImageID in extendParam is specified during node creation, you do not need to configure this parameter.• This parameter is mandatory when creating a node pool.
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node

Parameter	Type	Description
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .
storage	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	NodeNicSpec object	NIC of the node
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Type	Description
taints	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"k8sTags": { "key": "value" }</pre>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none"> Clusters of v1.25 or earlier: docker. Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-535 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-536 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-537 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-538 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-539 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-540 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-541 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-542 StorageGroups

Parameter	Type	Description
name	String	<p>Name of a virtual storage group, which must be unique.</p> <p>NOTE</p> <ul style="list-style-type: none"> • If cceManaged is set to true, the name must be set to vgpass. • If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral. • If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-543 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">● Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.● runtime: runtime space configuration. runtimeConfig needs to be configured.● user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-544 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-545 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-546 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-547 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-548 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-549 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-550 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-551 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-552 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-553 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">Clusters earlier than v1.25: The default value is <code>docker</code>.Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-554 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/90%VG;kubernetesLV=vgpaas/10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none">• userLV (optional): size of the user space, for example, vgpaas/20%VG.• userPath (optional): mount path of the user space, for example, /home/wqt-test.• diskType: disk type. Currently, only evs, hdd, and ssd are supported.• lvType: type of a logic volume. The value can be linear or striped.• dockerThinpool: Docker space size, for example, vgpaas/60%VG.• kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-555 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none"> • privatelp: The Kubernetes node is named after its IP address. • cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none"> • For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization. • For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-556 NodePoolNodeAutoscaling

Parameter	Type	Description
enable	Boolean	Whether to enable auto scaling.
minNodeCount	Integer	Minimum number of nodes allowed if auto scaling is enabled. The value cannot be greater than the maximum number of nodes allowed by the cluster specifications.
maxNodeCount	Integer	Maximum number of nodes allowed if auto scaling is enabled. This value must be greater than or equal to the value of minNodeCount and cannot exceed the maximum number of nodes in the cluster specifications.

Parameter	Type	Description
scaleDownCooldownTime	Integer	Interval between two scaling operations, in minutes. During this period, nodes added after a scale-up will not be deleted.
priority	Integer	Weight of a node pool. A node pool with a higher weight has a higher priority during scaling.

Table 4-557 NodeManagement

Parameter	Type	Description
serverGroupReference	String	Cloud server group ID. If this field is specified, all nodes in the node pool will be created in this group. The group ID can be specified only when you create the node pool and cannot be modified. When you specify a cloud server group, the number of nodes in the node pool cannot exceed the group quota.

Table 4-558 SecurityID

Parameter	Type	Description
id	String	Security group ID

Table 4-559 NodePoolStatus

Parameter	Type	Description
currentNode	Integer	Total number of nodes in the current node pool (excluding the nodes that are being deleted)
creatingNode	Integer	Number of nodes in the creation process in the node pool
deletingNode	Integer	Number of nodes being deleted in the current node pool.

Parameter	Type	Description
phase	String	<p>Node pool status.</p> <ul style="list-style-type: none">• Null: available (the number of current nodes in the node pool has reached the expected value, and no node scaling is being performed.)• Synchronizing: scaling in progress (the number of current nodes in the node pool does not reach the expected value and no node scaling is being performed.)• Synchronized: pending scaling (the number of current nodes in the node pool does not reach the expected value, or node scaling is being performed.)• SoldOut: The node pool cannot be scaled out. (This field is used in multiple scenarios, for example, resources in the node pool have been sold out or the resource quota is insufficient.) <p>NOTE This node pool status has been discarded and is reserved only for compatibility. You are not advised to use it. The replacements are as follows:</p> <ul style="list-style-type: none">• Node pool scaling status: You can obtain accurate status of the current node pool based on parameters such as currentNode, creatingNode, or deletingNode.• Node pool scale-out: You can use conditions to obtain the detailed status of a node pool. Scalable can replace SoldOut.• Deleting: The object is being deleted.• Error: An error occurs.
jobId	String	ID of a job executed on the node pool. This field is available only when the node pool is being deleted.
conditions	Array of NodePoolCondition objects	Node pool status details. For details, see the definition of Condition .

Table 4-560 NodePoolCondition

Parameter	Type	Description
type	String	Condition type. The options are as follows: <ul style="list-style-type: none">• Scalable: whether a node pool can be scaled. If the status is False, node pool scaling will not be triggered again.• QuotaInsufficient: Quotas on which node pool scaling depends are insufficient, affecting the node pool scaling status.• ResourceInsufficient: Resources on which node pool scaling depends are insufficient, affecting the node pool scaling status.• UnexpectedError: The node pool fails to be scaled out due to unexpected reasons, affecting the node pool scaling status.• Error: A node pool error occurs. A common trigger is deletion failure.
status	String	Current status of Condition . The options are as follows: <ul style="list-style-type: none">• "True"• "False"
lastProbeTime	String	Time when the status was last checked
lastTransitTime	String	Time when the status was last changed
reason	String	Reason why the status was last changed
message	String	Detailed condition description

Example Requests

None

Example Responses

Status code: 200

Information about all node pools in the cluster is successfully obtained.

```
{  
    "kind" : "List",  
    "apiVersion" : "v3",  
    "items" : [ {  
        "kind" : "NodePool",  
        "apiVersion" : "v3",  
        "metadata" : {  
            "name" : "az1.dc1#s1.large#EulerOS 2.2",  
            "uid" : "az1.dc1#s1.large#EulerOS 2.2"  
        },  
    },
```

```
"spec" : {
    "nodeTemplate" : {
        "flavor" : "s1.large",
        "az" : "az1.dc1",
        "os" : "EulerOS 2.2",
        "login" : {
            "sshKey" : "KeyPair-001"
        },
        "rootVolume" : { },
        "publicIP" : {
            "eip" : {
                "bandwidth" : { }
            }
        },
        "billingMode" : 0
    },
    "autoscaling" : {
        "enable" : true,
        "maxNodeCount" : 50
    }
},
"status" : {
    "currentNode" : 1
}
}]
```

Status Codes

Status Code	Description
200	Information about all node pools in the cluster is successfully obtained.

Error Codes

See [Error Codes](#).

4.4.4 Updating a Specified Node Pool

Function

This API is used to update information about a specified node pool. This API can be called only when the cluster is in the Available, Scale Out, or Scale In state.

NOTE

- The URL for cluster management is in the following format: `https://Endpoint/uri`. `uri` indicates the resource path, that is, the API access path.
- Currently, only the node pool name can be updated. `initialNodeCount`, `k8sTags`, `taints`, `login` and `userTags` under `spec` are related to the scaling configuration of the node pool. If no value is set for this update, the initial value is used by default.

URI

`PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}`

Table 4-561 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
nodepool_id	Yes	String	Node pool ID.

Request Parameters

Table 4-562 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-563 Request body parameters

Parameter	Mandatory	Type	Description
metadata	Yes	NodePoolMetadataUpdate object	Metadata information of the node pool.
spec	Yes	NodePoolSpecUpdate object	Node pool specifications.

Table 4-564 NodePoolMetadataUpdate

Parameter	Mandatory	Type	Description
name	Yes	String	<p>Name of the node pool.</p> <p>NOTE</p> <p>Naming rules:</p> <ul style="list-style-type: none">• Enter 1 to 50 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.• You cannot create node pools named DefaultPool.

Table 4-565 NodePoolSpecUpdate

Parameter	Mandatory	Type	Description
nodeTemplate	Yes	NodeSpecUpdate object	Detailed parameters of the node pool template.
initialNodeCount	Yes	Integer	Initial number of nodes for the node pool. When queried, the value is the number of target nodes in the node pool. The default value is 0.
autoscaling	Yes	NodePoolNo deAutoscaling object	Auto scaling parameters. Only pay-per-use node pools support auto scaling.

Table 4-566 NodeSpecUpdate

Parameter	Mandatory	Type	Description
taints	Yes	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. This parameter is left blank by default. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: Enter 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key.• Value: Enter 1 to 63 characters with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed.• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre> <p>NOTE If this parameter is not specified or left empty, the custom taints of the node pool will be deleted.</p>

Parameter	Mandatory	Type	Description
k8sTags	Yes	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed. This parameter is left blank by default.</p> <ul style="list-style-type: none">• Key: Enter 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain containing a maximum of 253 characters (such as example.com/my-key) can be prefixed to a key.• Value: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. <p>Example: <code>"k8sTags": { "key": "value" }</code></p> <p>NOTE If this parameter is not specified or left empty, the custom Kubernetes labels of the node pool will be deleted.</p>
userTags	Yes	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE varies depending on regions and cannot exceed 8. This parameter is left blank by default.</p> <p>NOTE If this parameter is not specified or left empty, the custom cloud server tags of the node pool will be deleted.</p>

Parameter	Mandatory	Type	Description
initializedConditions	No	Array of strings	<p>Custom initialization flag, which is left blank by default. Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured. Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following:<pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <p>1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.</p> <p>2. initializedConditions allows you to configure a</p>

Parameter	Mandatory	Type	Description
			<p>timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.</p> <ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).
login	No	Login object	Node login mode. Either the key pair login mode or the password login mode must be used.

Table 4-567 Taint

Parameter	Mandatory	Type	Description
key	Yes	String	Key.
value	No	String	Value.
effect	Yes	String	Effect.

Table 4-568 UserTag

Parameter	Mandatory	Type	Description
key	No	String	Key of the cloud server label. The value cannot start with CCE- or _type_baremetal .
value	No	String	Value of the cloud server label.

Table 4-569 Login

Parameter	Mandatory	Type	Description
sshKey	No	String	Name of the key pair used for login.

Table 4-570 UserPassword

Parameter	Mandatory	Type	Description
username	No	String	Login account. Defaults to root .
password	Yes	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@#\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-571 NodePoolNodeAutoscaling

Parameter	Mandatory	Type	Description
enable	No	Boolean	Whether to enable auto scaling.
minNodeCount	No	Integer	Minimum number of nodes allowed if auto scaling is enabled. The value cannot be greater than the maximum number of nodes allowed by the cluster specifications.

Parameter	Mandatory	Type	Description
maxNodeCount	No	Integer	Maximum number of nodes allowed if auto scaling is enabled. This value must be greater than or equal to the value of minNodeCount and cannot exceed the maximum number of nodes in the cluster specifications.
scaleDownCooldownTime	No	Integer	Interval between two scaling operations, in minutes. During this period, nodes added after a scale-up will not be deleted.
priority	No	Integer	Weight of a node pool. A node pool with a higher weight has a higher priority during scaling.

Response Parameters

Status code: 200

Table 4-572 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at NodePool .
apiVersion	String	API version. The value is fixed at v3 .
metadata	NodePoolMetadata object	Metadata of the node pool.
spec	NodePoolSpec object	Node pool specifications.
status	UpdateNodePoolStatus object	Node pool status.

Table 4-573 NodePoolMetadata

Parameter	Type	Description
name	String	<p>Node pool name.</p> <p>NOTE</p> <p>Naming rules:</p> <p>Enter 1 to 50 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.</p> <ul style="list-style-type: none">• You cannot create node pools named DefaultPool.
uid	String	UID of the node pool. The value is automatically generated after the object is updated. A user-defined value will not take effect.
annotations	Map<String, String>	Annotations of a node pool in key-value pairs. This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
updateTimestamp	String	Update time.
creationTimestamp	String	Creation time.

Table 4-574 NodePoolSpec

Parameter	Type	Description
type	String	<p>Node pool type. If this parameter is left blank, the value vm is used by default.</p> <ul style="list-style-type: none">• vm: ECS• ElasticBMS: C6 general computing-plus BMS. An example flavor is c6.22xlarge.2.physical.• pm: BMS
nodeTemplate	NodeSpec object	Detailed parameters of the node pool template.
initialNodeCount	Integer	Initial number of nodes for the node pool. When queried, the value is the number of target nodes in the node pool.
autoscaling	NodePoolNodeAutoscaling object	Auto scaling parameters

Parameter	Type	Description
nodeManagement	NodeManagement object	Node management configuration
podSecurityGroups	Array of SecurityID objects	Security group configuration. This parameter is available only for CCE Turbo clusters.
customSecurityGroups	Array of strings	Custom security group settings for a node pool. New nodes scaled out in a node pool can be bound to a specified security group. <ul style="list-style-type: none">• Specifying no security group ID will add the new nodes to the default security group of the worker nodes.• Specifying a valid security group ID will put new nodes in that security group.• When specifying a security group, do not modify the rules of the port on which CCE running depends.

Table 4-575 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.
os	String	The OS type of the node. For details about the supported OSs, see Node OS . NOTE <ul style="list-style-type: none">• The system automatically selects the supported OS based on the cluster version. If the current cluster does not support the OS, an error will be reported.• If alpha.cce/NodeImageID in extendParam is specified during node creation, you do not need to configure this parameter.• This parameter is mandatory when creating a node pool.
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node

Parameter	Type	Description
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for rootVolume .
storage	Storage object	Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node . If this parameter retains its default, disks are managed based on the DockerLVMConfigOverride (discarded) parameter in extendParam. This parameter is supported by clusters of version 1.15.11 and later. NOTE If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.
publicIP	NodePublicIP object	EIP of a node. NOTE This parameter is not supported when you add a node to a node pool.
nodeNicSpec	NodeNicSpec object	NIC of the node
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use

Parameter	Type	Description
taints	Array of Taint objects	<p>You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters:</p> <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{ "key": "status", "value": "unavailable", "effect": "NoSchedule" }, { "key": "looks", "value": "bad", "effect": "NoSchedule" }]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example: "k8sTags": { "key": "value" }</p>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">• Clusters of v1.25 or earlier: docker.• Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-576 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-577 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-578 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-579 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-580 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-581 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-582 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-583 StorageGroups

Parameter	Type	Description
name	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-584 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">● Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.● runtime: runtime space configuration. runtimeConfig needs to be configured.● user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-585 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-586 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-587 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-588 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-589 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-590 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-591 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-592 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-593 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-594 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">• Clusters earlier than v1.25: The default value is <code>docker</code>.• Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-595 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/ 90%VG;kubernetesLV=vgpaas/ 10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none"> • userLV (optional): size of the user space, for example, vgpaas/20%VG. • userPath (optional): mount path of the user space, for example, /home/wqt-test. • diskType: disk type. Currently, only evs, hdd, and ssd are supported. • lvType: type of a logic volume. The value can be linear or striped. • dockerThinpool: Docker space size, for example, vgpaas/60%VG. • kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-596 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none">• privatelp: The Kubernetes node is named after its IP address.• cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none">• For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization.• For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-597 NodePoolNodeAutoscaling

Parameter	Type	Description
enable	Boolean	Whether to enable auto scaling.
minNodeCount	Integer	Minimum number of nodes allowed if auto scaling is enabled. The value cannot be greater than the maximum number of nodes allowed by the cluster specifications.
maxNodeCount	Integer	Maximum number of nodes allowed if auto scaling is enabled. This value must be greater than or equal to the value of minNodeCount and cannot exceed the maximum number of nodes in the cluster specifications.

Parameter	Type	Description
scaleDownCooldownTime	Integer	Interval between two scaling operations, in minutes. During this period, nodes added after a scale-up will not be deleted.
priority	Integer	Weight of a node pool. A node pool with a higher weight has a higher priority during scaling.

Table 4-598 NodeManagement

Parameter	Type	Description
serverGroupReference	String	Cloud server group ID. If this field is specified, all nodes in the node pool will be created in this group. The group ID can be specified only when you create the node pool and cannot be modified. When you specify a cloud server group, the number of nodes in the node pool cannot exceed the group quota.

Table 4-599 SecurityID

Parameter	Type	Description
id	String	Security group ID

Table 4-600 UpdateNodePoolStatus

Parameter	Type	Description
currentNode	Integer	Total number of nodes in the current node pool (excluding the nodes that are being deleted).
creatingNode	Integer	Number of nodes that are being created in the node pool.
deletingNode	Integer	Number of nodes that are being deleted in the current node pool.

Parameter	Type	Description
phase	String	<p>Node pool status. Options:</p> <ul style="list-style-type: none">• Null: The node pool is available. (The number of nodes in the current node pool has reached the expected value, and no node scaling is being performed.)• Synchronizing: The node pool is being scaled. (The number of nodes in the current node pool has not reached the expected value, and no node scaling is being performed.)• Synchronized: The node pool scaling is pending. (The number of nodes in the current node pool has not reached the expected value, or node scaling is being performed.)• SoldOut: The node pool cannot be scaled out. (This field is used in multiple scenarios, for example, resources in the node pool have been sold out or the resource quota is insufficient.) <p>NOTE This node pool status has been deprecated. It is reserved only for compatibility. Do not use it anymore. Use the following instead:</p> <ul style="list-style-type: none">• Node pool scaling status: You can obtain the status of the current node pool using parameters such as currentNode, creatingNode, or deletingNode.• Node pool scale-out: You can use conditions to obtain the detailed status of a node pool. Scalable can replace SoldOut.• Deleting: The node pool is being deleted.• Error: An error occurred in the node pool.
conditions	Array of NodePoolCondition objects	Node pool status details. For details, see the definition of Condition .

Table 4-601 NodePoolCondition

Parameter	Type	Description
type	String	Condition type. The options are as follows: <ul style="list-style-type: none">• Scalable: whether a node pool can be scaled. If the status is False, node pool scaling will not be triggered again.• QuotaInsufficient: Quotas on which node pool scaling depends are insufficient, affecting the node pool scaling status.• ResourceInsufficient: Resources on which node pool scaling depends are insufficient, affecting the node pool scaling status.• UnexpectedError: The node pool fails to be scaled out due to unexpected reasons, affecting the node pool scaling status.• Error: A node pool error occurs. A common trigger is deletion failure.
status	String	Current status of Condition . The options are as follows: <ul style="list-style-type: none">• "True"• "False"
lastProbeTime	String	Time when the status was last checked
lastTransitTime	String	Time when the status was last changed
reason	String	Reason why the status was last changed
message	String	Detailed condition description

Example Requests

- Change the number of nodes in the node pool to 1.

```
PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}
```

```
{  
    "metadata": {  
        "name": "lc-it-nodepool-3"  
    },  
    "spec": {  
        "nodeTemplate": {  
            "k8sTags": {},  
            "taints": [  
                {  
                    "key": "status",  
                    "value": "unavailable",  
                    "effect": "NoSchedule"  
                }]  
            "userTags": []  
        },  
        "autoscaling": {  
            "enable": false,  
            "minNodeCount": 0,  
            "maxNodeCount": 1  
        }  
    }  
}
```

```
        "maxNodeCount" : 0,
        "scaleDownCooldownTime" : 0,
        "priority" : 0
    },
    "initialNodeCount" : 1
}
}
```

- **Modify the key pair.**
`PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}`

```
{
  "metadata" : {
    "name" : "lc-it-nodepool-2"
  },
  "spec" : {
    "nodeTemplate" : {
      "k8sTags" : { },
      "taints" : [ {
        "key" : "status",
        "value" : "unavailable",
        "effect" : "NoSchedule"
      }],
      "userTags" : [ ],
      "login" : {
        "sshKey" : "KeyPair-IES"
      }
    },
    "autoscaling" : {
      "enable" : false,
      "minNodeCount" : 0,
      "maxNodeCount" : 0,
      "scaleDownCooldownTime" : 0,
      "priority" : 0
    },
    "initialNodeCount" : 1
  }
}
```

Example Responses

Status code: 200

Information about the specified node pool is successfully updated.

```
{
  "kind" : "NodePool",
  "apiVersion" : "v3",
  "metadata" : {
    "name" : "lc-it-nodepool-3",
    "uid" : "1def848-690d-11ea-a11b-0255ac1001b7"
  },
  "spec" : {
    "initialNodeCount" : 1,
    "type" : "vm",
    "nodeTemplate" : {
      "flavor" : "S13.xlarge.2",
      "az" : "*****",
      "os" : "EulerOS 2.5",
      "login" : {
        "sshKey" : "KeyPair-001"
      },
      "rootVolume" : {
        "volumetype" : "SAS",
        "size" : 40
      },
      "dataVolumes" : [ {
        "volumetype" : "SAS",
        "size" : 100,
      }]
    }
  }
}
```

```
"extendParam" : {
    "useType" : "docker"
}
},
"publicIP" : {
    "eip" : {
        "bandwidth" : { }
    }
},
"nodeNicSpec" : {
    "primaryNic" : {
        "subnetId" : "7e767d10-7548-4df5-ad72-aeac1d08bd8a"
    }
},
"billingMode" : 0,
"extendParam" : {
    "maxPods" : 110
},
"k8sTags" : {
    "cce.cloud.com/cce-nodepool" : "lc-it-nodepool-3"
},
"autoscaling" : { },
"nodeManagement" : { }
},
"status" : {
    "phase" : ""
}
}
```

Status Codes

Status Code	Description
200	Information about the specified node pool is successfully updated.

Error Codes

See [Error Codes](#).

4.4.5 Deleting a Node Pool

Function

This API is used to delete a specified node pool.



The URL for cluster management is in the format of `https://Endpoint/uri`. In the URL, `uri` indicates the resource path, that is, the path for API access.

URI

`DELETE /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}`

Table 4-602 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
nodepool_id	Yes	String	Node pool ID.

Request Parameters

Table 4-603 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-604 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at NodePool .
apiVersion	String	API version. The value is fixed at v3 .
metadata	NodePoolMetadata object	Metadata of the node pool.
spec	NodePoolSpec object	Node pool specifications.

Parameter	Type	Description
status	DeleteNodePoolStatus object	Node pool status.

Table 4-605 NodePoolMetadata

Parameter	Type	Description
name	String	<p>Node pool name. NOTE Naming rules: Enter 1 to 50 characters, starting with a lowercase letter and not ending with a hyphen (-). Only lowercase letters, digits, and hyphens (-) are allowed.</p> <ul style="list-style-type: none">• You cannot create node pools named DefaultPool.
uid	String	UID of the node pool. The value is automatically generated after the object is updated. A user-defined value will not take effect.
annotations	Map<String, String>	Annotations of a node pool in key-value pairs. This parameter is used only for query and cannot be input through a request. Entered data of this parameter is invalid.
updateTimestamp	String	Update time.
creationTimestamp	String	Creation time.

Table 4-606 NodePoolSpec

Parameter	Type	Description
type	String	<p>Node pool type. If this parameter is left blank, the value vm is used by default.</p> <ul style="list-style-type: none">• vm: ECS• ElasticBMS: C6 general computing-plus BMS. An example flavor is c6.22xlarge.2.physical.• pm: BMS
nodeTemplate	NodeSpec object	Detailed parameters of the node pool template.

Parameter	Type	Description
initialNodeCount	Integer	Initial number of nodes for the node pool. When queried, the value is the number of target nodes in the node pool.
autoscaling	NodePoolNo deAutoscaling object	Auto scaling parameters
nodeManagement	NodeManagement object	Node management configuration
podSecurityGroups	Array of SecurityID objects	Security group configuration. This parameter is available only for CCE Turbo clusters.
customSecurityGroups	Array of strings	Custom security group settings for a node pool. New nodes scaled out in a node pool can be bound to a specified security group. <ul style="list-style-type: none">• Specifying no security group ID will add the new nodes to the default security group of the worker nodes.• Specifying a valid security group ID will put new nodes in that security group.• When specifying a security group, do not modify the rules of the port on which CCE running depends.

Table 4-607 NodeSpec

Parameter	Type	Description
flavor	String	Node specifications. For details about the node specifications supported by CCE, see Node Flavor Description .
az	String	AZ where the node to be created is located. You need to specify the AZ name. If it is set to random , the node will be created in a random AZ.

Parameter	Type	Description
os	String	<p>The OS type of the node. For details about the supported OSs, see Node OS.</p> <p>NOTE</p> <ul style="list-style-type: none">• The system automatically selects the supported OS based on the cluster version. If the current cluster does not support the OS, an error will be reported.• If <code>alpha.cce/NodeImageID</code> in <code>extendParam</code> is specified during node creation, you do not need to configure this parameter.• This parameter is mandatory when creating a node pool.
login	Login object	Node login mode. Either the key pair or password must be used for login.
rootVolume	Volume object	Information about disks on the node
dataVolumes	Array of Volume objects	Data disk parameters of the node. Currently, you can add the second data disk for your node on the CCE console. This data disk is used by the container runtime and kubelet. Do not uninstall this disk. Otherwise, the node will become unavailable. For DeC nodes, the parameter description is the same as that for <code>rootVolume</code> .
storage	Storage object	<p>Disk initialization management parameter. This parameter is complex to configure. For details, see Attaching Disks to a Node.</p> <p>If this parameter retains its default, disks are managed based on the <code>DockerLVMConfigOverride</code> (discarded) parameter in <code>extendParam</code>. This parameter is supported by clusters of version 1.15.11 and later.</p> <p>NOTE</p> <p>If a node specification involves local disks and EVS disks at the same time, do not retain the default value of this parameter to prevent unexpected disk partitions.</p>
publicIP	NodePublicIP object	EIP of a node.
nodeNicSpec	NodeNicSpec object	NIC of the node

Parameter	Type	Description
count	Integer	Number of nodes to be created in a batch. The value must be a positive integer greater than or equal to 1 and less than or equal to the defined limit. This parameter can be left blank when it is used for a node pool.
billingMode	Integer	Node billing mode. <ul style="list-style-type: none">• 0: pay-per-use
taints	Array of Taint objects	You can add taints to created nodes to configure anti-affinity. A maximum of 20 taints can be added. Each taint contains the following parameters: <ul style="list-style-type: none">• Key: A key must contain 1 to 63 characters starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain name can be used as the prefix of a key.• Value: A value must start with a letter or digit and can contain a maximum of 63 characters, including letters, digits, hyphens (-), underscores (_), and periods (.).• Effect: Available options are NoSchedule, PreferNoSchedule, and NoExecute. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example:</p> <pre>"taints": [{"key": "status", "value": "unavailable", "effect": "NoSchedule"}, {"key": "looks", "value": "bad", "effect": "NoSchedule"}]</pre>

Parameter	Type	Description
k8sTags	Map<String, String>	<p>Defined in key-value pairs. A maximum of 20 key-value pairs are allowed.</p> <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query. <p>Example: "k8sTags": { "key": "value" }</p>
ecsGroupId	String	<p>ECS group ID. If this parameter is configured, nodes will be created in the specified ECS group.</p> <p>NOTE This configuration does not take effect when a node pool is created. To ensure that all nodes in a node pool are in the same ECS group, configure nodeManagement in the node pool.</p>
dedicatedHostId	String	<p>ID of the DeH to which the node is scheduled.</p> <p>NOTE This parameter is not supported when you add a node during node pool creation.</p>

Parameter	Type	Description
userTags	Array of UserTag objects	<p>Cloud server tag. The key of a tag must be unique. The maximum number of custom tags supported by CCE depends on the region and cannot exceed 8. When creating a node, you can specify the initial value for this parameter and this field is not returned during query. In using node pools, the initial value can be specified in the node template and this field is returned during query. In other scenarios, this field is not returned during query.</p> <p>NOTE Use only letters, Unicode characters, digits, special characters(-,_). Max characters: 36</p>
runtime	Runtime object	<p>Container runtime:</p> <ul style="list-style-type: none">Clusters of v1.25 or earlier: docker.Clusters of v1.25 or later: Container runtime varies with the OS. For nodes running EulerOS 2.5 or EulerOS 2.8, the default container runtime is docker. For nodes running other OSs, the default container runtime is containerd.

Parameter	Type	Description
initializedConditions	Array of strings	<p>Custom initialization flag, which is left blank by default.</p> <p>Before CCE nodes are initialized, node.cloudprovider.kubernetes.io/uninitialized is added to the nodes to prevent pods from being scheduled to these nodes. When creating a node, you can configure the initializedConditions parameter to control the taint removal time. By default, the timeout period is not configured.</p> <p>Example:</p> <ol style="list-style-type: none">1. Create a node and add parameter "initializedConditions": ["CCEInitial", "CustomedInitial"].2. After custom initialization is complete, CCE will call a Kubernetes API (for example, PATCH /v1/nodes/{node_ip}/status) to update the node conditions by adding two labels of types CCEInitial and CustomedInitial and setting the status to True, as shown in the following: <pre>status: conditions: - type: CCEInitial status: 'True' - type: CustomedInitial status: 'True'</pre> <ol style="list-style-type: none">1. CCE polls status.Conditions of nodes to check whether there are conditions of types CCEInitial and CustomedInitial. If such conditions exist and the status is True, the node initialization is complete and the initialization taint is removed.2. initializedConditions allows you to configure a timeout period during node creation. For example, "initializedConditions": ["CCEInitial:15m", "CustomedInitial:15m"] indicates that the timeout period is 15 minutes. After the timeout period is reached, the initialization conditions will be automatically ignored and the initialization taint will be removed when CCE polls the node.<ul style="list-style-type: none">• Use only letters and digits. Max. characters: 20.• Max. flags: 2.• The unit of the timeout period is minute (m).

Parameter	Type	Description
extendParam	NodeExtendParam object	Extended parameters for creating a node.
hostnameConfig	HostnameConfig object	Kubernetes node name configuration parameter, which is supported by clusters of v1.23.6-r0 to v1.25 or clusters of v1.25.2-r0 or later versions.

Table 4-608 Login

Parameter	Type	Description
sshKey	String	Name of the key pair used for login.

Table 4-609 UserPassword

Parameter	Type	Description
username	String	Login account. Defaults to root .
password	String	If a username and a password are used to create a node, this field is shielded in the response body. A password must meet the following complexity requirements: <ul style="list-style-type: none">• Contains 8 to 26 characters.• Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters (!@\$%^_=+[{}]:./?~#*)• Cannot contain the username or the username spelled backwards. The password field must be salted during node creation. For details, see Adding a Salt in the password Field When Creating a Node.

Table 4-610 Volume

Parameter	Type	Description
size	Integer	Disk size, in GB. <ul style="list-style-type: none">• System disk: 40 to 1024 -Value range for data disks: 100 to 32768

Parameter	Type	Description
volumetype	String	Disk type. For details about possible values, see the description of the root_volume parameter in the API used to create an ECS. <ul style="list-style-type: none">• SAS: high I/O SAS disk• SSD: ultra-high I/O SSD disk• SATA: common I/O SATA disk. SATA disks have been removed from EVS. You can find them attached only on existing nodes.
extendParam	Map<String, Object>	Extended disk parameters, defined in extendparam in the API used to create an ECS.
cluster_id	String	ID of the storage pool used by the ECS system disk. This field is used only for DeC clusters, which functions as dssPoolID , that is, the ID of the DSS storage pool.
cluster_type	String	Storage class of the cloud server system disk. The value is always dss . This field is used only for DeC clusters.
hw:passthrough	Boolean	<ul style="list-style-type: none">• Pay attention to this field if your ECS is SDI-compliant. If the value of this field is true, an SCSI disk will be created.• If the node pool type is ElasticBMS, this field must be set to true.• If a node specification involves local disks and EVS disks at the same time, set the disk initialization parameters. For details, see Attaching Disks to a Node.
metadata	VolumeMetadata object	EVS disk encryption information. This field is mandatory only when you need to encrypt the system disk or data disks of the node to be created.

Table 4-611 VolumeMetadata

Parameter	Type	Description
_system_encrypted	String	Whether the EVS disk is encrypted. The value 0 indicates that the EVS disk is not encrypted, and the value 1 indicates that the EVS disk is encrypted. If this parameter is not specified, EVS disks will not be encrypted by default.

Parameter	Type	Description
<code>_system_cm_kid</code>	String	CMK ID, which indicates encryption in metadata . This field is used with _system_encrypted .

Table 4-612 Storage

Parameter	Type	Description
<code>storageSelectors</code>	Array of StorageSelectors objects	Disk selection. Matched disks are managed according to matchLabels and storageType .
<code>storageGroups</code>	Array of StorageGroups objects	A storage group consists of multiple storage devices. It is used to divide storage space.

Table 4-613 StorageSelectors

Parameter	Type	Description
<code>name</code>	String	Selector name, used as the index of selectorNames in storageGroup . Therefore, the name of each selector must be unique.
<code>storageType</code>	String	Specifies the storage type. Currently, only evs (EVS volumes) and local (local volumes) are supported. The local storage does not support disk selection. All local disks will form a VG. Therefore, only one storageSelector of the local type is allowed.
<code>matchLabels</code>	matchLabels object	Matching field of an EVS volume. The size , volumeType , metadataEncrypted , metadataCmkid and count fields are supported.

Table 4-614 matchLabels

Parameter	Type	Description
<code>size</code>	String	Matched disk size. If this parameter is left unspecified, the disk size is not limited. Example: 100
<code>volumeType</code>	String	EVS disk type. SSD , GPSSD , SAS , ESSD , and SATA are supported.

Parameter	Type	Description
metadataEncrypted	String	Disk encryption identifier. 0 indicates that the disk is not encrypted, and 1 indicates that the disk is encrypted.
metadataCmkId	String	Customer master key ID of an encrypted disk. The value is a 36-byte string.
count	String	Number of disks to be selected. If this parameter is left blank, all disks of this type are selected.

Table 4-615 StorageGroups

Parameter	Type	Description
name	String	Name of a virtual storage group, which must be unique. NOTE <ul style="list-style-type: none">• If cceManaged is set to true, the name must be set to vgpass.• If the data disk is used as a temporary storage volume, the name must be vg-everest-localvolume-ephemeral.• If the data disk is used as a persistent storage volume, the name must be vg-everest-localvolume-persistent.
cceManaged	Boolean	Storage space for Kubernetes and runtime components. Only one group can be set to true . If this parameter is left blank, the default value false is used.
selectorNames	Array of strings	This parameter corresponds to name in storageSelectors . A group can match multiple selectors, but a selector can match only one group.
virtualSpaces	Array of VirtualSpace objects	Detailed management of space configuration in a group.

Table 4-616 VirtualSpace

Parameter	Type	Description
name	String	Name of a virtualSpace. <ul style="list-style-type: none">● Kubernetes: Kubernetes space configuration. lvmConfig needs to be configured.● runtime: runtime space configuration. runtimeConfig needs to be configured.● user: user space configuration. lvmConfig needs to be configured.
size	String	Size of a virtualSpace. The value must be an integer in percentage. Example: 90%. NOTE The sum of the percentages of all virtualSpaces in a group cannot exceed 100%.
lvmConfig	LVMConfig object	LVM configurations, applicable to kubernetes and user spaces. Note that one virtual space supports only one config.
runtimeConfig	RuntimeConfig object	runtime configurations, applicable to the runtime space. Note that one virtual space supports only one config.

Table 4-617 LVMConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.
path	String	Path to which the disk is attached. This parameter takes effect only in user configuration. The value is an absolute path. Digits, letters, periods (.), hyphens (-), and underscores (_) are allowed.

Table 4-618 RuntimeConfig

Parameter	Type	Description
lvType	String	LVM write mode. linear indicates the linear mode. striped indicates the striped mode, in which multiple disks are used to form a strip to improve disk performance.

Table 4-619 NodePublicIP

Parameter	Type	Description
ids	Array of strings	IDs of existing EIPs. The quantity cannot be greater than the number of nodes to be created. NOTE If ids has been set, you do not need to set count and eip .
count	Integer	Number of EIPs to be dynamically created. NOTE count and eip must be set at the same time.
eip	NodeEIPSpec object	EIP configuration.

Table 4-620 NodeEIPSpec

Parameter	Type	Description
iptype	String	EIP type, specified in publicip.type in the API for assigning an EIP.
bandwidth	NodeBandwidth object	Bandwidth parameters of the EIP

Table 4-621 NodeBandwidth

Parameter	Type	Description
chargemode	String	Bandwidth billing mode. <ul style="list-style-type: none">• If this field is not specified, the billing is based on bandwidth. - If the field is null, the billing is based on bandwidth.• If the field value is traffic, the billing is based on traffic.• If the value is out of the preceding options, the cloud server will fail to be created. NOTE <ul style="list-style-type: none">• Billed by bandwidth: The billing will be based on the data transmission rate (in Mbps) of public networks. This billing mode is recommended if your bandwidth usage is higher than 10%.• Billed by traffic: The billing is based on the total amount of data (in GB) transmitted over the public network. This mode is available only when you are creating a pay-per-use node. This billing mode is recommended if your bandwidth usage is lower than 10%.

Parameter	Type	Description
size	Integer	Bandwidth size, specified in bandwidth.size in the API for assigning an EIP.
sharetype	String	Bandwidth sharing type. Value options: PER (exclusive bandwidth)

Table 4-622 NodeNicSpec

Parameter	Type	Description
primaryNic	NicSpec object	Description of the primary NIC.
extNics	Array of NicSpec objects	Extension NIC NOTE This parameter is not supported when you add a node to a node pool.

Table 4-623 NicSpec

Parameter	Type	Description
subnetId	String	Network ID of the subnet to which a NIC belongs. If subnetId is not specified when a primary NIC is creating, the cluster subnet will be used. If subnetList is also configured for a node pool, the subnetList field is used for adding subnets to the node pool. When creating an extension NIC, you must specify subnetId .
fixedIps	Array of strings	The IP address of the primary ENI is specified using fixedIps . The number of IP addresses cannot be greater than the number of created nodes. Either fixedIps or ipBlock can be specified. fixedIps cannot be specified for extension ENIs.
ipBlock	String	CIDR format of the primary NIC IP range. The IP address of the created node falls in this range. fixedIps and ipBlock cannot be specified at the same time.

Table 4-624 Taint

Parameter	Type	Description
key	String	Key.
value	String	Value.
effect	String	Effect.

Table 4-625 UserTag

Parameter	Type	Description
key	String	Key of the cloud server label. The value cannot start with CCE- or <code>_type_baremetal</code> .
value	String	Value of the cloud server label.

Table 4-626 Runtime

Parameter	Type	Description
name	String	Container runtime. Default value: <ul style="list-style-type: none">Clusters earlier than v1.25: The default value is <code>docker</code>.Clusters of v1.25 or later: The default container runtime varies depending on the OS. For nodes running EulerOS 2.5, the default container runtime is <code>docker</code>; for nodes running other OSs, the default container runtime is <code>containerd</code>.

Table 4-627 NodeExtendParam

Parameter	Type	Description
ecs:performancetype	String	ECS flavor types. This field is returned in the response.

Parameter	Type	Description
maxPods	Integer	<p>Maximum number of pods that can be created on a node, including the default system pods. Value range: 16 to 256.</p> <p>This limit prevents the node from being overloaded of pods.</p> <p>The number of pods that can be created on a node is determined by multiple parameters. For details, see Maximum Number of Pods That Can Be Created on a Node.</p>
DockerLVMConfigOverride	String	<p>Docker data disk configuration item. (This parameter has been discarded. Use the storage field instead.) Example default configuration:</p> <pre>"DockerLVMConfigOverride":"dockerThinpool=vgpaas/ 90%VG;kubernetesLV=vgpaas/ 10%VG;diskType=evs;lvType=linear"</pre> <p>By default, if no VD disk is available, an error occurs because the data disk fails to be found. Set diskType based on the actual drive letter type. The following fields are included:</p> <ul style="list-style-type: none"> • userLV (optional): size of the user space, for example, vgpaas/20%VG. • userPath (optional): mount path of the user space, for example, /home/wqt-test. • diskType: disk type. Currently, only evs, hdd, and ssd are supported. • lvType: type of a logic volume. The value can be linear or striped. • dockerThinpool: Docker space size, for example, vgpaas/60%VG. • kubernetesLV: kubelet space size, for example, vgpaas/20%VG.

Parameter	Type	Description
dockerBaseSize	Integer	<p>Available disk space of a single container on a node, in GB.</p> <p>If this parameter is left blank or is set to 0, the default value is used. In Device Mapper mode, the default value is 10. In OverlayFS mode, the available space of a single container is not limited by default, and the dockerBaseSize setting takes effect only on EulerOS nodes in the cluster of the new version.</p> <p>For details about how to allocate the space for the container runtime, see Data Disk Space Allocation.</p> <p>When Device Mapper is used, you are advised to set dockerBaseSize to a value less than or equal to 80 GB. If the value is too large, the container runtime may fail to be started due to long initialization. If there are special requirements for the container disk space, you can mount an external or local storage device.</p>
publicKey	String	Public key of a node.
alpha.cce/preInstall	String	<p>Pre-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/postInstall	String	<p>Post-installation script.</p> <p>NOTE The input value must be Base64-encoded. (Command: echo -n "Content to be encoded" base64)</p>
alpha.cce/NodeImageID	String	This parameter is required when a custom image is used to create a BMS node.
chargingMode	Integer	Billing mode of a node. This parameter has been deprecated. Use the billingMode parameter in NodeSpec .
agency_name	String	<p>Name of an agency</p> <p>An agency is created by a tenant administrator on Identity and Access Management (IAM) to provide temporary credentials for CCE nodes to access cloud servers. This parameter is returned only when it is transferred during node creation.</p>
kubeReservedMem	Integer	Reserved node memory, which is reserved for Kubernetes components.

Parameter	Type	Description
systemReservedMem	Integer	Reserved node memory, which is reserved for system components.
init-node-password	String	Node password. If this parameter is used as a response parameter, asterisks (*) will be displayed.

Table 4-628 HostnameConfig

Parameter	Type	Description
type	String	<p>Configuration type of the Kubernetes node name. The default value is privatelp.</p> <ul style="list-style-type: none"> • privatelp: The Kubernetes node is named after its IP address. • cceNodeName: The Kubernetes node is named after the CCE node. <p>NOTE</p> <ul style="list-style-type: none"> • For a node which is configured using cceNodeName, the name is the same as the Kubernetes node name and the ECS name. The node name cannot be changed. If the ECS name is changed on the ECS console, the node name will retain unchanged after ECS synchronization. • For a node which is configured using cceNodeName, to avoid a conflict between Kubernetes nodes, the system automatically adds a suffix to each node name. The suffix is in the format of A hyphen (-) Five random characters. The value of the random characters is a lowercase letter or a digit ranging from 0 to 9.

Table 4-629 NodePoolNodeAutoscaling

Parameter	Type	Description
enable	Boolean	Whether to enable auto scaling.
minNodeCount	Integer	Minimum number of nodes allowed if auto scaling is enabled. The value cannot be greater than the maximum number of nodes allowed by the cluster specifications.
maxNodeCount	Integer	Maximum number of nodes allowed if auto scaling is enabled. This value must be greater than or equal to the value of minNodeCount and cannot exceed the maximum number of nodes in the cluster specifications.

Parameter	Type	Description
scaleDownCooldownTime	Integer	Interval between two scaling operations, in minutes. During this period, nodes added after a scale-up will not be deleted.
priority	Integer	Weight of a node pool. A node pool with a higher weight has a higher priority during scaling.

Table 4-630 NodeManagement

Parameter	Type	Description
serverGroupReference	String	Cloud server group ID. If this field is specified, all nodes in the node pool will be created in this group. The group ID can be specified only when you create the node pool and cannot be modified. When you specify a cloud server group, the number of nodes in the node pool cannot exceed the group quota.

Table 4-631 SecurityID

Parameter	Type	Description
id	String	Security group ID

Table 4-632 DeleteNodePoolStatus

Parameter	Type	Description
currentNode	Integer	Total number of nodes in the current node pool (excluding the nodes that are being deleted).
creatingNode	Integer	Number of nodes that are being created in the node pool.
deletingNode	Integer	Number of nodes that are being deleted in the current node pool.

Parameter	Type	Description
phase	String	<p>Node pool status. Options:</p> <ul style="list-style-type: none">• Null: The node pool is available. (The number of nodes in the current node pool has reached the expected value, and no node scaling is being performed.)• Synchronizing: The node pool is being scaled. (The number of nodes in the current node pool has not reached the expected value, and no node scaling is being performed.)• Synchronized: The node pool scaling is pending. (The number of nodes in the current node pool has not reached the expected value, or node scaling is being performed.)• SoldOut: The node pool cannot be scaled out. (This field is used in multiple scenarios, for example, resources in the node pool have been sold out or the resource quota is insufficient.) <p>NOTE This node pool status has been deprecated. It is reserved only for compatibility. Do not use it anymore. Use the following instead:</p> <ul style="list-style-type: none">• Node pool scaling status: You can obtain the status of the current node pool using parameters such as currentNode, creatingNode, or deletingNode.• Node pool scale-out: You can use conditions to obtain the detailed status of a node pool. Scalable can replace SoldOut.• Deleting: The node pool is being deleted.• Error: An error occurred in the node pool.
jobId	String	ID of a job executed on the node pool.
conditions	Array of NodePoolCondition objects	Node pool status details. For details, see the definition of Condition .

Table 4-633 NodePoolCondition

Parameter	Type	Description
type	String	Condition type. The options are as follows: <ul style="list-style-type: none">• Scalable: whether a node pool can be scaled. If the status is False, node pool scaling will not be triggered again.• QuotaInsufficient: Quotas on which node pool scaling depends are insufficient, affecting the node pool scaling status.• ResourceInsufficient: Resources on which node pool scaling depends are insufficient, affecting the node pool scaling status.• UnexpectedError: The node pool fails to be scaled out due to unexpected reasons, affecting the node pool scaling status.• Error: A node pool error occurs. A common trigger is deletion failure.
status	String	Current status of Condition . The options are as follows: <ul style="list-style-type: none">• "True"• "False"
lastProbeTime	String	Time when the status was last checked
lastTransitTime	String	Time when the status was last changed
reason	String	Reason why the status was last changed
message	String	Detailed condition description

Example Requests

None

Example Responses

Status code: 200

The job for deleting the node pool is successfully delivered.

```
{  
  "kind": "NodePool",  
  "apiVersion": "v3",  
  "metadata": {  
    "name": "lc-it-nodepool-79796",  
    "uid": "99addaa2-69eb-11ea-a592-0255ac1001bb"  
  },  
  "spec": {  
    "type": "vm",  
    "nodeTemplate": {  
      "image": "centos:7",  
      "cpu": 2,  
      "memory": 4096  
    }  
  }  
}
```

```
"flavor" : "s6.large.2",
"az" : "*****",
"os" : "EulerOS 2.5",
"login" : {
    "sshKey" : "KeyPair-001"
},
"rootVolume" : {
    "volumetype" : "SAS",
    "size" : 40
},
"dataVolumes" : [ {
    "volumetype" : "SAS",
    "size" : 100,
    "extendParam" : {
        "useType" : "docker"
    }
} ],
"publicIP" : {
    "eip" : {
        "bandwidth" : { }
    }
},
"nodeNicSpec" : {
    "primaryNic" : {
        "subnetId" : "7e767d10-7548-4df5-ad72-aeac1d08bd8a"
    }
},
"billingMode" : 0,
"extendParam" : {
    "maxPods" : 110
},
"k8sTags" : {
    "cce.cloud.com/cce-nodepool" : "lc-it-nodepool-79796"
},
"autoscaling" : { },
"nodeManagement" : { }
},
"status" : {
    "phase" : "Deleting",
    "jobId" : "3281fa02-69ee-11ea-a592-0255ac1001bb"
}
```

Status Codes

Status Code	Description
200	The job for deleting the node pool is successfully delivered.

Error Codes

See [Error Codes](#).

4.5 Add-on Management

4.5.1 Installing an Add-on Instance

Function

This API is used to install an add-on instance by using an add-on template.

URI

POST /api/v3/addons

Request Parameters

Table 4-634 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-635 Request body parameters

Parameter	Mandatory	Type	Description
kind	Yes	String	API type. The value is fixed at Addon and cannot be changed. Any user-defined value is invalid.
apiVersion	Yes	String	API version. The value is fixed at v3 and cannot be changed. Any user-defined value is invalid.
metadata	Yes	AddonMetadata object	Basic information about the object. Metadata is a collection of attributes.
spec	Yes	InstanceRequestSpec object	Detailed description of add-on installation or upgrade.

Table 4-636 AddonMetadata

Parameter	Mandatory	Type	Description
uid	No	String	Unique ID
name	No	String	Add-on name
alias	No	String	Add-on alias
labels	No	Map<String, String>	Add-on labels in key-value pairs. This is a reserved field and does not take effect.
annotations	No	Map<String, String>	Add-on annotations in the format of key-value pairs. <ul style="list-style-type: none">• For add-on installation, the value is fixed at <code>{"addon.install/type":"install"}</code>.• For add-on upgrade, the value is fixed at <code>{"addon.upgrade/type":"upgrade"}</code>.
updateTimestamp	No	String	Updated at
creationTimestamp	No	String	Created at

Table 4-637 InstanceRequestSpec

Parameter	Mandatory	Type	Description
version	No	String	Version of the add-on to install or upgrade, for example, 1.0.0 . <ul style="list-style-type: none">• Installation: This parameter is optional. If not specified, the latest version supported by the cluster is used.• Upgrade: This parameter is mandatory. The version number must be specified.
clusterID	Yes	String	Cluster ID.

Parameter	Mandatory	Type	Description
values	Yes	Map<String, Object>	Add-on template installation parameters (varying depending on the add-on). During the add-on upgrade, you need to specify all the installation parameters. If the parameters are not specified, the default values in the add-on template are used. The current add-on installation parameters can be obtained through the API for querying add-on instances.
addonTemplateName	Yes	String	Name of the add-on template to be installed, for example, coredns .

Response Parameters

Status code: 201

Table 4-638 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Addon and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	AddonMetadata object	Basic information about the object. Metadata is a collection of attributes.
spec	InstanceSpec object	Detailed description of the add-on instance.
status	AddonInstanceState object	Add-on instance status.

Table 4-639 AddonMetadata

Parameter	Type	Description
uid	String	Unique ID
name	String	Add-on name

Parameter	Type	Description
alias	String	Add-on alias
labels	Map<String, String>	Add-on labels in key-value pairs. This is a reserved field and does not take effect.
annotations	Map<String, String>	Add-on annotations in the format of key-value pairs. <ul style="list-style-type: none">• For add-on installation, the value is fixed at {"addon.install/type":"install"}.• For add-on upgrade, the value is fixed at {"addon.upgrade/type":"upgrade"}.
updateTimestamp	String	Updated at
creationTimestamp	String	Created at

Table 4-640 InstanceSpec

Parameter	Type	Description
clusterID	String	Cluster ID.
version	String	Add-on template version, for example, 1.0.0 .
addonTemplate Name	String	Add-on template name, for example, coredns .
addonTemplate Type	String	Add-on template type.
addonTemplate Logo	String	URL for obtaining the add-on template logo.
addonTemplate Labels	Array of strings	Labels of the add-on template.
description	String	Add-on template description.
values	Map<String, Object>	Add-on template installation parameters (varying depending on the add-on). Set the parameters accordingly.

Table 4-641 AddonInstanceStatus

Parameter	Type	Description
status	String	<p>Statuses of add-on instances. Options:</p> <ul style="list-style-type: none">• running: All of the add-on instances are running and the add-on is running properly.• abnormal: The add-on instances are abnormal and the add-on cannot be used. Click the add-on name to view exceptions.• installing: The add-on is being installed.• installFailed: Installing the add-on failed. In this case, uninstall the add-on and then reinstall it.• upgrading: The add-on is being upgraded.• upgradeFailed: Upgrading the add-on failed. In this case, upgrade the add-on again or uninstall the add-on and reinstall it.• deleting: The add-on is being deleted.• deleteFailed: Deleting the add-on failed. In this case, uninstall the add-on again.• deleteSuccess: Deleting the add-on succeeded.• available: Only some instances of the add-on are running. This indicates that some functions of the add-on are available.• rollbacking: The add-on is being rolled back.• rollbackFailed: Rolling back the add-on failed. In this case, roll back the add-on again or uninstall the add-on and reinstall it.• unknown: The add-on chart instance does not exist.
Reason	String	Cause of the add-on installation failure.
message	String	Installation error details.
targetVersions	Array of strings	Versions to which the current add-on version can be upgraded.
currentVersion	Versions object	Information about the current add-on version.
isRollbackable	Boolean	Whether the add-on version can be rolled back to the source version.
previousVersion	String	The add-on version before upgrade or rollback

Table 4-642 Versions

Parameter	Type	Description
version	String	Add-on version.
input	Object	Add-on installation parameters.
stable	Boolean	Whether the add-on version is a stable release.
translate	Object	Translation information used by the GUI.
supportVersions	Array of SupportVersions objects	Cluster versions that support the add-on.
creationTimestamp	String	Creation time.
updateTimestamp	String	Update time.

Table 4-643 SupportVersions

Parameter	Type	Description
clusterType	String	Cluster type that supports the add-on.
clusterVersion	Array of strings	Cluster versions that support the add-on. The value is a regular expression.

Example Requests

Install the coredns add-on of version 1.17.15. The add-on specification is 2500 QPS, and the number of add-on instances is 2.

```
{  
    "kind": "Addon",  
    "apiVersion": "v3",  
    "metadata": {  
        "annotations": {  
            "addon.install/type": "install"  
        }  
    },  
    "spec": {  
        "clusterID": "1b2ec02d-a3b2-11ec-b0d0-0255ac100099",  
        "version": "1.17.15",  
        "addonTemplateName": "coredns",  
        "values": {  
            "basic": {  
                "cluster_ip": "10.247.3.10",  
                "image_version": "1.17.15",  
                "platform": "linux-amd64",  
                "swr_addr": "<Replace_SWR_address>",  
                "swr_user": "hwofficial",  
            }  
        }  
    }  
}
```

```
        "rbac_enabled" : true
    },
    "flavor" : {
        "name" : 2500,
        "replicas" : 2,
        "resources" : [ {
            "limitsCpu" : "500m",
            "limitsMem" : "512Mi",
            "name" : "coredns",
            "requestsCpu" : "500m",
            "requestsMem" : "512Mi"
        } ]
    },
    "custom" : {
        "stub_domains" : { },
        "upstream_nameservers" : [ ],
        "cluster_id" : "1b2ec02d-a3b2-11ec-b0d0-0255ac100099",
        "tenant_id" : "0504201b6c80256b2f08c0099f0c8fe4"
    }
}
```

Example Responses

Status code: 201

OK

```
{
  "kind" : "Addon",
  "apiVersion" : "v3",
  "metadata" : {
    "uid" : "b748aaea-a984-11ec-987b-0255ac1000bc",
    "name" : "coredns",
    "alias" : "coredns",
    "creationTimestamp" : "2022-03-22T02:06:41Z",
    "updateTimestamp" : "2022-03-22T02:06:41Z"
  },
  "spec" : {
    "clusterID" : "1b2ec02d-a3b2-11ec-b0d0-0255ac100099",
    "version" : "1.17.15",
    "addonTemplateName" : "coredns",
    "addonTemplateType" : "helm",
    "addonTemplateLogo" : "",
    "addonTemplateLabels" : [ "ServiceDiscovery" ],
    "description" : "CoreDNS is a DNS server that chains plugins and provides Kubernetes DNS Services",
    "values" : {
      "basic" : {
        "cluster_ip" : "10.247.3.10",
        "image_version" : "1.17.15",
        "platform" : "linux-amd64",
        "rbac_enabled" : true,
        "swr_addr" : "",
        "swr_user" : "hwofficial"
      },
      "custom" : {
        "cluster_id" : "1b2ec02d-a3b2-11ec-b0d0-0255ac100099",
        "stub_domains" : { },
        "tenant_id" : "0504201b6c80256b2f08c0099f0c8fe4",
        "upstream_nameservers" : [ ]
      }
    },
    "flavor" : {
        "name" : 2500,
        "replicas" : 2,
        "resources" : [ {
            "limitsCpu" : "500m",
            "limitsMem" : "512Mi",
            "name" : "coredns",
            "requestsCpu" : "500m",
            "requestsMem" : "512Mi"
        } ]
    }
}
```

```
        "requestsCpu" : "500m",
        "requestsMem" : "512Mi"
    } ]
}
},
"status" : {
  "status" : "installing",
  "Reason" : "",
  "message" : "",
  "targetVersions" : null,
  "currentVersion" : {
    "version" : "1.17.15",
  },
  "input" : {
    "basic" : {
      "cluster_ip" : "10.247.3.10",
      "image_version" : "1.17.15",
      "platform" : "linux-amd64",
      "swr_addr" : "",
      "swr_user" : "hwofficial"
    },
    "parameters" : {
      "custom" : {
        "stub_domains" : "",
        "upstream_nameservers" : ""
      },
      "flavor1" : {
        "name" : 2500,
        "replicas" : 2,
        "resources" : [ {
          "limitsCpu" : "500m",
          "limitsMem" : "512Mi",
          "name" : "coredns",
          "requestsCpu" : "500m",
          "requestsMem" : "512Mi"
        } ]
      },
      "flavor2" : {
        "name" : 5000,
        "replicas" : 2,
        "resources" : [ {
          "limitsCpu" : "1000m",
          "limitsMem" : "1024Mi",
          "name" : "coredns",
          "requestsCpu" : "1000m",
          "requestsMem" : "1024Mi"
        } ]
      },
      "flavor3" : {
        "name" : 10000,
        "replicas" : 2,
        "resources" : [ {
          "limitsCpu" : "2000m",
          "limitsMem" : "2048Mi",
          "name" : "coredns",
          "requestsCpu" : "2000m",
          "requestsMem" : "2048Mi"
        } ]
      },
      "flavor4" : {
        "name" : 20000,
        "replicas" : 4,
        "resources" : [ {
          "limitsCpu" : "2000m",
          "limitsMem" : "2048Mi",
          "name" : "coredns",
          "requestsCpu" : "2000m",
          "requestsMem" : "2048Mi"
        } ]
      }
    }
  }
}
```

```
        }
    },
    "stable" : true,
    "translate" : {
        "en_US" : {
            "addon" : {
                "changeLog" : "Supported CCE clusters of v1.21.",
                "description" : "CoreDNS is a DNS server that chains plugins and provides Kubernetes DNS Services"
            },
            "description" : {
                "Parameters.custom.stub_domains" : "The target nameserver may itself be a Kubernetes service. For instance, you can run your own copy of dnsmasq to export custom DNS names into the ClusterDNS namespace, a JSON map using a DNS suffix key (e.g. \"acme.local\") and a value consisting of a JSON array of DNS IPs.",
                "Parameters.custom.upstream_nameservers" : "If specified, then the values specified replace the nameservers taken by default from the node's /etc/resolv.conf. Limits:a maximum of three upstream nameservers can be specified, A JSON array of DNS IPs.",
                "Parameters.flavor1.description" : "Concurrent domain name resolution ability - External domain name: 2500 qps, Internal domain name: 10000 qps",
                "Parameters.flavor1.name" : 2500,
                "Parameters.flavor2.description" : "Concurrent domain name resolution ability - External domain name: 5000 qps, Internal domain name: 20000 qps",
                "Parameters.flavor2.name" : 5000,
                "Parameters.flavor3.description" : "Concurrent domain name resolution ability - External domain name: 10000 qps, Internal domain name: 40000 qps",
                "Parameters.flavor3.name" : 10000,
                "Parameters.flavor4.description" : "Concurrent domain name resolution ability - External domain name: 20000 qps, Internal domain name: 80000 qps",
                "Parameters.flavor4.name" : 20000
            },
            "key" : {
                "Parameters.custom.stub_domains" : "stub domain",
                "Parameters.custom.upstream_nameservers" : "upstream nameservers"
            }
        },
        "fr_FR" : {
            "addon" : {
                "changeLog" : "Prise en charge du cluster 1.21.",
                "description" : "Un serveur DNS qui enchaîne les plug-ins et fournit des services DNS Kubernetes."
            },
            "description" : {
                "Parameters.custom.stub_domains" : "Le serveur de noms cible peut lui-même être un service Kubernetes. Par exemple, vous pouvez exécuter votre propre copie de dnsmasq pour exporter des noms DNS personnalisés dans l'espace de noms ClusterDNS, une carte JSON à l'aide d'une clé de suffixe DNS (par exemple, «acme.local») et une valeur constituée d'un tableau JSON d'adresses IP DNS.",
                "Parameters.custom.upstream_nameservers" : "Si spécifié, les valeurs spécifiées remplacent les serveurs de noms pris par défaut dans le fichier /etc/resolv.conf du nœud. Limites: un maximum de trois serveurs de noms en amont peuvent être spécifiés, un tableau JSON d'adresses IP DNS.",
                "Parameters.flavor1.description" : "Capacité de résolution de nom de domaine simultanée - Nom de domaine externe: 2500 qps, Nom de domaine interne: 10000 qp",
                "Parameters.flavor1.name" : 2500,
                "Parameters.flavor2.description" : "Capacité de résolution de nom de domaine simultanée - Nom de domaine externe: 5000 qps, Nom de domaine interne: 20000 qp",
                "Parameters.flavor2.name" : 5000,
                "Parameters.flavor3.description" : "Capacité de résolution de nom de domaine simultanée - Nom de domaine externe: 10000 qps, Nom de domaine interne: 40000 qp",
                "Parameters.flavor3.name" : 10000,
                "Parameters.flavor4.description" : "Capacité de résolution de nom de domaine simultanée - Nom de domaine externe: 20000 qps, Nom de domaine interne: 80000 qp",
                "Parameters.flavor4.name" : 20000
            },
            "key" : {
                "Parameters.custom.stub_domains" : "domaine stub",
                "Parameters.custom.upstream_nameservers" : "serveurs de noms en amont"
            }
        },
        "zh_CN" : {
            "addon" : {
```

```
        "changeLog" : "",
        "description" : ""
    },
    "description" : {
        "Parameters.custom.stub_domains" : "",
        "Parameters.custom.upstream_nameservers" : "",
        "Parameters.flavor1.description" : "",
        "Parameters.flavor1.name" : 2500,
        "Parameters.flavor2.description" : "",
        "Parameters.flavor2.name" : 5000,
        "Parameters.flavor3.description" : "",
        "Parameters.flavor3.name" : 10000,
        "Parameters.flavor4.description" : "",
        "Parameters.flavor4.name" : 20000
    },
    "key" : {
        "Parameters.custom.stub_domains" : "",
        "Parameters.custom.upstream_nameservers" : ""
    }
},
"supportVersions" : null,
"creationTimestamp" : "2021-12-14T13:43:15Z",
"updateTimestamp" : "2022-01-11T14:32:10Z"
}
}
```

Status Codes

Status Code	Description
201	OK

Error Codes

See [Error Codes](#).

4.5.2 Listing Add-on Templates

Function

This API is used to query add-on templates.

URI

GET /api/v3/addontemplates

Table 4-644 Query Parameters

Parameter	Mandatory	Type	Description
addon_template_name	No	String	Add-on name or alias for search. If this parameter is not specified, all the add-ons will be searched.

Request Parameters

Table 4-645 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-646 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Addon and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
items	Array of AddonTemplate objects	List of add-on templates.

Table 4-647 AddonTemplate

Parameter	Type	Description
kind	String	API type. The value is fixed at Addon and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	AddonMetadata object	Basic information about the object. Metadata is a collection of attributes.

Parameter	Type	Description
spec	TemplateSpec object	Detailed description of the add-on template.

Table 4-648 AddonMetadata

Parameter	Type	Description
uid	String	Unique ID
name	String	Add-on name
alias	String	Add-on alias
labels	Map<String, String>	Add-on labels in key-value pairs. This is a reserved field and does not take effect.
annotations	Map<String, String>	Add-on annotations in the format of key-value pairs. <ul style="list-style-type: none">• For add-on installation, the value is fixed at {"addon.install/type":"install"}.• For add-on upgrade, the value is fixed at {"addon.upgrade/type":"upgrade"}.
updateTimestamp	String	Updated at
creationTimestamp	String	Created at

Table 4-649 TemplateSpec

Parameter	Type	Description
type	String	Template type. The value is helm or static .
require	Boolean	Whether the add-on is mandatory.
labels	Array of strings	Group to which the template belongs.
logoURL	String	URL of the logo image.
readmeURL	String	Add-on details and usage description.
description	String	Description
versions	Array of Versions objects	Template version details.

Table 4-650 Versions

Parameter	Type	Description
version	String	Add-on version.
input	Object	Add-on installation parameters.
stable	Boolean	Whether the add-on version is a stable release.
translate	Object	Translation information used by the GUI.
supportVersions	Array of SupportVersions objects	Cluster versions that support the add-on.
creationTimestamp	String	Creation time.
updateTimestamp	String	Update time.

Table 4-651 SupportVersions

Parameter	Type	Description
clusterType	String	Cluster type that supports the add-on.
clusterVersion	Array of strings	Cluster versions that support the add-on. The value is a regular expression.

Example Requests

None

Example Responses

Status code: 200

OK

```
"labels" : [ "ServiceDiscovery" ],
"logoURL" : "",
"description" : "CoreDNS is a DNS server that chains plugins and provides Kubernetes DNS Services",
"versions" : [ {
  "version" : "1.13.6",
  "input" : {
    "basic" : {
      "cluster_ip" : "10.247.3.10",
      "ipv6" : false,
      "platform" : "linux-amd64",
      "swr_addr" : "100.125.16.65:20202",
      "swr_user" : "hwofficial"
    },
    "parameters" : {
      "custom" : {
        "stub_domains" : "",
        "upstream_nameservers" : ""
      }
    }
  },
  "flavor1" : {
    "name" : 2500,
    "replicas" : 2,
    "resources" : [ {
      "limitsCpu" : "500m",
      "limitsMem" : "512Mi",
      "name" : "coredns",
      "requestsCpu" : "500m",
      "requestsMem" : "512Mi"
    } ]
  },
  "flavor2" : {
    "name" : 5000,
    "replicas" : 2,
    "resources" : [ {
      "limitsCpu" : "1000m",
      "limitsMem" : "1024Mi",
      "name" : "coredns",
      "requestsCpu" : "1000m",
      "requestsMem" : "1024Mi"
    } ]
  },
  "flavor3" : {
    "name" : 10000,
    "replicas" : 2,
    "resources" : [ {
      "limitsCpu" : "2000m",
      "limitsMem" : "2048Mi",
      "name" : "coredns",
      "requestsCpu" : "2000m",
      "requestsMem" : "2048Mi"
    } ]
  },
  "flavor4" : {
    "name" : 20000,
    "replicas" : 4,
    "resources" : [ {
      "limitsCpu" : "2000m",
      "limitsMem" : "2048Mi",
      "name" : "coredns",
      "requestsCpu" : "2000m",
      "requestsMem" : "2048Mi"
    } ]
  }
},
"stable" : true,
"translate" : {
  "en_US" : {
    "addon" : {
      "changeLog" : "Support for clusters with new version",
      "description" : "CoreDNS is a DNS server that chains plugins and provides Kubernetes DNS Services",
      "flavor1" : {
        "name" : 2500,
        "replicas" : 2,
        "resources" : [ {
          "limitsCpu" : "500m",
          "limitsMem" : "512Mi",
          "name" : "coredns",
          "requestsCpu" : "500m",
          "requestsMem" : "512Mi"
        } ]
      },
      "flavor2" : {
        "name" : 5000,
        "replicas" : 2,
        "resources" : [ {
          "limitsCpu" : "1000m",
          "limitsMem" : "1024Mi",
          "name" : "coredns",
          "requestsCpu" : "1000m",
          "requestsMem" : "1024Mi"
        } ]
      },
      "flavor3" : {
        "name" : 10000,
        "replicas" : 2,
        "resources" : [ {
          "limitsCpu" : "2000m",
          "limitsMem" : "2048Mi",
          "name" : "coredns",
          "requestsCpu" : "2000m",
          "requestsMem" : "2048Mi"
        } ]
      },
      "flavor4" : {
        "name" : 20000,
        "replicas" : 4,
        "resources" : [ {
          "limitsCpu" : "2000m",
          "limitsMem" : "2048Mi",
          "name" : "coredns",
          "requestsCpu" : "2000m",
          "requestsMem" : "2048Mi"
        } ]
      }
    }
  }
}
```

```
        "description" : "CoreDNS is a DNS server that chains plugins and provides Kubernetes DNS Services"
    },
    "description" : {
        "Parameters.custom.stub_domains" : "The target nameserver may itself be a Kubernetes service. For instance, you can run your own copy of dnsmasq to export custom DNS names into the ClusterDNS namespace, a JSON map using a DNS suffix key (e.g. \"acme.local\") and a value consisting of a JSON array of DNS IPs.",
        "Parameters.custom.upstream_nameservers" : "If specified, then the values specified replace the nameservers taken by default from the node's /etc/resolv.conf. Limits:a maximum of three upstream nameservers can be specified, A JSON array of DNS IPs.",
        "Parameters.flavor1.description" : "Concurrent domain name resolution ability - External domain name: 2500 qps, Internal domain name: 10000 qps",
        "Parameters.flavor1.name" : 2500,
        "Parameters.flavor2.description" : "Concurrent domain name resolution ability - External domain name: 5000 qps, Internal domain name: 20000 qps",
        "Parameters.flavor2.name" : 5000,
        "Parameters.flavor3.description" : "Concurrent domain name resolution ability - External domain name: 10000 qps, Internal domain name: 40000 qps",
        "Parameters.flavor3.name" : 10000,
        "Parameters.flavor4.description" : "Concurrent domain name resolution ability - External domain name: 20000 qps, Internal domain name: 80000 qps",
        "Parameters.flavor4.name" : 20000
    },
    "key" : {
        "Parameters.custom.stub_domains" : "stub domain",
        "Parameters.custom.upstream_nameservers" : "upstream nameservers"
    }
},
"fr_FR" : {
    "addon" : {
        "changeLog" : "Prise en charge des clusters avec une nouvelle version",
        "description" : "Un serveur DNS qui enchaîne les plug-ins et fournit des services DNS Kubernetes."
    },
    "description" : {
        "Parameters.custom.stub_domains" : "Le serveur de noms cible peut lui-même être un service Kubernetes. Par exemple, vous pouvez exécuter votre propre copie de dnsmasq pour exporter des noms DNS personnalisés dans l'espace de noms ClusterDNS, une carte JSON à l'aide d'une clé de suffixe DNS (par exemple, «acme.local») et une valeur constituée d'un tableau JSON d'adresses IP DNS.",
        "Parameters.custom.upstream_nameservers" : "Si spécifié, les valeurs spécifiées remplacent les serveurs de noms pris par défaut dans le fichier /etc/resolv.conf du noeud. Limites: un maximum de trois serveurs de noms en amont peuvent être spécifiés, un tableau JSON d'adresses IP DNS.",
        "Parameters.flavor1.description" : "Capacité de résolution de nom de domaine simultanée - Nom de domaine externe: 2500 qps, Nom de domaine interne: 10000 qp",
        "Parameters.flavor1.name" : 2500,
        "Parameters.flavor2.description" : "Capacité de résolution de nom de domaine simultanée - Nom de domaine externe: 5000 qps, Nom de domaine interne: 20000 qp",
        "Parameters.flavor2.name" : 5000,
        "Parameters.flavor3.description" : "Capacité de résolution de nom de domaine simultanée - Nom de domaine externe: 10000 qps, Nom de domaine interne: 40000 qp",
        "Parameters.flavor3.name" : 10000,
        "Parameters.flavor4.description" : "Capacité de résolution de nom de domaine simultanée - Nom de domaine externe: 20000 qps, Nom de domaine interne: 80000 qp",
        "Parameters.flavor4.name" : 20000
    },
    "key" : {
        "Parameters.custom.stub_domains" : "domaine stub",
        "Parameters.custom.upstream_nameservers" : "serveurs de noms en amont"
    }
},
"zh_CN" : {
    "addon" : {
        "changeLog" : "",
        "description" : ""
    },
    "description" : {
        "Parameters.custom.stub_domains" : "",
        "Parameters.custom.upstream_nameservers" : "",
        "Parameters.flavor1.description" : ""
    }
}
```

```
"Parameters.flavor1.name" : 2500,
"Parameters.flavor2.description" : "",
"Parameters.flavor2.name" : 5000,
"Parameters.flavor3.description" : "",
"Parameters.flavor3.name" : 10000,
"Parameters.flavor4.description" : "",
"Parameters.flavor4.name" : 20000
},
"key" : {
"Parameters.custom.stub_domains" : "",
"Parameters.custom.upstream_nameservers" : ""
}
}
],
"supportVersions" : [ {
"clusterType" : "VirtualMachine",
"clusterVersion" : [ "v1.13.*" ]
}, {
"clusterType" : "BareMetal",
"clusterVersion" : [ "v1.13.*" ]
}, {
"clusterType" : "ARM64",
"clusterVersion" : [ "v1.13.*" ]
}],
"creationTimestamp" : "2021-03-18T12:51:05Z",
"updateTimestamp" : "2021-03-18T12:51:05Z"
}
]
}
]
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.5.3 Updating an Add-on Instance

Function

This API is used to update an add-on instance.

URI

PUT /api/v3/addons/{id}

Table 4-652 Path Parameters

Parameter	Mandatory	Type	Description
id	Yes	String	Add-on instance ID.

Request Parameters

Table 4-653 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-654 Request body parameters

Parameter	Mandatory	Type	Description
kind	Yes	String	API type. The value is fixed at Addon and cannot be changed. Any user-defined value is invalid.
apiVersion	Yes	String	API version. The value is fixed at v3 and cannot be changed. Any user-defined value is invalid.
metadata	Yes	AddonMetadata object	Basic information about the object. Metadata is a collection of attributes.
spec	Yes	InstanceRequestSpec object	Detailed description of add-on installation or upgrade.

Table 4-655 AddonMetadata

Parameter	Mandatory	Type	Description
uid	No	String	Unique ID
name	No	String	Add-on name
alias	No	String	Add-on alias
labels	No	Map<String, String>	Add-on labels in key-value pairs. This is a reserved field and does not take effect.

Parameter	Mandatory	Type	Description
annotations	No	Map<String, String>	Add-on annotations in the format of key-value pairs. <ul style="list-style-type: none">For add-on installation, the value is fixed at <code>{"addon.install/type": "install"}</code>.For add-on upgrade, the value is fixed at <code>{"addon.upgrade/type": "upgrade"}</code>.
updateTimestamp	No	String	Updated at
creationTimestamp	No	String	Created at

Table 4-656 InstanceRequestSpec

Parameter	Mandatory	Type	Description
version	No	String	Version of the add-on to install or upgrade, for example, 1.0.0 . <ul style="list-style-type: none">Installation: This parameter is optional. If not specified, the latest version supported by the cluster is used.Upgrade: This parameter is mandatory. The version number must be specified.
clusterID	Yes	String	Cluster ID.
values	Yes	Map<String, Object>	Add-on template installation parameters (varying depending on the add-on). During the add-on upgrade, you need to specify all the installation parameters. If the parameters are not specified, the default values in the add-on template are used. The current add-on installation parameters can be obtained through the API for querying add-on instances.

Parameter	Mandatory	Type	Description
addonTemplateName	Yes	String	Name of the add-on template to be installed, for example, coredns .

Response Parameters

Status code: 200

Table 4-657 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Addon and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	AddonMetadata object	Basic information about the object. Metadata is a collection of attributes.
spec	InstanceSpec object	Detailed description of the add-on instance.
status	AddonInstanceStatus object	Add-on instance status.

Table 4-658 AddonMetadata

Parameter	Type	Description
uid	String	Unique ID
name	String	Add-on name
alias	String	Add-on alias
labels	Map<String, String>	Add-on labels in key-value pairs. This is a reserved field and does not take effect.
annotations	Map<String, String>	Add-on annotations in the format of key-value pairs. <ul style="list-style-type: none">• For add-on installation, the value is fixed at <code>{"addon.install/type": "install"}</code>.• For add-on upgrade, the value is fixed at <code>{"addon.upgrade/type": "upgrade"}</code>.

Parameter	Type	Description
updateTimestamp	String	Updated at
creationTimestamp	String	Created at

Table 4-659 InstanceSpec

Parameter	Type	Description
clusterID	String	Cluster ID.
version	String	Add-on template version, for example, 1.0.0 .
addonTemplate_name	String	Add-on template name, for example, coredns .
addonTemplate_type	String	Add-on template type.
addonTemplate_logo	String	URL for obtaining the add-on template logo.
addonTemplate_labels	Array of strings	Labels of the add-on template.
description	String	Add-on template description.
values	Map<String, Object>	Add-on template installation parameters (varying depending on the add-on). Set the parameters accordingly.

Table 4-660 AddonInstanceStatus

Parameter	Type	Description
status	String	<p>Statuses of add-on instances. Options:</p> <ul style="list-style-type: none">• running: All of the add-on instances are running and the add-on is running properly.• abnormal: The add-on instances are abnormal and the add-on cannot be used. Click the add-on name to view exceptions.• installing: The add-on is being installed.• installFailed: Installing the add-on failed. In this case, uninstall the add-on and then reinstall it.• upgrading: The add-on is being upgraded.• upgradeFailed: Upgrading the add-on failed. In this case, upgrade the add-on again or uninstall the add-on and reinstall it.• deleting: The add-on is being deleted.• deleteFailed: Deleting the add-on failed. In this case, uninstall the add-on again.• deleteSuccess: Deleting the add-on succeeded.• available: Only some instances of the add-on are running. This indicates that some functions of the add-on are available.• rollbacking: The add-on is being rolled back.• rollbackFailed: Rolling back the add-on failed. In this case, roll back the add-on again or uninstall the add-on and reinstall it.• unknown: The add-on chart instance does not exist.
Reason	String	Cause of the add-on installation failure.
message	String	Installation error details.
targetVersions	Array of strings	Versions to which the current add-on version can be upgraded.
currentVersion	Versions object	Information about the current add-on version.
isRollbackable	Boolean	Whether the add-on version can be rolled back to the source version.
previousVersion	String	The add-on version before upgrade or rollback

Table 4-661 Versions

Parameter	Type	Description
version	String	Add-on version.
input	Object	Add-on installation parameters.
stable	Boolean	Whether the add-on version is a stable release.
translate	Object	Translation information used by the GUI.
supportVersions	Array of SupportVersions objects	Cluster versions that support the add-on.
creationTimestamp	String	Creation time.
updateTimestamp	String	Update time.

Table 4-662 SupportVersions

Parameter	Type	Description
clusterType	String	Cluster type that supports the add-on.
clusterVersion	Array of strings	Cluster versions that support the add-on. The value is a regular expression.

Example Requests

Update the everest add-on to version 2.1.30.

```
{  
    "kind" : "Addon",  
    "apiVersion" : "v3",  
    "metadata" : {  
        "annotations" : {  
            "addon.upgrade/type" : "upgrade"  
        }  
    },  
    "spec" : {  
        "clusterID" : "*****",  
        "version" : "2.1.30",  
        "addonTemplateName" : "everest",  
        "values" : {  
            "basic" : {  
                "bms_url" : "*****",  
                "driver_init_image_version" : "2.1.30",  
                "ecsEndpoint" : "*****",  
                "everest_image_version" : "2.1.30",  
                "evs_url" : "*****",  
                "iam_url" : "*****",  
            }  
        }  
    }  
}
```

```
"ims_url" : "*****",
"obs_url" : "*****",
"platform" : "linux-amd64",
"sfs30_url" : "*****",
"sfs_turbo_url" : "*****",
"sfs_url" : "*****",
"supportHcs" : false,
"swr_addr" : "*****",
"swr_user" : "hwofficial",
"rbac_enabled" : true,
"cluster_version" : "v1.23"
},
"flavor" : {
"description" : "High avaialbe",
"name" : "HA",
"replicas" : 2,
"resources" : [ {
"limitsCpu" : "250m",
"limitsMem" : "2000Mi",
"name" : "everest-csi-controller",
"requestsCpu" : "250m",
"requestsMem" : "1500Mi"
}, {
"limitsCpu" : "500m",
"limitsMem" : "300Mi",
"name" : "everest-csi-driver",
"requestsCpu" : "100m",
"requestsMem" : "300Mi"
} ],
"category" : [ "CCE", "Turbo" ]
},
"custom" : {
"cluster_id" : "*****",
"csi_attacher_detach_worker_threads" : "60",
"csi_attacher_worker_threads" : "60",
"default_vpc_id" : "*****",
"disable_auto_mount_secret" : false,
"enable_node_attacher" : true,
"flow_control" : { },
"multiAZEnabled" : false,
"over_subscription" : "80",
"project_id" : "*****",
"volume_attaching_flow_ctrl" : "0"
}
}
```

Example Responses

Status code: 200

OK

```
{
"kind" : "Addon",
"apiVersion" : "v3",
"metadata" : {
"uid" : "*****",
"name" : "everest",
"alias" : "everest",
"creationTimestamp" : "2023-07-03T10:57:43Z",
"updateTimestamp" : "2023-07-03T11:24:05Z"
},
"spec" : {
"clusterID" : "*****",
"version" : "2.1.30",
"addonTemplateName" : "everest",
"addonTemplateType" : "helm",
```

```
"addonTemplateLogo" : "*****",
"addonTemplateLabels" : [ "Storage" ],
"description" : "",
"values" : {
"basic" : {
"bms_url" : "*****",
"cluster_version" : "v1.23",
"driver_init_image_version" : "2.1.30",
"ecsEndpoint" : "*****",
"everest_image_version" : "2.1.30",
"evs_url" : "*****",
"iam_url" : "*****",
"ims_url" : "*****",
"obs_url" : "*****",
"platform" : "linux-amd64",
"rbac_enabled" : true,
"sfs30_url" : "*****",
"sfs_turbo_url" : "*****",
"sfs_url" : "*****",
"supportHcs" : false,
"swr_addr" : "*****",
"swr_user" : "hwofficial"
},
"custom" : {
"cluster_id" : "*****",
"cluster_version" : "v1.23.8-r0",
"csi_attacher_detach_worker_threads" : "60",
"csi_attacher_worker_threads" : "60",
"default_vpc_id" : "*****",
"disable_auto_mount_secret" : false,
"enable_node_attacher" : false,
"flow_control" : { },
"multiAZEnabled" : false,
"over_subscription" : "80",
"project_id" : "*****",
"volume_attaching_flow_ctrl" : "0"
},
"flavor" : {
"category" : [ "CCE", "Turbo" ],
"description" : "Has only one instance",
"name" : "Single",
"replicas" : 1,
"resources" : [ {
"limitsCpu" : "250m",
"limitsMem" : "600Mi",
"name" : "everest-csi-controller",
"requestsCpu" : "250m",
"requestsMem" : "600Mi"
}, {
"limitsCpu" : "100m",
"limitsMem" : "300Mi",
"name" : "everest-csi-driver",
"requestsCpu" : "100m",
"requestsMem" : "300Mi"
} ]
},
"systemAutoInject" : {
"cluster" : {
"clusterID" : "*****",
"clusterNetworkMode" : "vpc-router",
"clusterVersion" : "v1.23.8-r0"
},
"user" : {
"projectID" : "*****"
}
}
},
"status" : {
```

```
"status" : "upgrading",
"Reason" : "addon upgrading",
"message" : "",
"targetVersions" : null,
"isRollbackable" : false,
"currentVersion" : {
    "version" : "2.1.30",
    "input" : {
        "basic" : {
            "bms_url" : "*****",
            "driver_init_image_version" : "2.1.30",
            "ecsEndpoint" : "*****",
            "everest_image_version" : "2.1.30",
            "evs_url" : "*****",
            "iam_url" : "*****",
            "ims_url" : "*****",
            "obs_url" : "*****",
            "platform" : "*****",
            "sfs30_url" : "*****",
            "sfs_turbo_url" : "*****",
            "sfs_url" : "*****",
            "supportHcs" : false,
            "swr_addr" : "*****",
            "swr_user" : "hwofficial"
        },
        "parameters" : {
            "common" : {
                "defaultVPCId" : 1234567
            },
            "custom" : {
                "cluster_id" : "",
                "csi_attacher_detach_worker_threads" : "60",
                "csi_attacher_worker_threads" : "60",
                "default_vpc_id" : "",
                "disable_auto_mount_secret" : false,
                "enable_node_attacher" : false,
                "flow_control" : { },
                "multiAZEnabled" : false,
                "over_subscription" : "80",
                "project_id" : "",
                "volume_attaching_flow_ctrl" : "0"
            },
            "flavor1" : {
                "description" : "High available",
                "name" : "HA",
                "replicas" : 2,
                "resources" : [ {
                    "limitsCpu" : "250m",
                    "limitsMem" : "1500Mi",
                    "name" : "everest-csi-controller",
                    "requestsCpu" : "250m",
                    "requestsMem" : "600Mi"
                }, {
                    "limitsCpu" : "500m",
                    "limitsMem" : "300Mi",
                    "name" : "everest-csi-driver",
                    "requestsCpu" : "100m",
                    "requestsMem" : "300Mi"
                } ]
            },
            "flavor2" : {
                "description" : "Has only one instance",
                "name" : "Single",
                "replicas" : 1,
                "resources" : [ {
                    "limitsCpu" : "250m",
                    "limitsMem" : "600Mi",
                    "name" : "everest-csi-controller",
                    "requestsCpu" : "250m",
                    "requestsMem" : "600Mi"
                } ]
            }
        }
    }
}
```

```
        "requestsMem" : "600Mi"
    }, {
        "limitsCpu" : "100m",
        "limitsMem" : "300Mi",
        "name" : "everest-csi-driver",
        "requestsCpu" : "100m",
        "requestsMem" : "300Mi"
    } ]
},
"flavor3" : {
    "description" : "custom resources",
    "name" : "custom-resources",
    "replicas" : 2,
    "resources" : [ {
        "limitsCpu" : "250m",
        "limitsMem" : "2000Mi",
        "name" : "everest-csi-controller",
        "requestsCpu" : "250m",
        "requestsMem" : "1500Mi"
    }, {
        "limitsCpu" : "500m",
        "limitsMem" : "300Mi",
        "name" : "everest-csi-driver",
        "requestsCpu" : "100m",
        "requestsMem" : "300Mi"
    } ]
}
},
"stable" : true,
"translate" : {
    "en_US" : {
        "addon" : {
            "changeLog" : "",
            "description" : ""
        },
        "description" : {
            "Parameters.flavor1.description" : "Deploy the add-on with two instances, delivering high availability but requiring more compute resources.",
            "Parameters.flavor1.name" : "HA",
            "Parameters.flavor2.description" : "Deploy the add-on with one instance.",
            "Parameters.flavor2.name" : "Standalone",
            "Parameters.flavor3.name" : "Custom"
        }
    },
    "fr_FR" : {
        "addon" : {
            "changeLog" : "",
            "description" : ""
        },
        "description" : {
            "Parameters.flavor1.description" : "Déployez avec deux instances, haute disponibilité.",
            "Parameters.flavor1.name" : "HA",
            "Parameters.flavor2.description" : "Déployez avec une seule instance.",
            "Parameters.flavor2.name" : "Célibataire",
            "Parameters.flavor3.name" : "Douane"
        }
    },
    "zh_CN" : {
        "addon" : {
            "changeLog" : "",
            "description" : ""
        },
        "description" : {
            "Parameters.flavor1.description" : "Dual-instance deployment features high availability but requires more compute resources.",
            "Parameters.flavor1.name" : "High availability",
            "Parameters.flavor2.description" : "Single-instance deployment",
            "Parameters.flavor2.name" : "Single instance",
        }
    }
}
```

```
        "Parameters.flavor3.description" : "Custom resource specifications for deployment",
        "Parameters.flavor3.name" : "Custom"
    }
}
},
"supportVersions" : null,
"creationTimestamp" : "2023-05-12T16:10:05Z",
"updateTimestamp" : "2023-05-12T16:10:05Z"
}
}
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.5.4 Rolling Back an Add-on Instance

Function

Roll back the add-on instance version to the source version. Only when the **status.isRollbackable** parameter is set to **true**, and the add-on instance is in the **running**, **available**, **abnormal**, **upgradeFailed**, or **rollbackFailed** state, the version can be rolled back to the source version.

URI

POST /api/v3/addons/{id}/operation/rollback

Table 4-663 Path Parameters

Parameter	Mandatory	Type	Description
id	Yes	String	Add-on instance ID

Request Parameters

Table 4-664 Request header parameters

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-665 Request body parameters

Parameter	Mandatory	Type	Description
clusterID	Yes	String	Cluster ID

Response Parameters

Status code: 200

Table 4-666 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Addon and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	AddonMetadata object	Basic information about the object. Metadata is a collection of attributes.
spec	InstanceSpec object	Detailed description of the add-on instance.
status	AddonInstanceStatus object	Add-on instance status.

Table 4-667 AddonMetadata

Parameter	Type	Description
uid	String	Unique ID
name	String	Add-on name
alias	String	Add-on alias
labels	Map<String, String>	Add-on labels in key-value pairs. This is a reserved field and does not take effect.
annotations	Map<String, String>	Add-on annotations in the format of key-value pairs. <ul style="list-style-type: none">• For add-on installation, the value is fixed at <code>{"addon.install/type":"install"}</code>.• For add-on upgrade, the value is fixed at <code>{"addon.upgrade/type":"upgrade"}</code>.
updateTimestamp	String	Updated at
creationTimestamp	String	Created at

Table 4-668 InstanceSpec

Parameter	Type	Description
clusterID	String	Cluster ID.
version	String	Add-on template version, for example, 1.0.0 .
addonTemplateName	String	Add-on template name, for example, coredns .
addonTemplateType	String	Add-on template type.
addonTemplateLogo	String	URL for obtaining the add-on template logo.
addonTemplateLabels	Array of strings	Labels of the add-on template.
description	String	Add-on template description.
values	Map<String, Object>	Add-on template installation parameters (varying depending on the add-on). Set the parameters accordingly.

Table 4-669 AddonInstanceStatus

Parameter	Type	Description
status	String	<p>Statuses of add-on instances. Options:</p> <ul style="list-style-type: none">• running: All of the add-on instances are running and the add-on is running properly.• abnormal: The add-on instances are abnormal and the add-on cannot be used. Click the add-on name to view exceptions.• installing: The add-on is being installed.• installFailed: Installing the add-on failed. In this case, uninstall the add-on and then reinstall it.• upgrading: The add-on is being upgraded.• upgradeFailed: Upgrading the add-on failed. In this case, upgrade the add-on again or uninstall the add-on and reinstall it.• deleting: The add-on is being deleted.• deleteFailed: Deleting the add-on failed. In this case, uninstall the add-on again.• deleteSuccess: Deleting the add-on succeeded.• available: Only some instances of the add-on are running. This indicates that some functions of the add-on are available.• rollbacking: The add-on is being rolled back.• rollbackFailed: Rolling back the add-on failed. In this case, roll back the add-on again or uninstall the add-on and reinstall it.• unknown: The add-on chart instance does not exist.
Reason	String	Cause of the add-on installation failure.
message	String	Installation error details.
targetVersions	Array of strings	Versions to which the current add-on version can be upgraded.
currentVersion	Versions object	Information about the current add-on version.
isRollbackable	Boolean	Whether the add-on version can be rolled back to the source version.
previousVersion	String	The add-on version before upgrade or rollback

Table 4-670 Versions

Parameter	Type	Description
version	String	Add-on version.
input	Object	Add-on installation parameters.
stable	Boolean	Whether the add-on version is a stable release.
translate	Object	Translation information used by the GUI.
supportVersions	Array of SupportVersions objects	Cluster versions that support the add-on.
creationTimestamp	String	Creation time.
updateTimestamp	String	Update time.

Table 4-671 SupportVersions

Parameter	Type	Description
clusterType	String	Cluster type that supports the add-on.
clusterVersion	Array of strings	Cluster versions that support the add-on. The value is a regular expression.

Example Requests

```
{  
    "clusterID" : "*****"  
}
```

Example Responses

Status code: 200

Add-on instance version is rolled back.

```
{  
    "kind" : "Addon",  
    "apiVersion" : "v3",  
    "metadata" : {  
        "uid" : "*****",  
        "name" : "everest",  
        "alias" : "everest",  
        "creationTimestamp" : "2023-03-15T02:48:01Z",  
        "updateTimestamp" : "2023-03-15T04:18:45Z"  
    },  
    "spec" : {
```

```
"clusterID" : "*****",
"version" : "2.1.16",
"addonTemplateName" : "everest",
"addonTemplateType" : "helm",
"addonTemplateLogo" : "*****",
"addonTemplateLabels" : [ "Storage" ],
"description" : "Everest is a cloud native container storage system based on CSI, used\rto support cloud storages services for Kubernetes",
"values" : {
"basic" : {
"base_image" : "euleros",
"bms_url" : "*****",
"cluster_version" : "v1.25",
"driver_init_image_version" : "2.1.16",
"ecsEndpoint" : "*****",
"euleros_version" : "2.2.5",
"everest_image_version" : "2.1.16",
"evs_url" : "*****",
"iam_url" : "*****",
"ims_url" : "*****",
"obs_url" : "*****",
"platform" : "linux-amd64",
"rbac_enabled" : true,
"sfs30_url" : "*****",
"sfs_turbo_url" : "*****",
"sfs_url" : "*****",
"supportHcs" : false,
"swr_addr" : "*****",
"swr_user" : "*****"
},
"custom" : {
"cluster_id" : "*****",
"cluster_version" : "v1.25.3-r0",
"csi_attacher_detach_worker_threads" : "60",
"csi_attacher_worker_threads" : "60",
"default_vpc_id" : "*****",
"disable_auto_mount_secret" : false,
"enable_node_attacher" : false,
"flow_control" : { },
"multiAZEnabled" : false,
"over_subscription" : "80",
"project_id" : "*****",
"volume_attaching_flow_ctrl" : "0"
},
"flavor" : {
"category" : [ "CCE", "Turbo" ],
"description" : "High avaialble",
"name" : "HA",
"replicas" : 2,
"resources" : [ {
"limitsCpu" : "250m",
"limitsMem" : "1500Mi",
"name" : "everest-csi-controller",
"requestsCpu" : "250m",
"requestsMem" : "600Mi"
}, {
"limitsCpu" : "500m",
"limitsMem" : "300Mi",
"name" : "everest-csi-driver",
"requestsCpu" : "100m",
"requestsMem" : "300Mi"
} ]
},
"multiAZPreferred" : {
"podAntiAffinity" : {
"preferredDuringSchedulingIgnoredDuringExecution" : [ {
"podAffinityTerm" : {
"labelSelector" : {
"matchExpressions" : [ {
```

```
        "key" : "app",
        "operator" : "In",
        "values" : [ "everest-csi-controller" ]
    }
},
"topologyKey" : "topology.kubernetes.io/zone"
},
"weight" : 100
}
}
},
"multiAZRequired" : {
    "podAntiAffinity" : {
        "requiredDuringSchedulingIgnoredDuringExecution" : [
            {
                "labelSelector" : {
                    "matchExpressions" : [
                        {
                            "key" : "app",
                            "operator" : "In",
                            "values" : [ "everest-csi-controller" ]
                        }
                    ],
                    "topologyKey" : "topology.kubernetes.io/zone"
                }
            }
        ]
    }
},
"systemAutoInject" : {
    "cluster" : {
        "category" : "CCE",
        "clusterID" : "*****",
        "clusterNetworkMode" : "vpc-router",
        "clusterVersion" : "v1.25.3-r0"
    },
    "user" : {
        "projectId" : "*****"
    }
},
"tolerations" : [
    {
        "effect" : "NoExecute",
        "key" : "node.kubernetes.io/not-ready",
        "operator" : "Exists",
        "tolerationSeconds" : 60
    },
    {
        "effect" : "NoExecute",
        "key" : "node.kubernetes.io/unreachable",
        "operator" : "Exists",
        "tolerationSeconds" : 60
    }
]
},
"status" : {
    "status" : "rollingback",
    "Reason" : "Rollback to 4",
    "message" : "",
    "targetVersions" : [ "2.1.18", "2.1.19" ],
    "isRollbackable" : false,
    "previousVersion" : "2.1.19",
    "currentVersion" : {
        "version" : "2.1.16",
        "input" : {
            "basic" : {
                "bms_url" : "*****",
                "driver_init_image_version" : "2.1.16",
                "ecsEndpoint" : "*****",
                "everest_image_version" : "2.1.16",
                "evs_url" : "*****",
                "iam_url" : "*****",
                "ims_url" : "*****",
                "obs_url" : "*****",
                "platform" : "linux-amd64",
            }
        }
    }
}
```

```
"sfs30_url" : "*****",
"sfs_turbo_url" : "*****",
"sfs_url" : "*****",
"supportHcs" : false,
"swr_addr" : "*****",
"swr_user" : "*****"
},
"parameters" : {
"common" : {
"defaultVPCId" : 0
},
"custom" : {
"cluster_id" : "",
"csi_attacher_detach_worker_threads" : "60",
"csi_attacher_worker_threads" : "60",
"default_vpc_id" : "",
"disable_auto_mount_secret" : false,
"enable_node_attacher" : false,
"flow_control" : { },
"multiAZEnabled" : false,
"over_subscription" : "80",
"project_id" : "",
"volume_attaching_flow_ctrl" : "0"
},
"flavor1" : {
"description" : "High available",
"name" : "HA",
"replicas" : 2,
"resources" : [ {
"limitsCpu" : "250m",
"limitsMem" : "1500Mi",
"name" : "everest-csi-controller",
"requestsCpu" : "250m",
"requestsMem" : "600Mi"
}, {
"limitsCpu" : "500m",
"limitsMem" : "300Mi",
"name" : "everest-csi-driver",
"requestsCpu" : "100m",
"requestsMem" : "300Mi"
} ]
},
"flavor2" : {
"description" : "Has only one instance",
"name" : "Single",
"replicas" : 1,
"resources" : [ {
"limitsCpu" : "250m",
"limitsMem" : "600Mi",
"name" : "everest-csi-controller",
"requestsCpu" : "250m",
"requestsMem" : "600Mi"
}, {
"limitsCpu" : "100m",
"limitsMem" : "300Mi",
"name" : "everest-csi-driver",
"requestsCpu" : "100m",
"requestsMem" : "300Mi"
} ]
},
"flavor3" : {
"description" : "custom resources",
"name" : "custom-resources",
"replicas" : 2,
"resources" : [ {
"limitsCpu" : "250m",
"limitsMem" : "2000Mi",
"name" : "everest-csi-controller",
"requestsCpu" : "250m",
"requestsMem" : "2000Mi"
} ]
}
```

```
        "requestsMem" : "1500Mi"
    }, {
        "limitsCpu" : "500m",
        "limitsMem" : "300Mi",
        "name" : "everest-csi-driver",
        "requestsCpu" : "100m",
        "requestsMem" : "300Mi"
    } ]
}
},
"stable" : true,
"translate" : {
    "en_US" : {
        "addon" : {
            "changeLog" : "*****",
            "description" : "*****"
        },
        "description" : {
            "Parameters.flavor1.description" : "*****",
            "Parameters.flavor1.name" : "*****",
            "Parameters.flavor2.description" : "*****",
            "Parameters.flavor2.name" : "*****",
            "Parameters.flavor3.name" : "*****"
        }
    },
    "zh_CN" : {
        "addon" : {
            "changeLog" : "*****",
            "description" : "*****"
        },
        "description" : {
            "Parameters.flavor1.description" : "*****",
            "Parameters.flavor1.name" : "*****",
            "Parameters.flavor2.description" : "*****",
            "Parameters.flavor2.name" : "*****",
            "Parameters.flavor3.description" : "*****",
            "Parameters.flavor3.name" : "*****"
        }
    }
},
"supportVersions" : null,
"creationTimestamp" : "2023-02-21T16:29:02Z",
"updateTimestamp" : "2023-02-22T06:49:50Z"
}
}
```

Status Codes

Status Code	Description
200	Add-on instance version is rolled back.

Error Codes

See [Error Codes](#).

4.5.5 Deleting an Add-on Instance

Function

This API is used to delete an add-on instance.

URI

DELETE /api/v3/addons/{id}

Table 4-672 Path Parameters

Parameter	Mandatory	Type	Description
id	Yes	String	Add-on instance ID.

Table 4-673 Query Parameters

Parameter	Mandatory	Type	Description
cluster_id	No	String	Cluster ID (deprecated). For details about how to obtain the cluster ID, see How Do I Obtain Parameters in the API URI .

Request Parameters

Table 4-674 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

None

Example Requests

None

Example Responses

Status code: 200

OK

success

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.5.6 Querying an Add-on Instance

Function

This API is used to obtain details about an add-on instance.

URI

GET /api/v3/addons/{id}

Table 4-675 Path Parameters

Parameter	Mandatory	Type	Description
id	Yes	String	Add-on instance ID.

Table 4-676 Query Parameters

Parameter	Mandatory	Type	Description
cluster_id	No	String	Cluster ID (deprecated). For details about how to obtain the cluster ID, see How Do I Obtain Parameters in the API URI .

Request Parameters

Table 4-677 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-678 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Addon and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	AddonMetadata object	Basic information about the object. Metadata is a collection of attributes.
spec	InstanceSpec object	Detailed description of the add-on instance.
status	AddonInstanceState object	Add-on instance status.

Table 4-679 AddonMetadata

Parameter	Type	Description
uid	String	Unique ID
name	String	Add-on name
alias	String	Add-on alias

Parameter	Type	Description
labels	Map<String, String>	Add-on labels in key-value pairs. This is a reserved field and does not take effect.
annotations	Map<String, String>	Add-on annotations in the format of key-value pairs. <ul style="list-style-type: none">• For add-on installation, the value is fixed at <code>{"addon.install/type":"install"}</code>.• For add-on upgrade, the value is fixed at <code>{"addon.upgrade/type":"upgrade"}</code>.
updateTimestamp	String	Updated at
creationTimestamp	String	Created at

Table 4-680 InstanceSpec

Parameter	Type	Description
clusterID	String	Cluster ID.
version	String	Add-on template version, for example, 1.0.0 .
addonTemplate Name	String	Add-on template name, for example, coredns .
addonTemplate Type	String	Add-on template type.
addonTemplate Logo	String	URL for obtaining the add-on template logo.
addonTemplate Labels	Array of strings	Labels of the add-on template.
description	String	Add-on template description.
values	Map<String, Object>	Add-on template installation parameters (varying depending on the add-on). Set the parameters accordingly.

Table 4-681 AddonInstanceStatus

Parameter	Type	Description
status	String	Statuses of add-on instances. Options: <ul style="list-style-type: none">• running: All of the add-on instances are running and the add-on is running properly.• abnormal: The add-on instances are abnormal and the add-on cannot be used. Click the add-on name to view exceptions.• installing: The add-on is being installed.• installFailed: Installing the add-on failed. In this case, uninstall the add-on and then reinstall it.• upgrading: The add-on is being upgraded.• upgradeFailed: Upgrading the add-on failed. In this case, upgrade the add-on again or uninstall the add-on and reinstall it.• deleting: The add-on is being deleted.• deleteFailed: Deleting the add-on failed. In this case, uninstall the add-on again.• deleteSuccess: Deleting the add-on succeeded.• available: Only some instances of the add-on are running. This indicates that some functions of the add-on are available.• rollbacking: The add-on is being rolled back.• rollbackFailed: Rolling back the add-on failed. In this case, roll back the add-on again or uninstall the add-on and reinstall it.• unknown: The add-on chart instance does not exist.
Reason	String	Cause of the add-on installation failure.
message	String	Installation error details.
targetVersions	Array of strings	Versions to which the current add-on version can be upgraded.
currentVersion	Versions object	Information about the current add-on version.
isRollbackable	Boolean	Whether the add-on version can be rolled back to the source version.
previousVersion	String	The add-on version before upgrade or rollback

Table 4-682 Versions

Parameter	Type	Description
version	String	Add-on version.
input	Object	Add-on installation parameters.
stable	Boolean	Whether the add-on version is a stable release.
translate	Object	Translation information used by the GUI.
supportVersions	Array of SupportVersions objects	Cluster versions that support the add-on.
creationTimestamp	String	Creation time.
updateTimestamp	String	Update time.

Table 4-683 SupportVersions

Parameter	Type	Description
clusterType	String	Cluster type that supports the add-on.
clusterVersion	Array of strings	Cluster versions that support the add-on. The value is a regular expression.

Example Requests

None

Example Responses

Status code: 200

OK

```
{  
  "kind" : "Addon",  
  "apiVersion" : "v3",  
  "metadata" : {  
    "uid" : "24b23108-55c0-11e9-926f-0255ac101a31",  
    "name" : "gpu-beta",  
    "alias" : "gpu",  
    "creationTimestamp" : "2019-04-03T03:25:34Z",  
    "updateTimestamp" : "2019-04-03T03:25:34Z"  
  },  
  "spec" : {  
    "clusterID" : "0c0e4a63-5539-11e9-95f7-0255ac10177e",  
    "version" : "1.0.0",  
  }  
}
```

```
"addonTemplateName" : "gpu-beta",
"addonTemplateType" : "helm",
"addonTemplateLogo" : "",
"addonTemplateLabels" : [ "Accelerator" ],
"description" : "A device plugin for nvidia.com/gpu resource on nvidia driver",
"values" : {
  "basic" : {
    "rbac_enabled" : true,
    "swr_addr" : "100.125.6.246:20202",
    "swr_user" : "hwofficial"
  }
},
"status" : {
  "status" : "installing",
  "Reason" : "",
  "message" : "",
  "targetVersions" : null,
  "currentVersion" : {
    "version" : "1.0.0",
    "input" : {
      "basic" : {
        "swr_addr" : "100.125.6.246:20202",
        "swr_user" : "hwofficial"
      },
      "parameters" : { }
    },
    "stable" : true,
    "translate" : {
      "en_US" : {
        "addon" : {
          "changeLog" : "A device plugin for nvidia.com/gpu resource on nvidia driver",
          "description" : "A device plugin for nvidia.com/gpu resource on nvidia driver"
        }
      },
      "zh_CN" : {
        "addon" : {
          "changeLog" : "",
          "description" : ""
        }
      }
    },
    "supportVersions" : null,
    "creationTimestamp" : "2018-10-23T13:14:55Z",
    "updateTimestamp" : "2018-12-07T09:40:24Z"
  }
}
}
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.5.7 Listing Add-on Instances

Function

This API is used to list all add-on instances in the cluster.

URI

GET /api/v3 addons

Table 4-684 Query Parameters

Parameter	Mandatory	Type	Description
cluster_id	Yes	String	Cluster ID. For details about how to obtain a cluster ID, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-685 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-686 Response body parameters

Parameter	Type	Description
kind	String	API type. The value is fixed at Addon and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.

Parameter	Type	Description
items	Array of AddonInstance objects	Add-on instance list.

Table 4-687 AddonInstance

Parameter	Type	Description
kind	String	API type. The value is fixed at Addon and cannot be changed.
apiVersion	String	API version. The value is fixed at v3 and cannot be changed.
metadata	AddonMetadata object	Basic information about the object. Metadata is a collection of attributes.
spec	InstanceSpec object	Detailed description of the add-on instance.
status	AddonInstanceState object	Add-on instance status.

Table 4-688 AddonMetadata

Parameter	Type	Description
uid	String	Unique ID
name	String	Add-on name
alias	String	Add-on alias
labels	Map<String, String>	Add-on labels in key-value pairs. This is a reserved field and does not take effect.
annotations	Map<String, String>	Add-on annotations in the format of key-value pairs. <ul style="list-style-type: none">• For add-on installation, the value is fixed at <code>{"addon.install/type": "install"}</code>.• For add-on upgrade, the value is fixed at <code>{"addon.upgrade/type": "upgrade"}</code>.
updateTimestamp	String	Updated at
creationTimestamp	String	Created at

Table 4-689 InstanceSpec

Parameter	Type	Description
clusterID	String	Cluster ID.
version	String	Add-on template version, for example, 1.0.0 .
addonTemplate Name	String	Add-on template name, for example, coredns .
addonTemplate Type	String	Add-on template type.
addonTemplate Logo	String	URL for obtaining the add-on template logo.
addonTemplate Labels	Array of strings	Labels of the add-on template.
description	String	Add-on template description.
values	Map<String, Object>	Add-on template installation parameters (varying depending on the add-on). Set the parameters accordingly.

Table 4-690 AddonInstanceStatus

Parameter	Type	Description
status	String	<p>Statuses of add-on instances. Options:</p> <ul style="list-style-type: none">• running: All of the add-on instances are running and the add-on is running properly.• abnormal: The add-on instances are abnormal and the add-on cannot be used. Click the add-on name to view exceptions.• installing: The add-on is being installed.• installFailed: Installing the add-on failed. In this case, uninstall the add-on and then reinstall it.• upgrading: The add-on is being upgraded.• upgradeFailed: Upgrading the add-on failed. In this case, upgrade the add-on again or uninstall the add-on and reinstall it.• deleting: The add-on is being deleted.• deleteFailed: Deleting the add-on failed. In this case, uninstall the add-on again.• deleteSuccess: Deleting the add-on succeeded.• available: Only some instances of the add-on are running. This indicates that some functions of the add-on are available.• rollbacking: The add-on is being rolled back.• rollbackFailed: Rolling back the add-on failed. In this case, roll back the add-on again or uninstall the add-on and reinstall it.• unknown: The add-on chart instance does not exist.
Reason	String	Cause of the add-on installation failure.
message	String	Installation error details.
targetVersions	Array of strings	Versions to which the current add-on version can be upgraded.
currentVersion	Versions object	Information about the current add-on version.
isRollbackable	Boolean	Whether the add-on version can be rolled back to the source version.
previousVersion	String	The add-on version before upgrade or rollback

Table 4-691 Versions

Parameter	Type	Description
version	String	Add-on version.
input	Object	Add-on installation parameters.
stable	Boolean	Whether the add-on version is a stable release.
translate	Object	Translation information used by the GUI.
supportVersions	Array of SupportVersions objects	Cluster versions that support the add-on.
creationTimestamp	String	Creation time.
updateTimestamp	String	Update time.

Table 4-692 SupportVersions

Parameter	Type	Description
clusterType	String	Cluster type that supports the add-on.
clusterVersion	Array of strings	Cluster versions that support the add-on. The value is a regular expression.

Example Requests

None

Example Responses

Status code: 200

ok

```
{  
  "kind" : "Addon",  
  "apiVersion" : "v3",  
  "items" : [ {  
    "kind" : "Addon",  
    "apiVersion" : "v3",  
    "metadata" : {  
      "uid" : "8ca259cc-553b-11e9-926f-0255ac101a31",  
      "name" : "storage-driver",  
      "alias" : "storage-driver",  
      "creationTimestamp" : "2019-04-02T11:36:26Z",  
      "updateTimestamp" : "2019-04-02T11:36:26Z"  
    },  
  },
```

```
"spec" : {
    "clusterID" : "0c0e4a63-5539-11e9-95f7-0255ac10177e",
    "version" : "1.0.10",
    "addonTemplateName" : "storage-driver",
    "addonTemplateType" : "helm",
    "addonTemplateLogo" : "https://192.149.48.66/cce-addon-southchina-aw1hz2u/storage-driverlogo.svg",
    "addonTemplateLabels" : [ "Storage" ],
    "description" : "A kubernetes FlexVolume Driver used to support cloud storage",
    "values" : {
        "basic" : {
            "addon_version" : "1.0.10",
            "euleros_version" : "2.2.5",
            "obs_url" : "",
            "platform" : "linux-amd64",
            "swr_addr" : "100.125.6.246:20202",
            "swr_user" : "hwofficial"
        },
        "flavor" : {
            "replicas" : 1
        },
        "parameters" : { }
    }
},
"status" : {
    "status" : "running",
    "Reason" : "Install complete",
    "message" : "",
    "targetVersions" : null,
    "currentVersion" : {
        "version" : "1.0.10",
        "input" : {
            "basic" : {
                "euleros_version" : "2.2.5",
                "obs_url" : "",
                "swr_addr" : "100.125.6.246:20202",
                "swr_user" : "hwofficial"
            },
            "parameters" : { }
        },
        "stable" : true,
        "translate" : {
            "en_US" : {
                "addon" : {
                    "changeLog" : "The plug-in is upgraded to enhance the storage plug-in function.",
                    "description" : "A kubernetes FlexVolume Driver used to support cloud storage"
                }
            },
            "zh_CN" : {
                "addon" : {
                    "changeLog" : "",
                    "description" : ""
                }
            }
        },
        "supportVersions" : null,
        "creationTimestamp" : "2019-03-29T13:45:37Z",
        "updateTimestamp" : "2019-03-29T13:45:37Z"
    }
}
}
]
```

Status Codes

Status Code	Description
200	ok

Error Codes

See [Error Codes](#).

4.6 Quota Management

4.6.1 Querying Resource Quotas

Function

This API is used to query CCE resource quotas.

URI

GET /api/v3/projects/{project_id}/quotas

Table 4-693 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-694 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).

Parameter	Mandatory	Type	Description
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-695 Response body parameters

Parameter	Type	Description
quotas	Array of QuotaResource objects	Resources

Table 4-696 QuotaResource

Parameter	Type	Description
quotaKey	String	Resource type
quotaLimit	Integer	Quota
used	Integer	Number of created resources
unit	String	Unit
regionId	String	Region ID. This parameter is not returned if not involved.
availabilityZoneId	String	AZ ID. This parameter is not returned if not involved.

Example Requests

None

Example Responses

Status code: 200

The resource quotas are obtained successfully.

```
{  
    "quotas": [ {  
        "quotaKey": "cluster",  
        "quotaLimit": 20,  
        "used": 13,  
        "unit": "count"  
    } ]  
}
```

Status Codes

Status Code	Description
200	The resource quotas are obtained successfully.

Error Codes

See [Error Codes](#).

4.7 API Versions

4.7.1 Obtaining API Versions

Function

This API is used to query the list of API versions supported by CCE.

URI

GET /

Request Parameters

None

Response Parameters

Status code: 200

Table 4-697 Response body parameters

Parameter	Type	Description
versions	Array of APIVersionDetail objects	API version list.

Table 4-698 APIVersionDetail

Parameter	Type	Description
id	String	API version ID. Example: v3
links	Array of APIVersionLink objects	URL of the API version.
min_version	String	Microversion. If the APIs of this version support microversions, set this parameter to the supported minimum microversion. If no microversion is supported, leave this parameter blank.
status	String	API version status. Possible values: <ul style="list-style-type: none">• CURRENT: preferred API version• SUPPORTED: old API version that is still supported• DEPRECATED: discarded API version that will be deleted
updated	String	Time when the API was released (UTC). For example, if the API version is v3, the value is '2018-09-15 00:00:00Z'.
version	String	Microversion. If the APIs of this version support microversions, set this parameter to the supported maximum microversion. If no microversion is supported, leave this parameter blank.

Table 4-699 APIVersionLink

Parameter	Type	Description
href	String	URL of the API version.
rel	String	Link attributes. self : A self link contains a versioned link to the resource. Use these links immediately after linking.

Example Requests

None

Example Responses

Status code: 200

The API version list is queried successfully.

```
{  
    "versions" : [ {  
        "id" : "v3",  
        "links" : [ {  
            "href" : "https://cce.region.***.com/v3",  
            "rel" : "self"  
        } ],  
        "min_version" : "",  
        "status" : "CURRENT",  
        "updated" : "2018-09-15 00:00:00Z",  
        "version" : ""  
    } ]  
}
```

Status Codes

Status Code	Description
200	The API version list is queried successfully.

Error Codes

See [Error Codes](#).

4.8 Tag Management

4.8.1 Adding Resource Tags to a Specified Cluster in Batches

Function

This API is used to add resource tags for a specified cluster in batches.

NOTE

- Each cluster supports a maximum of 20 resource tags.
- This API is idempotent. If the to-be-added tag has the same tag key and tag value as an existing tag, the tag will be added. If the to-be-added tag has the same key but different value as an existing tag, the tag will overwrite the existing one.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/tags/create

Table 4-700 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Parameter	Mandatory	Type	Description
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-701 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-702 Request body parameters

Parameter	Mandatory	Type	Description
tags	Yes	Array of ResourceTag objects	List of cluster resource tags to be created. Each cluster supports a maximum of 20 resource tags.

Table 4-703 ResourceTag

Parameter	Mandatory	Type	Description
key	No	String	Key. <ul style="list-style-type: none">• Cannot be null. Max characters: 128.• Use letters, digits, and spaces in UTF-8 format.• Can contain the following special characters: _.:;/=-@.• Cannot start with <code>_sys_</code>.

Parameter	Mandatory	Type	Description
value	No	String	<p>Value.</p> <ul style="list-style-type: none">• Can be null but not the default. Max characters: 255.• Use letters, digits, and spaces in UTF-8 format.• Can contain the following special characters: _.:;/=+-@.

Response Parameters

None

Example Requests

Adding Resource Tags to a Specified Cluster in Batches

```
POST /api/v3/projects/{project_id}/clusters/{cluster_id}/tags/create
```

```
{
  "tags" : [ {
    "key" : "key1",
    "value" : "value1"
  }, {
    "key" : "key2",
    "value" : "value3"
  } ]
}
```

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See [Error Codes](#).

4.8.2 Deleting Resource Tags of a Specified Cluster in Batches

Function

This API is used to delete resource tags of a specified cluster in batches.

 NOTE

- This API is idempotent. If the tag key of the to-be-deleted tag does not exist, the tag will be deleted.

URI

POST /api/v3/projects/{project_id}/clusters/{cluster_id}/tags/delete

Table 4-704 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-705 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-706 Request body parameters

Parameter	Mandatory	Type	Description
tags	Yes	Array of ResourceDeleteTag objects	List of cluster resource tags to be deleted

Table 4-707 ResourceDeleteTag

Parameter	Mandatory	Type	Description
key	No	String	<p>The key value of the resource tag</p> <ul style="list-style-type: none">• It cannot be null. It can contain a maximum of 128 characters.• It can contain letters, digits, and spaces in UTF-8 format.• It can contain the following special characters: _.:/=+-@.• It cannot start with <code>_sys_</code>.

Response Parameters

None

Example Requests

Deleting Resource Tags of a Specified Cluster in Batches

```
POST /api/v3/projects/{project_id}/clusters/{cluster_id}/tags/delete

{
  "tags": [
    {
      "key": "key1"
    },
    {
      "key": "key2"
    }
  ]
}
```

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See [Error Codes](#).

4.9 Configuration Management

4.9.1 Obtaining the Parameters That Can Be Configured for a Node Pool

Function

This API is used to obtain the parameters that can be configured in a specified CCE node pool.

URI

GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}/configuration/detail

Table 4-708 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
nodepool_id	Yes	String	Node pool ID.

Request Parameters

Table 4-709 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

None

Example Requests

None

Example Responses

Status code: 200

The parameters of the specified node pool are obtained.

```
{  
  "kubelet": [ {  
    "name": "kube-api-qps",  
    "default": 300,  
    "validAt": "immediately",  
    "empty": false,  
    "schema": "",  
    "type": "float"  
  }]  
}
```

Status Codes

Status Code	Description
200	The parameters of the specified node pool are obtained.

Error Codes

See [Error Codes](#).

4.9.2 Obtaining the List of Parameters That Can Be Configured for a Cluster

Function

This API is used to obtain the list of parameters that can be configured for a CCE cluster.

URI

GET /api/v3/projects/{project_id}/clusters/{cluster_id}/configuration/detail

Table 4-710 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-711 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

None

Example Requests

None

Example Responses

Status code: 200

A list of parameters that can be configured for a cluster is obtained successfully.

```
{  
  "kube-apiserver" : [ {  
    "name" : "default-not-ready-toleration-seconds",  
    "default" : 300,  
    "validAt" : "immediately",  
    "empty" : true,  
    "schema" : "kubernetes",  
    "type" : "int"  
  } ]  
}
```

```
    } ]  
}
```

Status Codes

Status Code	Description
200	A list of parameters that can be configured for a cluster is obtained successfully.

Error Codes

See [Error Codes](#).

4.9.3 Obtaining the Parameters That Can Be Configured for a Node Pool

Function

This API is used to obtain the parameters that can be configured for a node pool.

URI

GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}/configuration

Table 4-712 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
nodepool_id	Yes	String	Node pool ID.

Request Parameters

Table 4-713 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-714 Response body parameters

Parameter	Type	Description
apiVersion	String	API version
kind	String	API type. The value is fixed at Configuration .
metadata	ConfigurationMetadata object	Configuration metadata
spec	ClusterConfigurationsSpec object	Configuration specifications
status	Object	Configuration status

Table 4-715 ConfigurationMetadata

Parameter	Type	Description
name	String	Configuration name

Parameter	Type	Description
labels	Map<String, String>	A configuration label in a key-value pair. <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. Example: "foo": "bar"

Table 4-716 ClusterConfigurationsSpec

Parameter	Type	Description
packages	Array of packages objects	Component configuration item details

Table 4-717 packages

Parameter	Type	Description
name	String	Component name
configurations	Array of Configuratio nItem objects	Component configuration items

Table 4-718 ConfigurationItem

Parameter	Type	Description
name	String	Component configuration item name.
value	Object	Component configuration item value.

Example Requests

None

Example Responses

Status code: 200

The parameter configurations of the node pool are obtained successfully.

```
{  
    "kind": "Configuration",  
    "apiVersion": "v3",  
    "metadata": {  
        "name": "configuration",  
        "labels": {  
            "nodepool_id": "61de338d-a1f9-11ed-8891-0255ac100036"  
        }  
    },  
    "spec": {  
        "packages": [ {  
            "name": "kube-apiserver",  
            "configurations": [ {  
                "name": "event-rate-limit-qps",  
                "value": 200  
            }, {  
                "name": "support-overload",  
                "value": false  
            } ]  
        }, {  
            "name": "kube-scheduler",  
            "configurations": [ {  
                "name": "kube-api-qps",  
                "value": 100  
            }, {  
                "name": "default-scheduler",  
                "value": "kube-scheduler"  
            } ]  
        },  
        "status": { }  
    }  
}
```

Status Codes

Status Code	Description
200	The parameter configurations of the node pool are obtained successfully.

Error Codes

See [Error Codes](#).

4.9.4 Changing the Values of Configuration Parameters of a Node Pool

Function

This API is used to change the values of parameter configurations of a node pool in the CCE cluster.

URI

PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}/configuration

Table 4-719 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .
nodepool_id	Yes	String	Node pool ID.

Request Parameters

Table 4-720 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-721 Request body parameters

Parameter	Mandatory	Type	Description
apiVersion	Yes	String	API version. The value is fixed at v3 .
kind	Yes	String	API type. The value is fixed at Configuration .
metadata	Yes	ConfigurationMetadata object	Configuration metadata

Parameter	Mandatory	Type	Description
spec	Yes	ClusterConfigurationsSpec object	Configuration specifications

Table 4-722 ConfigurationMetadata

Parameter	Mandatory	Type	Description
name	Yes	String	Configuration name
labels	No	Map<String, String>	A configuration label in a key-value pair. <ul style="list-style-type: none">• Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-key• Value: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. Example: "foo": "bar"

Table 4-723 ClusterConfigurationsSpec

Parameter	Mandatory	Type	Description
packages	Yes	Array of packages objects	Component configuration item details

Table 4-724 packages

Parameter	Mandatory	Type	Description
name	No	String	Component name
configurations	No	Array of ConfigurationItem objects	Component configuration items

Table 4-725 ConfigurationItem

Parameter	Mandatory	Type	Description
name	No	String	Component configuration item name.
value	No	Object	Component configuration item value.

Response Parameters

Status code: 200

Table 4-726 Response body parameters

Parameter	Type	Description
apiVersion	String	API version
kind	String	API type. The value is fixed at Configuration .
metadata	ConfigurationMetadata object	Configuration metadata
spec	ClusterConfigurationsSpec object	Configuration specifications
status	Object	Configuration status

Table 4-727 ConfigurationMetadata

Parameter	Type	Description
name	String	Configuration name

Parameter	Type	Description
labels	Map<String, String>	A configuration label in a key-value pair. <ul style="list-style-type: none">Key: Enter 1 to 63 characters, starting with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed. A DNS subdomain can be prefixed to a key and contain a maximum of 253 characters. Example DNS subdomain: example.com/my-keyValue: The value can be left blank or contain 1 to 63 characters that start with a letter or digit. Only letters, digits, hyphens (-), underscores (_), and periods (.) are allowed in the character string. Example: "foo": "bar"

Table 4-728 ClusterConfigurationsSpec

Parameter	Type	Description
packages	Array of packages objects	Component configuration item details

Table 4-729 packages

Parameter	Type	Description
name	String	Component name
configurations	Array of Configuratio nItem objects	Component configuration items

Table 4-730 ConfigurationItem

Parameter	Type	Description
name	String	Component configuration item name.
value	Object	Component configuration item value.

Example Requests

The following example describes how to update the **system-reserved-mem** and **kube-reserved-mem** parameters in kubelet.

```
/api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}/configuration

{
  "kind": "Configuration",
  "apiVersion": "v3",
  "metadata": {
    "name": "configuration"
  },
  "spec": {
    "packages": [
      {
        "name": "kubelet",
        "configurations": [
          {
            "name": "system-reserved-mem",
            "value": 600
          },
          {
            "name": "kube-reserved-mem",
            "value": 800
          }
        ]
      }
    ]
  }
}
```

Example Responses

Status code: 200

The parameter configurations of the node pool are updated successfully.

```
{
  "kind": "Configuration",
  "apiVersion": "v3",
  "metadata": {
    "name": "configuration",
    "labels": {
      "nodepool_id": "61de338d-a1f9-11ed-8891-0255ac100036"
    }
  },
  "spec": {
    "packages": [
      {
        "name": "kube-apiserver",
        "configurations": [
          {
            "name": "event-rate-limit-qps",
            "value": 200
          },
          {
            "name": "support-overload",
            "value": false
          }
        ]
      },
      {
        "name": "kube-scheduler",
        "configurations": [
          {
            "name": "kube-api-qps",
            "value": 100
          },
          {
            "name": "default-scheduler",
            "value": "kube-scheduler"
          }
        ]
      }
    ],
    "status": {}
  }
}
```

Status Codes

Status Code	Description
200	The parameter configurations of the node pool are updated successfully.

Error Codes

See [Error Codes](#).

4.10 Chart Management

4.10.1 Uploading a Chart

Function

This API is used to upload a chart.

URI

POST /v2/charts

Request Parameters

Table 4-731 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-732 FormData parameters

Parameter	Mandatory	Type	Description
parameters	No	String	Parameter configurations for uploading a chart. The following is an example: {"override":true,"skip_lint":true,"source":"package"} <ul style="list-style-type: none">skip_lint: whether lint uploaded chart - override: whether override existed chart - visible: update chart visible
content	Yes	File	Chart package file

Response Parameters

Status code: 201

Table 4-733 Response body parameters

Parameter	Type	Description
id	String	Chart ID
name	String	Chart name
values	String	Chart value
translate	String	Chart translation resources
instruction	String	Chart description
version	String	Chart version
description	String	Chart description
source	String	Chart source
icon_url	String	URL to chart icons
public	Boolean	Whether the chart is public
chart_url	String	URL to the chart
create_at	String	Created at
update_at	String	Updated at

Example Requests

POST /v2/charts

```
{  
  "parameters" : "{\"override\":true,\"skip_lint\":true,\"source\":\"package\"}",  
  "content" : "chart-file.tgz"  
}
```

Example Responses

Status code: 201

Created

```
{  
  "id" : "e99a7e86-afdd-11eb-aca3-0255ac100b0e",  
  "name" : "neo4j",  
  "values" : {"\"acceptLicenseAgreement\":\"no\", \"affinity\":{}, \"authEnabled\":true, \"clusterDomain \":\"cluster.local\", \"core\":{\"initContainers\":[], \"numberOfServers\":3, \"persistentVolume\":{\"enabled \":true, \"mountPath\":\"/data\", \"size\":\"10Gi\"}, \"sidecarContainers\":[]}, \"defaultDatabase\":\"neo4j \", \"image\":\"neo4j\", \"imagePullPolicy\":\"IfNotPresent\", \"imageTag\":\"4.0.3-enterprise\", \"name \":\"neo4j\", \"nodeSelector\":{}, \"podDisruptionBudget\":{}, \"readReplica\":{\"autoscaling\":{\"enabled \":false, \"maxReplicas\":3, \"minReplicas\":1, \"targetAverageUtilization\":70}, \"initContainers\":[]}, \"numberOfServers\":0, \"resources\":{}, \"sidecarContainers\":[]}, \"resources\":{}, \"testImage \":\"markhneedham/k8s-kubectl\", \"testImageTag\":\"master\", \"tolerations\":[], \"useAPOC\":true\"}  
  "translate" : "",  
  "instruction" : "README.md",  
  "version" : "3.0.1",  
  "description" : "DEPRECATED Neo4j is the world's leading graph database",  
  "source" : "",  
  "icon_url" : "https://info.neo4j.com/rs/773-GON-065/images/neo4j_logo.png",  
  "public" : false,  
  "chart_url" : "neo4j-3.0.1.tgz",  
  "create_at" : "2021-05-08T08:53:13Z",  
  "update_at" : "2021-05-08T08:53:13Z"  
}
```

Status Codes

Status Code	Description
201	Created

Error Codes

See [Error Codes](#).

4.10.2 Obtaining a Chart List

Function

This API is used to obtain the chart list.

URI

GET /v2/charts

Request Parameters

Table 4-734 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-735 Response body parameters

Parameter	Type	Description
[items]	Array of ChartResp objects	Chart list

Table 4-736 ChartResp

Parameter	Type	Description
id	String	Chart ID
name	String	Chart name
values	String	Chart value
translate	String	Chart translation resources
instruction	String	Chart description
version	String	Chart version
description	String	Chart description
source	String	Chart source
icon_url	String	URL to chart icons
public	Boolean	Whether the chart is public

Parameter	Type	Description
chart_url	String	URL to the chart
create_at	String	Created at
update_at	String	Updated at

Example Requests

None

Example Responses

Status code: 200

OK

```
[ {
  "id" : "1abd3bd6-0258-11ec-b8b0-0255ac100b05",
  "name" : "magento-mysql",
  "values" : "{\"basic\":{\"admin_password\":\"*****\",\"admin_username\":\"username\",\"app_name\":\"magento\"},\"mysql_database\":\"magento\",\"mysql_name\":\"mysql\",\"mysql_password\":\"*****\", \"mysql_port\":3306,\"mysql_root_password\":\"*****\",\"mysql_user\":\"magento\"},\"storage_class\":\"csin-nas\",\"storage_mode\":\"ReadWriteMany\",\"storage_size\":\"10G\"},\"global\":{\"magento_EIP\":\"100.100.100.100\"},\"magento_EPORT\":32080,\"namespace\":{\"default\"},\"image\":{\"magento_image\":\"example.com/everest/magento:latest\"},\"mysql_image\":\"example.com/everest/mysql:5.7.14\"}}",
  "translate" : "",
  "instruction" : "",
  "version" : "1.0.0",
  "description" : "chart description",
  "source" : "",
  "icon_url" : "https://example.com/magento-stack-110x117.png",
  "public" : false,
  "chart_url" : "magento-mysql-1.0.0.tgz",
  "create_at" : "2021-08-20T08:00:29Z",
  "update_at" : "2021-08-20T08:00:29Z"
} ]
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.3 Obtaining a Release List

Function

This API is used to obtain a release list.

URI

GET /cce/cam/v3/clusters/{cluster_id}/releases

Table 4-737 Path Parameters

Parameter	Mandatory	Type	Description
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Table 4-738 Query Parameters

Parameter	Mandatory	Type	Description
chart_id	No	String	Chart ID
namespace	No	String	Namespace of the chart

Request Parameters

Table 4-739 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-740 Response body parameters

Parameter	Type	Description
[items]	Array of ReleaseResp objects	OK

Table 4-741 ReleaseResp

Parameter	Type	Description
chart_name	String	Chart name
chart_public	Boolean	Whether the chart is public
chart_version	String	Chart version
cluster_id	String	Cluster ID
cluster_name	String	Current name
create_at	String	Created at
description	String	Release description
name	String	Release name
namespace	String	Namespace to which a chart release belongs
parameters	String	Release parameters
resources	String	Resources required by the release
status	String	Release status
status_description	String	Release status description
update_at	String	Updated at
values	String	Release value
version	Integer	Release version

Example Requests

None

Example Responses

Status code: 200

OK

```
[ {  
    "chart_name" : "magento-mysql",
```

```

"chart_public" : false,
"chart_version" : "1.0.0",
"cluster_id" : "a870253f-5dc7-11ee-bf71-0255ac100b03",
"cluster_name" : "sfs-turbo-test",
"create_at" : "2023-11-14T20:30:57+08:00",
"description" : "Initial install underway",
"name" : "testwww",
"namespace" : "monitoring",
"parameters" : "",
"resources" : "",
"status" : "PENDING_INSTALL",
"status_description" : "Initial install underway",
"update_at" : "2023-11-14T20:30:57+08:00",
"values" : "{\"basic\":{\"admin_password\":\"*****\",\"admin_username\":\"username\",\"app_name\":\"magento\",\"mysql_database\":\"magento\",\"mysql_name\":\"mysql\",\"mysql_password\":\"*****\",\"mysql_port\":3306,\"mysql_root_password\":\"*****\",\"mysql_user\":\"magento\"},\"storage_class\":\"cenisas\", \"storage_mode\":\"ReadWriteMany\", \"storage_size\":\"10G\"},\"global\":{\"magento_EIP\":\"100.100.100.100\", \"magento_EPORT\":32080, \"namespace\":\"default\", \"image\":{\"example.com/everest/magento:latest\", \"mysql_image\":\"example.com/everest/mysql:5.7.14\"}}, \"version\" : 1
} ]

```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.4 Updating a Chart

Function

This API is used to update a chart.

URI

PUT /v2/charts/{chart_id}

Table 4-742 Path Parameters

Parameter	Mandatory	Type	Description
chart_id	Yes	String	Chart ID

Request Parameters

Table 4-743 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-744 FormData parameters

Parameter	Mandatory	Type	Description
parameters	No	String	Parameter configurations for uploading a chart. The following is an example: "{"override":true,"skip_lint":true,"source":"package"}"- skip_lint: whether lint uploaded chart - override: whether override existed chart - visible: update chart visible
content	Yes	File	Chart package file

Response Parameters

Status code: 200

Table 4-745 Response body parameters

Parameter	Type	Description
id	String	Chart ID
name	String	Chart name
values	String	Chart value
translate	String	Chart translation resources
instruction	String	Chart description

Parameter	Type	Description
version	String	Chart version
description	String	Chart description
source	String	Chart source
icon_url	String	URL to chart icons
public	Boolean	Whether the chart is public
chart_url	String	URL to the chart
create_at	String	Created at
update_at	String	Updated at

Example Requests

```
PUT /v2/charts/{chart_id}

{
  "parameters" : "{\"override\":true,\"skip_lint\":true,\"source\":\"package\"}",
  "content" : "chart-file.tgz"
}
```

Example Responses

Status code: 200

OK

```
{
  "id" : "e99a7e86-afdd-11eb-aca3-0255ac100b0e",
  "name" : "neo4j",
  "values" : "{\"acceptLicenseAgreement\":\"no\",\"affinity\":{},\"authEnabled\":true,\"clusterDomain\":\"cluster.local\",\"core\":{},\"initContainers\":[],\"numberOfServers\":3,\"persistentVolume\":{},\"enabled\":true,\"mountPath\":\"/data\",\"size\":\"10Gi\"},\"sidecarContainers\":[],\"defaultDatabase\":\"neo4j\",\"image\":\"neo4j\",\"imagePullPolicy\":\"IfNotPresent\",\"imageTag\":\"4.0.3-enterprise\"},\"name\":\"neo4j\",\"nodeSelector\":{},\"podDisruptionBudget\":{},\"readReplica\":{},\"autoscaling\":{},\"enabled\":false,\"maxReplicas\":3,\"minReplicas\":1,\"targetAverageUtilization\":70},\"initContainers\":[],\"numberOfServers\":0,\"resources\":{},\"sidecarContainers\":[],\"resources\":{},\"testImage\":\"markhneedham/k8s-kubectl\",\"testImageTag\":\"master\",\"tolerations\":[],\"useAOPC\":true}",
  "translate" : "",
  "instruction" : "README.md",
  "version" : "3.0.1",
  "description" : "DEPRECATED Neo4j is the world's leading graph database",
  "source" : "",
  "icon_url" : "https://example.com/images/neo4j_logo.png",
  "public" : false,
  "chart_url" : "neo4j-3.0.1.tgz",
  "create_at" : "2021-05-08T08:53:13Z",
  "update_at" : "2021-05-08T08:53:13Z"
}
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.5 Creating a Release

Function

This API is used to create a release.

URI

POST /cce/cam/v3/clusters/{cluster_id}/releases

Table 4-746 Path Parameters

Parameter	Mandatory	Type	Description
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-747 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-748 Request body parameters

Parameter	Mandatory	Type	Description
chart_id	Yes	String	Chart ID
description	No	String	Release description
name	Yes	String	Release name
namespace	Yes	String	Namespace to which a chart release belongs
version	Yes	String	Release version
parameters	No	ReleaseReqBodyParams object	Release parameters
values	Yes	values object	Release value

Table 4-749 ReleaseReqBodyParams

Parameter	Mandatory	Type	Description
dry_run	No	Boolean	After this function is enabled, only chart parameters are verified, and installation is not performed.
name_template	No	String	Release name template
no_hooks	No	Boolean	Whether to disable hooks during installation
replace	No	Boolean	Whether to replace the release with the same name
recreate	No	Boolean	Whether to rebuild the release
reset_values	No	Boolean	Whether to reset values during an update
release_version	No	Integer	Version of the rollback release
include_hooks	No	Boolean	Enable hooks during an update or deletion.

Table 4-750 values

Parameter	Mandatory	Type	Description
imagePullPolicy	No	String	Image pull policy
imageTag	No	String	Image tag

Response Parameters

Status code: 201

Table 4-751 Response body parameters

Parameter	Type	Description
chart_name	String	Chart name
chart_public	Boolean	Whether the chart is public
chart_version	String	Chart version
cluster_id	String	Cluster ID
cluster_name	String	Current name
create_at	String	Created at
description	String	Release description
name	String	Release name
namespace	String	Namespace to which a chart release belongs
parameters	String	Release parameters
resources	String	Resources required by the release
status	String	Release status
status_description	String	Release status description
update_at	String	Updated at
values	String	Release value
version	Integer	Release version

Example Requests

```
POST /cce/cam/v3/clusters/{cluster_id}/releases
```

```
{  
    "name" : "nino21",  
    "namespace" : "project01",  
}
```

```
"version" : "1.0.0",
"chart_id" : "3c138b72-7ce4-6d76-7c55-604cdb2ce423",
"values" : {
  "imageTag" : "v2",
  "imagePullPolicy" : "IfNotPresent"
},
"parameters" : {
  "dry_run" : false,
  "no_hooks" : false,
  "replace" : false,
  "name_template" : ""
}
```

Example Responses

Status code: 201

Created

```
{
  "chart_name" : "magento-mysql",
  "chart_public" : false,
  "chart_version" : "1.0.0",
  "cluster_id" : "a870253f-5dc7-11ee-bf71-0255ac100b03",
  "cluster_name" : "sfs-turbo-test",
  "create_at" : "2023-11-14T20:30:57+08:00",
  "description" : "Initial install underway",
  "name" : "testwww",
  "namespace" : "monitoring",
  "parameters" : "",
  "resources" : "",
  "status" : "PENDING_INSTALL",
  "status_description" : "Initial install underway",
  "update_at" : "2023-11-14T20:30:57+08:00",
  "values" : "[{"basic": {"admin_password": "*****", "admin_username": "username", "app_name": "magento", "mysql_database": "magento", "mysql_name": "mysql", "mysql_password": "*****", "mysql_port": 3306, "mysql_root_password": "*****", "mysql_user": "magento", "storage_class": "csi-nas", "storage_mode": "ReadWriteMany", "storage_size": "10G"}, "global": {"magento_EIP": "100.100.100.100", "magento_EPORT": 32080}, "namespace": "default", "image": {"magento_image": "example.com/everest/magento:latest", "mysql_image": "example.com/everest/mysql:5.7.14"}}]",
  "version" : 1
}
```

Status Codes

Status Code	Description
201	Created

Error Codes

See [Error Codes](#).

4.10.6 Deleting a Chart

Function

This API is used to delete a chart.

URI

DELETE /v2/charts/{chart_id}

Table 4-752 Path Parameters

Parameter	Mandatory	Type	Description
chart_id	Yes	String	Chart ID

Request Parameters

Table 4-753 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

None

Example Requests

None

Example Responses

None

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.7 Updating a Release

Function

This API is used to update a release.

URI

PUT /cce/cam/v3/clusters/{cluster_id}/namespace/{namespace}/releases/{name}

Table 4-754 Path Parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Release name
namespace	Yes	String	Namespace of the chart
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-755 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Table 4-756 Request body parameters

Parameter	Mandatory	Type	Description
chart_id	Yes	String	Chart ID

Parameter	Mandatory	Type	Description
action	Yes	String	upgrade for an upgrade and rollback for a rollback
parameters	Yes	ReleaseReqBodyParams object	Release parameters
values	Yes	values object	Release value

Table 4-757 ReleaseReqBodyParams

Parameter	Mandatory	Type	Description
dry_run	No	Boolean	After this function is enabled, only chart parameters are verified, and installation is not performed.
name_template	No	String	Release name template
no_hooks	No	Boolean	Whether to disable hooks during installation
replace	No	Boolean	Whether to replace the release with the same name
recreate	No	Boolean	Whether to rebuild the release
reset_values	No	Boolean	Whether to reset values during an update
release_version	No	Integer	Version of the rollback release
include_hooks	No	Boolean	Enable hooks during an update or deletion.

Table 4-758 values

Parameter	Mandatory	Type	Description
imagePullPolicy	No	String	Image pull policy
imageTag	No	String	Image tag

Response Parameters

Status code: 200

Table 4-759 Response body parameters

Parameter	Type	Description
chart_name	String	Chart name
chart_public	Boolean	Whether the chart is public
chart_version	String	Chart version
cluster_id	String	Cluster ID
cluster_name	String	Current name
create_at	String	Created at
description	String	Release description
name	String	Release name
namespace	String	Namespace to which a chart release belongs
parameters	String	Release parameters
resources	String	Resources required by the release
status	String	Release status
status_description	String	Release status description
update_at	String	Updated at
values	String	Release value
version	Integer	Release version

Example Requests

```
PUT /cce/cam/v3/clusters/{cluster_id}/namespace/{namespace}/releases/{name}

{
    "chart_id" : "af4b699e-018c-11ec-b8b0-0255ac100b05",
    "action" : "upgrade",
    "parameters" : {
        "dry_run" : false,
        "name_template" : "string",
        "no_hooks" : false,
        "replace" : false,
        "recreate" : false,
        "reset_values" : false,
        "release_version" : 1,
        "include_hooks" : false
    },
    "values" : {
        "imagePullPolicy" : "IfNotPresent",
        "imageTag" : "v2"
    }
}
```

```
}
```

Example Responses

Status code: 200

OK

```
{
  "chart_name" : "magento-mysql",
  "chart_public" : false,
  "chart_version" : "1.0.0",
  "cluster_id" : "a870253f-5dc7-11ee-bf71-0255ac100b03",
  "cluster_name" : "sfs-turbo-test",
  "create_at" : "2023-11-14T20:30:57+08:00",
  "description" : "Initial install underway",
  "name" : "testwww",
  "namespace" : "monitoring",
  "parameters" : "",
  "resources" : "",
  "status" : "PENDING_INSTALL",
  "status_description" : "Initial install underway",
  "update_at" : "2023-11-14T20:30:57+08:00",
  "values" : "{\"basic\":{\"admin_password\":\"*****\",\"admin_username\":\"username\",\"app_name\"
  \":\"magento\",\"mysql_database\":\"magento\",\"mysql_name\":\"mysql\",\"mysql_password\":\"*****\"
  \",\"mysql_port\":3306,\"mysql_root_password\":\"*****\",\"mysql_user\":\"magento\",\"storage_class\"
  \":\"cassandra\",\"storage_mode\":\"ReadWriteMany\",\"storage_size\":\"10G\"},\"global\"
  \":{\"magento_EIP\"
  \":\"100.100.100.100\",\"magento_EPORT\":32080,\"namespace\"
  \":\"default\"},\"image\"
  \":{\"magento_image\"
  \":\"example.com/everest/magento:latest\",\"mysql_image\"
  \":\"example.com/everest/mysql:5.7.14\"}}",
  "version" : 1
}
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.8 Obtaining a Chart

Function

This API is used to obtain a chart.

URI

GET /v2/charts/{chart_id}

Table 4-760 Path Parameters

Parameter	Mandatory	Type	Description
chart_id	Yes	String	Chart ID

Request Parameters

Table 4-761 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-762 Response body parameters

Parameter	Type	Description
id	String	Chart ID
name	String	Chart name
values	String	Chart value
translate	String	Chart translation resources
instruction	String	Chart description
version	String	Chart version
description	String	Chart description
source	String	Chart source
icon_url	String	URL to chart icons
public	Boolean	Whether the chart is public
chart_url	String	URL to the chart

Parameter	Type	Description
create_at	String	Created at
update_at	String	Updated at

Example Requests

None

Example Responses

Status code: 200

OK

```
{
  "id" : "e99a7e86-afdd-11eb-aca3-0255ac100b0e",
  "name" : "neo4j",
  "values" : {
    "acceptLicenseAgreement": "no",
    "affinity": {},
    "authEnabled": true,
    "clusterDomain": "cluster.local",
    "core": {
      "initContainers": [],
      "numberOfServers": 3,
      "persistentVolume": {
        "enabled": true,
        "mountPath": "/data",
        "size": "10Gi"
      },
      "sidecarContainers": [],
      "defaultDatabase": "neo4j",
      "image": "neo4j",
      "imagePullPolicy": "IfNotPresent",
      "imageTag": "4.0.3-enterprise",
      "name": "neo4j",
      "nodeSelector": {},
      "podDisruptionBudget": {},
      "readReplica": {
        "autoscaling": {
          "enabled": false,
          "maxReplicas": 3,
          "minReplicas": 1
        },
        "targetAverageUtilization": 70
      },
      "initContainers": [],
      "numberOfServers": 0,
      "resources": {},
      "sidecarContainers": [],
      "resources": {},
      "testImage": "markhneedham/k8s-kubectl",
      "testImageTag": "master",
      "tolerations": [],
      "useAPOC": true
    },
    "translate": "",
    "instruction": "README.md",
    "version": "3.0.1",
    "description": "DEPRECATED Neo4j is the world's leading graph database",
    "source": "",
    "icon_url": "https://info.neo4j.com/rs/773-GON-065/images/neo4j_logo.png",
    "public": false,
    "chart_url": "neo4j-3.0.1.tgz",
    "create_at": "2021-05-08T08:53:13Z",
    "update_at": "2021-05-08T08:53:13Z"
  }
}
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.9 Deleting a Release

Function

This API is used to delete a release.

URI

DELETE /cce/cam/v3/clusters/{cluster_id}/namespace/{namespace}/releases/{name}

Table 4-763 Path Parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Release name
namespace	Yes	String	Namespace of the chart
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-764 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

None

Example Requests

None

Example Responses

None

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.10 Downloading a Chart

Function

This API is used to download a chart.

URI

GET /v2/charts/{chart_id}/archive

Table 4-765 Path Parameters

Parameter	Mandatory	Type	Description
chart_id	Yes	String	Chart ID

Request Parameters

Table 4-766 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-767 Response body parameters

Parameter	Type	Description
-	File	OK

Example Requests

None

Example Responses

Status code: 200

OK

"chart-file.tgz"

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.11 Obtaining a Release

Function

This API is used to obtain a release.

URI

GET /cce/cam/v3/clusters/{cluster_id}/namespace/{namespace}/releases/{name}

Table 4-768 Path Parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Release name
namespace	Yes	String	Namespace of the chart
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-769 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-770 Response body parameters

Parameter	Type	Description
chart_name	String	Chart name
chart_public	Boolean	Whether the chart is public
chart_version	String	Chart version
cluster_id	String	Cluster ID
cluster_name	String	Current name
create_at	String	Created at
description	String	Release description
name	String	Release name
namespace	String	Namespace to which a chart release belongs
parameters	String	Release parameters
resources	String	Resources required by the release
status	String	Release status
status_description	String	Release status description
update_at	String	Updated at

Parameter	Type	Description
values	String	Release value
version	Integer	Release version

Example Requests

None

Example Responses

Status code: 200

OK

```
{
  "chart_name" : "magento-mysql",
  "chart_public" : false,
  "chart_version" : "1.0.0",
  "cluster_id" : "a870253f-5dc7-11ee-bf71-0255ac100b03",
  "cluster_name" : "sfs-turbo-test",
  "create_at" : "2023-11-14T20:30:57+08:00",
  "description" : "Initial install underway",
  "name" : "testwww",
  "namespace" : "monitoring",
  "parameters" : "",
  "resources" : "",
  "status" : "PENDING_INSTALL",
  "status_description" : "Initial install underway",
  "update_at" : "2023-11-14T20:30:57+08:00",
  "values" : "{\"basic\":{\"admin_password\":\"*****\",\"admin_username\":\"username\",\"app_name\":\"magento\",\"mysql_database\":\"magento\",\"mysql_name\":\"mysql\",\"mysql_password\":\"*****\",
  \"mysql_port\":3306,\"mysql_root_password\":\"*****\",\"mysql_user\":\"magento\",\"storage_class\":\"cassandra\",\\\"storage_mode\\\":\\\"ReadWriteMany\\\",\\\"storage_size\\\":\\\"10G\\\"},\\\"global\\\":{\\\"magento_EIP\\\":\\\"100.100.100.100\\\",\\\"magento_EPORT\\\":32080,\\\"namespace\\\":\\\"default\\\",\\\"image\\\":\\\"magento_image\\\"\\:\\\"example.com/everest/magento:latest\\\",\\\"mysql_image\\\":\\\"example.com/everest/mysql:5.7.14\\\"}}",
  "version" : 1
}
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.12 Obtaining Chart Values

Function

This API is used to obtain chart values.

URI

GET /v2/charts/{chart_id}/values

Table 4-771 Path Parameters

Parameter	Mandatory	Type	Description
chart_id	Yes	String	Chart ID

Request Parameters

Table 4-772 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-773 Response body parameters

Parameter	Type	Description
values	Map<String, Object>	Data in values.yaml . The data structure depends on the chart.

Example Requests

None

Example Responses

Status code: 200

OK

```
{  
  "values" : {
```

```
"basic" : {  
    "admin_password" : "*****",  
    "admin_username" : "username"  
},  
"global" : {  
    "magento_EIP" : "127.0.0.1",  
    "magento_EPORT" : 32080,  
    "namespace" : "demo"  
},  
"image" : {  
    "magento_image" : "example.com/demo/magento:latest",  
    "mysql_image" : "example.com/demo/mysql:5.7.14"  
}  
}
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.13 Obtaining Historical Records of a Release

Function

This API is used to obtain historical records of a release.

URI

GET /cce/cam/v3/clusters/{cluster_id}/namespace/{namespace}/releases/{name}/history

Table 4-774 Path Parameters

Parameter	Mandatory	Type	Description
name	Yes	String	Release name
namespace	Yes	String	Namespace of the chart
cluster_id	Yes	String	Cluster ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-775 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-776 Response body parameters

Parameter	Type	Description
[items]	Array of ReleaseResp objects	OK

Table 4-777 ReleaseResp

Parameter	Type	Description
chart_name	String	Chart name
chart_public	Boolean	Whether the chart is public
chart_version	String	Chart version
cluster_id	String	Cluster ID
cluster_name	String	Current name
create_at	String	Created at
description	String	Release description
name	String	Release name
namespace	String	Namespace to which a chart release belongs
parameters	String	Release parameters

Parameter	Type	Description
resources	String	Resources required by the release
status	String	Release status
status_description	String	Release status description
update_at	String	Updated at
values	String	Release value
version	Integer	Release version

Example Requests

None

Example Responses

Status code: 200

OK

```
[ {
  "chart_name" : "magento-mysql",
  "chart_public" : false,
  "chart_version" : "1.0.0",
  "cluster_id" : "a870253f-5dc7-11ee-bf71-0255ac100b03",
  "cluster_name" : "efs-turbo-test",
  "create_at" : "2023-11-14T20:30:57+08:00",
  "description" : "Initial install underway",
  "name" : "testwww",
  "namespace" : "monitoring",
  "parameters" : "",
  "resources" : "",
  "status" : "PENDING_INSTALL",
  "status_description" : "Initial install underway",
  "update_at" : "2023-11-14T20:30:57+08:00",
  "values" : "[{"basic": {"admin_password": "*****", "admin_username": "username", "app_name": "magento", "mysql_database": "magento", "mysql_name": "mysql", "mysql_password": "*****", "mysql_port": 3306, "mysql_root_password": "*****", "mysql_user": "magento", "storage_class": "csi-nas", "storage_mode": "ReadWriteMany", "storage_size": "10G"}, "global": {"magento_EIP": "100.100.100.100", "magento_EPORT": 32080}, "namespace": "default", "image": {"magento_image": "example.com/everest/magento:latest", "mysql_image": "example.com/everest/mysql:5.7.14"}}]
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.10.14 Obtaining the Quota of a User Chart

Function

This API is used to obtain the quota of a user chart.

URI

GET /v2/charts/{project_id}/quotas

Table 4-778 Path Parameters

Parameter	Mandatory	Type	Description
project_id	Yes	String	Project ID. For details about how to obtain the value, see How to Obtain Parameters in the API URI .

Request Parameters

Table 4-779 Request header parameters

Parameter	Mandatory	Type	Description
Content-Type	Yes	String	Message body type (format).
X-Auth-Token	Yes	String	Requests for calling an API can be authenticated using either a token or AK/SK. If token-based authentication is used, this parameter is mandatory and must be set to a user token. For details, see Obtaining a User Token .

Response Parameters

Status code: 200

Table 4-780 Response body parameters

Parameter	Type	Description
quotas	quotas object	Chart quota

Table 4-781 quotas

Parameter	Type	Description
resources	Array of resources objects	Resources

Table 4-782 resources

Parameter	Type	Description
type	String	Resource type
quota	Integer	Resource quota
used	Integer	Used resources

Example Requests

None

Example Responses

Status code: 200

OK

```
{  
  "quotas" : {  
    "resources" : [ {  
      "type" : "Charts",  
      "quota" : 200,  
      "used" : 2  
    } ]  
  }  
}
```

Status Codes

Status Code	Description
200	OK

Error Codes

See [Error Codes](#).

4.11 Add-on Instance Parameters

4.11.1 CoreDNS

Add-on Overview

CoreDNS is a DNS server that uses chain plug-ins to provide domain name resolution services for Kubernetes clusters. It is the recommended DNS server solution by the Kubernetes community.

Add-on Parameters

Table 4-783 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-784 object	Flavor parameters
custom	Yes	Table 4-785 object	Custom parameters

Table 4-784 Configuration of flavor

Parameter	Mandatory	Type	Description
replicas	Yes	int	Number of pods. The default value is 2.
resources	Yes	Array of resources object	Container resource (CPU and memory) quotas

Table 4-785 Configuration of custom

Parameter	Mandatory	Type	Description
servers	No	object	Configuration of servers
stub_domains	No	Map<String>[]string	Stub domain configuration

Parameter	Mandatory	Type	Description
multiAZEnable	No	bool	Whether to enable the forcible mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on will be forcibly scheduled to nodes in different AZs. If there are fewer AZs than pods, the extra pods will fail to run. If both multiAZEnable and multiAZBalance are set to true, the settings of multiAZBalance take effect, which means, the equivalent mode of multi-AZ deployment is used.
multiAZBalance	No	bool	Whether to enable the equivalent mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on are evenly scheduled to the nodes in the cluster in each AZ. If a new AZ is added, it is recommended that you increase add-on pods for cross-AZ HA deployment. With the equivalent multi-AZ deployment, the difference between the number of add-on pods in different AZs will be less than or equal to 1. If resources in one of the AZs are insufficient, pods cannot be scheduled to that AZ.
tolerations	No	Array of Table 4-787	Toleration configuration

Table 4-786 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at coredns .
requestsCpu	Yes	String	Requested CPU size (unit: m)
requestsMem	Yes	String	Requested memory size (unit: Mi)

Table 4-787 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator
tolerationSeconds	No	Int	Toleration time window

Table 4-788 Configuration of server

Parameter	Mandatory	Type	Description
port	No	Int	Domain port number. The default value is 5353.
zones	No	Array of Table 4-790	Domain configuration
plugins	No	Array of Table 4-789	Configuration of plugin

Table 4-789 Configuration of plugin

Parameter	Mandatory	Type	Description
name	Yes	String	Plugin name
configBlock	No	String	Configuration of plugin
parameters	No	String/Int	Extended parameters of the plugin

Table 4-790 Configuration of zone

Parameter	Mandatory	Type	Description
zone	Yes	String	Domain to be listened on. The default value is a period (.)

Example Request

```
{  
    "kind": "Addon",  
    "apiVersion": "v3",  
    "metadata": {
```

```
"annotations": {
    "addon.install/type": "install"
},
"spec": {
    "clusterID": "2292498e-*****-0255ac1001ba",
    "version": "1.29.2",
    "addonTemplateName": "coredns",
    "values": {
        "basic": {
            "basickey": "val"
        },
        "flavor": {
            "replicas": 2,
            "resources": [
                "limitsCpu": "2000m",
                "limitsMem": "2000Mi",
                "name": "coredns",
                "requestsCpu": "2000m",
                "requestsMem": "2000Mi"
            ]
        },
        "custom": {
            "multiAZBalance": false,
            "multiAZEnabled": false,
            "node_match_expressions": [],
            "servers": [
                "plugins": [
                    {
                        "name": "bind",
                        "parameters": "{$POD_IP}"
                    },
                    {
                        "configBlock": "servfail 5s",
                        "name": "cache",
                        "parameters": 30
                    },
                    {
                        "name": "errors"
                    },
                    {
                        "name": "health",
                        "parameters": "{$POD_IP}:8080"
                    },
                    {
                        "name": "ready",
                        "parameters": "{$POD_IP}:8081"
                    },
                    {
                        "configBlock": "pods insecure\\nfallthrough in-addr.arpa ip6.arpa",
                        "name": "kubernetes",
                        "parameters": "cluster.local in-addr.arpa ip6.arpa"
                    },
                    {
                        "name": "loadbalance",
                        "parameters": "round_robin"
                    },
                    {
                        "name": "prometheus",
                        "parameters": "{$POD_IP}:9153"
                    },
                    {
                        "configBlock": "policy random",
                        "name": "forward",
                        "parameters": ". /etc/resolv.conf"
                    },
                    {
                        "name": "reload"
                    }
                ],
                "port": 5353,
```

```
        "zones": [
            "zone": "."
        ],
        "stub_domains": {
        },
        "tolerations": [
            {
                "key": "node.kubernetes.io/not-ready",
                "operator": "Exists",
                "effect": "NoExecute",
                "tolerationSeconds": 60
            },
            {
                "key": "node.kubernetes.io/unreachable",
                "operator": "Exists",
                "effect": "NoExecute",
                "tolerationSeconds": 60
            }
        ]
    }
}
```

4.11.2 CCE Container Storage (Everest)

Add-on Overview

The CCE Container Storage (Everest) add-on uses the Container Storage Interface (CSI) to link Kubernetes clusters with cloud storage services.

Add-on Parameters

Table 4-791 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-792 object	Flavor parameters
custom	Yes	Table 4-793 object	Custom parameters

Table 4-792 Configuration of flavor

Parameter	Mandatory	Type	Description
description	No	String	Add-on description
name	Yes	String	Add-on specification name

Parameter	Mandatory	Type	Description
replicas	Yes	String	Number of pods. The default value is 1.
resources	Yes	resources object	Container resource (CPU and memory) quotas

Table 4-793 Configuration of custom

Parameter	Mandatory	Type	Description
default_vpc_id	Yes	String	VPC ID
cluster_id	Yes	String	Cluster ID
cluster_name	Yes	String	Cluster name
project_id	Yes	String	Project ID
disable_auto_mount_secret	No	bool	Whether to allow the default AK/SK to be used during OBS volume mounting Default value: false
over_subscription	No	String	Local PV overcommitment ratio Default value: 80
csi_attachDetach_detach_worker_threads	No	String	The number of concurrent workers for detaching volumes Default value: 60
volume_attaching_flow_ctrl	No	String	Attaching flow control data Default value: 0 .
number_of_reserved_disks	No	String	Disk attaching capability reserved for non-container scenarios Default value: 6
flow_control	No	Map<String>string	Flow control parameter Default value: {}
enable_node_attacher	No	bool	Whether to start agent attacher Default value: false

Parameter	Mandatory	Type	Description
multiAZEnabled	No	bool	Whether to enable the forcible mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on will be forcibly scheduled to nodes in different AZs. If there are fewer AZs than pods, the extra pods will fail to run. If both multiAZEnable and multiAZBalance are set to true, the settings of multiAZBalance take effect, which means, the equivalent mode of multi-AZ deployment is used.
multiAZBalance	No	bool	Whether to enable the equivalent mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on are evenly scheduled to the nodes in the cluster in each AZ. If a new AZ is added, it is recommended that you increase add-on pods for cross-AZ HA deployment. With the equivalent multi-AZ deployment, the difference between the number of add-on pods in different AZs will be less than or equal to 1. If resources in one of the AZs are insufficient, pods cannot be scheduled to that AZ.
tolerations	No	Array of Table 4-795	Toleration configuration
node_match_expressions	No	Array of Table 4-796	Add-on pod affinity configuration

Table 4-794 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at everest-csi-controller or everest-csi-driver .

Parameter	Mandatory	Type	Description
requestsCpu	Yes	String	Requested CPU size (unit: m)
requestsMem	Yes	String	Requested memory size (unit: Mi)

Table 4-795 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator
tolerationSeconds	No	Int	Toleration time window

Table 4-796 nodeMatchExpression node affinity

Parameter	Mandatory	Type	Description
key	No	String	Taint key
values	No	List<String>	Node affinity name
operator	No	String	Operator

Example Request

```
{
  "kind": "Addon",
  "apiVersion": "v3",
  "metadata": { "annotations": { "addon.install/type": "install" } },
  "spec": {
    "clusterID": "cea63ae5-df9b-11ee-9f27-0255ac1001b2",
    "version": "2.4.4",
    "addonTemplateName": "everest",
    "values": {
      "basic": {
        "bms_url": "bms.***.com",
        "driver_init_image_version": "2.4.4",
        "ecsEndpoint": "https://ecs.***.com",
        "everest_image_version": "2.4.4",
        "evs_url": "evs.***.com",
        "iam_url": "iam.***.com",
        "ims_url": "ims.***.com",
        "obs_url": "obs.***.com",
        "platform": "linux-amd64",
        "sfs30_url": "obs.***.com",
        "sfs_turbo_url": "sfs-turbo.***.com",
        "sfs_url": "sfs.***.com",
        "supportHcs": false,
      }
    }
  }
}
```

```
"swr_addr": "swr.***.com",
"swr_user": "hwofficial",
"rbac_enabled": true,
"cluster_version": "v1.23"
},
"flavor": {
    "description": "High available",
    "is_default": true,
    "name": "HA50",
    "recommend_cluster_flavor_types": ["small"],
    "replicas": 2,
    "resources": [
        {
            "limitsCpu": "250m",
            "limitsMem": "600Mi",
            "name": "everest-csi-controller",
            "requestsCpu": "250m",
            "requestsMem": "600Mi"
        },
        {
            "limitsCpu": "300m",
            "limitsMem": "300Mi",
            "name": "everest-csi-driver",
            "requestsCpu": "300m",
            "requestsMem": "300Mi"
        }
    ],
    "category": ["CCE", "Turbo"]
},
"custom": {
    "annotations": {},
    "cluster_id": "",
    "cluster_name": "",
    "csi_attacher_detach_worker_threads": "60",
    "csi_attacher_worker_threads": "60",
    "default_vpc_id": "",
    "disable_auto_mount_secret": false,
    "enable_node_attacher": false,
    "flow_control": {},
    "multiAZBalance": false,
    "multiAZEnabled": false,
    "node_match_expressions": [],
    "number_of_reserved_disks": "6",
    "over_subscription": "80",
    "project_id": "",
    "tolerations": [
        {
            "key": "node.kubernetes.io/not-ready",
            "operator": "Exists",
            "effect": "NoExecute",
            "tolerationSeconds": 60
        },
        {
            "key": "node.kubernetes.io/unreachable",
            "operator": "Exists",
            "effect": "NoExecute",
            "tolerationSeconds": 60
        }
    ],
    "volume_attaching_flow_ctrl": "0"
}
}
```

4.11.3 CCE Node Problem Detector

Add-on Overview

CCE Node Problem Detector (node-problem-detector, NPD) is an add-on that monitors abnormal events of cluster nodes and connects to a third-party monitoring platform. It is a daemon running on each node. It collects node issues from different daemons and reports them to the API server. It can run as a DaemonSet or a daemon.

Add-on Parameters

Table 4-797 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-798 object	Flavor parameters
custom	Yes	Table 4-799 object	Custom parameters

Table 4-798 Configuration of flavor

Parameter	Mandatory	Type	Description
description	No	String	Add-on description
name	Yes	String	Add-on specification name. The value is fixed at Single-instance .
replicas	Yes	String	Number of pods. The default value is 1.
resources	Yes	resources object	Container resource (CPU and memory) quotas

Table 4-799 Configuration of custom

Parameter	Man datory	Type	Description
feature_gate	No	String	Feature gate, which is used to enable the beta features

Parameter	Mandatory	Type	Description
multiAZBalance	No	Bool	Multi AZ deployment
multiAZEnabled	No	Bool	Whether to deploy the add-on pods in multiple AZs. The default value is false . If this parameter is set to true , cross-AZ deployment is forcibly performed. If this parameter is set to false , cross-AZ deployment is preferred.
npc	Yes	object Table 4-801	node-problem-controller configuration
tolerations	No	List<Object> Table 4-803	Tolerations of the add-on
node_match_expressions	No	List<Object> Table 4-803	Node affinity configuration of the add-on

Table 4-800 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at custom-resources .
requestsCpu	Yes	String	Requested CPU size (unit: m)
requestsMem	Yes	String	Requested memory size (unit: Mi)

Table 4-801 Data structure of the npc field

Parameter	Mandatory	Type	Description
maxTainte dNode	Yes	String or Int	<p>The maximum number of nodes that NPC can add taints to when a single fault occurs on multiple nodes for minimizing impact.</p> <p>The value can be in int or percentage format.</p>

Table 4-802 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator
tolerationSeconds	No	Int	Toleration time window

Table 4-803 nodeMatchExpression node affinity

Parameter	Mandatory	Type	Description
key	No	String	Taint key
values	No	List<String>	Node affinity name
operator	No	String	Operator

Example Request

```
{
  "kind": "Addon",
  "apiVersion": "v3",
  "metadata": {
    "annotations": {
      "addon.install/type": "install"
    }
  },
  "spec": {
    "clusterID": "b78fb690-b82c-11ee-83cf-0255ac100b0f",
    "version": "1.18.48",
    "addonTemplateName": "npd",
    "values": {
      "basic": {
        "image_version": "1.18.48",
        "swr_addr": "****",
        "swr_user": "****",
        "rbac_enabled": true
      }
    }
  }
}
```

```
        "cluster_version": "v1.23"
    },
    "flavor": {
        "description": "custom resources",
        "name": "custom-resources",
        "replicas": 2,
        "resources": [
            {
                "limitsCpu": "100m",
                "limitsMem": "300Mi",
                "name": "node-problem-controller",
                "requestsCpu": "30m",
                "requestsMem": "100Mi"
            },
            {
                "limitsCpu": "100m",
                "limitsMem": "300Mi",
                "name": "node-problem-detector",
                "requestsCpu": "30m",
                "requestsMem": "100Mi"
            }
        ],
        "category": [
            "CCE",
            "Turbo"
        ]
    },
    "custom": {
        "annotations": {},
        "common": {},
        "feature_gates": "",
        "multiAZBalance": false,
        "multiAZEnabled": false,
        "node_match_expressions": [],
        "npc": {
            "maxTaintedNode": "10%"
        },
        "tolerations": [
            {
                "key": "node.kubernetes.io/not-ready",
                "operator": "Exists",
                "effect": "NoExecute",
                "tolerationSeconds": 60
            },
            {
                "key": "node.kubernetes.io/unreachable",
                "operator": "Exists",
                "effect": "NoExecute",
                "tolerationSeconds": 60
            }
        ]
    }
}
```

4.11.4 Kubernetes Dashboard

Add-on Overview

Kubernetes Dashboard is a general purpose, web-based UI designed for managing Kubernetes clusters. With this tool, you can easily manage applications running within the clusters, troubleshoot issues, and even run commands to manage the clusters themselves.

Add-on Parameters

Table 4-804 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-805 object	Flavor parameters
custom	Yes	Table 4-806 object	Custom parameters

Table 4-805 Configuration of flavor

Parameter	Mandatory	Type	Description
replicas	Yes	String	Number of pods. The default value is 1.
resources	Yes	Array of resources object	Container resource (CPU and memory) quotas

Table 4-806 Configuration of custom

Parameter	Mandatory	Type	Description
serviceType	Yes	String	External access type. The value can be NodePort or ELB and defaults to NodePort .
port	No	int	Port number of the kubernetes-dashboard Service. The default value is 8443 .
loadBalancerIP	No	String	IP address of the ELB when external access type is ELB.
elbClass	No	String	ELB type when external access type is ELB. The value can be union (shared load balancer) or performance (dedicated load balancer) and defaults to union .
elbID	No	String	ID of the ELB when external access type is ELB.

Parameter	Mandatory	Type	Description
certUploaded	No	bool	Whether to use a custom certificate. The default value is true .
cert	No	String	Cert of a custom certificate
key	No	String	Key of a custom certificate

Table 4-807 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at dashboard .
requestsCpu	Yes	String	Requested CPU size (unit: m)
requestsMem	Yes	String	Requested memory size (unit: Mi)

Example Request

```
{  
    "kind": "Addon",  
    "apiVersion": "v3",  
    "metadata": {  
        "annotations": {  
            "addon.install/type": "install"  
        }  
    },  
    "spec": {  
        "clusterID": "2292498e-d169-**-9151-**1001ba",  
        "version": "2.2.27",  
        "addonTemplateName": "dashboard",  
        "values": {  
            "basic": {  
                "basickey": "val"  
            },  
            "flavor": {  
  
                "replicas": 1,  
                "resources": [{  
                    "limitsCpu": "100m",  
                    "limitsMem": "512Mi",  
                    "name": "dashboard",  
                    "requestsCpu": "50m",  
                    "requestsMem": "256Mi"  
                }]  
  
            },  
        }  
    }  
}
```

```
        "custom": {
          "cert": "***",
          "certUploaded": true,
          "elbClass": "union",
          "elbID": 0,
          "key": "***",
          "loadBalancerIP": "",
          "port": 8443,
          "serviceType": "NodePort",
          "cluster_id": "2292498e-d169-**-9151-**1001ba",
          "tenant_id": "*****"
        }
      }
    }
```

4.11.5 CCE Cluster Autoscaler

Add-on Overview

The CCE Cluster Autoscaler (autoscaler) add-on enables node pools to be scaled in or out.

Add-on Parameters

Table 4-808 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-809 object	Flavor parameters
custom	Yes	Table 4-810 object	Custom parameters

Table 4-809 flavor

Parameter	Mandatory	Type	Description
replicas	Yes	String	Number of pods. The default value is 2.
resources	Yes	Array of resources object	Container resource (CPU and memory) quotas

Table 4-810 custom

Parameter	Mandatory	Type	Description
cluster_id	Yes	string	Cluster ID.
tenant_id	Yes	string	ID of the project where the current cluster is in.
scaleDownEnabled	No	bool	Whether to enable auto scale-in. The default value is false .
scaleDownDelayAfterAdd	No	int	Coldown period (in minutes) for starting scale-in evaluation again after auto scale-out was triggered in a cluster. The default value is 10 .
scaleDownDelayAfterDelete	No	int	Coldown period (in minutes) for starting scale-in evaluation again after auto scale-in was triggered in a cluster. The default value is 10 .
scaleDownDelayAfterFailure	No	int	Coldown period (in minutes) for starting scale-in evaluation again after auto scale-in triggered by a cluster failed. The default value is 10 .
maxEmptyBulkDeleteFlag	No	int	Number of idle nodes that can be concurrently scaled in. The default value is 10 .
unremovableNodeRecheckTimeout	No	int	Interval (in minutes) for starting the checks again after a node is determined not to be scaled in. The default value is 5 .
scaleDownUtilizationThreshold	No	double	CPU and memory usage thresholds for determining whether a node can be scaled in. The default value is 0.5 .
maxNodesTotal	No	int	Maximum number of nodes that can be added to a cluster. The default value is 1000 .
coresTotal	No	int	Maximum number of CPU cores that can be added to a cluster. The default value is 32000 .
memoryTotal	No	int	Memory upper limit (in Gi) for cluster scale-out. The default value is 128000 .
scaleUpUtilizationEnabled	No	bool	Whether to enable custom scaling. The default value is true .

Parameter	Mandatory	Type	Description
scaleUpUnscheduledPodEnabled	No	bool	Whether to enable automatic scale-out for unscheduled pods. The default value is true .
ignoreDaemonSetsUtilization	No	bool	Whether to ignore DaemonSets' resource usage when thresholds determine if scale-in is performed. The default value is false .
skipNodesWithCustomControllerPods	No	bool	Scale-in is not performed on the node which has containers created by a third-party controller running on it. The default value is true .
logLevel	No	int	Log level. The default value is 4 .
multiAZEnable	No	bool	Whether to enable the forcible mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on will be forcibly scheduled to nodes in different AZs. If there are fewer AZs than pods, the extra pods will fail to run. If both multiAZEnable and multiAZBalance are set to true, the settings of multiAZBalance take effect, which means, the equivalent mode of multi-AZ deployment is used.
multiAZBalance	No	bool	Whether to enable the equivalent mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on are evenly scheduled to the nodes in the cluster in each AZ. If a new AZ is added, it is recommended that you increase add-on pods for cross-AZ HA deployment. With the equivalent multi-AZ deployment, the difference between the number of add-on pods in different AZs will be less than or equal to 1. If resources in one of the AZs are insufficient, pods cannot be scheduled to that AZ.
tolerations	No	Array of Table 4-812	Toleration configuration

Parameter	Mandatory	Type	Description
node_match_expressions	No	Array of Table 4-813	Add-on pod affinity configuration

Table 4-811 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at autoscaler .
requestsCpu	Yes	String	Requested CPU size (unit: m)
requestsMem	Yes	String	Requested memory size (unit: Mi)

Table 4-812 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator
tolerationSeconds	No	Int	Toleration time window

Table 4-813 nodeMatchExpression node affinity

Parameter	Mandatory	Type	Description
key	No	String	Taint key
values	No	List<String>	Node affinity name
operator	No	String	Operator

Example Request

```
{
  "kind": "Addon",
```

```
"apiVersion": "v3",
"metadata": {
    "annotations": {
        "addon.install/type": "install"
    }
},
"spec": {
    "clusterID": "2292498e-*****-0255ac1001ba",
    "version": "1.23.116",
    "addonTemplateName": "autoscaler",
    "values": {
        "basic": {
            "basickey": "val"
        },
        "flavor": {
            "replicas": 2,
            "resources": [
                {
                    "limitsCpu": "1000m",
                    "limitsMem": "1000Mi",
                    "name": "autoscaler",
                    "requestsCpu": "1000m",
                    "requestsMem": "1000Mi"
                }
            ],
            "custom": {
                "cluster_id": "2292498e-*****-0255ac1001ba",
                "coresTotal": 32000,
                "ignoreDaemonSetsUtilization": false,
                "logLevel": 4,
                "maxEmptyBulkDeleteFlag": 10,
                "maxNodeProvisionTime": 15,
                "maxNodesTotal": 1000,
                "memoryTotal": 128000,
                "multiAZBalance": false,
                "multiAZEnabled": false,
                "node_match_expressions": [],
                "scaleDownDelayAfterAdd": 10,
                "scaleDownDelayAfterDelete": 10,
                "scaleDownDelayAfterFailure": 3,
                "scaleDownEnabled": false,
                "scaleDownUnneededTime": 10,
                "scaleDownUtilizationThreshold": 0.5,
                "scaleUpUnscheduledPodEnabled": true,
                "scaleUpUtilizationEnabled": true,
                "skipNodesWithCustomControllerPods": true,
                "tenant_id": "*****",
                "tolerations": [
                    {
                        "key": "node.kubernetes.io/not-ready",
                        "operator": "Exists",
                        "effect": "NoExecute",
                        "tolerationSeconds": 60
                    },
                    {
                        "key": "node.kubernetes.io/unreachable",
                        "operator": "Exists",
                        "effect": "NoExecute",
                        "tolerationSeconds": 60
                    }
                ],
                "unremovableNodeRecheckTimeout": 5
            }
        }
    }
}
```

4.11.6 NGINX Ingress Controller

Add-on Overview

The NGINX Ingress Controller add-on can automatically modify configurations when there are changes to pods in Services. This add-on uses Nginx's excellent stability, performance, and concurrent processing ability to effectively manage containerized applications at the application layer.

Add-on Parameters

Table 4-814 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-815 object	Flavor parameters
custom	Yes	Table 4-816 object	Custom parameters

Table 4-815 flavor

Parameter	Mandatory	Type	Description
replicas	Yes	String	Number of pods. The default value is 1.
resources	Yes	resources object	Container resource (CPU and memory) quotas

Table 4-816 custom

Parameter	Mandatory	Type	Description
ingressClass	Yes	String	Controller name. The default value is nginx .
namespace	Yes	String	Namespace where the add-on is in. The default value is kube-system .
service	Yes	Table 4-821	Configuration of a Service that provides external access

Parameter	Mandatory	Type	Description
config	No	Map<String>String	Nginx configuration parameters. For details, see ConfigMaps .
admission Webhooks	No	Table 4-820	Configuration of ingress admission verification.
metrics	No	Table 4-822	Monitoring metric configuration.
defaultBackendService	No	String	Default 404 service, which is in the format of <namespace>/<service_name>.
extraArgs	No	Table 4-823	Extended parameter configuration.
multiAZEnable	No	bool	Whether to enable the forcible mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on will be forcibly scheduled to nodes in different AZs. If there are fewer AZs than pods, the extra pods will fail to run. If both multiAZEnable and multiAZBalance are set to true, the settings of multiAZBalance take effect, which means, the equivalent mode of multi-AZ deployment is used.
multiAZBalance	No	bool	Whether to enable the equivalent mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on are evenly scheduled to the nodes in the cluster in each AZ. If a new AZ is added, it is recommended that you increase add-on pods for cross-AZ HA deployment. With the equivalent multi-AZ deployment, the difference between the number of add-on pods in different AZs will be less than or equal to 1. If resources in one of the AZs are insufficient, pods cannot be scheduled to that AZ.
tolerations	No	Array of Table 4-818	Toleration configuration
node_match_expressions	No	Array of Table 4-819	Add-on pod affinity configuration

Table 4-817 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at nginx-ingress .
requestsCpu	Yes	String	Requested CPU size (unit: m)
requestsMem	Yes	String	Requested memory size (unit: Mi)

Table 4-818 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator
tolerationSeconds	No	Int	Toleration time window

Table 4-819 nodeMatchExpression node affinity

Parameter	Mandatory	Type	Description
key	No	String	Taint key
values	No	List<String>	Node affinity name
operator	No	String	Operator

Table 4-820 admissionWebhook

Parameter	Mandatory	Type	Description
enable	No	bool	Whether to enable ingress resource admission verification. The default value is true .

Table 4-821 service

Parameter	Mandatory	Type	Description
annotations	No	Map<String>String	Annotations of a Service that provides external access. This parameter is only for configurations of ELB-related options, such as kubernetes.io/elb.class , kubernetes.io/elb.id , and kubernetes.io/elb.pass-through .
loadBalancerIP	No	String	Load balancer IP address used by the Service that is interconnected with the load balancer.

Table 4-822 metrics

Parameter	Mandatory	Type	Description
enable	No	bool	Whether to monitor metrics. The default value is true .
excludeSocketMetrics	No	String	Shielded monitoring metrics. The default value is "nginx_ingress_controller_success,nginx_ingress_controller_header_duration_seconds,nginx_ingress_controller_ingress_upstream_latency_seconds".

Table 4-823 extraArg extended parameter

Parameter	Mandatory	Type	Description
default-ssl-certificate	No	String	Default certificate configuration. For details, see Default SSL Certificate .

Example Request

```
        "basickey": "val"
    },
    "flavor": {
        "replicas": 2,
        "resources": [
            "limitsCpu": "8000m",
            "limitsMem": "4000Mi",
            "name": "nginx-ingress",
            "requestsCpu": "8000m",
            "requestsMem": "4000Mi"
        ]
    },
    "custom": {
        "config": {
            "keep-alive-requests": "100"
        },
        "defaultBackend": {
            "enabled": true
        },
        "defaultBackendService": "",
        "extraArgs": {
            "default-ssl-certificate": ""
        },
        "ingressClass": "nginx",
        "multiAZBalance": false,
        "multiAZEnabled": false,
        "namespace": "kube-system",
        "node_match_expressions": [],
        "service": {
            "annotations": {
                "kubernetes.io/elb.class": "performance",
                "kubernetes.io/elb.id": "8d6bd485-d8ac-4693-815d-9d54d79b0666"
            },
            "loadBalancerIP": ""
        },
        "tolerations": [
            {
                "key": "node.kubernetes.io/not-ready",
                "operator": "Exists",
                "effect": "NoExecute",
                "tolerationSeconds": 60
            },
            {
                "key": "node.kubernetes.io/unreachable",
                "operator": "Exists",
                "effect": "NoExecute",
                "tolerationSeconds": 60
            }
        ]
    }
}
```

4.11.7 Kubernetes Metrics Server

Add-on Overview

From version 1.8 onwards, Kubernetes provides resource usage metrics, such as the container CPU and memory usage, through the Metrics API. These metrics can be directly accessed by users (for example, by using the **kubectl top** command) or used by controllers (for example, Horizontal Pod Autoscaler) in a cluster for decision-making. The specific component is metrics-server, which is used to substitute for Heapster for providing the similar functions. Heapster has been gradually abandoned since v1.11.

Add-on Parameters

Table 4-824 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-825 object	Flavor parameters
custom	Yes	Table 4-826 object	Custom parameters

Table 4-825 flavor

Parameter	Mandatory	Type	Description
description	No	String	Add-on description
name	Yes	String	Add-on specification name. The value is fixed at Single-instance .
replicas	Yes	String	Number of pods. The default value is 1 .
resources	Yes	resources object	Container resource (CPU and memory) quotas

Table 4-826 custom

Parameter	Mandatory	Type	Description
multiAZBalance	No	Bool	Whether the equivalent mode of multi-AZ deployment is enabled. If this function is enabled, the equivalent mode is used.
multiAZEnabled	No	Bool	Whether to deploy the add-on pods in multiple AZs. The default value is false . If this parameter is set to true , cross-AZ deployment is forcibly performed. If this parameter is set to false , cross-AZ deployment is preferred.
tolerations	No	List<Object> Table 4-829	Tolerations of the add-on

Parameter	Mandatory	Type	Description
node_match_expressions	No	List<Object> Table 4-829	Node affinity configuration of the add-on

Table 4-827 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at metrics-server .
requestsCpu	Yes	String	Requested CPU size (unit: m)
requestsMem	Yes	String	Requested memory size (unit: Mi)

Table 4-828 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator
tolerationSeconds	No	Int	Toleration time window

Table 4-829 nodeMatchExpression node affinity

Parameter	Mandatory	Type	Description
key	No	String	Taint key
values	No	List<String>	Node affinity name
operator	No	String	Operator

Example Request

```
{  
    "kind": "Addon",
```

```
"apiVersion": "v3",
"metadata": {
  "annotations": {
    "addon.install/type": "install"
  }
},
"spec": {
  "clusterID": "b78fb690-b82c-11ee-83cf-0255ac100b0f",
  "version": "1.3.39",
  "addonTemplateName": "metrics-server",
  "values": {
    "basic": {
      "image_version": "v0.6.2",
      "swr_addr": "***",
      "swr_user": "***",
      "rbac_enabled": true,
      "cluster_version": "v1.23"
    },
    "flavor": {
      "description": "Has only one instance",
      "name": "Single",
      "replicas": 1,
      "resources": [
        {
          "limitsCpu": "1000m",
          "limitsMem": "1000Mi",
          "name": "metrics-server",
          "requestsCpu": "100m",
          "requestsMem": "300Mi"
        }
      ],
      "category": [
        "CCE",
        "Turbo"
      ]
    },
    "custom": {
      "annotations": {},
      "multiAZBalance": false,
      "multiAZEnabled": false,
      "node_match_expressions": [],
      "tolerations": [
        {
          "key": "node.kubernetes.io/not-ready",
          "operator": "Exists",
          "effect": "NoExecute",
          "tolerationSeconds": 60
        },
        {
          "key": "node.kubernetes.io/unreachable",
          "operator": "Exists",
          "effect": "NoExecute",
          "tolerationSeconds": 60
        }
      ]
    }
  }
}
```

4.11.8 CCE Advanced HPA

Add-on Overview

CCE Advanced HPA (cce-hpa-controller) is an in-house add-on, which can be used to flexibly scale in or out Deployments based on metrics such as CPU usage and memory usage.

Add-on Parameters

Table 4-830 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-831 object	Flavor parameters
custom	Yes	Table 4-832 object	Custom parameters

Table 4-831 flavor

Parameter	Mandatory	Type	Description
replicas	Yes	String	Number of pods. The default value is 2.
resources	Yes	resources object	Container resource (CPU and memory) quotas.

Table 4-832 custom

Parameter	Mandatory	Type	Description
multiAZEnable	No	bool	Whether to enable the forcible mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on will be forcibly scheduled to nodes in different AZs. If there are fewer AZs than pods, the extra pods will fail to run. If both multiAZEnable and multiAZBalance are set to true, the settings of multiAZBalance take effect, which means, the equivalent mode of multi-AZ deployment is used.

Parameter	Mandatory	Type	Description
multiAZBalance	No	bool	Whether to enable the equivalent mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on are evenly scheduled to the nodes in the cluster in each AZ. If a new AZ is added, it is recommended that you increase add-on pods for cross-AZ HA deployment. With the equivalent multi-AZ deployment, the difference between the number of add-on pods in different AZs will be less than or equal to 1. If resources in one of the AZs are insufficient, pods cannot be scheduled to that AZ.
tolerations	No	Array of Table 4-834	Toleration configuration
node_match_expressions	No	Array of Table 4-835	Add-on pod affinity configuration

Table 4-833 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at customedhpa-controller .
requestsCpu	Yes	String	Requested CPU size (unit: m)
requestsMem	Yes	String	Requested memory size (unit: Mi)

Table 4-834 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator

Parameter	Mandatory	Type	Description
tolerationSeconds	No	Int	Toleration time window

Table 4-835 nodeMatchExpression node affinity

Parameter	Mandatory	Type	Description
key	No	String	Taint key
values	No	List<String>	Node affinity name
operator	No	String	Operator

Example Request

```
{  
    "kind": "Addon",  
    "apiVersion": "v3",  
    "metadata": {  
        "annotations": {  
            "addon.install/type": "install"  
        }  
    },  
    "spec": {  
        "clusterID": "2292498e-*****-0255ac1001ba",  
        "version": "1.4.2",  
        "addonTemplateName": "cce-hpa-controller",  
        "values": {  
            "basic": {  
                "basicKey": "val"  
            },  
            "flavor": {  
                "replicas": 1,  
                "resources": [{  
                    "limitsCpu": "100m",  
                    "limitsMem": "300Mi",  
                    "name": "customedhpa-controller",  
                    "requestsCpu": "100m",  
                    "requestsMem": "300Mi"  
                }]  
            },  
            "custom": {  
                "multiAZBalance": false,  
                "multiAZEnabled": false,  
                "node_match_expressions": [],  
                "tolerations": [{  
                    "key": "node.kubernetes.io/not-ready",  
                    "operator": "Exists",  
                    "effect": "NoExecute",  
                    "tolerationSeconds": 60  
                },  
                {  
                    "key": "node.kubernetes.io/unreachable",  
                    "operator": "Exists",  
                    "effect": "NoExecute",  
                    "tolerationSeconds": 60  
                }]  
            }  
        }  
    }  
}
```

{}

4.11.9 CCE AI Suite (NVIDIA GPU)

Add-on Overview

CCE AI Suite (NVIDIA GPU) is a device management add-on that supports GPUs in containers. To use GPU nodes in a cluster, this add-on must be installed.

Add-on Parameters

Table 4-836 Parameters

Parameter	Mandatory	Type	Description
basic	Yes	object	Basic add-on configuration parameters
custom	Yes	Table 4-838 object	Custom parameters

Table 4-837 Configuration of basic

Parameter	Mandatory	Type	Description
cluster_version	No	String	CCE cluster version
device_version	Yes	String	Add-on version
driver_version	Yes	String	Image tag of an add-on pod where a driver is installed. Generally, the value is the same as that of <code>device_version</code> .
obs_url	Yes	String	When a GPU driver is downloaded from the default driver address, the value is the GPU driver address.
swr_addr	Yes	String	Image repository address

Parameter	Mandatory	Type	Description
swr_user	Yes	String	Tenant path of an image repository

Table 4-838 Configuration of custom

Parameter	Mandatory	Type	Description
compatible_with_legacy_api	No	Bool	API compatibility switch Default value: false true : The add-on supports the GPU native mode and xGPU virtualization.
component_schedulername	Yes	String	Name of the scheduler used by the add-on. Default value: default-scheduler
disable_mount_path_v1	No	Bool	Default value: false true : <code>/opt/cloud/cce/nvidia</code> is not mounted to the <code>/usr/lib/nvidia</code> directory of a GPU container.
disable_nvidia_gsp	No	Bool	Default value: true true : The GPU GSP firmware is disabled.
driver_mount_paths	No	String	Driver file directory that needs to be automatically mounted to a GPU container Default value: " bin,lib64 "
enable_fault_isolation	No	Bool	Default value: true true : The add-on detects hardware faults or driver issues of a GPU and then sets the GPU to be unavailable.
enable_health_monitoring	No	Bool	Default value: true true : The add-on detects hardware faults or driver issues of a GPU.
enable_metrics_monitoring	No	Bool	Default value: true true : The add-on collects GPU metrics and reports these metrics to Prometheus.
enable_simple_lib64_mount	No	Bool	Default value: true true : Only the <code>libxxx.so.x</code> file is mounted to a container.

Parameter	Mandatory	Type	Description
enable_xgpu	No	Bool	Default value: false Whether to enable xGPU virtualization.
gpu_driver_config	No	Map	Configurations of the GPU driver for a single node pool Default value: <code>{}</code>
health_check_xids_v2	No	String	GPU error range for the add-on health checks Default value: "74,79"
inject_ld_Library_path	No	String	Value of the LD_LIBRARY_PATH environment variable automatically injected by the add-on to a GPU container Default value: ""
lib64_container_paths	No	String	Mount path of NVIDIA lib64 in a GPU container Default value: "/usr/lib64,/usr/lib/x86_64-linux-gnu"
metrics_delete_interval	No	int	Timeout threshold for deleting a metric when the metric cannot be obtained. The unit is millisecond. Default value: 30000
metrics_monitor_interval	No	int	Interval for obtaining metrics, in milliseconds. Default value: 15000
nvidia_driver_download_url	Yes	String	Path for downloading the NVIDIA driver Default value: ""

Example Request

```
{  
  "kind": "Addon",  
  "apiVersion": "v3",  
  "metadata": {  
    "name": "gpu-beta",  
  },  
  "spec": {  
    "clusterID": "80c9e306-**-**-0255ac100043",  
    "version": "2.0.69",  
    "addonTemplateName": "gpu-beta",  
    "values": {  
      "basic": {  
        "cluster_version": "v1.27",  
        "device_version": "2.0.69",  
      }  
    }  
  }  
}
```

```
"driver_version": "2.0.69",
"obs_url": "***",
"region": "***",
"swr_addr": "***",
"swr_user": "***"
},
"custom": {
  "compatible_with_legacy_api": true,
  "component_schedulename": "kube-scheduler",
  "disable_mount_path_v1": false,
  "disable_nvidia_gsp": true,
  "driver_mount_paths": "bin,lib64",
  "enable_fault_isolation": true,
  "enable_health_monitoring": true,
  "enable_metrics_monitoring": true,
  "enable_simple_lib64_mount": true,
  "enable_xgpu": true,
  "gpu_driver_config": {},
  "health_check_xids_v2": "74,79",
  "inject_ld_Library_path": "",
  "lib64_container_paths": "/usr/lib64/usr/lib/x86_64-linux-gnu",
  "metrics_delete_interval": 30000,
  "metrics_monitor_interval": 15000,
  "nvidia_driver_download_url": ""
},
}
}
```

4.11.10 Volcano Scheduler

Add-on Overview

Volcano is a batch scheduling platform based on Kubernetes. It provides a series of features required by machine learning, deep learning, bioinformatics, genomics, and other big data applications, as a powerful supplement to Kubernetes capabilities.

Add-on Parameters

Table 4-839 Parameters

Parameter	Mandatory	Type	Description
basic	No	Table 4-840 object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-841 object	Flavor parameters
custom	Yes	Table 4-842 object	Custom parameters

Table 4-840 Configuration of basic

Parameter	Mandatory	Type	Description
swr_addr	Yes	String	Add-on download address, which does not need to be specified
swr_user	Yes	String	User who can download the add-on. This parameter does not need to be specified.
platform	Yes	String	Add-on platform, which does not need to be specified
escEndpoint	Yes	String	ECS address, which does not need to be specified

Table 4-841 Configuration of flavor

Parameter	Mandatory	Type	Description
description	No	String	Add-on description
name	Yes	String	Add-on specification name. The value is fixed at Single-instance .
replicas	Yes	String	Number of pods. The default value is 1.
resources	Yes	resources object	Container resource (CPU and memory) quotas

Table 4-842 Configuration of custom

Parameter	Mandatory	Type	Description
multiAZEnabled	No	Bool	Whether multi-AZ deployment is enabled true : The Volcano Scheduler pods are deployed based on anti-affinity.
node_match_expressions	No	Table 4-845	Expression for matching the Volcano Scheduler pods to nodes
tolerations	No	Table 4-844	The format is the same as that of Kubernetes tolerations. It is used to add taints to Volcano Scheduler pods.
oversubscription_ratio	No	int	Node resource overcommitment ratio in the Volcano scheduling environment

Parameter	Mandatory	Type	Description
deschedule_r_enable	No	Bool	Whether to support rescheduling
enable_wor_kload_balancer	No	Bool	Whether load balancers are supported
default_scheduler_config	Yes	yaml	The format is the same as that of the YAML for Volcano.
deschedule_rPolicy	No	yaml	The format is the same as that of the YAML for Volcano descheduling configuration.

Table 4-843 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m) Default value: 250m
limitsMem	Yes	String	Memory size limit (unit: Mi) Default value: 512Mi
name	Yes	String	Add-on name. The value is fixed at virtual-kubelet .
requestsCpu	Yes	String	Requested CPU size (unit: m) Default value: 250m
requestsMem	Yes	String	Requested memory size (unit: Mi) Default value: 512Mi

Table 4-844 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator
tolerationSeconds	No	Int	Toleration time window

Table 4-845 nodeMatchExpression node affinity

Parameter	Mandatory	Type	Description
key	No	String	Taint key
values	No	List<String>	Node affinity name
operator	No	String	Operator

Example Request

```
{  
    "kind": "Addon",  
    "apiVersion": "v3",  
    "metadata": {  
        "annotations": {  
            "addon.install/type": "install"  
        }  
    },  
    "spec": {  
        "clusterID": "2292498e-d169-*****-0255ac1001ba",  
        "version": "1.12.14",  
        "addonTemplateName": "volcano",  
        "values": {  
            "basic": {  
                "swr_addr": "x.x.x.x:20202",  
                "swr_user": "hwofficial",  
                "platform": "linux-amd64",  
                "ecsEndpoint": "x.x.x.x"  
            },  
            "flavor": {  
                "resources": [{  
                    "limitsCpu": "500m",  
                    "limitsMem": "500Mi",  
                    "name": "volcano-scheduler",  
                    "requestsCpu": "2000m",  
                    "requestsMem": "2000Mi"  
                },  
                {  
                    "limitsCpu": "500m",  
                    "limitsMem": "500Mi",  
                    "name": "volcano-controller",  
                    "requestsCpu": "2000m",  
                    "requestsMem": "2000Mi"  
                },  
                {  
                    "limitsCpu": "200m",  
                    "limitsMem": "500Mi",  
                    "name": "volcano-admission",  
                    "requestsCpu": "500m",  
                    "requestsMem": "500Mi"  
                },  
                {  
                    "limitsCpu": "100m",  
                    "limitsMem": "150Mi",  
                    "name": "volcano-agent",  
                    "requestsCpu": "200m",  
                    "requestsMem": "200Mi"  
                },  
                {  
                    "limitsCpu": "50m",  
                    "limitsMem": "50Mi",  
                    "name": "volcano-exporter",  
                    "requestsCpu": "100m",  
                    "requestsMem": "100Mi"  
                }  
            }  
        }  
    }  
}
```

```
        "requestsMem": "100Mi"
    },
    {
        "limitsCpu": "500m",
        "limitsMem": "256Mi",
        "name": "volcano-descheduler",
        "requestsCpu": "1000m",
        "requestsMem": "512Mi"
    },
    {
        "limitsCpu": "300m",
        "limitsMem": "300Mi",
        "name": "volcano-recommender",
        "requestsCpu": "500m",
        "requestsMem": "500Mi"
    },
    {
        "limitsCpu": "200m",
        "limitsMem": "200Mi",
        "name": "volcano-recommender-prometheus-adapter",
        "requestsCpu": "300m",
        "requestsMem": "300Mi"
    }
],
"custom": {
    "default_scheduler_conf": {
        "actions": "allocate,backfill,preempt",
        "tiers": [
            {
                "plugins": [
                    {
                        "name": "priority"
                    },
                    {
                        "name": "conformance"
                    },
                    {
                        "name": "gang",
                        "enablePreemptable": "false",
                        "enableJobStarving": "false"
                    }
                ]
            },
            {
                "plugins": [
                    {
                        "name": "predicates"
                    },
                    {
                        "name": "nodeorder"
                    },
                    {
                        "name": "drf",
                        "enablePreemptable": "false"
                    }
                ]
            },
            {
                "plugins": [
                    {
                        "name": "cce-gpu-topology-predicate"
                    },
                    {
                        "name": "cce-gpu-topology-priority"
                    },
                    {
                        "name": "xgpu"
                    }
                ]
            },
            {
                "plugins": [
                    {
                        "name": "nodelocalvolume"
                    },
                    {
                        "name": "nodeemptydirvolume"
                    }
                ]
            }
        ]
    }
}
```

```
        },
        {
          "name":"nodeCSIscheduling"
        },
        {
          "name":"networkresource"
        }
      ],
      "metrics":{
        "type":"",
        "interval":30s,
      }
    }
  }
}
```

4.11.11 CCE Secrets Manager for DEW

Add-on Overview

The CCE Secrets Manager for DEW add-on (dew-provider) is used to interconnect with Data Encryption Workshop (DEW). This add-on allows you to mount secrets stored outside a cluster (DEW for storing sensitive information) to pods. In this way, sensitive information can be decoupled from the cluster environment, which prevents information leakage caused by program hardcoding or plaintext configuration.

Add-on Parameters

Table 4-846 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
custom	Yes	Table 4-847 object	Custom parameters

Table 4-847 Configuration of custom

Parameter	Mandatory	Type	Description
rotation_poll_interval	No	String	Rotation interval. The default value is 2m . The rotation interval specifies the interval for sending requests to Cloud Secret Management Service (CSMS) and getting the latest credentials. The proper interval is [1m, 1440m] .

Example Request

```
{  
    "kind": "Addon",  
    "apiVersion": "v3",  
    "metadata": {  
        "annotations": {  
            "addon.install/type": "install"  
        }  
    },  
    "spec": {  
        "clusterID": "2292498e-d169-*****-0255ac1001ba",  
        "version": "1.1.1",  
        "addonTemplateName": "dew-provider",  
        "values": {  
            "basic": {  
                "basickey": "val"  
            },  
            "flavor": {  
                "resources": [{  
                    "limitsCpu": "100m",  
                    "limitsMem": "100Mi",  
                    "name": "dew-provider",  
                    "requestsCpu": "100m",  
                    "requestsMem": "100Mi"  
                }]  
            },  
            "custom": {  
                "rotation_poll_interval": "2m"  
            }  
        }  
    }  
}
```

4.11.12 NodeLocal DNSCache

Add-on Overview

NodeLocal DNSCache is an add-on developed based on the community NodeLocal DNSCache. This add-on functions as a DaemonSet to run the DNS cache proxy on cluster nodes to improve cluster DNS performance.

Add-on Parameters

Table 4-848 Parameters

Parameter	Mandatory	Type	Description
basic	No	object	Basic configuration parameters, which do not need to be specified
flavor	Yes	Table 4-849 object	Flavor parameters
custom	Yes	Table 4-850 object	Custom parameters

Table 4-849 Configuration of flavor

Parameter	Mandatory	Type	Description
replicas	No	String	Number of admission-controller component instances in the add-on. The default value is 2.
resources	No	Array resources object	Container resource (CPU and memory) quotas

Table 4-850 Configuration of custom

Parameter	Mandatory	Type	Description
enable_dnscconfig_admission	No	bool	Enables DNSConfig automatic injection. The default value is true . After this function is enabled, a DNSConfig admission controller will be created. The controller intercepts pod creation requests in the namespace labeled with node-localdns-injection=enabled based on Admission Webhook, and automatically configures Pod dnsConfig that uses the DNS cache. If this function is disabled or the pod belongs to a non-target namespace, you must manually configure DNSConfig for the pod.
enable_namespace_admission	No	bool	Adds node-local-dns-injection=enabled to a created namespace. The default value is true . After this tag is added to a namespace, the system identifies the namespace creation request and automatically adds the tag. The target of these operations does not include the built-in namespaces (such as kube-system).

Parameter	Mandatory	Type	Description
multiAZEnable	No	bool	Whether to enable the forcible mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on will be forcibly scheduled to nodes in different AZs. If there are fewer AZs than pods, the extra pods will fail to run. If both multiAZEnable and multiAZBalance are set to true, the settings of multiAZBalance take effect, which means, the equivalent mode of multi-AZ deployment is used.
multiAZBalance	No	bool	Whether to enable the equivalent mode of multi-AZ deployment for the deployment component. The default value is false . Deployment pods of the add-on are evenly scheduled to the nodes in the cluster in each AZ. If a new AZ is added, it is recommended that you increase add-on pods for cross-AZ HA deployment. With the equivalent multi-AZ deployment, the difference between the number of add-on pods in different AZs will be less than or equal to 1. If resources in one of the AZs are insufficient, pods cannot be scheduled to that AZ.
tolerations	No	Array of Table 4-852	Tolerations of the admission-controller component

Table 4-851 Data structure of the resources field

Parameter	Mandatory	Type	Description
limitsCpu	Yes	String	CPU size limit (unit: m)
limitsMem	Yes	String	Memory size limit (unit: Mi)
name	Yes	String	Add-on name. The value is fixed at node-local-dns-admission-controller or node-local-dns-cache .
requestsCpu	Yes	String	Requested CPU size (unit: m)

Parameter	Mandatory	Type	Description
requestsMem	Yes	String	Requested memory size (unit: Mi)

Table 4-852 Taints and tolerations

Parameter	Mandatory	Type	Description
key	No	String	Taint key
effect	No	String	Taint policy
operator	No	String	Operator
tolerationSeconds	No	Int	Toleration time window

Example Request

```
{  
    "kind": "Addon",  
    "apiVersion": "v3",  
    "metadata": {  
        "annotations": {  
            "addon.install/type": "install"  
        }  
    },  
    "spec": {  
        "clusterID": "2292498e-d169-*****-0255ac1001ba",  
        "version": "1.6.2",  
        "addonTemplateName": "node-local-dns",  
        "values": {  
            "basic": {  
                "basicKey": "val"  
            },  
            "flavor": {  
                "replicas": 2,  
                "resources": [{  
                    "limitsCpu": "250m",  
                    "limitsMem": "512Mi",  
                    "name": "node-local-dns-admission-controller",  
                    "requestsCpu": "250m",  
                    "requestsMem": "512Mi"  
                },  
                {  
                    "limitsCpu": "500m",  
                    "limitsMem": "512Mi",  
                    "name": "node-local-dns-cache",  
                    "requestsCpu": "25m",  
                    "requestsMem": "5Mi"  
                }]  
            },  
            "custom": {  
                "enable_dnsconfig_admission": true,  
                "enable_namespace_admission": true,  
                "multiAZBalance": false,  
                "multiAZEnabled": false,  
                "node_match_expressions": [],  
                "tolerations": [{  
                    "key": "node.kubernetes.io/not-ready",  
                    "operator": "Exists",  
                    "value": "true"  
                }]  
            }  
        }  
    }  
}
```

```
        "effect": "NoExecute",
        "tolerationSeconds": 60
    },
    {
        "key": "node.kubernetes.io/unreachable",
        "operator": "Exists",
        "effect": "NoExecute",
        "tolerationSeconds": 60
    }]
}
}
```

5 Kubernetes APIs

Description

Kubernetes APIs are resource-based (RESTful) programming interfaces provided through HTTP. It supports query, creation, update, and deletion of various cluster resources using standard HTTP request methods (POST, PUT, PATCH, DELETE, and GET).

CCE allows you to use native [Kubernetes APIs](#) in the following ways:

- [Calling Kubernetes APIs Through the Cluster API Server](#). It is suitable for API calls on scale thanks to its direct connection to the API Server. This is a recommended option.
- [Calling Kubernetes APIs Through API Gateway](#). It applies to small-scale API calls. API gateway flow control may be triggered when APIs are called on scale.

Calling Kubernetes APIs Through the Cluster API Server

You can use the API server of a Kubernetes cluster to call Kubernetes-native APIs.

Step 1 Obtain the cluster certificate and API server.

- Method 1: Obtain the certificate by calling the API for [obtaining the cluster certificate](#), save the returned information to the **kubeconfig.json** file, and extract the certificate, private key, and API server information. The commands are as follows:

```
# Obtain the CA certificate of the cluster and save it as ca.crt.  
cat ./kubeconfig.json |grep certificate-authority-data | awk -F ""'{print $4}' | base64 -d > ./ca.crt  
# Obtain the client certificate and save it as client.crt.  
cat ./kubeconfig.json |grep client-certificate-data | awk -F ""'{print $4}' | base64 -d > ./client.crt  
# Obtain the client private key and save it as client.key.  
cat ./kubeconfig.json |grep client-key-data | awk -F ""'{print $4}' | base64 -d > ./client.key  
# Obtain the API server.  
cat ./kubeconfig.json |grep server | awk -F ""'{print $4}'
```
- Method 2: Obtain the API server IP address (private or public network address) on the [Overview](#) page of the CCE console and download the certificate (**ca.crt**, **client.crt**, and **client.key** files).

Step 2 Call Kubernetes-native APIs using the cluster certificate.

For example, run the **curl** command to call an API to view the pod information. The following is an example:

```
curl --cacert ./ca.crt --cert ./client.crt --key ./client.key https://192.168.0.198:5443/api/v1/namespaces/default/pods/
```

Specifically:

- `./ca.crt`, `./client.crt`, and `./client.key` specify that the certificate files in the current path are used. Replace them with the actual file paths.
- **192.168.0.198:5443** is the IP address of the cluster API server.
- `/api/v1/namespaces/default/pods/` specifies the URI of the cluster API for viewing pod information in the **default** namespace. For more cluster APIs, see [Kubernetes API](#).

----End

Calling Kubernetes APIs Through API Gateway

You can call Kubernetes-native APIs through API Gateway using the URL in the format of `https://{{clusterid}}.Endpoint/uri`. In the URL, `{clusterid}` indicates the cluster ID, and `uri` indicates the resource path, that is, the path for API access.

Table 5-1 URL parameters

Parameter	Description
<code>{clusterid}</code>	Cluster ID. After a cluster is created, call the API for obtaining a cluster in a specified project to obtain the cluster ID.
Endpoint	Entry (URL) for a web service, which can be obtained from Endpoints .
<code>uri</code>	Access path of an API for performing an operation. Obtain the value from the URI of the API. For details, see Kubernetes API .

Related Documents

- [Accessing a Cluster Using Kubernetes APIs](#)
- [Kubernetes official SDKs](#) (including Go, Python, and Java)

Language	Client Library	Sample Program
C	github.com/kubernetes-client/c	Browse
dotnet	github.com/kubernetes-client/csharp	Browse
Go	github.com/kubernetes/client-go/	Browse
Haskell	github.com/kubernetes-client/haskell	Browse
Java	github.com/kubernetes-client/java	Browse

Language	Client Library	Sample Program
JavaScript	github.com/kubernetes-client/javascript	Browse
Perl	github.com/kubernetes-client/perl/	Browse
Python	github.com/kubernetes-client/python/	Browse
Ruby	github.com/kubernetes-client/ruby/	Browse

6

Permissions and Supported Actions

You can use Identity and Access Management (IAM) for fine-grained permissions management of your CCE clusters. If your account does not need individual IAM users, you can skip this section.

New IAM users do not have any permissions assigned by default. You need to first add them to one or more groups and attach policies or roles to these groups. Users inherit permissions from the groups to which they are added and can perform specific operations on cloud services based on the assigned permissions.

You can grant users permissions by using roles and policies. Roles are provided by IAM to define service-based permissions that match users' job responsibilities. Policies define API-based permissions for operations on specific resources under certain conditions, allowing for more fine-grained, secure access control of cloud resources.

NOTE

If you want to allow or deny the access to an API, fine-grained authorization is a good choice.

An account has all of the permissions required to call all APIs, but IAM users must have the required permissions specifically assigned. The required permissions are determined by the actions supported by the API. Only users with the permissions allowing for those actions can call the API successfully. For example, if an IAM user wants to query ECSs using an API, the user must have been granted permissions that allow the **ecs:servers:list** action.

Supported Actions

CCE provides system-defined policies that can be directly used in IAM. You can also create custom policies to supplement system-defined policies for more refined access control. Operations supported by policies are specific to APIs. The following are common concepts related to policies:

- Permissions: statements in a policy that allow or deny certain operations.
- APIs: REST APIs that can be called by a user who has been granted specific permissions.
- Actions: specific operations that are allowed or denied in a custom policy.

- Dependencies: actions which a specific action depends on. When allowing an action for a user, you also need to allow any existing action dependencies for that user.
- IAM projects: the authorization scope of a custom policy. A custom policy can be applied to IAM projects. Policies that contain actions for IAM projects can be assigned to user groups and be applied in IAM. Policies that contain actions only for IAM projects can be assigned to user groups and be applied in IAM.

 NOTE

The check mark (✓) and cross symbol (✗) respectively indicate that an action takes effect or does not take effect for the corresponding type of projects.

CCE supports the following actions in custom policies.

Table 6-1 Cluster management actions

Permission	API	Action	IAM Project
Obtaining clusters in a project	GET /api/v3/projects/{project_id}/clusters	cce:cluster:list	✓
Obtaining a cluster	GET /api/v3/projects/{project_id}/clusters/{cluster_id}	cce:cluster:get	✓
Creating a cluster	POST /api/v3/projects/{project_id}/clusters	cce:cluster:create	✓
Updating a cluster	PUT /api/v3/projects/{project_id}/clusters/{cluster_id}	cce:cluster:update	✓
Deleting a cluster	DELETE /api/v3/projects/{project_id}/clusters/{cluster_id}	cce:cluster:delete	✓
Upgrading a cluster	POST /api/v2/projects/:projectid/clusters/:clusterid/upgrade	cce:cluster:upgrade	✓
Waking up a cluster	POST /api/v3/projects/{project_id}/clusters/{cluster_id}/operation/awake	cce:cluster:start	✓
Hibernating a cluster	POST /api/v3/projects/{project_id}/clusters/{cluster_id}/operation/hibernate	cce:cluster:stop	✓
Changing the specifications of a cluster	POST /api/v2/projects/{project_id}/clusters/:clusterid/resize	cce:cluster:resize	✓

Permission	API	Action	IAM Project
Obtaining the certificate of a cluster	POST /api/v3/projects/{project_id}/clusters/{cluster_id}/clustercert	cce:cluster:get	✓

Table 6-2 Node management actions

Permission	API	Action	IAM Project
Obtaining all nodes in a cluster	GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes	cce:node:list	✓
Obtaining a node	GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/{node_id}	cce:node:get	✓
Creating a node	POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes	cce:node:create	✓
Updating a node	PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/{node_id}	cce:node:update	✓
Deleting a node	DELETE /api/v3/projects/{project_id}/clusters/{cluster_id}/nodes/{node_id}	cce:node:delete	✓

Table 6-3 Job management actions

Permission	API	Action	IAM Project
Obtaining information about a job	GET /api/v3/projects/{project_id}/jobs/{job_id}	cce:job:get	✓
Listing all jobs	GET /api/v2/projects/{project_id}/jobs	cce:job:list	✓
Deleting one or all jobs	DELETE /api/v2/projects/{project_id}/jobs DELETE /api/v2/projects/{project_id}/jobs/{job_id}	cce:job:delete	✓

Table 6-4 Node pool management actions

Permission	API	Action	IAM Project
Obtaining all node pools in a cluster	GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools	cce:nodepool:list	✓
Obtaining a node pool	GET /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}	cce:nodepool:get	✓
Creating a node pool	POST /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools	cce:nodepool:create	✓
Updating a node pool	PUT /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}	cce:nodepool:update	✓
Deleting a node pool	DELETE /api/v3/projects/{project_id}/clusters/{cluster_id}/nodepools/{nodepool_id}	cce:nodepool:delete	✓

Table 6-5 Chart management actions

Permission	API	Action	IAM Project
Updating a chart	PUT /v2/charts/{id}	cce:chart:update	✓
Uploading a chart	POST /v2/charts	cce:chart:upload	✓
Listing all charts	GET /v2/charts	cce:chart:list	✓
Obtaining information about a chart	GET /v2/charts/{id}	cce:chart:get	✓
Deleting a chart	DELETE /v2/charts/{id}	cce:chart:delete	✓

Table 6-6 Release management actions

Permission	API	Action	IAM Project
Updating a release	PUT /v2/releases/{name}	cce:release:update	✓
Listing all releases	GET /v2/releases	cce:release:list	✓
Creating a release	POST /v2/releases	cce:release:create	✓
Obtaining information about a release	GET /v2/releases/{name}	cce:release:get	✓
Deleting a release	DELETE /v2/releases/{name}	cce:release:delete	✓

Table 6-7 Storage management actions

Permission	API	Action	IAM Project
Creating a PersistentVolumeClaim	POST /api/v1/namespaces/{namespace}/cloudpersistentvolumeclaims	cce:storage:create	✓
Deleting a PersistentVolumeClaim	DELETE /api/v1/namespaces/{namespace}/cloudpersistentvolumeclaims/{name}	cce:storage:delete	✓
Listing all volumes	GET /storage/api/v1/namespaces/{namespace}/listvolumes	cce:storage:list	✓

Table 6-8 Add-on management actions

Permission	API	Action	IAM Project
Creating an add-on instance	POST /api/v3/addons	cce:addonInstance:create	✓
Obtaining an add-on instance	GET /api/v3/addons/{id}?cluster_id={cluster_id}	cce:addonInstance:get	✓
Listing all add-on instances	GET /api/v3/addons?cluster_id={cluster_id}	cce:addonInstance:list	✓

Permission	API	Action	IAM Project
Deleting an add-on instance	DELETE /api/v3/addons/{id}?cluster_id={cluster_id}	cce:addonInstance:delete	✓
Updating an add-on instance	PUT /api/v3/addons/{id}	cce:addonInstance:update	✓

Table 6-9 Quota management actions

Permission	API	Action	IAM Project
Obtaining quota details	GET /api/v3/projects/{project_id}/quotas	cce:quota:get	✓

7 Appendix

7.1 Status Code

Table 7-1 describes the status codes.

Table 7-1 Status code

Status Code	Code	Description
100	Continue	The server has received the initial part of the request and the client should continue to send the remaining part. It is issued on a provisional basis while request processing continues. It alerts the client to wait for a final response.
101	Switching Protocols	The requester has asked the server to switch protocols and the server has agreed to do so. The target protocol must be more advanced than the source protocol. For example, the current HTTP protocol is switched to a later version of HTTP.
201	Created	The request has been fulfilled, resulting in the creation of a new resource.
202	Accepted	The request has been accepted for processing, but the processing has not been completed.
203	Non-Authoritative Information	The server successfully processed the request, but is returning information that may be from another source.

Status Code	Code	Description
204	NoContent	The server has successfully processed the request, but does not return any content. The status code is returned in response to an HTTP OPTIONS request.
205	Reset Content	The server successfully processed the request, but is not returning any content.
206	Partial Content	The server has successfully processed a part of the GET request.
300	Multiple Choices	There are multiple options for the requested resource. For example, this code could be used to present a list of resource characteristics and addresses from which the client such as a browser may choose.
301	Moved Permanently	This and all future requests should be permanently directed to the given URI indicated in this response.
302	Found	The requested resource was temporarily moved.
303	See Other	The response to the request can be found under a different URI, and should be retrieved using a GET or POST method.
304	Not Modified	The requested resource has not been modified. In such case, there is no need to retransmit the resource since the client still has a previously-downloaded copy.
305	Use Proxy	The requested resource is available only through a proxy.
306	Unused	This HTTP status code is no longer used.
400	BadRequest	The request is invalid. The client should modify the request instead of re-initiating it.
401	Unauthorized	The authorization information provided by the client is incorrect or invalid.
402	Payment Required	This status code is reserved for future use.

Stat us Cod e	Code	Description
403	Forbidden	<p>The server has received the request and understood it, but the server is refusing to respond to it.</p> <p>The client should modify the request instead of re-initiating it.</p>
404	NotFound	<p>The requested resource cannot be found.</p> <p>The client should modify the request instead of re-initiating it.</p>
405	MethodNotAllowed	<p>A request method is not supported for the requested resource.</p> <p>The client should modify the request instead of re-initiating it.</p>
406	Not Acceptable	<p>The server cannot fulfill the request based on the content characteristics of the request.</p>
407	Proxy Authentication Required	<p>This code is similar to 401, but indicates that the client must first authenticate itself with the proxy.</p>
408	Request Time-out	<p>The server timed out waiting for the request.</p> <p>The client may re-initiate the request without modifications at any later time.</p>
409	Conflict	<p>The request cannot be processed due to a conflict.</p> <p>This status code indicates that the resource that the client attempts to create already exists, or the request fails to be processed because of the update of the conflict request.</p>
410	Gone	<p>The requested resource cannot be found.</p> <p>The status code indicates that the requested resource has been deleted permanently.</p>
411	Length Required	<p>The server refused to process the request because the request does not specify the length of its content.</p>
412	Precondition Failed	<p>The server does not meet one of the preconditions that the requester puts on the request.</p>

Status Code	Code	Description
413	Request Entity Too Large	The server refuses to process a request because the request entity is too large. The server may disable the connection to prevent the client from sending requests consecutively. If the server temporarily cannot process the request, the response will contain a Retry-After header field.
414	Request-URI Too Large	The URI provided was too long for the server to process.
415	Unsupported Media Type	The server does not support the media type in the request.
416	Requested range not satisfiable	The requested range is invalid.
417	Expectation Failed	The server fails to meet the requirements of the Expect request-header field.
422	UnprocessableEntity	The request is well-formed but is unable to be processed due to semantic errors.
429	TooManyRequests	The client sends excessive requests to the server within a given time (exceeding the limit on the access frequency of the client), or the server receives excessive requests within a given time (beyond its processing capability). In this case, the client should repeat requests after the time specified in the Retry-After header of the response expires.
500	InternalServerError	The server is able to receive the request but it could not understand the request.
501	Not Implemented	The server does not support the requested function.
502	Bad Gateway	The server acting as a gateway or proxy receives an invalid response from a remote server.
503	ServiceUnavailable	The requested service is invalid. The client should modify the request instead of re-initiating it.
504	ServerTimeout	The server could not return a timely response. The response will reach the client only if the request carries a timeout parameter.

Status Code	Code	Description
505	HTTP Version not supported	The server does not support the HTTP protocol version used in the request.

7.2 Error Codes

If an error occurs in API calling, no result is returned. Identify the cause based on the error code of each API. If an error occurs in API calling, HTTP status code 4xx or 5xx is returned. The response body contains the specific error code and information. If you fail to locate the cause of an error, contact customer service and provide the error code, so that we can help you solve the problem as soon as possible.

Format of an Error Response Body

If an error occurs during API calling, an error code and a message will be displayed. The following shows an error response body.

```
{  
    "errorMessage": "The format of message is error",  
    "errorCode": "CCE.01400001"  
}
```

In the preceding information, **errorCode** is an error code, and **errorMessage** describes the error.

Error Code Description

Status Code	Error Code	Error Message	Description	Troubleshooting
400	CCE.01400001	Invalid request.	Invalid request body.	Modify the request body based on the returned message and the CCE API documentation, or contact technical support.
400	CCE.01400002	Subnet not found in the VPC.	No subnet is found in the VPC.	Check whether the subnet in the request body is in the corresponding VPC.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	CCE.01400003	IPv6 not supported for the subnet.	The subnet does not support IPv6.	Use a subnet that supports IPv6.
400	CCE.01400004	No available flavors for master nodes.	There is no available flavor for the master node.	Change to another available cluster flavor or contact technical support.
400	CCE.01400005	Container network CIDR blocks conflict.	The container CIDR block conflicts with the existing one.	Check the container CIDR block based on the returned message.
400	CCE.01400006	Content type not supported.	The content type is invalid.	Use the supported content type by referring to the CCE API documentation.
400	CCE.01400007	Insufficient cluster quota.	Insufficient cluster quota.	Submit a service ticket to increase the cluster quota.
400	CCE.01400008	Insufficient server quota	Insufficient ECS quota.	Submit a service ticket to increase the ECS quota.
400	CCE.01400009	Insufficient CPU quota.	Insufficient ECS CPU quota.	Submit a service ticket to increase the ECS CPU quota.
400	CCE.01400010	Insufficient memory quota.	Insufficient ECS memory quota.	Submit a service ticket to increase the ECS memory quota.
400	CCE.01400011	Insufficient security group quota.	Insufficient security group quota.	Submit a service ticket to increase the security group quota.
400	CCE.01400012	Insufficient EIP quota.	Insufficient EIP quota.	Submit a service ticket to increase the EIP quota.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	CCE.01400013	Insufficient volume quota.	Insufficient disk quota.	Submit a service ticket to increase the disk quota based on the returned message.
400	CCE.01400014	Excessive nodes in the cluster.	The number of nodes exceeds the cluster scale.	Submit a service ticket to change the cluster flavor.
400	CCE.01400015	Version not supported.	The cluster version is not supported.	Create a cluster of the supported version based on the returned message.
400	CCE.01400016	Current cluster type does not support this node flavor.	The current cluster type does not support this node flavor.	Use the correct node flavor based on the returned message.
400	CCE.01400017	No available container CIDR block found.	No available container CIDR block is found.	Use a correct container CIDR block based on the returned message.
400	CCE.01400018	This type of OS cannot be created in this CCE version.	The current CCE version does not support this type of OS.	Use a supported OS based on the returned message.
400	CCE.01400019	Insufficient resource tenant quota.	The quota of the resource tenant is insufficient.	Rectify the fault based on the returned message or contact technical support.
400	CCE.01400020	Insufficient VPC quota.	Insufficient VPC quota.	Rectify the fault based on the returned message or contact technical support.
400	CCE.01400021	No available flavors for nodes.	There is no available flavor for the node.	Change to another available node flavor or contact technical support.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	CCE.01400022	No available node volumes for nodes.	There is no available EVS disk flavor for the node.	Change to another available EVS disk flavor or contact technical support.
400	CCE.01400023	operation conflict	Nodes cannot be created during cluster scale-out.	Try again later.
400	CCE.01400024	operation conflict	The cluster cannot be deleted during node creation.	Try again later.
400	CCE.01400025	Unsupported flavor with insufficient sub-ENI quota	The sub-ENI quota is insufficient. The VM flavor is not supported by CCE Turbo clusters.	Select a VM flavor whose sub-ENI quota is not 0.
400	CCE.01400033	Snapshot task already exists.	The cluster backup task already exists.	Wait until the cluster backup task is complete and try again.
400	CCE.02400001	Invalid request.	Invalid request body.	Modify the request body based on the returned message and the CCE API documentation, or contact technical support.
400	CCE.03400001	Invalid request.	Invalid request body.	Modify the request body based on the returned message and the CCE API documentation, or contact technical support.

Status Code	Error Code	Error Message	Description	Troubleshooting
400	CCE.03400002	Missing access key.	The access key is missing.	Ensure that the version of the installed or upgraded storage add-on is correct, or contact technical support.
401	CCE.01401001	Authorization failed.	Authentication failed.	Rectify the fault based on the returned message or contact technical support.
401	CCE.02401001	Authorization failed.	Authentication failed.	Rectify the fault based on the returned message or contact technical support.
401	CCE.03401001	Authorization failed.	Authentication failed.	Rectify the fault based on the returned message or contact technical support.
403	CCE.01403001	Forbidden.	Access denied.	Rectify the fault based on the returned message or contact technical support.
403	CCE.01403002	Current cluster status does not allow node pool to be deleted.	A node pool in the cluster that is in the current state cannot be deleted.	Wait until the cluster runs properly and try again.
403	CCE.01403003	Current node pool status does not allow node pool to be deleted.	The node pool in the current state cannot be deleted.	Wait until the node pool runs properly and try again.
403	CCE.01403005	Node pool cannot be deleted when it is scaling.	The node pool is being scaled out and cannot be deleted.	Wait until the node pool scale-out completes and try again.

Status Code	Error Code	Error Message	Description	Troubleshooting
403	CCE.01403006	Node pool cannot be deleted when exists installing or deleting nodes.	There are nodes that are being installed or deleted and the node pool cannot be deleted.	Wait until the nodes in the node pool are installed or deleted and try again.
403	CCE.02403001	Forbidden.	Access denied.	Rectify the fault based on the returned message or contact technical support.
403	CCE.03403001	Forbidden.	Access denied.	Rectify the fault based on the returned message or contact technical support.
404	CCE.01404001	Resource not found.	Resources not found.	Check whether the resource to be accessed has been deleted.
404	CCE.02404001	Resource not found.	Resources not found.	Check whether the resource to be accessed has been deleted.
404	CCE.03404001	Resource not found.	Resources not found.	Check whether the resource to be accessed has been deleted.
409	CCE.01409001	The resource already exists.	The resource already exists.	Delete the resource and try again.
409	CCE.01409002	Resource updated with out-of-date version.	An out-of-date version is used to update the target resource.	Ensure that the target resource version is the latest one or contact technical support.
409	CCE.02409001	The resource already exists.	The resource already exists.	Delete the resource and try again.

Status Code	Error Code	Error Message	Description	Troubleshooting
409	CCE.03409001	Addon instance has installed.	The add-on instance has been installed.	Delete the add-on instance and install it again.
429	CCE.01429002	Resource locked by other requests.	The resource is locked by another request.	Rectify the fault based on the returned message or contact technical support.
429	CCE.01429003	The concurrency limit of tasks has been reached.	The number of concurrent tasks has reached the upper limit.	Reduce the frequency of sending requests or contact technical support.
429	CCE.02429001	The throttling threshold has been reached.	The maximum number of requests has been reached.	Reduce the frequency of sending requests or contact technical support.
500	CCE.01500001	Internal error.	Internal error.	Rectify the fault based on the returned message or contact technical support.
500	CCE.02500001	Internal error.	Internal error.	Rectify the fault based on the returned message or contact technical support.
500	CCE.03500001	Internal error.	Internal error.	Rectify the fault based on the returned message or contact technical support.

7.3 Obtaining a Project ID

Scenarios

A project ID is required for some URLs when APIs are called. Therefore, obtain a project ID in advance. Two methods are available:

- [Call an API](#)

Obtaining the Project ID by Calling an API

The API for obtaining a project ID is **GET https://{{Endpoint}}/v3/projects**.

Endpoint indicates the endpoint of IAM, which can be obtained from [Endpoints](#).
For details about API authentication, see [Authentication](#).

The following is an example response. The value of **id** is the project ID.

```
{  
    "projects": [  
        {  
            "domain_id": "65382450e8f64ac0870cd180d14e684b",  
            "is_domain": false,  
            "parent_id": "65382450e8f64ac0870cd180d14e684b",  
            "name": "project_name",  
            "description": "",  
            "links": {  
                "next": null,  
                "previous": null,  
                "self": "https://www.example.com/v3/projects/a4a5d4098fb4474fa22cd05f897d6b99"  
            },  
            "id": "a4a5d4098fb4474fa22cd05f897d6b99",  
            "enabled": true  
        }  
    ],  
    "links": {  
        "next": null,  
        "previous": null,  
        "self": "https://www.example.com/v3/projects"  
    }  
}
```

7.4 Obtaining an Account ID

An account ID (domain-id) is required for some URLs when an API is called. To obtain an account ID, perform the following operations:

1. Sign up and log in to the management console.
2. Click the username in the upper right corner and choose **My Credentials** from the drop-down list.

On the **API Credentials** page, view the account ID.

7.5 Specifying Add-ons to Be Installed During Cluster Creation

When creating a cluster, you can add a key-value pair to **annotations** of the **metadata** field in the request body to install an add-on in the cluster. The key is **cluster.install.addons/install**, and the value is a JSON array of **AddonTemplate**.

Table 7-2 Value data structure

Parameter	Mandatory	Type	Description
Value	Yes	JSON array of AddonTemplate string	Add-on to be installed in the cluster. If this parameter is not specified, the CoreDNS and CCE Container Storage (Everest) add-ons are installed in the cluster by default. For details about the parameter values, see Table 7-3 .

Table 7-3 Data structure of the AddonTemplate field

Parameter	Mandatory	Type	Description
addonTemplateName	Yes	String	Add-on name. Options: <ul style="list-style-type: none">● coredns: Install CoreDNS.● everest: Install CCE Container Storage (Everest).● node-local-dns: Install NodeLocal DNSCache.● volcano: Install Volcano Scheduler.● npd: Install CCE Node Problem Detector.
version	No	String	Add-on version. To view the add-on version, log in to the CCE console, choose Add-ons in the navigation pane, click the name of the target add-on, and check the change history. If this parameter is left blank, the latest version is used by default.
values	No	Json Map	<ul style="list-style-type: none">● CoreDNS: For details about the parameters required for installing the add-on, see CoreDNS. <p>NOTE You do not need to specify this parameter when installing the CCE Container Storage (Everest), NodeLocal DNSCache, Volcano Scheduler, or CCE Node Problem Detector add-on.</p>

Example Request

Create a cluster using a VPC network and install CoreDNS and CCE Container Storage (Everest) in it.

```
{
  "kind": "Cluster",
  "apiVersion": "v3",
  "metadata": {
    "name": "test",
    "annotations": {
      "cluster.install.addons.external/install": "[{\\"addonTemplateName\\":\\"icagent\\",\\"extendParam\\":\\"\\logSwitch\\":\\\"false\\\",\\\"tDSEnable\\\":\\\"false\\\"}}]",
      "cluster.install.addons/install": "[{\\"addonTemplateName\\":\\"coredns\\",\\"values\\":{\\"flavor\\":\\"is_default\\":false,\\"name\\":2500,\\"recommend_cluster_flavor_types\\":[\\"small\\"],\\"replicas\\":2,\\"resources\\":[\{\\"limitsCpu\\\":\\\"500m\\\",\\\"limitsMem\\\":\\\"512Mi\\\",\\\"name\\\":\\"coredns\\",\\"replicas\\":2,\\"requestsCpu\\\":\\\"500m\\\",\\\"requestsMem\\\":\\\"512Mi\\\"}],\\\"size\\\":\\\"small\\\",\\\"category\\\":[\\"CCE\\\",\\\"Turbo\\\"]]}}, {\\"addonTemplateName\\":\\"everest\\"}]"
    }
  },
  "spec": {
    "category": "CCE",
    "flavor": "cce.s1.small",
    "version": "v1.29",
    "type": "VirtualMachine",
    "hostNetwork": {
      "vpc": "*****",
      "subnet": "*****"
    },
    "containerNetwork": {
      "mode": "vpc-router",
      "cidrs": [
        {
          "cidr": "10.0.0.0/16"
        }
      ]
    },
    "ipv6enable": false,
    "description": "",
    "billingMode": 0,
    "kubeProxyMode": "iptables",
    "extendParam": {
      "alpha.cce/fixPoolMask": "25",
      "enterpriseProjectId": "0"
    },
    "authentication": {
      "mode": "rbac"
    },
    "configurationsOverride": [
      {
        "name": "kube-apiserver",
        "configurations": [
          {
            "name": "support-overload",
            "value": true
          }
        ]
      }
    ],
    "deletionProtection": false,
    "serviceNetwork": {
      "IPv4CIDR": "10.247.0.0/16"
    }
  }
}
```

7.6 How to Obtain Parameters in the API URI

Obtaining a Project ID (`project_id`)

`project_id` indicates the project ID, which can be obtained from the console or APIs. For details, see [Obtaining a Project ID](#).

Obtaining a Cluster ID (`cluster_id`)

Step 1 Log in to the CCE console. In the navigation pane, choose **Clusters**.

Step 2 Click the name of the created cluster. The cluster details page is displayed. Obtain the cluster ID.

----End

Obtaining a Node ID (`node_id`)

Step 1 Log in to the CCE console. In the navigation pane, choose **Clusters**.

Step 2 Click the name of the created cluster to access the cluster console. In the navigation pane, choose **Nodes**. On the **Nodes** tab, move the cursor to the node name and view the node ID.

----End

Obtaining a Node Pool ID (`nodepool_id`)

Step 1 Log in to the CCE console. In the navigation pane, choose **Clusters**.

Step 2 Click the name of the created cluster to access the cluster console. In the navigation pane, choose **Nodes**. On the **Node Pools** tab, move the cursor to the node pool name and view the node pool ID.


----End

Obtaining a Job ID (`job_id`)

Step 1 Log in to the CCE console. In the navigation pane, choose **Clusters**. The following uses cluster management as an example to describe how to obtain the **job_id** of the cluster that is being created.

Step 2 Obtain the job ID.

1. If you are using Google Chrome, press **F12**. On the pane displayed on the right, click the **Network** tab.
2. Click **Operation Records** on the CCE console to view details about cluster operation records.
3. Enter **jobs** in the **Filter** text box to filter out the jobs. Select a job from the list on the left and click **Preview**. The **uid** field indicates the job UID.

Figure 7-1 Obtaining the job ID

----End

7.7 Creating a VPC and Subnet

Context

To provide a secure and isolated network environment for CCE, create a VPC before creating a cluster.

If you have already created a VPC, you do not need to create it again.

Creating a VPC

- Step 1** On the management console, click **Service List**, and choose **Network > Virtual Private Cloud** to launch the VPC console.
- Step 2** On the VPC console, click **Create VPC** to create a VPC.
- Step 3** The created VPC is displayed in the list. Click its name and obtain the VPC ID, which will be required in **cluster creation**.

----End

Creating a Subnet

- Step 1** On the management console, click **Service List**, and choose **Network > Virtual Private Cloud** to launch the VPC console.
- Step 2** On the VPC console, choose **Virtual Private Cloud > Subnets** in the navigation pane, and click **Create Subnet** in the upper right corner.
- Step 3** Create a subnet as prompted and click its name to obtain the network ID, which will be required in **cluster creation**.

----End

7.8 Creating a Key Pair

Context

Create a key pair before you create a container cluster. Key pairs are used for user identity authentication upon login to a worker node.

If you have already created a key pair, you do not need to create it again.

Procedure

- Step 1** On the management console, click **Service List**, and choose **Compute > Elastic Cloud Server** to go to the ECS console.
 - Step 2** In the navigation pane, choose **Key Pair**.
 - Step 3** Click **Create Key Pair** and create a key pair as prompted.
 - Step 4** After the creation is complete, a key file in the **.pem** format is generated and automatically saved to the default directory on your local computer.
- End

7.9 Node Flavor Description

NOTE

Different regions support different node flavors, and node flavors may be added or brought offline. You are advised to log in to the CCE console and check whether the required node flavors are supported on the page for creating nodes.

- **CCE standard cluster**

CCE clusters support only 2 vCPUs and 4 GiB of memory or higher flavors. You are advised to get node flavors on the console. For details about node flavors, see A Summary List of x86 ECS Specifications.

You need to enter the specific flavor name, for example, **c6.large.2**.

7.10 Adding a Salt in the password Field When Creating a Node

When a node is created through the API, you need to add a salt to the **password** field to safeguard the password. The procedure is as follows:

NOTE

The salt must be set based on the password complexity requirements:

- A string of 8–26 characters.
- Contains at least three of the following character types: uppercase letters, lowercase letters, digits, and special characters !@#\$%^_=+[{}]:.,/?
- Cannot contain the username or the username spelled backwards.
- Cannot contain the username, the username spelled backwards, or more than two consecutive characters in the username (for Windows ECSS).

Python

To salt a password in the Python 3.7.7 environment, perform the following steps:

```
pip install passlib
python -c "import base64; from passlib.hash import sha512_crypt; salted_password =
base64.b64encode(sha512_crypt.hash('*****', salt='salt', rounds=5000).encode()).decode();
print(salted_password)"
```

 NOTE

The **python crypt** package has compatibility issues in macOS. If the package cannot be executed, run it in Linux.

Java

To salt a password in the Java environment, perform the following steps:

1. Obtain a random number as the salt.

```
private static String getCharAndNumr(int length) {  
    String val = "";  
    Random random = new SecureRandom();  
    for (int i = 0; i < length; i++) {  
        // Indicates whether to output letters or digits.  
        String charOrNum = random.nextInt(2) % 2 == 0 ? "char" : "num";  
        // Character string  
        if ("char".equalsIgnoreCase(charOrNum)) {  
            // Indicates whether an upper-case or lower-case letter is obtained.  
            int choice = random.nextInt(2) % 2 == 0 ? 65 : 97;  
            val += (char) (choice + random.nextInt(26));  
        } else if ("num".equalsIgnoreCase(charOrNum)) { // Digit  
            val += String.valueOf(random.nextInt(10));  
        }  
    }  
    return val;  
}
```

2. Generate a salt.

```
private static String generateSalt() {  
    String salt;  
    try {  
        salt = "$6$" + getCharAndNumr(16);  
    } catch (Exception e){  
        salt = defaultSalt;  
    }  
  
    return salt;  
}
```

3. Generate a ciphertext password based on the salt.

```
public static String getSaltPassword(String password) {  
    if(StringUtils.isBlank(password)) {  
        throw new BizException("password is empty");  
    }  
  
    String salt = generateSalt();  
  
    Crypt crypt = new Crypt();  
    return crypt.crypt(password, salt);  
}
```

4. Encode the value of the **password** field using Base64.

```
(Base64.getEncoder().encodeToString(AddSaltPasswordUtil.getSaltPassword(cceNodeCreateVo.getPassword()).getBytes()))
```

5. A complete example is as follows:

```
import java.util.Base64;  
import java.util.Random;  
import java.security.SecureRandom;  
  
import org.apache.commons.codec.digest.Crypt;  
import org.apache.commons.lang.StringUtils;  
  
public class PassWord {  
  
    static String defaultSalt = null;  
  
    public static void main(String[] args) throws Exception {
```

```
System.out.println(Base64.getEncoder().encodeToString(PassWord.getSaltPassword( "Custom
password").getBytes()));
}

// Generate a ciphertext password based on the salt.
public static String getSaltPassword(String password) throws Exception {
    if(StringUtils.isBlank(password)) {
        throw new Exception("password is empty");
    }
    String salt = generateSalt();
    return Crypt.crypt(password, salt);
}

//Generate a salt.
private static String generateSalt() {
    String salt;
    try {
        salt = "$6$" + getCharAndNumr(16);
    }catch (Exception e){
        salt = defaultSalt;
    }
    return salt;
}

// Obtain a random number as the salt.
private static String getCharAndNumr(int length) {
    String val = "";
    Random random = new SecureRandom();
    for (int i = 0; i < length; i++) {
        // Indicates whether to output letters or digits.
        String charOrNum = random.nextInt(2) % 2 == 0 ? "char" : "num";
        // Character string
        if ("char".equalsIgnoreCase(charOrNum)) {
            // Indicates whether an upper-case or lower-case letter is obtained.
            int choice = random.nextInt(2) % 2 == 0 ? 65 : 97;
            val += (char) (choice + random.nextInt(26));
        } else if ("num".equalsIgnoreCase(charOrNum)) {// Digit
            val += String.valueOf(random.nextInt(10));
        }
    }
    return val;
}
```

Go

You can use either of the following methods to salt passwords for the Go language:

- <https://github.com/amoghe/go-crypt>
- <https://github.com/GehirnInc/crypt>

7.11 Maximum Number of Pods That Can Be Created on a Node

Calculation of the Maximum Number of Pods on a Node

The maximum number of pods that can be created on a node is calculated based on the cluster type:

Network Model	Maximum Number of Pods on a Node	Recommended Configuration
Tunnel network	Maximum number of pods on a node	None
VPC network	The smaller value between the maximum number of pods on a node and the number of container IP addresses that can be allocated on a node	To ensure new pods run smoothly on a node, make sure that the number of pods on the node does not exceed the number of container IP addresses that can be assigned to it. If there are not enough container IP addresses available on the node, the new pods may not function properly.

Number of Allocatable Container IP Addresses on a Node

When creating a cluster in the VPC network model, specify the number of container IP addresses that can be allocated on each node using alpha.cce/fixPoolMask based on the rules for managing container IP addresses.

The maximum number of pods that can be created on a node is determined by the number of container IP addresses that can be allocated to it. In a **container network**, each pod needs its own IP address. If there are not enough pre-allocated container IP addresses on the node, pods cannot be created. If **hostNetwork: true** is configured in the YAML file, pods will use the **host network** instead of the allocatable container IP addresses. For details, see [Pod IP Address Allocation Differences Between the Container Network and Host Network](#).

By default, a node occupies three container IP addresses (network address, gateway address, and broadcast address). Therefore, the number of container IP addresses that can be allocated to a node equals the number of selected container IP addresses minus 3.

Maximum Number of Pods on a Node

When creating a node, you can configure the maximum number of pods (maxPods) that can be created on the node. This parameter is a configuration item of kubelet and determines the maximum number of pods that can be created by kubelet.

NOTICE

For nodes in the default node pool (**DefaultPool**), the maximum number of pods cannot be changed after the nodes are created.

After a node in a custom node pool is created, you can modify the **max-pods** parameter in the node pool configuration to change the maximum number of pods on the node.

Table 7-4 lists the default maximum number of pods on a node based on node specifications.

Table 7-4 Default maximum number of pods on a node

Memory	Max. Pods
4 GB	20
8 GB	40
16 GB	60
32 GB	80
64 GB or above	110

Pod IP Address Allocation Differences Between the Container Network and Host Network

When creating a pod, you can select the container network or host network for the pod.

- Container network (default): **Each pod is assigned an IP address by the cluster networking add-ons, which occupies the IP addresses of the container network.**
- Host network: Pods with **hostNetwork: true** configured directly use the network of the host. After the configuration, the pods use the ports on the host and their IP address is identical to that of the host, **without relying on the IP addresses of the container network.** When using a host network, avoid conflicts between the pod ports and service ports on the host. Use a host network only if a particular application requires access to a specific port on the host.

7.12 Node OS

Node OSs and Cluster Types

Table 7-5 Mapping between node OSs and cluster types

OS	Cluster Version	CCE Standard Cluster		Latest Kernel
		VPC Network	Tunnel Network	
Ubuntu 22.04	v1.29	✓	✗	5.15.0-46-generic
	v1.28	✓	✗	5.15.0-46-generic
	v1.27	✓	✗	5.15.0-46-generic
	v1.25	✓	✗	5.15.0-46-generic
	v1.23	✓	✗	5.15.0-46-generic
EulerOS release 2.9	v1.29	✓	✓	4.18.0-147.5.1.6.h541.eule rosv2r9.x86_64
	v1.28	✓	✓	4.18.0-147.5.1.6.h541.eule rosv2r9.x86_64
	v1.27	✓	✓	4.18.0-147.5.1.6.h541.eule rosv2r9.x86_64
	v1.25	✓	✓	4.18.0-147.5.1.6.h541.eule rosv2r9.x86_64
	v1.23	✓	✓	4.18.0-147.5.1.6.h541.eule rosv2r9.x86_64
	v1.21	✓	✓	4.18.0-147.5.1.6.h541.eule rosv2r9.x86_64
	v1.19.10	✓	✓	4.18.0-147.5.1.6.h541.eule rosv2r9.x86_64
CentOS Linux release 7.7	v1.23	✓	✓	3.10.0-1062.12.1.el7.x86_6 4
	v1.21	✓	✓	3.10.0-1062.12.1.el7.x86_6 4
	v1.19.10	✓	✓	3.10.0-1062.12.1.el7.x86_6 4
	v1.17.9	✓	✓	3.10.0-1062.12.1.el7.x86_6 4

OS	Cluster Version	CCE Standard Cluster		Latest Kernel
		VPC Network	Tunnel Network	
EulerOS release 2.5	v1.25	√	√	3.10.0-862.14.1.0.h197.eulerosv2r7.x86_64
	v1.23	√	√	3.10.0-862.14.1.0.h197.eulerosv2r7.x86_64
	v1.21	√	√	3.10.0-862.14.1.0.h197.eulerosv2r7.x86_64
	v1.19.10	√	√	3.10.0-862.14.1.0.h197.eulerosv2r7.x86_64
	v1.17.9	√	√	3.10.0-862.14.1.5.h470.eulerosv2r7.x86_64
	v1.15.11	√	√	3.10.0-862.14.1.5.h470.eulerosv2r7.x86_64

7.13 Space Allocation of a Data Disk

This section describes how to allocate data disk space to nodes so that you can configure the data disk space accordingly.

Allocating Default Data Disk Space

When creating a node, you can customize Data Disk Space Allocation in the expanded area of **Data Disk**.

- **Space Allocation for Container Engines**
 - Specified disk space: CCE divides the data disk space for two parts by default. One part is used to store the Docker/containerd working directories, container image data, and image metadata. The other is reserved for kubelet and emptyDir volumes. The available container engine space affects image pulls and container startup and running.
 - Container engine and container image space (90% by default): stores the container runtime working directories, container image data, and image metadata.
 - kubelet and emptyDir space (10% by default): stores pod configuration files, secrets, and mounted storage such as emptyDir volumes.



NOTE

If the sum of the container engine and container image space and the kubelet and emptyDir space is less than 100%, the remaining space will be allocated for user data. You can mount the storage volume to a service path. Do not leave the path empty or set it to a key OS path such as the root directory.

- Shared disk space: In clusters of v1.21.10-r0, v1.23.8-r0, v1.25.3-r0, or later versions, CCE allows **a container engine (Docker/containerd) and kubelet components to share data disk space.**
- **Space Allocation for Pods:** indicates the basesize of a pod. You can set an upper limit for the disk space occupied by each workload pod (including the space occupied by container images). This setting prevents the pods from taking all the disk space available, which may cause service exceptions. It is recommended that the value is less than or equal to 80% of the container engine space. This parameter is related to the node OS and container storage rootfs and is not supported in some scenarios. For details, see [Mapping Between OS and Container Storage Rootfs](#).
- Write Mode
 - **Linear:** A linear logical volume integrates one or more physical volumes. Data is written to the next physical volume when the previous one is used up.
 - **Striped:** available only if there are at least two data disks. A striped logical volume stripes data into blocks of the same size and stores them in multiple physical volumes in sequence. This allows data to be concurrently read and written. A storage pool consisting of striped volumes cannot be scaled-out.

Space Allocation for Container Engines

For a node using a non-shared data disk (100 GiB for example), the division of the disk space varies depending on the container storage Rootfs type **Device Mapper** or **OverlayFS**. For details about the container storage Rootfs corresponding to different OSs, see [Mapping Between OS and Container Storage Rootfs](#).


- **Rootfs (Device Mapper)**

By default, the container engine and image space, occupying 90% of the data disk, can be divided into the following two parts:

- The **/var/lib/docker** directory is used as the Docker working directory and occupies 20% of the container engine and container image space by default. (Space size of the **/var/lib/docker** directory = **Data disk space x 90% x 20%**)
- The thin pool is used to store container image data, image metadata, and container data, and occupies 80% of the container engine and container image space by default. (Thin pool space = **Data disk space x 90% x 80%**)

The thin pool is dynamically mounted. You can view it by running the **lsblk** command on a node, but not the **df -h** command.


Figure 7-2 Space allocation for container engines of Device Mapper



- **Rootfs (OverlayFS)**

No separate thin pool. The entire container engine and container image space (90% of the data disk by default) are in the `/var/lib/docker` directory.

Figure 7-3 Space allocation for container engines of OverlayFS



Space Allocation for Pods

The customized pod container space (`basesize`) is related to the node OS and container storage Rootfs. For details about the container storage Rootfs, see [Mapping Between OS and Container Storage Rootfs](#).

- Device Mapper supports custom pod `basesize`. The default value is 10 GiB.
- In OverlayFS mode, the pod container space is not limited by default.

When configuring `basesize`, consider the maximum number of pods allowed on one node. The container engine space should be greater than the total disk space used by containers. Formula: **Container engine space and container image space (90% by default) > Number of containers x basesize**. Otherwise, the container engine space allocated to the node may be insufficient and the container cannot be started.

For nodes that support `basesize`, when Device Mapper is used, although you can limit the size of the `/home` directory of a single container (to 10 GiB by default), all containers on the node still share the thin pool of the node for storage. They are not completely isolated. When the sum of the thin pool space used by certain containers reaches the upper limit, other containers cannot run properly.

In addition, after a file is deleted in the `/home` directory of the container, the thin pool space occupied by the file is not released immediately. Therefore, even if `basesize` is set to 10 GiB, the thin pool space occupied by files keeps increasing until 10 GiB when files are created in the container. The space released after file deletion will be reused but after a while. If **the number of containers on the node multiplied by basesize** is greater than the thin pool space size of the node, there is a possibility that the thin pool space has been used up.

Mapping Between OS and Container Storage Rootfs

Table 7-6 Node OSs and container engines in CCE clusters

OS	Container Storage Rootfs	Custom Basesize
CentOS 7.x	Clusters of v1.19.16 and earlier use Device Mapper. Clusters of v1.19.16 and later use OverlayFS.	Supported when Rootfs is set to Device Mapper and the runtime is Docker. The default value is 10 GiB. If Rootfs is set to OverlayFS, the basesize cannot be customized.
EulerOS 2.5	Device Mapper	Supported only when the runtime is Docker. The default value is 10 GiB.
EulerOS 2.9	OverlayFS	Supported by Docker clusters of v1.19.16-r0, v1.21.3-r0, v1.23.3-r0, or later. There are no limits by default. Not supported by clusters of a version earlier than v1.19.16-r0, v1.21.3-r0, or v1.23.3-r0.
Ubuntu 22.04	OverlayFS	Not supported

Garbage Collection Policies for Container Images

When the container engine space is insufficient, image garbage collection is triggered.

The policy for garbage collecting images takes two factors into consideration: **HighThresholdPercent** and **LowThresholdPercent**. Disk usage exceeding the high threshold (default: 80%) will trigger garbage collection. The garbage collection will delete least recently used images until the low threshold (default: 70%) is met.

Recommended Configuration for the Container Engine Space

- The container engine space should be greater than the total disk space used by containers. Formula: **Container engine space > Number of containers x basesize**
- You are advised to create and delete files of containerized services in local storage volumes (such as emptyDir and hostPath volumes) or cloud storage directories mounted to the containers. In this way, the thin pool space is not occupied. emptyDir volumes occupy the kubelet space. Therefore, properly plan the size of the kubelet space.
- You can deploy services on nodes that use the OverlayFS (for details, see [Mapping Between OS and Container Storage Rootfs](#)) so that the disk space

occupied by files created or deleted in containers can be released immediately.

Data Disk Shared Between a Container Engine and kubelet Components

Docker/containerd and kubelet components share the space of a data disk.


NOTICE

- This function is available only to clusters of v1.21.10-r0, v1.23.8-r0, v1.25.3-r0, or later versions.
- If Rootfs is set to OverlayFS, shared data disks are supported. If Rootfs is set to Device Mapper, shared data disks are not supported.
- If you have installed an NPD add-on in the cluster, upgrade the add-on to v1.18.10 or later. Otherwise, false alarms will be generated.
- If you have installed a log-agent add-on in the cluster, upgrade the add-on to v1.3.0 or later. Otherwise, log collection will be affected.
- If you have installed ICAgent in the cluster, upgrade it to v5.12.140 or later. Otherwise, log collection will be affected.

For nodes using a shared data disk, the container storage Rootfs is of the **OverlayFS** type. After such a node is created, the data disk space (for example, 100 GiB) will not be divided for the container engines, container images, and kubelet components. The data disk is mounted to **/mnt/paas**, and the storage space is divided using two file systems.

- dockersys: /mnt/paas/runtime
- Kubernetes: /mnt/paas/kubernetes/kubelet

Figure 7-4 Allocating the storage space of a shared data disk



7.14 Attaching Disks to a Node

Challenges

In disk planning and striped logical disk creation, it is difficult for users to flexibly attach and partition disks when creating a node.


During node creation, the **storage** field selects a data disk based on parameters, such as the disk size and disk type, to prevent failures in node creation, resetting, migration, and management caused by drive letter matching failures.

Solution

This section provides details about the **storage** field used in node creation so that you can implement complex disk selection and partitioning by calling the node creation API.


The **storage** field consists of **storageSelectors** and **storageGroups**. The **storageSelectors** field is responsible for disk selection, and the **storageGroups** field is responsible for disk processing.

The basic logic for field matching is as follows:



- storageSelectors** selects an EVS disk or a local disk based on the value of **storageType**.
 - Local disks do not support exact match. All local disks will be selected as data disks.
If some local disks need to be reserved, occupy the disks in the pre-installation script. The script is similar to the following:

```
# prepare
vgName=vg-test
storageDevice=/dev/vdb
# vgcreate
vgcreate ${vgName} ${storageDevice}
```
 - EVS disks match the disks created in **dataVolumes** based on the settings of **matchLabels**.
- Policies have priorities to match **matchLabels**. The **matchLabels** policy nearest to **storageSelectors** has a higher priority and the disk nearest to **dataVolumes** will be preferentially matches. As **matchLabels** uses loose matching, you are advised to place the **matchLabels** policy with a small matching range on the top. For example:




- In step 1, the first disk in **dataVolumes** is matched by the EVS disk whose size is 100 GiB and storage class is SAS. In step 2, the second disk in **dataVolumes** is matched by the EVS disk whose size is 100 GiB because the first disk has been selected.
 - In step 3, two disks in **dataVolumes** can be matched because **volumeType** or **count** is not specified in **matchLabels**. In this case, no disk is available for matching in step 4.
3. **storageGroups** associates with **storageSelectors** based on **selectorName**. Finally, two 100 GiB disks are selected. The CCE backend groups the two PVs into a volume group (VG) and divides the VG into two logical volumes (LVs) in the ratio of 9:1. 10% of Kubernetes LVs are partitioned in striped mode. 90% runtime LVs are partitioned in linear mode by default because **runtimeConfig** is not configured.

Creating a Raw Disk

During node creation on the CCE console, click **Add Data Disk**. Then, click **Expand** next to the newly added data disk and select **Default**. The created disk is a raw disk.

The following figure shows the API calling logic.



- The **cceUse** selector matches a 100 GiB data disk.
- The selected disk is managed by CCE and used as a data disk.
- The other 100 GiB data disk created in **dataVolumes** is not selected by any selector and is managed by **storageGroups**. Therefore, this EVS disk will be attached to the node as a raw disk and will not be initialized.

After the node is created, log in to the node and check whether a 100 GiB disk has been attached but not initialized.

```
[root@test-83790 ~]# lsbblk -n
sda
└─sda1
sdb
└─vgpaas-dockersys
└─vgpaas-thinpool_tmeta
└─vgpaas-thinpool
    ├─docker_253:0_786433-7cb37dc21202bfef2cf78dd1d3b70571e7e1982e56a4118f6fcadcc630cbc8b38 253:5 0 10G 0 disk
    ├─docker_253:0_786433-e17cd8670b9ff423eaaff34b92bd82a2e62018b227c26da2e41eda7894361c9942 253:6 0 10G 0 dm [var/lib/docker/devicemapper/m
    ├─docker_253:0_786433-0dedb47e7eed3f635cbe2d47584587ae6270db0eafaeade1e4693a3146a0 253:7 0 10G 0 dm [var/lib/docker/devicemapper/m
    ├─docker_253:0_786433-93ed766e14313d13cef1a152937b153f599c48cfdaf9ecdd43c136cae89a38a 253:8 0 10G 0 dm [var/lib/docker/devicemapper/m
    ├─docker_253:0_786433-e706be08bf5f6249850a9e080c4f3d9a7be499eae33aaeb06c027d26fa1e9 253:9 0 10G 0 dm [var/lib/docker/devicemapper/m
    └─docker_253:0_786433-5ecc4420da958fb66108db599a8267af3e8856da86b9c3d7fb820908a781a8 253:10 0 10G 0 dm [var/lib/docker/devicemapper/m
└─vgpaas-thinpool_tdata
└─vgpaas-thinpool
    ├─docker_253:0_786433-7cb37dc21202bfef2cf78dd1d3b70571e7e1982e56a4118f6fcadcc630cbc8b38 253:5 0 10G 0 disk
    ├─docker_253:0_786433-e17cd8670b9ff423eaaff34b92bd82a2e62018b227c26da2e41eda7894361c9942 253:6 0 10G 0 dm [var/lib/docker/devicemapper/m
    ├─docker_253:0_786433-0dedb47e7eed3f635cbe2d47584587ae6270db0eafaeade1e4693a3146a0 253:7 0 10G 0 dm [var/lib/docker/devicemapper/m
    ├─docker_253:0_786433-93ed766e14313d13cef1a152937b153f599c48cfdaf9ecdd43c136cae89a38a 253:8 0 10G 0 dm [var/lib/docker/devicemapper/m
    ├─docker_253:0_786433-e706be08bf5f6249850a9e080c4f3d9a7be499eae33aaeb06c027d26fa1e9 253:9 0 10G 0 dm [var/lib/docker/devicemapper/m
    └─docker_253:0_786433-5ecc4420da958fb66108db599a8267af3e8856da86b9c3d7fb820908a781a8 253:10 0 10G 0 dm [var/lib/docker/devicemapper/m
└─vgpaas-kubernetes
└─sdc
[root@test-83790 ~]#
```

The following is an API example:

```
{ "kind": "Node", "apiVersion": "v3", "metadata": { "name": "test-83790" }, "spec": { "flavor": "c3.large.2", "az": "eu-west-0a", "os": "EulerOS 2.9", "dataVolumes": [ { "size": 100, "volumetype": "SAS" }, { "size": 100, "volumetype": "SAS" } ], "billingMode": 0, "extendParam": { "maxPods": 110 }, "nodeNicSpec": { "primaryNic": { "subnetId": "ca964acf-8468-4735-8229-97940ef6c881" } }, "rootVolume": { "size": 50, "volumetype": "SAS" }, "runtime": { "name": "docker" }, "login": { "userPassword": { "username": "root", "password": "*****" } }, "storage": { "storageSelectors": [ { "name": "cceUse", "storageType": "evs", "matchLabels": { "size": "100", "volumeType": "SAS" } } ] } }
```

```


        "volumeType": "SAS",
        "count": "1"
    }
},
"storageGroups": [
{
    "name": "vgpaas",
    "selectorNames": [
        "cceUse"
    ],
    "cceManaged": true,
    "virtualSpaces": [
        {
            "name": "runtime",
            "size": "90%"
        },
        {
            "name": "kubernetes",
            "size": "10%"
        }
    ]
},
{
    "count": 1
}
]
}

```

Attaching a Disk to a Specified Path

During node creation on the CCE console, click **Add Data Disk**. Then, click **Expand** next to the newly added data disk, select **Mount Disk**, and set the mount path. In this case, CCE initializes and attaches the disk by default.

The following figure shows the API calling logic.



1. The **user1** selector selects a 100 GiB data disk.
2. Create a VG named **vguser1** using LVM.
3. Strip all the space of **vguser1** into an LV named **user** and format the disk in ext4 format. Finally, attach the disk to the **/tmp2** directory.

After the node is created, log in to the node and check whether a 100 GiB disk has been attached and managed by LVM.

```
[root@test-37106 ~]# lsblk -n
sda
└─sda1
sdb
└─vgpaas-dockersys
└─vgpaas-thinpool_tmeta
  └─vgpaas-thinpool
    ├─docker-253:0-917505-3a36be80c1a49db5da9639d222f19ce5983489080a36gefdda1f17fa2d0bb7da9 253:0   0   50G  0 disk
    ├─docker-253:0-917505-46a876d16929a54d4f5ea97da81c3603c79cd5630be1c1010b476387a5d3c886 253:1   0   10G  0 part /
    ├─docker-253:0-917505-93081c851099968299fda13a@77e82252e725afe37cae7299841db482656b815 253:2   0   10G  0 lvm /var/lib/docker/devicemapper/
    ├─docker-253:0-917505-513c5bda896de61c85d917366da4ea4d78ab9f87cd4caeae9e465badc0003c62 253:3   0   10G  0 lvm /var/lib/docker/devicemapper/
    ├─docker-253:0-917505-a6ac0d3ae8bfbd57a92e6812079e503db49942619d5bbc69hb9516b31e15e67 253:4   0   10G  0 lvm /var/lib/docker/devicemapper/
    └─docker-253:0-917505-f9dfa31cdc3eb514a797c98311372ac8497d9a99581acdfefff0114bdfd8e525 253:5   0   10G  0 lvm /var/lib/docker/devicemapper/
└─vgpaas-thinpool_tdata
  └─vgpaas-thinpool
    ├─docker-253:0-917505-3a36be80c1a49db5da9639d222f19ce5983489080a36gefdda1f17fa2d0bb7da9 253:6   0   10G  0 dm /var/lib/docker/devicemapper/
    ├─docker-253:0-917505-46a876d16929a54d4f5ea97da81c3603c79cd5630be1c1010b476387a5d3c886 253:7   0   10G  0 dm /var/lib/docker/devicemapper/
    ├─docker-253:0-917505-93081c851099968299fda13a@77e82252e725afe37cae7299841db482656b815 253:8   0   10G  0 dm /var/lib/docker/devicemapper/
    ├─docker-253:0-917505-513c5bda896de61c85d917366da4ea4d78ab9f87cd4caeae9e465badc0003c62 253:9   0   10G  0 dm /var/lib/docker/devicemapper/
    ├─docker-253:0-917505-a6ac0d3ae8bfbd57a92e6812079e503db49942619d5bbc69hb9516b31e15e67 253:10  0   10G  0 dm /var/lib/docker/devicemapper/
    └─docker-253:0-917505-f9dfa31cdc3eb514a797c98311372ac8497d9a99581acdfefff0114bdfd8e525 253:11  0   10G  0 dm /var/lib/docker/devicemapper/
└─vgpaas-kubernetes
  └─vguser1-user
[root@test-37106 ~]#
```

The following is an API example. There are two data disks. One is used by CCE, and the other is mounted to the `/tmp2` directory.

```
{
  "kind": "Node",
  "apiVersion": "v3",
  "metadata": {
    "name": "test-37106"
  },
  "spec": {
    "flavor": "c3.large.2",
    "az": "eu-west-0a",
    "os": "EulerOS 2.9",
    "dataVolumes": [
      {
        "size": 100,
        "volumetype": "SAS"
      },
      {
        "size": 100,
        "volumetype": "SAS"
      }
    ],
    "billingMode": 0,
    "extendParam": {
      "maxPods": 110
    },
    "nodeNicSpec": {
      "primaryNic": {
        "subnetId": "ca964acf-8468-4735-8229-97940ef6c881"
      }
    },
    "rootVolume": {
      "size": 50,
      "volumetype": "SAS"
    },
    "runtime": {
      "name": "docker"
    },
    "login": {
      "userPassword": {
        "username": "root",
        "password": "*****"
      }
    },
    "storage": {
      "storageSelectors": [
        {
          "name": "cceUse",

```

```
"storageType": "evs",
"matchLabels": {
  "size": "100",
  "volumeType": "SAS",
  "count": "1"
},
{
  "name": "user1",
  "storageType": "evs",
  "matchLabels": {
    "size": "100",
    "volumeType": "SAS",
    "count": "1"
  }
},
],
"storageGroups": [
  {
    "name": "vgpaas",
    "selectorNames": [
      "cceUse"
    ],
    "cceManaged": true,
    "virtualSpaces": [
      {
        "name": "runtime",
        "size": "80%"
      },
      {
        "name": "kubernetes",
        "size": "20%"
      }
    ]
  },
  {
    "name": "vguser1",
    "selectorNames": [
      "user1"
    ],
    "virtualSpaces": [
      {
        "name": "user",
        "size": "100%",
        "lvmConfig": {
          "lvType": "linear",
          "path": "/tmp2"
        }
      }
    ]
  }
],
"count": 1
}
```

Creating Striped LVs to Improve Disk Performance

Currently, the striped LV function is supported only by calling an API. The following is an example:



1. **storageSelectors** matches all EVS disks in **dataVolumes** because **matchLabels** is not contained in **storageSelectors**.
 2. Create a VG named **vgpaas** using LVM.
 3. Strip 90% of the **vgpaas** space into runtime LVs.
 4. Strip 10% of the **vgpaas** space into Kubernetes LVs.

NOTE

- Two or more data disks are required for striping.
 - When creating a striped LV, ensure that the types and sizes of the PVs added to the VG are the same. Otherwise, the creation will fail.
 - When creating a striped LV, use the striping configuration for both the runtime LV and Kubernetes LV. Otherwise, the creation will fail.

Log in to the node and run the following command to view the striping result:

```
[root@test-83773 ~]# lvdisplay -m | grep -C 10 striped
  LV Size           36.00 GiB
  Current LE        9216
  Segments          1
  Allocation        inherit
  Read ahead sectors auto
  - currently set to   512
  Block device      253:0

  --- Segments ---
  Logical extents 0 to 9215:
    Type            striped
    Stripes         2
    Stripe size     64.00 KiB
    Stripe 0:
      Physical volume  /dev/sdb
      Physical extents 0 to 4607
    Stripe 1:
      Physical volume  /dev/sdc
      Physical extents 0 to 4607

  --
  LV Size           20.00 GiB
  Current LE        5120
  Segments          1
  Allocation        inherit
  Read ahead sectors auto
  - currently set to   8192
  Block device      253:4

  --- Segments ---
  Logical extents 0 to 5119:
    Type            striped
    Stripes         2
    Stripe size     64.00 KiB
    Stripe 0:
      Physical volume  /dev/sdb
```

The following is an API example:

```
{
  "kind": "Node",
  "apiVersion": "v3",
  "metadata": {
    "name": "test-83773"
  },
  "spec": {
    "flavor": "c3.large.2",
    "az": "eu-west-0a",
    "os": "EulerOS 2.9",
    "dataVolumes": [
      {
        "size": 100,
        "volumetype": "SAS"
      },
    ]
  }
}
```

```
{  
    "size": 100,  
    "volumetype": "SAS"  
}  
],  
"billingMode": 0,  
"extendParam": {  
    "maxPods": 110  
},  
"nodeNicSpec": {  
    "primaryNic": {  
        "subnetId": "ca964acf-8468-4735-8229-97940ef6c881"  
    }  
},  
"rootVolume": {  
    "size": 50,  
    "volumetype": "SAS"  
},  
"runtime": {  
    "name": "docker"  
},  
"login": {  
    "userPassword": {  
        "username": "root",  
        "password": "*****"  
    }  
},  
"storage": {  
    "storageSelectors": [  
        {  
            "name": "cceUse",  
            "storageType": "evs"  
        }  
    ],  
    "storageGroups": [  
        {  
            "name": "vgpaas",  
            "selectorNames": [  
                "cceUse"  
            ],  
            "cceManaged": true,  
            "virtualSpaces": [  
                {  
                    "name": "runtime",  
                    "size": "90%",  
                    "runtimeConfig": {  
                        "lvType": "striped"  
                    }  
                },  
                {  
                    "name": "kubernetes",  
                    "size": "10%",  
                    "lvmConfig": {  
                        "lvType": "striped"  
                    }  
                }  
            ]  
        },  
        {"count": 1  
    }  
}
```