Direct Connect

API Reference

Issue 01

Date 2024-07-25





Copyright © Huawei Cloud Computing Technologies Co., Ltd. 2024. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Cloud Computing Technologies Co., Ltd.

Trademarks and Permissions

HUAWEI and other Huawei trademarks are the property of Huawei Technologies Co., Ltd. All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei Cloud and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, quarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Contents

1 Before You Start	1
1.1 Introduction	1
1.2 API Calling	1
1.3 Endpoints	1
1.4 Constraints	1
1.5 Concepts	2
2 API Overview	4
3 Calling APIs	5
3.1 Making an API Request	5
3.2 Authentication	g
3.3 Response	11
4 API Usage	13
5 API	14
5.1 Connection	14
5.1.1 Querying Details About a Connection	14
5.1.2 Updating a Connection	21
5.1.3 Deleting a Connection	29
5.1.4 Querying the Connection List	30
5.1.5 Querying the Hosted Connection List	38
5.1.6 Creating a Hosted Connection	44
5.1.7 Querying Details About a Hosted Connection	50
5.1.8 Updating a Hosted Connection	55
5.1.9 Deleting a Hosted Connection	60
5.2 Virtual Gateway	61
5.2.1 Querying Details About a Virtual Gateway	61
5.2.2 Updating a Virtual Gateway	64
5.2.3 Deleting a Virtual Gateway	68
5.2.4 Querying Virtual Gateways	
5.2.5 Creating a Virtual Gateway	
5.3 Virtual Interface	
5.3.1 Querying Details About a Virtual Interface	
5.3.2 Updating a Virtual Interface	87

5.3.3 Deleting a Virtual Interface	97
5.3.4 Querying the Virtual Interface List	98
5.3.5 Creating a Virtual Interface	108
5.3.6 Updating a Virtual Interface Peer	120
5.3.7 Deleting a Virtual Interface Peer	124
5.3.8 Creating a Virtual Interface Peer	125
5.3.9 Performing a Virtual Interface Switchover Test	131
5.3.10 Querying the Switchover Test Records of a Virtual Interface	134
5.4 Tag management	138
5.4.1 Querying Tags by Resource Type	139
5.4.2 Querying Resource Tags	140
5.4.3 Adding a Resource Tag	143
5.4.4 Adding or Deleting Tags in Batches	145
5.4.5 Deleting a Resource Tag	147
5.4.6 Querying Resources by Tag	149
5.5 Quota Management	156
5.5.1 Querying Resource Quotas	156
6 Public Parameters	159
6.1 Common Status Codes	
6.2 Error Codes	
A Appendixes	166
A.1 Obtaining a Project ID	
B Change History	168

Before You Start

1.1 Introduction

Welcome to Direct Connect API Reference. Direct Connect allows you to connect your on-premises data center to the cloud over a dedicated network connection that features stable performance, high transmission speed, low network latency, and secure data transmission. Direct Connect allows you to maximize legacy IT facilities and leverage cloud services to build a flexible, scalable hybrid cloud computing environment.

This document describes how to use application programming interfaces (APIs) to perform operations on Direct Connect resources, such as creating, querying, modifying, or deleting connections. For details about all supported operations, see API Overview.

Before you access Direct Connect by calling APIs, get yourself familiar with product concepts. For details, see "Service Overview" in *Direct Connect User Guide*.

1.2 API Calling

Direct Connect supports Representational State Transfer (REST) APIs that can be called using HTTPS. For details, see **Calling APIs**.

1.3 Endpoints

An endpoint is the **request address** for calling an API. Endpoints vary depending on services and regions. For Direct Connect endpoints, see **Regions and Endpoints**.

1.4 Constraints

For more constraints, see API descriptions.

1.5 Concepts

Account

An account is created upon successful signing up. The account has full access permissions for all of its cloud services and resources. It can be used to reset user passwords and grant user permissions. The account is a payment entity, which should not be used directly to perform routine management. For security purposes, create Identity and Access Management (IAM) users and grant them permissions for routine management.

User

An IAM user is created by an account in IAM to use cloud services. Each IAM user has its own identity credentials (password and access keys).

API authentication requires information such as the account name, username, and password.

Region

A region is a geographic area in which cloud resources are deployed. Availability zones (AZs) in the same region can communicate with each other over an intranet, while AZs in different regions are isolated from each other. Deploying cloud resources in different regions can better suit certain user requirements or comply with local laws or regulations.

AZ

An AZ comprises of one or more physical data centers equipped with independent ventilation, fire, water, and electricity facilities. Computing, network, storage, and other resources in an AZ are logically divided into multiple clusters. AZs within a region are interconnected using high-speed optical fibers to allow you to build cross-AZ high-availability systems.

Project

A project corresponds to a region. Default projects are defined to group and physically isolate resources (including computing, storage, and network resources) across regions. Users can be granted permissions in a default project to access all resources under their accounts in the region associated with the project. If you need more refined access control, create subprojects under a default project and create resources in subprojects. Then you can assign users the permissions required to access only the resources in the specific subprojects.

Project B_

Region B

Project B

Project A Project B

Figure 1-1 Project isolation model

Project A

Region A

Project A_1

• Enterprise Project

Enterprise projects group and manage resources across regions. Resources in different enterprise projects are logically isolated. An enterprise project can contain resources of multiple regions, and resources can be added to or removed from enterprise projects.

For details about enterprise projects and about how to obtain enterprise project IDs, see *Enterprise Management User Guide*.

2 API Overview

These APIs allow you to use all Direct Connect functions, for example, performing operations on connections, virtual gateways, virtual interfaces, quotas, and tags.

Table 2-1 describes the APIs provided by Direct Connect.

Table 2-1 Direct Connect APIs

Resource	APIs
Connections	APIs for querying connection details, updating a connection, deleting a connection, querying the connection list, querying the hosted connection list, creating a hosted connection, querying hosted connection details, updating hosted connection information, and deleting a hosted connection
Virtual gateways	APIs for querying virtual gateway details, updating a virtual gateway, deleting a virtual gateway, querying the virtual gateway list, and creating a virtual gateway
Virtual interfaces	APIs for querying virtual interface details, updating a virtual interface, deleting a virtual interface, querying the virtual interface list, creating a virtual interface, updating a virtual interface peer, deleting a virtual interface peer, and creating a virtual interface peer
Tags	APIs for querying project tags, querying resource tags, adding a resource tag, batch adding or deleting resource tags, deleting a resource tag, and querying resources by tag
Quotas	API for querying resource quotas

3 Calling APIs

3.1 Making an API Request

This section describes the structure of a REST API request, and uses the IAM API for **obtaining a user token** as an example to demonstrate how to call an API. The obtained token can then be used to authenticate the calling of other APIs.

Request URI

A request URI is in the following format:

{URI-scheme}://{Endpoint}/{resource-path}?{query-string}

Although a request URI is included in the request header, most programming languages or frameworks require the request URI to be transmitted separately.

Table 3-1 URI parameter description


Parameter	Description
URI-scheme	Protocol used to transmit requests. All APIs use HTTPS.
Endpoint	Domain name or IP address of the server bearing the REST service. The endpoint varies between services in different regions. It can be obtained from Regions and Endpoints. For example, the endpoint of IAM in the my-kualalumpur-1 region is iam.my-kualalumpur-1.myhuaweicloud.com.
resource-path	Access path of an API for performing a specified operation. Obtain the path from the URI of an API. For example, the resource-path of the API used to obtain a user token is /v3/auth/tokens.

Parameter	Description
query-string	Query parameter, which is optional. Ensure that a question mark (?) is included before each query parameter that is in the format of <i>Parameter name=Parameter value</i> . For example, ? limit=10 indicates that a maximum of 10 data records will be displayed.

For example, to obtain an IAM token in the AP-Kuala Lumpur-OP6 region, obtain the endpoint of IAM (iam.my-kualalumpur-1.myhuaweicloud.com) for this region and the resource-path (/v3/auth/tokens) in the URI of the API used to obtain a user token. Then, construct the URI as follows:

https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/tokens

Figure 3-1 Example URI



◯ NOTE

To simplify the URI display in this document, each API is provided only with a **resource-path** and a request method. The **URI-scheme** of all APIs is **HTTPS**, and the endpoints of all APIs in the same region are identical.

Request Methods

The HTTP protocol defines the following request methods that can be used to send a request to the server.

Table 3-2 HTTP methods

Method	Description
GET	Requests the server to return specified resources.
PUT	Requests the server to update specified resources.
POST	Requests the server to add resources or perform special operations.
DELETE	Requests the server to delete specified resources, for example, an object.
HEAD	Same as GET except that the server must return only the response header.

Method	Description
PATCH	Requests the server to update partial content of a specified resource.
	If the resource does not exist, a new resource will be created.

For example, in the case of the API used to **obtain a user token**, the request method is **POST**. The request is as follows:

POST https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/tokens

Request Header

You can also add additional header fields to a request, such as the fields required by a specified URI or HTTP method. For example, to request for the authentication information, add **Content-Type**, which specifies the request body type.

Common request header fields are as follows.

Table 3-3 Common request header fields

Parameter	Description	Mandatory	Example Value
Host	Specifies the server domain name and port number of the resources being requested. The value can be obtained from the URL of the service API. The value is in the format of Hostname:Port number. If the port number is not specified, the default port is used. The default port number for https is 443.	No This field is mandatory for AK/SK authentication.	code.test.com or code.test.com:44 3
Content-Type	Specifies the type (or format) of the message body. The default value application/json is recommended. Other values of this field will be provided for specific APIs if any.	Yes	application/json
Content- Length	Specifies the length of the request body. The unit is byte.	No	3495

Parameter	Description	Mandatory	Example Value
X-Project-Id	Specifies the project ID. Obtain the project ID by following the instructions in Obtaining a Project ID.	No	e9993fc787d94b 6c886cbaa340f9c 0f4
X-Auth-Token	Specifies the user token. It is a response to the API for obtaining a user token (This is the only API that does not require authentication). After the request is processed, the value of X-Subject-Token in the response header is the token value.	No This field is mandatory for token authentication.	The following is part of an example token: MIIPAgYJKoZIhvc NAQcCoggg1B BIINPXsidG9rZ

□ NOTE

In addition to supporting authentication using tokens, APIs support authentication using AK/SK, which uses SDKs to sign a request. During the signature, the **Authorization** (signature authentication) and **X-Sdk-Date** (time when a request is sent) headers are automatically added in the request.

For more details, see "Authentication Using AK/SK" in Authentication.

The API used to **obtain a user token** does not require authentication. Therefore, only the **Content-Type** field needs to be added to requests for calling the API. An example of such requests is as follows:

POST https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/tokens Content-Type: application/json

(Optional) Request Body

This part is optional. The body of a request is often sent in a structured format (for example, JSON or XML) as specified in the **Content-Type** header field. The request body transfers content except the request header.

The request body varies between APIs. Some APIs do not require the request body, such as the APIs requested using the GET and DELETE methods.

Ⅲ NOTE

The **scope** parameter specifies where a token takes effect. You can set **scope** to an account or a project under an account. In the following example, the token takes effect only for the resources in a specified project. For more information about this API, see **Obtaining a User Token**.

```
POST https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/tokens
Content-Type: application/json
  "auth": {
     "identity": {
        "methods": [
           "password"
        "password": {
           "user": {
             "name": "username",
             "password": "$ADMIN PASS",
                                             //You are advised to store it in ciphertext in the
configuration file or an environment variable and decrypt it when needed to ensure security.
             "domain": {
                "name": "domainname"
       }
      'scope": {
        "project": {
           "name": "xxxxxxxxxxxxxxxxxx"
     }
  }
```

If all data required for the API request is available, you can send the request to call the API through **curl**, **Postman**, or coding. In the response to the API used to obtain a user token, **X-Subject-Token** is the desired user token. This token can then be used to authenticate the calling of other APIs.

3.2 Authentication

Requests for calling an API can be authenticated using either of the following methods:

- AK/SK authentication: Requests are encrypted using AK/SK pairs. AK/SK authentication is recommended because it is more secure than token authentication.
- Token authentication: Requests are authenticated using tokens.

AK/SK Authentication

◯ NOTE

AK/SK authentication supports API requests with a body not larger than 12 MB. For API requests with a larger body, token authentication is recommended.

In AK/SK authentication, AK/SK is used to sign requests and the signature is then added to the requests for authentication.

 AK: access key ID, which is a unique identifier used in conjunction with a secret access key to sign requests cryptographically. SK: secret access key, which is used in conjunction with an AK to sign requests cryptographically. It identifies a request sender and prevents the request from being modified.

In AK/SK authentication, you can use an AK/SK to sign requests based on the signature algorithm or using the signing SDK. For details about how to sign requests and use the signing SDK, see **API Request Signing Guide**.

□ NOTE

The signing SDK is only used for signing requests and is different from the SDKs provided by services.

Token Authentication

□ NOTE

The validity period of a token is 24 hours. When using a token for authentication, cache it to prevent frequently calling the IAM API used to obtain a user token.

A token specifies temporary permissions in a computer system. During API authentication using a token, the token is added to requests to get permissions for calling the API. You can obtain a token by calling the **Obtaining User Token** API.

IMS is a project-level service. When you call the API, set **auth.scope** in the request body to **project**.

```
"auth": {
     "identity": {
        "methods": [
           "password"
        "password": {
           "user": {
             "name": "username", // IAM user name
             "password": $ADMIN PASS, //IAM user password. You are advised to store it in ciphertext in
the configuration file or an environment variable and decrypt it when needed to ensure security.
                "name": "domainname" // Name of the account to which the IAM user belongs
          }
       }
     "scope": {
        "project": {
           "name": "xxxxxxxx" // Project name
     }
  }
```

After a token is obtained, the **X-Auth-Token** header field must be added to requests to specify the token when calling other APIs. For example, if the token is **ABCDEFJ....**, **X-Auth-Token: ABCDEFJ....** can be added to a request as follows:

```
POST https://iam.my-kualalumpur-1.myhuaweicloud.com/v3/auth/projects
Content-Type: application/json
X-Auth-Token: ABCDEFJ....
```

3.3 Response

Status Code

After sending a request, you will receive a response, including a status code, response header, and response body.

A status code is a group of digits, ranging from 1xx to 5xx. It indicates the status of a request. For more information, see **Common Status Codes**.

For example, if status code **201** is returned for calling the API used to **obtain a user token**, the request is successful.

Response Header

Similar to a request, a response also has a header, for example, **Content-Type**.

Figure 3-2 shows the response header fields for the API used to **obtain a user token**. The **X-Subject-Token** header field is the desired user token. This token can then be used to authenticate the calling of other APIs.

For security purposes, you are advised to set the token in ciphertext in configuration files or environment variables and decrypt it when using it.

Figure 3-2 Header fields of the response to the request for obtaining a user token



(Optional) Response Body

The body of a response is often returned in a structured format (for example, JSON or XML) as specified in the **Content-Type** header field. The response body transfers content except the response header.

The following is part of the response body for the API used to **obtain a user token**.

If an error occurs during API calling, an error code and a message will be displayed. The following shows an error response body.

```
{
    "error_msg": "The request message format is invalid.",
    "error_code": "IMG.0001"
}
```

In the response body, **error_code** is an error code, and **error_msg** provides information about the error.

4 API Usage

Direct Connect has independent endpoints. When API calls are made to Direct Connect, the Direct Connect APIs are used. Therefore, you need pay special attention to the service endpoints used when you make calls to the Direct Connect APIs.

 $\mathbf{5}_{\mathsf{API}}$

5.1 Connection

5.1.1 Querying Details About a Connection

Function

This API is used to query details about a connection.

URI

GET /v3/{project_id}/dcaas/direct-connects/{direct_connect_id}

Table 5-1 Path Parameters

Parameter	Mandatory	Туре	Description
direct_connec t_id	Yes	String	Specifies the connection ID. Minimum: 36 Maximum: 36
project_id	Yes	String	Specifies the project ID.

Table 5-2 Query Parameters

Parameter	Mandatory	Туре	Description
fields	No	Array	Specifies the list of fields to be displayed. Array Length: 1 - 5

Request Parameters

Table 5-3 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Status code: 200

Table 5-4 Response body parameters

Parameter	Туре	Description	
request_id	String	Specifies the request ID.	
direct_connec t	DirectConnec t object	Specifies parameters for creating a connection.	

Table 5-5 DirectConnect

Parameter	Туре	Description	
id	String	Specifies the connection ID.	
tenant_id	String	Specifies the ID of the project that the instance belongs to.	
name	String	Specifies the connection name. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the connection. Minimum: 0 Maximum: 128	

Parameter	Туре	Description	
port_type	String	Specifies the type of the port used by the connection. The value can be 1G , 10G , 40G , or 100G .	
		Enumeration values:	
		• 1G	
		• 10G	
		• 40G	
		• 100G	
bandwidth	Integer	Specifies the connection bandwidth in Mbit/s.	
		Minimum: 2	
		Maximum: 100000	
location	String	Specifies information about the Direct Connect location.	
		Minimum: 0	
		Maximum: 255	
peer_location	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name.	
		Minimum: 0	
		Maximum: 255	
device_id	String	Specifies the ID of the device connected to the connection.	
		Minimum: 0	
		Maximum: 36	
type	String	Specifies the type of a connection. The value can be standard (a standard connection), hosting (an operations connection) or hosted (a hosted connection).	
		Default: standard	
		Enumeration values:	
		• standard	
		• hosting	
		• hosted	
		onestop_standard	
		onestop_hosted	
hosting_id	String	Specifies the ID of the operations connection on which the hosted connection is created.	

Parameter	Туре	Description		
charge_mode	String	Specifies the billing mode, which can be prepayment , bandwidth , or traffic .		
		Enumeration values:		
		• prepayment		
		bandwidth		
		• traffic		
provider	String	Specifies the line carrier of a connection.		
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false .		
		Default: true		
vlan	Integer	Specifies the VLAN allocated to the hosted connection.		
		Minimum: 0		
		Maximum: 3999		

Parameter	Туре	Description
status	String	Specifies the connection status. The options are as follows: ACTIVE: The connection is in the normal state. DOWN: The port for the connection is in the down state, which may cause line faults. BUILD: Operations related to the connection are being performed. ERROR: The connection configuration is incorrect. Contact customer service to rectify the fault. PENDING_DELETE: The connection is being deleted. DELETED: The connection has been deleted. APPLY: A request for a connection is submitted. DENY: A site survey is rejected because the customer fails to meet the requirements. PENDING_PAY: The order for the connection is to be paid. PAID: The order for the connection has been paid. PENDING_SURVEY: A site survey is required for the connection. Enumeration values: BUILD PAID APPLY PENDING_SURVEY ACTIVE DOWN ERROR PENDING_DELETE DELETED DENY PENDING_PAY
apply_time	String	Specifies when the connection was requested. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
create_time	String	Specifies when the connection was created. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
provider_statu s	String	Specifies the status of the carrier's leased line. The status can be ACTIVE or DOWN . Enumeration values: • ACTIVE • DOWN
peer_port_typ e	String	Specifies the peer port type.

Parameter	Туре	Description	
peer_provider	String	Specifies the carrier connected to the connection.	
order_id	String	Specifies the connection order ID, which is used to support duration-based billing and identify user orders.	
product_id	String	Specifies the product ID corresponding to the connection's order, which is used to custom billing policies such as duration-based packages.	
spec_code	String	Specifies the product specifications corresponding to the connection's order, which is used to custom billing policies such as duration-based packages.	
period_type	Integer	Specifies whether a connection in a specified order is billed by year or month.	
period_num	Integer	Specifies the required service duration of a yearly/monthly connection.	
vgw_type	String	Specifies the gateway type required by a direct connection. Default: default Enumeration values: • default	
lag_id	String	Specifies the ID of the LAG that the connection belongs to.	
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the connection belongs to. Minimum: 36 Maximum: 36	
locales	LocalesBody object	Specifies the region of the connection.	
support_featu re	Array of strings	Lists the features supported by the connection.	
ies_id	String	Specifies the ID of an IES edge site.	
reason	String	Displays error information if the status of a line is Error .	
email	String	Specifies the customer email information.	
onestop_prod uct_id	String	Specifies the product ID of a full-service connection. This parameter is used in line sales scenarios.	

Parameter	Туре	Description	
building_line_ product_id	String	Specifies the product ID of the line resource used in the equipment room. This parameter is used in line sales scenarios.	
last_onestop_ product_id	String	Specifies the product ID of a full-service connection before the change. This parameter is used in line sales scenarios and used to save the last record when the line bandwidth is changed.	
last_building_l ine_product_i d	String	Specifies the product ID of the line resource used in the equipment room before the change. This parameter is used in line sales scenarios and used to save the last record when the line bandwidth is changed.	
modified_ban dwidth	Integer	Specifies the new bandwidth after the line bandwidth is changed.	
change_mode	Integer	Specifies the status of a renewal change.	
onestopdc_sta tus	String	Specifies the status of a full-service connection.	
public_border _group	String	Specifies the public border group of the AZ, indicating whether the site is a HomeZones site.	
auto_renew	Integer	Specifies whether to automatically renew a yearly/monthly subscription.	
ratio_95peak	Integer	Specifies the percentage of the minimum bandwidth for 95th percentile billing. Minimum: 0	
		Maximum: 100	

Table 5-6 LocalesBody

Parameter	Туре	Description	
en_us	String	Specifies the region name in English. Minimum: 0 Maximum: 255	
zh_cn	String	Specifies the region name in Chinese. Minimum: 0 Maximum: 255	

Example Requests

Querying details about a connection

 $GET\ https://\{dc_endpoint\}/v3/6fbe9263116a4b68818cf1edce16bc4f/dcaas/direct-connects/6ecd9cf3-ca64-46c7-863f-f2eb1b9e838a$

Example Responses

Status code: 200

OK

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.1.2 Updating a Connection

Function

This API is used to update a connection, including updating its name and description.

URI

PUT /v3/{project_id}/dcaas/direct-connects/{direct_connect_id}

Table 5-7 Path Parameters

Parameter	Mandatory	Туре	Description
direct_connec t_id	Yes	String	Specifies the connection ID. Minimum: 36 Maximum: 36
project_id	Yes	String	Specifies the project ID.

Request Parameters

Table 5-8 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-9 Request body parameters

Parameter	Mandatory	Туре	Description
direct_connec t	No	UpdateDirect Connect object	Specifies parameters required for updating a connection.

Table 5-10 UpdateDirectConnect

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the connection name. Minimum: 0 Maximum: 64
description	No	String	Provides supplementary information about the connection. Minimum: 0 Maximum: 128
bandwidth	No	Integer	Specifies the bandwidth size of the hosted connection in Mbit/s. Minimum: 2 Maximum: 100000

Parameter	Mandatory	Туре	Description
peer_location	No	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name. Minimum: 0 Maximum: 255
status	No	String	Specifies the resource status, which can be PENDING_PAY or APPLY. Enumeration values: PENDING_PAY APPLY
provider_statu s	No	String	Specifies the carrier status, which can be ACTIVE or DOWN. Enumeration values: ACTIVE DOWN

Response Parameters

Status code: 200

Table 5-11 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.
direct_connec t	DirectConnec t object	Specifies parameters for creating a connection.

Table 5-12 DirectConnect

Parameter	Туре	Description	
id	String	Specifies the connection ID.	
tenant_id	String	Specifies the ID of the project that the instance belongs to.	

Parameter	Туре	Description	
name	String	Specifies the connection name. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the connection. Minimum: 0 Maximum: 128	
port_type	String	Specifies the type of the port used by the connection. The value can be 1G, 10G, 40G, or 100G. Enumeration values: 1G 10G 10G 10G	
bandwidth	Integer	Specifies the connection bandwidth in Mbit/s. Minimum: 2 Maximum: 100000	
location	String	Specifies information about the Direct Connect location. Minimum: 0 Maximum: 255	
peer_location	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name. Minimum: 0 Maximum: 255	
device_id	String	Specifies the ID of the device connected to the connection. Minimum: 0 Maximum: 36	

Parameter	Туре	Description	
type	String	Specifies the type of a connection. The value can be standard (a standard connection), hosting (an operations connection) or hosted (a hosted connection).	
		Default: standard	
		Enumeration values:	
		standard	
		• hosting	
		hosted	
		onestop_standard	
		onestop_hosted	
hosting_id	String	Specifies the ID of the operations connection on which the hosted connection is created.	
charge_mode	String	Specifies the billing mode, which can be prepayment, bandwidth, or traffic.	
		Enumeration values:	
		• prepayment	
		bandwidth	
		• traffic	
provider	String	Specifies the line carrier of a connection.	
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true	
vlan	Integer	Specifies the VLAN allocated to the hosted connection. Minimum: 0	
		Maximum: 3999	

Parameter	Туре	Description
status	String	Specifies the connection status. The options are as follows: ACTIVE: The connection is in the normal state. DOWN: The port for the connection is in the down state, which may cause line faults. BUILD: Operations related to the connection are being performed. ERROR: The connection configuration is incorrect. Contact customer service to rectify the fault. PENDING_DELETE: The connection is being deleted. DELETED: The connection has been deleted. APPLY: A request for a connection is submitted. DENY: A site survey is rejected because the customer fails to meet the requirements. PENDING_PAY: The order for the connection is to be paid. PAID: The order for the connection has been paid. PENDING_SURVEY: A site survey is required for the connection. Enumeration values: BUILD PAID APPLY PENDING_SURVEY ACTIVE DOWN ERROR PENDING_DELETE DELETED DENY PENDING_PAY
apply_time	String	Specifies when the connection was requested. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
create_time	String	Specifies when the connection was created. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
provider_statu s	String	Specifies the status of the carrier's leased line. The status can be ACTIVE or DOWN . Enumeration values: • ACTIVE • DOWN
peer_port_typ e	String	Specifies the peer port type.

Parameter	Туре	Description
peer_provider	String	Specifies the carrier connected to the connection.
order_id	String	Specifies the connection order ID, which is used to support duration-based billing and identify user orders.
product_id	String	Specifies the product ID corresponding to the connection's order, which is used to custom billing policies such as duration-based packages.
spec_code	String	Specifies the product specifications corresponding to the connection's order, which is used to custom billing policies such as duration-based packages.
period_type	Integer	Specifies whether a connection in a specified order is billed by year or month.
period_num	Integer	Specifies the required service duration of a yearly/monthly connection.
vgw_type	String	Specifies the gateway type required by a direct connection. Default: default Enumeration values: • default
lag_id	String	Specifies the ID of the LAG that the connection belongs to.
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the connection belongs to. Minimum: 36 Maximum: 36
locales	LocalesBody object	Specifies the region of the connection.
support_featu re	Array of strings	Lists the features supported by the connection.
ies_id	String	Specifies the ID of an IES edge site.
reason	String	Displays error information if the status of a line is Error .
email	String	Specifies the customer email information.
onestop_prod uct_id	String	Specifies the product ID of a full-service connection. This parameter is used in line sales scenarios.

Parameter	Туре	Description
building_line_ product_id	String	Specifies the product ID of the line resource used in the equipment room. This parameter is used in line sales scenarios.
last_onestop_ product_id	String	Specifies the product ID of a full-service connection before the change. This parameter is used in line sales scenarios and used to save the last record when the line bandwidth is changed.
last_building_l ine_product_i d	String	Specifies the product ID of the line resource used in the equipment room before the change. This parameter is used in line sales scenarios and used to save the last record when the line bandwidth is changed.
modified_ban dwidth	Integer	Specifies the new bandwidth after the line bandwidth is changed.
change_mode	Integer	Specifies the status of a renewal change.
onestopdc_sta tus	String	Specifies the status of a full-service connection.
public_border _group	String	Specifies the public border group of the AZ, indicating whether the site is a HomeZones site.
auto_renew	Integer	Specifies whether to automatically renew a yearly/monthly subscription.
ratio_95peak	Integer	Specifies the percentage of the minimum bandwidth for 95th percentile billing. Minimum: 0
		Maximum: 100

Table 5-13 LocalesBody

Parameter	Туре	Description
en_us	String	Specifies the region name in English. Minimum: 0 Maximum: 255
zh_cn	String	Specifies the region name in Chinese. Minimum: 0 Maximum: 255

Example Requests

Updating the name and description of a connection

```
PUT https://{dc_endpoint}/v3/6fbe9263116a4b68818cf1edce16bc4f/dcaas/direct-connects/6ecd9cf3-ca64-46c7-863f-f2eb1b9e838a

{
    "direct_connect" : {
        "description" : "",
        "name" : "direct connect1"
     }
}
```

Example Responses

Status code: 200

OK

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.1.3 Deleting a Connection

Function

This API is used to delete pay-per-use connections only. To delete yearly/monthly connections, you need to first unsubscribe them.

URI

DELETE /v3/{project_id}/dcaas/direct-connects/{direct_connect_id}

Table 5-14 Path Parameters

Parameter	Mandatory	Туре	Description
direct_connec t_id	Yes	String	Specifies the connection ID. Minimum: 36 Maximum: 36
project_id	Yes	String	Specifies the project ID.

Request Parameters

Table 5-15 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

None

Example Requests

Deleting a connection

 $DELETE\ https://\{dc_endpoint\}/v3/6fbe9263116a4b68818cf1edce16bc4f/dcaas/direct-connects/6ecd9cf3-ca64-46c7-863f-f2eb1b9e838a$

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See **Error Codes**.

5.1.4 Querying the Connection List

Function

This API is used to query all direct connections created by a tenant.

URI

GET /v3/{project_id}/dcaas/direct-connects

Table 5-16 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Table 5-17 Query Parameters

Parameter	Mandatory	Туре	Description
limit	No	Integer	Specifies the number of records returned on each page. Value range: 1 to 2000 Minimum: 1 Maximum: 2000 Default: 2000
marker	No	String	Specifies the ID of the last resource record on the previous page. If this parameter is left blank, the first page is queried. This parameter must be used together with limit. Minimum: 0 Maximum: 36
fields	No	Array	Specifies the list of fields to be displayed. Array Length: 1 - 5
sort_key	No	String	Specifies the sorting field. Default: id Minimum: 0 Maximum: 36
sort_dir	No	Array	Specifies the sorting order of returned results, which can be asc (ascending order) or desc (descending order). The default value is asc.
hosting_id	No	Array	Specifies operations connection ID by which hosted connections are filtered. Array Length: 0 - 5

Parameter	Mandatory	Туре	Description
enterprise_pro ject_id	No	Array	Filters resource instances by enterprise project ID. Array Length: 1 - 10
id	No	Array	Specifies the resource ID by which instances are filtered. Array Length: 1 - 5
name	No	Array	Specifies the resource name by which instances are filtered. You can specify multiple names. Array Length: 1 - 5

Request Parameters

Table 5-18 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Status code: 200

Table 5-19 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.
direct_connec ts	Array of DirectConnec t objects	Specifies parameters for creating a connection.

Parameter	Туре	Description	
page_info	PageInfo object	Specifies the pagination query information.	

Table 5-20 DirectConnect

Parameter	Туре	Description	
id	String	Specifies the connection ID.	
tenant_id	String	Specifies the ID of the project that the instance belongs to.	
name	String	Specifies the connection name. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the connection. Minimum: 0 Maximum: 128	
port_type	String	Specifies the type of the port used by the connection. The value can be 1G, 10G, 40G, or 100G. Enumeration values: 1G 10G 10G 10G	
bandwidth	Integer	Specifies the connection bandwidth in Mbit/s. Minimum: 2 Maximum: 100000	
location	String	Specifies information about the Direct Connect location. Minimum: 0 Maximum: 255	
peer_location	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name. Minimum: 0 Maximum: 255	

Parameter	Туре	Description	
device_id	String	Specifies the ID of the device connected to the connection. Minimum: 0 Maximum: 36	
type	String	Specifies the type of a connection. The value can be standard (a standard connection), hosting (an operations connection) or hosted (a hosted connection). Default: standard Enumeration values: • standard • hosting • hosted • onestop_standard • onestop_hosted	
hosting_id	String	Specifies the ID of the operations connection on which the hosted connection is created.	
charge_mode	String	Specifies the billing mode, which can be prepayment, bandwidth, or traffic. Enumeration values: • prepayment • bandwidth • traffic	
provider	String	Specifies the line carrier of a connection.	
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true	
vlan	Integer	Specifies the VLAN allocated to the hosted connection. Minimum: 0 Maximum: 3999	

Parameter	Туре	Description
status	String	Specifies the connection status. The options are as follows: ACTIVE: The connection is in the normal state. DOWN: The port for the connection is in the down state, which may cause line faults. BUILD: Operations related to the connection are being performed. ERROR: The connection configuration is incorrect. Contact customer service to rectify the fault. PENDING_DELETE: The connection is being deleted. DELETED: The connection has been deleted. APPLY: A request for a connection is submitted. DENY: A site survey is rejected because the customer fails to meet the requirements. PENDING_PAY: The order for the connection is to be paid. PAID: The order for the connection has been paid. PENDING_SURVEY: A site survey is required for the connection. Enumeration values: BUILD PAID APPLY PENDING_SURVEY ACTIVE DOWN ERROR PENDING_DELETE DELETED DENY PENDING_PAY
apply_time	String	Specifies when the connection was requested. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
create_time	String	Specifies when the connection was created. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
provider_statu s	String	Specifies the status of the carrier's leased line. The status can be ACTIVE or DOWN . Enumeration values: • ACTIVE • DOWN
peer_port_typ e	String	Specifies the peer port type.

Parameter	Туре	Description	
peer_provider	String	Specifies the carrier connected to the connection.	
order_id	String	Specifies the connection order ID, which is used to support duration-based billing and identify user orders.	
product_id	String	Specifies the product ID corresponding to the connection's order, which is used to custom billing policies such as duration-based packages.	
spec_code	String	Specifies the product specifications corresponding to the connection's order, which is used to custom billing policies such as duration-based packages.	
period_type	Integer	Specifies whether a connection in a specified order is billed by year or month.	
period_num	Integer	Specifies the required service duration of a yearly/monthly connection.	
vgw_type	String	Specifies the gateway type required by a direct connection. Default: default Enumeration values: • default	
lag_id	String	Specifies the ID of the LAG that the connection belongs to.	
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the connection belongs to. Minimum: 36 Maximum: 36	
locales	LocalesBody object	Specifies the region of the connection.	
support_featu re	Array of strings	Lists the features supported by the connection.	
ies_id	String	Specifies the ID of an IES edge site.	
reason	String	Displays error information if the status of a line is Error .	
email	String	Specifies the customer email information.	
onestop_prod uct_id	String	Specifies the product ID of a full-service connection. This parameter is used in line sales scenarios.	

Parameter	Туре	Description	
building_line_ product_id	String	Specifies the product ID of the line resource used in the equipment room. This parameter is used in line sales scenarios.	
last_onestop_ product_id	String	Specifies the product ID of a full-service connection before the change. This parameter is used in line sales scenarios and used to save the last record when the line bandwidth is changed.	
last_building_l ine_product_i d	String	Specifies the product ID of the line resource used in the equipment room before the change. This parameter is used in line sales scenarios and used to save the last record when the line bandwidth is changed.	
modified_ban dwidth	Integer	Specifies the new bandwidth after the line bandwidth is changed.	
change_mode	Integer	Specifies the status of a renewal change.	
onestopdc_sta tus	String	Specifies the status of a full-service connection.	
public_border _group	String	Specifies the public border group of the AZ, indicating whether the site is a HomeZones site.	
auto_renew	Integer	Specifies whether to automatically renew a yearly/monthly subscription.	
ratio_95peak	Integer	Specifies the percentage of the minimum bandwidth for 95th percentile billing. Minimum: 0	
		Maximum: 100	

Table 5-21 LocalesBody

Parameter	Туре	Description	
en_us	String	Specifies the region name in English. Minimum: 0	
		Maximum: 255	
zh_cn	String	Specifies the region name in Chinese. Minimum: 0	
		Maximum: 255	

Table 5-22 PageInfo

Parameter	Туре	Description	
previous_mar ker	String	Specifies the marker of the previous page. The value is the resource UUID.	
		Minimum: 0	
		Maximum: 36	
current_count	Integer	Specifies the number of resources in the current list.	
		Minimum: 0	
		Maximum: 2000	
next_marker	String	Specifies the marker of the next page. The value is the resource UUID. If the value is empty, the resource is on the last page.	
		Minimum: 0	
		Maximum: 36	

Querying the connection list

GET https://{dc_endpoint}/v3/6fbe9263116a4b68818cf1edce16bc4f/dcaas/direct-connects

Example Responses

Status code: 200

OK

Status Codes

Status Code	Description
200	ОК

Error Codes

See **Error Codes**.

5.1.5 Querying the Hosted Connection List

Function

This API is used to query hosted connections created by partners.

URI

GET /v3/{project_id}/dcaas/hosted-connects

Table 5-23 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Table 5-24 Query Parameters

Parameter	Mandatory	Туре	Description
limit	No	Integer	Specifies the number of records returned on each page. Value range: 1 to 2000 Minimum: 1 Maximum: 2000 Default: 2000
marker	No	String	Specifies the ID of the last resource record on the previous page. If this parameter is left blank, the first page is queried. This parameter must be used together with limit. Minimum: 0 Maximum: 36
fields	No	Array	Specifies the list of fields to be displayed. Array Length: 1 - 5
sort_dir	No	Array	Specifies the sorting order of returned results, which can be asc (ascending order) or desc (descending order). The default value is asc.
sort_key	No	String	Specifies the sorting field. Default: id Minimum: 0 Maximum: 36
hosting_id	No	Array	Specifies operations connection ID by which hosted connections are filtered. Array Length: 0 - 5

Parameter	Mandatory	Туре	Description
id	No	Array	Specifies the resource ID by which instances are filtered. Array Length: 1 - 5
name	No	Array	Specifies the resource name by which instances are filtered. You can specify multiple names. Array Length: 1 - 5

Table 5-25 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Table 5-26 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID of the current operation.
hosted_conne cts	Array of HostedDirect Connect objects	Specifies the parameters for creating a hosted connection.
page_info	PageInfo object	Specifies the pagination query information.

Table 5-27 HostedDirectConnect

Parameter	Туре	Description	
id	String	Specifies the hosted connection ID. Minimum: 36 Maximum: 36	
tenant_id	String	Specifies the ID of the project that the instance belongs to.	
name	String	Specifies the connection name. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the connection. Minimum: 0 Maximum: 128	
bandwidth	Integer	Specifies the connection bandwidth in Mbit/s. Minimum: 2 Maximum: 400000	
location	String	Specifies information about the Direct Connect location. Minimum: 0 Maximum: 255	
peer_location	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name. Minimum: 0 Maximum: 255	
hosting_id	String	Specifies the ID of the operations connection on which the hosted connection is created.	
provider	String	Specifies the provider of the leased line.	
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true	
vlan	Integer	Specifies the VLAN allocated to the hosted connection. Minimum: 0 Maximum: 3999	

Parameter	Туре	Description
status	String	Specifies the operating status of the hosted connection. The options are as follows: BUILD: The hosted connection has been created. ACTIVE: The associated virtual gateway is normal. DOWN: The port used by the hosted connection is down, indicating that there may be line faults. ERROR: The associated virtual gateway is abnormal. PENDING_DELETE: The hosted connection is being deleted. PENDING_UPDATE: The hosted connection is being updated. PENDING_CREATE: The hosted connection is being created. Enumeration values: BUILD ACTIVE DOWN ERROR PENDING_DELETE PENDING_DELETE PENDING_UPDATE
apply_time	String	Specifies when the connection was requested. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
create_time	String	Specifies when the connection was created. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
provider_statu s	String	Specifies the status of the carrier's leased line. The status can be ACTIVE or DOWN . Enumeration values: • ACTIVE • DOWN

Parameter	Туре	Description	
port_type	String	Specifies the type of the port used by the connection. The value can be 1G , 10G , 40G , or 100G .	
		Enumeration values:	
		• 1G	
		• 10G	
		• 40G	
		• 100G	
type	String	Specifies the type of a connection. The value can be standard (a standard connection), hosting (an operations connection) or hosted (a hosted connection). Default: standard	
		Enumeration values:	
		• standard	
		hosting	
		• hosted	
		onestop_standard	
		onestop_hosted	

Table 5-28 PageInfo

Parameter	Туре	Description	
previous_mar ker	String	Specifies the marker of the previous page. The value is the resource UUID.	
		Minimum: 0	
		Maximum: 36	
current_count	Integer	Specifies the number of resources in the current list.	
		Minimum: 0	
		Maximum: 2000	
next_marker	String	Specifies the marker of the next page. The value is the resource UUID. If the value is empty, the resource is on the last page.	
		Minimum: 0	
		Maximum: 36	

Querying the list of hosted connections created by a partner

POST https://{dc_endpoint}/v3/6fbe9263116a4b68818cf1edce16bc4f/dcaas/hosted-connects

Example Responses

Status code: 200

OK

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.1.6 Creating a Hosted Connection

Function

This API is used by partners to create hosted connections for their users. The creator must have the partner qualification and have an operations connection.

URI

POST /v3/{project_id}/dcaas/hosted-connects

Table 5-29 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Table 5-30 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-31 Request body parameters

Parameter	Mandatory	Туре	Description
hosted_conne ct	Yes	CreateHosted DirectConnec t object	Specifies the parameters for creating a hosted connection.

Table 5-32 CreateHostedDirectConnect

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the hosted connection name. Minimum: 0 Maximum: 64
description	No	String	Provides supplementary information about the hosted connection. Minimum: 0 Maximum: 128
bandwidth	Yes	Integer	Specifies the bandwidth size of the hosted connection in Mbit/s. Minimum: 2 Maximum: 400000

Parameter	Mandatory	Туре	Description
hosting_id	Yes	String	Specifies the ID of the operations connection on which the hosted connection is created.
vlan	Yes	Integer	Specifies the VLAN allocated to the hosted connection. Minimum: 0 Maximum: 3999
resource_tena nt_id	Yes	String	Specifies the project ID of the specified tenant for whom a hosted connection is to be created. Minimum: 0 Maximum: 32
peer_location	No	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name. Minimum: 0 Maximum: 255

Response Parameters

Table 5-33 Response body parameters

Parameter	Туре	Type Description	
request_id	String	Specifies the request ID.	
hosted_conne ct	HostedDirect Connect object	Specifies the parameters for creating a hosted connection.	

Table 5-34 HostedDirectConnect

Parameter	Туре	Description	
id	String	Specifies the hosted connection ID.	
		Minimum: 36	
		Maximum: 36	

Parameter	Туре	Description	
tenant_id	String	Specifies the ID of the project that the instance belongs to.	
name	String	Specifies the connection name. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the connection. Minimum: 0 Maximum: 128	
bandwidth	Integer	Specifies the connection bandwidth in Mbit/s. Minimum: 2 Maximum: 400000	
location	String	Specifies information about the Direct Connect location. Minimum: 0 Maximum: 255	
peer_location	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name. Minimum: 0 Maximum: 255	
hosting_id	String	Specifies the ID of the operations connection on which the hosted connection is created.	
provider	String	Specifies the provider of the leased line.	
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true	
vlan	Integer	Specifies the VLAN allocated to the hosted connection. Minimum: 0 Maximum: 3999	

Parameter	Туре	Description
status	String	Specifies the operating status of the hosted connection. The options are as follows:
		BUILD: The hosted connection has been created.
		ACTIVE: The associated virtual gateway is normal.
		DOWN: The port used by the hosted connection is down, indicating that there may be line faults.
		ERROR: The associated virtual gateway is abnormal.
		PENDING_DELETE: The hosted connection is being deleted.
		PENDING_UPDATE: The hosted connection is being updated.
		PENDING_CREATE: The hosted connection is being created.
		Enumeration values:
		BUILD
		• ACTIVE
		• DOWN
		• ERROR
		PENDING_DELETE PENDING_UDDATE
		PENDING_UPDATEPENDING_CREATE
apply_time	String	Specifies when the connection was requested. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
create_time	String	Specifies when the connection was created. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
provider_statu s	String	Specifies the status of the carrier's leased line. The status can be ACTIVE or DOWN .
		Enumeration values:
		ACTIVE
		DOWN

Parameter	Туре	Description	
port_type	String	Specifies the type of the port used by the connection. The value can be 1G , 10G , 40G , or 100G .	
		Enumeration values:	
		• 1G	
		• 10G	
		• 40G	
		• 100G	
type	String	Specifies the type of a connection. The value can be standard (a standard connection), hosting (an operations connection) or hosted (a hosted connection).	
		Default: standard	
		Enumeration values:	
		• standard	
		hosting	
		• hosted	
		onestop_standard	
		onestop_hosted	

Creating a hosting connection with the bandwidth set to 10 Mbit/s and VLAN to 441

```
POST https://{dc_endpoint}/v3/6fbe9263116a4b68818cf1edce16bc4f/dcaas/hosted-connects

{
    "hosted_connect" : {
        "name" : "client-dc-faf1",
        "description" : "Hosted Connect",
        "resource_tenant_id" : "0605768a3300d5762f82c01180692873",
        "hosting_id" : "2cfb53be-b05f-40d5-a2f8-3a59ac383836",
        "vlan" : 441,
        "bandwidth" : 10
    }
}
```

Example Responses

Status code: 201

Created

Status Codes

Status Code	Description
201	Created

Error Codes

See Error Codes.

5.1.7 Querying Details About a Hosted Connection

Function

This API is used to query a hosted connection of a partner.

URI

GET /v3/{project_id}/dcaas/hosted-connects/{hosted_connect_id}

Table 5-35 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
hosted_conne ct_id	Yes	String	Specifies the hosted connection ID. Minimum: 36 Maximum: 36

Table 5-36 Query Parameters

Parameter	Mandatory	Туре	Description
limit	No	Integer	Specifies the number of records returned on each page. Value range: 1 to 2000 Minimum: 1 Maximum: 2000 Default: 2000

Parameter	Mandatory	Туре	Description
marker	No	String	Specifies the ID of the last resource record on the previous page. If this parameter is left blank, the first page is queried. This parameter must be used together with limit. Minimum: 0 Maximum: 36
fields	No	Array	Specifies the list of fields to be displayed. Array Length: 1 - 5
sort_dir	No	Array	Specifies the sorting order of returned results, which can be asc (ascending order) or desc (descending order). The default value is asc.
sort_key	No	String	Specifies the sorting field. Default: id Minimum: 0 Maximum: 36
hosting_id	No	Array	Specifies operations connection ID by which hosted connections are filtered. Array Length: 0 - 5

Table 5-37 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Table 5-38 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.
hosted_conne ct	HostedDirect Connect object	Specifies the parameters for creating a hosted connection.

Table 5-39 HostedDirectConnect

Parameter	Туре	Description
id	String	Specifies the hosted connection ID.
		Minimum: 36
		Maximum: 36
tenant_id	String	Specifies the ID of the project that the instance belongs to.
name	String	Specifies the connection name.
		Minimum: 0
		Maximum: 64
description	String	Provides supplementary information about the connection.
		Minimum: 0
		Maximum: 128
bandwidth	Integer	Specifies the connection bandwidth in Mbit/s.
		Minimum: 2
		Maximum: 400000
location	String	Specifies information about the Direct Connect location.
		Minimum: 0
		Maximum: 255
peer_location	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name.
		Minimum: 0
		Maximum: 255

Parameter	Туре	Description
hosting_id	String	Specifies the ID of the operations connection on which the hosted connection is created.
provider	String	Specifies the provider of the leased line.
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true
vlan	Integer	Specifies the VLAN allocated to the hosted connection. Minimum: 0 Maximum: 3999
status	String	Specifies the operating status of the hosted connection. The options are as follows: BUILD: The hosted connection has been created. ACTIVE: The associated virtual gateway is normal. DOWN: The port used by the hosted connection is down, indicating that there may be line faults. ERROR: The associated virtual gateway is abnormal. PENDING_DELETE: The hosted connection is being deleted. PENDING_UPDATE: The hosted connection is being updated. PENDING_CREATE: The hosted connection is being created. Enumeration values: BUILD ACTIVE DOWN ERROR PENDING_DELETE PENDING_DELETE
apply_time	String	• PENDING_CREATE Specifies when the connection was requested. The UTC time format yyyy-MM-
create_time	String	ddTHH:mm:ss.SSSZ is used. Specifies when the connection was created. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.

Parameter	Туре	Description
provider_statu s	String	Specifies the status of the carrier's leased line. The status can be ACTIVE or DOWN .
		Enumeration values:
		ACTIVE
		DOWN
port_type	String	Specifies the type of the port used by the connection. The value can be 1G , 10G , 40G , or 100G .
		Enumeration values:
		• 1G
		• 10G
		• 40G
		• 100G
type	String	Specifies the type of a connection. The value can be standard (a standard connection), hosting (an operations connection) or hosted (a hosted connection).
		Default: standard
		Enumeration values:
		standard
		hosting
		• hosted
		onestop_standard
		onestop_hosted

Querying details about a hosted connection created by a partner

 $GET\ https://\{dc_endpoint\}/v3/6fbe9263116a4b68818cf1edce16bc4f/dcaas/hosted-connects/0278b472-ffa5-4eb3-8c0d-979d479f8ef6$

Example Responses

Status code: 200

OK

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.1.8 Updating a Hosted Connection

Function

Updating a hosted connection by a partner

URI

PUT /v3/{project_id}/dcaas/hosted-connects/{hosted_connect_id}

Table 5-40 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
hosted_conne ct_id	Yes	String	Specifies the hosted connection ID. Minimum: 36 Maximum: 36

Request Parameters

Table 5-41 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-42 Request body parameters

Parameter	Mandatory	Туре	Description
hosted_conne ct	No		Specifies parameters required for updating a hosted connection.

Table 5-43 UpdateHostedDirectConnect

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the connection name. Minimum: 0 Maximum: 64
description	No	String	Provides supplementary information about the connection. Minimum: 0 Maximum: 128
bandwidth	No	Integer	Specifies the bandwidth size of the hosted connection in Mbit/s. Minimum: 2 Maximum: 400000
peer_location	No	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name. Minimum: 0 Maximum: 255

Response Parameters

Table 5-44 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.

Parameter	Туре	Description
hosted_conne ct	HostedDirect Connect object	Specifies the parameters for creating a hosted connection.

Table 5-45 HostedDirectConnect

Parameter	Туре	Description	
id	String	Specifies the hosted connection ID. Minimum: 36 Maximum: 36	
tenant_id	String	Specifies the ID of the project that the instance belongs to.	
name	String	Specifies the connection name. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the connection. Minimum: 0 Maximum: 128	
bandwidth	Integer	Specifies the connection bandwidth in Mbit/s. Minimum: 2 Maximum: 400000	
location	String	Specifies information about the Direct Connect location. Minimum: 0 Maximum: 255	
peer_location	String	Specifies the location of the on-premises facility at the other end of the connection, specific to the street or data center name. Minimum: 0 Maximum: 255	
hosting_id	String	Specifies the ID of the operations connection on which the hosted connection is created.	
provider	String	Specifies the provider of the leased line.	
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true	

Parameter	Туре	Description
vlan	Integer	Specifies the VLAN allocated to the hosted connection. Minimum: 0 Maximum: 3999
status	String	 Specifies the operating status of the hosted connection. The options are as follows: BUILD: The hosted connection has been created. ACTIVE: The associated virtual gateway is normal. DOWN: The port used by the hosted connection is down, indicating that there may be line faults. ERROR: The associated virtual gateway is abnormal. PENDING_DELETE: The hosted connection is being deleted. PENDING_UPDATE: The hosted connection is being updated. PENDING_CREATE: The hosted connection is being created. Enumeration values: BUILD ACTIVE DOWN ERROR PENDING_DELETE PENDING_UPDATE PENDING_UPDATE PENDING_UPDATE PENDING_UPDATE PENDING_CREATE
apply_time	String	Specifies when the connection was requested. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
create_time	String	Specifies when the connection was created. The UTC time format yyyy-MM- ddTHH:mm:ss.SSSZ is used.
provider_statu s	String	Specifies the status of the carrier's leased line. The status can be ACTIVE or DOWN . Enumeration values: • ACTIVE • DOWN

Parameter	Туре	Description	
port_type	String	Specifies the type of the port used by the connection. The value can be 1G , 10G , 40G , or 100G .	
		Enumeration values:	
		• 1G	
		• 10G	
		• 40G	
		• 100G	
type	String	Specifies the type of a connection. The value can be standard (a standard connection), hosting (an operations connection) or hosted (a hosted connection).	
		Default: standard	
		Enumeration values:	
		• standard	
		hosting	
		• hosted	
		onestop_standard	
		onestop_hosted	

Updating the name and description of a hosted connection

```
PUT https://{dc_endpoint}/v3/6fbe9263116a4b68818cf1edce16bc4f/dcaas/hosted-connects/0278b472-ffa5-4eb3-8c0d-979d479f8ef6

{
    "hosted_connect" : {
        "name" : "client-dc-faf1",
        "description" : ""
     }
}
```

Example Responses

Status code: 200

OK

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.1.9 Deleting a Hosted Connection

Function

This API is used by partners to delete hosted connections.

URI

DELETE /v3/{project_id}/dcaas/hosted-connects/{hosted_connect_id}

Table 5-46 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
hosted_conne ct_id	Yes	String	Specifies the hosted connection ID. Minimum: 36 Maximum: 36

Request Parameters

Table 5-47 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

None

Example Requests

Deleting a hosted connection

 $\label{lem:decomposition} DELETE\ https://{dc_endpoint}/v3/08d5a9564a704afda6039ae2babbef3c/dcaas/hosted-connects/94c2b814-99dc-939a-e811-ae84c61ea3ff}$

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See Error Codes.

5.2 Virtual Gateway

5.2.1 Querying Details About a Virtual Gateway

Function

This API is used to query details about a specified virtual gateway.

URI

GET /v3/{project_id}/dcaas/virtual-gateways/{virtual_gateway_id}

Table 5-48 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
virtual_gatew ay_id	Yes	String	Specifies the virtual gateway ID.

Table 5-49 Query Parameters

Parameter	Mandatory	Туре	Description
fields	No	Array	Specifies the list of fields to be displayed.
			Array Length: 1 - 5

Table 5-50 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Table 5-51 Response body parameters

Parameter	Туре	Description
virtual_gatew ay	VirtualGatew ay object	Specifies parameters for creating a virtual gateway.
request_id	String	Specifies the request ID.

Table 5-52 VirtualGateway

Parameter	Туре	Description
id	String	Specifies the virtual gateway ID.
vpc_id	String	Specifies the ID of the VPC connected by the virtual gateway.
tenant_id	String	Specifies the ID of the project that the instance belongs to. Minimum: 32
		Maximum: 32
name	String	Specifies the virtual gateway name. Minimum: 0 Maximum: 64

Parameter	Туре	Description
description	String	Provides supplementary information about the virtual gateway. Minimum: 0 Maximum: 128
type	String	Specifies the virtual gateway type. The value can only be default . Default: default
local_ep_grou p	Array of strings	Specifies the IPv4 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC.
local_ep_grou p_ipv6	Array of strings	Specifies the IPv6 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC. This is a reserved field.
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true
status	String	Specifies the virtual gateway status, which can be ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING_UPDATE, or PENDING_DELETE.
bgp_asn	Integer	Specifies the local BGP ASN of the virtual gateway. Minimum: 1 Maximum: 4294967295
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the virtual gateway belongs to. Minimum: 36 Maximum: 36
device_id	String	Specifies the ID of the device that the virtual interface belongs to.
redundant_de vice_id	String	Specifies the ID of the redundant device.
public_border _group	String	Specifies the public border group of the AZ, indicating whether the site is a HomeZones site.

Querying a virtual gateway

 $\label{eq:GET https://dc_endpoint} $$ GET https://dc_endpoint}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-gateways/20082c1b-3c99-48d8-8e8c-116af5d7e9f0$

Example Responses

Status code: 200

OK

• The details of the virtual gateway associated with a VPC are gueried.

```
"virtual_gateway" : {
 "id" : "20082c1b-3c99-48d8-8e8c-116af5d7e9f0",
 "name": "vgw-c7b22",
 "description": ""
 "tenant_id": "0605768a3300d5762f82c01180692873",
 "vpc_id": "6592c28e-95d7-4b0a-9f61-004fdf03420c",
 "device_id" : "26.151.63.100",
 "redundant_device_id": "26.152.128.20",
 "type" : "default",
 "status" : "ACTIVE",
 "admin_state_up" : true,
 "bgp_asn" : 64512,
 "local_ep_group" : [ "192.168.1.0/24" ],
 "enterprise_project_id": "0",
 "public_border_group" : "center"
"request_id": "765f7aaf8f2edd0e719de564ef72e2de"
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.2.2 Updating a Virtual Gateway

Function

This API is used to update a virtual gateway.

URI

PUT /v3/{project_id}/dcaas/virtual-gateways/{virtual_gateway_id}

Table 5-53 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Parameter	Mandatory	Туре	Description
virtual_gatew ay_id	Yes	String	Specifies the virtual gateway ID.

Table 5-54 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-55 Request body parameters

Parameter	Mandatory	Туре	Description
virtual_gatew ay	No	UpdateVirtua lGateway object	Specifies the virtual gateway to be updated.

Table 5-56 UpdateVirtualGateway

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the virtual gateway name.
			Minimum: 0
			Maximum: 64
description	No	String	Provides supplementary information about the virtual gateway. Minimum: 0 Maximum: 128

Parameter	Mandatory	Туре	Description
local_ep_grou p	No	Array of strings	Lists the IPv4 subnets that can be accessed over the virtual gateway. Generally, the list contains the subnet CIDR blocks of the associated VPC. Array Length: 1 - 200
local_ep_grou p_ipv6	No	Array of strings	Lists the IPv6 subnets that can be accessed using the virtual gateway. Usually, the subnets are those in the VPC associated with the virtual gateway. Array Length: 1 - 50

Response Parameters

Table 5-57 Response body parameters

Parameter	Туре	Description
virtual_gatew ay	VirtualGatew ay object	Specifies parameters for creating a virtual gateway.
request_id	String	Specifies the request ID.

Table 5-58 VirtualGateway

Parameter	Туре	Description
id	String	Specifies the virtual gateway ID.
vpc_id	String	Specifies the ID of the VPC connected by the virtual gateway.
tenant_id	String	Specifies the ID of the project that the instance belongs to. Minimum: 32 Maximum: 32
name	String	Specifies the virtual gateway name. Minimum: 0 Maximum: 64

Parameter	Туре	Description
description	String	Provides supplementary information about the virtual gateway. Minimum: 0 Maximum: 128
type	String	Specifies the virtual gateway type. The value can only be default . Default: default
local_ep_grou p	Array of strings	Specifies the IPv4 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC.
local_ep_grou p_ipv6	Array of strings	Specifies the IPv6 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC. This is a reserved field.
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true
status	String	Specifies the virtual gateway status, which can be ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING_UPDATE, or PENDING_DELETE.
bgp_asn	Integer	Specifies the local BGP ASN of the virtual gateway. Minimum: 1 Maximum: 4294967295
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the virtual gateway belongs to. Minimum: 36 Maximum: 36
device_id	String	Specifies the ID of the device that the virtual interface belongs to.
redundant_de vice_id	String	Specifies the ID of the redundant device.
public_border _group	String	Specifies the public border group of the AZ, indicating whether the site is a HomeZones site.

Updating the name and description of a virtual gateway and changing its IPv4 subnet to 192.168.3.0/24

```
PUT https://{dc_endpoint}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-gateways/
20082c1b-3c99-48d8-8e8c-116af5d7e9f0

{
    "virtual_gateway" : {
        "name" : "update-vgw-c7b22",
        "description" : "",
        "local_ep_group" : [ "192.168.3.0/24" ]
    }
}
```

Example Responses

Status code: 200

OK

The virtual gateway associated with a VPC is updated.

```
"virtual_gateway" : {
    "id" : "20082c1b-3c99-48d8-8e8c-116af5d7e9f0",
    "name" : "update-vgw-c7b22",
    "description" : "",
    "tenant_id" : "0605768a3300d5762f82c01180692873",
    "vpc_id" : "6592c28e-95d7-4b0a-9f61-004fdf03420c",
    "device_id" : "26.151.63.100",
    "redundant_device_id" : "26.152.128.20",
    "type" : "default",
    "status" : "ACTIVE",
    "admin_state_up" : true,
    "bgp_asn" : 64512,
    "local_ep_group" : [ "192.168.3.0/24" ],
    "enterprise_project_id" : "0",
    "public_border_group" : "center"
},
    "request_id" : "765f7aaf8f2edd0e719de564ef72e2de"
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.2.3 Deleting a Virtual Gateway

Function

The API is used to delete a specified virtual gateway.

URI

DELETE /v3/{project_id}/dcaas/virtual-gateways/{virtual_gateway_id}

Table 5-59 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
virtual_gatew ay_id	Yes	String	Specifies the virtual gateway ID.

Table 5-60 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

None

Example Requests

Deleting a virtual gateway

 $DELETE\ https://\{dc_endpoint\}/v3/08d5a9564a704afda6039ae2babbef3c/dcaas/virtual-gateways/20082c1b-3c99-48d8-8e8c-116af5d7e9f0$

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See Error Codes.

5.2.4 Querying Virtual Gateways

Function

This API is used to query virtual gateways.

URI

GET /v3/{project_id}/dcaas/virtual-gateways

Table 5-61 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Table 5-62 Query Parameters

Parameter	Mandatory	Туре	Description
limit	No	Integer	Specifies the number of records returned on each page. Value range: 1 to 2000 Minimum: 1 Maximum: 2000 Default: 2000
marker	No	String	Specifies the ID of the last resource record on the previous page. If this parameter is left blank, the first page is queried. This parameter must be used together with limit. Minimum: 0 Maximum: 36
fields	No	Array	Specifies the list of fields to be displayed. Array Length: 1 - 5
sort_dir	No	Array	Specifies the sorting order of returned results, which can be asc (ascending order) or desc (descending order). The default value is asc .

Parameter	Mandatory	Туре	Description
sort_key	No	String	Specifies the sorting field. Default: id Minimum: 0 Maximum: 36
id	No	Array	Specifies the resource ID by which instances are filtered. Array Length: 1 - 5
enterprise_pro ject_id	No	Array	Filters resource instances by enterprise project ID. Array Length: 1 - 10
vpc_id	No	Array	Specifies the VPC ID by which virtual gateways are filtered.

Table 5-63 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Table 5-64 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.
virtual_gatew ays	Array of VirtualGatew ay objects	Specifies parameters for creating a virtual gateway.

Parameter	Туре	Description
page_info	PageInfo object	Specifies the pagination query information.

Table 5-65 VirtualGateway

Parameter	Туре	Description
id	String	Specifies the virtual gateway ID.
vpc_id	String	Specifies the ID of the VPC connected by the virtual gateway.
tenant_id	String	Specifies the ID of the project that the instance belongs to. Minimum: 32 Maximum: 32
name	String	Specifies the virtual gateway name. Minimum: 0 Maximum: 64
description	String	Provides supplementary information about the virtual gateway. Minimum: 0 Maximum: 128
type	String	Specifies the virtual gateway type. The value can only be default . Default: default
local_ep_grou p	Array of strings	Specifies the IPv4 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC.
local_ep_grou p_ipv6	Array of strings	Specifies the IPv6 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC. This is a reserved field.
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true
status	String	Specifies the virtual gateway status, which can be ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING_UPDATE, or PENDING_DELETE.

Parameter	Туре	Description
bgp_asn	Integer	Specifies the local BGP ASN of the virtual gateway. Minimum: 1 Maximum: 4294967295
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the virtual gateway belongs to. Minimum: 36 Maximum: 36
device_id	String	Specifies the ID of the device that the virtual interface belongs to.
redundant_de vice_id	String	Specifies the ID of the redundant device.
public_border _group	String	Specifies the public border group of the AZ, indicating whether the site is a HomeZones site.

Table 5-66 PageInfo

Parameter	Туре	Description
previous_mar ker	String	Specifies the marker of the previous page. The value is the resource UUID.
		Minimum: 0
		Maximum: 36
current_count	Integer	Specifies the number of resources in the current list.
		Minimum: 0
		Maximum: 2000
next_marker	String	Specifies the marker of the next page. The value is the resource UUID. If the value is empty, the resource is on the last page.
		Minimum: 0
		Maximum: 36

Example Requests

Querying the virtual gateway list

GET https://{dc_endpoint}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-gateways

Example Responses

Status code: 200

OK

• The list of virtual gateways associated with VPCs is gueried.

```
"virtual_gateways" : [ {
    "id" : "20082c1b-3c99-48d8-8e8c-116af5d7e9f0",
    "name" : "vgw-c7b22",
    "description" : "",
    "tenant_id" : "0605768a3300d5762f82c01180692873",
    "vpc_id" : "6592c28e-95d7-4b0a-9f61-004fdf03420c",
    "device_id" : "26.151.63.100",
    "redundant_device_id" : "26.152.128.20",
    "type" : "default",
    "status" : "ACTIVE",
    "admin_state_up" : true,
    "bgp_asn" : 64512,
    "local_ep_group" : [ "192.168.1.0/24" ],
    "enterprise_project_id" : "0",
    "public_border_group" : "center"
} ],
    "request_id" : "765f7aaf8f2edd0e719de564ef72e2de"
}
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.2.5 Creating a Virtual Gateway

Function

This API is used to create a virtual gateway.

URI

POST /v3/{project_id}/dcaas/virtual-gateways

Table 5-67 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Table 5-68 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-69 Request body parameters

Parameter	Mandatory	Туре	Description
virtual_gatew ay	No	CreateVirtual Gateway object	Specifies parameters for creating a virtual gateway.

Table 5-70 CreateVirtualGateway

Parameter	Mandatory	Туре	Description
vpc_id	Yes	String	Specifies the ID of the VPC that the virtual gateway is associated with.
name	No	String	Specifies the virtual gateway name. Minimum: 0 Maximum: 64
description	No	String	Provides supplementary information about the virtual gateway. Minimum: 0 Maximum: 128

Parameter	Mandatory	Туре	Description
local_ep_grou p	Yes	Array of strings	Lists the IPv4 subnets that can be accessed over the virtual gateway. Generally, the list contains the subnet CIDR blocks of the associated VPC.
local_ep_grou p_ipv6	No	Array of strings	Specifies the IPv6 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC. This is a reserved field.
bgp_asn	No	Integer	Specifies the local BGP autonomous system number (ASN) of the virtual gateway. Minimum: 1 Maximum: 4294967295
enterprise_pro ject_id	No	String	Specifies the ID of the enterprise project that the virtual gateway belongs to. Minimum: 36 Maximum: 36

Response Parameters

Table 5-71 Response body parameters

Parameter Type		Description	
virtual_gatew ay	VirtualGatew ay object	Specifies parameters for creating a virtual gateway.	
request_id	String	Specifies the request ID.	

Table 5-72 VirtualGateway

Parameter	Туре	Description	
id	String	Specifies the virtual gateway ID.	
vpc_id	String	Specifies the ID of the VPC connected by the virtual gateway.	

Parameter	Туре	Description	
tenant_id	String	Specifies the ID of the project that the instance belongs to. Minimum: 32 Maximum: 32	
name	String	Specifies the virtual gateway name. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the virtual gateway. Minimum: 0 Maximum: 128	
type	String	Specifies the virtual gateway type. The value can only be default . Default: default	
local_ep_grou p	Array of strings	Specifies the IPv4 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC.	
local_ep_grou p_ipv6	Array of strings	Specifies the IPv6 subnets connected by the virtual gateway, which is usually the CIDR blocks of a VPC. This is a reserved field.	
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false . Default: true	
status	String	Specifies the virtual gateway status, which can be ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING_UPDATE, or PENDING_DELETE.	
bgp_asn	Integer	Specifies the local BGP ASN of the virtual gateway. Minimum: 1 Maximum: 4294967295	
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the virtual gateway belongs to. Minimum: 36 Maximum: 36	
device_id	String	Specifies the ID of the device that the virtual interface belongs to.	
redundant_de vice_id	String	Specifies the ID of the redundant device.	

Parameter	Туре	Description	
public_border _group	String	Specifies the public border group of the AZ, indicating whether the site is a HomeZones site.	

Example Requests

• Creating a virtual gateway that will be used to access a VPC, with the local BGP ASN set to 64512 and the IPv4 subnet to 192.168.1.0/24

```
POST https://{dc_endpoint}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-gateways

{
    "virtual_gateway" : {
        "name" : "vgw-c7b22",
        "description" : "",
        "vpc_id" : "6592c28e-95d7-4b0a-9f61-004fdf03420c",
        "bgp_asn" : 64512,
        "local_ep_group" : [ "192.168.1.0/24" ]
    }
}
```

Example Responses

Status code: 201

Created

The virtual gateway for accessing the VPC is created

```
{
  "virtual_gateway" : {
    "id" : "20082c1b-3c99-48d8-8e8c-116af5d7e9f0",
    "name" : "vgw-c7b22",
    "description" : "",
    "tenant_id" : "0605768a3300d5762f82c01180692873",
    "vpc_id" : "6592c28e-95d7-4b0a-9f61-004fdf03420c",
    "device_id" : "26.151.63.100",
    "redundant_device_id" : "26.152.128.20",
    "type" : "default",
    "status" : "ACTIVE",
    "admin_state_up" : true,
    "bgp_asn" : 64512,
    "local_ep_group" : [ "192.168.1.0/24" ],
    "enterprise_project_id" : "0",
    "public_border_group" : "center"
    }
}
```

Status Codes

Status Code	Description
201	Created

Error Codes

See Error Codes.

5.3 Virtual Interface

5.3.1 Querying Details About a Virtual Interface

Function

This API is used to querying details about a virtual interface.

URI

GET /v3/{project_id}/dcaas/virtual-interfaces/{virtual_interface_id}

Table 5-73 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
virtual_interfa ce_id	Yes	String	Specifies the virtual interface ID.
			Minimum: 36
			Maximum: 36

Table 5-74 Query Parameters

Parameter	Mandatory	Туре	Description
fields	No	Array	Specifies the list of fields to be displayed.
			Array Length: 1 - 5

Table 5-75 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Table 5-76 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.
virtual_interfa ce	VirtualInterf ace object	Specifies parameters for creating a virtual interface.

Table 5-77 VirtualInterface

Parameter	Туре	Description
id	String	Specifies the virtual interface ID. Maximum: 36
name	String	Specifies the virtual interface name. Maximum: 64
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false .
bandwidth	Integer	Specifies the virtual interface bandwidth. Minimum: 2 Maximum: 2147483647

Parameter	Туре	Description
create_time	String	Specifies the time when the virtual interface was created. The UTC time format yyyy-MM-ddTHH:mm:ss.SSSZ is used. Maximum: 255
description	String	Provides supplementary information about the virtual interface. Maximum: 128
direct_connec t_id	String	Specifies the connection ID. Maximum: 36
service_type	String	Specifies the gateway type. The value is VGW .
status	String	Specifies the operating status, which can be ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING_UPDATE, PENDING_DELETE, DELETED, AUTHORIZATION, or REJECTED.
tenant_id	String	Specifies the project ID.
		Minimum: 32
		Maximum: 32
type	String	Specifies the type of the virtual interface. The value is private .
		Default: private
		Maximum: 255
		Enumeration values:
		• private
		• public
vgw_id	String	Specifies the virtual gateway ID.
		Minimum: 36
		Maximum: 36
vlan	Integer	Specifies the VLAN for connecting to the user gateway. The value ranges from 0 to 3999 . Minimum: 0 Maximum: 3999
route_limit	Integer	Specifies the remote subnet route configurations of the virtual interface. Minimum: 1 Maximum: 200 Default: 50

Parameter	Туре	Description
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .
enable_bfd	Boolean	Specifies whether to enable Bidirectional Forwarding Detection (BFD). The value can be true or false .
lag_id	String	Specifies the ID of the LAG associated with the virtual interface. Minimum: 36 Maximum: 36
device_id	String	Specifies the ID of the device that the virtual interface belongs to.
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the virtual interface belongs to. Minimum: 36 Maximum: 36
local_gateway _v4_ip	String	Specifies the IPv4 interface address of the gateway used on the cloud. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
remote_gatew ay_v4_ip	String	Specifies the IPv4 interface address of the gateway used on premises. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
ies_id	String	Specifies the ID of an IES edge site.
reason	String	Displays error information if the status of a line is Error .
rate_limit	Boolean	Specifies whether rate limiting is enabled on a virtual interface.
address_famil y	String	Specifies the address family of the virtual interface, which can be IPv4 or IPv6 . This parameter has been migrated to the vifpeer parameter list and will be discarded later.
local_gateway _v6_ip	String	Specifies the IPv6 interface address of the gateway used on the cloud. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
remote_gatew ay_v6_ip	String	Specifies the IPv6 interface address of the gateway used on premises. This parameter has been migrated to the vifpeer parameter list and will be discarded later.

Parameter	Туре	Description
lgw_id	String	Specifies the ID of the local gateway, which is used in IES scenarios.
gateway_id	String	Specifies the ID of the gateway associated with the virtual interface.
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
bgp_route_lim it	Integer	Specifies the BGP route configuration.
priority	String	Specifies the priority of a virtual interface. The value can be normal or low . If the priorities are the same, the virtual interfaces work in load balancing mode. If the priorities are different, the virtual interfaces work in active/standby pairs. Outbound traffic is preferentially forwarded to the normal virtual interface with a higher priority. This option is only supported by virtual interfaces that use BGP routing.
		Default: normal
		Enumeration values: • normal
		• low
vif_peers	Array of VifPeer objects	Provides information about virtual interface peers.
extend_attrib ute	VifExtendAtt ribute object	Provides extended parameter information.

Table 5-78 VifPeer

Parameter	Туре	Description
id	String	Specifies the resource ID. Minimum: 36 Maximum: 36
tenant_id	String	Specifies the ID of the project that the virtual interface peer belongs to. Minimum: 36 Maximum: 36
name	String	Specifies the name of the virtual interface peer. Minimum: 0 Maximum: 64
description	String	Provides supplementary information about the virtual interface peer. Minimum: 0 Maximum: 128
address_famil y	String	Specifies the address family type of the virtual interface, which can be IPv4 or IPv6 .
local_gateway _ip	String	Specifies the address of the virtual interface peer used on the cloud.
remote_gatew ay_ip	String	Specifies the address of the virtual interface peer used in the on-premises data center.
route_mode	String	Specifies the routing mode, which can be static or bgp. Maximum: 255 Enumeration values: bgp static
bgp_asn	Integer	Specifies the ASN of the BGP peer. Minimum: 1 Maximum: 4294967295
bgp_md5	String	Specifies the MD5 password of the BGP peer.
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections.

Parameter	Туре	Description
device_id	String	Specifies the ID of the device that the virtual interface peer belongs to.
bgp_route_lim it	Integer	Specifies the BGP route configuration.
bgp_status	String	Specifies the BGP protocol status of the virtual interface peer. If the virtual interface peer uses static routing, the status is null . Maximum: 10
status	String	Specifies the status of the virtual interface peer.
vif_id	String	Specifies the ID of the virtual interface corresponding to the virtual interface peer. Minimum: 36 Maximum: 36
receive_route_ num	Integer	Specifies the number of received BGP routes if BGP routing is used. If static routing is used, this parameter is meaningless and the value is -1. Note: If this parameter cannot be obtained, contact customer service to migrate your ports.
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .
enable_bfd	Boolean	Specifies whether to enable BFD. The value can be true or false .

Table 5-79 VifExtendAttribute

Parameter	Туре	Description
ha_type	String	Specifies the availability detection type of the virtual interface. Enumeration values:
		nqabfd

Parameter	Туре	Description
ha_mode	String	Specifies the availability detection mode. Enumeration values: auto_single auto_multi static_single static_multi enhance_nqa
detect_multipl ier	Integer	Specifies the number of detection retries. Default: 5
min_rx_interv al	Integer	Specifies the interval for receiving detection packets. Default: 1000
min_tx_interv al	Integer	Specifies the interval for sending detection packets. Default: 1000
remote_disclai m	Integer	Specifies the remote identifier of the static BFD session.
local_disclaim	Integer	Specifies the local identifier of the static BFD session.

Example Requests

Querying a virtual interface

 $POST\ https://\{dc_endpoint\}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-interfaces/0d0fdf63-f2c4-491c-8866-d504796189be$

Example Responses

Status code: 200

OK

```
{
"virtual_interface" : {
    "id" : "0d0fdf63-f2c4-491c-8866-d504796189be",
    "name" : "vif-0819",
    "description" : "",
    "tenant_id" : "0605768a3300d5762f82c01180692873",
    "direct_connect_id" : "4673e339-8412-4ee1-b73e-2ba9cdfa54c1",
    "vgw_id" : "8a47064a-f34c-4f94-b7fe-cac456c9b37b",
    "type" : "private",
    "service_type" : "VGW",
    "vlan" : 332,
    "bandwidth" : 2,
    "status" : "ACTIVE",
    "create_time" : "2022-08-19T11:28:06.000Z",
    "admin_state_up" : true,
```

```
"enable_bfd" : false,
 "route_limit" : 50,
 "enable_nqa" : false,
 "local_gateway_v4_ip" : "1.1.1.1/30",
 "remote_gateway_v4_ip" : "1.1.1.2/30",
 "ies_id" : null,
 "reason" : null,
 "rate_limit" : false,
 "address_family" : "ipv4",
 "local_gateway_v6_ip": null,
 "remote_gateway_v6_ip" : null,
 "lgw_id" : null,
"lag_id" : null,
 "gateway_id": null,
 "remote_ep_group" : [ "1.1.2.0/30" ],
"service_ep_group" : [ ],
"bgp_route_limit" : 100,
 "priority" : "normal",
"vif_peers" : [ {
   "id": "c768eb52-12a8-4859-9b43-81194643040c",
   "tenant_id": "0605768a3300d5762f82c01180692873",
   "name" : "vif-0819",
"description" : "",
   "address_family": "ipv4",
   "local_gateway_ip" : "1.1.1.1/30",
"remote_gateway_ip" : "1.1.1.2/30",
   "route_mode" : "static",
   "bgp_asn" : null,
"bgp_md5" : null,
"device_id" : "18.9.215.131",
   "bgp_route_limit": 100,
   "bgp_status" : null,
"status" : "ACTIVE",
"vif_id" : "0d0fdf63-f2c4-491c-8866-d504796189be",
   "receive_route_num" : -1,
"remote_ep_group" : [ "1.1.2.0/30" ],
   "service_ep_group" : null,
   "enable_bfd" : false,
   "enable_nqa" : false
 "enterprise_project_id": "0"
"request_id": "5633df7af874576d819a481c76673236"
```

Status Codes

Status Code	Description
200	OK

Error Codes

See Error Codes.

5.3.2 Updating a Virtual Interface

Function

This API is used to update a virtual interface.

URI

PUT /v3/{project_id}/dcaas/virtual-interfaces/{virtual_interface_id}

Table 5-80 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
virtual_interfa ce_id	Yes	String	Specifies the virtual interface ID.
			Minimum: 36
			Maximum: 36

Request Parameters

Table 5-81 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-82 Request body parameters

Parameter	Mandatory	Туре	Description
virtual_interfa ce	Yes	UpdateVirtua IInterface object	Virtual interface objects to be updated

Table 5-83 UpdateVirtualInterface

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the virtual interface name. Minimum: 0 Maximum: 64
description	No	String	Provides supplementary information about the virtual interface. Minimum: 0 Maximum: 128
bandwidth	No	Integer	Specifies the virtual interface bandwidth configuration. Minimum: 2 Maximum: 2147483647
remote_ep_gr oup	No	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.
service_ep_gr oup	No	Array of strings	Specifies the local endpoint group that is connected to the public network over a connection.
enable_bfd	No	Boolean	Specifies whether to enable BFD. The value can be true or false .
enable_nqa	No	Boolean	Specifies whether to enable NQA. The value can be true or false .
status	No	String	Confirms the virtual interfaces created by other users. The value can be ACCEPTED or REJECTED. Enumeration values: ACCEPTED REJECTED

Response Parameters

Table 5-84 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.
virtual_interfa ce	VirtualInterf ace object	Specifies parameters for creating a virtual interface.

Table 5-85 VirtualInterface

Parameter	Туре	Description
id	String	Specifies the virtual interface ID. Maximum: 36
name	String	Specifies the virtual interface name. Maximum: 64
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false .
bandwidth	Integer	Specifies the virtual interface bandwidth. Minimum: 2 Maximum: 2147483647
create_time	String	Specifies the time when the virtual interface was created. The UTC time format yyyy-MM-ddTHH:mm:ss.SSSZ is used. Maximum: 255
description	String	Provides supplementary information about the virtual interface. Maximum: 128
direct_connec t_id	String	Specifies the connection ID. Maximum: 36
service_type	String	Specifies the gateway type. The value is VGW .
status	String	Specifies the operating status, which can be ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING_UPDATE, PENDING_DELETE, DELETED, AUTHORIZATION, or REJECTED.
tenant_id	String	Specifies the project ID. Minimum: 32 Maximum: 32

Parameter	Туре	Description
type	String	Specifies the type of the virtual interface. The value is private . Default: private Maximum: 255 Enumeration values: • private • public
vgw_id	String	Specifies the virtual gateway ID. Minimum: 36 Maximum: 36
vlan	Integer	Specifies the VLAN for connecting to the user gateway. The value ranges from 0 to 3999 . Minimum: 0 Maximum: 3999
route_limit	Integer	Specifies the remote subnet route configurations of the virtual interface. Minimum: 1 Maximum: 200 Default: 50
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .
enable_bfd	Boolean	Specifies whether to enable Bidirectional Forwarding Detection (BFD). The value can be true or false .
lag_id	String	Specifies the ID of the LAG associated with the virtual interface. Minimum: 36 Maximum: 36
device_id	String	Specifies the ID of the device that the virtual interface belongs to.
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the virtual interface belongs to. Minimum: 36 Maximum: 36
local_gateway _v4_ip	String	Specifies the IPv4 interface address of the gateway used on the cloud. This parameter has been migrated to the vifpeer parameter list and will be discarded later.

Parameter	Туре	Description
remote_gatew ay_v4_ip	String	Specifies the IPv4 interface address of the gateway used on premises. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
ies_id	String	Specifies the ID of an IES edge site.
reason	String	Displays error information if the status of a line is Error .
rate_limit	Boolean	Specifies whether rate limiting is enabled on a virtual interface.
address_famil y	String	Specifies the address family of the virtual interface, which can be IPv4 or IPv6 . This parameter has been migrated to the vifpeer parameter list and will be discarded later.
local_gateway _v6_ip	String	Specifies the IPv6 interface address of the gateway used on the cloud. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
remote_gatew ay_v6_ip	String	Specifies the IPv6 interface address of the gateway used on premises. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
lgw_id	String	Specifies the ID of the local gateway, which is used in IES scenarios.
gateway_id	String	Specifies the ID of the gateway associated with the virtual interface.
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
bgp_route_lim it	Integer	Specifies the BGP route configuration.

Parameter	Туре	Description
priority	String	Specifies the priority of a virtual interface. The value can be normal or low . If the priorities are the same, the virtual interfaces work in load balancing mode. If the priorities are different, the virtual interfaces work in active/standby pairs. Outbound traffic is preferentially forwarded to the normal virtual interface with a higher priority. This option is only supported by virtual interfaces that use BGP routing. Default: normal
		Enumeration values:
		normal
		• low
vif_peers	Array of VifPeer objects	Provides information about virtual interface peers.
extend_attrib ute	VifExtendAtt ribute object	Provides extended parameter information.

Table 5-86 VifPeer

Parameter	Туре	Description
id	String	Specifies the resource ID.
		Minimum: 36
		Maximum: 36
tenant_id	String	Specifies the ID of the project that the virtual interface peer belongs to.
		Minimum: 36
		Maximum: 36
name	String	Specifies the name of the virtual interface peer.
		Minimum: 0
		Maximum: 64
description	String	Provides supplementary information about the virtual interface peer.
		Minimum: 0
		Maximum: 128
address_famil y	String	Specifies the address family type of the virtual interface, which can be IPv4 or IPv6 .

Parameter	Туре	Description
local_gateway _ip	String	Specifies the address of the virtual interface peer used on the cloud.
remote_gatew ay_ip	String	Specifies the address of the virtual interface peer used in the on-premises data center.
route_mode	String	Specifies the routing mode, which can be static or bgp. Maximum: 255 Enumeration values: bgp static
bgp_asn	Integer	Specifies the ASN of the BGP peer. Minimum: 1 Maximum: 4294967295
bgp_md5	String	Specifies the MD5 password of the BGP peer.
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections.
device_id	String	Specifies the ID of the device that the virtual interface peer belongs to.
bgp_route_lim it	Integer	Specifies the BGP route configuration.
bgp_status	String	Specifies the BGP protocol status of the virtual interface peer. If the virtual interface peer uses static routing, the status is null . Maximum: 10
status	String	Specifies the status of the virtual interface peer.
vif_id	String	Specifies the ID of the virtual interface corresponding to the virtual interface peer. Minimum: 36 Maximum: 36

Parameter	Туре	Description
receive_route_ num	Integer	Specifies the number of received BGP routes if BGP routing is used. If static routing is used, this parameter is meaningless and the value is -1. Note: If this parameter cannot be obtained, contact customer service to migrate your ports.
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .
enable_bfd	Boolean	Specifies whether to enable BFD. The value can be true or false .

Table 5-87 VifExtendAttribute

Parameter	Туре	Description
ha_type	String	Specifies the availability detection type of the virtual interface.
		Enumeration values:
		• nqa
		• bfd
ha_mode	String	Specifies the availability detection mode.
		Enumeration values:
		auto_single
		auto_multi
		static_single
		static_multi
		enhance_nqa
detect_multipl	Integer	Specifies the number of detection retries.
ier		Default: 5
min_rx_interv al	Integer	Specifies the interval for receiving detection packets.
		Default: 1000
min_tx_interv	Integer	Specifies the interval for sending detection packets.
		Default: 1000
remote_disclai m	Integer	Specifies the remote identifier of the static BFD session.
local_disclaim	Integer	Specifies the local identifier of the static BFD session.

Example Requests

Updating the name and description of a virtual interface and changing its bandwidth to 2 Mbit/s

```
PUT https://{dc_endpoint}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-interfaces/0d0fdf63-f2c4-491c-8866-d504796189be

{
    "virtual_interface" : {
        "name" : "vif-0819",
        "description" : "mytest",
        "bandwidth" : 2
    }
}
```

Example Responses

Status code: 200

OK

```
"virtual_interface" : {
 "id": "0d0fdf63-f2c4-491c-8866-d504796189be",
 "name": "vif-0819",
"description" : "mytest",
"tenant_id" : "0605768a3300d5762f82c01180692873",
 "direct_connect_id" : "4673e339-8412-4ee1-b73e-2ba9cdfa54c1",
 "vgw_id" : "8a47064a-f34c-4f94-b7fe-cac456c9b37b",
 "type" : "private",
 "service_type": "VGW",
 "vlan" : 332,
 "bandwidth": 2,
 "status": "ACTIVE",
 "create_time": "2022-08-19T11:28:06.000Z",
 "admin_state_up" : true,
 "enable_bfd" : false,
 "route_limit": 50,
 "enable_nqa" : false,
 "local_gateway_v4_ip" : "1.1.1.1/30",
 "remote_gateway_v4_ip": "1.1.1.2/30",
 "ies_id" : null,
 "reason" : null,
 "rate_limit" : false,
 "address_family" : "ipv4",
 "local_gateway_v6_ip" : null,
 "remote_gateway_v6_ip" : null,
 "lgw_id" : null,
 "lag_id" : null,
 "gateway_id": null,
"remote_ep_group" : [ "1.1.2.0/30" ],
"service_ep_group" : [ ],
 "bgp_route_limit": 100,
 "priority" : "normal",
"vif_peers" : [ {
  "id": "c768eb52-12a8-4859-9b43-81194643040c",
  "tenant_id": "0605768a3300d5762f82c01180692873",
  "name" : "vif-0819",
  "description": "",
  "address_family": "ipv4",
"local_gateway_ip": "1.1.1.1/30",
"remote_gateway_ip": "1.1.1.2/30",
  "route_mode": "static",
   "bgp_asn" : null,
  "bgp_md5" : null,
  "device_id" : "18.9.215.131",
  "bgp_route_limit": 100,
```

```
"bgp_status" : null,
    "status" : "ACTIVE",
    "vif_id" : "0d0fdf63-f2c4-491c-8866-d504796189be",
    "receive_route_num" : -1,
    "remote_ep_group" : [ "1.1.2.0/30" ],
    "service_ep_group" : null,
    "enable_bfd" : false,
    "enable_nqa" : false
} ],
    "enterprise_project_id" : "0"
},
    "request_id" : "5633df7af874576d819a481c76673236"
}
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.3.3 Deleting a Virtual Interface

Function

This API is used to delete a virtual interface.

URI

DELETE /v3/{project_id}/dcaas/virtual-interfaces/{virtual_interface_id}

Table 5-88 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
virtual_interfa ce_id	Yes	String	Specifies the virtual interface ID.
			Minimum: 36
			Maximum: 36

Table 5-89 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

None

Example Requests

Deleting a virtual interface

DELETE https://{dc_endpoint}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-interfaces/0d0fdf63-f2c4-491c-8866-d504796189be

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See **Error Codes**.

5.3.4 Querying the Virtual Interface List

Function

This API is used to query all virtual interfaces of a tenant.

URI

GET /v3/{project_id}/dcaas/virtual-interfaces

Table 5-90 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Table 5-91 Query Parameters

Parameter	Mandatory	Туре	Description
limit	No	Integer	Specifies the number of records returned on each page. Value range: 1 to 2000 Minimum: 1 Maximum: 2000 Default: 2000
marker	No	String	Specifies the ID of the last resource record on the previous page. If this parameter is left blank, the first page is queried. This parameter must be used together with limit. Minimum: 0 Maximum: 36
fields	No	Array	Specifies the list of fields to be displayed. Array Length: 1 - 5
sort_dir	No	Array	Specifies the sorting order of returned results, which can be asc (ascending order) or desc (descending order). The default value is asc.
sort_key	No	String	Specifies the sorting field. Default: id Minimum: 0 Maximum: 36
enterprise_pro ject_id	No	Array	Filters resource instances by enterprise project ID. Array Length: 1 - 10

Parameter	Mandatory	Туре	Description
id	No	Array	Specifies the resource ID by which instances are filtered. Array Length: 1 - 5
status	No	Array	Specifies the status by which instances are filtered. Array Length: 1 - 5
direct_connec t_id	No	Array	Specifies the connection ID by which connections are filtered and queried. Array Length: 1 - 5
vgw_id	No	Array	Specifies the virtual gateway ID by which virtual gateways are filtered and queried. Array Length: 1 - 5

Table 5-92 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Table 5-93 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.

Parameter	Туре	Description
virtual_interfa ces	Array of VirtualInterf ace objects	Specifies parameters for creating a virtual interface.
page_info	PageInfo object	Specifies the pagination query information.

Table 5-94 VirtualInterface

Parameter	Туре	Description
id	String	Specifies the virtual interface ID. Maximum: 36
name	String	Specifies the virtual interface name. Maximum: 64
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false .
bandwidth	Integer	Specifies the virtual interface bandwidth. Minimum: 2 Maximum: 2147483647
create_time	String	Specifies the time when the virtual interface was created. The UTC time format yyyy-MM-ddTHH:mm:ss.SSSZ is used. Maximum: 255
description	String	Provides supplementary information about the virtual interface. Maximum: 128
direct_connec t_id	String	Specifies the connection ID. Maximum: 36
service_type	String	Specifies the gateway type. The value is VGW .
status	String	Specifies the operating status, which can be ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING_UPDATE, PENDING_DELETE, DELETED, AUTHORIZATION, or REJECTED.
tenant_id	String	Specifies the project ID. Minimum: 32 Maximum: 32
		IVIAXIIIIUIII: 32

Parameter	Туре	Description
type	String	Specifies the type of the virtual interface. The value is private . Default: private Maximum: 255 Enumeration values: • private • public
vgw_id	String	Specifies the virtual gateway ID. Minimum: 36 Maximum: 36
vlan	Integer	Specifies the VLAN for connecting to the user gateway. The value ranges from 0 to 3999 . Minimum: 0 Maximum: 3999
route_limit	Integer	Specifies the remote subnet route configurations of the virtual interface. Minimum: 1 Maximum: 200 Default: 50
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .
enable_bfd	Boolean	Specifies whether to enable Bidirectional Forwarding Detection (BFD). The value can be true or false .
lag_id	String	Specifies the ID of the LAG associated with the virtual interface. Minimum: 36 Maximum: 36
device_id	String	Specifies the ID of the device that the virtual interface belongs to.
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the virtual interface belongs to. Minimum: 36 Maximum: 36
local_gateway _v4_ip	String	Specifies the IPv4 interface address of the gateway used on the cloud. This parameter has been migrated to the vifpeer parameter list and will be discarded later.

Parameter	Туре	Description
remote_gatew ay_v4_ip	String	Specifies the IPv4 interface address of the gateway used on premises. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
ies_id	String	Specifies the ID of an IES edge site.
reason	String	Displays error information if the status of a line is Error .
rate_limit	Boolean	Specifies whether rate limiting is enabled on a virtual interface.
address_famil y	String	Specifies the address family of the virtual interface, which can be IPv4 or IPv6 . This parameter has been migrated to the vifpeer parameter list and will be discarded later.
local_gateway _v6_ip	String	Specifies the IPv6 interface address of the gateway used on the cloud. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
remote_gatew ay_v6_ip	String	Specifies the IPv6 interface address of the gateway used on premises. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
lgw_id	String	Specifies the ID of the local gateway, which is used in IES scenarios.
gateway_id	String	Specifies the ID of the gateway associated with the virtual interface.
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections. This parameter has been migrated to the vifpeer parameter list and will be discarded later.
bgp_route_lim it	Integer	Specifies the BGP route configuration.

Parameter	Туре	Description
priority	String	Specifies the priority of a virtual interface. The value can be normal or low . If the priorities are the same, the virtual interfaces work in load balancing mode. If the priorities are different, the virtual interfaces work in active/standby pairs. Outbound traffic is preferentially forwarded to the normal virtual interface with a higher priority. This option is only supported by virtual interfaces that use BGP routing. Default: normal
		Enumeration values:
		• normal
		• low
vif_peers	Array of VifPeer objects	Provides information about virtual interface peers.
extend_attrib ute	VifExtendAtt ribute object	Provides extended parameter information.

Table 5-95 VifPeer

Parameter	Туре	Description
id	String	Specifies the resource ID.
		Minimum: 36
		Maximum: 36
tenant_id	String	Specifies the ID of the project that the virtual interface peer belongs to.
		Minimum: 36
		Maximum: 36
name	String	Specifies the name of the virtual interface peer.
		Minimum: 0
		Maximum: 64
description	String	Provides supplementary information about the virtual interface peer.
		Minimum: 0
		Maximum: 128
address_famil y	String	Specifies the address family type of the virtual interface, which can be IPv4 or IPv6 .

Parameter	Туре	Description	
local_gateway _ip	String	Specifies the address of the virtual interface peer used on the cloud.	
remote_gatew ay_ip	String	Specifies the address of the virtual interface peer used in the on-premises data center.	
route_mode	String	Specifies the routing mode, which can be static or bgp. Maximum: 255 Enumeration values: • bgp • static	
bgp_asn	Integer	Specifies the ASN of the BGP peer. Minimum: 1 Maximum: 4294967295	
bgp_md5	String	Specifies the MD5 password of the BGP peer.	
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.	
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections.	
device_id	String	Specifies the ID of the device that the virtual interface peer belongs to.	
bgp_route_lim it	Integer	Specifies the BGP route configuration.	
bgp_status	String	Specifies the BGP protocol status of the virtual interface peer. If the virtual interface peer uses static routing, the status is null . Maximum: 10	
status	String	Specifies the status of the virtual interface peer.	
vif_id	String	Specifies the ID of the virtual interface corresponding to the virtual interface peer. Minimum: 36 Maximum: 36	

Parameter	Туре	Description
receive_route_ num	Integer	Specifies the number of received BGP routes if BGP routing is used. If static routing is used, this parameter is meaningless and the value is -1. Note: If this parameter cannot be obtained, contact customer service to migrate your ports.
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .
enable_bfd	Boolean	Specifies whether to enable BFD. The value can be true or false .

Table 5-96 VifExtendAttribute

Parameter	Туре	Description
ha_type	String	Specifies the availability detection type of the virtual interface.
		Enumeration values:
		• nqa
		• bfd
ha_mode	String	Specifies the availability detection mode.
		Enumeration values:
		auto_single
		auto_multi
		static_single
		static_multi
		enhance_nqa
detect_multipl	Integer	Specifies the number of detection retries.
ier		Default: 5
min_rx_interv al	Integer	Specifies the interval for receiving detection packets.
		Default: 1000
min_tx_interv	Integer	Specifies the interval for sending detection packets.
		Default: 1000
remote_disclai m	Integer	Specifies the remote identifier of the static BFD session.
local_disclaim	Integer	Specifies the local identifier of the static BFD session.

Table 5-97 PageInfo

Parameter	Туре	Description	
previous_mar ker	String	Specifies the marker of the previous page. The value is the resource UUID.	
		Minimum: 0	
		Maximum: 36	
current_count	Integer	Specifies the number of resources in the current list.	
		Minimum: 0	
		Maximum: 2000	
next_marker	String	Specifies the marker of the next page. The value is the resource UUID. If the value is empty, the resource is on the last page.	
		Minimum: 0	
		Maximum: 36	

Querying the virtual interface list

GET https://{dc_endpoint}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-interfaces

Example Responses

Status code: 200

OK

```
"virtual_interfaces" : [ {
 "id": "0d0fdf63-f2c4-491c-8866-d504796189be",
 "name" : "vif-0819",
"description" : "mytest",
"tenant_id" : "0605768a3300d5762f82c01180692873",
 "direct_connect_id": "4673e339-8412-4ee1-b73e-2ba9cdfa54c1",
"vgw_id": "8a47064a-f34c-4f94-b7fe-cac456c9b37b",
"type": "private",
"service_type": "VGW",
 "vlan": 332,
 "bandwidth" : 2,
 "status" : "ACTIVE",
 "create_time": "2022-08-19T11:28:06.000Z",
 "admin_state_up" : true,
"enable_bfd" : false,
"route_limit" : 50,
 "enable_nqa" : false,
 "local_gateway_v4_ip": "1.1.1.1/30",
 "remote_gateway_v4_ip" : "1.1.1.2/30",
 "ies_id" : null,
 "reason" : null,
 "rate_limit" : false,
 "address_family" : "ipv4",
 "local_gateway_v6_ip" : null,
 "remote_gateway_v6_ip" : null,
```

```
"lgw_id" : null,
 "gateway_id" : null,
"remote_ep_group" : [ "1.1.2.0/30" ],
"service_ep_group" : [ ],
"bgp_route_limit" : 100,
"priority" : "normal",
"vif_peers" : [ {
  "id": "c768eb52-12a8-4859-9b43-81194643040c",
  "tenant_id": "0605768a3300d5762f82c01180692873",
  "name": "vif-0819",
  "description": "'
  "address_family" : "ipv4",
  "local_gateway_ip": "1.1.1.1/30",
  "remote_gateway_ip" : "1.1.1.2/30",
  "route_mode" : "static",
  "bgp_asn" : null,
  "bgp_md5": null,
  "device_id" : "18.9.215.131",
  "bgp_route_limit": 100,
  "bgp_status" : null,
  "status" : "ACTIVE"
  "vif_id": "0d0fdf63-f2c4-491c-8866-d504796189be",
  "receive_route_num" : -1,
"remote_ep_group" : [ "1.1.2.0/30" ],
  "service_ep_group" : null,
"enable_bfd" : false,
  "enable_nqa": false
}],
 "enterprise_project_id": "0"
"request_id" : "5633df7af874576d819a481c76673236"
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.3.5 Creating a Virtual Interface

Function

This API is used to create a virtual interface.

URI

POST /v3/{project_id}/dcaas/virtual-interfaces

Table 5-98 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Request Parameters

Table 5-99 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-100 Request body parameters

Parameter	Mandatory	Туре	Description
virtual_interfa ce	Yes	CreateVirtual Interface object	Specifies parameters for creating a virtual interface.

Table 5-101 CreateVirtualInterface

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the virtual interface name. Minimum: 0 Maximum: 64
description	No	String	Provides supplementary information about the virtual interface. Minimum: 0 Maximum: 128

Parameter	Mandatory	Туре	Description
direct_connec t_id	No	String	Specifies the ID of the connection associated with the virtual interface. When creating a virtual interface, you need to specify direct_connect_id or lag_id. This parameter is mandatory when LAG is not supported at the site.
type	Yes	String	Specifies the type of the virtual interface. The value is private. Enumeration values: private public
vlan	Yes	Integer	Specifies the customer VLAN to be connected. If you select a hosted connection, the VLAN must be the same as that of the hosted connection. Minimum: 0 Maximum: 3999
bandwidth	Yes	Integer	Specifies the virtual interface bandwidth. Minimum: 2 Maximum: 2147483647
local_gateway _v4_ip	No	String	Specifies the IPv4 interface address of the gateway used on the cloud. This parameter is mandatory if address_family is set to an IPv4 address.
remote_gatew ay_v4_ip	No	String	Specifies the IPv4 interface address of the gateway on the on-premises network. This parameter is mandatory if address_family is set to an IPv4 address.
address_famil y	No	String	Specifies the address family type of the virtual interface, which can be IPv4 or IPv6. Default: ipv4

Parameter	Mandatory	Туре	Description
local_gateway _v6_ip	No	String	Specifies the IPv6 interface address of the gateway used on the cloud. This parameter is mandatory if address_family is set to an IPv6 address.
remote_gatew ay_v6_ip	No	String	Specifies the IPv6 interface address of the gateway on the on-premises network. This parameter is mandatory if address_family is set to an IPv6 address.
vgw_id	Yes	String	Specifies the ID of the virtual gateway connected by the virtual interface.
route_mode	Yes	String	Specifies the routing mode, which can be static or bgp. Default: static Enumeration values: • static • bgp
bgp_asn	No	Integer	Specifies the ASN of the BGP peer on the customer side. Minimum: 1 Maximum: 4294967295
bgp_md5	No	String	Specifies the MD5 password of the BGP peer.
remote_ep_gr oup	Yes	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.
service_ep_gr oup	No	Array of strings	Specifies the subnets that access Internet services through a direct connection.
enable_bfd	No	Boolean	Specifies whether to enable Bidirectional Forwarding Detection (BFD). The value can be true or false . Default: false

Parameter	Mandatory	Туре	Description
enable_nqa	No	Boolean	Specifies whether to enable NQA. The value can be true or false . Default: false
			Default: laise
lag_id	No	String	Specifies the ID of the LAG associated with the virtual interface.
			Minimum: 36
			Maximum: 36
resource_tena nt_id	No	String	Specifies the project ID of another tenant, which is used to create virtual interfaces across tenants.
enterprise_pro ject_id	No	String	Specifies the ID of the enterprise project that the resource belongs to.
			Minimum: 36
			Maximum: 36

Response Parameters

Table 5-102 Response body parameters

Parameter	Туре	Description	
request_id	String	Specifies the request ID.	
virtual_interfa ce	VirtualInterf ace object	Specifies parameters for creating a virtual interface.	

Table 5-103 VirtualInterface

Parameter	Туре	Description	
id	String	Specifies the virtual interface ID. Maximum: 36	
name	String	Specifies the virtual interface name. Maximum: 64	
admin_state_ up	Boolean	Specifies the administrative status, which can be true or false .	

Parameter	Туре	Description	
bandwidth	Integer	Specifies the virtual interface bandwidth. Minimum: 2 Maximum: 2147483647	
create_time	String	Specifies the time when the virtual interface was created. The UTC time format yyyy-MM-ddTHH:mm:ss.SSSZ is used. Maximum: 255	
description	String	Provides supplementary information about the virtual interface. Maximum: 128	
direct_connec t_id	String	Specifies the connection ID. Maximum: 36	
service_type	String	Specifies the gateway type. The value is VGW .	
status	String	Specifies the operating status, which can be ACTIVE, DOWN, BUILD, ERROR, PENDING_CREATE, PENDING_UPDATE, PENDING_DELETE, DELETED, AUTHORIZATION, or REJECTED.	
tenant_id	String	Specifies the project ID. Minimum: 32 Maximum: 32	
type	String	Specifies the type of the virtual interface. The value is private . Default: private Maximum: 255 Enumeration values: • private • public	
vgw_id	String	Specifies the virtual gateway ID. Minimum: 36 Maximum: 36	
vlan	Integer	Specifies the VLAN for connecting to the user gateway. The value ranges from 0 to 3999 . Minimum: 0 Maximum: 3999	

Parameter	Туре	Description	
route_limit	Integer	Specifies the remote subnet route configurations of the virtual interface. Minimum: 1 Maximum: 200 Default: 50	
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .	
enable_bfd	Boolean	Specifies whether to enable Bidirectional Forwarding Detection (BFD). The value can be true or false .	
lag_id	String	Specifies the ID of the LAG associated with the virtual interface. Minimum: 36 Maximum: 36	
device_id	String	Specifies the ID of the device that the virtual interface belongs to.	
enterprise_pro ject_id	String	Specifies the ID of the enterprise project that the virtual interface belongs to. Minimum: 36 Maximum: 36	
local_gateway _v4_ip	String	Specifies the IPv4 interface address of the gateway used on the cloud. This parameter has been migrated to the vifpeer parameter list and will be discarded later.	
remote_gatew ay_v4_ip	String	Specifies the IPv4 interface address of the gateway used on premises. This parameter has been migrated to the vifpeer parameter list and will be discarded later.	
ies_id	String	Specifies the ID of an IES edge site.	
reason	String	Displays error information if the status of a line is Error .	
rate_limit	Boolean	Specifies whether rate limiting is enabled on a virtual interface.	
address_famil y	String	Specifies the address family of the virtual interface, which can be IPv4 or IPv6 . This parameter has been migrated to the vifpeer parameter list and will be discarded later.	

Parameter	Туре	Description	
local_gateway _v6_ip	String	Specifies the IPv6 interface address of the gateway used on the cloud. This parameter has been migrated to the vifpeer parameter list and will be discarded later.	
remote_gatew ay_v6_ip	String	Specifies the IPv6 interface address of the gateway used on premises. This parameter has been migrated to the vifpeer parameter list and will be discarded later.	
lgw_id	String	Specifies the ID of the local gateway, which is used in IES scenarios.	
gateway_id	String	Specifies the ID of the gateway associated with the virtual interface.	
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center. This parameter has been migrated to the vifpeer parameter list and will be discarded later.	
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections. This parameter has been migrated to the vifpeer parameter list and will be discarded later.	
bgp_route_lim it	Integer	Specifies the BGP route configuration.	
priority	String	Specifies the priority of a virtual interface. The value can be normal or low . If the priorities are the same, the virtual interfaces work in load balancing mode. If the priorities are different, the virtual interfaces work in active/standby pairs. Outbound traffic is preferentially forwarded to the normal virtual interface with a higher priority. This option is only supported by virtual interfaces that use BGP routing. Default: normal Enumeration values: • normal • low	
vif_peers	Array of VifPeer objects	Provides information about virtual interface peers.	
extend_attrib ute	VifExtendAtt ribute object	Provides extended parameter information.	

Table 5-104 VifPeer

Parameter	Туре	Description	
id	String	Specifies the resource ID. Minimum: 36 Maximum: 36	
tenant_id	String	Specifies the ID of the project that the virtual interface peer belongs to. Minimum: 36 Maximum: 36	
name	String	Specifies the name of the virtual interface peer. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the virtual interface peer. Minimum: 0 Maximum: 128	
address_famil y	String	Specifies the address family type of the virtual interface, which can be IPv4 or IPv6 .	
local_gateway _ip	String	Specifies the address of the virtual interface peer used on the cloud.	
remote_gatew ay_ip	String	Specifies the address of the virtual interface peer used in the on-premises data center.	
route_mode	String	Specifies the routing mode, which can be static or bgp. Maximum: 255 Enumeration values: bgp static	
bgp_asn	Integer	Specifies the ASN of the BGP peer. Minimum: 1 Maximum: 4294967295	
bgp_md5	String	Specifies the MD5 password of the BGP peer.	
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.	

Parameter	Туре	Description	
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections.	
device_id	String	Specifies the ID of the device that the virtual interface peer belongs to.	
bgp_route_lim it	Integer	Specifies the BGP route configuration.	
bgp_status	String	Specifies the BGP protocol status of the virtual interface peer. If the virtual interface peer uses static routing, the status is null .	
		Maximum: 10	
status	String	Specifies the status of the virtual interface peer.	
vif_id	String	Specifies the ID of the virtual interface corresponding to the virtual interface peer. Minimum: 36 Maximum: 36	
receive_route_ num	Integer	Specifies the number of received BGP routes if BGP routing is used. If static routing is used, this parameter is meaningless and the value is -1. Note: If this parameter cannot be obtained, contact customer service to migrate your ports.	
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .	
enable_bfd	Boolean	Specifies whether to enable BFD. The value can be true or false .	

Table 5-105 VifExtendAttribute

Parameter	Туре	Description	
ha_type	String	Specifies the availability detection type of the virtual interface. Enumeration values:	
		nqa bfd	

Parameter	Туре	Description	
ha_mode	String	Specifies the availability detection mode.	
		Enumeration values:	
		auto_single	
		auto_multi	
		• static_single	
		static_multi	
		enhance_nqa	
detect_multipl	Integer	Specifies the number of detection retries.	
ier		Default: 5	
min_rx_interv	Integer	Specifies the interval for receiving detection	
al		packets.	
		Default: 1000	
min_tx_interv al	Integer	Specifies the interval for sending detection packets.	
		Default: 1000	
remote_disclai m	Integer	Specifies the remote identifier of the static BFD session.	
local_disclaim	Integer	Specifies the local identifier of the static BFD session.	

Creating a private virtual interface, with the bandwidth set to 2 Mbit/s, VLAN to 332, local gateway to 1.1.1.1/30, and remote gateway to 1.1.1.2/30, and routing mode to static routing

```
POST https://{dc_endpoint}/v3/0605768a3300d5762f82c01180692873/dcaas/virtual-interfaces

{
    "virtual_interface" : {
        "name" : "vif-0819",
        "description" : "mytest",
        "direct_connect_id" : "4673e339-8412-4ee1-b73e-2ba9cdfa54c1",
        "vgw_id" : "8a47064a-f34c-4f94-b7fe-cac456c9b37b",
        "vlan" : 332,
        "bandwidth" : 2,
        "local_gateway_v4_ip" : "1.1.1.1/30",
        "remote_gateway_v4_ip" : "1.1.1.2/30",
        "type" : "private",
        "route_mode" : "static",
        "remote_ep_group" : [ "1.1.2.0/30" ]
    }
}
```

Example Responses

Created

```
"virtual_interface" : {
 "id": "0d0fdf63-f2c4-491c-8866-d504796189be",
 "name": "vif-0819",
 "description": "mytest",
 "tenant_id": "0605768a3300d5762f82c01180692873",
 "direct_connect_id": "4673e339-8412-4ee1-b73e-2ba9cdfa54c1",
 "vgw_id" : "8a47064a-f34c-4f94-b7fe-cac456c9b37b",
 "type" : "private",
 "service_type" : "VGW",
 "vlan": 332,
 "bandwidth": 2,
 "device_id" : "18.9.215.131",
 "status": "ACTIVE",
 "create_time": "2022-08-19T11:28:06.000Z",
 "admin_state_up" : true,
 "enable_bfd" : false,
"route_limit" : 50,
 "enable_nga" : false,
 "local_gateway_v4_ip": "1.1.1.1/30",
 "remote_gateway_v4_ip": "1.1.1.2/30",
"ies_id" : null,
"reason" : null,
 "rate_limit": false,
 "local_gateway_v6_ip" : null,
 "remote_gateway_v6_ip": null,
"lgw_id" : null,
"lag_id" : null,
"priority" : "normal",
"vif_peers" : [ {
  "id": "c768eb52-12a8-4859-9b43-81194643040c",
  "tenant_id": "0605768a3300d5762f82c01180692873",
  "name": "vif-0819",
  "description": ""
  "address_family" : "ipv4",
  "local_gateway_ip" : "1.1.1.1/30",
"remote_gateway_ip" : "1.1.1.2/30",
  "route_mode" : "static",
  "bgp_asn" : null,
  "bgp_md5": null,
  "device_id" : "18.9.215.131",
   "bgp_route_limit" : 100,
  "bgp_status" : null,
  "status" : "ACTIVE"
  "vif_id": "0d0fdf63-f2c4-491c-8866-d504796189be",
  "receive_route_num": -1,
  "remote_ep_group" : [ "1.1.2.0/30" ],
  "enable_bfd" : false,
"enable_nqa" : false,
  "service_ep_group" : null
 }],
 "enterprise_project_id" : "0"
"request_id" : "5633df7af874576d819a481c76673236"
```

Status Codes

Status Code	Description
201	Created

Error Codes

See Error Codes.

5.3.6 Updating a Virtual Interface Peer

Function

This API is used to update a virtual interface peer, for example, its remote subnet, name, and description. This API is available only in regions that support IPv6. To use this API, contact customer service.

URI

PUT /v3/{project_id}/dcaas/vif-peers/{vif_peer_id}

Table 5-106 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
vif_peer_id	Yes	String	Specifies the virtual interface peer ID.

Request Parameters

Table 5-107 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-108 Request body parameters

Parameter	Mandatory	Туре	Description
vif_peer	No	UpdateVifPe er object	Specifies parameters for updating a virtual interface peer.

Table 5-109 UpdateVifPeer

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the name of the virtual interface peer.
			Minimum: 0
			Maximum: 64
description	No	String	Provides supplementary information about the virtual interface peer. Minimum: 0 Maximum: 128
remote_ep_gr oup	No	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.

Response Parameters

Table 5-110 Response body parameters

Parameter	Туре	Description
vif_peer	VifPeer object	Specifies the virtual interface peer.

Table 5-111 VifPeer

Parameter	Туре	Description	
id	String	Specifies the resource ID.	
		Minimum: 36	
		Maximum: 36	

Parameter	Туре	Description	
tenant_id	String	Specifies the ID of the project that the virtual interface peer belongs to. Minimum: 36 Maximum: 36	
name	String	Specifies the name of the virtual interface peer. Minimum: 0 Maximum: 64	
description	String	Provides supplementary information about the virtual interface peer. Minimum: 0 Maximum: 128	
address_famil y	String	Specifies the address family type of the virtual interface, which can be IPv4 or IPv6 .	
local_gateway _ip	String	Specifies the address of the virtual interface peer used on the cloud.	
remote_gatew ay_ip	String	Specifies the address of the virtual interface peer used in the on-premises data center.	
route_mode	String	Specifies the routing mode, which can be static or bgp. Maximum: 255 Enumeration values: bgp static	
bgp_asn	Integer	Specifies the ASN of the BGP peer. Minimum: 1 Maximum: 4294967295	
bgp_md5	String	Specifies the MD5 password of the BGP peer.	
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.	
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections.	
device_id	String	Specifies the ID of the device that the virtual interface peer belongs to.	
bgp_route_lim it	Integer	Specifies the BGP route configuration.	

Parameter	Туре	Description	
bgp_status	String	Specifies the BGP protocol status of the virtual interface peer. If the virtual interface peer uses static routing, the status is null .	
		Maximum: 10	
status	String	Specifies the status of the virtual interface peer.	
vif_id	String	Specifies the ID of the virtual interface corresponding to the virtual interface peer.	
		Minimum: 36	
		Maximum: 36	
receive_route_ num	Integer	Specifies the number of received BGP routes if BGP routing is used. If static routing is used, this parameter is meaningless and the value is -1. Note: If this parameter cannot be obtained, contact customer service to migrate your ports.	
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .	
enable_bfd	Boolean	Specifies whether to enable BFD. The value can be true or false .	

Updating the name, description, and remote subnet of a virtual interface peer

```
PUT https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dcaas/vif-peers/68250543-0a13-4ac7-aa36-d018856ac640

{
    "vif_peer" : {
        "name" : "vif-0819",
        "description" : "mytest",
        "remote_ep_group" : [ "20.1.1.0/24" ]
    }
```

Example Responses

Status code: 200

OK

```
{
    "vif_peer" : {
        "name" : "vif-0819",
        "description" : "mytest",
        "id" : "4c95de3e-9f75-4357-9c79-b22498dd71c7",
        "tenant_id" : "ed28c294165741faaeccab26913122a1",
        "address_family" : "ipv4",
        "local_gateway_ip" : "12.3.4.1/30",
        "remote_gateway_ip" : "12.3.4.2/30",
        "route_mode" : "static",
```

```
"bgp_asn": null,
"bgp_md5": null,
"bgp_route_limit": 100,
"bgp_status": null,
"status": "ACTIVE",
"vif_id": "5d6c17bc-0ebe-420b-8734-21f519e9d7ad",
"receive_route_num": -1,
"remote_ep_group": [ "20.1.1.0/24" ]
}
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.3.7 Deleting a Virtual Interface Peer

Function

This API is used to delete a virtual interface. The virtual interface must contain at least one peer. The last peer cannot be deleted. This API is available only in regions that support IPv6. To use this API, contact customer service.

URI

DELETE /v3/{project_id}/dcaas/vif-peers/{vif_peer_id}

Table 5-112 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
vif_peer_id	Yes	String	Specifies the virtual interface peer ID.

Request Parameters

Table 5-113 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

None

Example Requests

Deleting a virtual interface peer

DELETE https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dcaas/vif-peers/68250543-0a13-4ac7-aa36-d018856ac640

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See Error Codes.

5.3.8 Creating a Virtual Interface Peer

Function

This API is used to create an IPv6 peer. Each virtual interface can have two peers: IPv4 and IPv6 peers. When a virtual interface is created, an IPv4 peer is created by

default. After a virtual interface peer is created, you can query its settings by viewing the virtual interface details. This API is available only in regions that support IPv6. To use this API, contact customer service.

URI

POST /v3/{project_id}/dcaas/vif-peers

Table 5-114 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Request Parameters

Table 5-115 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-116 Request body parameters

Parameter	Mandatory	Туре	Description
vif_peer	No	CreateVifPee r object	Specifies parameters for creating a virtual interface peer.

Table 5-117 CreateVifPeer

Parameter	Mandatory	Туре	Description
name	No	String	Specifies the name of the virtual interface peer.
			Minimum: 0
			Maximum: 64
description	No	String	Provides supplementary information about the virtual interface peer.
			Minimum: 0
			Maximum: 128
address_famil y	No	String	Specifies the address family of the virtual interface, which can be IPv4 or IPv6 .
local_gateway _ip	No	String	Specifies the cloud-side gateway IP address of the virtual interface peer.
remote_gatew ay_ip	No	String	Specifies the customer-side gateway address of the virtual interface peer.
route_mode	No	String	Specifies the routing mode, which can be static or bgp . Maximum: 255
			Enumeration values:
			• bgp
			• static
bgp_asn	No	Integer	Specifies the AS of the BGP peer.
			Minimum: 1
			Maximum: 4294967295
bgp_md5	No	String	Specifies the MD5 password of the BGP peer.
remote_ep_gr oup	No	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.
vif_id	No	String	Specifies the ID of the virtual interface corresponding to the virtual interface peer. Minimum: 36 Maximum: 36

Response Parameters

Table 5-118 Response body parameters

Parameter	Туре	Description
vif_peer	VifPeer object	Specifies the virtual interface peer.

Table 5-119 VifPeer

Parameter	Туре	Description
id	String	Specifies the resource ID. Minimum: 36 Maximum: 36
tenant_id	String	Specifies the ID of the project that the virtual interface peer belongs to. Minimum: 36 Maximum: 36
name	String	Specifies the name of the virtual interface peer. Minimum: 0 Maximum: 64
description	String	Provides supplementary information about the virtual interface peer. Minimum: 0 Maximum: 128
address_famil y	String	Specifies the address family type of the virtual interface, which can be IPv4 or IPv6 .
local_gateway _ip	String	Specifies the address of the virtual interface peer used on the cloud.
remote_gatew ay_ip	String	Specifies the address of the virtual interface peer used in the on-premises data center.

Parameter	Туре	Description
route_mode	String	Specifies the routing mode, which can be static or bgp. Maximum: 255 Enumeration values: bgp static
bgp_asn	Integer	Specifies the ASN of the BGP peer. Minimum: 1 Maximum: 4294967295
bgp_md5	String	Specifies the MD5 password of the BGP peer.
remote_ep_gr oup	Array of strings	Specifies the remote subnet list, which records the CIDR blocks used in the on-premises data center.
service_ep_gr oup	Array of strings	Specifies the list of public network addresses that can be accessed by the on-premises data center. This field is required in the APIs of public network connections.
device_id	String	Specifies the ID of the device that the virtual interface peer belongs to.
bgp_route_lim it	Integer	Specifies the BGP route configuration.
bgp_status	String	Specifies the BGP protocol status of the virtual interface peer. If the virtual interface peer uses static routing, the status is null . Maximum: 10
status	String	Specifies the status of the virtual interface peer.
vif_id	String	Specifies the ID of the virtual interface corresponding to the virtual interface peer. Minimum: 36 Maximum: 36
receive_route_ num	Integer	Specifies the number of received BGP routes if BGP routing is used. If static routing is used, this parameter is meaningless and the value is -1. Note: If this parameter cannot be obtained, contact customer service to migrate your ports.
enable_nqa	Boolean	Specifies whether to enable NQA. The value can be true or false .

Parameter	Туре	Description
enable_bfd	Boolean	Specifies whether to enable BFD. The value can be true or false .

Creating a virtual interface peer with the remote subnet set to 20.1.1.0/24

```
POST https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dcaas/vif-peers/68250543-0a13-4ac7-aa36-d018856ac640

{
    "vif_peer" : {
        "name" : "vif-0819",
        "description" : "mytest",
        "remote_ep_group" : [ "20.1.1.0/24" ]
    }
}
```

Example Responses

Status code: 201

Created

```
{
  "vif_peer" : {
    "name" : "vif-0819",
    "description" : "mytest",
    "id" : "4c95de3e-9f75-4357-9c79-b22498dd71c7",
    "tenant_id" : "ed28c294165741faaeccab26913122a1",
    "address_family" : "ipv4",
    "local_gateway_ip" : "12.3.4.1/30",
    "remote_gateway_ip" : "12.3.4.2/30",
    "route_mode" : "static",
    "bgp_asn" : null,
    "bgp_md5" : null,
    "bgp_route_limit" : 100,
    "bgp_status" : null,
    "status" : "ACTIVE",
    "vif_id" : "5d6c17bc-0ebe-420b-8734-21f519e9d7ad",
    "receive_route_num" : -1,
    "remote_ep_group" : [ "12.3.4.0/30 172.56.0.0/16" ]
}
```

Status Codes

Status Code	Description
201	Created

Error Codes

See Error Codes.

5.3.9 Performing a Virtual Interface Switchover Test

Function

If there are two connections, automatic switchover between the connections is required for connectivity testing. If a switchover is performed, the virtual interface of the connection in use is disabled and traffic is interrupted. You can perform two operations on a virtual interface: Run the **shutdown** command to disable the virtual interface. Run the **undo_shutdown** command to enable the virtual interface. If **shutdown** is selected for the switchover test, the virtual interface is in the **ADMIN_SHUTDOWN** state, and no operations can be performed on the virtual interface. If **undo_shutdown** is selected for the switchover test, the virtual interface is in the **ACTIVE** state.

URI

POST /v3/{project_id}/dcaas/switchover-test

Table 5-120 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Request Parameters

Table 5-121 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Table 5-122 Request body parameters

Parameter	Mandatory	Туре	Description
switchover_te st_record	No	CreateSwitch overTest object	Specifies the parameters for creating a switchover test record.

Table 5-123 CreateSwitchoverTest

Parameter	Mandatory	Туре	Description
resource_id	Yes	String	Specifies the ID of the resource on which the switchover test is to be performed.
resource_type	No	String	Specifies the type of the resource on which the switchover test is to be performed.
			Default: virtual_interface
			Minimum: 0
			Maximum: 128
			Enumeration values:
			virtual_interface
operation	Yes	String	Specifies whether to perform a switchover test. Value options: shutdown and undo_shutdown
			Minimum: 0
			Maximum: 128
			Enumeration values:
			• shutdown
			• undo_shutdown

Response Parameters

Table 5-124 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.
switchover_te st_record	SwitchoverTe stRecord object	Provides supplementary information about the switchover test record.

Table 5-125 SwitchoverTestRecord

Parameter	Туре	Description
id	String	Specifies the unique ID of the switchover test record.
tenant_id	String	Specifies the tenant ID. Minimum: 32 Maximum: 32
resource_id	String	Specifies the ID of the resource on which the switchover test is to be performed.
resource_type	String	Specifies the type of the resource on which the switchover test is to be performed. Default: virtual_interface Minimum: 0 Maximum: 128 Enumeration values: • virtual_interface
operation	String	Specifies whether to perform a switchover test. Value options: shutdown and undo_shutdown Minimum: 0 Maximum: 128 Enumeration values: • shutdown • undo_shutdown
start_time	String	Specifies the start time of the switchover test.
end_time	String	Specifies the end time of the switchover test.
operate_statu s	String	Specifies the switchover test status. STARTING: initial status INPROGRESS: delivering configuration COMPLETE: configuration delivered ERROR: Configuration delivery failed Enumeration values: STARTING INPROGRESS COMPLETE ERROR

Shutting down the virtual interface to perform a switchover test

```
POST https://{dc_endpoint}/v3/de58f033eb664102ba85e4a5db473ca5/dcaas/switchover-test

{
    "switchover_test_record" : {
        "resource_type" : "virtual_interface",
        "resource_id" : "d0b3329c-0063-470c-b1dc-657656b2e540",
        "operation" : "shutdown"
    }
}
```

Example Responses

Status code: 201

Created

```
{
    "switchover_test_record" : {
        "id" : "862d61f1-d9ea-4093-ba0e-2b8d415e3ab3",
        "tenant_id" : "de58f033eb664102ba85e4a5db473ca5",
        "resource_type" : "virtual_interface",
        "resource_id" : "d0b3329c-0063-470c-b1dc-657656b2e540",
        "operation" : "shutdown",
        "start_time" : "2023-10-09T18:41:23.000Z",
        "end_time" : "2023-10-09T18:41:23.000Z",
        "operate_status" : "STARTING"
        },
        "request_id" : "f91634a12b116b6f946d7871f5b4de18"
}
```

Status Codes

Status Code	Description
201	Created

Error Codes

See Error Codes.

5.3.10 Querying the Switchover Test Records of a Virtual Interface

Function

This API is used to query the switchover test record list. Only the records whose **operate_status** is **COMPELTE** are displayed.

URI

GET /v3/{project_id}/dcaas/switchover-test

Table 5-126 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Table 5-127 Query Parameters

Parameter	Mandatory	Туре	Description
limit	No	Integer	Specifies the number of records returned on each page. Value range: 1 to 2000 Minimum: 1 Maximum: 2000 Default: 2000
marker	No	String	Specifies the ID of the last resource record on the previous page. If this parameter is left blank, the first page is queried. This parameter must be used together with limit. Minimum: 0 Maximum: 36
fields	No	Array	Specifies the list of fields to be displayed. Array Length: 1 - 5
sort_dir	No	Array	Specifies the sorting order of returned results, which can be asc (ascending order) or desc (descending order). The default value is asc.
sort_key	No	String	Specifies the sorting field. Default: id Minimum: 0 Maximum: 36
resource_id	No	Array	Resource ID used for querying switchover test records.

Request Parameters

Table 5-128 Request header parameters

Parameter	Mandatory	Туре	Description
X-Auth-Token	Yes	String	Specifies the user token. To obtain the token, see section "Obtaining the User Token" in the <i>Identity and Access Management API Reference</i> . The token is the value of X-Subject-Token in the response header. Minimum: 0 Maximum: 10240

Response Parameters

Table 5-129 Response body parameters

Parameter	Туре	Description
request_id	String	Specifies the request ID.
switchover_te st_records	Array of SwitchoverTe stRecord objects	Lists the switchover test records.
page_info	PageInfo object	Specifies the pagination query information.

Table 5-130 SwitchoverTestRecord

Parameter	Туре	Description	
id	String	Specifies the unique ID of the switchover test record.	
tenant_id	String	Specifies the tenant ID. Minimum: 32 Maximum: 32	
resource_id	String	Specifies the ID of the resource on which the switchover test is to be performed.	

Parameter	Туре	Description	
resource_type	String	Specifies the type of the resource on which the switchover test is to be performed.	
		Default: virtual_interface	
		Minimum: 0	
		Maximum: 128	
		Enumeration values:	
		virtual_interface	
operation	String	Specifies whether to perform a switchover test. Value options: shutdown and undo_shutdown	
		Minimum: 0	
		Maximum: 128	
		Enumeration values:	
		shutdown	
		undo_shutdown	
start_time	String	Specifies the start time of the switchover test.	
end_time	String	Specifies the end time of the switchover test.	
operate_statu	String	Specifies the switchover test status.	
S		STARTING: initial status	
		INPROGRESS: delivering configuration	
		COMPLETE: configuration delivered	
		ERROR: Configuration delivery failed	
		Enumeration values:	
		• STARTING	
		• INPROGRESS	
		COMPLETE	
		• ERROR	

Table 5-131 PageInfo

Parameter	Туре	Description
previous_mar ker	String	Specifies the marker of the previous page. The value is the resource UUID.
		Minimum: 0
		Maximum: 36

Parameter	Туре	Description	
current_count	Integer	Specifies the number of resources in the current list.	
		Minimum: 0	
		Maximum: 2000	
next_marker	String	Specifies the marker of the next page. The value is the resource UUID. If the value is empty, the resource is on the last page.	
		Minimum: 0	
		Maximum: 36	

Querying the switchover test record list

GET https://{dc_endpoint}/v3/de58f033eb664102ba85e4a5db473ca5/dcaas/switchover-test

Example Responses

Status code: 200

OK

```
{
    "request_id" : "bb154519fb167f99cdb01b7b9995ad14",
    "switchover_test_records" : [ {
        "id" : "862d61f1-d9ea-4093-ba0e-2b8d415e3ab3",
        "tenant_id" : "de58f033eb664102ba85e4a5db473ca5",
        "resource_type" : "virtual_interface",
        "resource_id" : "d0b3329c-0063-470c-b1dc-657656b2e540",
        "operation" : "shutdown",
        "start_time" : "2023-10-10T10:41:23.000Z",
        "end_time" : "2023-10-10T10:41:23.000Z",
        "operate_status" : "COMPLETE"
    } ]
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.4 Tag management

5.4.1 Querying Tags by Resource Type

Function

This API is used to query the tags of a resource type in a specific project. TMS uses this API to list tags created by a tenant to facilitate tag creation and resource filtering on the console.

URI

GET /v3/{project_id}/{resource_type}/tags

Table 5-132 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
resource_type	Yes	String	Specifies the Direct Connect resource type. • dc-directconnect: connection • dc-vgw: virtual gateway • dc-vif: virtual interface Enumeration values: • dc-directconnect • dc-vgw
			• dc-vif

Request Parameters

None

Response Parameters

Table 5-133 Response body parameters

Parameter	Туре	Description
tags	Array of Tag objects	Specifies the tags.
request_id	String	Specifies the request ID.

Table 5-134 Tag

Parameter	Туре	Description
key	String	Specifies the tag key. The key can contain a maximum of 36 Unicode characters, including letters, digits, hyphens (-), and underscores (_).
		Minimum: 0
		Maximum: 36
value	String	Specifies the tag value. The value can contain a maximum of 43 Unicode characters, including letters, digits, hyphens (-), underscores (_), and periods (.).
		Minimum: 0
		Maximum: 43

GET https://{dc_endpoint}/v3/ed28c294165741faaeccab26913122a1/dc-directconnect/tags

Example Responses

Status code: 200

OK

```
{
  "tags" : [ {
    "key" : "department",
    "value" : "finance"
  } ]
}
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.4.2 Querying Resource Tags

Function

This API is used to query resource tags.

URI

GET /v3/{project_id}/{resource_type}/{resource_id}/tags

Table 5-135 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
resource_type	Yes	String	Specifies the Direct Connect resource type. • dc-directconnect: connection • dc-vgw: virtual gateway • dc-vif: virtual interface Enumeration values: • dc-directconnect • dc-vgw • dc-vif
resource_id	Yes	String	Specifies the resource ID.

Request Parameters

None

Response Parameters

Status code: 200

Table 5-136 Response body parameters

Parameter	Туре	Description
tags	Array of Tag objects	Specifies the tag list.
sys_tags	Array of Tag objects	Specifies the list of queried tags. If no tag is matched, an empty array is returned.
request_id	String	Specifies the request ID.

Table 5-137 Tag

Parameter	Туре	Description
key	String	Specifies the tag key. The key can contain a maximum of 36 Unicode characters, including letters, digits, hyphens (-), and underscores (_). Minimum: 0
		Maximum: 36
value	String	Specifies the tag value. The value can contain a maximum of 43 Unicode characters, including letters, digits, hyphens (-), underscores (_), and periods (.). Minimum: 0 Maximum: 43

Example Requests

Querying tags of a resource

https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dc-vgw/resource-instances/action

Example Responses

Status code: 200

OK

```
{
    "request_id" : "80ef5f21-b81a-4546-b23d-84272507d330",
    "tags" : [ {
        "key" : "key2",
        "value" : "value2"
    }, {
        "key" : "key1",
        "value" : "value1"
}, {
        "key" : "key3",
        "value" : "value3"
} ]
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.4.3 Adding a Resource Tag

Function

- A resource can have a maximum of 10 tags.
- This API is idempotent.
- If a to-be-created tag has the same key as an existing tag, the tag will be created and overwrite the existing one.

URI

POST /v3/{project_id}/{resource_type}/{resource_id}/tags

Table 5-138 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
resource_id	Yes	String	Specifies the resource ID.
resource_type	Yes	String	Specifies the Direct Connect resource type.
			dc-directconnect: connection
			dc-vgw: virtual gateway
			dc-vif: virtual interface
			Enumeration values:
			dc-directconnect
			• dc-vgw
			• dc-vif

Request Parameters

Table 5-139 Request body parameters

Parameter	Mandatory	Туре	Description
tag	Yes	Tag object	Specifies the resource tag.

Table 5-140 Tag

Parameter	Mandatory	Туре	Description
key	Yes	String	Specifies the tag key. The key can contain a maximum of 36 Unicode characters, including letters, digits, hyphens (-), and underscores (_). Minimum: 0 Maximum: 36
value	No	String	Specifies the tag value. The value can contain a maximum of 43 Unicode characters, including letters, digits, hyphens (-), underscores (_), and periods (.). Minimum: 0 Maximum: 43

Response Parameters

None

Example Requests

Adding tags to a resource

```
POST https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dc-vgw/3320166e-b937-40cc-a35c-02cd3f2b3ee2/tags

{
    "tag": {
        "key": "key1",
        "value": "value1"
    }
}
```

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See **Error Codes**.

5.4.4 Adding or Deleting Tags in Batches

Function

This API is used to batch add tags to or delete tags from a specified resource. TMS needs to use this API to manage tags of resources in batches. A resource can have a maximum of 10 tags.

URI

POST /v3/{project_id}/{resource_type}/{resource_id}/tags/action

Table 5-141 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
resource_id	Yes	String	Specifies the resource ID.
resource_type	Yes	String	Specifies the Direct Connect resource type.
			dc-directconnect: connection
			• dc-vgw: virtual gateway
			dc-vif: virtual interface
			Enumeration values:
			dc-directconnect
			• dc-vgw
			• dc-vif

Request Parameters

Table 5-142 Request body parameters

Parameter	Mandatory	Туре	Description
action	Yes	String	Specifies the operation. The options are as follows:
			• create
			• delete
			Enumeration values:
			• create
			• delete
tags	No	Array of Tag objects	Specifies the tags.
sys_tags	No	Array of Tag objects	Specifies the system tags.

Table 5-143 Tag

Parameter	Mandatory	Туре	Description
key	Yes	String	Specifies the tag key. The key can contain a maximum of 36 Unicode characters, including letters, digits, hyphens (-), and underscores (_). Minimum: 0 Maximum: 36
value	No	String	Specifies the tag value. The value can contain a maximum of 43 Unicode characters, including letters, digits, hyphens (-), underscores (_), and periods (.). Minimum: 0 Maximum: 43

Response Parameters

None

Example Requests

• Batch adding tags to resources

```
POST https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dc-vgw/3320166e-b937-40cc-a35c-02cd3f2b3ee2/tags/action

{
    "action" : "create",
    "tags" : [ {
        "key" : "key1",
        "value" : "value1"
    }, {
        "key" : "key2",
        "value" : "value2"
    } ]
}
```

Batch deleting resource tags

```
POST https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dc-vgw/3320166e-b937-40cc-a35c-02cd3f2b3ee2/tags/action

{
    "action" : "delete",
    "tags" : [ {
        "key" : "key1"
    }, {
        "key" : "key2",
        "value" : "value3"
    } ]
}
```

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See Error Codes.

5.4.5 Deleting a Resource Tag

Function

When a tag is deleted, the tag character set is not verified. Before calling this API, the API URL must be encoded. If the key to be deleted does not exist, 404 is displayed. The key cannot be left blank or an empty string.

URI

DELETE /v3/{project_id}/{resource_type}/{resource_id}/tags/{key}

Table 5-144 Path Parameters

Parameter	Mandatory	Туре	Description
key	Yes	String	Specifies the tag key.
project_id	Yes	String	Specifies the project ID.
resource_id	Yes	String	Specifies the resource ID.
resource_type	Yes	String	Specifies the Direct Connect resource type.
			dc-directconnect: connection
			• dc-vgw: virtual gateway
			dc-vif: virtual interface
			Enumeration values:
			dc-directconnect
			• dc-vgw
			• dc-vif

Request Parameters

None

Response Parameters

None

Example Requests

Deleting tags from a resource

 $DELETE\ https://\{dc\text{-endpoint}\}/v3/cfa563efb77d4b6d9960781d82530fd8/instance/3320166e-b937-40cc-a35c-02cd3f2b3ee2/tags/key1$

Example Responses

None

Status Codes

Status Code	Description
204	No Content

Error Codes

See Error Codes.

5.4.6 Querying Resources by Tag

Function

This API is used to query resources such as virtual gateways and virtual interfaces by tag.

URI

POST /v3/{project_id}/{resource_type}/resource-instances/action

Table 5-145 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.
resource_type	Yes	String	Specifies the Direct Connect resource type.
			dc-directconnect: connection
			• dc-vgw: virtual gateway
			dc-vif: virtual interface
			Enumeration values:
			dc-directconnect
			• dc-vgw
			• dc-vif

Request Parameters

Table 5-146 Request body parameters

Parameter	Mandatory	Туре	Description
offset	No	String	Specifies the index position. The query starts from the next data record indexed by this parameter. You do not need to specify this parameter when you query resources on the first page. When you query resources on subsequent pages, set this parameter to the value returned in the response body for the previous query. This parameter is not available when action is set to count. If action is set to filter, the value must be a number, and the default value is 0. The value cannot be a negative number.
limit	No	String	Specifies the number of records to be queried. This parameter is not available when action is set to count . If action is set to filter , the default value is 1000 . The maximum value is 1000 , and the minimum value is 1 . The value cannot be a negative number.
action	Yes	String	Specifies the operation to perform, which can only be filter (filtering) or count (querying the total number). filter indicates pagination query. count indicates that the total number of query results meeting the search criteria will be returned. Returning other fields is not allowed. Enumeration values: • filter • count

Parameter	Mandatory	Туре	Description
matches	No	Array of Match objects	Specifies the search criteria. key is the field to match, for example, resource_name. value indicates the value to be matched. This field is a fixed dictionary value.Determine whether fuzzy match is required based on different fields. For example, if key is resource_name, fuzzy search (case insensitive) is used by default. If value is an empty string, exact match is used. If key is resource_id, exact match is used. Currently, only resource_name is supported.
not_tags	No	Array of Tags objects	Specifies tags that are not included. Each tag contains a maximum of 10 keys, and each key contains a maximum of 10 values. The structure body cannot be missing, and the key cannot be left blank or set to an empty string. Keys must be unique and values of a key must be unique. Resources not identified by different keys are in AND relationship, and values in one tag are in OR relationship. If no filtering condition is specified, full data is returned.
tags	No	Array of Tags objects	Specifies tags that are included. Each tag contains a maximum of 10 keys, and each key contains a maximum of 10 values. The structure body cannot be missing, and the key cannot be left blank or set to an empty string. Keys must be unique and values of a key must be unique. Resources identified by different keys are in AND relationship, and values in one tag are in OR relationship. If no tag filtering criteria is specified, full data is returned.

Parameter	Mandatory	Туре	Description
tags_any	No	Array of Tags objects	Specifies any tag that is included. Each tag contains a maximum of 10 keys, and each key contains a maximum of 10 values. The structure body cannot be missing, and the key cannot be left blank or set to an empty string. Keys must be unique and values of a key must be unique. Resources identified by different keys are in OR relationship, and values in one tag are in OR relationship. If no filtering condition is specified, full data is returned.
not_tags_any	No	Array of Tags objects	Specifies any tag that is not included. Each tag contains a maximum of 10 keys, and each key contains a maximum of 10 values. The structure body cannot be missing, and the key cannot be left blank or set to an empty string. Keys must be unique and values of a key must be unique. Resources not identified by different keys are in OR relationship, and values in one tag are in OR relationship. If no filtering condition is specified, full data is returned.

Parameter	Mandatory	Туре	Description
sys_tags	No	Array of Tags objects	Only users with the op_service permission can use this field to filter resources. Only one tag structure is contained when this API is called by Tag Management Service (TMS). key is _sys_enterprise_project_id, and value is the enterprise project ID list. When TMS invokes this API, a key can have only one value. 0 indicates the default enterprise project. sys_tags and tenant tag filtering conditions (without_any_tag, tags, tags_any, not_tags, and not_tags_any) cannot be used at the same time.

Table 5-147 Match

Parameter	Mandatory	Туре	Description
key	Yes	String	Specifies the tag key. The value can be dc-directconnect, dc-vgw, or dc-vif.
value	Yes	String	Specifies the tag value. Each value can contain a maximum of 255 Unicode characters.

Table 5-148 Tags

Parameter	Mandatory	Туре	Description
key	Yes	String	Specifies the tag key. Each tag key can contain a maximum of 127 Unicode characters. key must be specified.
values	Yes	Array of strings	Specifies the list of tag values. Each value can contain a maximum of 255 Unicode characters.

Response Parameters

Status code: 200

Table 5-149 Response body parameters

Parameter	Туре	Description
resources	Array of Resource objects	Specifies the resource list.
total_count	Integer	Specifies the total number of records.
request_id	String	Specifies the request ID.

Table 5-150 Resource

Parameter	Туре	Description
resource_deta il	Object	Specifies the resource details.
resource_id	String	Specifies the resource ID.
resource_nam e	String	Specifies the resource name. This parameter is an empty string by default if there is no resource name.
tags	Array of Tag objects	Specifies the list of queried tags. If no tag is matched, an empty array is returned.
sys_tags	Array of Tag objects	Specifies the list of queried tags. If no tag is matched, an empty array is returned.

Table 5-151 Tag

Parameter	Туре	Description
key	String	Specifies the tag key. The key can contain a maximum of 36 Unicode characters, including letters, digits, hyphens (-), and underscores (_).
		Minimum: 0
		Maximum: 36
value	String	Specifies the tag value. The value can contain a maximum of 43 Unicode characters, including letters, digits, hyphens (-), underscores (_), and periods (.).
		Minimum: 0
		Maximum: 43

Example Requests

• Querying resources (action set to filter)

```
https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dc-vgw/resource-instances/action
{
"offset" : "10",
 "limit" : "10",
 "action": "filter",
  "matches" : [ {
   "key": "resource_name",
   "value" : "resource1"
 }],
  "not_tags" : [ {
   "key" : "key1",
"values" : [ "*value1", "value2" ]
  "tags" : [ {
  "key" : "key1",
   "values" : [ "*value1", "value2" ]
 }],
 "tags_any" : [ {
   "key" : "key1",
"values" : [ "value1", "value2" ]
 }],
  "not_tags_any" : [ {
   "key" : "key1",
   "values" : [ "value1", "value2" ]
```

Querying the total number of resources (action set to count)
 https://{endpoint}/v3/cfa563efb77d4b6d9960781d82530fd8/dc-vgw/resource_instances/action

```
{
 "action" : "count",
 -" · [ {
  "not_tags" : [ {
    "key" : "key1",
    "values" : [ "value1", "*value2" ]
  "tags" : [ {
    "key" : "key1",
    "values" : [ "value1", "value2" ]
    "key" : "key2",
    "values" : [ "value1", "value2" ]
  }],
  "tags_any" : [ {
    "key" : "key1",
"values" : [ "value1", "value2" ]
  }],
  "not_tags_any" : [ {
    "key" : "key1",
"values" : [ "value1", "value2" ]
  "sys_tags" : [ {
    "key" : "_sys_enterprise_project_id",
    "values" : [ "5aa119a8-d25b-45a7-8d1b-88e127885635" ]
  }],
  "matches" : [ {
   "key" : "resource_name",
"value" : "resource1"
 }]
}
```

Example Responses

Status code: 200

OK

```
{
    "resources" : [ ],
    "total_count" : 0,
    "request_id" : "9a4f4dfc4fb2fc101e65bba07d908535"
}
```

Status Codes

Status Code	Description
200	ОК

Error Codes

See Error Codes.

5.5 Quota Management

5.5.1 Querying Resource Quotas

Function

This API is used to query the usage of resources, for example, how many connections and virtual interfaces have been created.

URI

GET /v3/{project_id}/dcaas/quotas

Table 5-152 Path Parameters

Parameter	Mandatory	Туре	Description
project_id	Yes	String	Specifies the project ID.

Table 5-153 Query Parameters

Parameter	Mandatory	Туре	Description
type	No	Array	 Specifies the resource quotas. physicalConnect: quota and usage of the connection virtualInterface: quota and usage of the virtual interface

Request Parameters

None

Response Parameters

Status code: 201

Table 5-154 Response body parameters

Parameter	Туре	Description
quotas	quotas object	Provides used quota details.

Table 5-155 quotas

Parameter	Туре	Description
resources	Array of Info objects	Lists the used quotas of resources.

Table 5-156 Info

Parameter	Туре	Description
type	String	Specifies the quota type.
quota	Long	Specifies the available quota. The value -1 indicates that there is no quota limit.
used	Long	Specifies the used quotas.
unit	String	Specifies the measurement unit of resource usage.

Example Requests

Querying quotas

GET https://{dc_endpoint}/v3/08d5a9564a704afda6039ae2babbef3c/dcaas/quotas

Example Responses

Status code: 201

Quotas are queried.

```
{
    "quotas" : {
        "resources" : [ {
            "type" : "direct_connnect",
            "quota" : 1,
            "used" : 0,
            "unit" : "count"
        } ]
    }
```

Status Codes

Status Code	Description
201	Quotas are queried.

Error Codes

See Error Codes.

6 Public Parameters

6.1 Common Status Codes

Successful Response	Message	Description
200	ОК	Normal response code for GET and PUT operations
201	Created	Normal response code for POST operations
204	No Content	Normal response code for DELETE operations

Error Response	Description	
400 Bad Request	The server failed to process the request.	
401 Unauthorized	You must enter the username and password to access the requested page.	
403 Forbidden	You are forbidden to access the requested page.	
404 Not Found	The server could not find the requested page.	
405 Method Not Allowed	You are not allowed to use the method specified in the request.	
406 Not Acceptable	The response generated by the server could not be received by the client.	
407 Proxy Authentication Required	You must use the proxy server for authentication so that the request can be processed.	

Error Response	Description
408 Request Timeout	The request timed out.
409 Conflict	The request could not be processed due to a conflict.
500 Internal Server Error	The request is not completed because the service is abnormal.
501 Not Implemented	The request is not completed because the server does not support the requested function.
502 Bad Gateway	The request is not completed because the server receives an invalid response from an upstream server.
503 Service Unavailable	The request is not completed because the system is out of service temporarily.
504 Gateway Timeout	A gateway timed out.

6.2 Error Codes

Status Code	Error Code	Description	Solution
400	DC.0000	The request body is abnormal.	Correct the parameter settings and send the request again.
400	DC.0001	Request parameter error.	Correct the parameter settings and send the request again.
400	DC.0002	The resource does not exist.	Correct the parameter settings and send the request again.
400	DC.0003	System error.	Correct the parameter settings and send the request again.
400	DC.0004	Invalid IP address.	Correct the parameter settings and send the request again.
400	DC.0005	Failed to call the VPC API.	Correct the parameter settings and send the request again.

Status Code	Error Code	Description	Solution
400	DC.0006	Failed to call the MO API.	Correct the parameter settings and send the request again.
400	DC.0007	The VPC does not exist.	Correct the parameter settings and send the request again.
400	DC.0008	The BGP ASN is out of range.	Correct the parameter settings and send the request again.
400	DC.0009	Invalid policy.	Contact technical support.
400	DC.0010	The VPC_VNI does not exist.	Contact technical support.
400	DC.0011	The AGENT is abnormal.	Correct the parameter settings and send the request again.
400	DC.0012	Failed to call the CBC API.	Contact technical support.
400	DC.0013	You have no permission to operate the field.	Contact technical support.
400	DC.1000	Insufficient connection bandwidth.	Contact technical support.
400	DC.1001	A VLAN is specified for a non-hosted connection.	Contact technical support.
400	DC.1002	Failed to create a hosted connection.	Contact technical support.
400	DC.1003	A VLAN is not specified for a hosted connection.	Contact technical support.
400	DC.1004	A non-operations connection is selected for creating a hosted connection.	Contact technical support.
400	DC.1005	The connection is abnormal.	Contact technical support.
400	DC.1006	The device and type cannot be modified when the connection is in use.	Contact technical support.
400	DC.1007	The connection is in use.	Contact technical support.

Status Code	Error Code	Description	Solution
400	DC.1008	Hosted connection VLANs conflict.	Contact technical support.
400	DC.1010	Connection bandwidth is decreased.	Contact technical support.
400	DC.1011	Connection bandwidth cannot be changed.	Contact technical support.
400	DC.1012	The connection does not exist.	Contact technical support.
400	DC.1014	A redundant connection is set for a non-standard connection.	Contact technical support.
400	DC.1015	The connection or LAG does not exist.	Contact technical support.
400	DC.1017	The VLAN ID of the hosted connection is 0.	Contact technical support.
400	DC.1019	The connection quota has been used up.	Contact technical support.
400	DC.1100	The local endpoint group ID of the virtual gateway is invalid.	Contact technical support.
400	DC.1101	The number of local subnets exceeds the limit.	Contact technical support.
400	DC.1102	The standby device is specified when the active device is not specified.	Contact technical support.
400	DC.1103	The active and standby devices are the same.	Contact technical support.
400	DC.1104	The device information cannot be updated for the virtual gateway.	Contact technical support.
400	DC.1105	The local CIDR block overlap with the remote CIDR block.	Contact technical support.
400	DC.1106	The virtual gateway is in use.	Contact technical support.
400	DC.1107	Virtual gateway VLANs are exhausted.	Contact technical support.
400	DC.1108	Virtual gateway VNIs are exhausted.	Contact technical support.

Status Code	Error Code	Description	Solution
400	DC.1109	Virtual gateway VRFs are exhausted.	Contact technical support.
400	DC.1110	A virtual gateway has been associated with the VPC.	Contact technical support.
400	DC.1111	The virtual gateway does not exist.	Contact technical support.
400	DC.1112	The devices used by the virtual gateway are not in active/standby mode.	Contact technical support.
400	DC.1113	The virtual gateway is in the cutover state.	Contact technical support.
400	DC.1114	traffic_mode cannot be updated for VLANs or virtual gateways with a single VTEP device.	Contact technical support.
400	DC.1115	The VNI of the virtual gateway does not exist.	Contact technical support.
400	DC.1116	Failed to update the route gateway.	Contact technical support.
400	DC.1117	The virtual gateway has been associated with two connections and cannot be associated with more connections.	Contact technical support.
400	DC.1118	The virtual gateway is being operated (locked).	Contact technical support.
400	DC.1119	Failed to create the route gateway device group.	Contact technical support.
400	DC.1120	The main_az_list configuration item is incorrect.	Contact technical support.
400	DC.1200	No LAG or connection is specified for the virtual interface.	Contact technical support.
400	DC.1201	The connection does not match the virtual gateway type.	Contact technical support.
400	DC.1202	Virtual interfaces of the double ipsec type cannot be created.	Contact technical support.

Status Code	Error Code	Description	Solution
400	DC.1203	No ASN is specified for the BGP virtual interface.	Contact technical support.
400	DC.1204	Creating virtual interfaces is not supported for operations connections.	Contact technical support.
400	DC.1205	The status of the resource associated with the virtual interface is abnormal.	Contact technical support.
400	DC.1206	The hosted connection has been associated with a virtual interface.	Contact technical support.
400	DC.1207	The VLAN of the virtual interface is inconsistent with that of the hosted connection.	Contact technical support.
400	DC.1208	The bandwidth of the virtual interface associated with a hosted connection cannot be modified.	Contact technical support.
400	DC.1209	Virtual interface VLANs conflict.	Contact technical support.
400	DC.1210	The virtual interface status cannot be changed.	Contact technical support.
400	DC.1211	The virtual interface does not exist.	Contact technical support.
400	DC.1212	The virtual gateway is in a different group from the connection.	Contact technical support.
400	DC.1213	The virtual interface does not match the tenant.	Contact technical support.
400	DC.1214	The virtual interface has been used.	Contact technical support.
400	DC.1215	The virtual interface type does not match.	Contact technical support.
400	DC.1216	The local gateway is invalid.	Contact technical support.
400	DC.1217	The IES edge site ID of the connection does not match that of the local gateway.	Contact technical support.

Status Code	Error Code	Description	Solution
400	DC.1218	The local gateway does not match.	Contact technical support.
400	DC.1219	A virtual interface with VLAN 0 is created.	Contact technical support.
400	DC.1220	The vif email field on the public network is empty.	Contact technical support.
400	DC.1221	The selected virtual gateway device does not support access from Direct Connect locations.	Contact technical support.
400	DC.1222	Insufficient POP VNIs.	Contact technical support.
400	DC.1223	The local BGP ASN is the same as the remote BGP ASN.	Contact technical support.
400	DC.1224	The virtual interface of the connection terminated at a Direct Connect location does not support VLAN 0.	Contact technical support.
400	DC.1225	The number of virtual interfaces for which traffic statistics collection is enabled reaches the limit.	Contact technical support.
400	DC.1226	Traffic statistics collection cannot be enabled on Layer 2 remote interfaces that have no sub-interfaces.	Contact technical support.
400	DC.1227	Traffic statistics cannot be updated because the virtual interface is abnormal.	Contact technical support.
400	DC.1400	The number of endpoint groups reaches the limit.	Contact technical support.
400	DC.1401	Duplicate CIDR blocks.	Contact technical support.
400	DC.1402	The endpoint group is in use.	Contact technical support.
400	DC.1403	The endpoint group does not exist.	Contact technical support.



A.1 Obtaining a Project ID

Scenarios

A project ID is required for some URLs when an API is called. Therefore, you need to obtain a project ID in advance. Two methods are available:

- Obtain the Project ID by Calling an API
- Obtain the Project ID from the Console

Obtain the Project ID by Calling an API

You can obtain the project ID by calling the IAM API used to query project information based on the specified criteria.

The API used to obtain a project ID is GET https://{Endpoint}/v3/projects. {Endpoint} is the IAM endpoint and can be obtained from **Regions and Endpoints**. For details about API authentication, see **Authentication**.

The following is an example response. The value of **id** is the project ID.

```
"self": "https://www.example.com/v3/projects"
}
}
```

Obtain a Project ID from the Console

To obtain a project ID from the console, perform the following operations:

- 1. Log in to the management console.
- Click the username and select My Credentials from the drop-down list.
 On the My Credentials page, view the project ID (value in the Project ID column).

B Change History

Released On	Description
2024-07-30	This issue is the first official release.